

ScreenFool

Chris Lawrence

Copyright © 1993-94 Chris Lawrence

COLLABORATORS

	<i>TITLE :</i> ScreenFool		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY	Chris Lawrence	March 1, 2023	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	ScreenFool	1
1.1	ScreenFool 3.0 AmigaGuide documentation	1
1.2	What is ScreenFool?	2
1.3	ScreenFool's features	2
1.4	System Requirements	3
1.5	Copyright and Registration Issues	3
1.6	The Font-Sensitive GUI	5
1.7	ScreenFool and Localization	6
1.8	Installation	7
1.9	Some basic terminology	7
1.10	Running and Using ScreenFool	8
1.11	Tool Types	10
1.12	About: Obtain program information (GUI)	11
1.13	Hide: Hide the control window (GUI)	11
1.14	Quit: Exit ScreenFool (GUI)	11
1.15	New: Open a new screen (GUI)	12
1.16	Close: Close a public screen (GUI)	12
1.17	Make Default: Change the default public screen (GUI)	13
1.18	To Front: Bring a public screen to the front (GUI)	13
1.19	To Back: Push a public screen to the back (GUI)	13
1.20	Information: Get information on a public screen (GUI)	13
1.21	Palette: Change a public screen's palette (GUI)	13
1.22	Write Palette: Save a screen's palette (GUI)	14
1.23	Jump Window: Jump the window to another public screen (GUI)	14
1.24	Update Display: Update the control window (GUI)	14
1.25	Help: Get information on ScreenFool commands	14
1.26	Macro » Script Menu (GUI)	15
1.27	Script » No Console: Execute ARexx macro (GUI)	15
1.28	Script » Console: Execute ARexx macro (GUI)	15
1.29	Command: Execute macro command (GUI)	15

1.30 Shanghai: Toggle the SHANGHAI flag (GUI)	15
1.31 AutoPop: Toggle the AUTOPOP flag (GUI)	16
1.32 The Macro Interface	16
1.33 ARexx and Macro Commands	17
1.34 Hide: Hide the main window	18
1.35 Show: Show the main window	19
1.36 Quit: Exit ScreenFool	19
1.37 About: Display program information	19
1.38 Shanghai: Change behavior of the default public screen	19
1.39 AutoPop: Change AutoPop flag	20
1.40 Requesters: Control display of ScreenFool requesters	20
1.41 New: Open a new public screen	20
1.42 Close: Close an existing public screen	22
1.43 Default: Change the default public screen	22
1.44 Info: Obtain information on a public screen	22
1.45 Front: Bring a screen to the front	23
1.46 Back: Send a screen to the back	23
1.47 Jump: Jump the ScreenFool window to a different screen	23
1.48 Palette: Allow user to edit the palette of a screen	23
1.49 GetPalette: Get palette entries for a screen	24
1.50 WritePalette: Save a screen's palette to a file	25
1.51 Command: Execute a single command line	25
1.52 Macro: Execute an ARexx script	25
1.53 GetAttr: Get Attributes	26
1.54 Help: Obsolete command	27
1.55 UserHelp: Open GUI AmigaGuide help	27
1.56 NOP: No operation	28
1.57 Update: Update the ScreenFool window	28
1.58 StatusLine: Display a message on the status line	28
1.59 LockGUI: Inhibit user interface function	28
1.60 UnlockGUI: Re-enable user interface function	29
1.61 In conclusion...	29
1.62 Versions covered	30
1.63 Appendix: Display ID reference	30
1.64 Appendix: A Note About Version Numbers	31
1.65 Appendix: Revision History	31
1.66 Index	35

Chapter 1

ScreenFool

1.1 ScreenFool 3.0 AmigaGuide documentation

ScreenFool 3.0 User Documentation

Table of Contents

Introduction

What~is~ScreenFool?

A~summary~of~features

System~Requirements

Copyright~and~Registration

Installation

A~summary~of~terminology

Using ScreenFool

Running~the~program

Tool~Types~and~Shell~Options

The~Macro~Interface

ARexx~Commands

Additional~points

Appendices:

Common~display~identifiers

A~Note~About~Version~Numbers

Revision~History

1.2 What is ScreenFool?

What Is ScreenFool?

ScreenFool is a utility for Amigas with Release 2 or later of the operating system. It allows you to work with so-called "Public" screens and thereby enhance your productivity, by allowing Workbench screen (and other) applications to use a different screen than the regular Workbench.

1.3 ScreenFool's features

Features:

ScreenFool has three main interfaces: the Intuition (GUI) interface, the Commodities (hot-key) interface, and the ARexx macro interface.

Some features of the Intuition interface include:

- Open a public screen in any available Intuition-supported display mode. *
- Close any open public screen.
- Make all windows that open on Workbench open on another screen (SHANGHAI).
- Set a default~public~screen for applications.
- Pop a screen to front when a visitor window appears on it (AUTOPOP).
- Change public screen palettes.
- Localization under Release 2.1 and above.
- Font-sensitive GUI.

The Commodities interface supports:

- Commodities Exchange control of the program window.
 - Hiding and showing the control window.
-

- Hotkey access.

The ARexx interface supports:

- All Intuition and Commodities interface functions, plus:
- Obtaining information on available screens and display modes
- Numeric palette setting
- Options not included in the GUI.

Workbench.library support:

- Pop up the window at any time from Workbench's Tools menu.
- * Full capability requires a keyfile that will be sent upon registration

1.4 System Requirements

System Requirements:

- * AmigaDOS Release 2 or later (Intuition V37)
- * 512K RAM (Much more recommended if you're opening many screens)
- * Any processor

ScreenFool is compatible with advanced processors and Release 3. It has been tested on a V37 (final) A2000 system with 3 MB RAM, 80 MB hard disk, and 68000 processor (7.14 MHz); and on a V39 A4000 system with 8 MB RAM, 120 MB hard disk, and 68040 processor (25 MHz).

1.5 Copyright and Registration Issues

Copyright:

ScreenFool is Copyright © 1992-94 Chris Lawrence. It is copyrighted shareware: you may make as many duplicate copies as you wish, provided the following restrictions are followed:

1. The program itself must remain unaltered.
2. This documentation file, and any others included, must remain unaltered.
3. The file reqtools.library is unaltered
(ReqTools is Copyright © 1991-94 Nico Francois)
4. The demonstration scripts and README file remain unaltered.

This archive may be included on the Fred Fish CD series (Frozen Fish, Fresh Fish, etc.) and the Aminet CD-ROM. If you are interested in some other form of distribution, contact the author at the address below.

Registration Details:

If you are satisfied with this program, you may send a registration fee of \$5 (\$10 for the program on disk via snail mail) to:

Chris Lawrence
Box 574060
Georgetown University
Washington, DC 20057-4060
United States of America

Registering ScreenFool will entitle you to:

- Immediately receive a keyfile
 - Free upgrades (*) of registered version for eternity after registration. This includes both maintenance upgrades and full upgrades.
 - Full technical support
 - Future upgrades - period. No money, no enhancements
- * Upgrades by mail will be assessed a \$2 handling fee for disk cost, shipping and handling. Upgrades downloaded from Aminet or obtained on BBSes are free.

Please include your mailing address with payment (US currency, cashier's check, postal order) for a prompt upgrade. Personal checks: allow 2-4 weeks for check to clear. For fastest possible receipt of the keyfile, include an Internet E-Mail address (will be sent as uuencoded .lha file).

Other correspondence can be sent to the above address, or via the Internet to clawrenc@cap.gwu.edu.

If you have previously registered ScreenFool and have not received a keyfile for this and future releases, please drop me a line.

Keyfiles:

Basically, they are governed by common sense. For those budding lawyers out there, it's spelled out below.

AGREEMENT FOR THE USE OF KEYFILES FOR SCREENFOOL

If you have registered the program, you are entitled to a keyfile that enables the New Screen requester. Upon receipt of the keyfile, you may use the keyfile on one system at any given time. The file may be duplicated onto any computers that you may own, lease, or rent, but must not be allowed to be distributed to computers owned, leased, or rented by another individual. Additional keyfiles for additional systems under your control may be issued at the discretion of the author for \$2 each. (These keyfiles will bear different registration numbers for tracking purposes.) Additional keyfiles are licenced from the main keyfile, and all of your keyfiles are considered a indivisible unit.

In essence: you may use a specific ScreenFool keyfile on one Amiga at a time. To use the New Screen requester on two Amigas at one time, you must have two

keyfiles. Additional keyfiles are \$2 each. All additional keyfiles must be retained by the owner of the main keyfile.

You may transfer all of your keyfiles to another individual, provided that you destroy all copies of all of your keyfiles, the other individual has read and understood this license, and you inform the author within thirty (30) days of the transfer. You must inform the author of the name, address, and email address (if applicable) of the transferee. The transferee will receive all of the rights that a registered ScreenFool user is entitled to, and you will be required to either re-register or be transferred the rights to another person's keyfiles in order to be considered a registered user again. There is no fee for a keyfile transfer. You may charge the transferee for the rights to your keyfiles if you wish. You must transfer all of your keyfiles, or not transfer any of them. Renting or leasing of keyfiles is not permitted.

In essence: you may sell ALL of your keyfiles to another individual. The other individual will receive all of the rights to ScreenFool that you had previously received, and you will revert to having the rights of an unregistered user. There is no limit to the number of transfers that can be made of a specific set of keyfiles.

Keyfiles may not be placed in (a) download directories of Bulletin Board Systems, (b) world-read directories of an AFS-based system, (c) world-read directories of an FTP site, (d) world-read directories of an FSP site, or (e) any place where an anonymous or unentitled (person who has not registered ScreenFool or been transferred someone else's registration) user might be able to receive a copy of the file (excepting floppy diskettes used for personal storage).

It is illegal for an unentitled user to use a keyfile. Violations will be prosecuted to the fullest extent of the law.

By receiving a keyfile and using it, you imply consent to this agreement.

Exceptions to this agreement must be made by the author (me) in writing.

Please Note:

Many terms used in this document are trademarks or registered trademarks. This is generally indicated by the use of capital letters, i.e. AmigaGuide.

1.6 The Font-Sensitive GUI

The Font-Sensitive GUI:

ScreenFool Release 2.4U added the additional feature of a font-sensitive GUI to the ScreenFool interface. Basically, ScreenFool tries to adapt to the screen font of screens that it opens on.

There are certain limitations to this feature:

- 1) If the screen font is greater than 18 point, the GUI reverts to topaz.
- 2) If ScreenFool thinks that the screen is too small to display the full window, ScreenFool will revert to topaz 8, or the BACKUPFONT set in the

```
Tool~Types
. If topaz or BACKUPFONT is still too large, ScreenFool
will attempt to use SystemThin.font 8 point, which is a narrow font
supplied with ProWrite, or the SMALLFONT set in the
Tool~Types
```

```
.* SystemThin.font IS NOT REQUIRED FOR SCREENFOOL TO WORK.
```

- 3) If your font has a tf_XSize somewhere in the vicinity of machine infinity, as is the case with many poorly designed fonts, ScreenFool will go through the steps as outlined in limitation 2, above.
- 4) The window may look odd at point sizes outside the 6-12 range. This is due to the fact that ScreenFool has not been extensively tested with very large and very small fonts.
- 5) Under Release 3 and later, the checkmarks are scaled if the font is greater than 11 points tall.

Please let me know about any enhancements you would like to see in the GUI font adaptivity.

1.7 ScreenFool and Localization

Localization:

ScreenFool 3.0 and above include language localization features. As demand for different languages becomes apparent, I will release new language catalogs for ScreenFool.

The current release includes the following languages:

- English (internal)
- Français

Please note that Release 2.1 or later of the Amiga operating system is required for localization to work.

If you would like to localize ScreenFool to your language, follow the following steps:

1. Edit the ScreenFool_translation.ct file, translating the provided English strings to your language.
2. Send the completed file to me, either by electronic or snail mail.

I will create the catalog file and mail it to you. In addition, your translation may be included with the next public release of ScreenFool. If this is the case, you will receive either a free registration or a refund of your registration fee.

Inclusion of translations is at the sole discretion of the author (me).

1.8 Installation

Installation:

ScreenFool 3.0 and above include an Installer script. To install ScreenFool, you'll need a copy of Installer somewhere in your search path (check your operating system Install disk if you don't already have Installer on your hard drive).

Double-click on the Installer icon to begin the installation process. If you choose a "User Level" of Novice, the program will automatically be installed to your SYS:WBStartup directory; otherwise, you will be able to choose from three installation options: SYS:WBStartup, SYS:Tools/Commodities, or Custom...

Installing to one of the Boot volume directories will install the libraries, this help file, and catalog files to the default system directories. This method is recommended if you will use ScreenFool often.

You can also install to a Custom directory. This will create a drawer called ScreenFool which contains all of the files ScreenFool needs to operate; however, reqtools.library will still be installed to your Libs: path (if necessary).

1.9 Some basic terminology

Terms You Need To Know:

PUBLIC SCREEN: A screen that other programs are allowed to open windows on. Intuition V36 (Release 2.0) and later support this feature. Many programs can open on a public screen.

DEFAULT SCREEN: The screen that applications that do not open their own screen will open onto. For pre-V36 applications, this was Workbench. Newer applications will go to this screen.

VISITOR WINDOW: A window on a public screen opened by an application that didn't open the screen. The ScreenFool main window is a visitor window, as is the IconEdit window.

DISPLAY ID: A number that represents a specific display mode. For example, a low resolution, non-interlaced screen has a display ID of 0. For more details, see the
Display~ID~reference
.

MODE PROMOTION: A feature of Release 3 (V39) of graphics.library, which allows some screen modes to be essentially replaced by others. For example, DBLNTSC:High Res No Flicker replaces NTSC:High Res Laced. ScreenFool fully supports Mode Promotion.

FLAG: A variable that can only have a value of on or off.

SHANGHAI: A system flag that determines the behavior of the default public

screen. If this flag is set, pre-V36 applications will open on the default public screen, even if they ask for Workbench.

AUTOPOP: A system flag that makes a public screen to pop to the front when a visitor window opens on it.

INTERLEAVED BITMAP: A screen type, only available in Release 3 and later, which improves the display on many-bitplane screens by reducing the "color flashing" during scrolling. ScreenFool opens its screens on V39 systems as interleaved, unless you override this behavior. Pre-V39 systems use a "standard bitmap," as does V39 if you use the

NEW~NOTINTERLEAVED
macro command.

1.10 Running and Using ScreenFool

Running And Using:

To run ScreenFool from the Workbench, double-click the Commodity icon labelled ScreenFool (if you are using a 68020 or higher computer, use the icon labelled ScreenFool-AP).

To run ScreenFool from the Shell, type "ScreenFool" at the command prompt. If you want to continue using the current shell window, type:

```
run <nil: >nil: ScreenFool
```

If you wish to set startup options from either Workbench or the Shell, see the section on

Tool~Types

.

The ScreenFool~window will then be displayed. This window allows you to manipulate the screens in the scrolling list.

The action gadgets on the right of the scrolling list (from top) will open a new screen, close the selected screen, and change the selected screen to the default screen.

The two checkboxes,

Shanghai

and

AutoPop

change the behavior of all Public

screens. Both default to OFF on the Amiga under Releases 2 and 3.

The two message lines at the bottom of the window display the name of the default screen and messages from executed commands. The status line might say 'Couldn't close screen' if you tried to close a screen with windows still open on it, for example.

Other features are concealed in the menus. All choices have keyboard equivalents. Note that you may use either Right Amiga-key combinations or the letter on its own. By menu, they are:

Project Menu:

- About...
(?) - Display program information.
- Hide
(H) - Conceal program user interface.
- Quit
(Q) - Exit the program.

Screen Menu:

- New...
(N) - Open a new screen.
- Close
(C) - Close selected screen.
- Make~Default
(D) - Make the selected screen the default screen.
- To~Front
(F) - Bring selected screen to front of stack.
- To~Back
(B) - Move selected screen to back of stack.
- Palette...
(P) - Change the palette for selected screen.
- Write~Palette...
(W) - Write a screen's palette to a script.
- Information...
(I) - Show screen name, resolution, etc.

Tools Menu:

- Jump~Window
(J) - Jump the ScreenFool window to the selected screen.
- Update~Display
(U) - Refresh scrolling and display mode lists.
- Help...
(L) - Get information on various topics.

Macro Menu:

- Command...
(X) - Execute a single command line.
-

Macro~>~Console...

(,) - Execute an ARexx macro with a window to display the output.

Macro~>~No~Console...

(M) - Execute an ARexx macro without a window to display any output (output redirected to NIL:).

For further information on menu choices, pull down the menu to the option you want information for, and then press Help BEFORE releasing the right mouse button.

Important note: Help is only available if the file ScreenFool.guide is in the directory that ScreenFool is launched from, the LOCALE:Help/English directory, or in a directory in the AmigaGuide search path.

1.11 Tool Types

Tool Types and Shell Options:

These options can be added to the Tool Types by using the "Icons » Information..." option on the Workbench. From the Shell, they can be used by following the ScreenFool command with the tool type and its option, in quotes, as below:

```
ScreenFool "TYPE1=OPTION1" "TYPE2=OPTION2" ...
```

The available Tool Types are:

DONOTWAIT - Make sure this Tool Type is included if ScreenFool will be run in WBStartup.

CX_POPUP - YES to have window pop up immediately when run; NO to hide window until summoned by hotkey or Commodities Exchange. Default: YES.

CX_POPKEY - The key specification for the keypress that will pop up the window. Default is "Control F1". The keypress combinations are listed on page 5-29 of "Using the System Software" (2.0 users) and on page 10-25 of the "Workbench 3.0" manual.

CX_PRIORITY - Sets relative priority of the ScreenFool program, from~127 to -128 (to other commodities). Defaults to 0.

STARTUP - ARexx macro to automatically run on startup. Defaults to "SF-Startup". ScreenFool uses a ".sf" extension on its macros, so SF-Startup.sf would be the proper name for the startup macro.

PORTNAME - Name for the ARexx port. Normally "ScreenFool.1".

PUBSCREEN - Name of the screen for ScreenFool to initially open on. Will normally open on the default screen.

COMMAND - A single macro command to run when the program initially starts. Normally there is no command.

REXXDIR - Default macro directory. REXX: if omitted.

BACKUPFONT - Font to use when screen font is too large. The default is topaz.font.

BACKUPSIZE - Point size for BACKUPFONT; defaults to 8.

SMALLFONT - Font to use when screen and backup fonts are too large. The default is SystemThin.font.

SMALLSIZE - Point size for SMALLFONT; defaults to 8.

WEIRDMODES - Set WEIRDMODES=YES if you want to see Extra Halfbrite and HAM modes in the New Screen requester. Defaults to NO.

FINDKEY - Set to NO if you want to disable the Keyfile search. Defaults to YES.

1.12 About: Obtain program information (GUI)

Project » About...

This option gives the version of the program, its registration status, the name of the ARexx port, and a summary of available Chip and Fast RAM.

Hotkey: Amiga-?

1.13 Hide: Hide the control window (GUI)

Project » Hide

Hide the main window. The window can be brought back up again by pressing the Commodities hotkey for this program (default: Control F1), by choosing "Show" in the Commodities Exchange program, or by using the Workbench Tools menu.

Hotkey: Amiga-H

1.14 Quit: Exit ScreenFool (GUI)

Project » Quit

Quit ScreenFool. This can also be accomplished by using the Commodities "Kill" button, or by breaking the ScreenFool process (using Control-C or the Shell BREAK command).

Hotkey: Amiga-Q

1.15 New: Open a new screen (GUI)

```
Screen » New...  
New Screen... (Action button)
```

Opens a new screen, duplicating the characteristics of the screen that the main window is currently open on.

Under Release 3 or later, the screen will be interleaved
.

If you register, you will be able to manipulate the options for the new screen in a requester.

The Listview gadget contains the available display modes.

The Screen Name text gadget is used to enter a name for the public screen. This name must be unique.

The Overscan cycle gadget allows you to choose from Text, Graphics (Standard), Maximum and Video overscan settings.

The Bitplanes slider gadget allows you to choose the number of bitplanes the screen should use (use the left and right cursor keys to change it from the keyboard). Note that all depths may not be available with HAM and EHB displays, so use care.

The Width and Height integer gadgets and check-boxes allow you to choose the screen's width and height. Note that you can't change the width and height of OSCAN_VIDEO screens.

The Like Workbench checkbox, under Release 3 and later, allows you to create a screen that is a direct clone of the Workbench screen automatically.

The Interleaved Screen checkbox, under Release 3 and later, creates a screen that has properties that reduce flickering during scrolling.

Note that help is not available directly from the Open New Screen... requester. This will be rectified in a later release.

Hotkey: Amiga-N

1.16 Close: Close a public screen (GUI)

```
Screen » Close  
Close Screen (Action button)
```

Close the currently selected public screen. The screen will not close if any windows are currently open on it.

The screen need not have been opened by ScreenFool.

Hotkey: Amiga-C

1.17 Make Default: Change the default public screen (GUI)

Screen » Make Default
Make Default (Action button)

Change the
default~public~screen
to the currently selected public screen.

Hotkey: Amiga-D

1.18 To Front: Bring a public screen to the front (GUI)

Screen » To Front

Bring the selected public screen to the front of the display. A shortcut is to double-click on the screen's name in the list.

Hotkey: Amiga-F

1.19 To Back: Push a public screen to the back (GUI)

Screen » To Back

Push the selected public screen to the back of the display. This is probably of limited usefulness.

Hotkey: Amiga-B

1.20 Information: Get information on a public screen (GUI)

Screen » Information...

Get information on the currently selected public screen. Information includes the screen's title, public screen name, display identifier, resolution, depth, and font.

Under Release 3, the information requester also indicates if the screen's bitmap is

interleaved
.

Hotkey: Amiga-I

1.21 Palette: Change a public screen's palette (GUI)

Screen » Palette...

Change the palette of the currently selected public screen, using the reqtools palette requester.

Hotkey: Amiga-P

1.22 Write Palette: Save a screen's palette (GUI)

Screen » Write Palette...

Save the palette of the selected screen as a macro. This macro can be used to set the colors of the screen by executing it later.

Hotkey: Amiga-W

1.23 Jump Window: Jump the window to another public screen (GUI)

Tools » Jump Window

Makes the control window appear on the currently selected public screen. This screen will pop to the front, and the window will be made active.

Hotkey: Amiga-J

1.24 Update Display: Update the control window (GUI)

Tools » Update Display

Update the control window display. This is sometimes necessary after closing a public screen.

Under ScreenFool 2.4U and later, this forces the reloading of the display mode list. This is useful after opening another monitor or changing locales.

In future, an automated update may be done for locale changes.

Hotkey: Amiga-U

1.25 Help: Get information on ScreenFool commands

Tools » Help...

This option allows the user to get direct help on the gadgets on the screen. In the requester, enter the name of the gadget you want information on.

Hotkey: Amiga-L

1.26 Macro » Script Menu (GUI)

Macro » Script Menu

Use

Macro~»~Script~»~Console...
for an output window, or use

Macro~»~Script~»~No~Console...
for a script without a window.

1.27 Script » No Console: Execute ARexx macro (GUI)

Macro » Script » No Console...

Execute an ARexx macro without console input and output.

Hotkey: Amiga-M

1.28 Script » Console: Execute ARexx macro (GUI)

Macro » Script » Console...

Execute an ARexx macro with console input and output.

Hotkey: Amiga-,

1.29 Command: Execute macro command (GUI)

Macro » Command...

Execute a macro command line.

Hotkey: Amiga-X

1.30 Shanghai: Toggle the SHANGHAI flag (GUI)

Shanghai (Check box)

Toggle the

SHANGHAI
public screen flag.

Hotkey: S

1.31 AutoPop: Toggle the AUTOPOP flag (GUI)

AutoPop (Check box)

Toggle the

AUTOPOP
public screen flag.

Hotkey: A

1.32 The Macro Interface

The ScreenFool macro interface:

One of ScreenFool's most powerful features is the ability to run completely under the control of an ARexx program or macro. This allows a lot of versatility in using the program.

A few commands can return information. To obtain this information, OPTIONS RESULTS must have been specified in the program; otherwise, you will need to use the VAR or STEM option of a command.

After each command, the ARexx variable SFSTATUS will contain the text currently on the status line. If RC is 0, this will usually state that the action was completed OK; otherwise, it will be an error message.

There are three main ways of using the macro interface:

1. Use the

Macro~»~Command
(Amiga-X) command, to execute one command line.

2. Use the

Macro~»~Script
commands, to execute an ARexx program.

3. Create a macro called SF-Startup.sf, which will be automatically executed on startup.

The

Macro~»~Command
command allows simple macro commands, like:

```
NEW DISPLAYID=0
```

Which would open a new, low resolution screen. (Note that case does not matter, EXCEPT in screen names)

More complicated actions require the writing of scripts. This requires a text editor.

Here's an example script:

```
/* Example.sf -- A really dumb example */
```

```
OPTIONS RESULTS
```

```
'new displayid=0 screenname="ReallyDumb.1"
'info "ReallyDumb.1" /* displays information requester */
'close "ReallyDumb.1" /* End of script */
```

An example script file, `SFTest.sf`, shows the basic format of ScreenFool ARexx script files. In addition, an example startup script is included which sets the SHANGHAI and AUTOPOP flags every time ScreenFool is started.

Note that only one command can be entered at a time using

```
Macro~>~Command
```

or

the `COMMAND` tooltype. If ARexx is not available, the

```
Macro~>~Command
```

```
facility
```

is still available, however.

```
ARexx~Command~Listing
```

1.33 ARexx and Macro Commands

```
ARexx and Macro Commands:
```

```
Macro Commands
```

```
GetAttr
```

```
Macro
```

```
Command
```

```
NOP
```

```
Screen Management Functions
```

```
New
```

```
Close
```

```
Default
```

```
Front
```

```
Back
```

```
Palette
```

```
GetPalette
```

```
WritePalette
```

Info

Shanghai

AutoPop

User Interface Control

Hide

Show

Jump

Requesters

LockGUI

UnlockGUI

StatusLine

Update

About

Quit

Aliases -- Old command names or style-guide synonyms

Get
for GetAttr

RX
for Macro

CmdShell
for Command

Deactivate
for LockGUI

Activate
for UnlockGUI

Status
for StatusLine

1.34 Hide: Hide the main window

Format: HIDE

Close the program window until reopened by either pressing the hotkey or sending the

Show
command.

See Also:

Show

1.35 Show: Show the main window

Format: SHOW

Open the program window on the screen that it was last on; or the default screen (if the last screen has been closed, or ScreenFool has not opened its window yet).

See Also:

Hide

1.36 Quit: Exit ScreenFool

Format: QUIT

Quit ScreenFool. All further ARexx commands to ScreenFool will return with an error message.

1.37 About: Display program information

Format: ABOUT

Display the version information for this copy of ScreenFool in a requester. Ignored if the ScreenFool window is hidden.

The requester will not be displayed if

Requesters
are off.

See Also:

Requesters

1.38 Shanghai: Change behavior of the default public screen

Format: SHANGHAI [On | Off | Toggle]

Change the global public screen flag that controls the behavior of the default public screen. When on, even programs that request Workbench will get the default screen; when off, only programs that don't care what screen they get

will get the default.

Options:

On/S: Sets the flag
Off/S: Clears the flag
Toggle/S: Toggles the flag

See Also:

AutoPop
,
SHANGHAI~Definition

1.39 AutoPop: Change AutoPop flag

Format: AUTOPOP [On | Off | Toggle]

Change the global public screen flag that determines whether a screen should pop to the front when a window opens onto it.

Options:

On/S: Sets the flag
Off/S: Clears the flag
Toggle/S: Toggles the flag

See Also:

Shanghai
,
AUTOPOP~Definition

1.40 Requesters: Control display of ScreenFool requesters

Format: REQUESTERS [On | Off | Toggle]

Change the internal flag in ScreenFool that determines whether requesters will be displayed requesting user input. This flag defaults to ON.

Options:

On/S: Sets the flag
Off/S: Clears the flag
Toggle/S: Toggles the flag

1.41 New: Open a new public screen

Format: NEW [ScreenName] DISPLAYID=[ID] PLANES=[Bitplanes] [NoGUI]
SCANTYPE=[Text | Standard | Max | Video] FONT=[name].font SIZE=[points]
[SysDefText] WIDTH=[width] HEIGHT=[height]

Extra V39 switches:

[NotInterleaved] [LikeWorkbench]

Open a new screen, using the chosen parameters. The default settings for these parameters are those of the screen that ScreenFool is (or was last) open on, except for Font and Size, which are taken from Preferences' Screen Text;

Interleaved
, which defaults On under V39; and LikeWorkbench, which is always off unless set by the user.

All screens are opened, by default, with a full set of pens (including the extra V39 pens, under V39), and with the full Workbench palette. Under V39, the screen will share its pens. The AutoScroll flag is also set for screens that exceed the DisplayClip region.

Options: {All Optional}

ScreenName - name for screen
(ScreenFool will make a name up if omitted (ScreenFool.x))

DisplayID/K/N - a valid
DisplayID
in decimal.
Hires=32768; Hires-Interlaced=32772.

Planes/K/N - number of bitplanes (1-maximum for this mode)

NoGUI/S - ensures requester will not be displayed, even if the user has a keyfile.

ScanType/K - Overscan setting. One of:
Text
Standard
Max
Video

Font/K - A valid font name (for screen titlebar).
Include the .font extension.

Size/K/N - A valid height for the font.

SysDefText/S - Use the monospaced font as set in Preferences for the screen font.

Width/K/N, Height/K/N - width and height for the screen

NotInterleaved/S - use a standard bitmap (under Release 3)
See

INTERLEAVED~BITMAP
for details.

LikeWorkbench/S - duplicate Workbench attributes (under Release 3)
Setting this flag on V39 will only permit the Interleaved flag to function. This flag is ignored under V38 and earlier.

See Also:

Close
,
Display~IDs

1.42 Close: Close an existing public screen

Format: CLOSE {Screen}

Close the specified public screen. This screen need not have been opened by ScreenFool.

Options:

Screen/A - name of screen to close ** REQUIRED

See Also:

New

1.43 Default: Change the default public screen

Format: DEFAULT {Screen}

Make the selected screen the
default~public~screen
.

Options:

Screen/A - Name of the screen ** REQUIRED

See Also:

Definition~of~Default~Public~Screen
,
Shanghai

1.44 Info: Obtain information on a public screen

Format: INFO {Screen} STEM=[Stem] VAR=[Var] [NoGUI]

Get information on the selected public screen, and (optionally) return this information to the macro.

Options:

Screen/A - name of screen to get info on ** REQUIRED

Stem/K - stem name to get stem result in. Fields will be filled as follows:

- .SCREEN - Handle
- .TITLE - Default title
- .DISPLAY.TITLE - Current title
- .DISPLAY.NAME - Name of current display mode
- .DISPLAY.ID - Display mode ID in decimal
- .DISPLAY.WIDTH - Display width in pixels
- .DISPLAY.HEIGHT - Display height in pixels
- .DISPLAY.DEPTH - Screen bitplanes
- .DISPLAY.COLORS - Screen colors
- .DISPLAY.LEAVED - Is this screen interleaved
? (Yes or No)

.FONT.NAME - Name of screen font
.FONT.YSIZE - Screen font height
Var/K - variable name to obtain information in. Fields will be filled in the same order as the stem.
NoGUI/S - Do not display requester with information. If there is not a Var or Stem, ScreenFool sets RESULT equal to what Var would have been.

See Also:

GetAttr

1.45 Front: Bring a screen to the front

Format: FRONT {Screen}

Bring the specified public screen to the front of the display.

Options:

Screen/A - name of screen to bring to the front ** REQUIRED

See Also:

Back

1.46 Back: Send a screen to the back

Format: BACK {Screen}

Push the specified public screen to the back of the display. This command is probably of limited usefulness.

Options:

Screen/A - name of screen to push to the back ** REQUIRED

See Also:

Front

1.47 Jump: Jump the ScreenFool window to a different screen

Format: JUMP {Screen}

Jump the ScreenFool window to a different screen. If the window is hidden when the command is issued, it will be popped up.

Options:

Screen/A - name of screen to jump to ** REQUIRED

1.48 Palette: Allow user to edit the palette of a screen

Format: PALETTE {Screen} [n] [r] [g] [b] [FullRes]

Edit the palette of the selected screen. If all that is specified is the name of a public screen, the ReqTools palette requester will appear on that screen.

If a palette entry number (between 0 and the maximum pen on the screen) is given, direct RGB entries can be made, in the order Red Green Blue.

The FullRes option determines how the RGB values will be interpreted. By default, ScreenFool uses a 256-level resolution in each position. This is sufficient for both ECS and AGA Amigas.

Note that in the default system, the values range from 0-255. If running under ECS, the values are mapped to the 0-15 range internally.

If FullRes is used, each color may be specified to 32-bit resolution.

Options:

Screen/A - name of screen to edit palette of ** REQUIRED

Entry/N - The palette entry. From 0 to 2**(planes)-1

Red/N - The Red value

Green/N - The Green value

Blue/N - The Blue value

FullRes/S - If set, use 32-bit color resolution.

See Also:

GetPalette

,

WritePalette

1.49 GetPalette: Get palette entries for a screen

Format: GETPALETTE {Screen} {n} [FullRes]

Returns the nth palette entry in RESULT, in the format "r g b".

The FullRes option determines how the RGB values will be returned. By default, ScreenFool uses a 256-level resolution in each position. This is sufficient for both ECS and AGA Amigas.

If FullRes is used, each color will be returned in 32-bit resolution. This may be useful for high resolution video cards, AAA, and the like.

Options:

Screen/A - name of screen get an entry from ** REQUIRED

Entry/N/A - The palette entry. From 0 to 2**(planes)-1 ** REQUIRED

FullRes/S - If set, use 32-bit color resolution.

See Also:

Palette

1.50 WritePalette: Save a screen's palette to a file

Format: WRITEPALETTE {Screen} [Filename]

Writes the entire palette of the chosen screen to a file. If the screen has a 3.0 extended palette, the entire palette will be written.

This file can later be executed by the

RX

command, to change the colors of the existing screen. It can also be edited to open the screen as well.

This command writes 32-bit resolution palette data.

Options:

Screen/A - name of screen get an entry from ** REQUIRED

Filename - name of file to write script to
If not specified, requester will be used.

See Also:

Palette

1.51 Command: Execute a single command line

Format: COMMAND [Commandline]

Alternate Form: CMDSHELL [Commandline]

Execute a single macro command line. If no commandline is offered by the program, a requester will be popped up.

The CMDSHELL form is available for style-guide pseudo-compatibility.

Options:

Commandline/F - a command to be executed

See Also:

Macro

1.52 Macro: Execute an ARexx script

Format: MACRO [CONSOLE] WINDOW=[Windowspec] [ASYNCH] [Command]

Alternate Form: RX [CONSOLE] WINDOW=[Windowspec] [ASYNCH] [Command]

Execute an ARexx macro program. If no command is given, a file requester will appear allowing the user to select a file to execute, or type a command line (with options).

The RX form, and the ASYNCH switch, are available for style-guide pseudo-compatibility.

Options:

CONSOLE/S - Specify if you need a CON: window for I/O.
 WINDOW/K - Specify a special window specification for I/O.
 ASYNCH/S - Non-functional. All macros are asynchronous.
 COMMAND/F - command line to send to ARExx. Filenames should have an extension if the filename does not end with ".sf"

See Also:

Command

1.53 GetAttr: Get Attributes

Format: GETATTR {RequestType} VAR=[Var] STEM=[Stem]

Alternate Form: GET {RequestType} VAR=[Var] STEM=[Stem]

Get information directly from ScreenFool that is unavailable through the Intuition interface.

Options:

RequestType/A - determines type of information to get -- see below.
 Var/K - sets variable to get information into
 Stem/K - sets stem to get information into.
 Not applicable for DefScreen or SFScreen.

If neither VAR or STEM are specified, the information will be returned (if possible) in RESULT.

These are the currently supported request types, along with the data that will be returned when specified.

Screens

Var or Result - List of open screens, quote & space delimited
 Stem - Will be set to the following:
 stem.COUNT - Number of open screens
 stem.0 to stem.(count-1) - Screen handles

Displays

Var or Result - List of display modes and their ID numbers
 Stem - Set to the following:
 stem.COUNT - Number of display modes available
 stem.0 to .(count-1) - Groups:
 stem.n.NAME - Display name
 stem.n.ID - Display ID number
 stem.n.PROP - Display property flags (see graphics/displayinfo.h)
 stem.n.MAXDEPTH - Maximum number of bitplanes
 stem.n.GFXWIDTH - Graphics overscan width
 stem.n.GFXHEIGHT - Graphics overscan height
 stem.n.TXTWIDTH - Text overscan width
 stem.n.TXTHEIGHT - Text overscan height

Modes

Var or Result - A string of the following format
"Shanghai AutoPop Requesters", where each flag is replaced by
On or Off, depending on the current state of the flag.

Stem
stem.SHANGHAI On/Off
stem.AUTOPOP On/Off
stem.REQUESTERS On/Off

DefScreen

Var or Result - Default public screen
Stem - No result

SFScreen

Var or Result - ScreenFool's public screen
Stem - No result

Application

Var or Result - ScreenFool's version information string
Stem - The following stem will be filled:
stem.VERSION - Normal version string
stem.COPYRIGHT - Copyright information
stem.SCREEN - Screen that the window is/was open on
stem.DEFSCREEN - The default public screen's name
stem.PORTNAME - ARExx port name
stem.IVERSION - Internal version number. Includes compilation date
and time. Use this information in bug reports, please!
stem.SCREENS - Number of open public screens
stem.DISPLAYMODES - Number of available display modes. This will not
include dual-playfield modes, and may not include EHB and HAM modes,
depending on the
WEIRDMODES
tool type.

See Also:

Info

1.54 Help: Obsolete command

Format: HELP

This command is obsolete. The online help facility has been moved to an
AmigaGuide document. See

UserHelp

.

A call to this command will return "Command obsolete."

1.55 UserHelp: Open GUI AmigaGuide help

Format: USERHELP [topic]

Obtain help using the AmigaGuide help system. If no topic is specified, the

"Running and Using" section of this .guide file will appear.

Options:

topic - The topic to be looked up

1.56 NOP: No operation

Format: NOP

No operation. Included for style-guide pseudo-compatibility.

1.57 Update: Update the ScreenFool window

Format: UPDATE

Refresh the ScreenFool window. This command is occasionally necessary from macro programs.

Under ScreenFool 2.4U and later, this forces a reload of the display mode listing. An automated UPDATE may be done in future versions if the locale is changed.

1.58 StatusLine: Display a message on the status line

Format: STATUSLINE [message]

Alternate Form: STATUS [message]

Display a message on the ScreenFool status line.

Options:

Message/F - message to display

1.59 LockGUI: Inhibit user interface function

Format: LOCKGUI

Alternate Form: DEACTIVATE

Lock ScreenFool's user interface from Intuition access. This is useful in some macro programs, such as PSPub.sf, which change the default public screen.

The DEACTIVATE form is provided for style-guide compatibility.

See Also:

UnlockGUI

1.60 UnlockGUI: Re-enable user interface function

Format: UNLOCKGUI

Alternate Form: ACTIVATE

Unlock ScreenFool's user interface. If multiple outstanding locks, will not take effect until all locks are unlocked.

The ACTIVATE form is provided for style-guide compatibility.

See Also:

LockGUI

1.61 In conclusion...

Some Features Not Mentioned Elsewhere:

Double-clicking on a screen name in the scrolling list will bring that screen to the front. Note that double-clicking is NOT supported in the display mode list.

You can use the up and down cursor keys to select screens from the scrolling lists.

Using the "Tools » ScreenFool" menu option on the Workbench will pop the ScreenFool window to the front.

For help on options without menu items (for example, Shanghai and AutoPop), press L and then type the option name into the requester that appears and press Return. [Look for gadget help in an upcoming release]

You can quit ScreenFool while public screens that it opened are still open. If you want to close the screens, use ScreenFool to close them later (simply re-run ScreenFool). The screens can also be closed by other applications; however, this will result in a loss of approximately 400 bytes of memory per screen.

The screen mode choices are, by default, limited to non-ExtraHalfBrite, non-HAM modes. ScreenFool refuses to open a screen in one of these modes when they are excluded, even from the command line. This behavior may be changed by using the

WEIRDMODES
tool type.

In Scripts:

If you want a high resolution "laced" (640x400) screen, specify the generic display ID 0x8004 (decimal 32772), not the NTSC or PAL specific display ID. This provides maximum compatibility with Mode Promotion under Release 3 and above. These can be found in the C header file <graphics/displayinfo.h> (under Release 3, <graphics/modeid.h>) or by making a copy of the output from ScreenFool's

GetAttr~Displays
or from the ShowAvailModes example included in

the screenfool.library developer distribution.

I hope that you enjoy ScreenFool!

Chris Lawrence
17 August 1994

1.62 Versions covered

VERSIONS COVERED IN THIS DOCUMENT:

ScreenFool 2.7 (5.9.94)
ScreenFool 2.7-AP020 (5.9.94)

ScreenFool is Copyright © 1992-94 Chris Lawrence
screenfool.guide and screenfool.library are Copyright © 1993-94 Chris
Lawrence

The user interface design is intellectual property of the National
Broadcasting Corporation, 30 Rockefeller Plaza, New York, NY 10011, and may
not be reproduced without their express written consent.

Damned is he who wears the yellow hat. -- I Corinthians 22:6

1.63 Appendix: Display ID reference

This is a brief guide to the most often-used available DisplayIDs ↔
in
ScreenFool. A more complete list can be found using
GetAttr~Displays
(as
demonstrated in the script SFTest.sf). Note that display IDs returned by this
function are absolute (monitor-specific), not generic.

Use the generic IDs in scripts for compatibility with Mode Promotion and
international systems. Unrecognized display IDs are converted to generic HiRes
in attempt to recover from script errors.

Please note that several monitors are not included in this list, notably the
Euro36 and Euro72 monitors (which provide European systems with NTSC
resolutions at higher refresh rates) and the Super72 monitor.

Default.monitor (NTSC/PAL/Db1NTSC/Db1PAL)

Name	Resolution	Display ID (hex)	Display ID (decimal)
LowRes	320x200 (256) \$^1\$ \$^2\$	0x0	0
HiRes	640x200 (256) \$^2\$	0x8000	32768
SuperHiRes	1280x200 (256)	0x8020	32800

LowResLace	320x400 (512) \$^2\$	0x4	4
HiResLace	640x400 (512) \$^2\$	0x8004	32772
SuperHiResLace	1280x400 (512)	0x8024	32804
Multisync.monitor (VGA/Multisync) *			
Productivity	640x480 \$^3\$	0x39024	233508
ProductLaced	640x960 \$^3\$	0x39025	233509
Doublescan (AGA) monitors *			
LoRes-DblLace	320x800 (1024)	0x5	5
HiRes-DblLace	640x800 (1024)	0x8005	32773

\$^1\$ Parentheses indicate PAL (50 Hz) vertical resolution. These resolutions are non-overscan and typical of Pre-2.0 screens.

\$^2\$ Promoted by Mode Promotion

\$^3\$ No overscan

* These resolutions require a VGA or Multisync monitor

1.64 Appendix: A Note About Version Numbers

There are two "revision tracks" for ScreenFool. They are Regular and Advanced Processor. The version string of the program depends on what track of ScreenFool you are using.

The regular version has version strings of the format:

ScreenFool x.x (d.m.y)

The advanced processor version has a version string like:

ScreenFool x.x-AP020 (d.m.y)

1.65 Appendix: Revision History

The following is a brief revision history of ScreenFool.

This Version: ScreenFool 3.0a (**INTERIM**)

CHANGES FROM SCREENFOOL 2.7 (5.9.94)

- * Localization! Maintenant, on peut utiliser ScreenFool en français!
(A .ct file is included, for your edification.)
- * Uses Installer. Now, two installation choices: If you run ScreenFool out of one directory, you can install the entire system there. Or, if you run it in WBStartup or Commodities, install the files to system directories.
- * Shortcut for
 Screen~»~Palette...
 changed to Amiga-P from Amiga-E.
(Forgot that P had been unused since I got my Amiga User Interface Style Guide & changed AutoPop to A (from P) and About to ? (from A))
- * Fixed bug that made ScreenFool crash if you did a GETATTR DISPLAYS and there were more than about 40 modes available. Upper limit increased to around 120.
Thanks to Nigel Davidson for reporting this.

CHANGES FROM SCREENFOOL 2.6 (17.8.94)

- * Direct setting of RGB values now available in the
 PALETTE
 macro command.
- * New
 GETPALETTE
 macro command to get specified palette entries.
- * Includes ability to
 write~a~screen's~palette
 to a script file.
- * Includes Advanced Processor version in standard distribution.

CHANGES FROM SCREENFOOL 2.5U (13.1.94)

- * Registered and Unregistered releases combined into one program. Currently registered users will receive a keyfile that enables the New Screen requester.

CHANGES FROM SCREENFOOL 2.4U (11.9.93)

- *
 UPDATE
 function now expanded in scope. May now force a mode list update.
 - * Window disable functions implemented using more speed-efficient methods.
 - * Main program and library recompiled using SAS/C 6.51 -- better optimizer, smaller code size.
 - * Library memory fragmentation greatly reduced.
-

- * Replaced extended character \times with x, for better compatibility with non-Amiga fonts.
- * Registered version requester now has better unusual screenmode identification and supports RTG monitors better (you set planes rather than colors).
- * Fixed bug with screen information requester not properly identifying display modes without names.

CHANGES FROM SCREENFOOL 2.3U (6.9.93)

- * Help file improved; incorrect references removed.
- * Registered version mode requester improved.
- * Now has a
font-sensitive
GUI.
- * Bug in library that would sometimes create an empty screen list removed.
- * New
tool~types
are available to control fonts.

CHANGES FROM SCREENFOOL 2.2U (29.8.93)

- * Help now moved to AmigaGuide file, resulting in a code decrease of approximately 10K. Online help is only available if the .guide file is in the directory ScreenFool is started from, or in a directory which is listed in ENV:AmigaGuide/Path.

NOTE: amigaguide.library need not be present for ScreenFool to run. However, no help will be available if the library is not opened.

- * All documentation now in AmigaGuide format.

CHANGES FROM SCREENFOOL 2.1U (13.7.93)

- * Includes support for V39 NewLookMenus, and interleaved bitmap screens.
- * Now includes better support for ReqTools V38.
- * Checked with Enforcer.

CHANGES FROM SCREENFOOL 1.12U (11.7.93)

- * Screen and display management functions moved to AmigaDOS shared library. This transfer will benefit Amiga developers by making high-level management functions available for all Amiga users (Release 2+).
-

- * Tooltype REXXDIR allows user to change default ARexx directory.

CHANGES FROM SCREENFOOL 1.11U/1.10U (Internal revisions)

- * Memory loss fixes. All commands previously caused a loss of 520 bytes from the system.
- * Bug-fix in registered version's New Screen interface -- the colors slider now works correctly.
- * Main window now WA_SimpleRefresh again
(Pick a WA_#?Refresh attribute, any WA_#?Refresh attribute)
- * Newer Commodities 3.0-style interface
- * Fixed bug that unlocked window if hidden and reopened using AppMenu

CHANGES FROM SCREENFOOL 1.9U (8.2.93)

- * Recompiled with SAS/C Release 6.0 -- program slightly more efficient
- * Tested on 68040-based system without problems
- * Internal cleanups too numerous to mention here

CHANGES FROM SCREENFOOL 1.8U (16.1.93)

- * Changed main window to WA_SmartRefresh
- * Added available memory to About... requester
- * Minor visual enhancements to About... requester
- * Properly attached Activate and Deactivate ARexx commands to their actual synonyms,
 UnlockGUI
 and
 LockGUI
 (Previously were attached to Hide and Show)
- * Added FONT and SIZE options to
 NEW
 command. See documentation for further details.

CHANGES FROM SCREENFOOL 1.7U (5.1.93)

- * Fixed bug that ate memory when an OpenPublicScreenA() failed.
 - * Better error reporting of why screens don't open.
 - * Makes window use SystemThin.font (included with ProWrite) if opened on
-

a low resolution screen. If not available, uses topaz.font.
NOTE: SystemThin.font IS NOT REQUIRED TO USE SCREENFOOL.

- * Fixed bug with vertical spacing in gadgets in fonts other than 8 points wide (that's right, WIDE).

CHANGES FROM SCREENFOOL 1.6U (23.12.92)

- * Fixed bug that would make status information act weird on a screen with a font other than 8 points tall -- that was a weird one to fix.
- * Internal support for opening screens with different fonts (implemented via GUI for registered users) -- a command line option may be added later.
 - * (Not really a change): Tested with low memory (EatMem) -- passes with flying colors (after your initial 40-50K load). Also tested using Mungwall, MemWatch, Drip, and EatCycles.

CHANGES FROM SCREENFOOL 1.5U (19.12.92)

- * ScreenFool now kills off less of your stack space -- 8K of stack is sufficient.
- * New ARexx command -


```
REQUESTERS~[ON~|~OFF~|~TOGGLE]
```

 - choose to disable
 the ScreenFool requesters for asynchronous operation without a user present -- helpful if your ARexx macro might stop because of a missing NOGUI option.
- *


```
GETATTR~MODES
```

 now includes the current Requesters mode.

1.66 Index

Index of database ScreenFool.guide

Documents

About: Display program information

About: Obtain program information (GUI)

Appendix: A Note About Version Numbers

Appendix: Display ID reference

Appendix: Revision History

ARexx and Macro Commands

AutoPop: Change AutoPop flag

AutoPop: Toggle the AUTOPOP flag (GUI)

Back: Send a screen to the back

Close: Close a public screen (GUI)

Close: Close an existing public screen

Command: Execute a single command line

Command: Execute macro command (GUI)

Copyright and Registration Issues

Default: Change the default public screen

Front: Bring a screen to the front

GetAttr: Get Attributes

GetPalette: Get palette entries for a screen

Help: Get information on ScreenFool commands

Help: Obsolete command

Hide: Hide the control window (GUI)

Hide: Hide the main window

In conclusion...

Info: Obtain information on a public screen

Information: Get information on a public screen (GUI)

Installation

Jump Window: Jump the window to another public screen (GUI)

Jump: Jump the ScreenFool window to a different screen

LockGUI: Inhibit user interface function

Macro » Script Menu (GUI)

Macro: Execute an ARexx script

Make Default: Change the default public screen (GUI)

New: Open a new public screen

New: Open a new screen (GUI)

NOP: No operation

Palette: Allow user to edit the palette of a screen

Palette: Change a public screen's palette (GUI)

Quit: Exit ScreenFool

Quit: Exit ScreenFool (GUI)

Requesters: Control display of ScreenFool requesters

Running and Using ScreenFool

ScreenFool 3.0 AmigaGuide documentation

ScreenFool and Localization

ScreenFool's features

Script » Console: Execute ARexx macro (GUI)

Script » No Console: Execute ARexx macro (GUI)

Shanghai: Change behavior of the default public screen

Shanghai: Toggle the SHANGHAI flag (GUI)

Show: Show the main window

Some basic terminology

StatusLine: Display a message on the status line

System Requirements

The Font-Sensitive GUI

The Macro Interface

To Back: Push a public screen to the back (GUI)

To Front: Bring a public screen to the front (GUI)

Tool Types

UnlockGUI: Re-enable user interface function

Update Display: Update the control window (GUI)

Update: Update the ScreenFool window

UserHelp: Open GUI AmigaGuide help

Versions covered

What is ScreenFool?

Write Palette: Save a screen's palette (GUI)

WritePalette: Save a screen's palette to a file
Buttons

A~Note~About~Version~Numbers

A~summary~of~features

A~summary~of~terminology

About

About...

Activate

Additional~points

ARexx~Command~Listing

ARexx~Commands

AUTOPOP

AutoPop

AUTOPOP

AutoPop

AUTOPOP~Definition

Back

Close

Close

CmdShell

Command

Command...

Common~display~identifiers

Copyright~and~Registration

Deactivate

Default

default~public~screen

Definition~of~Default~Public~Screen

Display~ID~reference
Display~IDs
DisplayID
Font-sensitive
Front
Get
GetAttr
GetAttr~Displays
GETATTR~MODES
GetPalette
Help...
Hide
Hide
Info
Information...
Installation
interleaved
INTERLEAVED~BITMAP
Jump
Jump~Window
Localization
LockGUI
Macro
Macro~»~Command
Macro~»~Console...
Macro~»~No~Console...
Macro~»~Script
Macro~»~Script~»~Console...
Macro~»~Script~»~No~Console...

Make~Default

New

NEW~NOTINTERLEAVED

New...

NOP

Palette

Palette...

PSPub.sf

Quit

Quit

registration

requester

Requesters

REQUESTERS~ [ON~ | ~OFF~ | ~TOGGLE]

Revision~History

Running~the~program

RX

Screen~»~Palette...

ScreenFool~window

SFTest.sf

SHANGHAI

Shanghai

SHANGHAI

Shanghai

SHANGHAI~Definition

Show

Status

StatusLine

System~Requirements

The~Macro~Interface

To~Back
To~Front
Tool~Types
Tool~Types~and~Shell~Options
UnlockGUI
Update
UPDATE
Update~Display
UserHelp
WEIRDMODES
What~is~ScreenFool?
write~a~screen's~palette
Write~Palette...
WritePalette
