

SkoEd

COLLABORATORS

	<i>TITLE :</i> SkoEd		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		December 11, 2024	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	SkoEd	1
1.1	MAIN	1
1.2	INTRODUCTION	1
1.3	FEATURES	2
1.4	INSTALLATION	2
1.5	DISTRIBUTION	3
1.6	Folding	4
1.7	Gadgets	4
1.8	EXECUTION	5
1.9	CONFIGURATION	5
1.10	AREXX	7
1.11	COMMANDS	7
1.12	UpUp	9
1.13	DownDown	9
1.14	StartOfBlock	9
1.15	EndOfBlock	9
1.16	Up	10
1.17	Down	10
1.18	Left	10
1.19	Right	10
1.20	Page_Up	10
1.21	Page_Down	11
1.22	StartOfFile	11
1.23	EndOfFile	11
1.24	StartOfLine	11
1.25	EndOfLine	12
1.26	Scroll_Up	12
1.27	Scroll_Down	12
1.28	Scroll_Left	12
1.29	Scroll_Right	12

1.30 Word_Left	13
1.31 Word_Right	13
1.32 Word_End	13
1.33 Goto_Line	13
1.34 Goto_Column	14
1.35 Next_Buffer	14
1.36 Prev_Buffer	14
1.37 Goto_Buffer	14
1.38 Next_Fold	14
1.39 Prev_Fold	15
1.40 Next_Mark	15
1.41 Prev_Mark	15
1.42 Goto_Mark	15
1.43 Match	16
1.44 Return	16
1.45 Backspace	16
1.46 Del	16
1.47 Del_Line	16
1.48 Word_Delete	17
1.49 Del_EOL	17
1.50 Del_SOL	17
1.51 Block_Begin	17
1.52 Block_End	18
1.53 Block_Copy	18
1.54 Block_Delete	18
1.55 Block_Move	18
1.56 Block_Hide	19
1.57 Block_Clip	19
1.58 Clip_Block	19
1.59 Block_File	19
1.60 File_Block	20
1.61 Block_Mode	20
1.62 Indent_Block	20
1.63 Unindent_Block	20
1.64 Undo	21
1.65 Split_Window	21
1.66 Close_Window	21
1.67 Zoom	21
1.68 Explode	22

1.69 Refresh	22
1.70 Load_File	22
1.71 Save_File	22
1.72 Print_File	23
1.73 Reload	23
1.74 Kill_Buffer	23
1.75 Make_Buffer	23
1.76 Print_Buffer	24
1.77 Compile	24
1.78 Link	24
1.79 Run	24
1.80 Make	25
1.81 Errors	25
1.82 New_CLI	25
1.83 Find	25
1.84 Replace	26
1.85 Again	26
1.86 Mark	26
1.87 Unmark	27
1.88 Fold_Line	27
1.89 Unfold_Line	27
1.90 Fold_Block	27
1.91 Unfold	27
1.92 Str_Size	28
1.93 None	28
1.94 Set_Var	28
1.95 Get_Var	29
1.96 Descriptions of Variables	30
1.97 Buffer_Info	31
1.98 Set_Env	32
1.99 Set_Vars	32
1.100Count_Braces	32
1.101Complete_Word	32
1.102Auto_Save	33
1.103Tab	33
1.104Exit	33
1.105Iconify	33
1.106Reconfigure	33
1.107Msg	34
1.108ARexx Command	34
1.109EXAMPLES	34
1.110DISCLAIMER	35

Chapter 1

SkoEd

1.1 MAIN

SkoEd V1.14
A Programmer's Editor Revisited.
Copyright (c) 1993 David McPaul

Introduction
Features
Installation
Starting SkoEd
Configuring SkoEd
Commands
AREXX
Examples
Distribution
Registering

DISCLAIMER
INDEX

AmigaGuide Documentation produced using AmigaGuide Writer by me :-)

SkoEd Icons and Gadgets created using IE by Peter Kiem.

1.2 INTRODUCTION

Before getting into this wonderfull doco :-) a quick look at why I wrote SkoEd.

Why another editor? Hmm it is hard to say, but the more I look around at editors the more I think that an Editor is a very personal preference. Not just in the keymappings (After all most editors these days will remap keys) but also in how they look and how they operate. (I refuse to say look and feel only a lawyer would use such terms).

Well, when I got my Amiga I found that there were no editors around that I really liked. Some were good and did quite a lot but they were not me. So I wrote SkoEd which is in many ways my personal preference. SkoEd is by no means the begin and end all of Editors; there are a number of areas which need improving. It is however at a stage that I feel can be released to the Amiga community.

1.3 FEATURES

Here is a list of what SkoEd can do.

- Remaps keystrokes to commands.
- Customisable.
- Multiple Files.
- Multiple Views of files.
- Clones the WorkBench Screen and WorkBench Screen text font.
- Set own Screen and Font.
- Reads, Writes and Converts IBM format files.
- A FAST Find/Replace.
- Column Blocks.
- Clipboard support.
- AutoSave after time limit expires.
- Folding.
- Match {[]}.
- Count number of braces {} in a file.
- Word Completion. (I like this one :-)
- Zoom/Explode of Views.
- Memory file to remember files previously loaded and cursor location.
- Unlimited Marks to allow you to go instantly to a marked location.
- Undelete n Deletes. (n is settable)
- Iconify.
- Script file bit is handled correctly (and is settable).
- AREXX
- User Configurable Gadget Strip
- And other, less obvious functions.

Here are the areas I wish to improve.

- A full macro language. (although with Arexx do I need this?)
- A full Undo as opposed to Undelete (and Redo).
- Repeat command.
- Allow user to create own menu strips.

1.4 INSTALLATION

SkoEd is for Workbench 2.0 and 3.0 only.

To Install SkoEd you may either:

Use the Installer Script supplied or,

Copy Skoed to somewhere in your path.

Copy Skoed.Config to the directory where SkoEd is located.

Copy Skoed.Macro to the directory you work in.
Copy Gadgets directory to the directory where SkoEd is located.
Make a directory in ENV: called SkoEd.

Edit both Skoed.Config and Skoed.Macro to map the key to commands etc.
Add the Assign SkoEd: <place where SkoEd is located> to user startup.

A note about the support files (Config & Macro) The following search order is performed - Current Directory, The Directory SkoEd was loaded from then "SKOED:". The way I work things is Config goes where SkoEd is located and Macro goes in my work directory. This way unchanging keymaps and commands are in SkoEd.Config and work specific commands are in SkoEd.Macro.

Additional support files are for the gadget strip. SkoEd looks for the gadgets using "<Search Path>Gadgets/#?.info". Any Icon located in that directory is checked for a COMMAND string and loaded into the gadget strip. The <Search Path> is the same as for the Config and Macro files.

These system libraries are needed in libs:

ReqTools.library
IffParse.library

1.5 DISTRIBUTION

SKOED VERSION 1.14 is SHAREWARE

So you may,

Distribute the NON REGISTERED versions of SkoEd as much as you like.
However no more than a nominal fee may be charged for distributing SkoEd.

If you use SkoEd on a regular basis then you should REGISTER.
Registered users receive :

- The latest version,
- 1 free update and then,
- Notification of the next update.

Registration is only \$25.00 Australian (which is cheaper than you think considering most exchange rates :-)

Please send Registration fee to:

David McPaul,
P.O. Box 2830,
Canberra,
A.C.T,
AUSTRALIA,
2601.

I prefer International Money Orders, Bankers Cheques or Cash.
Personal cheques are just too difficult to get changed.

Please include with your Registration:

Your Name (So I can personalise SkoEd for you)
Your Address (So you can get SkoEd sent to you :-)
Comments, thoughts, wish list etc or even just a hello.

Other programs available

- AmigaGuide Writer (AGW) (\$15)

1.6 Folding

Folding is a method whereby sections of code is hidden from the display. This makes the studying of code sections easier because you hide away code that you know is working or not relevant. SkoEd allows you to highlight the section of code that you do not wish to see and use the `Fold_Block` command to hide it away. `Unfold` reverses this process.

1.7 Gadgets

SkoEd now supports a user configurable gadget strip. To add a gadget to the strip just create an icon with a maximum height of 28 pixels and store it in "Gadgets/". Add a `COMMAND` tooltype and you are ready to go.

TOOLTYPES Used are:

- `COMMAND` - This is the command that will be executed by skoed when you press the gadget. Macros are also supported.
e.g `COMMAND=Make;`
or `COMMAND=ARexx(screxx:NextError.Rexx);`
- `TICK` - Add this tooltype if you want the command to be repeated while the gadget is activated. This tooltype overrides the `GADGETUP` tooltype.
- `GADGETUP` - Add this tooltype if you want the command to be executed when the gadget is released instead of selected. Does not function when `TICK` is present.
- `ORDER` - This tooltype controls the order of gadget placement. by giving each icon an `ORDER` of placement you can control which gadget goes where.
e.g `ORDER=5`
This makes the gadget the 5th gadget in the strip. Note if you do not supply an order it defaults to 0 and this may affect other gadget ordering.
- `GAP` - Use to determine the `GAP` between this gadget and the previous gadget.
e.g `GAP=30`
This leaves 30 pixels between this gadget and the
-

previous gadget default is 3.

1.8 EXECUTION

SkoEd only works with Workbench 2.0 and above.

SkoEd can be started via the CLI or the Workbench, when run from the CLI some parameters may be accepted. These may be seen by typing Skoed ?

```
Usage: Skoed [options] [filename]
options are :
+r - Use Reload file if available
-r - Don't use a Reload file if found
```

The filename specified in the command line will be loaded (names can be surrounded by double quotes ("") if the name contains spaces).

SkoEd will open it's own Public screen (SkoEd). The screens width, Height and Font will be cloned from the Workbench Screen & Screen font. If the font found is a non proportional font then topaz/8 will be used.

SkoEd can then be configured using the Set Font and Set Screen menu options. When you have decided on your preferred Screen and Font select Save Prefs.

1.9 CONFIGURATION

In order to use SkoEd with the keymappings you like, then you will need to change the SkoEd.Config/SkoEd.Macro files to contain the mappings you wish to use.

Each keymapping is of the format :

```
<Key Description> <Equals> <String>|<Command> <SemiColon> <Comment>
```

where

```
<Equals>          -> =
<SemiColon>       -> ;
<Comment>         -> Whatever you like.
<Key Description> -> {<Qualifier><Key><Key>}
<Command>         -> <CommandName>{<(><Parameters><)>}<SemiColon>
<CommandName>     -> A command from the command list.
<Parameters>      -> The parameters seperated by spaces that are to be
                        parsed by the command using ReadArgs.
<(>               -> (
<)>               -> )
<String>          -> Anything enclosed in Double Quotes e.g "fred"
<Qualifier>       -> A qualifier from the list below.
<Key>             -> The key you wish to map (Case is ignored)
```

Qualifiers are :

- Shift key
^ - Control key
@ - Alt key
& - Numeric Keypad
!L - Left Amiga
!R - Right Amiga

or you may also use

SHIFT - Shift key
CTRL - Control key
ALT - Alt key
KEYPAD - Numeric Keypad
LEFTAMIGA - Left Amiga
RIGHTAMIGA - Right Amiga

Special Keys are :

\$Fn where $0 \leq n \leq 9$ - Function keys
RETURN - The Return Key
UP - The up arrow key
DOWN - The down arrow key
LEFT - The left arrow key
RIGHT - The right arrow key
DEL - The Del key
HELP - The Help key
BACKSPACE - The Backspace key
TAB - The Tab key
ESC - The ESC key
\
- The next character is not a special character
eg \# is the hash character not a Shift qualifier.

See also Examples and ARexx

Several variables may also be set in the configuration files. These are :

C_DIR	- This string determines where to save the current file for compiling. Set to blank if you wish to use current directory.
COMPILE	- This string is inserted before the filename and then that string is passed to System(). eg "SC" to use the SAS C compiler.
LINK	- This string is passed to System when you call the Link command.
MAKE	- This string is passed to System when you call the Make command.
EXECUTE	- This is the default string to use when you call the Run command.
ERRORS	- This is the default string to use when you call the Errors command.
CLI	- This is the default string to create a new CLI/Shell.
INSERT	- This boolean variable is set to TRUE if you want insert mode to be on at startup.
INDENT	- This boolean variable is set to TRUE if you want automatic

- indenting to be on.
- CAPTIVECRSR - This boolean variable is set to TRUE if you want Captive Cursor mode on at startup.
- MEMORY - This boolean variable is set to TRUE if you want to have SkoEd save memory files when you exit.
- BACKUPS - This boolean variable is set to TRUE if you want to have SkoEd create .BAK files when saving.
- TABSIZE - This numeric variable sets the size of a TAB character.
- AUTOTIME - This numeric variable sets the amount of time in minutes between autosaves of the most changed file.
- MAXUNDO - This numeric variable sets the maximum level of Undo you want.
- RELOAD - This boolean variable if set to TRUE in the config file will force a reload if a memory file is available.
- PRINTER - This string is passed to System() and is used to support printing.
- SAVETABS - This boolean variable is set to TRUE if you want SkoEd to save every TABSIZE spaces at the start of a line as a TAB character.
- LOADTABS - This boolean variable is set to TRUE if you want SkoEd to load TABS as TABS and NOT convert them to spaces.
- TABSSPACES - This boolean variable is set to TRUE if you want TAB command to output TABSIZE spaces or a TAB character.

1.10 AREXX

SkoEd now has an Arexx Port named "SKOED1". All commands are available to Arexx via this port. All commands in SkoEd are Case Sensistive and should therefor be enclosed in Quotes.

For example to put up the About requester in Skoed

```
ADDRESS SKOED1 "About"
```

Commands will either return 0 for success or 10 for failure.

Some commands accept parameters (eg Load_File) and parameters are passed as follows:

```
ADDRESS SKOED1 "Load_File(work:Skoed.doc) "
ADDRESS SKOED1 "Goto_Line(10) "
```

Basically everything between the () is passed to the routine as a single string and then ParseArgs is used to make sense of it.

The same method of parameter passing is used for parameter passing in SkoEd.Config.

See the example ARExx routines given for more clues on interfacing ARExx to SkoEd.

1.11 COMMANDS

Movement Commands

Up
Down
Left
Right
Page_Up
Page_Down
StartOfFile
EndOfFile
StartOfLine
EndOfLine
Scroll_Up
Scroll_Down
Scroll_Left
Scroll_Right
Goto_Line
Goto_Column
UpUp
DownDown

Word Commands

Word_Left
Word_Right
Word_End
Word_Delete
Complete_Word

Fold Commands

Fold_Line
Unfold_Line
Fold_Block
Unfold
Next_Fold
Prev_Fold

Mark Commands

Mark
Unmark
Next_Mark
Prev_Mark
Goto_Mark

Window Commands

Split_Window
Close_Window
Zoom
Explode
Refresh

Miscellaneous Commands

File/Buffer Commands

Load_File
Save_File
Print_File
Reload
Kill_Buffer
Make_Buffer
Print_Buffer
Next_Buffer
Prev_Buffer
Goto_Buffer
Buffer_Info

Block Commands

Block_Begin
Block_End
Block_Copy
Block_Delete
Block_Move
StartOfBlock
EndOfBlock
Block_Hide
Block_Clip
Clip_Block
Block_File
File_Block
Block_Mode
Indent_Block
Unindent_Block
Undo

String Commands

Find
Replace
Again
Match
Count_Braces
Str_Size

CLI/Compiler Commands

Compile
Link
Run
Make
Errors
New_CLI

Generic Editing Commands

Return

None	Backspace
Set_Var	Tab
Get_Var	Del
Set_Env	Del_Line
Set_Vars	Del_EOL
Auto_Save	Del_SOL
Iconify	Exit
Reconfigure	
Msg	
ARexx	

1.12 UpUp

COMMAND : UpUp

PARAMETERS : NONE

DESCRIPTION: This command moves the Cursor up 1 line, scrolling if needed. This routine attempts to keep the Cursor 1 line below the topline so that the line above the Cursor is always visible.

1.13 DownDown

COMMAND : DownDown

PARAMETERS : NONE

DESCRIPTION: This command moves the Cursor Down 1 line, scrolling if needed. This routine attempts to keep the Cursor 1 line above the bottomline so that the line below the Cursor is always visible.

1.14 StartOfBlock

COMMAND : StartOfBlock

PARAMETERS : NONE

DESCRIPTION: This command moves the Cursor to the start of the current Block.

1.15 EndOfBlock

COMMAND : EndOfBlock

PARAMETERS : NONE

DESCRIPTION: This command moves the Cursor to the end of the current Block.

1.16 Up

COMMAND : Up

PARAMETERS : NONE

DESCRIPTION: This moves the Cursor up 1 line, scrolling if needed.

See Also : Down Left Right Page_Up Page_Down

1.17 Down

COMMAND : Down

PARAMETERS : NONE

DESCRIPTION: This moves the Cursor Down 1 line, scrolling if needed.

See Also : Up Left Right Page_Up Page_Down

1.18 Left

COMMAND : Left

PARAMETERS : NONE

DESCRIPTION: This moves the Cursor Left 1 character. If the Start of a line is reached the the Cursor is move to the end of the line above.

See Also : Up Down Right Page_Up Page_Down

1.19 Right

COMMAND : Right

PARAMETERS : NONE

DESCRIPTION: This moves the Cursor Right 1 character until you reach the maximum length of the line (Currently 4096 chars).

See Also : Up Down Left Page_Up Page_Down

1.20 Page_Up

COMMAND : Page_Up

PARAMETERS : NONE

DESCRIPTION: Move Cursor up 1 page.

See Also : Up Down Left Right Page_Down

1.21 Page_Down

COMMAND : Page_Down

PARAMETERS : NONE

DESCRIPTION: Move Cursor down 1 page.

See Also : Up Down Left Right Page_Up

1.22 StartOfFile

COMMAND : StartOfFile

PARAMETERS : NONE

DESCRIPTION: Move to First Line, First Column of File.

See Also : EndOfFile

1.23 EndOfFile

COMMAND : EndOfFile

PARAMETERS : NONE

DESCRIPTION: Move to Last Line, End of the Line.

See Also : StartOfFile

1.24 StartOfLine

COMMAND : StartOfLine

PARAMETERS : NONE

DESCRIPTION: Move to the Start of Current Line.

See Also : EndOfLine

1.25 EndOfLine

COMMAND : EndOfLine

PARAMETERS : NONE

DESCRIPTION: Move to End of Current Line.

See Also : StartOfLine

1.26 Scroll_Up

COMMAND : Scroll_Up

PARAMETERS : NONE

DESCRIPTION: Scroll File Up beneath the Cursor.

See Also : Scroll_Down Scroll_Left Scroll_Right

1.27 Scroll_Down

COMMAND : Scroll_Down

PARAMETERS : NONE

DESCRIPTION: Scroll File Down beneath the Cursor.

See Also : Scroll_Up Scroll_Left Scroll_Right

1.28 Scroll_Left

COMMAND : Scroll_Left

PARAMETERS : NONE

DESCRIPTION: Scroll File Left beneath the Cursor.

See Also : Scroll_Up Scroll_Down Scroll_Right

1.29 Scroll_Right

COMMAND : Scroll_Right

PARAMETERS : NONE

DESCRIPTION: Scroll File Right beneath the Cursor.

See Also : Scroll_Up Scroll_Down Scroll_Left

1.30 Word_Left

COMMAND : Word_Left

PARAMETERS : NONE

DESCRIPTION: Move the Cursor to the previous word if at the start of a word or move to the start of the current word.

See Also : Word_Right Word_End Word_Delete Complete_Word

1.31 Word_Right

COMMAND : Word_Right

PARAMETERS : NONE

DESCRIPTION: Move the Cursor to the start of the next word.

See Also : Word_Left Word_End Word_Delete Complete_Word

1.32 Word_End

COMMAND : Word_End

PARAMETERS : NONE

DESCRIPTION: Move the Cursor to the end of the current word.

See Also : Word_Left Word_Right Word_Delete Complete_Word

1.33 Goto_Line

COMMAND : Goto_Line

PARAMETERS : LINE/N

DESCRIPTION: Goto a line Number. If Line number is not given then display a Requester asking for a line number.

See Also : Goto_Column Goto_Buffer

1.34 Goto_Column

COMMAND : Goto_Column

PARAMETERS : COLUMN/N/A

DESCRIPTION: Goto the Column Number given.

See Also : Goto_Line Goto_Buffer

1.35 Next_Buffer

COMMAND : Next_Buffer

PARAMETERS : NONE

DESCRIPTION: Switch to the next buffer in the list.

See Also : Prev_Buffer Goto_Buffer Kill_Buffer Make_Buffer Print_Buffer

1.36 Prev_Buffer

COMMAND : Prev_Buffer

PARAMETERS : NONE

DESCRIPTION: Switch to the previous buffer in the list.

See Also : Next_Buffer Goto_Buffer Kill_Buffer Make_Buffer Print_Buffer

1.37 Goto_Buffer

COMMAND : Goto_Buffer

PARAMETERS : NAME

DESCRIPTION: Switch to the buffer given. If NO buffer given then show a requester listing all buffers and select a buffer to switch to.

See Also : Next_Buffer Prev_Buffer Kill_Buffer Make_Buffer Print_Buffer

1.38 Next_Fold

COMMAND : Next_Fold

PARAMETERS : NONE

DESCRIPTION: Move to the Next Fold if any.

See Also : Fold_Line Unfold Prev_Fold Fold_Block Unfold_Line

1.39 Prev_Fold

COMMAND : Prev_Fold

PARAMETERS : NONE

DESCRIPTION: Move to the Previous Fold if any.

See Also : Fold_Line Unfold Next_Fold Fold_Block Unfold_Line

1.40 Next_Mark

COMMAND : Next_Mark

PARAMETERS : NONE

DESCRIPTION: Make the Next Mark the Current Mark.

See Also : Mark Unmark Prev_Mark Goto_Mark

1.41 Prev_Mark

COMMAND : Prev_Mark

PARAMETERS : NONE

DESCRIPTION: Make the previous Mark the Current Mark.

See Also : Mark Unmark Next_Mark Goto_Mark

1.42 Goto_Mark

COMMAND : Goto_Mark

PARAMETERS : MARKNUM/N

DESCRIPTION: If no parameter then
 move to the current Mark
 else
 move to mark number NUM.

See Also : Mark Unmark Next_Mark Prev_Mark

1.43 Match

COMMAND : Match

PARAMETERS : NONE

DESCRIPTION: Currently matches up {[&]}}

See Also : Count_Braces

1.44 Return

COMMAND : Return

PARAMETERS : NONE

DESCRIPTION: Splits the line at the Cursor position.

1.45 Backspace

COMMAND : Backspace

PARAMETERS : NONE

DESCRIPTION: Deletes the character to the left of the Cursor. If the Cursor is at the start of the line then Join the current line to the line above.

See Also : Del

1.46 Del

COMMAND : Del

PARAMETERS : NONE

DESCRIPTION: Deletes the character under the Cursor. If the Cursor is at the end of the line the join the line below to the current line.

See Also : Backspace

1.47 Del_Line

COMMAND : Del_Line

PARAMETERS : NONE

DESCRIPTION: Delete the current line.

See Also : Del_EOL Del_SOL Block_Delete Undo

1.48 Word_Delete

COMMAND : Word_Delete

PARAMETERS : NONE

DESCRIPTION: Delete the Word beneath the Cursor.

See Also : Word_Left Word_Right Word_End Complete_Word

1.49 Del_EOL

COMMAND : Del_EOL

PARAMETERS : NONE

DESCRIPTION: Delete all characters from Cursor until the End Of Line.

See Also : Del_Line Del_SOL Block_Delete Undo

1.50 Del_SOL

COMMAND : Del_SOL

PARAMETERS : NONE

DESCRIPTION: Delete all characters from Cursor until the Start Of Line.

See Also : Del_EOL Del_Line Block_Delete Undo

1.51 Block_Begin

COMMAND : Block_Begin

PARAMETERS : NONE

DESCRIPTION: Set the Start of a block to the Cursor position.

See Also : Block_End Block_Copy Block_Delete Block_Move

Block_Hide Block_Mode Block_Clip Clip_Block Block_File
File_Block Undo Indent_Block Unindent_Block

1.52 Block_End

COMMAND : Block_End

PARAMETERS : NONE

DESCRIPTION: Set the End of a block to the Cursor position.

See Also : Block_Begin Block_Copy Block_Delete Block_Move
Block_Hide Block_Mode Block_Clip Clip_Block Block_File
File_Block Undo Indent_Block Unindent_Block

1.53 Block_Copy

COMMAND : Block_Copy

PARAMETERS : NONE

DESCRIPTION: Copy a Block to the Cursor position.

See Also : Block_Begin Block_End Block_Delete Block_Move
Block_Hide Block_Mode Block_Clip Clip_Block Block_File
File_Block Undo Indent_Block Unindent_Block

1.54 Block_Delete

COMMAND : Block_Delete

PARAMETERS : NONE

DESCRIPTION: Delete the current Block.

See Also : Block_Begin Block_End Block_Copy Block_Move
Block_Hide Block_Mode Block_Clip Clip_Block Block_File
File_Block Undo Indent_Block Unindent_Block

1.55 Block_Move

COMMAND : Block_Move

PARAMETERS : NONE

DESCRIPTION: Move the current block to the Cursor position.

See Also : Block_Begin Block_End Block_Copy Block_Delete
Block_Hide Block_Mode Block_Clip Clip_Block Block_File
File_Block Undo Indent_Block Unindent_Block

1.56 Block_Hide

COMMAND : Block_Hide

PARAMETERS : NONE

DESCRIPTION: Turn off the block.

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Mode Block_Clip Clip_Block Block_File
File_Block Undo Indent_Block Unindent_Block

1.57 Block_Clip

COMMAND : Block_Clip

PARAMETERS : NONE

DESCRIPTION: Copy the Current block to the clipboard Unit 0

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Hide Block_Mode Clip_Block Block_File
File_Block Undo Indent_Block Unindent_Block

1.58 Clip_Block

COMMAND : Clip_Block

PARAMETERS : NONE

DESCRIPTION: Copy the contents of Clipboard Unit 0 to the Buffer and make it the current block.

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Hide Block_Mode Block_Clip Block_File
File_Block Undo Indent_Block Unindent_Block

1.59 Block_File

COMMAND : Block_File

PARAMETERS : NONE

DESCRIPTION: Copy the current block to a File.

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Hide Block_Mode Block_Clip Clip_Block
File_Block Undo Indent_Block Unindent_Block

1.60 File_Block

COMMAND : File_Block

PARAMETERS : NONE

DESCRIPTION: Copy a file into the current buffer and make it the current block.

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Hide Block_Mode Block_Clip Clip_Block Block_File
Undo Indent_Block Unindent_Block

1.61 Block_Mode

COMMAND : Block_Mode

PARAMETERS : NONE

DESCRIPTION: Switch between Normal Block Mode and Column Block Mode.

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Hide Block_Clip Clip_Block Block_File
File_Block Undo Indent_Block Unindent_Block

1.62 Indent_Block

COMMAND : Indent_Block

PARAMETERS : NONE

DESCRIPTION: Inserts 1 space before each fully highlighted line.

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Hide Block_Mode Block_Clip Clip_Block Block_File
File_Block Undo Unindent_Block

1.63 Unindent_Block

COMMAND : Unindent_Block

PARAMETERS : NONE

DESCRIPTION: Removes 1 space before each fully highlighted line.

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Hide Block_Mode Block_Clip Clip_Block Block_File
File_Block Undo Indent_Block

1.64 Undo

COMMAND : Undo

PARAMETERS : NONE

DESCRIPTION: Reverses the effects of Block_Delete, Del_Line & Word_Delete.
The Undo limit is set by MAXUNDO.

See Also : Block_Begin Block_End Block_Copy Block_Delete Block_Move
Block_Hide Block_Mode Block_Clip Clip_Block Block_File
File_Block Indent_Block Unindent_Block

1.65 Split_Window

COMMAND : Split_Window

PARAMETERS : NONE

DESCRIPTION: Split the current window into 2 windows.

See Also : Close_Window Zoom Explode Refresh

1.66 Close_Window

COMMAND : Close_Window

PARAMETERS : NONE

DESCRIPTION: Close the current window.

See Also : Split_Window Zoom Explode Refresh

1.67 Zoom

COMMAND : Zoom

PARAMETERS : NONE

DESCRIPTION: Switch between Full sized window and current size of window.

See Also : Split_Window Close_Window Explode Refresh

1.68 Explode

COMMAND : Explode

PARAMETERS : NONE

DESCRIPTION: Make the current window full size.

See Also : Split_Window Close_Window Zoom Refresh

1.69 Refresh

COMMAND : Refresh

PARAMETERS : NONE

DESCRIPTION: Force a refresh of all windows.

See Also : Split_Window Close_Window Zoom Explode

1.70 Load_File

COMMAND : Load_File

PARAMETERS : NAME,OVER/S,NODUP/S

DESCRIPTION: Load a file into a Buffer.

NAME : The name of the file to load - Full path preferred.
If not present then get a filename from the filerequester.
OVER : If present the current buffer will be OVERWRITTEN.
NODUP : If present the Buffer list will be searched and if the file
requested is already in memory then the file will not be
loaded.

See Also : Save_File Print_File Reload

1.71 Save_File

COMMAND : Save_File

PARAMETERS : NEW/S

DESCRIPTION: Save the current buffer. If the file is a temp file or parameter \leftrightarrow NEW present then request a new filename.

See Also : Load_File Print_File Reload

1.72 Print_File

COMMAND : Print_File

PARAMETERS : NAME

DESCRIPTION: Print the given file. If no file given then prompt for a filename. Printing is accomplished by executing the PRINTER string with the filename appended.

See Also : Load_File Save_File Reload

1.73 Reload

COMMAND : Reload

PARAMETERS : NONE

DESCRIPTION: Read the Reload file (Skoed.Memory) and load all files contained in it.

See Also : Load_File Save_File Print_File

1.74 Kill_Buffer

COMMAND : Kill_Buffer

PARAMETERS : NONE

DESCRIPTION: Free the current Buffer.

See Also : Next_Buffer Prev_Buffer Goto_Buffer Make_Buffer Print_Buffer

1.75 Make_Buffer

COMMAND : Make_Buffer

PARAMETERS : NONE

DESCRIPTION: Create a new buffer named "Temp". Please note temp files are not saved and are not put into memory files.

See Also : Next_Buffer Prev_Buffer Goto_Buffer Kill_Buffer Print_Buffer

1.76 Print_Buffer

COMMAND : Print_Buffer

PARAMETERS : NAME

DESCRIPTION: Print the buffer specified. If no buffer specified then select a buffer from the list. Printing is accomplished by saveing the ↵ buffer to C_DIR and then append the filename to the PRINTER string before executeing the PRINTER string.

See Also : Next_Buffer Prev_Buffer Goto_Buffer Kill_Buffer Make_Buffer

1.77 Compile

COMMAND : Compile

PARAMETERS : NONE

DESCRIPTION: Save the current file to C_DIR, Append the filename to the compile string and then Execute it.

See Also : Link Make Run Errors New_CLI

1.78 Link

COMMAND : Link

PARAMETERS : NONE

DESCRIPTION: Execute the LINK string.

See Also : Compile Make Run Errors New_CLI

1.79 Run

COMMAND : Run

PARAMETERS : NONE

DESCRIPTION: Display a requester asking for a EXECUTE string and then execute it.

See Also : Compile Make Link Errors New_CLI

1.80 Make

COMMAND : Make

PARAMETERS : NONE

DESCRIPTION: Execute the MAKE string.

See Also : Compile Link Run Errors New_CLI

1.81 Errors

COMMAND : Errors

PARAMETERS : NONE

DESCRIPTION: Execute the ERRORS string.

See Also : Compile Make Run Link New_CLI

1.82 New_CLI

COMMAND : New_CLI

PARAMETERS : NONE

DESCRIPTION: Execute the NEWCLI string.

See Also : Compile Make Run Errors Link

1.83 Find

COMMAND : Find

PARAMETERS : NONE

DESCRIPTION: Find a String.
The following options are available :

No Care Case : Case is ignored in search.
All Buffers : Search all buffers for word.
Continuous : Count words instead of search.
(Not yet implemented)

See Also : Replace Again

1.84 Replace

COMMAND : Replace

PARAMETERS : NONE

DESCRIPTION: Find and Replace a string.
The following options are available :
No Care Case : Case is ignored in search.
All Buffers : Search all buffers for word.
Continuous : Replace all words.
Hold Updates : Keep updates to minimum (Fast)
Query : Ask before replacing.

See Also : Find Again

1.85 Again

COMMAND : Again

PARAMETERS : NONE

DESCRIPTION: Repeat previous Find or Replace command

See Also : Find Replace

1.86 Mark

COMMAND : Mark

PARAMETERS : MARKNUM/N

DESCRIPTION: Create a new mark at current position.
An optional Number may be given as a parameter and will be assigned ↔
to
this mark. Parameter must be > 0.

See Also : Unmark Next_Mark Prev_Mark Goto_Mark

1.87 Unmark

COMMAND : Unmark

PARAMETERS : NONE

DESCRIPTION: Remove the current Mark.

See Also : Mark Next_Mark Prev_Mark Goto_Mark

1.88 Fold_Line

COMMAND : Fold_Line

PARAMETERS : NONE

DESCRIPTION: Fold the current line.

See Also : Unfold Next_Fold Prev_Fold Fold_Block Unfold_Line

1.89 Unfold_Line

COMMAND : Unfold_Line

PARAMETERS : NONE

DESCRIPTION: Unfold a line from a fold

See Also : Unfold Next_Fold Prev_Fold Fold_Block Fold_Line

1.90 Fold_Block

COMMAND : Fold_Block

PARAMETERS : NONE

DESCRIPTION: Fold an entire block

See Also : Unfold Next_Fold Prev_Fold Fold_Line Unfold_Line

1.91 Unfold

COMMAND : Unfold

PARAMETERS : NONE

DESCRIPTION: Unfold the entire fold

See Also : Next_Fold Prev_Fold Fold_Block Unfold_Line Fold_Line

1.92 Str_Size

COMMAND : Str_Size

PARAMETERS : NONE

DESCRIPTION: Display the length of a string that the Cursor is in.
- A number preceded by \ (eg \123) is considered 1 char.
- A \ followed by a character is considered 1 char.

1.93 None

COMMAND : None

PARAMETERS : NONE

DESCRIPTION: Do Nothing. :-) Well actually this will force a refresh of the menu strip.

1.94 Set_Var

COMMAND : Set_Var

PARAMETERS : VAR/A,VALUE,TOGGLE/S

DESCRIPTION: Set an internal variable.

VAR is the variable name and must be one of :

C_DIR
COMPILE
LINK
MAKE
EXECUTE
ERRORS
CLI
INSERT
INDENT
CAPTIVECRSR
MEMORY
BACKUPS
TABSIZ
AUTOTIME
MAXUNDO
RELOAD
PRINTER
SAVETABS
LOADTABS

TABSPACES
SCRIPT

VALUE is the value to set the variable to and may be :

a BOOLEAN -> TRUE/FALSE
a string -> "fred"
a number -> 123

TOGGLE if present will toggle the value of a boolean variable

See Also : Get_Var

1.95 Get_Var

COMMAND : Get_Var

PARAMETERS : VAR/A

DESCRIPTION: This command is for ARexx only and will retrieve the variable specified.

VAR is the variable whose value you wish to retrieve and must be one of :

C_DIR
COMPILE
LINK
MAKE
EXECUTE
ERRORS
CLI
INSERT
INDENT
CAPTIVECRSR
MEMORY
BACKUPS
TABSIZ
AUTOTIME
MAXUNDO
RELOAD
PRINTER
SAVETABS
LOADTABS
TABSPACES
SCRIPT
CurrX
CurrY
LineNum
MaxLines
FileName
FilePath
CurrLine
CurrWord

See Also : Set_Var

1.96 Descriptions of Variables

Descriptions of variables are :

C_DIR <String>

This string stores the directory to save the current buffer to when the compile command is used. Set this to "" if you want to save to the current directory.

COMPILE <String>

This is the string that will be executed by the compile command. the C_DIR and the filename of the current buffer will be appended to this string.

LINK <String>

This is the string that will be executed by the link command.

MAKE <String>

This is the string that will be executed by the Make command.

EXECUTE <String>

This is the string that will be the default for the execute command.

ERRORS <String>

This is the string that will be executed by the Error command.

CLI <String>

This is the string that will be executed by the CLI command.

INSERT <Boolean>

This variable is set to TRUE for insert mode and FALSE for Overwrite mode.

INDENT <Boolean>

This variable is set to TRUE for Indent On and FALSE for No Indent.

CAPTIVECRSR <Boolean>

This variable is set to TRUE for a Captive Cursor and FALSE for a free Cursor.

MEMORY <Boolean>

This variable is set to TRUE if SkoEd is to save all files loaded to a Memory file on exit.

BACKUPS <Boolean>

This variable is set to TRUE if SkoEd is to rename the file being saved to <File>.bak before saving.

TABSIZE <Integer>

This variable is set to the number of spaces that a tab is defined as.

AUTOTIME <Integer>

This variable is the number of minutes before the AutoSave command is invoked. Setting this value to 0 will turn off AutoSave.

MAXUNDO <Integer>

This variable defines the maximum number of Undo commands that can be

performed.

RELOAD <Boolean>

This variable is set to TRUE if you want skoed to automatically invoke the reload command upon startup.

PRINTER <String>

This is the string that will be executed by the print commands. A filename will be appended to this string.

SAVETABS <Boolean>

This variable is set to TRUE if you want leading spaces on a line to be converted to TABS when saving the file.

LOADTABS <Boolean>

This variable is set to TRUE wif you want TABS to be converted to SPACES on loading a file. FALSE will leave TABS alone.

TABSSPACES <Boolean>

This variable is set to FALSE if you want to insert a TAB character into your file. TRUE will convert the TAB to upto TABSIZE spaces.

SCRIPT <Boolean>

This variable is set to TRUE if the current file has the Script protection bit set. FALSE otherwise

CurrX <Integer> <Read Only>

This is the column position of the cursor. Ranges from 1 to 4096.

CurrY <Integer> <Read Only>

This is the abs position of the cursor relative to the Top most visible line in the window. Ranges from 1 to WindowSize.

LineNum <Integer> <Read Only>

This is the current line number of the cursor.

MaxLines <Integer> <Read Only>

This is the number of lines in the file.

FileName <String>

This is the filename of the file.

FilePath <String>

This is the filepath of the file.

CurrLine <String> <Read Only>

This is the current line.

CurrWord <String> <Read Only>

This is the word beneath the Cursor.

1.97 Buffer_Info

COMMAND : Buffer_Info

PARAMETERS : NONE

DESCRIPTION: Give some hopefully usefull information about the current buffer.
Also allows you to :
 convert the file from AMIGA -> IBM and back.
 Set/Unset the Script bit.
 Set/Unset the Read Only flag.

1.98 Set_Env

COMMAND : Set_Env

PARAMETERS : NONE

DESCRIPTION: Allow you to set a keymapping on the fly.
 basically requests a string and parses it in the same manner as the
 Skoed.Config file is.

1.99 Set_Vars

COMMAND : Set_Vars

PARAMETERS : NONE

DESCRIPTION: Allow you to set various variables via a requester.

1.100 Count_Braces

COMMAND : Count_Braces

PARAMETERS : NONE

DESCRIPTION: Count all the { and } characters in the current buffer.

See Also : Match

1.101 Complete_Word

COMMAND : Complete_Word

PARAMETERS : NONE

DESCRIPTION: Attempt to complete the word that was started.
 This will only work if the word has been used previously in the file ↵
 .

See Also : Word_Left Word_Right Word_End Word_Delete

1.102 Auto_Save

COMMAND : Auto_Save

PARAMETERS : NONE

DESCRIPTION: Save the file that has had the most changes as <File>.Auto

1.103 Tab

COMMAND : Tab

PARAMETERS : NONE

DESCRIPTION: Insert/Overwrite with TABSIZE spaces.

1.104 Exit

COMMAND : Exit

PARAMETERS : NONE

DESCRIPTION: Exit SkoEd.

1.105 Iconify

COMMAND : Iconify

PARAMETERS : NONE

DESCRIPTION: Closes the SkoEd screen and window and open up a small window on WorkBench. Use Right mouse button to UnIconify.

1.106 Reconfigure

COMMAND : Reconfigure

PARAMETERS : NONE

DESCRIPTION: This removes all configuration details and reloads them from the SkoEd.Config ans SkoEd.Macro files.

1.107 Msg

COMMAND : Msg

PARAMETERS : MESSAGE/A/K

DESCRIPTION: Puts the message given onto the message line.

1.108 ARexx Command

COMMAND : ARexx

PARAMETERS : COMMAND/A

DESCRIPTION: Execute an ARexx script given in COMMAND.

Note: the script is executed Asynchronously. SkoEd will continue to accept input from the user even if ARexx is giving commands. ↵

However

I believe under the current implementation if ARexx begins communicating with SkoEd then User commands are held until ARexx has finished but don't bet on it.

1.109 EXAMPLES

Some Examples of configuring keys.

`^Y = Del_Line;` This will delete the current line.

`CTRL Y=Del_Line;`

^ Note the space

`^Q = Exit;` Exit Skoed

`$F1 = "Hello";` Output the string "Hello" when Function key 1 is pressed.

`&RETURN = Return;` Make the enter key on the numeric keypad the same as Return key.

`^UP = Page_Up;`

`$F5 = Zoom;`

`^$F5 = Explode;`

`^KB = Block_Begin;`

`!LP = Prev_Buffer;`

Note that `^>` is incorrect as the shift key needs to be down to get `>`. You should use `^#>` or `#^>` or `SHIFT CTRL >`.

SkoEd sets the following keys automatically :

`RETURN = Return;`

`&RETURN = Return;`

`UP = Up;`

`DOWN = Down;`

`LEFT = Left;`

`RIGHT = Right;`

`DEL = Del;`

`BACKSPACE = Backspace;`

```
TAB = Tab;
```

Some examples of setting variables in Config files.

```
COMPILE = "cc";  
CLI = "AShell";  
MEMORY = FALSE;  
BACKUPS = TRUE;  
TABSIZe = 4;  
MAXUNDO = 10;
```

Have a look at the config and macro files given with this distribution for more examples. A lot of it is test configs that I use so there is a fair range of key and variable configurations.

1.110 DISCLAIMER

THIS PROGRAM IS PROVIDED ON AN "AS IS" BASIS, NO WARRANTIES ARE MADE, EITHER EXPRESSED OR IMPLIED. IN NO EVENT WILL I, DAVID MCPAUL, BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES ARISING FROM ANY USE OR MISUSE OF THIS PROGRAM. THE ENTIRE RISK AS TO THE RESULTS AND PERFORMANCE OF THIS PROGRAM IS ASSUMED BY YOU.

IBM is a registered trademark of International Business Machines Corp.
AMIGA is a registered trademark of Commodore-Amiga, Inc.
ReqTools is Copyright (c) Nico François