

Symbolic Constants

Connection Status

DECLARED IN `nikit/domain.h`

SYNOPSIS NI_ALREADYCONNECTED
NI_NOTCONNECTED

DESCRIPTION These constants are used as return values to indicate whether a connection to a NetInfo domain already exists.

Test Modes

DECLARED IN `nikit/NILoginPanel.h`

```
SYNOPSIS                                NI_USERTESTMODE    0
NI_NETINFOTESTMODE                        1
```

DESCRIPTION These constants are used to set the value of the **bootMode** instance variable. You shouldn't need to use them unless you're subclassing `NILoginPanel` and are overriding one of the **runModal** methods or implementing a similar method. The method should set **bootMode** to `NI_USERTESTMODE` if the delegate should validate the authentication. The **bootMode** instance variable should be set to `NI_NETINFOTESTMODE` if the authentication should be validated by the **ni_setuser()** and **ni_setpassword()** functions, which are documented in the **netinfo(3)** UNIX manual page.

Structures

NIDomainCellData

DECLARED IN `nikit/domain.h`

```
SYNOPSIS
char *name;
BOOL isaLeaf;
}

struct NIDomainCellData {
```

DESCRIPTION	Data for a cell of a domain browser.
--------------------	--------------------------------------

NIHierarchyOfDomains

DECLARED IN nikit/domain.h

SYNOPSIS

```
int numberOfLevels;  
struct NIMultiDomainList *domainListAtLevel;  
}
```

struct **NIHierarchyOfDomains** {

DESCRIPTION Hierarchy of NetInfo domains.

NIMultiDomainList

DECLARED IN nikit/domain.h

SYNOPSIS

```
int numberOfDomains;  
int activeDomain;  
id activeDomainObject;  
struct NIDomainCellData *topDomain;  
}
```

struct **NIMultiDomainList**{

DESCRIPTION Data for a domain browser column.