

**Xoper**

**COLLABORATORS**

	<i>TITLE :</i> Xoper		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		April 15, 2022	

**REVISION HISTORY**

NUMBER	DATE	DESCRIPTION	NAME

# Contents

<b>1</b>	<b>Xoper</b>	<b>1</b>
1.1	Xoper Documentation - Contents . . . . .	1
1.2	Xoper Documentation - Introduction . . . . .	2
1.3	Xoper Documentation - Requirements . . . . .	2
1.4	Xoper Documentation - Installation . . . . .	2
1.5	Xoper Documentation - Usage . . . . .	3
1.6	Xoper Documentation - Keys . . . . .	4
1.7	Xoper Documentation - Commands . . . . .	6
1.8	Xoper Documentation - Viewing Exec lists . . . . .	6
1.9	Xoper Documentation - Viewing other system lists . . . . .	9
1.10	Xoper Documentation - Commands with parameter . . . . .	12
1.11	Xoper Documentation - Commands without parameter . . . . .	17
1.12	Xoper Documentation - Toggles and Options . . . . .	19
1.13	Xoper Documentation - Dangerous Commands . . . . .	22
1.14	Xoper Documentation - Bugs and Limitations . . . . .	23
1.15	Xoper Documentation - Technical Info . . . . .	25
1.16	Xoper Documentation - History . . . . .	26
1.17	Xoper Documentation - Acknowledgments . . . . .	30
1.18	Xoper Documentation - Disclaimer . . . . .	30
1.19	Xoper Documentation - Copyright . . . . .	31
1.20	Xoper Documentation - Author . . . . .	31
1.21	Xoper Documentation - Task Types . . . . .	31
1.22	Xoper Documentation - Task States . . . . .	32
1.23	Xoper Documentation - Task Names . . . . .	33
1.24	Xoper Documentation - CLI Infos . . . . .	33
1.25	Xoper Documentation - Base Address . . . . .	33
1.26	Xoper Documentation - Open Count . . . . .	33
1.27	Xoper Documentation - Version and Revision . . . . .	34
1.28	Xoper Documentation - Flags . . . . .	34
1.29	Xoper Documentation - Name . . . . .	34
1.30	Xoper Documentation - The Amiga Guru Book . . . . .	34

---

# Chapter 1

# Xoper

## 1.1 Xoper Documentation - Contents

Xoper 2.8

A powerful system monitor  
Copyright © 1988/99 by Werner Günther and Gunther Nikl  
All Rights Reserved.

Introduction	What is Xoper?
Requirements	System requirements
Installation	Getting started
Usage	How to use Xoper
Some Basics	Keyboard Control
Command Overview	Description of all commands
Bugs/Limitations	Existing problems
Technical Info	How it was done
History	What is new?

---

Acknowledgments	Whom I want to thank.
Disclaimer	No Warrantries
Copyright	About legal issues.
Author	Who did it?

## 1.2 Xoper Documentation - Introduction

### Introduction

\*\*\*\*\*

Xoper is a system monitor to display various system lists, eg. it can show all running tasks with their cpu-usage. Xoper does not only display a list of all tasks but it can show other system lists from Exec, Dos or Intuition as well eg. the port list, available windows and screens or Dos-devices.

Xoper is FREeware.

## 1.3 Xoper Documentation - Requirements

### Requirements

\*\*\*\*\*

Xoper has no special requirements to run. To use Xoper an Amiga with at least 512KB RAM and Kickstart 1.2 (V33) is sufficient. It works with any amiga system upto Kickstart 3.1 (V40). No problems should arise with 68020, 68030, 68040 and 68060 processors.

## 1.4 Xoper Documentation - Installation

### Installation

\*\*\*\*\*

Installing Xoper is fairly easy. Copy the program including its info file to a location on your harddisk. If you want you can then add this location to the global search path using the 'path' command, but this is not required. Thats all :-)

---

## 1.5 Xoper Documentation - Usage

### Usage

\*\*\*\*\*

Xoper can be started either from CLI/Shell or Workbench. To start Xoper from the Workbench doubleclick on its icon. To start Xoper from the shell simply type:

```
1> Xoper
```

followed by a return. This should start Xoper provided that it could be located somewhere in your search path.

Xoper can be started with several options. If you run it from the shell with a questionmark (?) as argument you'll get the argument template:

```
"CMD/K,KEEPPIO/S,NOSCRIP/S,CX_POPUP/K,CX_POPKEY/K,CX_PRIORITY/N/K"
```

- CMD

used to specify which system list Xoper shall show by default  
or  
used to remove Xoper from memory -> CMD=kill

```
!!! WARNING: Killing Xoper this way is a REAL hack! WARNING !!!
```

- KEEPPIO

This switch tells Xoper not to create a background process when called from CLI. Instead it will block its shell unless you used 'run' to launch the program.  
By default Xoper 'detaches' itself from the CLI.

- NOSCRIP

Specifying this option disables the execution of Xopers startup script.

- CX\_POPUP

This switch decides whether to open Xopers window at startup or not by specifying ON or OFF. It replaces the '-b' switch prior to v2.4. The default is to open Xopers main window. Please note, this argument will be used even with Kickstart 1.2/1.3!

- CX\_POPKEY

This specifies which hotkey Xoper shall use. The format of this string has to be a valid commodity string description. Its necessary to quote the description, eg.

```
CX_POPKEY="lalt lshift numpad *"
```

This argument affects only the \*commodity\* hotkey not the inpuhandler hotkey. That one is hard-coded into Xoper and its always "Amiga-Amiga-x ←".

Because the commodity.library is only available with Kickstart 2.0 or higher CX\_POPKEY is ignored with older Kickstart revisions.

- CX\_PRIORITY

This argument is used to specify the priority for Xopers commodity broker. ←  
 It has to be between -128 and +127. Here applies the same as with ←  
 CX\_POPKEY: ←  
 this switch is ignored under Kickstart 1.2/1.3.

All those arguments can also be specified when running Xoper from Workbench ←  
 by ←  
 adding tooltypes to Xopers icon. An exception is 'KEEPPIO' but its useless ←  
 for ←  
 the workbench start anyway. If you place Xoper in the WBStartup-drawer ←  
 available ←  
 with OS2.0 or higher please add the tooltype "DONOTWAIT" or the system will ←  
 wait ←  
 until Xoper ends...

At startup Xoper loads and executes a file named 'Xoper.Startup'. That file ←  
 can ←  
 be placed in various locations. First Xoper tries to open the script in the ←  
 current directory, then in env: and lastly in s:. This startup-script is ←  
 used to ←  
 set default values, the window size or the initial default list to be ←  
 displayed. ←  
 Xopers window will be opened after the startup-script has been processed (if ←  
 one ←  
 was found of course).

NOTE: Please make sure that the startup script is not bigger than 2400 bytes ←  
 since Xoper only reads that amount of data! ←  
 (I really think this size should be sufficient :)

Xoper can be controlled via 'Exchange' - the commodities master control ←  
 program. ←  
 With Exchange its possible to force Xoper to show/hide its window or to ←  
 remove ←  
 Xoper from memory. Removing can also be done by sending Xoper a Ctrl-C. Its ←  
 not ←  
 possible to deactivate Xopers commodity broker. It stays always active - I ←  
 feel ←  
 that a hotkey has always to be present.

## 1.6 Xoper Documentation - Keys

Keys  
 \*\*\*\*

Xoper has to be controlled over the keyboard. The only exceptions there the ←  
 mouse ←  
 can be used are:

- the slider gadget to scroll in the output window up or down
- the dragbar to move Xopers window around
- the various gadgets to control the window size, to depth arrange the ←  
 window ←  
 or the screen.

All commands, however, have to be entered via the keyboard. This may seem to be a little bit ancient, but its in no way a restriction. There are not many keys that need to be remembered. :-)

Xopers window (or screen, but even then its the window) is divided into two sections: an very small input line on the bottom and a large output area on the top. If the output exceeds the size of the window you may scroll or 'page through the text using the num-pad keys:

A1000	others	
7	Home	Top of display
1	End	Bottom
9	Pg Up	one page up
3	Pg Dn	one page down
8	Up Arrow	one line up
2	Down Arrow	one line down
4	Left Arrow	one page left
6	Right Arrow	one page right

For up and down scrolling you can also use the slider gadget, but this should be obvious.

The input section has some line editing facilities and a history buffer controllable with the following keys:

Cursor left	cursor one character left
Shift left	cursor to the start of the previous word
Cursor right	cursor one character right
Shift right	cursor to the start of the next word
Cursor Up	previous line in history buffer
Shift Up	top of buffer
Cursor Down	next line in history buffer
Shift Down	bottom of buffer
DEL	delete char under the cursor
BS	delete char left from the cursor
Ctrl a	jump to start of line
Ctrl e	jump to end of line
Ctrl x	delete the entire line
Ctrl k	delete EOL
Ins (numpad '0')	toggles insert mode (default is 'on')
Del (numpad '.')	same as DEL
Tab	Command line completion Example: press <c>, hit <tab> several times.
ESC output	moves the input area from the bottom into the output section. Entering a command here (i.e overwriting an output line), will cause Xoper to add the address of that node to your command line.



Example: Show the hunks of a 'File.System' process ↵  
 :  
 type 'T' to get a list of all tasks, press <esc>, ↵  
 move  
 the cursor to the line displaying the File.System  
 process and type 'Hunks <enter>'. Press <enter> ↵  
 once  
 more to return to the usual Xoper display.

HELP displays the help panel (may be pressed at any ↵  
 time)

## 1.7 Xoper Documentation - Commands

Commands

\*\*\*\*\*

Commands have to be entered in the input line at the bottom of the window.  
 These are divided into several groups:

Exec lists

Other system lists

Commands with parameter

Commands without parameter

Toggles and options

Dangerous commands

## 1.8 Xoper Documentation - Viewing Exec lists

- EXEC lists

-----

These are always single character entries and may be specified in any ↵  
 order,  
 upper or lower case, after the prompt or from CLI/WB as parameters. If ↵  
 more  
 than one list has to be displayed, you may enter several commands in one  
 line. Separating them with blanks displays the list one by one instead of  
 showing them all at once.

T = Tasks (default if Xoper is started without parameters)

Shows some essential values for  
 tasks  
 (this includes dos processes). The

display contains the address of the tasknode,  
 task type  
 ,  
 task state  
 ,  
 task priority in decimal , CPU usage in percent, the process number ( ←  
 only  
  
 dos processes  
 started from CLI), and  
 task name  
 .

#### F = Task Flags

Shows also the task list but with some other information than the 'T' ←  
 command.  
 Lists the task node in HEX,  
 task state  
 , allocated signals, signals the task  
 is waiting for, so far received signals, the address of the next ←  
 instruction to  
 be executed - usually refered as the program counter (pc) -, for ←  
 amigas equiped  
 with a FPU the fpu-state and  
 task name  
 .

#### U = CPU Usage

Shows again the task list but also with other information than the 'T' ←  
 or 'F'  
 command.  
 Lists the task node in HEX,  
 task state  
 , a tasks run time and its total amount  
 of cpu time it used so far (both values since Xoper was started!), the ←  
 process  
 number and  
 task name  
 .

#### C = CLI Commands

Shows a list of all CLI commands.  
 Displays the task node in HEX,  
 task state  
 ,  
 type  
 ,  
 mode  
 , cli number, cli name  
 (the process name) and command (the actual executed command).

L = Libraries  
D = Devices  
R = Resources

Shows a list of all currently loaded libraries, devices or resources. ↔

They are explained together because all have the same basic structure.

Displays the  
base address  
,  
open count  
,  
version  
and  
revision  
,  
flags  
and  
name

E = Resident

Shows a list of all resident modules of the system.

Displays the base address, priority, flags, version, type and name for ↔  
every  
resident module found.

M = Memory

Shows all available memory types

Displays the lower and upper bound, free bytes, memory attributes, ↔  
priority  
and hunkname for all memory regions

P = Ports

Shows a list of all public ports in the system.

Displays the port address, port name, port flags, signal bit, queue ↔  
length  
(number of messages) and taskname of the owner.

I = Interrupts

Shows a lists of all interrupts.

Displays the interrupts node address, pointer to interrupt data, ↔  
pointer to  
interrupt code, priority, interrupt type ([S]erver/[H]andler), ↔  
interrupt  
interrupt state ([E]nabled/[D]isabled), another type (interrupt queue ↔  
the  
interrupt belongs to) and interrupt name.

S = Stack

---

Shows information about task stacks.  
 Displays the lower limit, the actual stack size, the currently used ↵  
 stacksize  
 and taskname. If the current stackpointer is not within the tasks ↵  
 stackbounds  
 this function displays "----" as used stacksize (possible candidates ↵  
 for this  
 are programs launched with ixemuls vfork() call)

CAUTION: if you want to minimize your stack using this utility, please  
 note that dos-functions prior Kickstart 2.0 use 1500 bytes at  
 the bottom of the stack frame for their own purpose and note  
 that the stacksize is only checked \*one\* time per second by  
 this command.

A = Semaphores

Shows information about public semaphores.  
 Displays the semaphores base address, current owner, queuecount, ↵  
 nesting count  
 and semaphore name.

Example: Entering TPM would display Tasks, Ports and Memory. The display ↵  
 would  
 be updated after a few seconds (5 by default, may be changed with ↵  
 the  
 'time' command)

## 1.9 Xoper Documentation - Viewing other system lists

- Other system lists

-----

Windows

Here you get a list of all existing windows. For every window will be  
 displayed its address, its ownertask, its location relative to its  
 screen, its size and finally the windowtitle.

Screens

This lists all existing screens. The information displayed will contain  
 for every screen the screen address, the screen size, its depth (how  
 many bitplanes) and the screen title. If Kickstart 2.0 or higher is  
 available the next line shows the screens modeid and if possible also  
 the mode name. If a mode name couldn't be retrieved '???' will be  
 displayed.

PubScreens

Only useful with Kickstart 2.0 or higher. Shows for all pubscreen nodes the node address, the screen name, the actual state (public or private) ←  
,  
the use count (how many visitors), the attached signal and the ←  
ownertask.

#### WindowFonts

This retrieves information which font is used in which window. You will see the window address, the ownertask of a window, the window location on its screen and the windowtitle. The next line will show the node address of the window font, the use count of this font, its X and Y size, its type (rom or diskfont, fixed or proportional), the lo and hi character and finally the font name.

#### Fonts

This command displays a list of all currently loaded fonts (its not a ←  
list  
of all \*available\* fonts). The display contains (as always) the node address, the font use count, its X and Y dimension, its type, the lo ←  
and  
hi character, the font name.

#### Capture

Displays the values for some entries in the ExecBase structure.

-> Cold capture, Cool Capture, Warm Capture and KickMemPtr

These entries can be used to install recoverable programs that survive resets. Using Cold or Cool capture is somewhat a 'dirty' method (in ←  
ancient  
times often used by viri). As far as I know Warm Capture has never and can never be used. The system conform way of installing programs that survive a reset is the usage of KickMemPtr. The display for those ←  
entries  
will contain the start and end location for an entry and its size.

#### TimerIO

Displays pending timer requests. It shows the address of the IORequest structure, the unit number (MICROHZ or VBLANK), the time to complete ←  
and  
the task submitting the request.  
Now fixed to work with Kickstart 2.0 and higher (not totally accurate ←  
though).  
Its somewhat "magic".

#### DiskChange

Shows all installed diskchange interrupts. It displays the node, data ↵  
 and  
 code field of the interrupt, the device it is attached to (df0:-df3:) ↵  
 and  
 the task that added the interrupt (if available). The main purpose of ↵  
 this  
 command was to check for a virus, as the diskchange interrupt is ↵  
 wonderful  
 place to install them.  
 To retrieve this information in a legal way a diskchange interrupt ↵  
 should  
 be installed. Unfortunately the trackdisk.device prior Kickstart 2.0 ↵  
 had  
 a bug that prevented installed interrupts from being removed. Therefore  
 this function used some internal knowledge of the trackdisk.device. ↵  
 Thats  
 the reason why its not working with OS2.0 anymore and has been disabled ↵  
 .  
 I was to lazy to correct this for OS2.0, sorry.

#### InputHandler

Displays the node, the priority and name (if any) of all input handlers  
 currently installed.  
 This was the usual way of implementing hotkeys or intercepting the ↵  
 input  
 stream prior Kickstart 2.0. Xopers hotkey facility itself was based on  
 an inputhandler. Since OS2.0 there exists a commodity.library, that  
 provides functions to deal with input events and to easily add a hotkey  
 to a program. Its much more flexible than the old method.

#### Devices

Displays the name, heads, sectors, tracks, buffers (if appropriate),  
 the state (loaded or not) and the handler-process of every dos-device  
 Note: DOS-Devices are totally different to exec devices!

#### Files

List the lock, access type, size and the name of all open files.  
 CAUTION! This may not work for all devices, but it works for C= ↵  
 Handlers  
 upto 3.1 ...

#### Locks

List any lock  
 BUG: Trying to lock a Volume "RAM Disk" crashes the machine sometimes. ↵  
 If  
 a vovolume "RAM Disk" is found it will be replaced by the ↵  
 devicename  
 "RAM:". Make sure you don't have a disk labeled "RAM Disk" or you ↵  
 will

never see its locks :-)  
 (The problem affected only V33 of the operating system)  
 CAUTION! Here applies the same as with 'Files'. It works for all C= ↔  
 Handlers  
 but others may fail (eg AmiCDROM) The problem is not a bug in ↔  
 the  
 handler but of an illegal assumption Xoper makes about a lock!

#### CurrentDir

List current directory settings of all processes

#### Low-Memory Handler

Displays the node, the priority and name (if any) of all lowmemory ↔  
 handlers  
 currently installed.  
 Only available with v39 or up.

#### Frag

Counts free memory hunks by size. Displays the size in hex and decimal,  
 number of hunks and the largest available hunk.

## 1.10 Xoper Documentation - Commands with parameter

### - Commands with parameter

-----

These commands may be entered in upper or lower case. Parameters enclosed  
 in '<>' must be, enclosed '[' may be specified. Names are usually entered  
 as ascii strings, it can however happen that two or more nodes of the ↔  
 same  
 name exist. On task you may specify the dos-processnumber to sort them out ↔  
 .  
 If everything fails, you can enter the node-address with a leading '\$'. ↔  
 This  
 address will be checked first before the command is being executed. If ↔  
 the  
 check fails you'll get an error message or a warning or a prompt, ↔  
 depending  
 on what went wrong. Names are always the last parameter to enter. This ↔  
 may  
 seem strange, but this is the simplest way to get rid of embedded blanks.

#### Time <seconds>

Set time between updates. Minimum is 0.1 seconds, maximum 255.9, ↔  
 default

is 5 seconds. "Time 0" stops any automatic update and waits for a keypress. Values < 0.5 are not recommended.

Example: Time 1.5

MyPri <priority>

Shortcut for "TaskPri Xoper <priority>"

Example: myPri 2

TaskPri <priority> [processnumber] <taskname>

Change the priority of a task. Values may range from -128 to 127, better use values between -5 and 5

Example: TaskPri 1 Shell Process

Break [processnumber] <taskname>

Set break signals. Useful for tasks running in background or from Workbench.

Example: Break 3 TolleUhr

Freeze [processnumber] <taskname>

Halt a Task. The task should be READY or WAITING. Frozen tasks are queued in a new list called FROZEN (this is a private list of Xoper itself!). When you leave Xoper, halted Task will be released automatically.

Example: Freeze Killer Graphics Task

Warm [processnum] <taskname>

Restart a halted Task. Task must be FROZEN.

Example: Warm Killer Graphics Task

SnoopMem [processnumber] <taskname>

Track memory allocation/deallocation of a task. Press break (CTRL-C) to stop. List includes: action (alloc/free), memory requirements (CHIP/FAST/PUBLIC/ etc.), memory size, memory location (start, end) and the address from where AllocMem() was called.



TraceOpen/TraceLock

Monitors dos calls to Open() and Lock(). Press break to stop.

Zerotimer [processnumber] <taskname>

Reset the used time counter on the cpu usage display. This is useful if benchmarking a cli command.

Hide <taskname>

The task-list tends to be longer than the window size. You may inhibit the output of some tasks you are not interested in using this command.

Example: Hide trackdisk.device

Pri <priority> <nodename>

Change the priority of any other node. If the specified node has been found, the entire list the node belongs to will be resorted. This command does not work for tasks.

Example: Pri 50 chip memory (try to allocate memory in CHIP first)

Info <librarynode | devicenode>

Show additional information stored in the lib\_IdString field. This can be useful for libraries, devices or resources.  
NOTE: Some programs dont follow the rules! That can cause an Enforcer hit.

Example: Info arp.library

RemResident <resident module name>

Kicks a resident module out of the ResModules-List. It does not free the module itself, but only makes sure it won't be reactivated during the next reset. Removing a ROM-based module does not have any effect.

Clear [longword]

Fill unused memory chunks with pattern, default is 0. Handy for debuggers.

---

Example: Clear \$66726565

Hunks [processnumber] <processname>

Show location, BCPL-Pointers and length of memory blocks the process uses. ↔

Note: If the process has only one hunk with length zero the process has ↔

usually been created by the dos-function 'CreateNewProc()'

Example: Hunks RAM

Openlib <libraryname>

Open a library. This is useful if you don't want a specified library being 'flushed' out. ↔

Example: Openlib arp.library

Myfont [size] <fontname> | default

This command changes the font for Xopers window. Since version 2.4 Xoper is no longer restricted to topaz/8. Every fixed width font any size can be used. For fontname the suffix '.font' can be omitted. This will be added automatically. This command can also be used to reenable the system default font for Xopers window by specifying "default" as fontname. ↔

Examples: myfont 8 macintosh  
or  
myfont default

SetFont [size] <fontname> <>window>

Change the default font of a window. To avoid confusion, you should use a font with the same font size as the original font, as many programs rely on the point size. ↔

Example: Windows

Press <esc>, move the cursor to the Xoper window line and type  
SetFont diamond.font  
(now you know what I mean by 'relying on a font size' :-)) ↔

Lockdrive <drivename:>

---

Prevent DOS, Workbench and Disk-Validator from cluttering on the drive. This command isn't very useful, but I needed it myself. Please note that the drivename is case sensitive and has to end with a ':'.

Freedrive <drivename:>

Re-enable a drive.

Window <leftedge> [toptedge [width [height]]]

Works only in script files. Defines the window to be opened.

Example: Window 0 0 550 190

IconPos <leftedge> [toptedge [width [height]]]

Defines the initial position of Xoper's icon. Used in the startup script.

Only useful prior Kickstart 2.0.

OutputLines <number of lines>

Set the maximum number of lines the output buffer may hold. If the buffer overflows, a line from the top of the buffer will be deleted for each new line.

The default value is 500, using a maximum of  $500 * 104 = 52000$  bytes.

HistoryLines <number of lines>

Set the maximum number of input lines the history buffer should hold. Default is 10 lines.

MinimumChars <number of characters>

Set the minimum number of characters an inputline should have to be added to the history buffer. Default is 2 characters.

SaveOutput <filename>

Write the contents of the output buffer to a file. If the file already exists, the output will be appended.

PopKey <description>

---

Change the hotkey description for our commodity. With the hotkey you can popup Xoper if it is in sleep mode or simply pop it's window (including screen) to front. See for instance 'Toolmanger.doc' for a complete key description (sorry!) The actual hotkey is always displayed in the window title.  
 The default hotkey is 'lcommand - rcommand - X' (means press left amiga right amiga and x at the same time).

Repeat <Command string>

Repeats the command string at the current refresh rate (see 'Time'). However, commands not producing any output won't be repeated, but only executed once. Press <enter> to stop.

```
Example: Time 1
         Repeat TimerIO
```

SetFKey <key number> <string>

Assign a string to a funktion key. 'Key number' is a value between 1-20, 10-20 denotes shifted keys. Use '^' to simulate a <return> and '\_' for space (the parser strips leading/trailing blanks).

```
Example: SetFKey 1 Hunks^
         enter t <return>, press <escape>, move the cursor to a
         process,
         press F1
```

Alias <AliasName> <CommandName>

Defines a new name to be used along with the original command name. The new name should not contain any blanks. To delete an existing alias use the <AliasName> without a commandname.

```
Example: Alias ih InputHandler
```

## 1.11 Xoper Documentation - Commands without parameter

- Commands without parameter

Alert

Show last Guru Xoper caught.

### Lastalert

Show last Guru Meditation code or rubbish. (information obtained by exec). Doesn't work when Enforcer is running, as it needs to peek ←  
memory  
location \$100.

### ClrCool,ClrCold,ClrWarm

Clear one of those pointers.

### TrapGuru

Activates a trap handler similar to GOMF. It only works with a 68000 processor, as it relies on a specified stack frame (at least I think so, couldn't check it out). If an exception occurs (i.e. GURU) Xoper will stop (or popup, if running in background) and display some information about what happened (the taskname causing the error, its program ←  
counter,  
the alert number etc.) and you'll be asked if you want to (K)ill the ←  
task  
or (I)gnore the exception. Choosing (i)gnore will do nothing at all if ←  
the  
erroneous program was a process (as it will stop itself displaying a 'Task held...' requester), but force a task to execute a 'Wait(0L)' (i. ←  
e.  
wait forever) as tasks do directly display an alert box.

### Flush

Clean up memory, flush unused libraries, devices and fonts.

### ShowHistory

Show the history buffer. (quite useless, I know)

### KillHistory

Delete all lines from the history buffer. (still useless)

### ColdReboot

destroys first execbase to force a "coldreboot" and then executes a ←  
normal  
reboot

### Reboot

Reboot the machine by either the "official reset code" or by Execs ←  
ColdReboot ()

---

[Q]uit or Hold

Exit Xoper but stay in background. When Xoper pops up window settings and the selected display are restored.

NOTE: When Xopers window is closed with the WINDOWCLOSE-Gadget, Xoper doesn't exit - it goes to sleep. This behavior is \*needed\* for a commodity, because it has to \*hide\* its window only.

Exit

Clean up and quit.

## 1.12 Xoper Documentation - Toggles and Options

- Toggles and Options

-----

All options can be entered with either on or off. If a option is entered alone it acts as toggle.

(Exceptions are usescreen/usewindow, those are the toggles itself)

Sort

The tasks listing is sorted to avoid 'jumping' of the display. Sort toggles this feature on/off. (Stupid command, but was easy to implement).

CLICmd

Toggles between showing the loaded command and the taskname of CLI processes in the tasks listing.

TaskInfo

Toggles additional process information (unitnumber, stdio, devicename) on and off.

Taskports

Disable / enable a listing of taskports if ports are displayed.

Hidden

---

Turn those hidden Tasks back on. It is actually a toggle.

#### Usage

Toggle CPUSE field on the task display between usage relative to all possible dispatches and usage relative to actually dispatched tasks. Ahem...not very clear I think. Well, let me try again...  
If you add all CPUSE fields together you get 100 % (more or less 1%). ←  
After  
entering "Usage" adding the fields together will give you the same ←  
value as  
shown in the 'CPU Activity field'. (I HATE having to write docs)

#### Header

Toggle the (rather long) header on the task display on/off.

#### UseScreen

Opens Xopers window on a screen. The new screen will take its data ( ←  
width,  
colors, viewmodes, etc.) from the Workbench screen prior to Kickstart ←  
2.0  
and will use tags with kick 2.0. Xoper opens a borderless backdrop ←  
window on  
the new screen. With V37+ of the operating system the screen will be a ←  
public  
screen, so other programs may open their windows there. Actually, thats ←  
a bad  
idea because Xoper uses only a two colour screen, so other programs ←  
window  
may look a bit strange ...

#### UseWindow

Opens Xoper on a window. The window will appear on the default public ←  
screen  
(usually the Workbech screen, but this can be changed eg. with " ←  
ScreenManager"  
by Bernhard Möllemann)

#### UseTopaz

Sets Xopers window font to topaz/8 or to the with 'myfont' selected one ←  
.  
This command has been implemented to quickly flip to topaz/8 because ←  
its  
fast for the window display.

#### PropGad

---

Turns the scrollbar on or off (as you like) The scrollbar with is always adapted to the right border size.

#### Iconify

Turns the iconify on or off. A small window or appicon will appear if iconify is on. The iconify window is always the fallback if the installation of the appicon fails. The reason for this is in most cases that the workbench has not been started yet (sigh!)

#### BackDropIcon

Puts the Xoper icon behind all other windows, instead of creating it on top of them.

#### SmartPatch

Xoper has to patch some system functions. If Xoper is forced to quit it checks that no other program patched the same functions. In this case we have to wait until the other program(s) end for safe restoring the patched library vectors. But if you use 'SaferPatches' or 'SetMan' you can quit though the vectors are patched again, because those programs keep track of the right order functions have been changed. This works only if library vectors are changed via Execs SetFunction(). Do NOT alter library vector by yourself !!!.

Xoper knows 'SetMan' internally and switches SmartPatch off regardless what is entered.

#### CxHandler

Prior Kickstart 2.0 the hotkey facility was realized with a lowlevel inpuhandler. Since Kickstart 2.0 there exist a much more flexible way to cope with hotkeys. The commodities.library provides an easy method to implement a hotkey facility where the hotkey itself can easily be changed. Changing the key combination for the inpuhandler is rather difficult (its hard-coded ;-). But the inpuhandler has one advantage: it gets all input events \*before\* the handler of the commodities.library in the input stream.

This command enables you to switch between the lowlevel inpuhandler and the commodity hotkey.



With Kickstart 2.0 and above the commodity hotkey facility is on by default. The command has no effect with Kickstarts prior 2.0!

## 1.13 Xoper Documentation - Dangerous Commands

- Dangerous commands (for experienced users only!)

-----

!!!!!! WARNING: The next few commands are dangerous and 'dirty' !!!!!  
 !!!!!!!!!!!!!!! don't use them if not strictly necessary !!!!!!!!!!!!!!!

Kill [processnumber] <taskname> (cancel is a synonym or vice versa ...)

Kill a task or a process. If the task has been called from CLI, the Task  
 itself and the CLI will be killed. Hunks, Windows, Screens and the  
 terminal-window will be freed. Simple tasks are just RemTask()'ed. If it  
 is  
 not a CLI Task you'll be asked if it is a Workbench task, if the answer  
 is  
 'Yes' unloading will be done by the Workbench. If not, you will be  
 prompted  
 if Xoper should unload the code. Enter 'No' if you don't know how the  
 task  
 has been started. A good example for tasks that should NEVER be  
 unloaded  
 are programs started by ARP'S ASyncRun (or ARun).  
 Unloading of workbench tasks is no longer possible because the  
 Workbench  
 port is since OS2.0 no longer a public port!

Closetlib <libraryname>

This is exactly the same as CloseLibrary().

Closewindow <title>

Closes a Window. Please, use it only if the corresponding Task has been  
 'Cancel'ed. Use the Window-Structure address if the window has no name.

Closescreen <title>

same as above, but for screens. If a screen will be closed first all  
 its windows will be removed.

Unlock <lock>

Unlock a file. \*\*\* VERY DIRTY \*\*\* (not the way how the lock will be  
 removed  
 but the way Xoper gets the lock)

CD [processnumber] <processname>

Change the current directory of a process. You are prompted if the old directory lock should be unlocked.

RemNode <node address>

remove a node from a list.

RemPort <port address>

remove a port from exec's port list.

RemIntServer <interrupt address>

Remove a interrupt server.

Signal <mask> [processnumber] <taskname>

Set any task-signal. Mask is a hexadecimal value with or w/o leading '\$ ←  
'.

See task's SIGWAIT field for sensible values. Tasks normally do not ←  
wait

for signals only, but for messages, that's why this command may not ←  
have

the desired effect, but it is quite useful for tasks hanging around and  
waiting for events that may never happen. Warning: Using Signal without  
any knowledge about what you are going to signal may cause a system- ←  
crash!

Example: Signal 10000000 PopCLI III

## 1.14 Xoper Documentation - Bugs and Limitations

Bugs and Limitations

\*\*\*\*\*

There are no severe bugs known at the moment, however Xoper has some ←  
limitations and  
problems.

Enforcer hits may happen due to accesses to the low memory area (\$100.W, ←  
\$180.W) but

these are not dangerous (read accesses). Other Enforcer hits may be ←  
caused by examing

system structures that are not initialized properly (eg. the "keymap. ←  
resource" with

OS3.x for lib\_IdString, but may be it can be nethertheless Xopers fault: ←  
if resources

are no "real" libraries).

It has been reported that with Kickstart 3.1 (v40) the system freezes ↵  
when attempting ↵  
to mount PC0: if Xoper is already running :( I tried to reproduce that ↵  
behavior on my ↵  
system, but it didn't happen. My program versions which worked:  
- mount 40.3 (27.5.93)  
- mfm.device 40.9 (21.5.93)  
- CrossDOSFileSystem 40.19 (9.6.93)  
Please note, that I fixed bugs with mfm.device (trashed d3 with ↵  
OpenDevice()) and ↵  
mount (didn't recognize tooltypes), but that shouldn't be the solution.

Many internal buffers have a fixed length:  
- input buffer can only hold a maximum of 120 characters  
- task buffer can only handle a maximum of 125 task (should be enough ↵  
anyway)

The trapguru function works only for 68000 processors. It may sometimes ↵  
work also ↵  
for higher cpus, but better don't rely on this. Every 680x0 processor has ↵  
a special ↵  
stackframe format for exceptions and I do not know much about this.

Killing a task is a very dirty and dangerous thing on the amiga. So using ↵  
this ↵  
command may lead to a system crash, so beware! Also, prior Kickstart 2.0 ↵  
the ↵  
workbench replyport was a public port. This is no longer true for OS3.x ↵  
or even ↵  
OS2.0! That makes it impossible to simulate a workbench exit :-)

The diskchange command works only with Kickstart 1.2/1.3. Please refer to ↵  
the ↵  
description of that command for the reasons.

And now the very dirty part:

All dos related functions make a special assumptions about one value in a ↵  
filelock ↵  
structure (nethertheless it works upto 3.1 ;-()). Those functions are ↵  
likely to produce ↵  
strange results, eg. if AmiCDROM is used as handler for a cdrom-drive ( ↵  
only with an ↵  
inserted medium)  
I left the functions in the program because they were often useful though ↵  
(eg. PasTeX ↵  
MUI-Specialhost did not unlock newly created directories)

Furthermore killing Xoper through cmd=kill and the pc-display make some ↵  
special ↵  
assumptions about the stack layout! This may not work with future ↵  
versions of the ↵  
os or different versions of 68060.libraries! So be \*very careful\*!

## 1.15 Xoper Documentation - Technical Info

### Technical Info

\*\*\*\*\*

Xoper was written entirely in assembler, but that is not a quality sign. ←  
In fact, if you  
look at the source, you will notice, that it doesn't follow the rules. ←  
Parameters are  
not passed in the regular registers and results don't come in "d0". ←  
Common non-scratch  
register are not saved in subroutines or sometimes a subroutine will be ←  
entered on a  
different location than the main entry. All these facts make it very hard ←  
to change  
Xoper due to unpredictable side effects. The source is not commented very ←  
well either.

First A68k v2.71 was used to assemble Xoper, later then SNMA (you need at ←  
least v1.95).  
Other assemblers may have problems with the source code (eg. PhxAss does ←  
not like ".")  
in labels and has problems with some expressions).

Xoper uses a combined data/bbs segment. This avoids lots of relocations ←  
because even  
bss entries can be accessed over the base register. Many c-compilers use ←  
this to keep  
its programs short (GCC,SAS/C,DICE,Aztec). To create such a "short" ←  
executable you  
need a linker that suppresses all zeros at the end of a hunk. I recommend ←  
PhxLnk  
because its free and fast. You need at least V4 of that linker!

Xoper v2.4 and up were developed on an A4000/030 with Kickstart 3.0. It ←  
was also  
tested with a softkicked 1.2 (V33).

Xoper is a system monitor and offers some information about the cpu usage ←  
of tasks.  
To get those information Xoper patches two functions in the Exec library: ←  
Switch()  
and AddTask(). The latter is well documented and in no way a secret. ←  
However, the  
Switch() entry in the Exec library seems to be "secret". This functions ←  
has never  
been documented but until v37 of the os the exec fd-file contained the ←  
name of this  
function. The only things Xoper "knows" about Switch() is its name, ←  
offset within  
the Exec library and purpose. Whether this function has arguments or not ←  
does in no  
way affect Xopers work. All that Xopers is doing in its patch function, ←  
is to add  
the current task (SysBase->ThisTask) to an internal buffer and to update ←  
an internal

timer value for that task. After that the original function will be ↵  
 executed with  
 the original registers settings. There is no magic how Xoper gets the cpu ↵  
 usage for  
 each task! (at least almost ;-)

## 1.16 Xoper Documentation - History

### History

\*\*\*\*\*

-----  
 versions developed by Gunther Nikl  
 -----

- 2.8 - startup script size was limited to 400 bytes due to a wrong buffer offset
- screens now show the 'real' screen depth for CyberGraphX (only 3.x and up)
- PC display for FPU activity was messed up :-/
- grabtimerio didn't handle PA\_SOFTINT type ports - always "assumed" ↵  
 PA\_SIGNAL  
 (shows interrupt or portname for such timer requests)
- new shortcuts for cursor movement (ctrl-a: line start && ctrl-e: line end)
- used wrong interrupt type for softints
  
- 2.7 - MemList for detaching had a wrong size  
 (lost 8 bytes during exit, thanks to MungWall for reporting the bug ;)
- jumptables now word based
- output from snoopmem was garbage if an allocation failed
- added idle and busy state recognition for mc68882
- gettaskname2 now validates its input
- cursor drawn with RectFill() now thus finally visible with gfx-cards  
 (thanks to Christian Wasner for the fix!)
- fixed kill and pc display when running with a m68060  
 (nethertheless this is a hack!)
- fixed a bug in cd() - wrong jump destination :-/
- priority of global port now defaults to -1
- replaced \*all\* ENABLE/DISABLE macros with the corresponding Exec call  
 (thus better DRACO compatibility, I hope ;)
- pri-command for non-tasks/non-processes was broken since...  
 (would crash the machine for sure)
- library, device, resource, semaphore and port display do show node  
 priority now
  
- 2.6 - failed to start from shell if pr\_CurrentDir was the ZERO lock :(
- unnecessary setupscreen() for received pubsig removed
- better error handling in gettooltypes() - no more enforcer hits  
 if no icon.library available (was it ever possible for a wb start?)
- uses Input() for reading instead of Output()
- does recognize the 68060 now + better fpu check for >= 68040
- reads startup-script with a single Read() (no more one byte reads  
 causing long startup time if the system is very busy)
- cursor should be visible now on graphic-cards (tested on a Retina Z3)
- displaying dos-devices could cause enforcer hits (dol\_Startup)
- removed a silly BCPL check for locks (can it ever be an APTR !?)
- safety check when scanning for locks, not waterproof but better

- than nothing
  - does now copy the commandline before modifying it (guru book)
  - startup code partially rewritten
  - new detach technique (only CLI, no 'seglst' splitting but will use segment list from cli\_Module -> hi Manx ;-)
  - new commandline option 'keepio' preventing detaching from CLI
  - does now make sanity checks during initialization...
  - corrected CreateTask() for V37+ of the OS (return code of AddTask() is valid now)
  - does free all resources now (including signals - wasn't a problem before since Xoper always created an own process and signals are local for a task, so...)
  - fixed a bug in the FPU code (could show wrong PC sometimes)
  - better seglst search when displaying hunks
  - found another bug in dos-devices: 'dol\_Task' can be a normal message port (FIFO: device, don't know if that's legal)
- 2.5
- cpuse dropped down to 0.0% for all tasks because of incorrect overflow handling in the switch function (Vogt, Bill Best)
  - window and iconpos examined only the first argument caused by not handling trailing blanks (Thomas Schwartz)
  - didn't recognize all floppy drives when one was missing eg DF0: -> DF2:
  - Enforcer hit in iconify() caused by using a null pointer instead of a pointer to a string with len zero - I should buy includes&autodocs (Jörg-Cyril Höhle)
  - crash due to killing Xoper twice or killing Xoper when it was waiting to restore the patched library vectors
  - exec list of libraries, devices and resources now show the correct values for opencount, version && revision (word instead lower byte) (Gary Duncan)
  - zip gadget behavior for kick2.0+ corrected, switches now between two different sizes (Jörg-Cyril Höhle)
  - checks first if a resource to be freed/deallocated is owned by Xoper eg. for windows, screens, ports and interrupt-servers. a problem is still how to validate a remnode() ?
  - system crash when 'cxhandler' was specified in the startup-script due to trying to set the windowtitle for the nonexisting! window (Stefan Becker)
  - new command 'myfont' to change Xopers window font
  - font handling improved. checks that the font returned by OpenFont() has the requested size, otherwise a OpenDiskFont() is performed. When a diskfont couldn't be opened the result of OpenFont() will be used
  - setprop now scans message list correctly, looked one to far - oops (Jörg Cyril Höhle)
  - no more (partial) overwriting of the delimiter line if window size was unsuitable (really fixed?)
  - when not running on an own custom screen adapts progadget size to the window border size (suggested by Jörg-Cyril Höhle)
  - largest value that can be converted to decimal is now 10^9-1, should be enough for virtual memory :-)
  - timerio finally works with kick2.0+, converts \_eclockval\_ to \_timeval\_! (Jörg-Cyril Höhle)
  - division function uses a 68020 instruction (if appropriate)
  - startup-code revised (better lock handling)
  - 'stack' command rewritten (according to the book),
  - stack now displays "----" if current stackpointer is not within the
-

- tasks stack bounds (suggested by Jörg-Cyril Höhle)
- crash if 'exit' was specified in the startup-script (tried to remove the noninstalled! inpuhandler)
- new commandline option 'noscript'
- EOL is now CON: default ctrl-k (suggested by Jörg-Cyril Höhle)
- fatal taskend if GUI-hiding was requested with pubscreen still used
- new command 'lowmemhandler'
- if iconify was off a hide-message erroneously caused a 'wakeup'

- 2.4
- major code cleanup and lots of bugs removed
  - non-proportional fonts different than 8x8 pixels are now handled correctly
  - new command 'usetopaz' to force Xoper to use the "default" topaz/8
  - takes care of the screens barheight and window borders width
  - commandline completion now works at every! position of the inputline and cycles instantly
  - when running under Kickstart 2.0+ Xoper clones the default public screen (size, modeid,...)
  - Xopers own screen is a public screen called 'Xoper' (2.0+)
  - uses commodity and appicon feature of Kickstart 2.0+
  - searches startupscript at various locations (currentdir, env:, s:)
  - older commands (cancel, alert, remnode, remintserver) displayed in the help page
  - input-handler (checking for Amiga-Amiga-X) now installed permanently
  - new command 'pubscreens'
  - screen display shows modeid (only when running under 2.0 or higher)
  - removed all selfmodifying code
  - system conform and safe patching of library vectors
  - IconifyOff and PropGadOff replaced with the options 'Iconify' and 'PropGad' that turn the corresponding feature on or off
  - startup code completely rewritten

-----  
 versions developed by Werner Günther  
 -----

- 2.3
- general fixes for WB2.0x, FPU and 680x0 processors
  - 'task usage' section completely redesigned, including a new display showing the total amount of cpu-time by task
  - added new fields to the task, fonts, screen and cli display
  - added a scrollbar (why not use the keyboard :)
  - open files and filelocks can now be logged
  - added a 'frags' like display
  - 'saveoutput' appends its output to a file if it exists
  - toggling commands may be followed by 'on' or 'off' for clearer startup-scripts
  - 68881 code was done by Lothar English
- 2.2
- 'KillXoper' integrated into Xoper's main program
  - loaded CLI commands are now always displayed, not only in the tasklist
- 2.1
- KS1.3 dependancy removed
  - fixed a crash with 'usescreen' in startup script if Xoper was started with the '-b' flag
  - s (stack) command wasn't robust enough
  - removed some strangness in the 'kill' routine
-

- iconizing routine couldn't distinguish between multiple drags and doubleclicks
  - 'time' now accepts values < 1
  - 'windows' shows owner task (if available)
  - task display shows name of the loaded command (enclosed in[]) instead of the name, if the task is a CLI.  
'clcmd' toggles this feature on/off
  - commandline completion using <tab>
  - added a new command (setfkey)
  - a new program 'KillXoper' has been added to remove Xoper from memory in case it loops or freezes (I hope it won't be needed)
- 2.0
- user interface (what user interface ?) rewritten from scratch
  - added a small iconify routine
  - added again a few new commands to customize the whole thing a little bit  
(minimumchars, historylines, showhistory, killhistory, outputlines, iconifyoff, backdropicon, usescreen, usewindow)
  - other new commands  
(timerio, remresident, repeat, trapguru, setfont, diskchange, alias, saveoutput)
  - addresses now shown as 32-bit values for 68020 compatibility
  - 'more' command was obsolete and has been removed
  - 'interrupt list' has two new fields
  - 'time' w/o parameters shows current setting
  - 'display commands' separated by blanks will display the list one by one, instead of displaying them all at once
- 1.3b
- added 'C' information on CLI-tasks
  - 'time 0' stops any update
  - system requesters are now handled correctly (affects 'kill' and 'closewindow')
- 1.3
- added new commands (stack, sort, hide, hidden, header, window, inputhandler)
  - added support for a startup-script
  - added I/O interrupts/second
  - added 'kill' as an alias for 'cancel'
  
  - fixed bug in the port-display that caused a GURU if more than 32 ports did exist
  - the cli Xoper has been started did act like having a priority of 127
  - unlock didn't unlock sometimes
  - interrupt/priority field did contain rubbish
  - currentdir didn't examine all processes
  - some more bugs (hopefully) removed
- 1.2
- added new commands (snoop, capture, clrcold, clrcool, clrwarm)
  - added cpu usage by task
  - cancel command rewritten
  - some minor bugs removed
-



## 1.17 Xoper Documentation - Acknowledgments

Acknowledgments

\*\*\*\*\*

Thanks to all who submitted bugreports ;-( or suggestions that kept me ←  
working  
on Xoper. Without their help there would be no new version.

Werner Günther - for writing the original program :-)

Jörg-Cyril Höhle - for bugreports, useful suggestions and demanding ' ←  
fixes' :-)

Stefan Becker - for bugreports and his excellent 'ToolManager'

Ralph Babel - for his great "Amiga Guru Book"

Samu Nuojua - for creating SNMA (a very good assembler)

Christian Wasner - for his cursor problem fix with gfx-cards

Vogt (france), Thomas Schwarz, Bill Best, Oliver Jeannet,  
Gary Duncan - for bugreports

## 1.18 Xoper Documentation - Disclaimer

Disclaimer

\*\*\*\*\*

Standard disclaimer:

THERE IS NO WARRANTY FOR THIS PROGRAM TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHERE OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDER AND/OR OTHER PARTIES PROVIDE THE PROGRAM "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

## 1.19 Xoper Documentation - Copyright

Copyright

\*\*\*\*\*

Xoper may be freely distributed for non-commercial purposes, as long as ←  
all the  
files in the original archive are present and have not been modified in ←  
any way.

It is illegal to distribute this program on disks which cost more than US ←  
\$5 per  
floppy disk, or more than US \$20 per CD.

## 1.20 Xoper Documentation - Author

Author

\*\*\*\*\*

Since v2.4 Xoper is maintained and enhanced by Gunther Nikl. If you find ←  
any bugs,  
have some suggestions to enhance or improve the program, please contact ←  
me:

email: gnikl@informatik.uni-rostock.de

or

smail: Gunther Nikl  
Ziegendorfer Chaussee 96  
Parchim  
19370  
GERMANY

The original program was written and developed upto v2.3 by Werner Günther ←  
.

email: x41@sun0.urz.uni-heidelberg.de

Thanks to him that he made the program (some people disagree - I know :)

PLEASE NOTE: He is no longer involved in the further development of Xoper,  
so please don't contact him - it would be the wrong address!

## 1.21 Xoper Documentation - Task Types

A so called "task" can be either a simple exec-task or ←  
dos-process. A process is  
an extension of an exec task. Only processes are allowed - with some ←  
exceptions -  
to call functions in the dos.library.

To create an exec-task one can use the Exec function AddTask() or the Exec support function CreateTask() (that also uses AddTask()). All programs started from CLI or Workbench are processes. One can create processes manually with the DOS functions CreateProc() or with the 2.0 version CreateNewProc(). These functions cannot be used from simple tasks!

For more information about this topic please consult  
The Amiga Guru Book

## 1.22 Xoper Documentation - Task States

The task state indicates what a task is currently doing. The state can be :

INVALID	- ???
ADDED	- a newly created task
RUNNING	- a task that has the processor (only one possible!)
READY	- a task that lost the processor and requests it again
WAITING	- a task waiting for an event (better: for signal(s))
EXCEPTION	- a task exception (not processor exception!) has happened
REMOVED	- a task that has ended
FROZEN	- a task has been frozen by Xoper meaning it has been removed

either from the ready or waiting queue  
(this in no way a system state!)

Usually you will only see tasks that are in a running (always Xoper!), a ready or a waiting state. If a task is permanent in a ready state, this indicates that the task is either heavily working or it makes "busy waiting" (very bad programming habit). To lower the system load you can decrease the taskpriority of this task with the 'taskpri' command. That doesn't hurt the task until no other task requests the processor.

To see ADDED or REMOVED is rather unlikely as well as EXCEPTION. Using task exceptions should be avoided due to some severe bugs within exec for handling those exceptions.

## 1.23 Xoper Documentation - Task Names

The taskname will be the name of the loaded command if the task is a CLI ↔  
command.

The loaded command name is then enclosed in [].

Additional information displayed can be:

- stdin and stdout enclosed in ()
- devicename enclosed in {} if the process is a handler
- unit number if the process is a device

## 1.24 Xoper Documentation - CLI Infos

The type field indicates whether the cli is an ↔  
interactive or a batch one (script  
files).

The mode for a CLI can be either foreground or background, meaning if the ↔  
program  
was started by Run or Execute().

For more information about this topic please consult  
The Amiga Guru Book

.

## 1.25 Xoper Documentation - Base Address

This value will be usually the result of a call to OpenLibrary() or ↔  
OpenResource(),  
but this may be wrong for multiple base libraries (means for libraries ↔  
that provide  
every user a fresh data area. Those libraries cannot be SetFunction()ed!)  
To get the base address of a device you have to open that device properly ↔  
by  
a call to OpenDevice() and extract the device pointer from the io\_Device ↔  
entry  
in the IORequest.  
This is a hexadecimal value.

## 1.26 Xoper Documentation - Open Count

The open count shows how many users a resource has. This value indicates ↔  
if the  
resource can removed in a low-memory situation. A non-zero open count ↔  
means that  
a resource is still in use.  
Its displayed as decimal.

## 1.27 Xoper Documentation - Version and Revision

The version of system libraries is usually a hint which version of the operating system is installed, eg. v33 indicates OS1.2, v37 OS2.04, etc. The revision field shows how often the resource has been changed during the development cycle. Programs that require a certain version of the operating system simply submit the at least needed library version to a call of OpenLibrary(). Both values re displayed as decimal.

## 1.28 Xoper Documentation - Flags

The flags indicate the current state of a resource or what shall happen if a certain state will arise, eg. an alert if the library checksum doesn't match the one stored in the library base. The value will be display as binary.

## 1.29 Xoper Documentation - Name

This field will be used if a certain library has to be opened. The name is case-sesitiv, so "Name" is not "name". It is also important that for transient resources its diskname matches excatly the internal name otherwise the system refuses loading those resources.

## 1.30 Xoper Documentation - The Amiga Guru Book

THE AMIGA GURU BOOK  
a reference manual  
by Ralph Babel

available from:

Hirsch & Wolf OHG  
Mittelstraße 33  
D-56564 Neuwied  
Germany  
Voice: +49 (2631) 8399-0  
Fax: +49 (2631) 8399-31

Stefan Ossowskis Schatztruhe  
Gesellschaft für Software mbH  
Veronikastraße 33  
D-45131 Essen  
Germany  
Voice: +49 (201) 788778  
Fax: +49 (201) 798447  
E-Mail: <stefano@tchest.e.eunet.de>

further information:

`ftp://ftp.pfm-mainz.de/pub/amiga/gurubook-info.lha`

---