### Revision and Copyright:

This is the 67th revision of this document and applies to version 1.11v of UUPC/extended. This document was last updated on September 4, 1992 by Katherine E. Williams. Portions of this documentation are Copyright (c) Andrew H. Derbyshire 1989 and Copyright (c) Kendra Electronic Wonderworks 1990-1992. Full copyright information for UUPC/extended appears in the file README.DOC.

#### Introduction:

This file describes how to invoke and use the UUPC/extended MAIL program. It lists the commands available from the question mark (?) prompt in when reading MAIL. See tilde.hlp for tilde (~) escape commands available when sending mail.

#### Command line options

The MAIL program is used for both sending and receiving mail. The options available depend whether you wish to send or receive mail. For sending mail interactively, the syntax is:

```
mail -s "subject" addressees
```

If the -s "subject" is omitted, the user is prompted for a subject. Addressees must be specified, and are in the form listed below. For receiving mail, the syntax is:

mail -f filename
mail -u userid

where filename is the mailbox to be read using the syntax described below for filenames, or userid is the user id whose system mailbox is to be read. The default is to read your own system mailbox.

## Types of operands

In the list of available commands, items refers to one or more items in the mail box. These items can be specified in the following fashion:

Item Number

A single numeric value, the special character dot (.) to specify the current item, or the special character dollar sign (\$) to specify the last item in the mailbox.

Item range

Two Item numbers separated by a hyphen (-).

The items must be in ascending order; for example, 1-\$ is valid, \$-1 is not valid.

List of items A list of item numbers and/or item ranges, separated by spaces. The list need not be in ascending order. An example is: 1-5 8 7 14 - 17.

Asterisk (\*) Subject

Selects all items in the mailbox A slash (/) followed by a subject to search for, optionally followed by a terminating slash. Each Subject: or Resent-Subject: will be searched for the specified string. An example is /UUPC bugs/

User id

A single word (no white space) appearing in the From or Resent-From lines of the mail header. Note that if the command accepts both an item and a userid, you cannot specify the item as a user id.

Note: If the command accepts both an item and file name and you specify a user id for the item, you must explicitly provide the default filename unless the user id includes the characters at sign (@), percent sign (%), or exclamation point (!).

Some commands also allow file names as operands. These may be described in the following fashion:

Simple file An MS-DOS file name with no path name name

Relative path An MS-DOS file name with one or more back slashes (\) which does not begin with a back slash or drive letter.

Absolute path An MS-DOS file name with one or more back name slashes (\) which begins with a back slash or drive letter.

Mailbox A simple file name prefixed by the plus sign (+) character. This will cause the file be referenced as if it is the mailbox for the

> specified user. For example, +postmast refers to the mailbox for user postmast. A simple file name preceded by a tilde and

Relative to slash  $(^{\sim}/)$ . The file is then referenced by your home the prepending the home directory listed in directory your PERSONAL.RC to the simple file name.

A simple file name preceded by a tilde, the Relative to another's home userid, and a slash (~userid/). The file is then referenced by the prepending the home directory. directory listed in the PASSWD file for user "userid" to the simple file name.

When sending mail from the MS-DOS command line or via the mail or forward commands, addressees must be entered. These take the form:

September 4, 1992 UUPC/extended 1.11v Mail Command Reference

userid A simple user id, for delivery on the

local system.

userid@node A user id and node combination, for

delivery to userid on system node.

nickname A user or list defined in the user's

ALIASES.TXT file.

If the flag -c is inserted before a user id, then all following users are delivered as Carbon Copy (Cc:) addressees. If the flag -b is inserted before a user id, then all following users are delivered as blind carbon copies; their addresses do not appear in the mail header. The blind carbon copy flag must follow any all normal addressees and carbon copy addressees.

### Commands available when reading mail:

?

Commands are entered in response to the mail question mark prompt (?); all commands must be separated from their operands, if any, by white space. Most commands can be abbreviated to a single character; the commands which cannot be so abbreviated and their shortest allowable abbreviation are debug (deb), dquit (dq), previous (pre), set (se), and status (st).

The commands supported by UUPC/extended are as follows:

empty line

If the current mail has not been touched, then an empty line acts as a print command; otherwise, it acts as a

next command.

! command as an MS-DOS command.

If command is omitted, runs an inferior command processor (which gives the user a new DOS prompt.)

Prints a summary of commands

available.

+ integer Alias for down command.
- integer Alias for up command.

alias a1 a2 a3 Displays alias information loaded from

user's ALIASES.TXT file for nicknames at a2 a3. If an alias is list of other aliases, the list is recursively exploded and displayed. This command has no default operand; at least one

alias must be specified.

copy items file Copies mail items into file with

headers. Default file is the printer

on device PRN.

UUPC/extended 1.11v Mail Command

debug integer

Sets internal trace level to integer; default is 0 at start up, 1 if command is entered with no operands. This can also be set by the command line flag - x.

delete items

Sets status of items to deleted. Deleted items are ignored when selecting mail by subject or user id, and are purged from the mailbox when the quit command is issued.

dquit items exit

Short for delete followed by quit. Exits mail without updating mailbox; deleted items are left alone. Compare this to the quit command.

forward items addrs

Resends items to addrs. Note that if the askcc option is set, each item forwarded will be prompted for Carbon Copy addressees.

go items

Positions to the last of the items selected.

headers

Displays summary information for all items in the mailbox.

Headers items

mail addrs

Displays summary information for the selected items in the mailbox.

help
mail -s subject addrs

Prints this long help text.
Interactively send mail to addrs with optional subject.

next integer
previous integer

Move down in mailbox by integer items. Default is 1.

previous integer print items

Alias of up command.

Print items from mailbox, using the external pager if defined in the configuration file and ignoring (not printing) a standard list of RFC-822 fields in the mail header such as Received: and Message-Id:. Compare this to the Print, type, and Type commands,

Print items

Print items from mailbox, using internal pager and ignoring (not printing) a standard list of RFC-822 fields in the mail header.

quit

Terminates the reading of mail. All deleted items are purged, and all other items are saved in the original mailbox or in =mbox depending on the setting of the save flag.

reply items

Interactively sends mail to the authors of each of the items requested. Note that each item is replied to separately, specifying "reply 1-10" will send ten pieces of

mail to ten people.

UUPC/extended 1.11v Mail Command

save items file

Saves the specified items complete with mail headers into file, and then deletes the items. Compare this to the copy and write commands.

set Se op PE

the copy and write commands.
Sets various boolean options. These option can also be set in your PERSONAL.RC file. The options are listed below under SET OPTIONS.
Reports miscellaneous program information, including:

status

The version and creation time of the program
The operating system version
The current address and related information

The current file name, size, and date last updated

type items

Print items from mailbox, using external pager if available and displaying RFC-822 fields suppressed by the print command. Compare this to the print, Print, and Type commands, Print items from mailbox, using internal pager and displaying RFC-822 fields suppressed by the print and Print commands.

Type items

Changes status of items to unread. Writes items to file without the RFC-822 headers and then deletes them. The default file is "/mbox. Compare this to the copy and save commands. Alias for the exit command.

undelete
write items file

xit

# Set options

In addition to the commands listed above, a variety of options can be set in the various configuration files; of special note are the boolean options specified via options = keyword in the configuration files, as they can be changed via the set command. Options are enabled by specifying their keyword, and disabled by prefixing the keyword with the characters "no"; the default for all options is disabled.

Valid boolean options which can be set by the user in the UUPC.RC file, their PERSONAL.RC file, or via the options command are as follows:

Option Default operation Operation if set name

askcc The user must enter all After composing, reply addressees when invoking to, or forwarding mail, mail or forward. the user is prompted for Additional addressees carbon copy (Cc:) cannot be added to mail addressees. generated by reply.

autoedit When sending mail, the If the user has defined an editor, when sending user is presented with the line oriented send mail, the editor is full screen editor, the user must use the ~e

mail interface. To use a immediately invoked for the user to enter mail with. The user must exit (edit) command or exit the editor to include line oriented data entry  $\ \ \mbox{mail}$  from the active mailbox. to invoke his editor.

autoincl Do not automatically include the text of mail ude being replied to.

When the reply command is invoked, automatically include the text of the mail being replied to as if the ~m command was issued.

When sending mail, the user's signature file is autosign not appended to outgoing mail automatically. If defined, the user mail defined, the user mail still include the file via the ~g (include autograph) command.

If defined in the user's configuration file, the signature is automatically appended to all outgoing mail.

backup

Do not create a backup of the file being processed before rewriting or deleting it.

Before updating or deleting the current file when exiting mail, rename the existing file to the same file name with the extension defined by the configuration variable BackupExt.

Note: If no extension is defined, a default extension of "BAK" is used.

doskey

Under DOS, interactive input is read from the console using standard DOS services (INT 21H function OAH). DOSKEY, if installed, is ignored. Empty input lines are processed normally.

If installed, the MS-DOS 5.0 DOSKEY program is used to read input from the console; normal DOSKEY functions, including the ability to edit and scroll input, along with macro expansion, is available. Empty lines (which can be generated by DOSKEY macro processing) are ignored at the command prompt unless the expert option is also set.

Note: If DOSKEY is not installed, when the user is first prompted for input the doskey option is reset to nodoskey with a warning message.

dot

When sending mail, interactive input must be interactive input can be terminated by the DOS end terminated by a single of file character (Ctrl-Z).

When sending mail, period (.) in column one.

expert

All informational messages are displayed, and if the doskey option is also set, empty input lines are ignored in response to the command prompt.

Boiler plate messages, such as the initial help prompt, are suppressed, and empty input lines are not ignored when the doskey option is set.

command is not saved in the user's outgoing mailbox.

forward- Mail sent via the forward If the user has defined an outgoing mailbox, then mail sent via the forward command is saved in the same fashion as other outgoing mail.

fromsep

Items in the mailbox must be separated by a line of binary ones (1).

Items in the mailbox can be separated only by UUCP format From lines. The line of binary ones (1) required between items by the default operation of nofromsep is still generated when updating mailboxes.

Note: This option must be set in a system or user configuration file, because it only examined at start up.

pager

help, print and type use the external pager if one the internal pager, and is defined, and Print and Print and Type use the Type use the internal pager.

help, print and type use external pager if one is defined

purqe

Empty mailboxes are left in place when the user exits mail.

Empty mailboxes are deleted when the user exits mail.

save

Mail is left in the user's system mailbox after reading.

If mail is not deleted from the user's system mailbox after reading, it is automatically saved in his ~/mbox file when the user exits mail.

suppress Display the UUPC/extended Suppress the copyright copyright notice at copyrigh program startup.

notice at program startup. This, of course, does not suppress the associated responsibility.

Note: This option must be set in a system or user configuration file, because it only examined at start up.

undelete The environment variable DELDIR is reset to a null string by UUPOLL, causing files deleted by its children (UUCICO, UUPOLL, and UUCLEAN) to not be archived by the OS/2 operating system for later recovery.

The DELDIR environment variable is left alone, causing OS/2 to copy all deleted files to a hidden directory. This causes a performance and free disk space impact by saving files which the user should never have to access, much recover.

Note: This option must be set in a system or user configuration file, because it is only examined at UUPOLL start up.

verbose When invoked from mail, When invoked from mail, RMAIL only displays error rmail displays both error messages.

messages and nominal status messages, including the addresses mail was delivered to.

Note: This option must be set in a system or user configuration file, because it only examined at start up.

The following system oriented options must apply to all users on a system and can only be set in the UUPC.RC file:

Option name	Default operation	Operation if set
bang	RFC-822 headers are generated with a "User name" <user@node> format.</user@node>	RFC-822 headers are generated with UUCP style (User name) node!user format.
collect	The size of mail is not reported by RMAIL.	The RMAIL delivery and spooling messages include the size of the files delivered.
director Y	Mail for "user" is delivered to the file user in the directory specified by the maildir= line in the system configuration file.	Mail for "user" is delivered to the file newmail in the user subdirectory of the directory specified by the maildir= line in the system configuration

file.

escape

Only Ctrl-Break can be used to exit from UUPOLL or UUCICO.

If the Esc (Escape) key is pressed, then the next time UUPOLL or UUCICO polls the type-ahead buffer the program will act as if Cntl-Break was pressed.

Note: Enabling this option effectively disables type-ahead, since all characters except Esc are discarded with an error message.

history No news history is maintained.

A history is maintained of all news articles read and posted.

Note: The history option is currently ignored.

kanji No translation of characters takes place during RMAIL processing. Mail which orginates locally is translated from a 2 byte Kanji code called Shift-JIS (Japanese ideogram) to Kanji in a 7bit subset of ISO2022 which can be transmitted via SMTP. Mail from remote systems which is delivered locally is translated from JIS 7bit back to Shift-JIS.

monocase Job sequence ids are generated in base 62 using numerics and upper using numerics and upper and lower case alphabetics.

Job sequence ids are generated in base 36 case alphabetics.

multitas Processing is optimized for speed over system integrity.

Additional processing is performed to insure system integrity. This additional processing includes creating lock files to prevent concurrent access to system spool directories, writing program logs to temporary files and then appending the file to the permanent log file at program termination, and movng new mail from the user's system mailbox into the user's home directory when MAIL is first run after the new mail's arrival.

multique When queuing mail for other hosts, each addressee is delivered separately.

When queuing mail for other hosts, a single file delivered via the remote UUCP can have multiple addressees.

snews

Incoming news is written to seperate files in directories based on the news group names listed in the ACTIVE file located in the NewsDir directory.

Incoming news is written to a file in the NewsDir directory without examing the ACTIVE file.

symmetri cgrades

When actively polling, UUCICO does not transmit the maximum grade for file transfers allowed by the SYSTEMS file to the remote system at startup.

UUCICO transmits the maximum grade for file transfers allowed by the SYSTEMS file to the remote system at startup.

syslog

No record is made of files transferred.

The file SYSLOG is written in the spool directory with a record for each file transferred to or from the local system.

September 4, 1992 UUPC/extended 1.11v Mail Command Reference