

Requirements for SQL Anywhere

To use Sybase Central with Sybase SQL Anywhere, you need:

- ◆ an Intel-based PC running Windows 95 or Windows NT 3.51 (or later)
- ◆ SQL Anywhere 5.0 (or later)
- ◆ a SQL Anywhere database or a Watcom SQL 3.2/4.0 database, preferably with a user account having [DBA authority](#)

Notes:

- ◆ Sybase Central can also administer Watcom SQL 4.0 databases running on a SQL Anywhere server, and can [upgrade](#) databases (Watcom SQL 3.2 or 4.0, or SQL Anywhere) to the latest SQL Anywhere database format.

[Related Topics](#)

Starting Sybase Central

Under Windows 95 or Windows NT 4.0 (or later):

- ◆ In the **Start** menu, click **Programs > Sybase SQL Anywhere 5.0 > Sybase Central**

Under Windows NT 3.51:

- ◆ In Program Manager, in the **Sybase SQL Anywhere 5.0** group window, double-click the **Sybase Central** icon.

[Related Topics](#)

How to get help

There are several kinds of help available for Sybase Central:

- ◆ [How-to help](#) for accomplishing tasks in Sybase Central (which you are reading now)
- ◆ [Pop-up help](#) (also known as **What's This?** help) for all controls in all dialogs
- ◆ Tooltips and status bar messages that appear when you point at a toolbar button or menu item
- ◆ [Step-by-step tutorials](#) on using Sybase Central, in the **SQL Anywhere User's Guide**.
- ◆ [Sybase customer support](#)

Notes:

- ◆ [This help file](#) describes how to use Sybase Central to manage Sybase SQL Anywhere. For complete help on SQL Anywhere, see the [SQL Anywhere User's Guide](#).

[Related Topics](#)

Getting how-to help for a task

To get how-to help for Sybase Central, do one of the following:

- ◆ In Sybase Central's main window, click **Help Topics** in the **Help** menu, or press **F1**.
- ◆ In Program Manager (or the **Start** menu), open the **Sybase Central for SQL Anywhere** help icon.

This opens the Topics dialog for Sybase Central on-line help. From this dialog, you can:

- ◆ browse the **Topics** in the table of contents
- ◆ look through the **Index**
- ◆ **Find** specific text in the on-line help

[Related Topics](#)

Connecting to a database

For most operations in Sybase Central, you must be connected to the database.

How you connect to a database depends on whether it is already running (and if it is, whether the server that it's running on is visible in Sybase Central).

Which of the following applies to you?

{button ,JI('>howto','IDH_scsa_database_connect_visible_server')} The database is already running on a server that I can see in Sybase Central

{button ,JI('>howto','IDH_scsa_database_connect_dialog')} The database isn't running, or is running on a server that I can't see

Once you connect to a database, it is shown in the left panel of the [main window](#), under the [server](#) that it is running on. The [user](#) that you connected with is shown in brackets after the [database name](#).

You can then administer the database by [navigating](#) and [selecting](#) objects that belong to the database.

You can make subsequent connections to a given database easier and faster by using a [connection profile](#).

Notes:

- ◆ If you connect to a database using an account that does not have [DBA authority](#), you can see all objects, but you can only alter objects that you have permissions on.
- ◆ Sybase Central does **not** show all servers running on your machine or on the network. It only shows those that are running the databases that you are connected to in Sybase Central.
- ◆ You can also [start a database without connecting](#) to it.

[Related Topics](#)

Connecting to a running database on a visible server

To connect to a running **database** on a **server** shown in Sybase Central:

- ◆ Open the [desired server](#).
- ◆ Do one of the following:
 - Click the database (shown as a [disconnected database](#)).
 - Click **Open** in the **File** menu or [pop-up menu](#).
- ◆ In the connection dialog, enter your [User ID](#) and [Password](#).
If you're using NT-integrated logins, you can leave these fields blank.

[Related Topics](#)

Using the connection dialog

To connect to a database on a server that isn't shown in Sybase Central, do one of the following:

- ◆ In the **Tools** menu, click **Connect**.
If your copy of Sybase Central supports more than one database product, click **Connect > Sybase SQL Anywhere**.
- ◆ Click the **Connect** button in the [main toolbar](#), or press **F11**.
If your copy of Sybase Central supports more than one database product, a dialog prompts you for the type of connection. Select **Sybase SQL Anywhere**.

Either of these steps opens the connection dialog. How you use the connection dialog depends on the state of the database that you want to connect to:

{button ,JI('>howto','IDH_scsa_database_connect_lone')} [A single database is already running on a single stand-alone engine](#)

{button ,JI('>howto','IDH_scsa_database_connect_invisible_server')} [The database is already running, but the server isn't visible in Sybase Central](#)

{button ,JI('>howto','IDH_scsa_database_connect_not_running')} [The database isn't running yet](#)

Notes:

- ◆ You can also connect to a [running database on a server shown](#) in Sybase Central.
- ◆ You can make subsequent connections to a given database easier and faster by using a [connection profile](#).

[Related Topics](#)

Connecting to a lone running database on a lone stand-alone engine

To connect to a **database** that is the only one running on a single **stand-alone engine** on your PC:

- ◆ Open the database [connection dialog](#).
- ◆ Enter your [User ID](#) and [Password](#).
If you're using NT-integrated logins, you can leave these fields blank.

[Related Topics](#)

Connecting to a running database if you can't see the server

To connect to a running **database** if you can't see the server in Sybase Central:

- ◆ Open the database [connection dialog](#).
- ◆ Enter your [User ID](#) and [Password](#).
If you're using NT-integrated logins, you can leave these fields blank.
- ◆ Click **More** to expand the dialog.
- ◆ If you are running more than one [stand-alone engine](#), or if you're using a [SQL Anywhere client](#) to connect to a [network server](#), enter a [Server Name](#).
- ◆ Enter the [Database Name](#).

[Related Topics](#)

Connecting to a database not currently running

To connect to a **database** that is not currently running:

- ◆ Open the database [connection dialog](#).
- ◆ Enter your [User ID](#) and [Password](#).
If you're using NT-integrated logins, you can leave these fields blank.
- ◆ Click **More** to expand the dialog.
- ◆ Enter a [Server Name](#).
{button ,PI(>howto','IDH_scsa_server_name_details')} [How?](#)
- ◆ Enter a [Database Name](#).
- ◆ Enter the path and name of a [Database File](#).
- ◆ If you're using a [stand-alone engine](#), click **Local**.
If you're using a [SQL Anywhere client](#) to connect to a [network server](#), click **Network**.
- ◆ To start the database with command-line parameters, click the **Custom** option, then click the **Custom** push-button to open the command-line dialog.

[Related Topics](#)

Specifying a server name

If you enter a name for the server, the database will try to use a running [stand-alone engine](#) or [SQL Anywhere client](#) of that name (depending on the **Local** or **Network** options).

If no engine/client of that name is running, one will be started automatically using that name.

If you leave the **Server Name** blank for an engine or client, the database will use the first active engine that it finds on the local machine (regardless on the **Local** or **Network** options).

If no engines are running, one will be started automatically, and will be named the same as the [database name](#) (or the root of the [database file](#), if the database name is blank). For example, starting a database file of **SADEMO.DB** yields a server named **SADEMO**.

Object tree for Sybase SQL Anywhere

For SQL Anywhere, the [object tree](#) shows all servers that you have connected to (more precisely, the ones with databases that you have connected to in Sybase Central).

For each server shown, you can see **all** databases running on it. You may be connected to some of these in Sybase Central ([connected databases](#)), and not connected to others ([disconnected databases](#)).

[Related Topics](#)

Starting a database without connecting

To start a database on a visible server (without connecting to the database):

- ◆ Select the desired server.
- ◆ Click **Start Database** in the **File** menu or [pop-up menu](#).
- ◆ In the start dialog, enter the desired values.
{button ,PI(^>howto', 'IDH_sc_help_whats_this')} [How?](#)

The database appears under the server as a [disconnected database](#).

Notes:

- ◆ You can also start a database and [connect](#) to it at the same time.

[Related Topics](#)

Stopping disconnected databases

To stop one or more **disconnected databases**:

- ◆ Open the [desired server](#).
- ◆ Select the desired databases.
- ◆ Click **Stop Database** in the **File** menu or [pop-up menu](#).

This unconditionally stops the selected databases (even if there are connections to them).

Notes:

- ◆ This is functionally equivalent to the [DBSTOP](#) program.



[Related Topics](#)

Showing performance statistics for a server

To show performance statistics for a server:

- ◆ Open the [desired server](#).
- ◆ Open the **Statistics** folder.

The various statistics are represented by two icons:

- ◆  Statistics that you've added to the [performance monitor](#)
- ◆  Statistics not shown in the monitor

Notes:

- ◆ You can also inspect statistics [for connected users](#) and [for individual tables](#).

[Related Topics](#)

Editing properties of a statistic

To edit the properties of a server **statistic**:

- ◆ Open the [Statistics folder](#).
- ◆ Select the desired statistic.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General

Notes:

- ◆ The only property you can change for a statistic is the [graphing of the statistic](#) in the Sybase Central performance monitor.

[Related Topics](#)

Overview of the Sybase Central performance monitor

The [Sybase Central performance monitor](#) displays a graph of [statistics](#) for a given SQL Anywhere [server](#). The graph is shown in its own window, and is updated in real time (at adjustable intervals).

You can [use the Sybase Central monitor](#) to graph statistics for any SQL Anywhere server that you can connect to in Sybase Central.

Note, however, that the Sybase Central monitor uses actual queries against the server to gather its statistics. This means that some statistics (such as Cache Reads/sec) are affected by the monitor itself.

As an alternative, you can graph server statistics using the [Windows NT performance monitor](#).

[Related Topics](#)

Using the Sybase Central performance monitor

To open the [Sybase Central performance monitor](#):

- ◆ Open the [Statistics folder](#) for the desired [server](#).
- ◆ Make sure that you've [added at least one statistic](#) to the monitor.
- ◆ In the right panel, double-click **Performance Monitor**.

If you close the monitor window, it will re-open automatically if you add more statistics to it.

The monitor can display statistics as a [line graph or bar graph](#).

To show or hide the legend (a detailed list of all graphed statistics), click **Legend** in the **View** menu of the monitor window.

To change the color or line style of a graphed statistic, edit the statistic's [display properties](#).

To clear existing plotted values from the graph, click **Clear** in the **File** menu. You can also [remove statistics](#) from the graph altogether.

You can also set [preferences](#) for the monitor.

The monitor's status bar shows a brief summary of menu commands as you navigate through its menus.

[Related Topics](#)

Adding statistics to the monitor

To add **statistics** to the [Sybase Central performance monitor](#):

- ◆ Open the [Statistics folder](#).
- ◆ Select the desired statistics.
- ◆ Click **Add to Performance Monitor** in the **File** menu.
{button ,PI(^>howto',`IDH_scsa_server_monitor_stats_add_other_ways')} [Other ways](#)

You can also add a statistic to the graph from the [statistic's property sheet](#).

[Related Topics](#)

Ways to add statistics

To add statistics to the monitor, do one of the following:

- ◆ Select the desired statistics, then click **Add to Performance Monitor** in the **File** menu or [pop-up menu](#).
- ◆ [Drag and drop](#) the statistics onto the **Performance Monitor** [template](#).

Changing the type of monitor graph

The [Sybase Central performance monitor](#) can display statistics as a line graph or bar graph.

To display a continuous line graph that scrolls right to left as statistics are updated, do one of the following:

- ◆ In the monitor window, click **Line Graph** in the **View** menu.
- ◆ Click the **Line Graph** button in the [monitor toolbar](#).

To display a stationary bar graph (where each bar shows that statistic's most recent value), do one of the following:

- ◆ In the monitor window, click **Bar Graph** in the **View** menu.
- ◆ Click the **Bar Graph** button in the monitor toolbar.

[Related Topics](#)

Editing a statistic's display properties in the monitor

To edit the **display properties** of a server **statistic** in the [Sybase Central performance monitor](#):

- ◆ In the monitor window, select the desired statistic in the legend.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

Display

[Related Topics](#)

Removing statistics from the monitor

To remove **statistics** from the [Sybase Central performance monitor](#), do one of the following:

- ◆ In the [Statistics folder](#), select the desired statistics, then click **Remove from Performance Monitor** in the **File** menu or [pop-up menu](#).
- ◆ In the monitor window, select the desired statistics in the legend, then click **Remove Statistic** in the **Edit** menu.
{button ,PI('>howto','IDH_scsa_server_monitor_stats_remove_other_ways')} [Other ways](#)

You can also remove statistics from the graph from the [statistic's property sheet](#).

[Related Topics](#)

Ways of removing statistics

To remove statistics while in the monitor window, do one of the following:

- ◆ Click **Remove Statistic** in the **Edit** menu or pop-up menu.
- ◆ Click the **Remove Statistic** button in the [monitor toolbar](#).

Using the monitor toolbar

The [Sybase Central performance monitor](#) toolbar (shown below) provides you with graphic buttons for common commands.



Click a button above to see a description of what it does.

To show or hide the toolbar, click **Toolbar** in the **View** menu.

[Related Topics](#)

Setting preferences for the performance monitor

To set your preferences for the [Sybase Central performance monitor](#):

- ◆ In the monitor window, click **Preferences** in the **File** menu.
- ◆ In the preferences dialog, enter the desired values.
{button ,PI(^>howto',`IDH_sc_help_whats_this')} [How?](#)

[Related Topics](#)

Graphing with the Windows NT performance monitor

SQL Anywhere supports two ways to monitor your [database servers](#):

- ◆ Sybase Central's own [integrated performance monitor](#)
- ◆ integration with the [Windows NT performance monitor](#) (included with Windows NT)

If you can use the NT monitor (it can only be used in a NT-to-NT setup), you should use it instead of the Sybase Central monitor because:

- ◆ The NT monitor offers more [statistics](#) (mainly those concerned with network communications).
- ◆ Unlike the Sybase Central monitor, the NT monitor is non-intrusive. It uses a shared-memory scheme instead of performing queries against the server, so it does not affect the statistics themselves.

[Related Topics](#)

Showing all databases on a server

To show all **databases** running on a given **server** that you are connected to:

- ◆ Open the [desired server](#).

This shows both [connected databases](#) and [disconnected databases](#).

Notes:

- ◆ You can also [connect to a disconnected database](#).

[Related Topics](#)

Editing properties of a database

To edit the properties of a **database**:

- ◆ Open the [desired server](#).
- ◆ Select the desired database.
- ◆ Click **Properties** in the **File** menu.
{button ,PI('^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI('^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Extended Information, [SQL Remote](#)

Notes:

- ◆ [Disconnected databases](#) have an abbreviated property sheet with no editable properties.
-

[Related Topics](#)

Setting options for a database

To set options for a **database**:

- ◆ Open the [desired server](#).
- ◆ Select the desired database.
- ◆ Click **Set Options** in the **File** menu or [pop-up menu](#).
- ◆ Edit the desired values.
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

Notes:

- ◆ You can also set database options for [specific users and groups](#).
- ◆ In Sybase Central, you can set [database options](#) (including compatibility options and replication options), but you cannot set ISQL options.
- ◆ When you set options for the database itself, you are actually setting options for the PUBLIC group in that database, since all users and groups inherit option settings from PUBLIC.

[Related Topics](#)

Setting a consolidated database

To set a consolidated **database**:

- ◆ Open the [desired server](#).
- ◆ Select the desired database.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Click the SQL Remote tab.
- ◆ Edit the desired properties.
{button ,PI(^>howto',`IDH_sc_help_whats_this')} [How?](#)

Extended Information, [SQL Remote](#)

Showing system objects in a database

To show or hide **system objects** in a database:

- ◆ Open the [desired server](#).
- ◆ Select the desired [connected database](#).
- ◆ Click **Show System Objects** in the **File** menu or [pop-up menu](#).

The system [tables](#), system [views](#), system [procedures](#), and system [user-defined data types](#) appear in their respective folders (for example, system tables appear alongside normal tables in the **Tables** folder).

[Related Topics](#)

Connecting to a database in ISQL

To open ISQL and automatically connect to a database:

- ◆ Open the [desired server](#).
- ◆ Select the desired [connected database](#).
- ◆ Click **Open ISQL** in the **File** menu or [pop-up menu](#).

Notes:

- ◆ If you are already running ISQL, Sybase Central will re-use it instead of starting a new ISQL.

[Related Topics](#)

Validating a database

To validate all indexes in a connected database:

- ◆ Open the [desired server](#).
- ◆ Select the desired [connected database](#).
- ◆ Click **Validate** in the **File** menu or [pop-up menu](#).

To validate all indexes in a database that is not running:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Validate Database**.
{button ,PI(^>howto','IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the wizard.

During the validation process, a status dialog shows the following:

- ◆ the names of the indexes as they are checked
- ◆ any validation errors encountered
- ◆ The total number of errors reported

Notes:

- ◆ You can also validate the indexes [on a particular table](#) instead of the entire database.
- ◆ This utility is functionally equivalent to the [DBVALID](#) program.

[Related Topics](#)

Extracting from a consolidated database

To extract a remote database from a consolidated database:

- ◆ Open the [desired server](#).
- ◆ Select the desired consolidated database (it must be a [connected database](#)).
- ◆ Click **Extract Database** in the **File** menu.
{button ,PI('>howto','IDH_scsa_database_extract_other_ways')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

To extract a remote database from any consolidated database (running or not):

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Extract Database**.
{button ,PI('>howto','IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the wizard.

Notes:

- ◆ You can also invoke the extraction wizard directly [for a particular remote user](#).

[Related Topics](#)

Rebuilding a Database

To rebuild a database:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Rebuild Database**.
{button ,PI(^>howto', 'IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the wizard.

Notes:

- ◆ When a database is being rebuilt, no other users should be connected to it.
- ◆ Users with replicated databases should not rebuild their database in this way.

[Related Topics](#)

Ways to extract from a database

To extract from a database, select it and do one of the following:

- ◆ Click **Extract Database** in the **File** menu or [pop-up menu](#).
- ◆ [Drag and drop](#) the database onto the **Extract Database** wizard in the **Utilities** folder.

Examining or stopping passthrough mode for SQL Remote

To examine the status of (or stop) a [passthrough](#) from a [consolidated database](#) to [remote databases](#):

- ◆ Open the [desired server](#).
- ◆ Select the desired consolidated database. (It must be a [connected database](#)).
- ◆ Click **Passthrough** in the **File** menu.
{button ,PI('>howto','IDH_scsa_database_passthrough_other_ways')} [Other ways](#)

This opens the [passthrough dialog](#).

[Related Topics](#)

Ways to open the passthrough dialog

To open the passthrough dialog, select the desired consolidated database and do one of the following:

- ◆ Click **Passthrough** in the **File** menu or [pop-up menu](#).
- ◆ Open the [database's property sheet](#), then click **Passthrough** on the **SQL Remote** page.

Disconnecting yourself from databases

To disconnect from one or more **connected databases**:

- ◆ Open the [desired server](#).
- ◆ Select the desired databases.
- ◆ Click **Disconnect** in the **File** menu or [pop-up menu](#).

You can also use the disconnect dialog:

- ◆ Do one of the following:
 - Click **Disconnect** in the **Tools** menu.
 - Click the **Disconnect** button in the [main toolbar](#).
- ◆ In the disconnect dialog, select the desired databases.
- ◆ Click **Disconnect**.

Notes:

- ◆ You can also [disconnect other users](#) from a given database.

[Related Topics](#)

Creating a new database

To create a new SQL Anywhere database:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Create Database**.
{button ,PI(^>howto',`IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Once you've created a database and [connected](#) to it, you can start creating objects in it (tables, users, and so on).

Notes:

- ◆ This utility is functionally equivalent to the [DBINIT](#) program.

[Related Topics](#)

Upgrading a database

To upgrade an existing database (Watcom SQL 3.2 or 4.0, or SQL Anywhere 5) to the latest SQL Anywhere 5 database format:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Upgrade Database**.
{button ,PI('^>howto','IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You cannot upgrade a database if you are already connected to it (in Sybase Central or any other application). You must disconnect from the database first.
- ◆ The upgrade process works on the database that you specify, upgrading it **in place**. Because of this, we recommend that you back up a database before upgrading it.
- ◆ This utility is functionally equivalent to the [DBUPGRAD](#) program.

[Related Topics](#)

Backing up a database

To back up a connected database:

- ◆ Open the [desired server](#).
- ◆ Select the desired database.
- ◆ Click **Backup Database** in the **File** menu.
{button ,PI('>howto','IDH_scsa_database_backup_other_ways')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

To back up any database (running or not) or a write file:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Backup Database**.
{button ,PI('>howto','IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the wizard.

Notes:

- ◆ This utility is functionally equivalent to the [DDBACKUP](#) program.

[Related Topics](#)

Ways to backup a connected database

To backup a connected database, do one of the following:

- ◆ Select the desired database, then click **Backup** in the **File** menu or [pop-up menu](#).
- ◆ [Drag and drop](#) the database onto the **Backup Database** wizard in the **Utilities** folder.

Compressing a database

To compress a database into a **compressed database file**:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Compress Database**.
{button ,PI(^>howto',`IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You cannot compress a database if you are already connected to it (in Sybase Central or any other application). You must disconnect from the database first.
- ◆ This utility is functionally equivalent to the [DBSHRINK](#) program.

[Related Topics](#)

Uncompressing a database

To uncompress a **compressed database file** into a normal **database file**:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Uncompress Database**.
{button ,PI(^>howto','IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You cannot uncompress a database if you are already connected to it (in Sybase Central or any other application). You must disconnect from the database first.
- ◆ This utility is functionally equivalent to the [DBEXPAND](#) program.

[Related Topics](#)

Creating a write file

To create a **write file** for an existing database:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Create Write File**.
{button ,PI(^>howto',`IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You cannot create a write file for a database if you are already connected to it (in Sybase Central or any other application). You must disconnect from the database first.
- ◆ This utility is functionally equivalent to the [DBWRITE](#) program.

[Related Topics](#)

Translating a log file

To translate an existing **transaction log** into a **SQL command file**:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Translate Log**.
{button ,PI(^>howto',`IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You cannot translate a log for a database if you are already connected to it (in Sybase Central or any other application). You must disconnect from the database first.
- ◆ This utility is functionally equivalent to the [DBTRAN](#) program.

[Related Topics](#)

Changing a log file

To change the name of the **transaction log file** for a database or **write file**:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Change Log File Information**.
{button ,PI(^>howto',`IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You cannot change the name of a log for a database if you are already connected to it (in Sybase Central or any other application). You must disconnect from the database first.
- ◆ This utility is functionally equivalent to the [DBLOG](#) program.

[Related Topics](#)

Unloading a database

To unload a connected database:

- ◆ Open the [desired server](#).
- ◆ Select the desired database.
- ◆ Click **Unload Database** in the **File** menu.
{button ,PI(^>howto','IDH_scsa_database_unload_other_ways')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

To unload any database or write file to a SQL command file:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Unload Database**.
{button ,PI(^>howto','IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the wizard.

Notes:

- ◆ This utility is functionally equivalent to the [DBUNLOAD](#) program.
- ◆ You can also [unload specific tables](#) in the database.

[Related Topics](#)

Ways to unload a connected database

To unload a connected database, do one of the following:

- ◆ Select the desired database, then click **Unload** in the **File** menu or [pop-up menu](#).
- ◆ [Drag and drop](#) the database onto the **Unload Database** wizard in the **Utilities** folder.

Erasing a database

To erase all or part of an existing database, **write file**, or **compressed database file**:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Erase Database**.
{button ,PI(^>howto',`IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You cannot erase a database if you are already connected to it (in Sybase Central or any other application). You must disconnect from the database first.
- ◆ This utility is functionally equivalent to the [DBERASE](#) program.

[Related Topics](#)

Starting ISQL

To start **ISQL** from Sybase Central:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **ISQL**.
{button ,PI(^>howto','IDH_sc_utilities_start')} [Other ways](#)

This starts a new ISQL session.

Notes:

- ◆ You can also use ISQL to automatically [connect to a database](#), browse data in [tables](#) or [views](#), or [test procedures](#).

[Related Topics](#)

Starting InfoMaker

To start Powersoft InfoMaker from Sybase Central:

- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **InfoMaker**.
{button ,PI(^>howto',`IDH_sc_utilities_start')} [Other ways](#)

[Related Topics](#)

Showing tables in a database

To show the **base tables** and **global temporary tables** in a database:

- ◆ Open the [desired database](#).
- ◆ Open the **Tables** folder.

Notes:

- ◆ For a given database, you also can choose to [show or hide system tables](#).

[Related Topics](#)

Creating a new table

To create a new **base table** or **global temporary table** in a database:

- ◆ Open the [Tables folder](#).
- ◆ In the right panel, double-click **Add Table**.
{button ,PI(^>howto',`IDH_sc_create_object`)} [Other ways](#)
- ◆ In the [table editor](#):
 - Enter a **Name** for the new table.
 - Select a **Creator** for the new table.
 - Create columns for the new table.

Notes:

- ◆ You can also create tables by [copying](#) them from the same database or a different database.

[Related Topics](#)

Copying tables within/between databases

To avoid having to re-create similar tables from scratch, you can copy table definitions within a [connected database](#) or between databases.

To copy tables by [dragging and dropping](#):

- ◆ Hold down the **Ctrl** key.
- ◆ Drag and drop the tables onto the **Tables** folder of the desired database.

To copy tables by copying and pasting:

- ◆ Select the tables to copy.
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the **Tables** folder.
- ◆ Click **Paste**.

In the copy dialog that appears for each of these tables, enter the desired values.

{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

The new table is created, and the original table's columns are copied to it.

Notes:

- ◆ Only the table itself and its columns are copied. The other table properties (check constraints, etc.), child objects (indexes, etc.), and data are **not** copied.

[Related Topics](#)

Editing properties of a table

To edit the properties of a given table:

- ◆ Open the [Tables folder](#).
- ◆ Select the desired table.
- ◆ Click **Properties** in the **File** menu.
{button ,PI('^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI('^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, [Columns](#), [Constraints](#), [Permissions](#), Statistics

Notes:

- ◆ You can also inspect statistics [for the server](#) and [for connected users](#).
-

[Related Topics](#)

Overview of the table editor

The table editor provides a quick way of creating and editing tables and their columns.

For new tables, you can:

- ◆ enter a table **Name** and choose a **Creator** in the [toolbar](#)
- ◆ set the [table's type](#) ([base table](#) or [global temporary table](#))

For existing tables, you can change the table's **Name**, but you cannot change the **Creator** or the table's type.

You can [create, edit, and delete](#) columns.

You can add and remove columns in the [primary key](#).

To save your changes to the table:

- ◆ Click **Save Table** in the toolbar or [pop-up menu](#).

To save your changes and close the table editor:

- ◆ Click **Save And Close** in the toolbar or pop-up menu.

[Related Topics](#)

Setting the table's type

In the [table editor](#), you can set or inspect a table's type ([base table](#) or [global temporary table](#)):

- ◆ Click **Advanced Table Properties** in the [toolbar](#) or [pop-up menu](#).
- ◆ Edit the desired values.
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

You can also edit the table's comment in this dialog.

Notes:

- ◆ You cannot change a table's type once the table has been created in the database.
- ◆ The table type and comment are also shown in the [table's property sheet](#).

[Related Topics](#)

Managing columns in the table editor

In the [table editor](#), you can quickly create and manipulate table columns.

To add a new column to the table:

- ◆ Click **Add Column** in the [toolbar](#) or [pop-up menu](#) (or press **Ins**).
- ◆ Enter values for the properties of the new column.
- ◆ To [edit advanced properties](#) for the column, click **Advanced Column Properties** in the toolbar or pop-up menu.

To edit properties of an existing table column:

- ◆ Select the desired column.
- ◆ Click on the desired property to edit it.
Note that some properties cannot be changed.
- ◆ To edit more properties of the column, click **Advanced Column Properties** in the toolbar or pop-up menu.

To delete a column from the table:

- ◆ Select the desired column.
- ◆ Click **Delete Column** in the toolbar or pop-up menu (or press **Ctrl-Del**).

Notes:

- ◆ You can also manage columns in the table's [Columns folder](#).

[Related Topics](#)

Editing the primary key in the table editor

In the [table editor](#), columns that are part of the [primary key](#) are shown with a special icon that represents their order in the key.

To add not-null columns to the primary key, do one of the following:

- ◆ Click their icon in the **Key** column.
- ◆ Click **Add To Primary Key** in the [pop-up menu](#).

To remove columns from the primary key, do one of the following:

- ◆ Click their icon in the **Key** column.
- ◆ Click **Remove From Primary Key** in the pop-up menu.

To move columns up in the key order, do one of the following:

- ◆ Shift-Ctrl-click their icon in the **Key** column.
- ◆ Click **Move Up In Key** in the pop-up menu.

To move columns down in the key order, do one of the following:

- ◆ Shift-click their icon in the **Key** column.
- ◆ Click **Move Down In Key** in the pop-up menu.

Notes:

- ◆ You can also edit the primary key in the table's [property sheet](#) and [Columns folder](#).

[Related Topics](#)

Using the table editor's toolbar

The [table editor's](#) toolbar (shown below) provides you with graphic buttons for common commands.



Click a button above to see a description of what it does.

[Related Topics](#)

Showing columns

To show the **columns** of a given table:

- ◆ In the [Tables folder](#), open the desired table.
- ◆ Open the **Columns** folder.

Columns that are part of the [primary key](#) are shown with a special icon.

Notes:

You can also edit the columns of a table using the [table editor](#) or the [table's property sheet](#).

[Related Topics](#)

Creating a new column

To create a new **column** in a given table:

- ◆ For the desired table, open the [Columns folder](#).
- ◆ In the right panel, double-click **Add Column**.
{button ,PI('>howto','IDH_sc_create_object')} [Other ways](#)
- ◆ In the [table editor](#), enter the desired values for the new column.

Notes:

- ◆ You can also create columns in a table by [copying them](#) from other tables.

[Related Topics](#)

Copying columns within/between tables

To avoid having to re-create similar columns from scratch, you can copy [columns](#) within a table or between tables.

To copy columns by [dragging and dropping](#):

- ◆ Open the source table's **Columns** folder.
- ◆ In the right panel, select the columns to copy.
- ◆ If you're copying within the same table, hold down the **Ctrl** key.
- ◆ Drag and drop the columns onto the destination table or onto its **Columns** folder.
- ◆ In the copy dialog that appears for each column, enter the desired values.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Notes:

- ◆ The column's comment is **not** copied to the new column.
- ◆ You cannot copy a not-NULL column to a table that already contains rows of data.
If you try to do this, you will get a "table must be empty" error.

[Related Topics](#)

Editing columns in the table editor

To edit the columns of a given table:

- ◆ Open the [Tables folder](#).
- ◆ Select the desired table.
- ◆ Click **Edit Columns** in the **File** menu or [pop-up menu](#).
- ◆ In the [table editor](#), edit the column definitions.

Notes:

- ◆ You can also edit columns in the table's [Columns folder](#).

[Related Topics](#)

Editing properties of a column

To edit the properties of a given table column:

- ◆ For the desired table, open the [Columns folder](#).
- ◆ Select the desired column.
- ◆ Click **Properties** in the **File** menu.
{button ,PI('>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Data Type

Notes:

- ◆ You can also **directly** edit the advanced properties of a column ([default value](#), [check constraint](#), [unique constraint](#), and [nullability](#)).
{button ,PI('>howto','IDH_scsa_table_column_properties_advanced')} [How?](#)
 - ◆ You can also create and edit columns in the [table editor](#).
-

[Related Topics](#)


Directly editing advanced properties of a column

To **directly** edit the advanced properties of a column:

- ◆ In the main window, select the desired column.
- ◆ Click **Advanced Properties** in the **File** menu or [pop-up menu](#).

Setting permissions on table columns

To manage **permissions** on table columns:

- ◆ Open the [Permissions page](#) of the table's property sheet.
- ◆ Click the  button for **Reference**, **Select**, or **Update** to open the column permissions dialog.

To grant or revoke permissions on specific table columns:

- ◆ Click **Grant permission on only these columns**.
- ◆ Select columns in the list.
- ◆ Set the **Column has permission** and [with grant option](#) options appropriately.

To grant permissions on all columns (not specific columns):

- ◆ Click **Grant permission on all columns**.

[Related Topics](#)

Deleting columns

To delete one or more **columns** from a table:

- ◆ For the desired table, open the [Columns folder](#).
- ◆ Select the desired columns.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_object_delete')} [Other ways](#)

Notes:

- ◆ You can also delete columns in the [table editor](#).

[Related Topics](#)

Managing unique constraints for a table

To manage **unique constraints** on a table:

- ◆ Open the [table's property sheet](#).
- ◆ Click the **Constraints** tab.

To create a new unique constraint on the table:

- ◆ In the **Unique constraints** section, click **New**.
- ◆ In the constraint dialog, use the controls to build the constraint. {button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

To remove a unique constraint on the table:

- ◆ In the **Unique constraints** section, select the desired constraint.
- ◆ Click **Remove**.

Notes:

- ◆ The **Constraints** list shows true table constraints (containing more than one column) **as well as** column constraints (containing a single column). Adding a single-column constraint here is equivalent to setting the column's **Unique** property in its [property sheet](#).
- ◆ You cannot edit an existing constraint. You must remove it and create a new one.

[Related Topics](#)

Editing the check constraint for a table

To edit the **check constraint** for a given table:

- ◆ Open the [table's property sheet](#).
- ◆ Click the **Constraints** tab.
- ◆ Edit the text in the **Check constraint** text box.

[Related Topics](#)

Showing the primary key

The [primary key](#) of a table is shown in several places:

- ◆ in the **Columns** page of the [table's property sheet](#)
- ◆ in the [Columns folder](#) of the table
- ◆ in the [table editor](#)

The primary-key columns have special icons to distinguish them from non-key columns.

The order of the columns in the primary key is shown in the **Primary Key Columns** field in the table's property sheet.

Notes:

- ◆ The lists in both the table property sheet and the **Columns** folder show the primary-key columns (along with the non-key columns) in the order that they were created in the database. This may differ from the actual ordering of columns in the primary key.

[Related Topics](#)

Editing the primary key

To edit the **primary key** of a given table:

- ◆ Open the [table's property sheet](#).
- ◆ Click the **Columns** tab.
- ◆ Use the controls to change the primary key.
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

To change the order of the columns in the key (as shown in the **Primary Key Columns** field), you must remove some or all of them and re-add them to the key.

You can also edit the primary key from the table's [Columns folder](#).
{button ,PI('>howto','IDH_scsa_primary_key_edit_details')} [How?](#)

[Related Topics](#)

Editing the primary key in the main window

You can edit the primary key directly in the table's [Columns folder](#) in the main window.

To add a column to the primary key:

- ◆ Select the desired column.
- ◆ Click **Add to Primary Key** in the **File** menu or [pop-up menu](#).

To remove a column from the primary key:

- ◆ Select the desired column.
- ◆ Click **Remove from Primary Key** in the **File** menu or pop-up menu.

Showing foreign keys

To show the **foreign keys** of a given table:

- ◆ Open the [desired table](#).
- ◆ Open the **Foreign Keys** folder.

[Related Topics](#)

Creating a new foreign key

To create a new **foreign key** in a given table:

- ◆ For the desired table, open the [Foreign Keys folder](#).
- ◆ In the right panel, double-click **Add Foreign Key**.
{button ,PI(^>howto',`IDH_sc_create_object`)} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You can quickly create a foreign key in a given table by [dragging and dropping](#) the primary table onto it (both tables must be in the same database). This automatically opens the foreign-key creation wizard.
- ◆ You can also create a foreign key in a given table by copying and pasting.
{button ,PI(^>howto',`IDH_scsa_foreign_key_copy`)} [How?](#)
- ◆ You cannot create a foreign key in a table if the table contains values for the foreign columns that can't be matched to values in the primary table's primary key.
If you try to do this, you will get a "no primary key value for foreign key <name> in table <name>" error.

[Related Topics](#)

Creating foreign keys by copying and pasting

You can create a foreign key in a given table by copying and pasting the primary table onto it:

- ◆ Select the primary table.
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the foreign table.
- ◆ Click **Paste**.

This automatically opens the foreign-key creation wizard.

Editing properties of a foreign key

To edit the properties of a given foreign key:

- ◆ For the desired table, open the [Foreign Keys folder](#).
- ◆ Select the desired foreign key.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Columns, Integrity

Notes:

- ◆ You cannot change the columns in the foreign key except by deleting and recreating the key.
-

[Related Topics](#)

Deleting foreign keys

To delete one or more foreign keys from a table:

- ◆ For the desired table, open the [Foreign Keys folder](#).
- ◆ Select the desired foreign keys.
- ◆ Click **Delete** in the **File** menu.
{button ,PI('>howto','IDH_sc_object_delete')} [Other ways](#)

[Related Topics](#)

Showing references from other tables

To show, for a given **table**, which tables have **foreign keys** that reference it:

- ◆ Open the [desired table](#).
- ◆ Open the **Referenced By** folder.

This shows any referencing (foreign) tables.

Double-clicking a referencing table opens that [table's property sheet](#).

[Related Topics](#)

Showing indexes

To show the **indexes** of a given table:

- ◆ Open the [desired table](#).
- ◆ Open the **Indexes** folder.

[Related Topics](#)

Creating a new index

To create a new **index** for a given table:

- ◆ For the desired table, open the [Indexes folder](#).
- ◆ In the right panel, double-click **Add Index**.
{button ,PI('>howto','IDH_sc_create_object')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

[Related Topics](#)

Editing properties of an index

To edit the properties of a given table index:

- ◆ For the desired table, open the [Indexes folder](#).
- ◆ Select the desired index.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Columns

Notes:

- ◆ You cannot change the [database space](#) or columns used in the index except by deleting and recreating the index.
-

[Related Topics](#)

Deleting indexes

To delete one or more indexes from a table:

- ◆ For the desired table, open the [Indexes folder](#).
- ◆ Select the desired indexes.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_object_delete')} [Other ways](#)

[Related Topics](#)

Showing triggers

To show the **triggers** of a given table:

- ◆ Open the [desired table](#).
- ◆ Open the **Triggers** folder.

[Related Topics](#)

Creating a new trigger

To create a new **trigger** for a given table:

- ◆ For the desired table, open the [Triggers folder](#).
- ◆ In the right panel, double-click **Add Trigger**.
{button ,PI(^>howto',`IDH_sc_create_object`)} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).
- ◆ When the wizard finishes and opens the [code editor](#) for you, complete the code of the trigger.
- ◆ Click **Execute Script** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_code_execute`)} [Other ways](#)

[Related Topics](#)

Editing a trigger's code

To edit the code of a trigger:

- ◆ For the desired table, open the [Triggers folder](#).
- ◆ Select the desired trigger.
- ◆ Click an [Open As](#) command in the **File** menu.
{button ,PI(^>howto',`IDH_scsa_code_open_as')} [Other ways](#)
- ◆ In the [code editor](#), edit the trigger's code.
- ◆ Click **Execute Script** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_code_execute')} [Other ways](#)

Notes:

- ◆ You cannot rename an existing trigger directly.
Instead, you must create a new trigger with the new name, copy the old code to it, then delete the old trigger.

[Related Topics](#)

Choosing a SQL dialect

When opening triggers or procedures in the code editor, you can choose the SQL dialect to use:

- ◆ **Open** shows the code in the SQL dialect in which it was last saved. (Double-clicking is equivalent to this).
- ◆ **Open as Watcom-SQL** shows the code in [Watcom-SQL](#) dialect.
- ◆ **Open as Transact-SQL** shows the code in [Transact-SQL](#) dialect.

Editing properties of a trigger

To edit the properties of a given trigger:

- ◆ For the desired table, open the [Triggers folder](#).
- ◆ Select the desired trigger.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Type Information

Notes:

- ◆ You cannot rename an existing trigger directly.
Instead, you must create a new trigger with the new name, copy the old code to it, then delete the old trigger.
-

[Related Topics](#)

Deleting triggers

To delete one or more triggers from a table:

- ◆ For the desired table, open the [Triggers folder](#).
- ◆ Select the desired triggers.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_object_delete')} [Other ways](#)

[Related Topics](#)

Setting permissions on a table

To manage **permissions** on a table:

- ◆ Open the [table's property sheet](#).
- ◆ Click the **Permissions** tab.

To grant full permissions to **users** or **groups**:

- ◆ Click **Grant** to open the selection dialog.
- ◆ Select the desired users and groups, then click **Grant Permission**.

To set specific permissions for users or groups:

- ◆ In the list, select the desired users and groups.
- ◆ Set the various table permissions, [grant options](#), and [column permissions](#).
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

To revoke table permissions for users or groups:

- ◆ Select the desired users and groups, then click **Revoke**.

Notes:

- ◆ You can also assign permissions from the [user/group property sheet](#).
To assign permissions to many users and groups at once, use the table's property sheet.
To assign permissions to many tables at once, use the user's property sheet.
- ◆ You can quickly assign full permissions on a table by [dragging and dropping](#) users or groups onto it (or by dragging the table itself onto a user or group).
- ◆ You can also assign full permissions on a table by copying and pasting.
{button ,PI('>howto','IDH_scsa_table_permissions_copy')} [How?](#)

[Related Topics](#)

Copying and pasting for table permissions

To assign full permissions on a table by copying and pasting:

- ◆ Select the desired users and groups (or tables).
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the destination table (or user/group).
- ◆ Click **Paste**.

Validating tables

To **validate all indexes** in a given set of tables:

- ◆ Open the [Tables folder](#).
- ◆ Select the tables to validate.
- ◆ Click **Validate** in the **File** menu or [pop-up menu](#)

During the validation process, a status dialog shows the following:

- ◆ the names of the indexes as they are checked
- ◆ any validation errors encountered
- ◆ The total number of errors reported

Notes:

- ◆ You can also [validate all indexes](#) in a database at once.

[Related Topics](#)

Unloading tables

To **unload** specific **tables** from a database:

- ◆ Open the [Tables folder](#).
- ◆ Select the tables to unload.
- ◆ Click **Unload** in the **File** menu or [pop-up menu](#)

During the unloading process, a status dialog shows the objects for which structure or data have been unloaded.

Notes:

- ◆ This is functionally equivalent to the [DBUNLOAD](#) program.
- ◆ You can also [unload the entire database](#).

[Related Topics](#)

Browsing a table's data in ISQL

To open ISQL and browse a base table's data:

- ◆ Open the [Tables folder](#).
- ◆ Select the base table to browse.
- ◆ Click **View Data** in the **File** menu or [pop-up menu](#).

Notes:

- ◆ If you are already running ISQL, Sybase Central will re-use it instead of starting a new ISQL.
- ◆ To browse the table, ISQL executes a **select * from <owner>.<table>** statement.
- ◆ You cannot use the **View Data** command on a [global temporary table](#), since a given data set for the table is only available in the same connection that it was created in. (Sybase Central uses its own connection, and you cannot create data directly in Sybase Central).

[Related Topics](#)

Deleting tables

To delete one or more **tables** from a database:

- ◆ Open the [Tables folder](#).
- ◆ Select the desired tables.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_object_delete')} [Other ways](#)

Notes:

- ◆ You cannot delete a table that is being used as an [article](#) in a SQL Remote [publication](#).
If you try to do this, you will get a "table <name> has publications" error.

[Related Topics](#)

Showing views in a database

To show the **views** in a database:

- ◆ Open the [desired database](#).
- ◆ Open the **Views** folder.

Notes:

- ◆ For a given database, you can choose to [show or hide system views](#).

[Related Topics](#)

Creating a new view

To create a new **view** in a database:

- ◆ Open the [Views folder](#).
- ◆ In the right panel, double-click **Add View Wizard**.
{button ,PI(^>howto',`IDH_sc_create_object')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).
- ◆ When the wizard finishes and opens the [code editor](#) for you, complete the code of the view.
- ◆ Click **Execute Script** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_code_execute')} [Other ways](#)

You can also create a view without the wizard's help.

{button ,PI(^>howto',`IDH_scsa_view_create_direct')} [How?](#)

[Related Topics](#)

Creating a view directly

You can bypass the creation wizard and write your own view from scratch.

In the right panel, double-click **Add View**.

{button ,PI(>howto','IDH_sc_create_object')} [Other ways](#)

This opens the code editor with a generic view code template.

Copying views within/between databases

To avoid having to re-create similar views from scratch, you can copy view definitions within a [connected database](#) or between databases.

To copy views by [dragging and dropping](#):

- ◆ Hold down the **Ctrl** key.
- ◆ Drag and drop the views onto the **Views** folder of the desired database.

To copy views by copying and pasting:

- ◆ Select the first view.
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the **Views** folder, then click an empty spot in the right panel.
- ◆ Click **Paste**.

In the copy dialog that appears for each of these views, enter the desired values.

```
{button ,PI('>howto','IDH_sc_help_whats_this')} How?
```

The new view is created, and the original view's code is copied to it.

Notes:

- ◆ Only the view code is copied to the new view. The other properties of the view (permissions, etc.) are **not** copied.

[Related Topics](#)

Editing a view's code

To edit the code of a **view**:

- ◆ Open the [Views folder](#).
- ◆ Select the desired view.
- ◆ Click **Open** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_code_open')} [Other ways](#)
- ◆ In the [code editor](#), edit the view's code.
- ◆ Click **Execute Script** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_code_execute')} [Other ways](#)

Notes:

- ◆ You cannot rename an existing view directly.
Instead, you must create a new view with the new name, copy the old code to it, then delete the old view.

[Related Topics](#)

Editing properties of a view

To edit the properties of a given view:

- ◆ Open the [Views folder](#).
- ◆ Select the desired view.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, [Permissions](#)

Notes:

- ◆ You cannot rename an existing view directly.
Instead, you must create a new view with the new name, copy the old code to it, then delete the old view.
-

[Related Topics](#)

Setting permissions on a view

To manage **permissions** on a given view:

- ◆ Open the [view's property sheet](#).
- ◆ Click the **Permissions** tab.

To grant full permissions to **users** or **groups**:

- ◆ Click **Grant** to open the selection dialog.
- ◆ Select the desired users and groups, then click **Grant Permission**.

To set specific permissions for users or groups:

- ◆ In the list, select the desired users and groups.
- ◆ Set the various view permissions and [grant options](#).
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

To revoke view permissions for users or groups:

- ◆ Select the desired users and groups, then click **Revoke**.

Notes:

- ◆ You can also assign permissions from the [user/group property sheet](#).
To assign permissions to many users and groups at once, use the view's property sheet.
To assign permissions to many views at once, use the user's property sheet.
- ◆ You can quickly assign full permissions to a view by [dragging and dropping](#) users or groups onto it (or by dragging the view itself onto a user or group).
- ◆ You can also assign full permissions to a view by copying and pasting.
{button ,PI('>howto','IDH_scsa_view_permissions_copy')} [How?](#)

[Related Topics](#)

Copying and pasting for view permissions

You can assign full permissions on a view by copying and pasting:

- ◆ Select the desired users and groups (or views).
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the destination view (or user/group).
- ◆ Click **Paste**.

Browsing a view's data in ISQL

To open ISQL and browse a view's data:

- ◆ Open the [Views folder](#).
- ◆ Select the view to browse.
- ◆ Click **View Data** in the **File** menu or [pop-up menu](#).

Notes:

- ◆ If you are already running ISQL, Sybase Central will re-use it instead of starting a new ISQL.
- ◆ To browse the view, ISQL executes a **select * from <owner>.<view>** statement

[Related Topics](#)

Deleting views

To delete one or more **views** from a database:

- ◆ Open the [Views folder](#).
- ◆ Select the desired views.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_object_delete')} [Other ways](#)

[Related Topics](#)

Showing procedures & functions in a database

To show the **stored procedures** and **functions** in a database:

- ◆ Open the [desired database](#).
- ◆ Open the **Procedures & Functions** folder.

Notes:

- ◆ In most cases, we use the term **procedure** to refer to both procedures **and** functions.
- ◆ For a given database, you can choose to [show or hide system procedures](#).

[Related Topics](#)

Creating a new procedure

To create a new **procedure** or **function** in a database:

- ◆ Open the [Procedures & Functions folder](#).
- ◆ In the right panel, double-click **Add Procedure/Function (Wizard)**.
{button ,PI(^>howto',`IDH_sc_create_object`)} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).
- ◆ When the wizard finishes and opens the [code editor](#) for you, complete the code of the procedure or function.
- ◆ Click **Execute Script** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_code_execute`)} [Other ways](#)

You can also create a procedure or function without the wizard's help.
{button ,PI(^>howto',`IDH_scsa_procedure_create_direct`)} [How?](#)

[Related Topics](#)

Creating a procedure or function directly

You can bypass the creation wizard and write your own procedure or function from scratch.

In the right panel, double-click **Add Procedure (Template)** or **Add Function (Template)**.

{button ,PI(>howto','IDH_sc_create_object')} [Other ways](#)

This opens the code editor with a generic code template for a procedure or function.

Copying procedures within/between databases

To avoid having to re-create similar procedures or functions from scratch, you can copy them within a [connected database](#) or between databases.

To copy procedures by [dragging and dropping](#):

- ◆ Hold down the **Ctrl** key.
- ◆ Drag and drop the procedures onto the **Procedures & Functions** folder of the desired database.

To copy procedures by copying and pasting:

- ◆ Select the first procedure.
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the **Procedures & Functions** folder, then click an empty spot in the right panel.
- ◆ Click **Paste**.

In the copy dialog that appears for each of these procedures, enter the desired values.

{button ,PI('>howto','IDH_sc_help_what_this')} [How?](#)

The new procedure is created, and the original procedure's code is copied to it.

Notes:

- ◆ Only the procedure code is copied to the new procedure. The other properties of the procedure (permissions, etc.) are **not** copied.

[Related Topics](#)

Editing a procedure's code

To edit the code of a procedure:

- ◆ Open the [Procedures & Functions folder](#).
- ◆ Select the desired procedure.
- ◆ Click an [Open As](#) command in the **File** menu.
{button ,PI(>howto',`IDH_scsa_code_open_as')} [Other ways](#)
- ◆ In the [code editor](#), edit the procedure's code.
- ◆ Click **Execute Script** in the **File** menu.
{button ,PI(>howto',`IDH_sc_code_execute')} [Other ways](#)

Notes:

- ◆ You cannot rename an existing procedure directly.
Instead, you must create a new procedure with the new name, copy the old code to it, then delete the old procedure.

[Related Topics](#)

Editing properties of a procedure

To edit the properties of a given procedure:

- ◆ Open the [Procedures & Functions folder](#).
- ◆ Select the desired procedure.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, [Permissions](#)

Notes:

- ◆ You cannot rename an existing procedure directly.
Instead, you must create a new procedure with the new name, copy the old code to it, then delete the old procedure.
-

[Related Topics](#)

Setting permissions on a procedure

To manage **permissions** on a given procedure:

- ◆ Open the [procedure's property sheet](#).
- ◆ Click the **Permissions** tab.

To grant permission to execute the procedure to **users or groups**:

- ◆ Click **Grant Execute** to open the selection dialog.
- ◆ Select the desired users and groups, then click **Grant Permission**.

To revoke permission to execute the procedure from users or groups:

- ◆ Select the desired users and groups, then click **Revoke Execute**.

Notes:

- ◆ You can also assign permissions from the [user/group property sheet](#).
To assign permissions to many users and groups at once, use the procedure's property sheet.
To assign permissions to many procedures at once, use the user's property sheet.
- ◆ You can quickly assign full permissions on a procedure by [dragging and dropping](#) users or groups onto it (or by dragging the procedure itself onto a user or group).
- ◆ You can also assign full permissions to a procedure by copying and pasting.
{button ,PI('^>howto','IDH_scsa_procedure_permissions_copy')} [How?](#)

[Related Topics](#)

Copying and pasting for procedure permissions

You can assign full permissions on a procedure by copying and pasting:

- ◆ Select the desired users and groups (or procedures).
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the destination procedure (or user/group).
- ◆ Click **Paste**.

Testing a procedure in ISQL

To test a procedure in ISQL:

- ◆ In the [Procedures & Functions folder](#), select the procedure to test.
- ◆ Click **Test Procedure** in the **File** menu or [pop-up menu](#).

This opens ISQL and does the following:

- ◆ connects to the database
- ◆ inserts a script in the command window, containing commands to:
 - drop, declare, and set variables for the procedure's parameters
 - call the procedure

You can then set the variables to your desired values, execute the script, and view the results as you normally would in ISQL.

Notes:

- ◆ If you are already running ISQL, Sybase Central will re-use it instead of starting a new ISQL.

[Related Topics](#)

Deleting procedures

To delete one or more **procedures** from a database:

- ◆ Open the [Procedures & Functions folder](#).
- ◆ Select the desired procedures.
- ◆ Click **Delete** in the **File** menu.
{button ,PI('^>howto',`IDH_sc_object_delete`)} [Other ways](#)

[Related Topics](#)

Showing users and groups in a database

To show the **users** and **groups** in a database:

- ◆ Open the [desired database](#).
- ◆ Open the **Users & Groups** folder.

The left panel shows all groups in the database (since it only shows [containers](#)). The right panel shows both users **and** groups. You can open groups to see the users and other groups that they contain.

Notes:

- ◆ You can also show all users and groups [currently connected](#) to a database.

[Related Topics](#)

Creating a new user or group

To create a new **user** or **group** in a database:

- ◆ Open the [Users & Groups folder](#).
- ◆ In the right panel, double-click **Add User** or **Add Group**.
{button ,PI(^>howto',`IDH_sc_create_object')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Once you have created a new user or group, you can:

- ◆ [add](#) it to other groups
- ◆ set its [permissions](#) on tables, views, and procedures
- ◆ set it as the [publisher](#) or as a [remote user](#) of the database

Notes:

- ◆ New users and groups are automatically added to the PUBLIC group.

[Related Topics](#)

Changing a user into a group

To change a **user** into a **group** in a database:

- ◆ Open the [Users & Groups folder](#).
- ◆ In the right panel, double-click **Add Group**.
{button ,PI(^>howto', 'IDH_sc_create_object')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#), making sure that the name of the existing user is entered for the new group name.

Once you have created a new user or group, you can:

- ◆ [add](#) it to other groups
- ◆ set its [permissions](#) on tables, views, and procedures
- ◆ set it as the [publisher](#) or as a [remote user](#) of the database

Notes:

- ◆ New users and groups are automatically added to the PUBLIC group.

[Related Topics](#)

Editing properties of a user or group

To edit the properties of a user or group:

- ◆ Open the [Users & Groups folder](#).
For [remote users](#), you can also open the **Remote Users** folder in the **SQL Remote** folder.
- ◆ Select the desired user or group.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Authorities, [Membership](#), [Permissions](#), [SQL Remote](#), Statistics

Notes:

- ◆ You cannot change the name of a existing user or group. Instead, you must delete it and create a new user or group with the new name and same properties.
-

[Related Topics](#)

Joining groups

Users and groups can belong to one or more other groups.

To add a **user** or **group** to another group:

- ◆ Open the [user/group's property sheet](#).
- ◆ Click the **Membership** tab.
- ◆ Click **Join Group** to open the selection dialog.
- ◆ Select the desired groups, then click **Join Group**.

Notes:

- ◆ You can quickly add users or groups to other groups by dragging and dropping.
{button ,PI('^>howto','IDH_scsa_user_group_join_drag')} [How?](#)
- ◆ You can also add users or groups to other groups by copying and pasting them.
{button ,PI('^>howto','IDH_scsa_user_group_join_copy')} [How?](#)
- ◆ You cannot join a group twice. If you try to do this using drag-and-drop or copy/paste, you will get a "primary key for table 'SYSGROUP' is not unique" error.

[Related Topics](#)

Joining groups by dragging and dropping

To add users or groups to other groups by [dragging and dropping](#):

- ◆ In the right panel, select the users and groups to add.
- ◆ Drag the users and groups to the left panel and drop them onto the destination group.

Joining groups by copying and pasting

To add users or groups to other groups by copying and pasting:

- ◆ Select the desired users and groups.
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the destination group.
- ◆ Click **Paste**.

Leaving groups

To remove a **user** or **group** from another group:

- ◆ Open the [user/group's property sheet](#).
- ◆ Click the **Membership** tab.
- ◆ Select the group to leave, then click **Leave Group**.

You can also remove users/groups from another group directly from the group's **container**:

- ◆ In the **Users & Groups** folder, open the group that you want to remove your users or groups from.
- ◆ In the right panel, select the users and groups to remove.
- ◆ Click **Leave Group** in the **File** menu or [pop-up menu](#)

Notes:

- ◆ Removing a user or group from a group does **not** delete them from the database (or from other groups). To do this, you must [delete the user/group](#) from the **Users & Groups** folder itself.

[Related Topics](#)

Setting object permissions for a user/group

To manage the **permissions** of a **user or group** on objects:

- ◆ Open the [property sheet](#) of the user or group.
- ◆ Click the **Permissions** tab.
- ◆ Select the type of object to **View permissions on** (tables, views, or procedures).
- ◆ In the list, select the objects to set permissions on.
- ◆ Set the various permissions and [grant options](#).
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

Notes:

- ◆ In the user/group property sheet, you cannot set specific column permissions. To do this, you must use the [table's property sheet](#).
- ◆ To assign permissions to many users and groups at once, use the object's property sheet. To assign permissions to many objects at once, use the user's property sheet.
- ◆ You can quickly assign full permissions on a given object by [dragging and dropping](#) users and groups onto it (or by dragging the object itself onto a user or group).
- ◆ You can also assign full permissions by copying and pasting.
{button ,PI('>howto','IDH_scsa_user_group_permissions_copy')} [How?](#)
- ◆ You should manage user permissions by assigning permissions to groups, then adding users to a group to give them the group's permissions.
- ◆ If you're using [SQL Remote](#) replication, you can also grant and revoke [publisher permissions](#) and [remote permissions](#) for a user.

[Related Topics](#)

Copying and pasting for user/group permissions

You can assign full permissions on a given table, view, or procedure by copying and pasting:

- ◆ Select the desired users and groups (or objects).
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the destination object (or user/group).
- ◆ Click **Paste**.

Setting options for a user or group

To set options for a user or group:

- ◆ Open the [Users & Groups folder](#).
- ◆ Select the desired user or group.
- ◆ Click **Set Options** in the **File** menu or [pop-up menu](#).
- ◆ Edit the desired values.
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

Notes:

- ◆ You can also set database options for the [entire database](#).
- ◆ In Sybase Central, you can set [database options](#) (including compatibility options and replication options), but you cannot set ISQL options.

[Related Topics](#)

Deleting users and groups

To delete **users** or **groups** from the database:

- ◆ Open the [Users & Groups folder](#).
- ◆ Select the desired users and groups.
- ◆ Click **Delete** in the **File** menu.
{button ,PI('>howto','IDH_sc_object_delete')} [Other ways](#)

Notes:

- ◆ Deleting a user or group also deletes all database objects (e.g. tables) that they own.
- ◆ You cannot delete users or groups when you select them in a group subfolder.
- ◆ Deleting users or groups from the database is different from [removing](#) them from other groups.
- ◆ Deleting a group from the database does **not** delete its members from the database, although they lose membership in the deleted group.

[Related Topics](#)

Showing user-defined data types in a database

To show the **user-defined data types** in a database:

- ◆ Open the [desired database](#).
- ◆ Open the **User-defined Data Types** folder.

Notes:

- ◆ For a given database, you can choose to [show or hide system user defined data types](#) .

[Related Topics](#)

Creating a new user-defined data type

To create a new **user-defined data type** in a database:

- ◆ Open the [User-defined Data Types folder](#).
- ◆ In the right panel, double-click **Add User-defined Data Type**.
{button ,PI(^>howto',`IDH_sc_create_object')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Once you've created a user-defined data type, you can [assign](#) it to columns in the database.

[Related Topics](#)

Inspecting properties of a user-defined data type

To inspect the properties of a **user-defined data type** in a database:

- ◆ Open the [User-defined Data Types folder](#).
- ◆ Select the desired user-defined data type.
- ◆ Click **Properties** in the **File** menu.
{button ,PI('^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Inspect the desired properties.
{button ,PI('^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Check Constraint

Notes:

- ◆ To change a user-defined data type, you must delete and recreate it.
-

[Related Topics](#)

Deleting user-defined data types

To delete one or more **user-defined data types** from a database:

- ◆ Open the [User-defined Data Types folder](#).
- ◆ Select the desired types.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_object_delete')} [Other ways](#)

Notes:

- ◆ You cannot delete a user-defined data type that is being used by columns in the database.
If you try to do this, you will get a "primary key for row in table <name> is referenced in another table" error.

[Related Topics](#)

Managing the Service Manager

The SQL Anywhere Service Manager allows you to start, stop, edit, pause, add, or remove a SQL Anywhere Service from your workstation. A service will continue to run even after you have logged out of your workstation.

[Adding a Service](#)

[Editing a Service](#)

[Starting and Stopping a Service](#)

[More Information about Services](#)

Adding a Service

To create a new service:

- ◆ Open the Services folder.
- ◆ In the right panel double click **Add New Service**
- ◆ Follow the instructions of the [wizard](#)

[Related Topics](#)

Editing a Service

To edit a service:

- ◆ Open the Services folder.
- ◆ In the right panel, double click the service that you wish to edit.
- ◆ The properties window will display. The service may be edited from the tabs displayed here.

[Related Topics](#)

Starting and Stopping a Service

To start a Service:

- ◆ Open the Services folder.
- ◆ In the right panel, right click on the service that you wish to start.
- ◆ Select start from the menu listing.

To stop a Service:

- ◆ Open the Services folder.
- ◆ In the right panel, right click on the service that you wish to stop.
- ◆ Select stop from the menu listing.

[Related Topics](#)

Managing SQL Remote replication in Sybase Central

Sybase Central allows you to set up a [SQL Remote](#) replication between a [consolidated database](#) and one or more [remote databases](#). All setup is done at the consolidated database, usually before extracting the remote databases from it.

To set up a SQL Remote replication using Sybase Central:

- ◆ [Connect to the consolidated database](#) using a user account with [DBA authority](#).
- ◆ [Set the publisher](#) of the consolidated database.
- ◆ For the [message systems](#) that you will be using (e.g. MAPI), [edit the corresponding message types](#) to include your publisher's address.
- ◆ [Create new remote users](#), or [grant remote permissions to existing users](#).
- ◆ [Create publications](#) based on the tables that you want to replicate.
- ◆ [Subscribe](#) the appropriate remote users to the appropriate publications.
- ◆ [Extract the remote databases](#) from the consolidated database using the extraction wizard.
- ◆ [Deploy](#) each remote database.

To help you maintain an existing SQL Remote replication setup, Sybase Central supports SQL Remote's [passthrough mode](#).

Notes:

- ◆ For a full discussion of SQL Remote replication, see the [SQL Anywhere User's Guide](#).

[Related Topics](#)

Showing publications in a database

To show the **publications** in a database:

- ◆ Open the [desired database](#).
- ◆ Open the **SQL Remote** folder.
- ◆ Open the **Publications** subfolder.

[Related Topics](#)

Creating a new publication

To create a new **publication** in a database:

- ◆ Open the [Publications folder](#).
- ◆ In the right panel, double-click **Add Publication**.
{button ,PI(^>howto',`IDH_sc_create_object')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ Once you have created a new publication, you can:
 - manage its [articles](#)
 - [subscribe users](#) to it

[Related Topics](#)

Editing properties of a publication

To edit the properties of a **publication** in a database:

- ◆ Open the [Publications folder](#).
- ◆ Select the desired publication.
- ◆ Click **Properties** in the **File** menu.
{button ,PI('>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Articles, [Subscriptions](#)

Notes:

- ◆ To [create](#), [edit](#), or [delete](#) articles, you must [show](#) them in the main window.
-

[Related Topics](#)

Showing articles in a publication

To show the **articles** in a **publication**:

- ◆ Open the [Publications folder](#).
- ◆ Open the desired publication.

Notes:

- ◆ The articles of a publication are also shown on the **Articles** page of its [property sheet](#).

[Related Topics](#)

Creating a new article

To create a new article in a publication:

- ◆ In the [Publications folder](#), open the desired publication.
- ◆ In the right panel, double-click **Add Article**.
{button ,PI(^>howto','IDH_sc_create_object')} [Other ways](#)
- ◆ In the [property sheet](#), enter the desired values.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Notes:

- ◆ You can quickly create new articles in a given publication by [dragging and dropping](#) tables (from the same database) onto the publication. For each table, this automatically opens a new article property sheet with the table pre-selected.
- ◆ You can also create new articles by copying and pasting tables.
{button ,PI(^>howto','IDH_scsa_article_create_copy')} [How?](#)

[Related Topics](#)

Creating new articles by copying and pasting

You can create new articles by copying and pasting tables:

- ◆ Select the desired tables.
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Open the destination publication, then click an empty spot in the right panel.
- ◆ Click **Paste**.

For each table, this automatically opens a new article property sheet with the table pre-selected.

Editing properties of an article

To edit the properties of an article:

- ◆ In the [Publications folder](#), open the desired publication.
- ◆ Select the desired article.
- ◆ Click **Properties** in the **File** menu.
{button ,PI('^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI('^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Table, Where Restriction, Subscribe Restriction

[Related Topics](#)

Editing properties of an article's table

To edit the properties of the table that an **article** is based on, do one of the following:

- ◆ On the **General** page of the [article's property sheet](#), click **Table Properties**.
- ◆ In the right panel, select the desired article, then click **Table Properties** in the **File** menu or [pop-up menu](#).

This opens the [table's property sheet](#), ready for editing.

[Related Topics](#)

Deleting articles

To delete one or more **articles** from a **publication**:

- ◆ Open the [Publications folder](#).
- ◆ Open the desired publication.
- ◆ Select the desired articles.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto','IDH_sc_object_delete')} [Other ways](#)

Notes:

- ◆ Deleting an article does **not** delete the table on which the article was based.

[Related Topics](#)

Managing subscriptions for a publication

To manage **subscriptions by remote users** to a publication:

- ◆ Open the [publication's property sheet](#).
- ◆ Click the **Subscriptions** tab.

You can **subscribe a remote user** to the publication.

{button ,PI('>howto','IDH_scsa_publication_subscribe_details')} [How?](#)

You can **unsubscribe remote users** from the publication.

{button ,PI('>howto','IDH_scsa_publication_unsubscribe_details')} [How?](#)

You can also manually **start, stop, or synchronize** subscriptions to the publication.

{button ,PI('>howto','IDH_scsa_publication_subscribe_advanced_details')} [How?](#)

Notes:

- ◆ You can quickly subscribe remote users to a publication by [dragging and dropping](#) them onto the publication. This opens a subscription dialog for each dropped user.
- ◆ You can also subscribe remote users by copying and pasting.
{button ,PI('>howto','IDH_scsa_publication_subscribe_copy')} [How?](#)

[Related Topics](#)

Subscribing users to the publication

To subscribe a remote user to the publication:

- ◆ Open the subscription dialog by doing one of the following:
 - On the **Subscriptions** page of the property sheet, click **Subscribe For**.
 - In the main window, select the desired publication, then click **Subscribe For** in the **File** menu or [pop-up menu](#).
- ◆ Enter the desired values.
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

Unsubscribing users from the publication

To unsubscribe remote users from the publication:

- ◆ On the **Subscriptions** page, select the desired users from the list.
- ◆ Click **Unsubscribe**.

Subscribing users by copying and pasting

You can subscribe remote users to a publication by copying and pasting them onto the publication:

- ◆ Select the desired users and groups.
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or toolbar button).
- ◆ Select the desired publication, then click an empty spot in the right panel.
- ◆ Click **Paste**.

This opens a subscription dialog for each user.

Starting/stopping/synchronizing for publications

To **manually** start, stop, or synchronize subscriptions to the publication:

- ◆ On the **Subscriptions** page of the property sheet, select the desired remote users from the list.
- ◆ Click **Advanced**.
- ◆ Click **Start Now**, **Stop Now**, or **Synchronize Now**.

The subscriptions are affected as soon as you click one of these buttons. Subsequently clicking **Cancel** in the publication's property sheet will **not** cancel your advanced actions on the subscriptions.

Deleting publications

To delete one or more **publications** from a database:

- ◆ Open the [Publications folder](#).
- ◆ Select the desired publications.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto',`IDH_sc_object_delete')} [Other ways](#)

Notes:

- ◆ If you delete a publication, all [subscriptions](#) to that publication are automatically deleted as well.

[Related Topics](#)

Showing users of SQL Remote in a database

To show the users involved in **SQL Remote** replication in a database:

- ◆ Open the [desired database](#).
- ◆ Open the **SQL Remote** folder.
This folder contains the [publisher](#) of the database.
- ◆ Open the **Remote Users** subfolder.
This folder contains all [remote users](#) of the database.

Notes:

- ◆ Users of SQL Remote are shown in both the **Users & Groups** folder (along with normal users) and by themselves in the **SQL Remote** folder.

[Related Topics](#)

Creating a new remote user

To create a new **remote user** in a database:

- ◆ Open the [Remote Users folder](#).
- ◆ In the right panel, double-click **Add Remote User**.
{button ,PI(^>howto',`IDH_sc_create_object`)} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You cannot create a new remote user until you define at least one [message type](#) in the database.
- ◆ By default, remote users are created with [remote DBA authority](#). Since this authority is required by the [message agent](#) for access to the remote database, you shouldn't revoke it.
- ◆ You can also [convert existing users](#) into remote users.
- ◆ Once you have created a new remote user, you can:
 - [add](#) it to other groups
 - set its [object permissions](#) (on tables, views, and procedures)
 - [subscribe](#) it to publications
 - [revoke](#) its remote permissions

[Related Topics](#)

Editing properties of a remote user

[Remote users](#) have the same properties as normal users and groups, and they also have additional [SQL Remote](#) properties.

To edit the SQL Remote properties of a remote user:

- ◆ Open the [user's property sheet](#).
- ◆ On the **Authorities** page, **Remote DBA authority** is checked. Since this [authority](#) is necessary for most replication functions, you should not revoke it.
- ◆ On the **SQL Remote** page, you can:
 - manage the [user's subscriptions](#) to publications
 - edit other replication-related properties.

{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Authorities, [Membership](#), [Permissions](#), SQL Remote, Statistics

[Related Topics](#)

Granting remote permissions to users

To grant [remote permissions](#) to normal users and groups (making them [remote users](#) in a [SQL Remote](#) replication setup):

- ◆ Open the [Users & Groups folder](#).
- ◆ Select the desired users and groups.
- ◆ Click **Set Remote** in the **File** menu.
{button ,PI(^>howto','IDH_scsa_remote_user_grant_other_ways')} [Other ways](#)
- ◆ For each user or group, a remote-properties dialog appears.
Enter the desired values.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Once you have granted remote permissions to a user or group, you can:

- ◆ [subscribe](#) it to publications
- ◆ [revoke](#) its remote permissions

Notes:

- ◆ You cannot grant remote permissions to a user or group until you define at least one [message type](#) in the database.
- ◆ While you can grant remote permissions to a group, those remote permissions do **not** automatically apply to users in the group (unlike table permissions, for example). To do this, you must explicitly grant remote permissions to each user in the group.
Otherwise, remote groups behave exactly like remote users (and are categorized as remote users).
- ◆ You can also create [new remote users](#) from scratch.

[Related Topics](#)

Ways of granting remote permissions

To grant remote permissions to users and groups, do any of the following:

- ◆ Select the desired users and groups, then click **Set Remote** in the **File** menu or [pop-up menu](#).
- ◆ [Drag and drop](#) the users and groups onto the **Remote Users** folder in the **SQL Remote** folder.
- ◆ **Copy** and **Paste** the users into the **Remote Users** folder.
{button ,PI(>howto',`IDH_scsa_remote_user_grant_copy')} [How?](#)

Granting remote permissions by copying and pasting

To grant remote permissions to users and groups by copying and pasting:

- ◆ Select the desired users and groups.
- ◆ Click **Copy** (using the **Edit** menu, [pop-up menu](#), or [toolbar](#) button).
- ◆ Select the **Remote Users** folder, then click an empty spot in the right panel.
- ◆ Click **Paste**.

Revoking remote permissions from users

To revoke **remote permissions** from **remote users** (making them normal users or groups):

- ◆ Open the [Users & Groups folder](#) or the [Remote Users folder](#) in the **SQL Remote** folder.
- ◆ Select the desired remote users.
- ◆ Click **Revoke Remote** in the **File** menu or [pop-up menu](#).

Notes:

- ◆ Revoking remote permissions for a remote user automatically [unsubscribes](#) that user from all [publications](#).

[Related Topics](#)

Managing subscriptions for a remote user

To manage **subscriptions to publications** for a remote user:

- ◆ Open the [remote user's property sheet](#).
- ◆ Click the **SQL Remote** tab.

You can **subscribe the remote user** to a publication.

{button ,PI('>howto','IDH_scsa_remote_user_subscribe_details')} [How?](#)

You can **unsubscribe the remote user** from publications.

{button ,PI('>howto','IDH_scsa_remote_user_unsubscribe')} [How?](#)

You can also manually **start, stop, or synchronize** subscriptions for the remote user.

{button ,PI('>howto','IDH_scsa_remote_user_subscribe_advanced_details')} [How?](#)

Notes:

- ◆ You can quickly subscribe remote users to a publication by [dragging and dropping](#) them onto the publication. This opens a subscription dialog for each dropped user.
- ◆ You can also subscribe remote users by copying and pasting.
{button ,PI('>howto','IDH_scsa_publication_subscribe_copy')} [How?](#)

[Related Topics](#)

Subscribing the user to a publication

To subscribe the remote user to an existing publication:

- ◆ Open the subscription dialog by doing one of the following:
 - On the **SQL Remote** page of the property sheet, click **Subscribe To**.
 - In the main window, select the desired remote user, then click **Subscribe To** in the **File** menu or [pop-up menu](#).
- ◆ Enter the desired values.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Unsubscribing the user from publications

To unsubscribe the remote user from existing publications:

- ◆ On the **SQL Remote** page of the property sheet, select the desired publications from the list.
- ◆ Click **Unsubscribe**.

Starting/stopping/synchronizing for remote users

To **manually** start, stop, or synchronize subscriptions for the remote user:

- ◆ On the **SQL Remote** page, select the desired publications from the list.
- ◆ Click **Advanced**.
- ◆ Click **Start Now**, **Stop Now**, or **Synchronize Now**.

The subscriptions are affected as soon as you click one of these buttons. Subsequently clicking **Cancel** in the remote user's property sheet will **not** cancel your advanced actions on the subscriptions.

Setting the publisher of a database

To set an existing user or group as the **publisher** of a database:

- ◆ Open the [desired database](#).
- ◆ Open the **SQL Remote** folder.
- ◆ In the right panel, double-click **Set Publisher**.
{button ,PI(>howto','IDH_scsa_publisher_set_other_ways')} [Other ways](#)
- ◆ In the publisher dialog, select the desired user or group.

Once a publisher exists, you can revoke their publisher permission.
{button ,PI(>howto','IDH_scsa_publisher_revoke')} [How?](#)

[Related Topics](#)

Other ways to set the publisher

To change the publisher from the [database's property sheet](#):

- ◆ Click the **SQL Remote** tab.
- ◆ Beside the current publisher, click **Change**.

If there is no current publisher, you can set the publisher directly from the **Users & Groups** folder by doing one of the following:

- ◆ Select a non-remote user or group, then click **Set As Publisher** in the **File** menu or [pop-up menu](#).
- ◆ When creating a [new user or group](#), select the **Publisher** option in the creation wizard.

Revoking publisher permission

To revoke publisher permission from the current publisher:

- ◆ Select the publisher in the **Users & Groups** folder or **SQL Remote** folder.
- ◆ Click **Revoke Publisher** in the **File** menu or [pop-up menu](#).

Extracting a database for a remote user

To **extract a remote database** for a particular remote user:

- ◆ Open the [desired consolidated database](#).
- ◆ Open the **Users & Groups** folder, or the **Remote Users** folder in the **SQL Remote** folder.
- ◆ Select the desired remote user.
- ◆ Click **Extract Database** in the **File** menu or [pop-up menu](#).
- ◆ Follow the instructions of the [wizard](#).

Notes:

- ◆ You can also invoke the extraction wizard directly [from a consolidated database](#).

[Related Topics](#)

Deleting users of SQL Remote

You cannot delete a [publisher](#) or [remote user](#) directly from the [SQL Remote](#) folder - you can only revoke their [publisher permission](#) or [remote permission](#) (respectively).

To delete a publisher or remote user from a database, you must select it in the main **Users & Groups** folder and [delete](#) it from there.

[Related Topics](#)

Showing message types in a database

To show the **message types** for **SQL Remote** replication in a database:

- ◆ Open the [desired database](#).
- ◆ Open the **SQL Remote** folder.
- ◆ Open the **Message Types** subfolder.

[Related Topics](#)

Creating a new message type

To create a new **message type** for **SQL Remote** replication in a database:

- ◆ Open the [Message Types folder](#).
- ◆ In the right panel, double-click **Add Message Type**.
{button ,PI(^>howto','IDH_sc_create_object')} [Other ways](#)
- ◆ In the [property sheet](#), enter the desired values.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

[Related Topics](#)

Editing properties of a message type

To edit the properties of a message type for SQL Remote replication:

- ◆ Open the [Message Types folder](#).
- ◆ Select the desired message type.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General

Notes:

- ◆ You cannot change the name of a existing message type. Instead, you must delete it and create a new message type with the new name.

[Related Topics](#)

Deleting message types

To delete one or more message types from a database:

- ◆ Open the [Message Types folder](#).
- ◆ Select the desired message types.
- ◆ Click **Delete** in the **File** menu.
{button ,PI(^>howto', 'IDH_sc_object_delete')} [Other ways](#)

Notes:

- ◆ You cannot delete a message type if it is being used by a remote user in the database. If you try to do this, you will get a "message type <name> not found" error.

[Related Topics](#)

Starting a SQL Remote replication (extracting)

Once you have set up your [publications](#) and users for [SQL Remote](#), and [subscribed](#) them appropriately, you can [extract](#) the [remote databases](#) from the [consolidated database](#) and start the replication.

To extract a remote database from a consolidated database:

- ◆ Open the [consolidated database](#).
- ◆ In the **Sybase SQL Anywhere** folder, open the **Utilities** folder.
- ◆ Double-click **Extract Remote Database**.
{button ,PI('>howto','IDH_sc_wizard_start')} [Other ways](#)
- ◆ Follow the instructions of the [wizard](#).

Sybase Central then completes the extraction process.

{button ,PI('>howto','IDH_scsa_SQL_Remote_extract_details')} [How?](#)

You can then [deploy](#) the remote database.

Notes:

- ◆ If you use the wizard to extract a non-running database, it will only be able to unload the structure and data for you. It will not be able to create the remote database and reload it.
For this reason, we recommend that you always extract from a consolidated database that you are connected to in Sybase Central.
- ◆ You can also invoke the extraction wizard [for a particular database](#) or [for a particular remote user](#) - Sybase Central automatically fills in the appropriate entries in the wizard.
- ◆ The extraction wizard always extracts (synchronizes) the remote database using the WITH SYNCHRONIZATION option. In those rare cases where you don't want to use this option, you must use the [DBXTRACT](#) command-line utility instead.

[Related Topics](#)

Sybase Central's extraction process

When you complete the extraction wizard, it does the following on your machine:

- ◆ creates the remote database
- ◆ extracts (unloads) the relevant structures and/or data from the consolidated database to files
- ◆ loads those files into the newly created remote database

Deploying a remote database

Once you've extracted a [remote database](#) from the [consolidated database](#), you can then deploy the remote database by:

- ◆ moving it to a remote machine (via network or removable media)
- ◆ ensuring that the remote machine is able to communicate with the consolidated machine

[Related Topics](#)

Using passthrough mode with remote databases

To help you maintain an existing [SQL Remote](#) replication setup, Sybase Central supports [passthrough mode](#). This ensures that structural changes that you subsequently make to the consolidated database (such as changing a table's structure) are mirrored in its deployed remote databases.

To [pass through](#) SQL statements from a [consolidated database](#) to [remote databases](#):

- ◆ Open the [consolidated database](#).
- ◆ Select the [remote users](#) for the passthrough
or,
select the [publications](#) whose [subscribers](#) should get the passthrough.
- ◆ Click **Passthrough** in the **File** menu or [pop-up menu](#).
- ◆ In the passthrough dialog, use the controls to start (or stop) passthrough mode for the users and publications.
{button ,PI(>howto','IDH_sc_help_whats_this')} [How?](#)

When passthrough mode is active, Sybase Central appends **Passthrough** to the consolidated database's name in the left and right panels of the main window.

Notes:

- ◆ You can also stop passthrough mode for **all** users and publications directly from the [database's property sheet](#).

[Related Topics](#)

Showing spaces in a database

To show the **database spaces** for a database:

- ◆ Open the [desired database](#).
- ◆ Open the **DB Spaces** folder.

[Related Topics](#)

Creating a new database space

To create a new **database space** in a database:

- ◆ Open the [DB Spaces folder](#).
- ◆ In the right panel, double-click **Add DB Space**.
{button ,PI(^>howto','IDH_sc_create_object')} [Other ways](#)
- ◆ In the [property sheet](#), enter the desired values.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

[Related Topics](#)

Editing properties of a space

To edit the properties of a **database space**:

- ◆ Open the [DB Spaces folder](#).
- ◆ Select the desired space.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Edit the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General

[Related Topics](#)

Deleting database spaces

To delete one or more **database spaces** from a database:

- ◆ Open the [DB Spaces folder](#).
- ◆ Select the desired spaces.
- ◆ Click **Delete** in the **File** menu.
{button ,PI('>howto', 'IDH_sc_object_delete')} [Other ways](#)

Notes:

- ◆ Before you can delete a space, you must delete all tables that use the space.

[Related Topics](#)

Showing users connected to a database

To show all **users** connected to a **database**:

- ◆ Open the [desired database](#).
- ◆ Open the **Connected Users** folder.

This shows all other users currently connected to a given database (**not** including yourself), regardless of the client that they used to connect (Sybase Central, [ISQL](#), a custom client application, etc.).

Notes:

- ◆ You can also show all users and groups that have [permission to connect](#) to a database.

[Related Topics](#)

Inspecting properties of a connected user

To inspect the properties of a **user's** connection to a **database**:

- ◆ Open the [Connected Users folder](#).
- ◆ Select the desired connected user.
- ◆ Click **Properties** in the **File** menu.
{button ,PI(^>howto','IDH_sc_open_property_sheet')} [Other ways](#)
- ◆ Inspect the desired properties.
{button ,PI(^>howto','IDH_sc_help_whats_this')} [How?](#)

Property pages:

General, Statistics

Notes:

- ◆ You can also inspect statistics [for the server](#) and [for individual tables](#).
-

[Related Topics](#)

Disconnecting connected users

To disconnect other users from a database:

- ◆ Open the [Connected Users folder](#).
- ◆ Select the connected users to disconnect.
- ◆ Click **Disconnect** in the **File** menu or [pop-up menu](#).

Notes:

- ◆ You can also [disconnect yourself](#) (in Sybase Central) from a given database.

[Related Topics](#)

Summary of drag-and-drop operations

You can do the following SQL Anywhere operations by dragging and dropping objects:

- ◆ [adding statistics](#) to the performance monitor
- ◆ [extracting, backing up,](#) and [unloading](#) a database
- ◆ [copying columns](#) within/between tables
- ◆ [creating foreign keys](#) between tables
- ◆ [copying tables, views,](#) and [procedures](#) within/between databases
- ◆ [adding users and groups](#) to other groups
- ◆ granting user [permissions for tables, views,](#) and [procedures](#)
- ◆ [creating new articles](#) in a publication
- ◆ [subscribing remote users](#) to a publication
- ◆ granting [remote permissions](#) to users
- ◆ moving text around in the [code editor](#)

[Related Topics](#)

SQL Anywhere help is not available

The main help file for Sybase SQL Anywhere (**DBENG50W.HLP**) is not installed.

Some OEM versions of SQL Anywhere (including the version bundled with PowerBuilder) do not include this file.

Please refer to your printed SQL Anywhere manuals, or in the case of PowerBuilder, refer to the PowerBuilder on-line documentation.

Designed and written by Dave O'Brien

Help version: 5.5.0.1

Last revised: 11/22/96 10:26 AM

Editing an object's code

To edit an object's code, do one of the following:

- ◆ Select the desired object, then click an **Open As** command in the **File** menu or [pop-up menu](#).
- ◆ Double-click the object.

This opens a code-editor window and displays the object's code.

Line Graph

Displays a continuous line graph that scrolls right to left as statistics are updated.

[More Help](#)

Bar Graph

Displays a stationary bar graph where each bar shows that statistic's most recent value.

[More Help](#)

Remove Statistic

Removes the selected statistic from the performance monitor.

[More Help](#)

Properties

Opens the selected statistic's display [property sheet](#).

[More Help](#)

Table Name

Provides a place for you to name (or rename) the table.

[More Help](#)

Table Creator

For new tables, this allows you to select an owner for the table.

For existing tables, this shows the owner of the table (and cannot be changed).

[More Help](#)

Add Column

Adds a new, empty row at the bottom of the table editor for defining a new table column.

[More Help](#)

Delete Column

Deletes the currently selected table column from the table editor.

[More Help](#)

Advanced Column Properties

Opens a dialog for editing advanced properties of the selected table column.

[More Help](#)

Advanced Table Properties

Opens a dialog for setting the table's type ([base table](#) or [global temporary table](#)).
The table type cannot be changed once the table has been created in the database.

[More Help](#)

Save Table

Saves (commits) your changes to this table.


[More Help](#)

Save and Close


Saves (commits) your changes to this table, then closes the table editor.

[More Help](#)

A database that you are connected to in Sybase Central.

A connected database is represented by the  icon, and shows its contents as an [object tree](#) under the database. See also [disconnected database](#).

A running database that is visible in Sybase Central (that is, running on a visible server), but that you are not connected to in Sybase Central.

A disconnected database is represented by the  icon.

Most database operations in Sybase Central require you to be connected to the database. You cannot see the [object tree](#) under a database until you connect to it using Sybase Central.

See also [connected database](#).

Provides a place for you to type the [password](#) of the SQL Anywhere [user](#).
For security, the typed characters are shown as asterisks.

[More Help](#)

Provides a place for you to type the [database name](#).

If you are starting a database, you can specify a new name for the database to run as.

If you don't enter a name, it defaults to the [database file](#) name without the **.DB** extension.

Example: **SADEMO** (for the **SADEMO.DB** sample database)

[More Help](#)

Provides a place for you to type the full path and name of the SQL Anywhere [database file](#) or [write file](#) on the server PC.

Example: **C:\SQLANY50\WSAMPLE.DB**

You can also click **Browse** to locate the file.

Note: To specify a database file on a PC other than the server, you must use a [UNC](#) filename.

[More Help](#)

Opens a standard file dialog to help you locate a [database file](#) or [write file](#) on your local PC.
[More Help](#)

Shuts down the database when the last [connection](#) to it is closed.

Note: This is different from the **-ga** engine switch (which auto-stops the database engine itself).

Provides a place for you to type the name of the new object.
By default, the new name is the original name with **_copy** appended.

Allows you to select the database user who will own the new object.

Allows you to select a [user](#) to be the creator of the new object.

Shows all [users](#) defined in the database.

Exits the dialog and sets the selected user as the creator of the new object.

The [table](#) that this object belongs to.

The database user who created (and owns) this object.

The SQL dialect in which the code was last saved.
Supported dialects: [Watcom-SQL](#), [Transact-SQL](#)

A unique number assigned by the server to each database that is started on it.
This makes it possible to distinguish between two instances of the same database running on the same server.

Provides a place for you to type a [comment](#) (text description) of this object.
For example, you could use this area to describe the object's purpose in the system.

Allows you to grant [permissions](#) on this object to other [users](#).

Exits this dialog and grants [permissions](#) to the selected [users](#).

Revokes [permissions](#) on this object from the selected [users](#).

The SUBSCRIBE BY column or clause.

If the articles in the publication use SUBSCRIBE BY columns that have different names, the column of the first article is displayed, followed by the other column names in brackets, separated by vertical bars.

Example: **province (prov | territory)**

Provides a place for you to type the value of the SUBSCRIBE_BY column or clause for the remote user.

The name of the [subscription](#) that you are starting, stopping, or [synchronizing](#).

The current state of the [subscription](#) (**Started** or **Not started**).

Starts the [subscription](#) manually.

Stops the [subscription](#) (if it has already been started).

Synchronizes the subscription manually.

Shows database options and replication options for the current user (or, for the database as a whole, the PUBLIC group).



Options that default to the PUBLIC setting



Options overridden for this user

[More Help](#)

The PUBLIC group's setting for the selected option.

[More Help](#)

Determines whether this user will use their own setting instead of the PUBLIC group's setting for the selected option.

[More Help](#)

Provides a place for you to type this user's value for the selected option.
The user will use this value instead of the PUBLIC group's value for the selected option.

[More Help](#)

Immediately sets the selected option to the new value.
This change lasts between sessions until explicitly changed again.

[More Help](#)

Immediately sets the selected option to the new value.

Temporary values only last for this SQL Central session.

You can only set temporary values for database options (not replication options), and only for the current SQL Central user (the user who you connected as in SQL Central).

[More Help](#)

Resets the selected option to the last-set value.

[More Help](#)

Opens the options dialog for the PUBLIC group.

This is handy if you decide that you want to change the PUBLIC setting (for everyone) instead of just setting it for a single user.

[More Help](#)

The name of the [server](#) to start the database on.

[More Help](#)

Starts the database on the server.

[More Help](#)

Shows all [remote_users](#) and [publications](#) currently in [passthrough](#) mode (indicated by their **On** state).

Also shows any remote users or publications that you selected to add to the passthrough (indicated by their **Off** state).

[More Help](#)

Sets the selected [remote users](#) and [publications](#) to start [passthrough](#) mode (when you click **OK** to exit this dialog).
[More Help](#)

Sets the database to stop [passthrough](#) mode for all of its objects (when you click **OK** to exit this dialog).

[More Help](#)

For a new [passthrough](#) session, this sets the mode to PASSTHROUGH ONLY (changes are made only in the [remote databases](#), not in the [consolidated database](#)).

[More Help](#)

The version number of the SQL Anywhere database. (Versions before 5.0 are Watcom SQL databases.)

The [root database file](#) for the database (also represented by the SYSTEM [database space](#)).

The [transaction log file](#) for the database.

The [transaction_log_mirror_file](#) for the database.

The page size of the database (in bytes).

Determines whether this database is [encrypted](#).

Determines whether this database [ignores trailing blanks](#) in comparisons.

Determines whether this database is case-sensitive.

The default [collation](#) of the database.

The [connection_ID](#) of SQL Central's connection to the database.

The total number of current connections to this database from all users (including SQL Central's connection).

The [publisher](#) of the database.

Allows you to select a [user](#) or [group](#) to be the database's [publisher](#).

Shows the non-remote [users](#) of this database.

Exits this dialog and sets the selected user or group as the publisher of the database.

The [consolidated_database](#) of this database (if this database is acting as a [remote_database](#)).

The number of [remote_users](#) [subscribing](#) to [publications](#) in this database.

The number of [subscriptions](#) by [remote_users](#) to [publications](#) in this database.

The number of [subscriptions](#) in this database that have been started.

Allows you to control [passthrough](#) mode for the database.

For new tables, this allows you to select the creator (owner) of the table.
For existing tables, this shows the owner of the table (you cannot change this).

[More Help](#)

Shows the following about the columns in this table:

Key	Click not-null column to add/remove it in primary key Shift-click to move down in key order Shift-Ctrl-click to move up in key order
Column Name	Edit the name of the column
Data Type	Select a data type for the column
Size/Prec.	Edit the size or precision (if any)
Scale	Edit the scale (if any) of the column
Allow Nulls	Set the nullability as allow null or not null
Comment	Edit the comment for the column

You can double-click a column for **Advanced Column Properties**.

You can add a column by pressing **Ins**, or delete one by pressing **Ctrl-Del**.

You can right-click for a pop-up menu of relevant commands.

[More Help](#)

Sets this table as a [base table](#).

You cannot change this setting for existing tables.

[More Help](#)

Allows you to select the [database space](#) used by the [table](#).
[More Help](#)

Sets this table as a [global temporary table](#).
You cannot change this setting for existing tables.
[More Help](#)

Sets the [global temporary table](#) to **delete** its [rows](#) when a COMMIT is executed.
[More Help](#)

Sets the [global temporary table](#) to **preserve** its [rows](#) when a COMMIT is executed.
[More Help](#)

The [database space](#) used by the [table](#).

Shows whether the rows of the global temporary table are deleted or preserved when a COMMIT is executed.

Shows the [columns](#) defined for the [table](#) (listed by column name and data type).
[Primary-key](#) columns are represented by different icons.

Adds the selected columns to the primary key of the table.

Removes the selected columns from the primary key of the table.

Removes all columns from the primary key of the table.

The order of columns in the primary key.

This is the order in which you added the columns to the key. To change the order, remove some or all of the columns and re-add them to the key.

The data type of the column.

The default value of the column.

The comment for the column.

Shows whether the values of this column in the [table's rows](#) must be unique.

The nullability of the column.

Shows the [unique constraints](#) defined for the [table](#).

Allows you to create a new [unique constraint](#) for the [table](#).

Shows all [columns](#) defined in the [table](#) (listed by column name and data type).

Adds the selected [columns](#) to the [unique constraint](#) (in list order).

Removes the selected [columns](#) from the [unique constraint](#).

Removes all columns from the unique constraint.

The order of columns in the unique constraint.

Removes the selected [unique constraint](#) from the [table](#).

Provides a place for you to type the [check constraint](#) on the [table](#).

This text box offers the same syntax highlighting and drag-and-drop features used in the [code editor](#).

Shows all [users](#) who have [permissions](#) on the [table](#).

Permissions: **A**=Alter, **D**=Delete, **I**=Insert, **R**=Reference, **S**=Select, **U**=Update

Permissions that also have a [grant option](#) are marked with an asterisk (*).

[More Help](#)

For [users](#) in the list, those [permissions](#) that also have a [grant option](#) are marked with an asterisk (*).
[More Help](#)

Shows the types of [permissions](#) for the selected [users](#).
[More Help](#)

Permits the selected [users](#) to alter the [table's](#) structure or to create [triggers](#) for the table.

[More Help](#)

Permits the selected [users](#) to delete [rows](#) in the [table](#) or [view](#).
[More Help](#)

Permits the selected [users](#) to insert [rows](#) in the [table](#) or [view](#).
[More Help](#)

Permits the selected [users](#) to create [indexes](#) and [foreign keys](#) on the [table](#).
[More Help](#)

Permits the selected [users](#) to read [rows](#) in the [table](#) or [view](#).
[More Help](#)

Permits the selected [users](#) to update [columns](#) of the [rows](#) in the [table](#) or [view](#).
[More Help](#)

For the selected [users](#), shows whether the [permissions](#) apply to all columns or a subset of columns.
[More Help](#)

For the selected [users](#), shows whether the type of [permission](#) applies to all columns or a subset of columns. For subsets of columns, those columns with [grant option](#) are marked with an asterisk (*).

[More Help](#)

Allows you to apply the [permission](#) to all columns or a subset of columns.

[More Help](#)

Grants this [permission](#) to all columns of the table (even if columns are subsequently added to the table).
[More Help](#)

Grants this [permission](#) to the selected columns of the table.

[More Help](#)

Shows the [columns](#) of the [table](#) (listed by name, [permission](#) state, and [grant option](#) state).
[More Help](#)

Grants this [permission](#) to the selected columns.

[More Help](#)

For this [permission](#), sets the [grant option](#) for the selected columns.
[More Help](#)

Shows the [grant_option](#) for each type of [permission](#) for the selected [users](#) .
[More Help](#)

For this [permission](#), sets the [grant option](#) for the selected [users](#) .
[More Help](#)

The number of columns in the table.

The number of rows in the table at the time of the last checkpoint.

The number of bytes required for each [row](#) in this [table](#).

This is calculated from the length of the string [columns](#), the [precision](#) of **numeric** columns, and the number of bytes of storage for all other [data types](#).

If the table includes **long binary** or **long varchar** columns, their arbitrary widths are **not** included, so the row width can only be approximated.

Allows you to select the [data type](#) of the column.

The list includes:

- ◆ [base data types](#) (with format where applicable)
- ◆ [user-defined data types](#) (with base type)

Selecting a user-defined data type automatically sets the column's [default value](#), [nullability](#), and [check constraint](#) if they are pre-defined by the type.

Provides a place for you to type the size or precision of the data type.
You can also use the up/down buttons to change the value.

Provides a place for you to type the scale for the **numeric** data type.
You can also use the up/down buttons to change the value.

The [default value](#) of the column.

If the column is based on a [user-defined data type](#), it inherits the type's default value (if any), but this can be overridden for the column.

Click **Edit** to change this for the column.

The [check constraint](#) of the column.

If the column is based on a [user-defined data type](#), it inherits the type's check constraint (if any), but this can be overridden for the column.

Click **Edit** to change this for the column.

Shows whether the values of this column in the [table's rows](#) must be unique.
Click **Edit** to change this for the column.

The [nullability](#) of the column.

If the column is based on a [user-defined data type](#), it inherits the type's nullability, but this can be overridden for the column. Click **Edit** to change this for the column.

Allows you to change the advanced properties of the column ([default value](#), [check constraint](#), unique constraint, and [nullability](#)).

Allows you to type a custom value (string or number) for the [default value](#).

If you've based this column on a [user-defined data type](#), you can retain the type's default value (if any) or override it for this column.

Allows you to select a pre-defined value (for example, **current date**) for the [default value](#).

If you've based this column on a [user-defined data type](#), you can retain the type's default value (if any) or override it for this column.

Determines whether this column's value in each [row](#) must be unique.

Note: Unique columns also appear as single-column [unique table constraints](#) in the [table's property sheet](#).

Determines the [nullability](#) of this column.

If you've based this column on a [user-defined data type](#), you can retain the type's nullability or override it for this column.

Provides a place for you to type the [check constraint](#) on the column.

If you've based this column on a [user-defined data type](#), you can retain the type's check constraint (if any) or override it for this column.

This text box offers the same syntax highlighting and drag-and-drop features used in the [code editor](#).

The [table](#) containing the [foreign_key](#) (this table).

The table containing the primary key that the foreign key is referencing.

Shows the order of columns in this foreign key.

Shows the columns in the primary table's primary key.

Prevents updates of the associated [primary table's primary key](#) value if there are corresponding [foreign keys](#) in this [table](#).

Updates the foreign key to match a new value for the associated primary key.

Sets to NULL all the foreign-key values in this table that correspond to the updated primary key of the associated primary table.
Note: To use this option, the foreign-key columns must **all** have **Allow Nulls** set.

Sets to the column's default value all the foreign-key values in this table that correspond to the updated primary key of the associated primary table.

Note: To use this option, the foreign-key columns must **all** have default values.

Prevents deletion of the associated [primary table's primary key](#) value if there are corresponding [foreign keys](#) in this [table](#).

Deletes the rows from this table that match the deleted primary key of the associated primary table.

Sets to NULL all the foreign-key values in this table that correspond to the deleted primary key of the associated primary table.
Note: To use this option, the foreign-key columns must **all** have **Allow Nulls** set.

Sets to the column's default value all the foreign-key values in this table that correspond to the deleted primary key of the associated primary table.

Note: To use this option, the foreign-key columns must **all** have default values.

Determines the [nullability](#) of the [foreign-key columns](#).

Note: To use this option, the foreign-key columns must **all** have **Allow Nulls** set.

Forces the database to wait for a [COMMIT](#) before checking the integrity of the [foreign_key](#), overriding the setting of the WAIT_FOR_COMMIT database option.

Note: This option can only be used with the **Restrict** actions.

The [database space](#) used by the [index](#).

Ensures that there will not be two rows in the table with identical values in all columns of the index.

Shows all columns in the table (listed by column name and data type).
Primary key columns are represented by a special icon.

The columns that make up the index. The order column indicates the order in which the columns are sorted.

Determines whether the [trigger](#) executes **Before** or **After** the event.

[Row-level triggers](#) can also have [SQL Remote conflict](#) timing, which executes before **UPDATE** or **UPDATE OF column-lists** events.

Determines which events cause the [trigger](#) to execute.

Events: **Insert, Delete, Update, Update Columns.**

Determines whether the [trigger](#) is [row-level](#) or [statement-level](#).

For [triggers](#) in this [table](#) that execute for the same kind of event with the same timing, this number determines the order in which these triggers are fired.

Shows all [users](#) who have [permissions](#) on the [view](#).

Permissions: **D**=Delete, **I**=Insert, **S**=Select, **U**=Update

Permissions that also have a [grant option](#) are marked with an asterisk (*).

[More Help](#)

Shows all users who have permission to execute the procedure.

For confirmation, this provides a place for you to re-type the new password that you entered in the **Password** field. The contents of the two fields must match exactly.

Determines whether the [user](#) or [group](#) is allowed to connect to the database.

If the user or group is not allowed to connect, the [password](#) (if any) is removed from the account. If you later change the user or group to allow them to connect, you must supply a new password.

Users are almost always allowed to connect. For a group, however, turning this option off prevents anyone from connecting to the database using the group account itself.

Grants DBA authority to the user or group.

Grants resource authority to the user or group.

For SQL Remote replication, grants [remote DBA authority](#) to the [user](#) or [group](#).

Shows the groups to which the user or group belongs.

Allows you to add the [user](#) or [group](#) to other groups.

Shows all [groups](#) in the database.

Exits this dialog and adds the [user](#) or [group](#) to the selected groups.

Removes this [user](#) or [group](#) from the selected groups.

Allows you to select a type of object ([tables](#), [views](#), or [procedures](#)) to show user [permissions](#) for.
[More Help](#)

Shows all objects of the given type in the database.

Permissions: **A**=Alter, **D**=Delete, **I**=Insert, **R**=Reference, **S**=Select, **U**=Update

[Permissions](#) that also have a [grant option](#) are marked with an asterisk (*).

[More Help](#)

Shows the types of [permissions](#) for the selected objects.

[More Help](#)

Permits the [user](#) or [group](#) to alter the structure of the selected objects, or to create [triggers](#) for the selected [tables](#).
[More Help](#)

Permits the [user](#) or [group](#) to delete [rows](#) in the selected [tables](#) or [views](#).
[More Help](#)

Permits the [user](#) or [group](#) to insert [rows](#) in the selected [tables](#) or [views](#).
[More Help](#)

Permits the [user](#) or [group](#) to create [indexes](#) and [foreign keys](#) on the selected [tables](#).
[More Help](#)

Permits the [user](#) or [group](#) to read [rows](#) in the selected [tables](#) or [views](#).
[More Help](#)

Permits the [user](#) or [group](#) to update all [columns](#) of the [rows](#) in the selected [tables](#) or [views](#).
[More Help](#)

Permits the [user](#) or [group](#) to execute the selected [procedures](#).
[More Help](#)

Shows the [grant_option](#) for each type of permission for the selected objects.

[More Help](#)

For this permission, sets the [grant_option](#) for the selected objects.

[More Help](#)

Shows all [subscriptions](#) by this [remote user](#) (listed by [publication](#) name, [SUBSCRIBE_BY](#) value (if any), and status).
[More Help](#)

Allows you to [subscribe](#) the [remote user](#) to an existing [publication](#).
[More Help](#)

The name of the remote_user who is subscribing.

Shows all [publications](#) in the database.

Exits this dialog and subscribes the remote user to the selected publication.

Removes the [remote user's subscriptions](#) to the selected [publications](#).
[More Help](#)

Allows you to manually start, stop, or [synchronize](#) a selected [subscription](#) for the [remote user](#).

Note: You must select a subscription that has already been stored in the database. (You can click **Apply** to make sure of this.)

[More Help](#)

Allows you to select a [message type](#) for communicating with the [publisher](#).
[More Help](#)

Provides a place for you to type the remote [address](#) of the [remote user](#).
[More Help](#)

Sets the [replication frequency](#) so that the [publisher's agent](#) will run once, sending all pending [messages](#) to this [remote user](#), then shut down.

This means that the agent must be restarted each time the publisher wants to send messages.

Note: In most replication setups, this option is not used for sending from the [consolidated](#) publisher to the remote user.

[More Help](#)

Sets the [replication frequency](#) so that the [publisher's agent](#) will run continuously, sending [messages](#) to this [remote user](#) at the given periodic interval.

[More Help](#)

Provides a place for you to type a periodic interval (in hours and minutes) as the [replication frequency](#).
You can also use the up/down buttons to change the values of each field.
Example: **01:30** (for every 90 minutes)

[More Help](#)

Sets the [replication frequency](#) so that the [publisher's agent](#) will run continuously, sending [messages](#) to this [remote user](#) each day at the given time.

[More Help](#)

Provides a place for you to type a daily time (in 24-hour format) for the [replication frequency](#).
You can also use the up/down buttons to change the values of each field.
Example: **22:00** (for 10 p.m.)

[More Help](#)

Shows whether the [remote user](#) is also a [consolidated database](#) for other remote users (a multi-tier replication setup).

The date and time when the [consolidated database](#) is scheduled to send the next batch of [replication messages](#) to this [remote user](#).

Shows SQL Remote usage statistics for this [remote user](#) (from the perspective of the [consolidated database](#)).
For example, **Latest send** shows when the most recent [replication messages](#) were sent from the consolidated database to this remote user.

The [base data type](#) of the [user-defined data type](#).

The format of the data type (where applicable) is listed after the type's name.

The default value of the user-defined data type.

Columns based on this type will inherit this default value (if any), but can subsequently override it.

The [nullability](#) of [columns](#) based on this type.

The [check_constraint](#) for the [user-defined_data_type](#).
This text box offers the same syntax highlighting used in the [code_editor](#).

Shows all [articles](#) in the [publication](#) (listed by article name, article type, and [conflict triggers](#) (if any)).

Shows all [subscriptions](#) to this [publication](#) (listed by [remote user](#) name, [SUBSCRIBE BY](#) value (if any), and status).

Allows you to [subscribe](#) an existing [remote user](#) to the [publication](#).

The name of the [publication](#) to [subscribe](#) to.

Shows all [remote_users](#) in the database.

Exits this dialog and subscribes the selected remote user to the publication.

Removes the selected [remote users' subscriptions](#) to the [publication](#).

Allows you to manually start, stop, or [synchronize](#) a selected [subscription](#) to the [publication](#).

Note: You must select a subscription that has already been stored in the database. (You can click **Apply** to make sure of this.)

The [publication](#) that this [article](#) belongs to.

The type of [article](#) (**Table** or **Table Subset**).

Opens the [property sheet](#) for the [table](#) that the [article](#) is based on.

The [table](#) that the [article](#) is based on.

For new articles, you can choose from a list of tables in the database.

Sets the [article](#) to use all [columns](#) in the [table](#).

Sets the [article](#) to use the table [columns](#) that you select in the list.

Shows all [columns](#) in the [table](#) that the [article](#) is based on.
To include a column in the article, make sure that it is checked.

Provides a place for you to type the WHERE clause to restrict the table [rows](#) that are included in the [article](#). This text box offers the same syntax highlighting and drag-and-drop features used in the [code editor](#).

Sets the article to **not** use SUBSCRIBE_BY columns or clauses to partition rows.

Sets the article to partition rows from the table based on a column (SUBSCRIBE_BY columns).

Allows you to select a table column for partitioning the rows from the table.

Sets the article to partition rows from the table based on an expression (SUBSCRIBE_BY clause).

Provides a place for you to type the [SUBSCRIBE BY](#) expression for partitioning the [rows](#) from the [table](#). This text box offers the same syntax highlighting and drag-and-drop features used in the [code editor](#).

The name of the [message type](#).

This name corresponds to the actual [message system](#), and must be unique for all message types in the database.

The name should correspond to a message-type DLL already installed in your SQL Anywhere directory. For example, you could type **FOOBAR** if you have a **DBFOOBAR.DLL** available.

Provides a place for you to type the [address](#) of the [publisher](#). [Remote databases](#) send [replication messages](#) back to the [consolidated database](#) at this address.

Provides a place for you to type the name of the [database file](#) that the [database space](#) points to:

- ◆ For new spaces, you can enter a new filename.
- ◆ For existing spaces, you can enter the filename of the moved/renamed file, or click **Browse** to locate it.

If you don't supply a path, the directory of the SYSTEM database space is assumed.

Example: **C:\TESTDB\ORDERS.DB**

Allows you to pre-allocate storage in the [database space](#) by adding [pages](#) to it.
This may improve performance for bulk-loading operations.

Provides a place for you to type the number of [pages](#) to add to the [database space](#).

Note: Once you have added pages to the database space, you cannot remove them.

The optional name of the [user's](#) connection.

Naming your [connections](#) allows multiple connections to the same database, or multiple connections to the same or different database servers, all simultaneously.

The [connection ID](#) of the [user's](#) connection.

This number can be useful for distinguishing between users connected under the same user name.

[More Help](#)

The full path and filename (that is, the SYSTEM database space) of the database to which the user is connected.

The full path and filename of the [transaction_log_file](#) of the database to which the [user](#) is connected.

The type of communications link used by the user's connection. If the connection is between a SQL Anywhere client and network server, the link type represents the network protocol being used.

Examples: **LOCAL**, **IPX**

The communications port ID used by the [user's](#) connection.

The number of [users](#) currently connected to this SQL Anywhere server (including your current SQL Central connection).

Shows statistics for the [user's](#) connection (listed by statistic name, value, and description).

If a user is connected to a [network server](#) using the [TCP/IP](#) network protocol, **NodeAddress** shows their TCP address (e.g. 123.45.0.67).

Provides a place for you to type the name of the SQL Anywhere [user](#).

[More Help](#)

Provides a place for you to type the name of the SQL Anywhere [stand-alone engine](#) or [network server](#).

Example: **myserver**

[More Help](#)

Starts the [database file](#) using a SQL Anywhere [stand-alone engine](#).

[More Help](#)

Starts a [SQL Anywhere client](#) that connects to the database specified by **Database Name** on the [network server](#) specified by **Server Name**.

[More Help](#)

Starts the database with command-line parameters that you supply.
To specify these parameters, click the **Custom** push-button.

[More Help](#)

Opens a dialog to specify custom startup parameters for the database.

[More Help](#)

Expands this dialog to reveal more options for connecting to a database.

[More Help](#)

Connects to the specified database using the options chosen in this dialog.

[More Help](#)

Closes this dialog without connecting to a database.

[More Help](#)

Provides a place for you to type the command and switches for starting the database.

- ◆ [stand-alone engine](#):

dbeng50 <[stand-alone engine switches](#)>

For example, to open the sample database using an engine with a cache size to 5 megabytes, you would type: **dbeng50 -c 5M sademo.db**

- ◆ [SQL Anywhere client](#) to [network server](#):

dbclient <[client switches](#)>
<[network server switches](#)>

For example, to connect a client to a server using TCP/IP as the network protocol, you would type: **dbclient -x tcpip my_server**

Name of the current service.

Services

Indicates the status of the service as being either stopped or started.

Services

Specifies that the service is to be started automatically whenever the NT operating system is started.

Services

Specifies that the service is to be started manually from the SQL Anywhere Service Manager each time or the NT Service Manager. Only a user with Administrator permission will be able to start the service.

[Services](#)

Indicates the type of service.

Services

Specifies that the service is to be disabled. It will not start.

Services

Enter the path of the executable.

[Services](#)

Enter the appropriate command line parameters (file names and switches) in the Parameters box.

[Services](#)

Selects your system's local account as the one that the service will run under.

[Services](#)

Indicates that an account other than the local one is to be selected. Choose the appropriate user ID from the pull down menu.

Services

Enter the appropriate password for the selected user ID.

[Services](#)

Re-enter the user ID's password to confirm that it was entered correctly.

[Services](#)

Check here if you wish the service to be visible on the desktop.

[Services](#)

Indicates that you do not wish the system to poll the services for changes to their states (started, stopped, paused or removed).

Services

Indicates that you wish the system to poll the services, at specified intervals, to check for changes in the current states (started, stopped, paused or removed). Enter the desired interval in seconds either manually or by using the spin buttons.

[Services](#)

Enter the load order group that the current service will belong to.

[Services](#)

Click here for a listing of all load order groups on the system.

[Services](#)

Lists the services or load order groups that are to be started before the current service.

Services

Opens a window that allows you to select the services that you wish to add to the list of dependencies.

[Services](#)

Opens a window that allows you to select the load order groups that you wish to add to the list of dependencies.

[Services](#)

Removes the selected group or service from the list box so that it will not be started before the current service.

[Services](#)

Select the SQL Anywhere groups that you wish to add to the list of items to start before the current service.

[Services](#)

Select any other groups that you wish to add to the list of items to be started before the current service.

[Services](#)

Enter a group that you wish to add that is not in either of the above lists.

Services

Select the services from the list that you would like the current service to depend on.

[Services](#)

Select a group or groups from the list that you would like the current service to depend on.

[Services](#)

Name of the service that is being copied

Services

Default name is entered here. You may change the new services name by typing over the default name.

Services

Enter the password.

[Services](#)

For information on switches, click the appropriate topic:

[SQL Anywhere Components](#)

[SQL Anywhere Database Server](#)

[SQL Anywhere Client](#)

[Services](#)

Click here to display indexes in the neighboring window. A check indicates that indexes are to be displayed. No check indicates that indexes are not to be displayed.

To display the properties of an object contained in this DB Space, select the object from the window listing and click the Properties button.

Depending upon the Show items selected, this window displays the objects (tables and indexes) currently saved in this DB Space.

This button opens a window that allows you to set the consolidated database.

Indicates that this is not a remote database.

Indicates that this is a remote database.

Click here to display tables in the neighboring window. A check indicates that tables are to be displayed. No check indicates that tables are not to be displayed.

What is Sybase Central?

Sybase Central is a Windows tool for managing databases and related products. It lets you, the database administrator, manage the objects in your servers and databases (tables, views, procedures, and so on). It also helps you perform common administrative tasks (creating databases, backing them up, and so on).

Sybase Central simplifies these tasks by providing an easy-to-use graphic interface, much like the Windows 95 Explorer. For example, to delete a database table, you select it in the main window and click **Delete**.

Sybase Central helps you with more complicated tasks (such as unloading a database) by providing [wizards](#) which walk you through the task step by step.

Sybase Central lets you use the type of interface that you're most comfortable with - menus, toolbars, keyboard shortcuts, or drag-and-drop.

Sybase Central can manage a variety of database products by using [plug-in modules](#).

[Related Topics](#)

Sybase Central's plug-in architecture

You can use Sybase Central as your common application for managing these database products:

{button ,IE(FE('SCSA.HLP'),'JI('SCSA.HLP>howto','IDH_scsa_requirements'),'JI(','IDH_sc_product_not_installed'))} [Sybase SQL Anywhere](#)

{button ,IE(FE('SCSS.HLP'),'JI('SCSS.HLP>howto','IDH_scss_requirements'),'JI(','IDH_sc_product_not_installed'))} [Sybase SQL Server Release 11 for Windows NT](#)

{button ,IE(FE('NIDYNA.HLP'),'EF('NIDYNA.HLP','',9'),'JI(','IDH_sc_product_not_installed'))} [NetImpact Dynamo](#)

Each of these products comes with a [plug-in module](#) for Sybase Central. When you install the product, its Sybase Central plug-in is also installed. When you next start Sybase Central, the new product automatically "plugs in" to Sybase Central and appears in the main window.

For special situations, you can also [manually control the plug-ins](#) that appear in Sybase Central.

[Related Topics](#)

Managing plug-ins

In most cases, you never have to manage [plug-ins](#) yourself. If you install a product that comes with a Sybase Central plug-in, it is **automatically** registered with Sybase Central and appears in your next Sybase Central session.

If, however, you don't want a product to appear in Sybase Central (for whatever reason), you can unregister ("unplug") it. You can then re-register it later if you wish.

To manage Sybase Central plug-ins:

- ◆ [Start](#) Sybase Central.
- ◆ Click **Plug-ins** in the **Tools** menu or [pop-up menu](#).
This shows all plug-ins that are registered (plugged in) in Sybase Central, including their individual version numbers.
- ◆ Use the controls to register or unregister the various plug-ins.
{button ,PI('>howto','IDH_sc_help_whats_this')} [How?](#)

Notes:

- ◆ Sybase Central has its own version number, separate from the plug-in version numbers.
To see Sybase Central's version number, click **About Sybase Central** in the **Help** menu.

[Related Topics](#)

Contacting Sybase Customer Support

If you have problems, questions, or suggestions for Sybase SQL Anywhere, please contact Sybase Customer Support in your part of the world:

- ◆ [North America and International](#) (excluding Europe)
- ◆ [Europe](#)

[Related Topics](#)

Customer Support - North America/International

Sybase, Inc., 6475 Christie Avenue Emeryville, California USA 94608

General Inquiries

- ◆ Tel: 617-564-7353
- ◆ FAX: 303-294-3739

Sales

(upgrades, other product orders, and reseller inquiries/orders)

- ◆ Tel: 800-8-SYBASE
- ◆ Annual support sales: 800-395-3525
(toll-free in North America)

Technical Support

- ◆ Installation and registration support
 - North America 519-884-0702
 - Latin America 713-977-0752
 - Singapore 65-378-0140
- ◆ Annual support 800-937-7693
- ◆ Pay-per-issue support 508-287-1950
- ◆ Customer service fax 508-369-4992
- ◆ BBS: 508-287-1850
- ◆ CompuServe: type GO SYBASE
or GO POWERSOFT
or GO WATCOM
- ◆ Microsoft Network: type GO SYBASE
or GO POWERSOFT
or GO WATCOM
- ◆ Internet FTP site: ftp.sybase.com
ftp.powersoft.com
ftp.watcom.com
- ◆ World Wide Web: www.sybase.com
www.powersoft.com

SQL Anywhere customer support services are subject to then-current price, terms, and conditions.

Faxline

Technical support and product information is available 24 hours a day using the Faxline fax-back system.
To reach Faxline, call 508-287-1600.

[Related Topics](#)

Customer Support - Europe

Sybase Europe, Windsor Court, Kingsmead Business Park, High Wycombe, Bucks., HP11 1JU, UNITED KINGDOM

Sales

(upgrades, other product orders, and reseller inquiries/orders)

◆ Austria	0660 6714
◆ Belgium	0800 1 5562
◆ Denmark	80 01 02 07
◆ France	05 90 81 35
◆ Germany	0130 81 88 62
◆ Italy	167 872036
◆ Netherlands	060 222102
◆ Norway	800 11012
◆ Spain	900 99 4417
◆ Sweden	020 791 705
◆ Switzerland	155 4881
◆ United Kingdom	0800 44 44 55
◆ All other locations	+44 1494 555 599 (UK)
Fax	+44 1494 555 595 (UK)

Technical Support

◆ Belgium	+32 2 352 3333
BBS	+32 2 352 3303
◆ Czech Republic	+42 2 311 4596
◆ France	+33 1 41 02 34 56
◆ Germany	+49 6122 9232 32
◆ Netherlands	+31 20 651 8402
◆ Norway	+47 51 52 12 20
◆ Spain	+34 1 593 26 36
◆ United Kingdom	+44 1494 555566
BBS:	+44 1494 555533
◆ CompuServe:	type GO SYBASE or GO POWERSOFT or GO WATCOM
◆ Microsoft Network:	type GO SYBASE or GO POWERSOFT or GO WATCOM
◆ Internet FTP site:	ftp.sybase.com ftp.powersoft.com ftp.watcom.com
◆ WorldWide Web:	www.sybase.com www.powersoft.com

For information on technical support in countries not listed, please call the appropriate sales line.
SQL Anywhere customer support services are subject to then-current price, terms, and conditions.

Faxline


Technical support and product information is available 24 hours a day using the Faxline fax-back system.
To reach Faxline, call +44 1 494 555522. In Belgium, call +32 2 352 3305.

[Related Topics](#)

Getting pop-up help in a dialog

You can get instant help for every control in every dialog in Sybase Central.

To get help for a particular control, do one of the following:

- ◆ Click the  button in the upper-right corner of the dialog, then click the help cursor on the control.
- ◆ Right-click the control, then click **What's This?** in the pop-up menu.
- ◆ Make the control active (e.g. by tabbing to it), then press **F1**.

This opens a pop-up window that describes the control.

[Related Topics](#)

Overview of connection profiles

When you first connect to a server or database, you typically enter a user name, password, and (in some cases) other optional connection parameters.

To make subsequent connections to that object easier and faster, you can create a [connection profile](#) that saves that group of parameters under a name that you supply. From then on, you can use that profile to connect to the object in one step.

To use and manage connection profiles, click **Connection Profiles** in the **Tools** menu.

This opens the connection profile dialog, where you can:

- ◆ [create](#) a new connection profile
- ◆ [connect](#) using a profile
- ◆ [edit](#) an existing profile
- ◆ set a profile to [connect automatically](#) when Sybase Central is started
- ◆ [delete](#) profiles

[Related Topics](#)

Creating a new connection profile

To create a new connection profile:

- ◆ Open the [connection profile dialog](#).
- ◆ Click **New**.
- ◆ In the profile name dialog, enter a **Name** and **Type** for the new profile.
{button ,PI('','IDH_sc_help_whats_this')} [How?](#)
- ◆ In the [connection dialog](#), enter the desired values.
{button ,PI('','IDH_sc_help_whats_this')} [How?](#)

You can then use the profile to:

- ◆ [connect now](#)
- ◆ [connect automatically](#) each time you start Sybase Central.

[Related Topics](#)

Connecting using a profile

To connect to a server or database using an existing **connection profile**:

- ◆ Open the [connection profile dialog](#).
- ◆ Do one of the following:
 - Select the profile in the list, then click **Connect**.
 - Double-click the profile.

Once you connect to a server or database, its icon is shown (or updated) in the [main window](#).

You can then administer the object and its contents by [navigating](#) and [selecting](#) in its [object tree](#).

[Related Topics](#)

Editing a connection profile

To edit the parameters of an existing connection profile:

- ◆ Open the [connection profile dialog](#).
- ◆ Select the profile in the list.
- ◆ Click **Edit**.
- ◆ In the [connection dialog](#), edit the desired values.
{button ,PI('','IDH_sc_help_whats_this')} [How?](#)

[Related Topics](#)

Setting profiles to connect at startup

To make a **profile** connect automatically when you next start Sybase Central:

- ◆ Open the [connection profile dialog](#).
- ◆ Select the profile in the list.
- ◆ Click **Set Startup** to change the current setting.

There are no restrictions on the number of automatic connections that you can have.

[Related Topics](#)

Deleting connection profiles

To delete one or more **connection profiles**:

- ◆ Open the [connection profile dialog](#).
- ◆ Select the desired profiles.
- ◆ Click **Delete**.

[Related Topics](#)

Layout of the main window

The main Sybase Central window is very similar to the Windows 95 Explorer.

The main window is split into two panels:

- ◆ The **left panel** shows the [object tree](#) (a hierarchical view of objects, such as servers and databases). Note that the left panel only shows the [containers](#) in the object tree. It does not show objects that are not containers of other objects. For example, the left panel may show a **Columns** folder (a container), but not the columns themselves (shown in the right panel instead).
- ◆ The **right panel** shows the contents of the currently selected container. You can change the appearance of the [right-panel view](#) to show large icons, small icons, a multi-column list, or a detailed list.

The main window also has a [toolbar](#) and [status bar](#).

Once you connect to a database or server, you can administer it by [navigating](#) and [selecting](#) its objects in the main window.

[Related Topics](#)

Changing the right-panel view

In the right panel of the main window, you can show objects as:

- ◆ **Large Icons** - shown left to right, top to bottom, labeled underneath
- ◆ **Small Icons** - shown left to right, top to bottom, labeled on right
- ◆ **List** - small icons, but shown top to bottom, left to right (as many columns as necessary)
- ◆ **Details** - small icons, but shown top to bottom, with columns for name, comment, and other properties

To change the view, do one of the following:

- ◆ Choose the desired view from the **View** menu or the right panel's [pop-up menu](#).
- ◆ Click the appropriate view button in the [main toolbar](#).


[Related Topics](#)


Navigating in panels

In the left and right panels, there are several ways to navigate through the [object tree](#).

To open a container, double-click it. This expands the container so that:

- ◆ the left panel shows all containers in it, and
- ◆ the right panel shows its contents.

To expand a container in the left panel without changing the right panel, click its  button in the left panel.

To close an open container, double-click it (or click its  button in the left panel). This collapses the container in the left panel by hiding the containers in it.

To move up one level in the object tree (for example, from a given table to the **Tables** folder), click the **Up One Level** button in the [main toolbar](#).

You can also move up in the object tree by choosing objects in the object-tree drop-down combo box (above the left panel). This is handy when the part of the tree that you want to select has scrolled out of sight in the left panel.

You can also use the arrow keys to navigate through the object tree.

{button ,PI(';', 'IDH_sc_panel_navigate_keyboard')} [How?](#)

[Related Topics](#)

Navigating using the keyboard

You can use the arrow keys to navigate through the object tree:

- ◆ In the left panel:
 - The up/down keys move up and down in the list of containers.
 - The right/left keys open and close the selected container.
- ◆ In the right panel:
 - The up/down keys move up and down in the list of objects.
 - The right/left keys scroll the panel.

Selecting objects in panels

In either panel, clicking an object selects that object.

If you select a [container](#) in the left panel, the right panel shows its contents.

In the left panel, you can only select one object at a time. In the right panel, you can select several objects at a time.

The **Select All** command in the **Edit** menu selects all objects in the right panel.

The **Invert Selection** command reverses which objects are selected and which are not.

[Right-clicking](#) an object opens a [pop-up menu](#) of commands for that object.

[Related Topics](#)

Refreshing the main window

While you are working in Sybase Central, other users can make changes to the database's structure (provided they have sufficient permissions). This means that the database's structure could change while you are examining it in Sybase Central.

When you first open a [container](#), Sybase Central reads its contents fresh from the database. If, however, someone then makes a change to the contents of that container, your view of it may be out of date. For example, if you are working in the **Tables** folder, and another user adds a table to the same database, your **Tables** folder will not immediately show the new table.


To ensure that you always have the latest changes to the database, Sybase Central provides two **Refresh** commands in the **View** menu. These commands query the database to get up-to-date information:

- ◆ **Refresh Folder** refreshes your view of the currently expanded container.
- ◆ **Refresh All** refreshes your view of all expanded containers.

[Related Topics](#)

Using the main toolbar

The [main window's](#) toolbar (shown below) provides you with graphic buttons for common commands.



Click a button above to see a description of what it does.

To show or hide the toolbar, click **Toolbar** in the **View** menu.

[Related Topics](#)

Using the main status bar

In the main window, the status bar shows a brief summary of menu commands as you navigate through the menus. To show or hide the status bar, click **Status Bar** in the **View** menu.

[Related Topics](#)

Ending your Sybase Central session

To quit Sybase Central, click **Exit** in the **File** menu.

This disconnects from all connected servers and databases, then exits the Sybase Central application.

Notes:

- ◆ If you try to exit Sybase Central while editing the code of a procedure, view, or trigger, Sybase Central prompts you first to commit any unsaved changes.
-

[Related Topics](#)

Overview of the code editor

Sybase Central's code editor is a separate window for displaying, editing, and printing the code of [triggers](#), [procedures](#), and [views](#).

Beyond the standard text-editing functions, it provides:

- ◆ automatic syntax highlighting
{button ,PI('','IDH_sc_editor_syntax_highlight')} [Details](#)
- ◆ language-sensitive indenting
- ◆ automatic formulation of DDL statements
{button ,PI('','IDH_sc_editor_create_alter')} [Details](#)
- ◆ unlimited **Undo** and **Redo**
- ◆ [drag-and-drop](#) editing (you can drag selected text to a new location in the code)
- ◆ ability to set the [display font](#)
- ◆ ability to [find and replace](#) text, and to [jump](#) to specific line numbers
- ◆ ability to [open](#) from and [save](#) to external files
- ◆ ability to [print](#) the code
- ◆ ability to [execute](#) the DDL code against the database
- ◆ a [toolbar](#) and [status bar](#)

[Related Topics](#)

Syntax highlighting in the code editor

The code in the editor window is automatically highlighted according to its [Watcom-SQL](#) or [Transact-SQL](#) syntax:

- ◆ keywords and constants are **blue**
- ◆ quoted strings are **purple**
- ◆ partially quoted strings are **red**
- ◆ comments are **green**

Automatic formulation of DDL statements

When you create or edit a SQL trigger, view, or procedure, the editor automatically chooses the appropriate SQL DDL statement for the object:

- ◆ CREATE <OBJECT> when creating objects.
- ◆ ALTER <OBJECT> when changing existing objects.

Setting the display font

You can customize the display font used in the [code editor](#). This font setting is remembered between sessions.

To set the font in the code editor window:

- ◆ Open the font dialog by doing one of the following:
 - In the **View** menu, click **Change Font**.
 - In the [editor toolbar](#), click the **Change Font** button.
- ◆ Choose the desired font settings.

To make the current font bigger or smaller, do one of the following:

- ◆ In the **View** menu, click **Increase Font Size** (or **Decrease Font Size**).
- ◆ In the [editor toolbar](#), click the **Increase Font Size** button (or **Decrease Font Size** button).

[Related Topics](#)

Finding text in the code editor

To search for specific text in the code editor window:

- ◆ In the code, position the cursor where you want to start the search.
- ◆ Open the find window by doing one of the following:
 - In the **Search** menu, click **Find**.
 - In the [editor toolbar](#), click the **Find** button.
- ◆ Enter the desired values.
{button ,PI(';`IDH_sc_help_whats_this')} [How?](#)
- ◆ Click **Find Next**.

The find window is modeless - you can keep it open while editing text in the editor window.

[Related Topics](#)

Replacing text in the code editor

To replace specific text in the code editor window:

- ◆ In the code, position the cursor where you want to start the search.
- ◆ In the **Search** menu, click **Replace**.
- ◆ Enter the desired values.
`{button ,PI('','IDH_sc_help_whats_this')}` [How?](#)
- ◆ Click **Replace** or **Replace All**.

The replace window is modeless - you can keep it open while editing text in the editor window.

[Related Topics](#)

Jumping to a line number

To jump to a specific line number in the code editor window:

- ◆ Open the go-to dialog by doing one of the following:
 - In the **Search** menu, click **Go To Line**.
 - In the [editor toolbar](#), click the **Go To Line** button.
- ◆ Enter the desired line number.

[Related Topics](#)

Opening an external file in the code editor

If you have code stored as a text file on your system, you can load it directly into the [code editor](#).

To open an external text file into the code editor window:

- ◆ Open the file dialog by doing one of the following:
 - In the **File** menu, click **Open From File**.
 - In the [editor toolbar](#), click the **Open From File** button.
- ◆ Locate the desired file.
By default, Sybase Central looks for files ending in **.SQL**.

The text loaded from the file **replaces** any existing text in the editor window.

[Related Topics](#)

Saving code as an external file

Typically, you write code in the [code editor](#) and execute it against the database. You can also save the code to an external file so that it can be reused elsewhere (in another application like ISQL, for example).

To save the current code in the editor as an external text file:

- ◆ Open the file dialog by doing one of the following:
 - In the **File** menu, click **Save To File**.
 - In the [editor toolbar](#), click the **Save To File** button.
- ◆ Choose a location and name for the new file.
By default, Sybase Central provides a file extension of **.SQL**.

[Related Topics](#)

Printing code

To print the current contents of the editor window, do one of the following:

- ◆ Click **Print** in the **File** menu.
- ◆ Click the **Print** button in the [editor toolbar](#).

This opens the standard print dialog.

[Related Topics](#)

Executing code in the code editor

Once you've finished writing code in the [code editor](#), you can execute the code as DDL against the database. Depending on the code itself, this will create or alter the definition of the object itself.

For example, if you're creating a stored procedure, the editor contains a CREATE PROCEDURE statement. Once you've finished filling out the statement, you can execute it to create the procedure in the current database.

To execute the code against the database:

- ◆ Click **Execute Script** in the **File** menu.
{button ,PI('`IDH_sc_code_execute')} [Other ways](#)

If there are any errors in your SQL syntax, Sybase Central alerts you and does not execute any of the code.


Notes:

- ◆ Executing code in the editor does not actually invoke the procedure itself against data - it only executes the CREATE PROCEDURE or ALTER PROCEDURE statement.

[Related Topics](#)

Using the code editor's toolbar

The [code editor's](#) toolbar (shown below) provides you with graphic buttons for common commands.



Click a button above to see a description of what it does.

To show or hide the toolbar, click **Toolbar** in the **View** menu.

[Related Topics](#)

Using the code editor's status bar

In the editor window, the status bar shows the following:

- ◆ a brief summary of menu commands as you navigate through the menus
- ◆ status messages when searching, etc.
- ◆ total number of lines in the current code
- ◆ the current line number and column number
- ◆ indicators for Caps Lock and Num Lock

To show or hide the status bar, click **Status Bar** in the **View** menu.

[Related Topics](#)

Product not installed

This product isn't supported in your current Sybase Central configuration.

For Sybase Central to manage a given database product (for example, SQL Anywhere), you must install the appropriate Sybase Central components for that product.

Sybase Central typically ships with support for one or more database products. The product components that you received depend on your version of Sybase Central.

For more information on other product components for Sybase Central, contact [Sybase Customer Support](#).

No related topics

Opening a creation sheet or wizard

To create an object:

- ◆ Open the [folder](#) that contains objects of that type.
- ◆ Do one of the following:
 - In the right panel, double-click the **Add <object>** [template](#).
 - Select the template, then click **Open** in the **File** menu or [pop-up menu](#).
 - Click **New > <object>** in the **File** menu or the right panel's pop-up menu.

Depending on the type of object, this opens a [wizard](#) or blank [property sheet](#) for the new object.

Starting a wizard

To start a wizard, do one of the following:

- ◆ In the right panel, double-click the wizard's [template](#).
- ◆ Select the template, then click **Open** in the **File** menu or [pop-up menu](#).

Starting a utility

To start a utility, do one of the following:

- ◆ In the right panel, double-click the utility's icon.
- ◆ Select the icon, then click **Open** in the **File** menu or [pop-up menu](#).

Opening a property sheet

To open an object's [property sheet](#), you can do any of the following:

- ◆ Select the object, then click **Properties** in the **File** menu or [pop-up menu](#).
- ◆ Select the object, then click the **Properties** button in the [toolbar](#).
- ◆ Double-click the object.
Note: If the object is a container (for example, a table), this expands the object instead.

Editing an object's code

To edit an object's code, do one of the following:

- ◆ Select the object, then click **Open** in the **File** menu or [pop-up menu](#).
- ◆ Double-click the object.

This opens a code-editor window and displays the object's code.

Executing code in the editor

To execute code in the editor, do one of the following:

- ◆ Click **Execute Script** in the **File** menu.
- ◆ Click the **Execute Script** button in the [editor toolbar](#).

Deleting an object

To delete objects, select them and do any of the following:

- ◆ Click **Delete** in the **File** menu or [pop-up menu](#).
- ◆ Click the **Delete** button in the [main toolbar](#).
- ◆ Press the **Delete** key (**Del** on some keyboards).

Sybase Central asks you to confirm the deletions.

Using an object's pop-up menu

In the main window, each object has a convenient pop-up menu of relevant commands.

To use the pop-up menu for an object:

- ◆ [Right-click](#) the object.
- ◆ In the pop-up menu, click the desired command.

To use a pop-up menu for **several objects at once**:

- ◆ Select the desired objects.
- ◆ Right-click one of the selected objects.
- ◆ In the pop-up menu, click the desired command.

Go to a different folder

Shows the current folder, and allows you to move up in the [object tree](#) by choosing a higher-level folder.

[More Help](#)

Up One Level

Moves up one level in the [object tree](#) (for example, from a given table to the **Tables** folder).

[More Help](#)

Connect

Connects to a database or server.

[More Help](#)

Disconnect

Disconnects from a connected database or server.

[More Help](#)

Cut

Places the selected objects in the clipboard. The selected objects are not removed from their current location until they are pasted elsewhere.

Copy

Places a copy of the selected objects in the clipboard.

Paste

Pastes the objects in the clipboard into the current container. If the objects were **Cut**, they are then removed from their original location.

Delete

Deletes the selected objects from the database.

Properties

Opens the selected object's [property sheet](#).

Large Icon

Shows objects in the right panel as large icons, arranged left to right, top to bottom.

[More Help](#)

Small Icon

Shows objects in the right panel as small icons, arranged left to right, top to bottom.

[More Help](#)

List

Shows objects in the right panel as small icons, arranged in as many columns as necessary.

[More Help](#)

Details

Shows objects in the right panel as small icons, top to bottom, with columns for name, type, and other properties.

[More Help](#)

Open From File

Loads text from an external file (for example, a text file containing SQL commands), **replacing** any existing text in the editor.

[More Help](#)

Save To File

Saves the text in the editor to an external text file.

[More Help](#)

Print

Prints the text in the editor.

[More Help](#)

Execute Script

Executes the code in the code editor as DDL against the database's definition.

For example, when editing an existing procedure, clicking **Execute Script** would run the ALTER PROCEDURE statement against the database's definition, thereby updating that procedure.

Note: **Execute Script** does not actually execute the procedure itself against data.

[More Help](#)

Cut

Removes the selected text from the editor and places it in the clipboard.

Copy

Places a copy of the selected text in the clipboard.

Paste

Pastes the text in the clipboard into the editor at the cursor.

Undo

Reverses the effect of your most recent change to the text. You can undo your actions in succession back to the original state of the text when you entered the editor.

Redo

Used immediately after an **Undo** command, this reverses the effect of the **Undo**. If you have used **Undo** several times in succession, you can also **Redo** these changes in succession.

Clear

Removes the selected text from the editor (without affecting the clipboard).

Change Font

Opens the font selection dialog to change the font, size, style, and so on.

[More Help](#)

Increase Font Size

Changes to the next biggest font size available.

[More Help](#)

Decrease Font Size

Changes to the next smallest font size available.

[More Help](#)

Find

Opens the find dialog to search for specific text.

[More Help](#)

Go To Line

Opens the go-to dialog to jump to a specific line number.

[More Help](#)

A container that only contains other objects, and has no inherent properties of its own.

In Sybase Central, a database object that holds other database objects.

Some containers (such as tables) are actual objects in themselves (as well as holding other objects). Other containers (such as the **Columns** folder in a table) are only folders - they don't have any inherent properties of their own.

The hierarchy of database-related objects that Sybase Central can manage.

The top level of the object tree shows all database products that your version of Sybase Central supports.

Each product expands to reveal its own sub-tree of objects.

[Details](#)

A named set of connection parameters (user name, password, server name, and so on).

A special dialog, usually organized as a series of pages, that guides you through the steps of a complex task.

In the right panel, a special icon that performs a task.

Most templates help you create new objects of a certain type. For example, the **Add Index** template opens a [wizard](#) that helps you create an index.

A dialog that shows the properties of an object. The properties are arranged on one or more tabbed pages. Some properties may be editable, while others are read-only.

Click an object using the right mouse button (instead of the left mouse button).

A real-time graph that shows performance statistics from a running server.

The color and line style of a statistic in the [performance monitor](#).

The SQL dialect used in Sybase SQL Server.

Sybase SQL Anywhere (a separate product from SQL Server) supports a large subset of Transact-SQL.

The SQL dialect used in Sybase SQL Anywhere.
Watcom-SQL conforms closely to ANSI SQL.

A module, stored as a file, that adds support for a specific database product to Sybase Central.

Plug-ins are usually installed and registered automatically with Sybase Central when you install the respective product.

Typically, a plug-in appears as a top-level container in the Sybase Central main window, using the name of the product itself (for example, **Sybase SQL Anywhere**).

Closes this dialog without saving your changes.

Closes this dialog and saves your changes.

Closes this dialog.

Opens a standard file dialog to help you locate a file.

The name of this object.

When creating objects, this provides a place for you to name the new object.

Certain types of objects can be renamed if you have the proper permissions.

The type of object.

Examples: **table**, **primary key**, **user**

Shows a summary of the properties of the selected object.

Opens the [property sheet](#) of the selected object.

Allows you to select the type of connection.

Example: **Sybase SQL Anywhere**, **Sybase SQL Server**, **NetImpact Dynamo**

Note: The types available depend on your Sybase Central configuration.

Shows all currently defined [connection profiles](#), and whether they are automatically connected each time Sybase Central is started.

Shortcut: Double-click a profile to **Connect**.

[More Help](#)

Connects using the selected [profile](#).

[More Help](#)

Closes this dialog.

[More Help](#)

Allows you to create a new [connection profile](#).

[More Help](#)

Provides a place for you to type the name of the new [profile](#).

Example: **sademo as dba**

Accepts the new [profile](#) name and opens the connection dialog.

Edits the parameters of the selected [profile](#).

[More Help](#)

Deletes the selected [profile](#) (asks for confirmation first).

[More Help](#)

Toggles the automatic-startup option for the selected [profile](#).

When this option is turned on, the profile is automatically connected each time Sybase Central is started.

[More Help](#)

Closes this dialog.

Can also **shift** this program's **control** into an **alternate** state.

Provides a place for you to type the text to search for.
You can also choose from a pop-up list of recent search items.

Provides options to search up or down in the code.

Searches up from the current position in the code.

If no occurrence is found when the top is reached, the search automatically wraps around to the bottom of the code.

Searches down from the current position in the code.

If no occurrence is found when the bottom is reached, the search automatically wraps around to the top of the code.

Finds the text only where it occurs as a separate word.

Finds the text only where it **exactly** matches the upper- and lower-case that you typed.

Finds the next occurrence of the specified text.

You can keep clicking this button (or the **Find Next** command in the **Search** or right-click menus) to move to successive occurrences of the text.

Provides a place for you to type the new text that will replace the old text.
You can also choose from a pop-up list of recent replacements.

Replaces the found text with the new text, then automatically finds the next occurrence.

Replaces all occurrences at once. The status bar reports the total number of changes.
To undo all changes made by clicking **Replace All** once, click **Undo** immediately afterward.

Provides a place for you to type the line number to go to.
You can also use the up/down buttons to change the number.

Closes the dialog and jumps to the supplied line number.

Brief explanation of the [performance statistic](#).

Adds this [statistic](#) to (or removes it from) the [performance monitor](#) window.

Provides options for setting the update interval of the [monitor](#) window.

Provides a place for you to type the number of seconds between updates in the [monitor](#) window.

Note: Setting very short intervals for updates can skew some statistics (like Cache Reads/sec) that are affected by the queries done by the performance monitor itself.

Resets the update interval to the default of 10 seconds.

Provides options for setting the horizontal grid lines in the [monitor](#) window.

Hides the grid lines in the [monitor](#) window.

Draws a horizontal grid line at the 50% interval in the [monitor](#) window.

Draws horizontal grid lines at 25% intervals in the [monitor](#) window.

Draws horizontal grid lines at 10% intervals in the [monitor](#) window.

Allows you to select a color for plotting this [statistic](#).

Allows you to select a line style for plotting this [statistic](#).

Shows how the statistic will look using the selected color and style.

Shows all current connections for your Sybase Central session.

Disconnects the selected connection (asks for confirmation first), then exits this dialog.

Opens a connection dialog for the selected product.

Shows the name and version of each [plug-in](#) currently available in Sybase Central.

Note: Sybase Central has its own version number.

[More Help](#)

Allows you to load a [plug-in](#) to use in Sybase Central.

[More Help](#)

Provides a place for you to type the filename of the SQL Anywhere [plug-in](#) to register in Sybase Central.

You can also click **Browse** to locate the file.

The filename should be **SCxxxxxx.DLL**, where **xxxxxx** depends on the specific plug-in:

<u>Product</u>	<u>Plug-in filename</u>
SQL Anywhere	SCSQLANY.DLL
SQL Server 11	SCSYB11.DLL
NetImpact Dynamo	SCNETIMP.DLL

The plug-in file should already exist on your PC, installed as part of the respective software.

If you supply just the filename itself (with no path), Sybase Central will look for it in:

- ◆ Sybase Central's current working directory (the probable location)
- ◆ your search path (defined by the PATH environment variable)

[More Help](#)

Closes this dialog and registers the specified [plug-in](#) in Sybase Central.

[More Help](#)

Removes the selected [plug-in](#) from use in Sybase Central.

Note: This does **not** delete the actual plug-in file from your PC - it just stops Sybase Central from using it until you register it again.

[More Help](#)

Shows a listing of all the currently available plug-ins for Sybase Central. Check the boxes of the components that you wish to manage in Sybase Central.

Allows you to type the filename of a plug-in to use in Sybase Central.

Glossary

About the glossary

This glossary contains words used in the SQL Anywhere User's Guide and industry-wide terms concerning SQL databases and related technologies.

address

In SQL Remote replication, the destination of replication messages sent by a given message system. Publishers and remote users each have their own address.

The format of the address depends on the message type.

article

In SQL Remote replication, a database object that represents a whole table, or a subset of the rows and columns in a table. Articles are grouped together in publications.

authority

Determines what structural actions a user can perform in a database. While most users will have no special authorities, a user with DBA authority can grant other users resource authority, DBA authority, or remote DBA authority.

autocommit

An ISQL option. If autocommit is set to TRUE, then a database COMMIT is performed after each successful command and a ROLLBACK after each failed command. The ODBC interface has a setting similar to autocommit. Users of applications communicating with SQL Anywhere through ODBC should check their application documentation for how to set this option. Developers programming directly to the ODBC interface should consult the ODBC documentation for information about implementing autocommit.

backup

It is important to make regular backups of your database files in case of media failure. A backup is a copy of the database file. You can make backups using the SQL Anywhere backup utility or using other archiving software of your choice.

base data type

One of the intrinsic (simple) data types included in SQL Anywhere (such as INTEGER). User-defined data types (including those supplied with SQL Anywhere) are built on base data types.

base table

The tables that permanently hold the data in the database are sometimes called **base tables** to distinguish them from temporary tables and from views.

batch

A batch is a set of SQL statements sent together to the database engine by an application.

buffer

An area of memory reserved for some dedicated use, such as storing incoming messages for processing.

business rules

The rules to which the data in a database must conform are often called business rules, as they reflect organizations' operating practices.

For example, a business rule limiting customers' credit can be enforced by a trigger in a sales order table. A rule requiring library books to be returned within two weeks can be checked by constraints, so that reminders can be issued or fines calculated.

cache

To avoid having to access a hard disk every time it needs to retrieve or write information to the database, SQL Anywhere keeps data it may need to access again in the computer's memory, where access is much quicker. The area of memory set aside for this information is called a cache. See also [checkpoint log](#).

case sensitivity

When creating a database, you can choose whether identifiers in this database (table names, column names, and so on) and values are considered to be case-sensitive in comparisons and string operations. If, for example, a database is case-sensitive, emp_id would not be the same as emp_ID.

checkpoint

A time at which all dirty pages held in cache are written to disk is called a checkpoint. Once all the dirty pages are written to disk, the checkpoint log is deleted. A checkpoint may occur for one of several reasons, at times specified by the user or decided internally by the database engine.

checkpoint log

A SQL Anywhere database file is composed of pages. Before a page is updated (made dirty), a copy of the original is always made. The copied pages are the checkpoint log. The checkpoint log is deleted when a checkpoint occurs.

client

Client is a widely-used term with several meanings. It refers to the user's side of a client/server arrangement: for example, an application that addresses a database, typically held elsewhere on a network, is called a client application.

code page

A code page is a character set. SQL Anywhere supports many different national languages and character sets, as long as they are available under the user's operating system. See also: [collation](#).

collation

SQL Anywhere supports many different national languages by providing a choice of collations. Each collation specifies a code page (character set) and a sorting and comparison order for that code page. SQL Anywhere also supports custom collations. See also: [code page](#).

collation sequence

A collation sequence is an ordering of characters used for sorting and comparing strings. Each national language employs a character set or code page, and a collation sequence for that set.

column

All data in relational databases such as SQL Anywhere is held in tables, composed of rows and columns. Each column holds a particular type of information. See also: [table](#), [row](#).

command file

A text file containing SQL statements. Command files can be built by yourself (manually) or by database utilities (automatically). The DBUNLOAD utility, for example, creates a command file consisting of the SQL statements necessary to recreate a given database.

command window

The SQL command window is an edit control for entering SQL statements for execution.

comment

A text description of an object in the database. These remarks are not parsed or executed by the database engine.

commit

When a user sends the SQL command COMMIT, all the work done to that point is applied to the database itself, and can no longer be undone. A commit marks the end of a transaction. See also: [transaction](#), [rollback](#).

compound statement

A compound statement is a set of SQL statements treated as a unit. The body of a procedure or trigger consists of a compound statement. A compound statement starts with BEGIN and finishes with END. See also: [stored procedure](#), [trigger](#).

compressed database file

A database file that has been compressed to a smaller physical size using SQL Anywhere's database compression utility (DBSHRINK). To make changes to a compressed database file, you must use an associated write file. Compressed database files can be re-expanded into normal database files using SQL Anywhere's database uncompression utility (DBEXPAND).

concurrency

Multi-user versions of SQL Anywhere support concurrent applications: separate connections which may address the same data in the database, running at the same time. SQL Anywhere provides transaction processing and automatic row-level locking to ensure that information remains consistent and that each concurrent application sees a consistent set of data. See also: [transaction](#), [locking](#).

conflict trigger

In SQL Remote replication, a trigger that is fired when an update conflict is detected, before the update is applied. Specifically, conflict triggers are fired by the failure of values in the VERIFY clause of an UPDATE statement to match the values in the database before the update. They are fired before each row is updated.

connection

When a client application connects to a database, it specifies several parameters that govern all aspects of the connection once it is established. A user ID, a password, the name of the database to attach to, are all parameters that specify the connection. All exchange of information between the client application and the database to which it is connected is governed by the connection. See also: [user ID](#), [password](#), named connection.

connection ID

A unique number that identifies a given connection between the user and the database. You can determine your own connection ID using the following SQL statement inside that connection:

```
select connection_property( 'Number' )
```

connection parameters

When a client application connects to a database, the connection parameters specify the characteristics of the connection. See [connection](#).

connection string

When a client application connects to a database, it uses connection parameters to specify the characteristics of the connection. These connection parameters are collected together as a connection string.

See also: [connection parameters](#).

consolidated database

In SQL Remote replication, a database that serves as the "master" database in the replication setup. The consolidated database contains all of the data to be replicated, while its remote databases may only contain their own subsets of the data. In case of conflict or discrepancy, the consolidated database is considered to have the primary copy of all data.

constraint

When tables and columns are created they may have constraints assigned to them. A constraint ensures that all entries in the database object to which it applies satisfy a particular condition. For example, a column may have a UNIQUE constraint, which requires that all values in the column be different. A table may have a foreign key constraint, which specifies how the information in the table relates to that in some other table.

See also: integrity, foreign key constraint, primary key constraint, column, table. unique constraint, check constraint.

container

In a graphical user interface, a container is an object that contains other objects. Containers can be expanded by double-clicking them.

cursor

A cursor is a handle, or identifier, for a particular SQL query and for the position within the result set that is being accessed. Cursors allow each row of a query that returns more than one row to be processed by a client application individually.

cursors

A cursor is a handle, or identifier, for a particular SQL query and for the position within the result set that is being accessed. Cursors allow each row of a query that returns more than one row to be processed by a client application individually.

cursor stability

Cursor stability is a concurrency condition, guaranteed by choosing an isolation level of 1, 2, or 3. Cursor stability guarantees that no row fetched through a cursor yields uncommitted data.

daemon

A background process on a computer, running periodically or all the time, which manages a particular function such as printing services or network communication services.

data dictionary
See system tables.

data source

Databases available to ODBC applications are defined through data sources.

data type

Each column in a table is associated with a particular data type. Integers, character strings, and dates are examples of data types.

database

A relational database is a collection of tables, related by primary and foreign keys. The tables hold the information in the database, and the tables and keys together define the structure of the database. A database may be stored in one or more database files, on one or more devices.

database administrator

The database administrator (DBA) is a person responsible for maintaining the database. The DBA is generally responsible for all changes to a database schema, and for managing users and user groups.

The role of database administrator is built in to SQL Anywhere databases as a user ID. When a database is initialized, a DBA user ID is created. The DBA user ID has authority to carry out any activity within the database.

database connection

All exchange of information between client applications and the database takes place in a particular connection. A valid user ID and password are required to establish a connection, and the actions that can be carried out during the connection are defined by the privileges granted to the user ID.

database engine

All access to information in a SQL Anywhere database goes through a SQL Anywhere engine. The specific SQL Anywhere engine you are using will depend on your operating system. Requests for information from a database are sent to the database engine, which carries out the instructions.

database file

A database is held in one or more distinct database files. The user does not have to be concerned with the organization of a database into files: requests are issued to the database engine about a database, and the engine knows in which file to look for each piece of required information.

Each table, together with its associated indexes, must be contained in a single database file.

database name

When a database is loaded by an engine, it is assigned a database name. Client applications can connect to a database by specifying its database name.

The default database name is the root of the database file.

database object

A database is made up of tables, indexes, views, procedures, and triggers. Each of these is a database object.

database owner

In SQL Anywhere, the user ID that creates a database is the owner of that database, and has the authority to carry out any changes to that database. The database owner is also referred to as the database administrator, or DBA. A database owner can grant permission to other users to have access to the database and to carry out different operations on the database, such as creating tables or stored procedures.

datagram

Communications across a network may take place in a session, (also called a connection, or virtual circuit) or in a connectionless manner. In the connectionless case, the independent packets of information are called datagrams, in analogy with telegrams.

Connectionless communications require routing decisions for all packets, and are not guaranteed. Multi-user editions of SQL Anywhere server use datagrams for their TCP/IP, IPX, and NetDG communication links.

DBA

An abbreviation for database administrator. When a database is first created, using the DBINIT utility, it is created with the single user ID **DBA**, with password **SQL**.

DBA authority

DBA (DataBase Administrator) authority enables a user to carry out any activity in the database (create tables, change table structures, assign ownership of new objects, create new users, revoke permissions from users, and so on). The DBA user has DBA authority by default.

dbspace

A SQL Anywhere database can be held in multiple files, called dbspaces. The SQL command CREATE DBSPACE adds a new file to the database.

Each table, together with its associated indexes, must be contained in a single database file.

DDE

Dynamic data exchange (DDE) is a method for Windows applications to communicate with each other. In any DDE conversation, one application is the client, or destination, while the other application is the server, or source.

default value

Also known as a "column default" or just "default", this is a value that is automatically assigned to particular columns when a new row is entered into a database table, without any action on the part of the client application, as long as no value is specified by the client application. If the client application does specify a value for the column, it overrides the column's default value. Default values can be user-defined (a string or number) or pre-defined (e.g. a timestamp supplied by the system).

device

A device is a disk drive, a tape drive, or other information storage medium.

DLL

A dynamic link library, or DLL, is a collection of compiled functions that can be addressed by a running application at run time. DLL's allow a single set of functions to be shared by many applications, and can be updated without updating every application that depends on them. The Windows, Windows NT, and OS/2 operating systems support DLLs.

driver

A piece of software that manages low-level functions on a computer, such as a communication with a network card or a printer.

Embedded SQL

The native programming interface to SQL Anywhere from C programs. SQL Anywhere embedded SQL is an implementation of the ANSI and IBM standard.

encryption

Encryption makes it more difficult for someone to decipher the data in your database by using a disk utility to look at the file. File-compression utilities are not able to compress an encrypted database file as much as an unencrypted one.

entity integrity

Each row in every table in a database must be uniquely identifiable in order to be accessed by the database engine. Each row is identified by its primary key. This requirement of identifiability is called entity integrity, and is automatically ensured by SQL Anywhere through a checking of the primary key. See also: [primary key](#), [referential integrity](#).

engine name

When a database engine is started it is assigned an engine name. Client applications specify the engine to which they want to connect by using the engine name.

The default engine name is the first database name.

environment variable

The DOS and OS/2 operating systems allow users to set environment variables that can be used by applications to identify system-specific information. Windows applications have access to DOS environment variables. SQL Anywhere uses the SQLCONNECT and SQLANY environment variables to identify default connection parameters and home directory for SQL Anywhere.

entity

In Entity-Relationship design of databases, a first step is to identify the entities in the information you will incorporate into your database. Entities become tables in the final implementation.

Entity-Relationship design

Entity-Relationship design is a systematic approach to designing databases, based on a top-down analysis of the tasks you need to perform.

erase

Erasing a database deletes all tables and data from disk, including the transaction log that records alterations to the database.

ethernet

Ethernet is a term associated with network cards, a protocol, and a network topology. In a network topology context, an ethernet is commonly associated with a bus network.

exception handler

In procedures and triggers, an exception handler is defined in the EXCEPTION part of a compound statement, and is code that is executed if an error is encountered in the compound statement.

extraction

In SQL Remote replication, the act of synchronizing a remote database with its consolidated database by unloading the appropriate structure and data from the consolidated database, then reloading it into the remote database. Extraction uses direct manipulation of ordinary files--it does not use the SQL Remote message system.

FILE

In SQL Remote replication, a message system that uses shared files for exchanging replication messages. This is useful for testing and for installations without an explicit message-transport system (such as MAPI).

For FILE, the addresses are subdirectory names relative to the directory defined by the SQLREMOTE environment variable. This is typically on a volume that is shared between the replicating databases. SQL Remote stores its messages as replication files in this subdirectory.

For example, if SQLREMOTE is set to S:\SQLANY50 (where S:\ is a shared volume), and a FILE address is set to SAMS, SQL Remote expects to find the replication files in the S:\SQLANY50\SAMS directory.

foreign key

Tables are related to each other by using foreign keys. A foreign key in one table (the foreign table) contains a value corresponding to the primary key of another table (the primary table). This relates the information in the foreign table to that in the primary table.

See also: [primary key](#), [referential integrity](#).

forward log
See transaction log.

full backup

In a full backup, a copy is made of the entire database file itself, and optionally of the transaction log. A full backup contains all the information in the database. See also: [incremental backup](#).

function

Also called a "user-defined function", this is a type of procedure that returns a single value to the calling environment. A function can be used, subject to permissions, in any place that a built-in non-aggregate function is used.

grant option

When a user is granted a permission WITH GRANT OPTION, they can grant the permission in turn to other users.

group

A user group is a database user ID that has been given the permission to have members. User groups are used to make the assignment of database permissions simpler. Rather than assign permissions to each user ID, a user ID is assigned to a particular group, and takes on the permissions assigned to that group. See also: [permissions](#), [DBA](#), [user ID](#).

identifier

An identifier is any string composed of the characters A through Z, a through z, 0 through 9, underscore (_), at sign (@), number sign (#), or dollar sign (\$). The first character must be a letter. Alternatively, any string of characters can be used as an identifier by enclosing it in double quotes.

incremental backup

An incremental backup is a copy of the transaction log. This log contains all the information needed to restore the database to its present state from its state when the transaction log was started.

index

An index on one or more columns of a database table allows fast lookup of the information in these columns, and so can greatly speed up database queries. Specifically, indexes assist WHERE clauses in SELECT statements.

inner join

An inner join is one kind of JOIN. operation allowed in the FROM clause of SELECT queries. INNER JOIN is the default type of join.

An inner join includes only those rows of the table on each side of the expression that has matching rows in the other table.

See also: outer join.

integrity

Integrity of information in a database ensures that each row in the database can be uniquely identified (entity integrity) and that relations between rows in different tables are properly maintained (referential integrity). SQL Anywhere provides several tools for maintaining the integrity of information in databases. See also: [entity integrity](#), [referential integrity](#).

IPX

IPX is a network-level protocol by Novell.

isolation levels

The isolation level for instructions within a transaction determines the extent to which other transactions may share the data addressed by the transaction. The isolation level can be set by the user: different isolation levels are appropriate for different kinds of transaction. See also: [locking](#), [transaction](#).

ISQL

ISQL (Interactive SQL) is a SQL Anywhere database administration and browsing utility.

join

The JOIN clause in a SELECT query enables a single database query to obtain information from several related tables.

keys

Database tables may contain two types of key: a primary key, and a foreign key.

LAN
See local area network.

local area network

A local area network (LAN) is a collection of networked computers characterized by two attributes:

- A diameter of not more than a few kilometres.
- Ownership by a single organization.

See also: [protocol](#).

locking

SQL Anywhere places a lock on a row that is being addressed by a transaction. The lock prevents other transactions from having access to the row in a way that could make the data in the database or the data seen by users of client applications inconsistent, while allowing concurrent transactions. See also: [concurrency](#), [transaction](#).

log files

SQL Anywhere maintains a set of three log files to ensure that the data in the database is recoverable in the event of a system or media failure, and to assist database performance. See also: [checkpoint log](#), [transaction log](#), [rollback log](#).

MAPI

Microsoft's Message Application Programming Interface, a message system used in several popular e-mail systems such as Microsoft Mail.

A typical MAPI address may take the form **jsmith**.

media failure

A media failure occurs when the information on a medium (typically a hard disk drive) becomes unusable. A media failure may occur as a result of damage to the file, the file system, or the actual device. SQL Anywhere includes tools for backup and recovery to minimize the effects of media failure. See also: [system failure](#), [backup](#).

Message Agent

In SQL Remote replication, a program (DBREMOTE) that sends and receives replication messages on behalf of a database. A consolidated database's message agent typically runs continuously, receiving replication messages continuously and sending replication messages periodically, while a remote database's agent typically runs on demand, receiving and sending all pending messages.

message system

In SQL Remote replication, a protocol for exchanging messages between the consolidated database and a remote database. SQL Anywhere includes support for several message systems, each encapsulated in a message type.

message type

In SQL Remote replication, a database object that specifies how remote users communicate with the publisher of a consolidated database. A consolidated database may have several message types defined for it; this allows different remote users to communicate with it using different message systems.

SQL Remote includes the following pre-defined message types: FILE, MAPI, SMTP, and VIM.

These message types are automatically added to databases created in or upgraded to SQL Anywhere. To use these pre-defined types, you must define publisher addresses for them.

messages

Message based communication between applications or computers does not require a direct connection. Instead, a message sent at one time by an application can be received at another time by another application at a later time.

named connection

Any connection from ISQL or an embedded SQL application to a database may optionally be given a name. If a client application has several connections in place simultaneously, the user may switch from one connection to another by using the SET CONNECTION command. See also: [connection](#).

named pipes

Named Pipes are an interprocess communication mechanism implemented by a number of leading operating system vendors. Named Pipes are usually implemented atop some transport-level protocol.

NDIS

NDIS (Network Driver Interface Specification) is a datalink-level protocol jointly defined by Microsoft and IBM.

NetBIOS

NetBIOS is a transport-level interface defined by IBM. See also: [protocol](#).

NetBEUI

NetBEUI is a transport-level protocol. See also: [protocol](#).

NetWare

A widely-used network operating system by Novell. NetWare generally employs the IPX protocol, although the TCP/IP protocol may also be used.

network adapter

A network adapter is the physical attachment to a computer allowing network communication. Also called a network card.

See also: [network driver](#)

network architecture

A network architecture is the physical interconnection of computers on a network. Typical architectures include bus, where all computers connect to a single carrier, and ring, where one computer is directly connected to another to form a closed ring.

network card

A network card is the physical attachment to a computer allowing network communication. Also called a network adapter.

See also: [network driver](#)

network driver

A network driver is the software logically located between the operating system and the network card, which allows applications to communicate to the network card. Network cards are usually bundled with a number of network drivers for various operating systems and network protocols.

network operating system

An operating system optimized for server deployment, such as Novell NetWare and Microsoft Windows NT Server Edition.

network server

A SQL Anywhere database engine that runs on a different PC from the client application (which uses the SQL Anywhere client). The server communicates with the client using a particular network protocol.

A network server can support many users connecting from many PCs on the network.

NULL

The NULL value is a special value for a database entry, different from any other valid value for any data type. The NULL value represents missing or inapplicable information. See also: [column](#), [constraint](#).

nullability

Determines whether a column allows a NULL value to be assigned to it. Columns are typically allowed to be NULL if their values are optional or not always available, and are not required for the data in the database to be correct.

ODBC

The Open Database Connectivity (ODBC) interface, defined by Microsoft Corporation, is a standard interface to database management systems in the Windows and Windows NT environments. ODBC is one of several interfaces supported by SQL Anywhere.

ODI

ODI (Open Datalink Interface) is a data link-level interface defined by Novell.

optimizer

The SQL Anywhere database engine contains an optimizer which attempts to pick the best strategy for executing each query. The optimizer uses educated guesses about the occurrence of particular elements in the database to select a strategy. The user can provide explicit estimates in order to help tune an execution strategy. See also: [index](#), [query](#).

outer join

An outer join is one kind of JOIN operation allowed in the FROM clause of SELECT queries.

An outer join may be either a LEFT OUTER or a RIGHT OUTER join. An outer join includes all rows of the table on the LEFT (RIGHT) of the expression whether or not there are matching rows in the other table.

See also inner join.

owner

Each object of a database is owned by the user ID that created it. The owner of a database object has rights to do anything with that object. See also: [DBA](#).

packet

A packet is a communication entity between processes. Messages between two processes are usually fragmented into a number of packets for data transmission from the source and then reassembled at the target host into a single message.

page

A SQL Anywhere database file is composed of pages. Before a page is updated (made dirty), a copy of the original is always made in memory. The copied pages are the checkpoint log. The page-size of a database file is specified when the database is created. See also: [cache](#), [checkpoint log](#).

page size

The size of each database page (in bytes). The page size can be 512, 1024, 2048 or 4096 bytes, with 1024 being the default. Other values for the size will be changed to the next larger size. Large databases usually benefit from a larger page size.

passthrough

In SQL Remote replication, a mode by which the publisher of the consolidated database can directly change remote databases with SQL statements. Passthrough is set up for specific remote users (you can specify all remote users, individual users, or those users who subscribe to given publications). In normal passthrough mode, all database changes made at the consolidated database are passed through to the selected remote databases. In "passthrough only" mode, the changes are made at the remote databases, but not at the consolidated database.

password

Whenever a user connects to a database, a password must be specified. The passwords are stored in the SYS.SYSUSERPERM system table, to which only the DBA has access.

performance statistics

Values that reflect the performance of the database system with respect to disk and memory usage. The CURRREAD statistic, for example, represents the number of file reads issued by the engine which have not yet completed.

permissions

Each user has a set of permissions that govern the actions they may take while connected to a database. Permissions are assigned by the DBA or by the owner of a particular database object. See also: DBA, database object, owner.

phantom lock

A phantom lock is one of three types of lock supported by SQL Anywhere to support concurrency, as part of SQL Anywhere's transaction processing capabilities.

A phantom lock is a type of read lock employed at isolation level 3. No other transaction can read or update the row once a phantom lock has been acquired.

See also: read lock, write lock, locking.

primary copy

In a replication installation, the primary copy of any data is considered to hold the original of the data. All other places in which the piece of data is held are copies of this original.

protocol

The rules and conventions used to communicate between computers are collectively known as a protocol. Instances of protocols include IPX, NetBEUI, and IP. The SQL Anywhere client and server can communicate using a number of different protocols, including NetBIOS, IPX, NamedPipes and TCP/IP.

See also: [IPX](#), [NetBIOS](#), [Named Pipes](#), [TCP/IP](#).

protocol stack

Network communications between communications take place according to a set of protocols. These protocols are logically organized in layers, each with a different function. The set of layers forms a protocol stack.

primary key

Each table in a relational database must be assigned a primary key. The primary key is a column, or set of columns, whose values uniquely identify every row in the table. See also: [entity integrity](#).

programming interface

Programs may connect to SQL Anywhere using one of the interfaces supported by SQL Anywhere. Embedded SQL is SQL Anywhere's native interface. ODBC is another low-level interface. WSQL DDE and WSQL HLI provide higher level interfaces.

publication

In SQL Remote replication, a database object that describes data to be replicated. A publication consists of articles (tables or subsets of tables). Periodically, the changes made to each publication in a database are replicated to all subscribers to that publication as publication updates.

publication update

In SQL Remote replication, a periodic batch of changes made to one or more publications in one database. A publication update is sent as part of a replication message to the remote database(s).

publisher

In SQL Remote replication, the single user in a database that can exchange replication messages with other replicating databases.

remote database

In SQL Remote replication, a database that exchanges replication messages with a consolidated database. Remote databases may contain all or some of the data in the consolidated database.

remote permission

In SQL Remote replication, the permission to exchange replication messages with the publishing database.

Granting remote permissions to a SQL Anywhere user make them a remote user. This requires you to specify a message type, an appropriate remote address, and a replication frequency. In general terms, remote permissions can also refer to any user involved in SQL Remote replication (for example, the consolidated publisher and remote publisher).

qualifier

The name of a database object, such as a table or a view, may be preceded by a qualifier to indicate its owner and hence uniquely identify the database object. For example, a table named **some_table** created by a user **A_User** can be uniquely identified as **A_User.some_table**.

Columns in tables or views may likewise be qualified by the table name (and owner) to identify them uniquely. For example, a column **this_column** may have the fully qualified name **User.some_table.this_column**.

Use of fully qualified names in SQL queries helps to avoid ambiguities.

query

Information is retrieved from SQL Anywhere databases by submitting a query. A query is an SQL SELECT statement, the clauses of which specify the exact information the database engine must return to the client application. See also: [SQL](#), [subquery](#).

read lock

A read lock is one of three types of lock supported by SQL Anywhere to support concurrency, as part of SQL Anywhere's transaction processing capabilities.

When a transaction reads a row, employing one of the more secure isolation levels available (level 2 or 3), other transactions can read the row, but cannot update it.

See also: phantom lock, write lock, locking.

referential integrity

The tables of a relational database are related to each other by foreign keys. SQL Anywhere provides tools that maintain the referential integrity of the database: that is, ensure that the relations between the rows in different tables remain valid. See also: [foreign key](#), [entity integrity](#).

relationship

A step in the Entity-Relationship design of databases, is to identify the relationships between the entities that you have identified.

One-to-many and one-to-one relationships become foreign key relationships in the final implementation, while a many-to-many relationship becomes a table. See also: entity.

remote DBA authority

The Message Agent should be run using a user ID with REMOTE DBA authority, to ensure that actions can be carried out, without creating security loopholes.

remote user

In SQL Remote replication, a SQL Anywhere user who has been granted remote permissions in a replication setup. When the remote database is extracted from the consolidated database, the remote user becomes the publisher of the remote database, able to exchange publication updates with the consolidated database. While SQL Anywhere groups can also be granted remote permissions, note that users in these "remote groups" do not inherit remote permissions from their group.

replication

For databases, a process by which the changes to data in one database (including creation, updating, and deletion of records) are also applied to the corresponding records in other databases. SQL Anywhere supports replication using SQL Remote or Sybase Replication Server.

replication frequency

In SQL Remote replication, a setting for each remote user that determines how often the publisher's message agent should send replication messages to that remote user. The frequency can be specified as on-demand, every given interval, or at a certain time of day.

replication message

In SQL Remote replication, a discrete communication that is sent from a publishing database to a subscribing database. Messages can contain a mixture of publication updates and passthrough statements (manual SQL statements such as DDL).

resource authority

Resource authority is the permission to create and modify objects of a database schema. Resource authority can be granted only by the DBA. See also: DBA, permissions.

role name

Each foreign key is assigned a name, called a role name, to distinguish it from other foreign keys in the same table. If no role name is specified by the user, the role name is set to the name of the primary table.

rollback

When a user sends a rollback SQL statement to the database engine, all work since the last savepoint or since the beginning of the current transaction is undone, and no changes are made to the database by any of the instructions. See also: [commit](#), [transaction](#), [rollback log](#).

rollback log

A log kept in order to cancel changes made to database tables. The rollback log is needed in the event of a ROLLBACK request or a system failure. There is a separate rollback log for each transaction. When a transaction is complete, its rollback log is deleted.

row

All data in relational databases such as SQL Anywhere is held in tables, composed of rows and columns. Each row holds a separate occurrence of each column. In a table of employee information, for example, each row contains information about a particular employee. See also: [table](#), [column](#).

row-level trigger

A trigger that executes BEFORE or AFTER each row modified by the triggering insert, update, or delete operation is changed.

runtime database engine

The SQL Anywhere Desktop Runtime engine is a royalty-free redistributable database engine. The runtime database engine supports all the database manipulation language features of the full SQL Anywhere, with the exception of procedures and triggers. Also, the runtime database engine does not employ a transaction log.

savepoint

Within a transaction, a SAVEPOINT statement allows flexibility in committing and rolling back work. Work since the most recent savepoint can be undone using ROLLBACK TO SAVEPOINT. The RELEASE SAVEPOINT disallows any future rollbacks to the most recent savepoint. Before SQL Anywhere version 4.0, savepoints were called subtransactions. See also: [transaction](#), [commit](#), [rollback](#).

schema

The structure of a database is called the schema. The schema is held in the system tables.

The schema includes the complete definitions of each database object in the database, including tables, indexes, views, procedures, and triggers.

search condition

In SQL, a search condition is a WHERE clause in a SELECT statement.

session

Communications across a network may take place in a session, (also called a connection, or virtual circuit) or in a connectionless manner, using a datagram method. When a connection is established, a route from the source computer to the destination computer is part of the session setup, and routing decisions are not required for every packet.

Network server editions of SQL Anywhere use sessions for their NetBIOS and local Named Pipes communication links.

SMTP

Simple Mail Transfer Protocol. This is a message system supported by SQL Remote. A typical SMTP mail address takes the form **boss@myown.com**.

SQL

Structured Query Language (SQL) is the language used to communicate to SQL Anywhere databases. SQL is very widely used in database applications, and in order to ensure compatibility among databases, SQL is the subject of standards set by several standards bodies.

SQLCA

A SQL Connection Area (SQLCA) is a segment of database client application code that manages the connection parameters governing the connections between the client application and a database. See also: [programming interface](#).

SQL Remote

An asynchronous message-based replication system for two-way server-to-laptop, server-to-desktop, and server-to-server replication between SQL Anywhere databases.

server

In SQL Anywhere, servers are database engines--the programs that manage the physical structure of the database and process queries on its data. Servers can be standalone engines or network servers. In SQL Central, standalone engines and network servers are both called servers.

stand-alone engine

A SQL Anywhere database engine that runs on the same PC as the client application. A stand-alone engine is typically for a single user on a single PC, but can support several concurrent connections from that user.

statement

SQL allows several kinds of statement. Some statements modify the data in a database (commands), others request information from the database (queries), and others modify the database schema itself. See also: [SQL](#), [query](#).

statement-level trigger

A trigger that executes after the entire triggering statement is completed.

store-and-forward

Store-and-forward exchange of information is typical of message based systems, and allows information to be exchanged without a direct connection between applications.

stored procedure

Stored procedures are procedures kept in the database itself, which can be called from client applications. Stored procedures provide a way of providing uniform access to important functions automatically, as the procedure is held in the database, not in each client application. See also: [trigger](#).

subquery

A subquery is a component of a SQL query (SELECT statement) that is itself a query. Subqueries are important tools in constructing complex queries to databases. See also: [SQL query](#).

submission

In a SQL Remote installation, changes made to a remote database and sent to the consolidated database are a submission. If and only if the changes are successfully applied at the consolidated database they will be replicated to other databases.

subscriber

In SQL Remote replication, a remote user who is subscribed to one or more of a database's publications.

subscribing

In a Replication Server or SQL Remote installation, a database that has subscribed to a replication or publication receives updates of changes to the data in that replication or publication.

subscription

In SQL Remote replication, a link between a publication and a remote user, allowing the user to exchange updates on that publication with the consolidated database. The user's subscription may include an argument (value) for the publication's SUBSCRIBE BY parameter (if any).

subtransaction
See [savepoint](#).

synchronization

In SQL Remote replication, the process by which SQL Remote deletes all existing rows from those tables of a remote database that form part of a publication, and copies the publication's entire contents from the consolidated database to the remote database. Synchronization is performed during the initial extraction of the remote database from the consolidated database, and may also be necessary later if a remote database becomes corrupt or gets out of step with the consolidated database (and cannot be repaired using passthrough mode). Synchronization can be accomplished by bulk extraction (the recommended method), by manually loading from files, or by sending synchronization messages through the message system.

system failure

A system failure occurs when a power failure or some other failure causes a computer to fail while there are partially completed transactions. See also: [media failure](#), [transaction](#), [backup](#).

system catalog

The system catalog is the list of all tables and views in the database.

The SQL Anywhere system view `SYS.SYSCATALOG` presents this information.

system object

In a database, a table, view, stored procedure, or user-defined data type that is pre-defined by SQL Anywhere. System tables store information about the database itself, while system views, procedures, and user-defined data types largely support Sybase Transact-SQL compatibility.

system tables

Every SQL Anywhere database includes a set of tables called the system tables, which hold information about the database structure itself: descriptions of the tables, users and their permissions, and so on.

The system tables are created and maintained automatically by the database engine. They are owned by the special user ID **SYS**, and cannot be modified by database users.

system views

Every SQL Anywhere database includes a set of views, which present the information held in the system tables in a more easily understood format.

table

All data in relational databases is stored in tables. Each table consists of rows and columns. Each column carries a particular kind of information (a phone number, a name, and so on), while each row specifies a particular entry. Each row in a relational database table must be uniquely identifiable by a primary key. See also: [database](#), [row](#), [column](#), [primary key](#), [database object](#), [owner](#).

TCP/IP

Transmission Control Protocol/Internet Protocol (TCP/IP) is a network protocol supported by SQL Anywhere. See also: [protocol](#), [IPX](#), [NetBIOS](#).

temporary table

Data in a temporary table is held for a single connection only. Global temporary table definitions (but not data) are kept in the database until dropped. Local temporary table definitions and data exist for the duration of a single connection only.

token ring

A token ring is a specification of a particular network architecture and protocol. A ring architecture is a topology in which every computer on the ring has a wire in and a wire out and forms a closed loop. A token is passed around the ring to arbitrate between computers that wish to communicate at the same time.

topics

Each separate panel in an online help system is a topic.

Transact-SQL

The SQL dialect used in Sybase SQL Server. SQL Anywhere supports a large subset of Transact-SQL.

transaction

A transaction is a logical unit of work that should be processed in its entirety by the database (though not necessarily at once) or not at all. SQL Anywhere supports transaction processing, with locking features built in to allow concurrent transactions to access the database without corrupting the data. Transactions begin following a COMMIT or ROLLBACK statement and end either with a COMMIT statement, which makes all the changes to the database required by the transaction permanent, or a ROLLBACK statement, which undoes all the changes made by the transaction. See also: [locking, concurrency](#).

transaction blocking

A transaction becomes blocked when it must wait for another transaction to finish before it can carry out its task. Proper design of transactions by application developers can minimize the occurrence of transaction blocks, which slow down database operation. See also: [transaction](#), [locking](#).

transaction log

A log storing all changes made to a database, in the order in which they are made. In the event of a media failure on a database file, the transaction log is essential for database recovery. The transaction log should therefore be kept on a different device from the database files for optimal security.

The SQL Anywhere Desktop Runtime System does not employ a transaction log.

transaction log mirror

An identical copy of the transaction log file, maintained at the same time. Every time a database change is written to the transaction log file, it is also written to the transaction log mirror file. A mirror file should be kept on a separate device from the transaction log, so that if either device fails, the other copy of the log keeps the data safe for recovery.

transaction processing

A database engine that supports transaction processing is capable of ensuring that the results of each transaction are either stored in the database in their entirety or not at all. Transaction processing is a key element in promoting secure and reliable databases.

translation driver

A translation driver is a part of the data link layer of a protocol stack. Data link layers conform to either ODI or NDIS specifications, and translation drivers supplied by networking software vendors enable multiple protocol stacks, requiring both ODI and NDIS drivers, to operate with a single network adapter.

trigger

A trigger is a procedure stored in the database that is executed automatically by the database engine whenever a particular action occurs, such as a row being updated. Triggers are used to enforce complex forms of referential integrity, or to log activity on database tables. See also: [integrity](#), [stored procedure](#).

two-phase commit

A mechanism to coordinate transactions across multiple database servers; only needed for distributed databases.

See also: [commit](#), [transaction](#).

UNC filename

A filename conforming to the Universal Naming Convention. A typical filename has the following structure: \\computer_name\shared_directory_name\sub_directory\filename.ext.

For example, a computer named **dobrien** has a directory **c:\public**, which is shared as "public". This directory has a subdirectory called "sample", containing a file called "sample.db". The UNC filename for this file would be: \\dobrien\public\sample\sample.db

unload

Unloading a database dumps the structure and/or data of the database to text files (command files for the structure, ASCII comma-delimited files for the data). This may be useful for creating extractions, creating a backup of your database, or building new copies of your database with the same or slightly modified structure. You can also unload the data (but not the structure) of a particular table.

updates

In replication, each set of changes sent from one database to another is an update to a publication or replication.

upgrade

A major release of SQL Anywhere (formerly Watcom SQL) generally means a revised internal database format (to support new database features). When you upgrade your SQL Anywhere software to a major revision (for example, moving from 4.0 to 5.0), you should upgrade your existing databases to the new database format (after making backups of them).

user-defined data type

A named combination of base data type, default value, check condition, and nullability. Defining similar columns using the same user-defined data type encourages consistency throughout the database.

user account

Every connection with a database requires a user account. The permissions that a user has are tied to their user account. A user account consists of a user ID and password.

user ID

A string of characters that identifies the user when connecting to a particular database. The user ID, together with a password, constitute a user account. See also: [permissions](#), [connection](#), [DBA](#).

validate

When the information in a database, or a database table, is checked for integrity it is validated. See also: entity integrity, referential integrity.

view

A view is a computed table. Every time a user uses a view of a particular table, or combination of tables, it is recomputed from the information stored in those tables. Views can be useful for security purposes, and to tailor the appearance of database information to make data access straightforward. As a permanent part of the database schema, a view is a database object. See also: [table](#), [database object](#).

VIM

Vendor-Independent Messaging, a message system used in cc:Mail and Lotus Notes. A typical VIM address takes the form **jsmith**.

Watcom-SQL

The SQL dialect used in SQL Anywhere. Watcom-SQL conforms closely to ANSI SQL.

Winsock

Winsock is a specification of the socket library with extensions. The socket library is a collection of functions used to interface to a number of different transport-level protocols. The socket library was initially specified by the University of California at Berkeley for the TCP/IP protocol.

write file

If a database is used with a write file, all changes made to the database do not modify the database itself, but instead are made to the write file. Write files are useful in applications development, so the developer can have access to the database without interfering with it. Also, write files are used in conjunction with compressed databases and other read-only databases.

write lock

A write lock is one of three types of lock supported by SQL Anywhere to support concurrency, as part of SQL Anywhere's transaction processing capabilities.

When a transaction updates or inserts a row, it acquires a write lock on the row. No other transaction can acquire a lock on the same row.

See also: read lock, phantom lock, locking.

WSQL DDE

A high level programming interface to SQL Anywhere for Windows applications.

WSQL HLI

A high level programming interface to SQL Anywhere.

sqlcode

A numeric error code identifying database errors. Negative values are errors, while positive values are warnings. SQLCODE 0 indicates successful completion.

See also [sqlstate](#).

sqlstate

A numeric error code identifying database errors. SQL Anywhere provides both the ODBC SQLSTATE, returned to ODBC applications, and the ANSI SQLSTATE, which is returned in the SQLCA to Embedded SQL applications.

atomic

A set of operations is atomic if it cannot be broken down into smaller pieces. Transactions are referred to as atomic because they must either be processed entirely or not at all. The body of a procedure or trigger can be forced to be atomic by adding the keyword `ATOMIC` after the `BEGIN` keyword.

dirty

A database page is considered dirty when a change is made to it. Before a page is made dirty, a copy of the original page is made and held as the checkpoint log.

SQL Communication Area

The SQL Communication Area (SQLCA) is a data structure used for passing data between a client application and the database engine. Both ODBC and Embedded SQL use one or more SQLCA's to communicate with the database engine.

user groups

Managing permissions of many users is simplified if you assign users to user groups, and GRANT or REVOKE permissions from those groups rather than from individual users.

SQL Descriptor Area
See [SQLDA](#).

SQLDA

The SQL Descriptor Area (SQLDA) is a data structure used for passing dynamic SQL statements to the database engine in Embedded SQL.

serializable

A set of concurrent operations is executed in a serializable manner if the net effect of the execution is identical to the result of executing each operation in turn, without any concurrency.

An isolation level of 3 is needed to guarantee the serializable execution of transactions.

conversation

A conversation between a client application and a server application is an organized exchange of data. The term is commonly used in discussing DDE operations.

NT service

In the Windows NT operating system, applications set up as NT services can run even when the user ID starting them logs off the machine.

Running a SQL Anywhere database server as a service under NT allows databases to keep running while not tying up the machine on which they are running.

service name

In DDE, the service name is the top level identifier for a DDE conversation.

All conversations between a client application and the WSQL DDE Server must use the service name **WSQLDDE**.

topic name

In DDE conversations using the WSQL DDE interface, the topic name identifies the user and optionally which database the user wishes to query.

The topic name must be of the form "**Username,Password,Database**" or "**Username,Password**".

item name

In DDE conversations using the WSQL DDE interface, the item name specifies the action to be performed by the WSQL DDE server.

wildconnects

In DDE, a wildconnect is an attempt to start a conversation without a service name or a topic name.

Wildconnects are not supported by the WSQL DDE server.

links

In DDE, a link is a method of exchanging data. Any DDE conversation takes place through a DDE link.

The type of link supported by the WSQL DDE server is called a cold link. Some other applications support links called a warm link and a hot link.

cold link

In a DDE cold link, the client must request data, and the server immediately supplies the data.

Cold links are also sometimes called **manual links**.

warm link

In a **DDE** warm link, the server notifies the client when data that the client is interested in has changed. The client must then request the data if it requires the new data.

Warm links are also sometimes called **notify links**. WSQL DDE Server does not support warm links.

hot link

In a DDE hot link, the server sends data of interest to the client as soon as the data changes.

Hot links are also sometimes called **automatic links**. WSQL DDE Server does not support hot links.

userid

A correct userid parameter of a connect string is required for a user to connect to a database, and identifies the user to the database. Each user's permissions are defined according to their userid.

Open Database Connectivity
See [ODBC](#).

Dynamic Data Exchange
See [DDE](#).

database application
See client application.

client application

In a database context, a client application is any application that communicates with a database engine.

client side

The client side of a client/server arrangement may consist of software and hardware.

The client-side software consists of a client application, and in a network setup also of DBCLIENT SQL Anywhere application, together with the host operating system and necessary network software.

The client-side hardware is the computer on which the client-side software is being run.

server side

The server side of a client/server arrangement may consist of both software and hardware, in addition to database files.

The server-side software consists of the SQL Anywhere database engine, and in a network setup also of the host operating system and necessary network software.

The server-side hardware is the computer on which the database engine is running, and the devices on which the database files are stored.

Structured Query Language
See [SQL](#).

SQL Anywhere Client
The SQL Anywhere Client is the DBCLIENT application.

network request manager

The network request manager is a component of the SQL Anywhere network server which handles interaction with the SQL Anywhere Client.

root file

Unless you specifically create multiple files for your database using the CREATE DBSPACE statement, the database root file is the file your database is held in: the database file.

If your database is held in multiple database files, the root file is the first file created, which holds the system tables. When supplying the database file parameter in a connection string, you need to supply the root file name.

unique constraint

A unique constraint identifies one or more columns that uniquely identify each row in the table. A table may have several unique constraints.

See also: [constraint](#)

primary key constraint

A primary key constraint identifies one or more columns that uniquely identify each row in a table. Imposing a primary key constraint on a set of columns makes that set the primary key for the table. The primary key usually identifies the best identifier for a row.

See also: constraint.

foreign key constraint

A foreign restricts the values for a set of columns to match the values in a primary key or uniqueness constraint of another table. For example, a foreign key constraint could be used to ensure that a customer number in an invoice table corresponds to a customer number in the customer table. Imposing a foreign key constraint on a set of columns makes that set the foreign key in a foreign key relationship.

See also: constraint.

check constraint

A check constraint allows specified conditions on a column or set of columns in a table to be verified.

See also: [constraint](#).

unique index

A unique index on a table is an index for which it is ensured that no two rows have identical values in all columns in the index.

foreign table

A foreign table is the table containing the foreign key in a foreign key relationship.

See also: [foreign key](#), [primary table](#), [referential integrity](#).

primary table

A primary table is the table containing the primary key in a foreign key relationship.

See also: [primary key](#), [foreign table](#), [referential integrity](#).

bind variable

In Embedded SQL, a bind variable is a host variable used to pass values to the database engine.

host variable

In Embedded SQL, a host variable is a C variable which is identified to the SQL preprocessor. Host variables can be used to send values to the database engine or receive values from the database engine.

See also: bind variable.

correlation name

In a SQL SELECT query, a correlation name can be given to a table. The correlation name must then be used to refer to the table in the rest of the query.

A correlation name is a convenient way of reducing error and effort in developing long queries that refer to tables with complex names.

join type

A JOIN clause in a SELECT query is one of several join types. The join types supported by SQL Anywhere are cross join, natural join, key join, inner join, and outer join.

key join

A key join is a join type used in SELECT queries that take information from more than one table. The key join restricts results to rows where the foreign key value in one table is equal to the corresponding primary key value in the other table.

join condition

For any join type in a join clause of a SQL query, except for a cross join, a join condition can be specified.

current query

The current query is the SELECT or INPUT command that generated the information displayed in the ISQL data window.

projection

The result of a SELECT query with DISTINCT specified has all duplicate rows eliminated, compared to the result that would be obtained without the DISTINCT specifier.

The DISTINCT result is called the projection of the result.

string

In SQL, a string is any sequence of characters enclosed in apostrophes ('single quotes'). To represent an apostrophe inside a string, use a sequence of two apostrophes. To represent a new line character, use a backslash followed by an n (n). To represent a backslash character, use a sequence of two backslashes (\).

dynamic link library
See DLL.

interprocess communication

In operating systems that enable several applications to run at once, interprocess communication allows applications to work together.

For example, Named pipes is a method of interprocess communication supported by OS/2 and Windows NT. DDE is a method of interprocess communication supported by the Microsoft Windows operating environment and the Windows NT operating system.

data buffer

In DDE, a data buffer is one of two pieces of information sent from a client application to the WSQL DDE interface. The other is the item name.

poking

In DDE, poking is one of three main ways for a DDE client to exchange information with a DDE server. Poking sends information from the client to the server.

executing

In DDE, executing is one of three main ways for a DDE client to exchange information with a DDE server. Executing sends a command from the client to the server: no data is returned by a DDE Execute transaction.

requesting

In DDE, requesting is one of three main ways for a DDE client to exchange information with a DDE server. A request lets the DDE server know that the client wants to receive the results of a query.

user
See user ID.

nonexclusive lock

A lock is nonexclusive when other transactions can acquire a lock of similar type on a row. The read lock is nonexclusive, while the write lock is exclusive.

exclusive lock

A lock is exclusive when other transactions cannot acquire a lock of similar type on a row. The write lock is exclusive, while the read lock is nonexclusive.

place holder

In Embedded SQL, are included in the SQL Descriptor Area to indicate places where a host variable is to be accessed.

cost

SQL Anywhere has a query optimizer that picks a strategy for executing each query by estimating the cost of different approaches, and choosing the route with the lowest cost. The cost of a query is the number of disk read and write operations required to carry out the query.

outer reference

A WHERE clause in a subquery can refer to columns in tables that do not form part of the subquery, but do form part of the main query. This kind of reference is called an outer reference. A subquery that contains an outer reference is called a correlated subquery.

correlated subquery

A subquery that contains an outer reference.

ODBC-enabled

An ODBC-enabled application is a client application that has an ODBC interface implemented. SQL Anywhere conforms to ODBC 2.1, level 2.

Many application design systems, such as Powersoft PowerBuilder, are ODBC-enabled applications.

ODBC Administrator

The ODBC Administrator is a Microsoft program included with SQL Anywhere for setting up ODBC data sources.
See also: [data_source](#).

updated

A row in a database is updated if one or more of its values is altered.

deleted

A row in a database is deleted if it is removed from the database.

inserted

Inserting a row in a database table creates a new row.

optional

A foreign key is optional if it is allowed to contain the NULL value.

See also: mandatory

mandatory

A foreign key is mandatory if it is not allowed to contain the NULL value.

See also: optional

concurrent

Multi-user versions of SQL Anywhere support concurrent applications: separate connections which may address the same data in the database, running at the same time. SQL Anywhere provides transaction processing and automatic row-level locking to ensure that information remains consistent and that each concurrent application sees a consistent set of data. See also: [transaction](#), [locking](#).

deadlock

A deadlock occurs when two or more concurrent transactions become blocked in such a way that they cannot become unblocked. In this situation one of the transactions must roll back its work in order for the other transaction(s) to continue.

handle

A handle is an integer that uniquely identifies an object. ODBC makes use of handles to identify environments, connections, and statements.

client/server

A software architecture where one application (the client) obtains information from and sends information to another application (the server).

In a database context, the server is a database engine, and the client is a database client application. The two applications often reside on different computers on a local area network.

DDE transactions

In DDE, a transaction is an exchange of information between the DDE client and the DDE server. poking, executing, and requesting are the three types of DDE transaction.

domain

Every column is associated with a particular domain: the data type and range of values that constitute valid data for that column. See also: [data type](#).

grantor

The user ID granting a permission to another user ID is the grantor. See also: [grantee](#).

grantee

A user ID receiving a permission from another user ID is a grantee. See also: [grantor](#).

procedures
See stored procedure.

interface

The boundary between two distinct entities is an interface. In the context of a protocol stack, an interface between the different layers governs how information is passed down and up the stack.

server name

When a database server is started it is assigned a server name. Client applications specify the server to which they want to connect by using the server name.

The default server name is the first database name.

database server

A multi-user database engine is also called a database server.

columns

All data in relational databases such as SQL Anywhere is held in tables, composed of rows and columns. Each column holds a particular type of information. See also: [table](#), [row](#).

tables

All data in relational databases is stored in tables. Each table consists of rows and columns. Each column carries a particular kind of information (a phone number, a name, and so on), while each row specifies a particular entry. Each row in a relational database table must be uniquely identifiable by a primary key. See also: [database](#), [row](#), [column](#), [primary key](#), [database object](#), [owner](#).

rows

All data in relational databases such as SQL Anywhere is held in tables, composed of rows and columns. Each row holds a separate occurrence of each column. In a table of employee information, for example, each row contains information about a particular employee. See also: [table](#), [column](#).

indexes

An index on one or more columns of a database table allows fast lookup of the information in these columns, and so can greatly speed up database queries. Specifically, indexes assist WHERE clauses in SELECT statements.

views

A view is a computed table. Every time a user uses a view of a particular table, or combination of tables, it is recomputed from the information stored in those tables. Views can be useful for security purposes, and to tailor the appearance of database information to make data access straightforward. As a permanent part of the database schema, a view is a database object. See also: [table](#), [database object](#).

triggers

A trigger is a procedure stored in the database that is executed automatically by the database engine whenever a particular action occurs, such as a row being updated. Triggers are used to enforce complex forms of referential integrity, or to log activity on database tables. See also: [integrity](#), [stored procedure](#).

stored procedures

Stored procedures are procedures kept in the database itself, which can be called from client applications. Stored procedures provide a way of providing uniform access to important functions automatically, as the procedure is held in the database, not in each client application. See also: [trigger](#).

data type size

For certain data types, the number of characters that the data type can contain.

data type precision

For decimal and numeric data types, the total number of digits (including scale) allowed in the number.

data type scale

For decimal and numeric data types, the number of digits allowed after the decimal point.

ignore trailing blanks

By default, trailing blanks are ignored for comparison purposes, and Embedded SQL programs pad strings fetched into character arrays. For example, the two strings 'Smith' and 'Smith ' would be treated as equal in a database created with trailing blanks ignored.

The database creation option to ignore trailing blanks is provided for compatibility with the ISO/ANSI SQL standard. The default is that blanks are significant for comparisons, which was the only behavior supported in releases up to Watcom SQL Version 3.0.

SUBSCRIBE BY

In a subscription to a publication, a SUBSCRIBE BY value is matched against the SUBSCRIBE BY column or expression for rows in the table. The subscriber receives all rows for which the value of the column or expression is equal to the SUBSCRIBE BY value.

Keyword Search

[Glossary](#)

