

NOTE: This Technical Note has been [retired](#). Please see the [Technical Notes](#) page for current documentation.

Technical Note PT01

Accessing Globals From MPW Assembly Language

CONTENTS

[Introduction](#)
[Pascal Source](#)
[C Source](#)
[References](#)
[Downloadables](#)

This technical note demonstrates how to access MPW Pascal and MPW C globals from the MPW Assembler.

[Jan 01 1987]

Introduction

To allow access of MPW Pascal globals from the MPW Assembler, you need to identify the variables that you wish to access as external. To do this, use the `{Z+}` compiler option. Using the `{Z+}` option can substantially increase the size of the object file due to the additional symbol information (no additional code is generated and the symbol information is stripped by the linker). If you are concerned about object file size, you can "bracket" the variables you wish to access as external variables with `{Z+}` and `{Z-}`. Here's a trivial example:

[Back to top](#)

Pascal Source

```
PROGRAM MyPascal;
USES
    MemTypes, QuickDraw, OSIntf, ToolIntf;

VAR
    myWRect: Rect;
    {Z+} {make the following external}
    myInt: Integer;
    {Z-} {make the following local to this file (not lexically local)}
    err: Integer;

PROCEDURE MyAsm; EXTERNAL; {routine doubles the value of myInt}

BEGIN {PROGRAM}
    myInt:= 5;
    MyAsm; {call the routine, myInt will be 10 now}
    writeln('The value of myInt after calling myAsm is ', myInt:1);
```

Assembly Source for Pascal

```
MyAsm    CASE    OFF           ;treat upper and lower case identically
        PROC    EXPORT        ;CASE OFF is the assembler's default
        IMPORT  myInt:DATA     ;we need :DATA, the assembler assumes CODE
        ASL.W   #1,myInt       ;multiply by two
        RTS                      ;all done with this extensive routine, whew!
```

The variable `myInt` is accessible from assembler. Neither `myWRect` nor `err` are accessible.

[Back to top](#)

C Source

In an MPW C program, one need only make sure that `MyAsm` is declared as an external function, that `myInt` is a global variable (capitalizations must match) and that the `CASE ON` directive is used in the Assembler:

```

#include <types.h>
#include <quickdraw.h>
#include <fonts.h>
#include <windows.h>
#include <events.h>
#include <textedit.h>
#include <dialogs.h>
#include <stdio.h>

extern MyAsm(); /* assembly routine that doubles value of myInt */
short myInt; /* we'll change the value of this from MyAsm */

main()
{
    WindowPtr MyWindow;
    Rect myWRect;

    myInt = 5;
    MyAsm();
    printf(" The value of myInt after calling myAsm is %d\n",myInt);
}

```

Assembly source for C

```

MyAsm    CASE    ON           ;treat upper and lower case distinct
        PROC    EXPORT       ;this is how C treats upper and lower case
        IMPORT  myInt:DATA    ;we need :DATA, the assembler assumes CODE
        ASL.W   #1,myInt      ;multiply by two
        RTS                ;all done with this extensive routine, whew!

```

[Back to top](#)

References

MPW Reference Manual

[Back to top](#)

Downloadables



Acrobat version of this Note (K).

[Download](#)

Technical Notes by [Date](#) | [Number](#) | [Technology](#) | [Title](#)
[Developer Documentation](#) | [Technical Q&As](#) | [Development Kits](#) | [Sample Code](#)