

# UUCP modifications

This is all the files that need to be changes in order to increase your uucp to 19200 baud.

/etc/gettytab

```
#
# Fast dialup terminals, 9600/2400/1200/300 rotary (can start either way)
#
j|D19200:nx=D9600:tc=19200-baud:
k|D2400|Fast-Dial-2400:\
    :nx=D1200:tc=2400-baud:
3|D1200|Fast-Dial-1200:\
    :nx=D300:fd@:tc=1200-baud:
5|D300|Fast-Dial-300:\
    :nx=D9600:tc=300-baud:
```

/etc/ ttys

ttyda	"/usr/etc/getty D9600"	unknown	off
ttydb	"/usr/etc/getty D19200"	dailup	on

/etc/remote

cua9600|Dial-out on cua at 9600 baud:\n:dv=/dev/cua:br#9600:el=^C^S^Q^U^D:ie=%\$:oe=^D:

cub19200|Dial-out on cub at 19200 baud:\n:dv=/dev/cub:br#19200:el=^C^S^Q^U^D:ie=%\$:oe=^D:

ttya9600|Hardwire on ttya at 9600 baud:\n:dv=/dev/ttya:br#9600:el=^C^S^Q^U^D:ie=%\$:oe=^D:

ttyb19200|Hardwire on ttyb at 19200 baud:\n

```
:dv=/dev/ttyb:br#19200:el=^C^S^Q^U^D:ie=%$:oe=^D:
a2400|2400Baud:\
:dv=/dev/cua:br#2400:el=^C^S^Q^U^D:ie=%$:oe=^D:
b19200|19200Baud:\
:dv=/dev/cub:br#19200:el=^C^S^Q^U^D:ie=%$:oe=^D:
cub19200|Dial-out on cub at 19200 baud:\
:dv=/dev/cub:br#19200:el=^C^S^Q^U^D:ie=%$:oe=^D:
```

/etc/uucp/L-devices

```
# For those unusual modems which have dialing scripts in L.sys which know how
# to dial them.
#
DIR cub unused 300  direct
DIR cub unused 1200 direct
DIR cub unused 2400 direct
DIR cub unused 9600 direct
```

**DIR cub unused 19200 direct**

**/etc/uucp/L.sys**

# L.sys: Please read UUAIDS/L.sys.samples for some discussions on how to  
# use this file as well as the documentation that can be found in the  
# Digital Librarian on uucp.  
#  
**hostname Any DIR 19200 cub "" ATDT3331111 ogin: user ssword: test**