

PhxAss

COLLABORATORS

	<i>TITLE :</i> PhxAss		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		June 24, 2025	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	PhxAss	1
1.1	PhxAss V4.36 Documentation (04-Jun-97)	1
1.2	Preface	1
1.3	Modifications since PhxAss V2.xx	2
1.4	Modifications since PhxAss V3.00	3
1.5	Modifications since PhxAss V4.00	5
1.6	Bug fixes since V2.11	9
1.7	Bug fixes since V3.00	9
1.8	Bug fixes since V4.00	12
1.9	Starting PhxAss	15
1.10	Command line arguments	16
1.11	Programmer Information	21
1.12	Comments	21
1.13	Labels	21
1.14	Executable M68000 instructions	22
1.15	General Format	22
1.16	M68000 Standard Addressing Modes	23
1.17	68020+ Extended Addressing Modes	24
1.18	68020+ Suppressed Registers	25
1.19	M68000 Instructions supported by PhxAss	26
1.20	Integer Instructions (68000,68010,68020,68030,68040,68060)	26
1.21	Integer Instructions (68010,68020,68030,68040,68060)	28
1.22	Integer Instructions (68020,68030,68040,68060)	28
1.23	Integer Instructions (68040,68060)	29
1.24	Integer Instructions (68060)	29
1.25	MOVEC Control Registers (Rc)	29
1.26	Floating Point Instructions (68881,68882,68040,68060)	30
1.27	Floating Point Instructions (68040,68060)	32
1.28	PMMU Instructions (68851)	32
1.29	PMMU Instructions (68030)	33

1.30	PMMU Instructions (68040,68060)	33
1.31	Expressions	33
1.32	Assembler Directives	35
1.33	EQU	37
1.34	EQU.x	37
1.35	EQR	37
1.36	REG	37
1.37	FREG	38
1.38	FEQR	38
1.39	SET	38
1.40	SET.x	39
1.41	INT	39
1.42	RSRESET,CLRSO	39
1.43	RSSET,SETSO	39
1.44	RS,SO	39
1.45	CLRFO	40
1.46	SETFO	40
1.47	FO	40
1.48	IDNT	40
1.49	SUBTTL	40
1.50	COMMENT	41
1.51	LIST	41
1.52	NOLIST	41
1.53	OPT	41
1.54	MACRO, ENDM	41
1.55	MEXIT	42
1.56	END	42
1.57	FAIL	42
1.58	ECHO	42
1.59	MACHINE	43
1.60	MC680x0	43
1.61	FPU	43
1.62	PMMU	43
1.63	SECTION	44
1.64	CODE, CSEG	44
1.65	DATA, DSEG	44
1.66	CODE_C, CODE_F, DATA_C, DATA_F, BSS_C, BSS_F	44
1.67	BSS	44
1.68	BSS	44

1.69 GLOBAL	45
1.70 OFFSET	45
1.71 RORG	45
1.72 INCDIR	45
1.73 INCLUDE	45
1.74 INCBIN	46
1.75 XREF	46
1.76 NREF	46
1.77 XDEF	46
1.78 PUBLIC	46
1.79 ORG	47
1.80 LOAD	47
1.81 FILE	47
1.82 SFORM	47
1.83 STYPE	47
1.84 TRACKDISK	48
1.85 OUTPUT	48
1.86 SYMDEBUG	48
1.87 LINEDEBUG	48
1.88 NEAR	49
1.89 FAR	49
1.90 INITNEAR	49
1.91 DC	49
1.92 DCB, BLK	50
1.93 DS, DX	50
1.94 CNOP	50
1.95 EVEN	51
1.96 IFcond, ELSEIF, ELSE, ENDIF, ENDC	51
1.97 PROCSTART,PROCEND	51
1.98 REPT/ENDR	51
1.99 SAVE	51
1.100RESTORE	52
1.101DEBUG	52
1.102DSOURCE	52
1.103Compiler Compatibility	52
1.104PhxOpts	53
1.105Environment Variables	53
1.106Linker	53
1.107Assembler Errors	53
1.108History / Literature	59
1.109Acknowledgements	60
1.110Known bugs in version V4.36	61
1.111My Address	61

Chapter 1

PhxAss

1.1 PhxAss V4.36 Documentation (04-Jun-97)

```

  \_____
  \_____/ / / /_____ \ . _ / ____/
  \____/ / / / / / / / / / / / / / /
  \____/ / / / / / / / / / / / / / /
  \____/
  Phantasm's
  
```

```

=====
P H X A S S   V 4 . x x       MC680x0 / 68851 / 6888x   Macro Assembler
=====
  
```

Preface	Command Line Parameters
Modifications since V2.00	Programmer Information
Modifications since V3.00	Assembler Errors
Modifications since V4.00	Linker
Bug fixes since V2.11	History
Bug fixes since V3.00	Acknowledgements
Bug fixes since V4.00	Bugs
Starting PhxAss	The Author's Address

1.2 Preface

PhxAss V4.xx is a highly optimizing macro assembler for Motorola's 680x0 CPUs, 6888x FPU's and 68851 MMU (of course, the 030, 040 and 060 MMUs are also supported).

PhxAss V4.xx requires OS2.04 (V37) as a minimum and does no longer support older operating systems! (Kick 1.x owners: Get PhxAss V3.97, it's the last version running under Kick 1.x). 1 MB of RAM recommended.

PhxAss V4.xx is FREEWARE and © copyright 1994-97 by Frank Wille. Commercial distribution of this program, without a written permission of the author, is strictly forbidden!

Most important features:

- o Symbolic and Source Level Debugging. Possibility to enable Source Level Debugging for high level languages too.
- o Automatic generation of executables (if possible).

- o Creates relocatable Amiga-DOS objects or absolute code (written into a file (raw or Motorola S-Format), into memory or directly onto disk).
- o Small Code and Small Data support (also support for `__MERGED` sections).
- o Listing file, Cross Reference Listing, Equates file.
- o Complete floating point support: You can use complex floating point expressions, including float functions (sine, logarithm, square root, power, etc.), everywhere in your source, e.g. defining float EQUates or SETs.
- o Switches for ten different optimizations.
- o Local symbols (`xxx$` and `.xxx` type).
- o Up to 36 macro parameters.
- o Support for Motorola's old and new operand style (even in 68000 mode).
- o locale.library usage (english, german, swedish, norwegian, italian, danish, dutch, hungarian and french).
- o Nearly all directives of the most popular assemblers like Seka, DevPac or AS (Aztec) are supported. Example: `INCBIN`, `INCDIR`, `CODE_C`, `REPT`, `RS`, `RSRESET`, `EQUR`, `REG`, `OFFSET`, `XDEF`, `XREF`, `PUBLIC`, `OUTPUT` ...
- o PhxAss is able to stay resident in memory.
- o Further development and support is guaranteed for years, because there's no other system for me than the Amiga. :)

You will find two different versions of PhxAss in this distribution:

1. PhxAss: The standard 680x0,FPU,MMU macro assembler.
2. GigaPhxAss: Identical to PhxAss, but source codes are not limited to 65535 lines. Quite useful for assembling Reassembler outputs. I recommend the PD-Reassembler IRA by Tim Rühnen (SiliconSurfer of Phantasm), which was written especially for use with PhxAss.

1.3 Modifications since PhxAss V2.xx

Register symbols (EQUR) must be defined before they are used. This enables a faster addressing mode recognition.

There are some new optimizations possible. The optimize-flags which can be specified after `-n` (since V4.00: OPT) or after the OPT directive have completely changed (see Command line parameters).

If you have enabled the near-code model, all jumps which are referencing external symbols are converted to PC-relative instead of long branch.

The `'*'`-symbol contains the current address. For example a `'bra +10'` would branch to the location 12 bytes behind the `'bra'`-opcode.

New directives: `FPU`, `PMMU`, `CODE_C`, `CODE_F`, `DATA_C`, `DATA_F`, `BSS_C`, `BSS_F` and `INCDIR`.

The instructions and addressing modes of 68020-68060, 68851(PMMU) and 6888x(FPCP) are completely supported. You can use Motorola's new addressing mode style even in the 68000 mode (e.g. `MOVE (4,A5),D0`).

The new addressing mode recognition has no difficulties with parentheses

'()' instead of brackets '[]' to indicate a term. An operand like

```
-([x|y]*z)+6([addr+2,A4,regxy*QSIZE],[outdisp+$10<<(1+3)]),((abc-xyz)+2,A3)
```

would cause no problems.

PhxAss enables floating-point numbers to be used with the 6888x (FPCP) instructions. For example: `fmove.d #3.1415926536,fp7` moves the double-precision number pi to the FPCP register seven.

1.4 Modifications since PhxAss V3.00

V3.10:

- o PhxAss is able to optimize forward-branches, which are coming into their 8/16-bit range by optimization of the subsequent code. As a result, other forward-branches could come into range and are also optimized, and so on.

V3.30:

- o Symbols which are preceded by a '.' will be regarded as local symbols too.
- o A special version of PhxAss is available, which is not limited to the maximum number of 65535 lines.

V3.40:

- o Macro parameters may contain 63 characters now.
- o The extended addressing mode recognition accepts the register symbols ZD0-ZD7 and ZA0-ZA7 to specify a suppressed register.
- o Two new escape codes available:
`\e` = escape (\$1b) and `\c` = control sequence introducer (\$9b).

V3.42:

- o Float constants may be replaced by hex-constants now.
- o When branch-optimization is activated, no extension-checking takes place. The best-possible code will be generated.

V3.47

- o New optimization flag: 'I' forces PhxAss to ignore a 'Too large distance' error.

V3.50

- o '@' is allowed to be the first character of a symbol name, providing the second character is non-numeric.
- o The RORG directive is implemented.
- o Two Devpac-specific directives are also supported now: RSRESET and RS.x for faster reading of (Devpac) include files.
- o The new option '-c' (V4:CASE) can be used to switch off the case-sensitivity.

V3.51

- o RSSET was forgotten in V3.50
- o New directives: IDNT, COMMENT, SUBTTL

V3.55

- o From now on near-data symbols can be accessed not only by Absolute

Addressing but also by Address Register Indirect mode ((An) must be the correct near-data base register). This will make the assembling of your source much faster, because PhxAss has to do less optimizations. As a side effect XREFs will be interpreted correctly and must not be replaced by NREFs.

- o If no unit name is given (by TTL or IDNT), PhxAss will use the name of the source code without extension as the default unit name.
- o The OFFSET directive is supported.

V3.60

- o PhxAss V3.60 is pure! You can use the CLI-command RESIDENT to add it to the resident list.

V3.70

- o '.W' and '.L' displacement-extensions for explicitly activating the 68020 base-displacement mode.

V3.71

- o PROCSTART/PROCEND directives for compatibility with DICE-C.

V3.75

- o Immediate values are checked for their correct size. For example a MOVE.B #\$1234,D0 will lead to an error now.

V3.80

- o New option '-w' (V4:ERRORS) to determine the maximum number of errors which will be displayed before a request.
- o The addressing mode syntax is checked much sharper (e.g. former versions accepted "(SP)-").

V3.81

- o DC.W / DC.L strings must no longer be aligned (e.g. DC.L "x" -> \$00000078).

V3.90

- o PhxAss was completely localized using the "locale.library". Available languages (August '94): english, german, polish.
- o Documentation converted to AmigaGuide format.

V3.92

- o New option '-v' (V4:VERBOSE) for displaying the names of all include files and macros, which are accessed during assembly.
- o New directive ELSEIF for DevPac compatibility.
- o Protection flags for created files will be "rw-d" now.

V3.94

- o The immediate value of BTST, BSET, BCLR and BCHG is checked for valid range (0..7 or 0..31).
- o You will need to enable (s)pecial optimization, to remove a ZRn-index. I think, if somebody explicitly writes 'ZRn', he doesn't want it to be removed by (n)ormal optimization.

V3.95

- o From now on, it is possible to shift distances! Example:
move.w #(label2-label1)>>1,d0
Although this is the same as "(label2-label1)/2", division and multiplication is not allowed on distances, use right- or left shift instead.

You might find it useful to use e.g. "`((label2-label1)>>1)-1`" to initialize the counter for a `DB<cc>-loop` - but be careful! Addition and subtraction after a distance-shift is not really supported, although it seems to work in this special case, if the distance between `label1` and `label2` is even.

The reason is, that the shift is always executed last, which means that the `"-1"` doesn't affect the result of the shifting but the result of the distance directly.

V4.00:

- o Conversion to OS 2. New command line parsing, using `ReadArgs()`, and new argument names.
- o Automatic generation of executable load files. You no longer need to start the linker, if your code doesn't make use of external references. This feature can be disabled by using the CLI parameter `NOEXE`.
- o Source Level Debugging support! By using the CLI parameter `LINEDEBUG`, PhxAss creates a Line Debug block for each section, which contains the addresses of each source code line.
- o Extended operand buffer from 80 to 128 characters.
- o Floating point symbols and constants can be used in expressions of any complexity (like integers) now. PhxAss supports five binary operators, `+` (plus), `-` (minus), `*` (mult.), `/` (division), `^` (power), and six unary operators: `SIN` (sine), `COS` (cosine), `TAN` (tangent), `EXP` (exponent), `LOG` (nat. logarithm), `SQR` (square root).
- o New directive `SET.x` for alterable floating point symbols.
- o New directive `INT` for assigning a float expression to an integer `SET-symbol`.
- o `REPT ... ENDR` directives, like with `DevPac`.
- o Floating point symbols in a listing file are displayed as floats instead of hexadecimals.
- o Float symbols do appear in an equates file.
- o Two new standard optimizations (which I must have forgotten in former versions):
 1. `move.l #0,An -> suba.l An,An` 2. `move.l #x,An -> move.w #x,An`
- o New Small Data Mode: By writing `NEAR A4,-2` only the sections which are named `"__MERGED"`, will be regarded as small data sections (similar to `SAS/C`).
- o 68060 instructions implemented! (except `PLPA`, because it was impossible for me to get its code).

1.5 Modifications since PhxAss V4.00

V4.01:

- o The `INCLUDE` directive does no longer ignore a label in the same line.
- o Implemented abbreviations `'I'` for `'INCPATH'` and `'H'` for `'HEADINC'`.

V4.05:

- o Code Sections are padded with `$4E71` (NOP) instead with `$0000`.
- o PhxAss accepts the `DevPac` options `'C'`, `'D'`, `'L'` and `'O'`.
- o `"DS.L 0"` corresponds to `"CNOP 0,4"`, `"DS.Q 0"` corresponds to `"CNOP 0,8"`, etc.. Previously it works only with `"DS.W 0"`.

V4.10:

- o Operand may contain blanks. Example: `'DC.B 1, 2, 3, 4'`
- o Operators may have the same priorities! Examples: `'*'` and `'/'` or `'<<'`

and '>>'.

- o INCDIR "" is allowed for compatibility reasons.
- o Operands may contain up to 511 characters (127 before V4.10).
- o New parsing routines accelerate PhxAss by 5% - 25% !
- o Swedish catalog.

V4.12:

- o New directive for compatibility: DX. Behaves the same like DS.
- o The 68060 instructions PLPAR and PLPAW are implemented!
- o When assembly fails, PhxAss quits with a return code of 20 instead 1.

V4.14:

- o Implemented the __RS symbol.
- o PhxAss checks for conflicts between macro names and directive or instruction names.
- o "" and '' within a string are recognized as a single ' or " character.
- o If a code section ends with a minimum of eight zero-bytes, no NOP-padding will be performed.
- o Italian catalog.

V4.15:

- o Improved the compatibility with old Seka-sources. The '=' (EQU) directives and labels, terminated by a ':', must no longer be separated from the rest of the line with blanks or TABs.
- o Because of numerous requests, symbol names are allowed to contain dots ('.'). But beware of terminating your symbols with ".w" or ".l"!
- o The new directive SFORM enables the output of Motorola S-Records in absolute mode.
- o Danish catalog.

V4.16:

- o Increased the number of possible macro parameters to 15. Parameter 10 to 15 can be accessed by '\a' to '\f'.
- o New CLI-Parameter "RC=ERRCODE/K/N" for defining the return code in case of an error.

V4.18:

- o MOVEQ #x,Dn with 128<x<255 will force PhxAss to display a warning, which can be disabled by the new NOWARN/S option.
- o Increased the number of possible macro parameters again. Now there are 36 parameters possible! (\0 - \9 and \a - \z)
- o Increased the buffer sizes from 512 to 1024 bytes.
- o French catalog.

V4.19

- o Relocatable symbols will be suffixed by a ' in the listing file.
- o SECTION allows a numerical third parameter to select the type of the section (should be \$40000000 or \$80000000, of course!).
- o Freeware-PhxAss assembles 68030-060, FPU and MMU code too.

V4.20

- o Dutch catalog.
 - o EQU works with register symbols.
 - o New directive FREG. It's like REG, but for the FPU registers. So FMOVEMs without any registers, which could be generated by a compiler, can be removed by optimization.
 - o Support for PHXOPTIONS option files, which are created by PhxOpts from
-

Johan Johanssen. PhxOpts offers a GUI for presetting the options of PhxAss. But of course, the command line options have still priority.

- o PHXASSINC has moved to ENV:PhxAss/ like the global PHXOPTIONS.
- o New directives SAVE and RESTORE to save name and type of the current section. Useful in macros.

V4.21

- o When an error occurs inside a macro, PhxAss will additionally display the line number and source text name from where the macro was invoked.

V4.23

- o Implemented the special 68060 debugging instructions HALT and PULSE (for completeness only ;)

V4.25

- o New directive IF, as an alias for IFNE.

V4.26

- o Two new directives, DEBUG and DSOURCE, enable the generation of source level debugging information for high level languages too.
- o With Branch Optimization enabled, PhxAss can convert a B<cc>.w instruction, which is out of range (in 68000 or 68010 mode), into a B<!cc>.b/JMP combination.

V4.30

- o From now on a difference between two addresses, which are not from the code section, is regarded as absolute! With that all arithmetic and logic operations are allowed. Only for differences from code section, the old constraints are valid.
- o Symbol names may additionally contain the following ascii characters: 192 - 214, 216 - 246 and 248 - 254. This includes for example the german umlauts.
- o MACHINE 68000 may be used to deactivate the PMMU mode.
- o In code sections CNOP uses NOP instructions, if an even amount of bytes is to be filled.
- o There are three new short cuts for the most common optimizations, because the old ones ('*' e.g.) could make problems in Makefiles. OPT 1 = default, OPT 2 = OPT *, OPT 3 = OPT !
- o Optimizing a MOVEM instruction into MOVE affects the condition codes. For this specific optimization the new opt-flag D was introduced, which may be set additionally to the 'M'-flag, if required.
- o Besides CODE_C, DATA_C and BSS_C, SECTION also supports the #?_F types.
- o New command line parameters: MACHINE, FPU and PMMU.
- o The new directive OUTPUT enables to specify the name of the destination file (equivalent to the command line parameter TO, but with a higher priority).

V4.31

- o The XREF sub type EXT_RELREF32 (\$88) for 32-bit PC-relative references is supported. External symbols may be used in really all addressing modes.
- o PhxAss uses buffered I/O (FWrite) for creating the output file.

V4.32

- o PhxAss is FREEWARE.
 - o PhxAss uses its own buffered I/O routines instead those which the dos.library offers. The size of the buffer is adjustable by the new CLI parameter BUFSIZE/K/N, which defaults to 8192.
-

- o The '%' character is allowed in the middle of a symbol name.
- o Macro parameters may have up to 127 characters now.
- o The IDNT directives additionally accepts the syntax where the unit name is specified in the label field, e.g.:
unitname idnt 2,1 testprogram
- o For the bit manipulation instructions, like BTST, BCHG, BSET, BCLR, PhxAss no longer generates an error but only a warning, if the bit-number is out of range.
- o Besides #\$xxxx, #:xxxx is also allowed in the operand of an FPU instruction, to specify a hexadecimal constant.
- o New assembler directives. Structure offset: SO, CLRSO, SETSO. Frame offset: FO, CLRFO, SETFO. Code generation: MC680x0.
- o PhxAss can generate S-Records of variable length for 16-bit and 32-bit addresses controlled by the new directive STYPE.

V4.33

- o New, bigger hash tables for symbols and mnemonics shorten the compilation time by approx. 10-30%. The size of those hash tables may be modified by GLOBHASHTAB/K/N, LOCHASHTAB/K/N and MNEMOHASHTAB/K/N.
- o The new SET symbol CARG can select a specific macro parameter by its value. \. selects the macro parameter with the number of CARG. A post incrementation and decrementation of CARG is supplied by \+ and \- .
- o __CPU contains the current CPU type, selected by MACHINE. __FPU contains the current FPU id., selected by MACHINE and FPU. __MMU shows, whether PMMU code generation is allowed.
- o The command line parameter TO allows a directory as destination. An object file with the name of the source text and ".o" extension will be created.
- o New command line parameter SHOWOPT/S enables listing of all optimized source lines together with the number of bytes gained.
- o A0 and A1 are additionally allowed for small data base register.
- o The small data base register may be changed by NEAR An multiple times in a source text.
- o Macro parameter \0 (extension) may be used in strings too.
- o Implemented FEQR directive (EQR for FPU registers).
- o <...> can be used in macros to indicate an indivisible term. Examples: <Hello World!> or <"Test",0>.
- o All undefined XDEF symbols will be listed when assembly has finished.

V4.34

- o New directive SYMDEBUG performs the same function as the CLI parameter DS=SYMDEBUG/S.
- o New directive LINEDEBUG performs the same function as the CLI parameter DL=LINEDEBUG/S.

V4.35

- o Small data addressing is allowed for the extended 020+ addressing modes. For example, indirect addressing: ([label,a4])
- o PRI/K/N can be used to change the process priority of PhxAss during assembly.
- o When setting the new switch EXE/S PhxAss tries to generate an executable file although XDEFs are present.
- o Norwegian catalog.

V4.36

- o DS/DCB/BLK <n> with a large <n> does no longer require more time to assemble than with a small <n>.
- o Displays the message "Illegal PHXOPTIONS file" if the format of the

- PHXOPTIONS file is incorrect.
- o ZEROPADDING/S forces PhxAss to use zero bytes for CNOP-padding instead NOP instructions.
 - o New directive IMAGE for AsmOne compatibility. Behaves the same like INCBIN.
 - o Directives for compatibility with OMA 3.x: EQURL (behaves like REG) and FEQURL (behaves like FREG).
 - o CMPI #0 and SUBI #0 will be optimized to TST, if (n)ormal optimization is enabled.
 - o (outerDisp,[...]) will be automatically converted into the 020+ addressing mode ([...],outerDisp).

1.6 Bug fixes since V2.11

- o Some instructions had generated a wrong error, e.g. TRAP and STOP generated 'Assembly aborted' instead of 'Out of range'.
- o 'move.l #xxxx,-(a0)' produced an illegal opcode.
- o If someone writes a program without first opening a section with CODE/CSEG, SECTION or an initial label, all labels got wrong values.
- o In some cases the equates file let PhxAss crash.
- o A XDEF for a symbol which was already defined in another section would add this symbol to the external-hunk of the section currently active.
- o Jump to Branch optimization did not check the addressing mode of the JMP/JSR instruction. It simply optimized all modes.
- o A long branch to the next instruction was incorrectly optimized to \$6x00.
- o B<cc>.B was not recognized as a short branch. PhxAss accepted only B<cc>.S.
- o The CNOP directive had disabled all optimizing in its section.
- o The 'Word at odd address'-error crashed PhxAss sometimes.
- o INITNEAR was useless in the absolute mode.

1.7 Bug fixes since V3.00

V3.01 (03.03.93)

- o The 68020 addressing-mode ([Rn]) was assembled with a wrong size in pass one.

V3.02 (20.04.93)

- o TRACKDISK now really works.

V3.05 (30.05.93)

- o The near-data range was incorrectly limited to 32k in object files.
- o The formatted text-output should also work on OS2.xx/3.xx now.
- o MOVE USP,An , MOVES and MOVEP produced incorrect code.
- o GLOBAL and BSS destroyed the MSW-bits of the BSS-hunk type (\$000003eb).

V3.10 (04.06.93)

- o PhxAss didn't accept octal numbers (@xxx).

V3.11 (06.06.93)

- o CNOP definitely bug-free (I hope).
 - o CMPI #x,(PC) (>=68020)
-

V3.12 (08.06.93)

- o Width 32 was impossible for bit fields.

V3.15 (12.06.93)

- o Fixed bug with MOVEM-optimization.

V3.20 (03.07.93)

- o References on "\@"-labels behind another macro nesting were impossible.

V3.21 (05.07.93)

- o "\@" only allowed 999 macro calls (now it's unlimited).

V3.22 (06.07.93)

- o Some extended addressing modes had made some problems:
([..],Rn.s|x,od) and ([PC.. got a wrong size in pass one,
([BaseDisp]) generated an error and (bd,An/PC,Xn) (where bd is outside
of the normal 8-bit range) crashed PhxAss.

V3.25 (17.07.93)

- o Fixed bug with MOVES.
- o FETOXM1 was forgotten (in my Reference Manual too).

V3.26 (18.07.93)

- o TAB-Codes within strings could not be expanded.

V3.30 (25.07.93)

- o Fixed bug with extended addressing modes ([..],Rn.x/*y,od), ([pc],..
and ([pc,Rn],..

V3.31 (28.07.93)

- o INITNEAR was useless in small-data mode.

V3.40 (07.08.93)

- o Include paths which are suffixed by a ':' (volume names) were not recognized.
- o FMOVEM.L Dn,FPcr got four bytes more in pass one than in pass two.
- o Starting with page 100 the listing file became unreadable.
- o The 'Out of memory' error was useless, because PhxAss crashed in most cases.
- o CPUSHL,CINVL,CPUSHP,CINVP didn't work.
- o BTST Dn,#x was missing.

V3.42 (24.08.93)

- o The new forward-branch optimization destroyed the CNOP-alignments, which are located between the branch-instruction and the branch-destination.

V3.46 (02.09.93)

- o PhxAss tried to optimize "MOVEP (d16,An)" with d16=0 into "MOVEP (An)".
This was a bug!

V3.50 (15.09.93)

- o Fixed bug with the '*'-symbol, containing the address of the current line.
- o ".local" was impossible with float symbols.

V3.57 (22.09.93)

- o PTESTR/PTESTW (68030) ignored the fourth operand.
-

V3.58 (23.09.93)

- o NARG was not zero for a macro call without arguments.
- o INCLUDE/INCBIN without quotes caused an error.

V3.61 (02.10.93)

- o IFC '\1','' only behaved reliable if \1 was not used before.

V3.64 (24.11.93)

- o The 16/32-bit displacements in the PC Indirect with Index addressing mode were wrong (+2 Bytes).

V3.65 (10.12.93)

- o Fixed bugs in AbsLong->AbsShort and Logical Shifts optimization.

V3.70 (15.12.93)

- o Fixed bug with (d16,An,ZRn) and (bd,PC).
- o PhxAss tried to optimize CMPI #x,AbsLong always to PC-relative, which caused an 'Illegal Addressing Mode' error in 68000/010 mode.

V3.76 (07.04.94)

- o Another bug in forward-branch optimizing (T-flag) made a mess with the object file in some specific cases.
- o An illegal Bcc.B *+2 was converted into Bcc.W *+2 instead of Bcc.W *+4.

V3.77 (21.04.94)

- o More than 13 sections in a file had lead to a crash or an infinite loop.

V3.78 (27.04.94)

- o When PhxAss discovered an error in a line >= 32768 it didn't show neither the line-counter nor the incorrect line itself (now it works until 65000).

V3.79 (01.05.94)

- o Absolute addressing with parentheses caused a Syntax Error.
E.g.: "move.w label+(x+y)*z", but "move.w (x+y)*z+label" works.

V3.90 (16.09.94)

- o Macro arguments which contained a comma (e.g. (d,An)) were unusable.

V3.93 (25.09.94)

- o An explicit B<cc>.L was calculated 2 bytes too short in 020+ mode and 2 bytes too far in normal mode.

V3.94 (09.10.94)

- o The code generated by MOVE.B #-1,d0 (also: cmp, and, or, eor, etc.) was \$103C \$FFFF, but the bits 8-15 of the first extension word are reserved, for a byte-instruction! Now PhxAss politely generates: \$103C \$00FF.
- o PhxAss changed (d,PC,ZRn) into (d,ZPC,ZRn).

V3.96 (23.10.94)

- o PhxAss crashed when the macro nesting depth exceeded 8.

V3.97 (01.11.94)

- o Distances, which are calculated by using a label directly behind a CNOP, were sometimes wrong.
 - o Because of some speed-improvements in V3.96, macro-arguments in opcode could lead to an error.
-

V4.00 (26.12.94)

- o PhxAss crashed when a fixed number of include files were open.
- o There were still some problems with removing empty sections.
- o ELSEIF was documented, but not supported (forgotten).

1.8 Bug fixes since V4.00

V4.01 (07.01.95)

- o Multiplication now has a lower priority than Division/Modulo to prevent situations like: $12/4*3 = 1$
I know, '*', '/' and '//' should have the same priorities, but currently my expression evaluation routines don't allow multiple operations at the same priority. Maybe I will completely rewrite them, in the future.

V4.05 (25.01.95)

- o FreePhxAss didn't create an object file!!! :((((very ugly bug)
- o The NOT operation (~) didn't pay attention to the operation size of the current instruction. So "move.b #~\$80,d0" generated an error 97.
- o An empty section, which was automatically removed during creation of an object file, deleted all XREFs of the subsequent sections.
- o \" and \" made still some problems within strings.
- o Macro parameters in the opcode field only worked, when using capital letters.

V4.10 (09.02.95)

- o INCLUDE and INCBIN didn't work, if the file name contains blanks.

V4.11 (21.02.95)

- o A numerical value within the command line, e.g. with "SMALLDATA x,y" crashes the system. It resulted from the massive changes in V4.10! :(

V4.14 (19.03.95)

- o Beginning with error-message 89, the locale catalogs generated the wrong message.

V4.15 (30.04.95)

- o If your source contains not a single byte, PhxAss sometimes crashed.

V4.16 (13.05.95)

- o As a result of improvements in V4.15, the OPT-parameter didn't work. :(

V4.17 (18.05.95)

- o MOVE16 didn't work with absolute addresses less than \$8000.

V4.18 (07.06.95)

- o #' and #' failed since V4.15.

V4.19 (27.06.95)

- o Long range branches, which were explicitly defined as Byte branches, were made to Word instead Long. This caused an error in the following branch optimization.
 - o Distance shifts didn't work with equates (EQU).
-

- o Distance shifts didn't get the correct value in the listing file.
- o Forgot to close two math-libraries during clean-up.

V4.20 (12.08.95)

- o Usage of scaling in 68000 mode will generate an error message now.
- o ASL will be optimized to ADD by (n)ormal optimization (if possible).
- o \@ generates '_000' labels instead '000'. So you will be no longer forced to change you exec/types.i include file.
- o It is possible again, to create an object file which contains only absolute XDEFs. It was already possible before v4.00, I think. ;)
- o Now you will get an error message, when a symbol inside a macro was defined twice.
- o When both Data and Bss sections were empty in small data mode, PhxAss generated an object file with 65535 size fields in the hunk header.

V4.21 (20.09.95)

- o The expression X in d(X) or (d,X) was ignored, if not a register. Now it generates a Syntax Error.
- o Missing Byte/Word range check in DC, DCB and BLK implemented.
- o In a situation where the system runs out of memory the error message 'Shift error' was displayed instead 'Out of memory'.

V4.22 (22.09.95)

- o Since v4.20 an expression may be preceded by a '+'. Unfortunately, that was not the case with float expressions.

V4.23 (03.10.95)

- o Operation size ist checked much stricter. It was possible to write MOVE.P for example, and PhxAss generated wrong code without a warning. Additionally, things like SWAP Dn,Dm are no longer supported... ;)
- o Because of the stricter expression checking in V4.21, operands like ea{x:y} did no longer work.

V4.24 (08.10.95)

- o The domino-effect in fwd-branch optimization leads to wrong branch destinations in some specific cases.

V4.25 (15.11.95)

- o Symbols which are terminated by .W or .L created an "Undefined Symbol" error since v4.21.
 - o Negative RORG offsets are forbidden.
 - o S-optimization MOVE.x #0,An -> CLR.x An disabled.
 - o Bug in S-optimization PEA 0.L -> CLR.L -(SP) shifted the following symbols by two bytes.
 - o OPT N has absolute priority against OPT P. Thereby MOVE.L #0,An can be optimized to SUBA.L An,An instead LEA 0.w,An, in spite of activated P-optimization.
 - o PhxAss crashed on encountering a non terminated string, as e.g. MOVE #"abc,<ea>.
 - o The bitfield instructions BF??? (d,An){x:y} didn't work since v4.21.
 - o FMOVEM.x label,<freglist> created a "Bad register list" error.
 - o DC.? "xxx" is treated as expression instead as a string, if "xxx" fits into the given data size. Thereby DC.L "DOS"<<8 for example, is allowed again.
 - o DC.? ("xxx") generated a syntax error in pass 1.
-

- o FILE, TTL and SFORM enable arguments without " or ', as with INCLUDE or INCBIN.

V4.30 (05.03.96)

- o The Forward Branch Optimization of B<cc>.L into B<cc>.W didn't work.
- o FMOVE.M.L <FPControlRegs> was four bytes longer in pass 2 than in pass 1.
- o DC.?'\\' didn't work in pass 1 and moved the following labels by a random amount of bytes.
- o CMP #x,#y didn't produce an error message.
- o The MOVEC registers MSP, ISP and MMUSR don't exist on an 68060.
- o The command line parameter SET only allowed multiple definitions, if all symbols were assigned a definite value by '='.
- o PC relative 020+ addressing modes include a format word behind the instruction word and must not contain an external symbol. This is, because all linkers are calculating the distance value relative to the address where this value would be inserted. But it should be relative to the format word in this case. There is no official support for it, so I'm forced to generate error messages for all addressing modes of this kind.
- o Removed a wrong error message for the addressing mode (<xrefsym>.L,An).

V4.31 (27.03.96)

- o The support for the ASCII-characters \$c0-\$fe in symbol names didn't work very well, especially in the case when a symbol was introduced by such a character.
- o ([xrefsym,PC],od) generated wrong informations in the HUNK_EXT block.
- o MOVEM (An)+xxxx was accepted without generating an error.

V4.32 (27.05.96)

- o PhxAss generated an unnecessary line feed in the cross reference listing after exactly six references.
- o When the DC-Align option was active, a label in the same line like the DC directive could get a wrong value.
- o Hex-, binary- and octal constants without a single digit doesn't invoke an error message.
- o PhxAss displays a warning, when a near addressing mode has come out of range while 020+ code generation is enabled (68000/010 mode would cause an error message anyway).

V4.33 (17.10.96)

- o Negation of floating point functions was impossible (Example: -sin(x)).
 - o Infinite loop on unknown section type or BSS_F.
 - o "section blah,code,chip" and "section blah,code,fast" were coalesced by PhxAss by using the MemFlags of the first definition. They're differentiated now.
 - o __RS got the value of the last RS-offset instead of the RS-counter.
 - o Crash on generation of an absolute file by using the FILE directive. The bug existed since the implementation of buffered I/O routines in v4.31.
 - o Setting new optimization flags in source text by using OPT, only caused an addition of the specified flags instead of a complete redefinition.
 - o There were still some problems with CNOP, where a short-branch over a CNOP could get out of range in some situations.
 - o Empty sections, which were referenced by code of another section, are no longer deleted. Instead a section with size 0 will be created in the object file or the executable.
 - o According to Motorola's 6888x User's Manual, only .b, .w, .l and .s are allowed as an extension for FMOVE.? Dm,FPn and FMOVE.? Fpm,Dn.
-

- o IFD/IFND didn't work if the symbol has a value of zero.
- o If DS does an automatic alignment, a label in the same line was not affected.
- o The bitfield instructions BFxxx <ea>{x:y}, caused a syntax error, when the addressing mode was absolute short/long.

V4.34 (22.10.96)

- o Using distances with symbols from DATA and BSS sections, with a CNOP in between them, didn't work in v4.33.
- o PhxAss didn't allow an assignment of a distance within a macro, e.g.:
\1 EQU *-label

V4.35 (11.02.97)

- o The "B<cc>.B *+0" problem is solved! If this special case occurs, caused by an optimization, the instruction will be replaced by a NOP.
- o <...> had some problems.
- o The (hopefully last) big CNOP-bug was fixed. The following constellation doesn't make problems anymore:
label1: cnop 0,4
label2:
- o The symbols __CPU, __FPU and __MMU were invalid, as long as the assembler hasn't seen a MACHINE, FPU or PMMU directive.
- o Symbols in the operand of an FPU instruction, which start with the letters "FP", lead to confusion with FPU register names. The result was a misinterpretation of the addressing mode in pass 1.
- o When the destination file name contained a '.', PhxAss always deletes the following characters including the '.', if an executable file could be created. From now on, only a ".o" extension will be removed.
- o Since V4.33 PhxAss lost 48k memory, when a PHXOPTIONS file is present.
- o Locale labels with the names ".W" and ".L" were impossible.
- o The assignment of an external symbol by the EQU directive now leads to an error message. Till now zero was assigned.

V4.36 (01.06.97)

- o The PUBLIC directive didn't work in a macro.
- o IFND <external symbol> had the side effect to disable optimization for all sections which were defined after the current one.
- o Assigning an address to a global symbol with EQU had the same effect like a global label. As a result this EQU ended a local label block.
Example:
start bra .l1
symbol equ start
.l1 rts
- o Branch optimization made a BRA.W *+6 from JMP *+6. It has to be BRA.W *+4.
- o PhxAss didn't create an object file, if a source text contained no code. Now an empty object will be created to prevent problems with Makefiles.

1.9 Starting PhxAss

PhxAss can be used from Shell only. You should copy it to "C:" or define a path or link. If you know that you will need PhxAss very often, I would recommend to make it resident by typing "Resident PhxAss".

Format: PhxAss [FROM] <source file> [TO <output file>] [OPT <opt flags>]
 [EQU <equ file>] [LIST <list file>] [INCPATH {<include paths>}]
 [HEADINC {<include files>}] [PAGE=<n>] [ERRORS=<n>]
 [ERRCODE=<n>] [SMALLDATA <basReg>,<sec>] [SMALLCODE] [LARGE]
 [VERBOSE] [SYMDEBUG] [LINEDEBUG] [ALIGN] [case] [XREFS] [QUIET]
 [NOWARN] [NOEXE] [MACHINE=<n>] [FPU=<n>] [PMMU] [BUFSIZE=<n>]
 [SHOWOPT] [PRI=<n>] [EXE] [GLOBHASHTAB=<n>] [LOCHASHTAB=<n>]
 [MNEMOHASHTAB=<n>] [ZEROPADDING]
 [SET "<symbol>[=<n>][,<symbol>...]"]

Template: FROM/A, TO/K, OPT/K, EQU/K, LIST/K, I=INCPATH/K, H=HEADINC/K, PAGE/K/N,
 ERRORS/K/N, RC=ERRCODE/K/N, SD=SMALLDATA/K, SC=SMALLCODE/S, LARGE/S,
 VERBOSE/S, DS=SYMDEBUG/S, DL=LINEDEBUG/S, A=ALIGN/S, C=CASE/S,
 XREFS/S, Q=QUIET/S, NOWARN/S, NOEXE/S, M=MACHINE/K/N, FPU/K/N,
 PMMU/S, BUFSIZE/K/N, SHOWOPT/S, PRI/K/N, EXE/S, GH=GLOBHASHTAB/K/N,
 LH=LOCHASHTAB/K/N, MH=MNEMOHASHTAB/K/N, Z=ZEROPADDING/S, SET/K

Starting PhxAss with no argument or with a single '?' will display a short description. For a more precise description of all arguments, refer to Command line arguments.

When PhxAss is running, it can be stopped at any time by holding CTRL-C.

1.10 Command line arguments

The standard version of PhxAss understands the following arguments:

FROM/A [FROM] <source file>	The only parameter, which is always required, is the name of your source code file. If this name has no extension, PhxAss automatically assumes ".asm" for being the extension. The source code must be an ASCII text file, where each line is terminated by a line feed (\$0a) character (the format, which all Amiga editors should generate). TAB-codes (\$09) are allowed and completely supported.
TO/K TO <output file/dir.>	Defines the name of the output file. If not specified, PhxAss takes the source code's filename and replaces its extension by ".o" . If PhxAss is able to create an executable file instead of an object module, the ".o"-extension will be removed. Since v4.33 the sole specification of a destination directory is also allowed.
EQU/K EQU <file name>	Generates an equates file. If the <file name> is "*", the name of the source code with extension ".equ" will be used. Since V4.00 equates files can also contain floating point equates.
LIST/K LIST <file name>	Generates a listing file. If the <file name> is "*", the name of the source code with extension ".lst" will be used.

PAGE/K/N PAGE=<lines>	Determines the page length for equates and listing files. If <lines> equals zero, no form feed (\$0c) characters will be generated. The default value is 60 lines.
XREFS/S XREFS	Appends a reference list with all global symbols in the listing file. If no listing file was opened, this switch will cause an error.
I=INCPATH/K I <path1>[,<path2>,...]	Defines one or more include-paths which will be used by the INCLUDE and INCBIN directives. The paths, specified by INCPATH/K, are used directly after the path, specified by the environment-variable PHXASSINC, has failed. Important: If the path- or file names after INCPATH or HEADINC contain blanks, you should embrace *all* names with quotation marks and not only the one, which contains blanks. Example: INCPATH "include:,dh1:inc dir"
H=HEADINC/K H <incl>[,<inc2>,...]	Creates one or more INCLUDE directives at the top of your source code. See also: INCPATH.
DS=SYMDEBUG/S DS	The names of all global labels of each section are stored to symbol data blocks. A debugger can use these names instead of addresses.
DL=LINEDEBUG/S DL	PhxAss creates a linedebug block, which can tell a Source Level Debugger the right line in your source code for any address. The location of your source is stored in this block with a complete path, e.g. "Work:Programs/Assembler/Tools/Source/Test.asm" (this is, for example, not the case with SAS's ASM :-). Compilers should use the directives DEBUG and DSOURCE instead this option. A useful PD-Debugger with source level debugging capabilities is for example "PowerVisor v1.42", which can be found on Aminet dev/debug/pv142.lha or on the GoldFish-CD.
SD=SMALLDATA/K SD <basReg>[,<sec>]	Forces all sections to use the small data model. <basReg> (default: 4) specifies the number of the address register which will be used as pointer to the small data section. Only the registers A2-A6 can be used. <sec> is the number of the section which will be your small data section (defaults to -2). If <sec> is -1, all Data and Bss sections will be treated as a whole small data section. If <sec> is -2, only the sections which are named "__MERGED", will be added to small data.
SC=SMALLCODE/S SC	Forces PhxAss to use the small code model. All JSR and JMP instructions which are referencing external (XREF) symbols are converted to PC-relative 16-bit jumps.

LARGE/S LARGE	Forces PhxAss to use the large code and large data model in all sections. NEAR directives within the source code will be ignored.
SET/K SET "<symbol>[=<val>]"	Predefines a symbol by SET directive. Definition of multiple symbols must be separated by commas. <val> default to 1, when missing. Don't forget the to embed the whole term, which follows SET, in quotes (because of some problems with ReadArgs()) !
A=ALIGN/S A	Enable auto-align for DC.x directives. All DC.W, DC.L, etc. directives in the code will be automatically aligned to word-boundaries.
C=CASE/S C	Case-sensitivity off. All symbol names will be converted to upper case. This will slow down PhxAss by 5%.
NOWARN/S	Disables the output of warning messages.
ERRORS/K/N ERRORS=<max errors>	Determines the maximum number of error-messages to be displayed before a "continue?"-request. If <max errors> is zero, PhxAss will never stop to perform a request.
RC=ERRCODE/K/N RC=<rc>	Defines the Shell return code in case of an error. <rc> defaults to 20.
VERBOSE/S VERBOSE	Displays the names of all include files and macros, which are accessed during assembly. This can be helpful to locate errors with macros.
Q=QUIET/S Q	Quiet mode. PhxAss makes no outputs until an error occurs.
NOEXE/S NOEXE	PhxAss always tries to create an executable load file, instead of an object module, which requires the additional use of a linker. NOEXE forces PhxAss to create object modules in any case.
M=MACHINE/K/N M=<cpu>	As with the MACHINE directive, you may set the CPU type for which the code should be generated. One difference: Besides 68000 ... 68060, the numbers 0,1,2,3,4,6 are allowed too.
FPU/K/N FPU=<fpuid>	Presets the usage of FPU instructions (see also: FPU directive).
PMMU/S PMMU	Presets the usage of an 68851 PMMU (see also: PMMU directive).
BUFSIZE/K/N BUFSIZE=<size>	Changes the size of the buffer, required for buffered I/O. Default size is 8192 bytes.
GH=GLOBHASHTAB/K/N	Size of the hash-code table for global symbols

GH=<size>	as a power of two in the range from 2 ⁸ to 2 ¹⁶ . Default size is 2 ¹² = 4096 entries.
LH=LOCHASHTAB/K/N LH=<size>	Size of the hash-code table for local symbols as a power of two in the range from 2 ² to 2 ¹⁰ . Default size is 2 ⁴ = 16 entries.
MH=MNEMOHASHTAB/K/N MH=<size>	Size of the hash-code table for mnemonics as a power of two in the range from 2 ⁶ to 2 ¹⁶ . Default size is 2 ¹⁰ = 1024 entries.
SHOWOPT/S SHOWOPT	Lists all optimized lines from the source text together with the number of bytes gained.
PRI/K/N PRI=<priority>	Determines the process priority for PhxAss during assembly. Usual values are between -10 and 10.
EXE/S EXE	As long as there are no external references or an explicit NOEXE/S, PhxAss always tries to gene- rate a load file. When setting EXE/S it even tries to do so when XDEFs are present in source.
Z=ZEROPADDING/S Z	Always use zero bytes for CNOP-padding. Never use NOP instructions.
OPT/K OPT <flags>	Sets the optimize flags. The following characters, without embedded blanks, can be specified after 'OPT':
	0 (None) No optimizing allowed. This flag should always stand alone.
	N (Normal) Standard optimizations:
	clr.l Dn -> moveq #0,Dn
	move.l #x,Dn -> moveq #x,Dn
	move.l #0,An -> suba.l An,An
	move.l #xxxx,An -> move.w #xx,An
	link.l(68020) -> link.w
	adda/suba -> lea
	(\$xxxx).L -> (\$xx).W
	(0,An) -> (An)
	asl #1,Dn -> add Dn,Dn
	asl.w/b #2,Dn -> add Dn,Dn add Dn,Dn
	subi/cmpi #0 -> tst
	R (Relative) (\$xxxx) -> (xx,PC)
	Q (Quick) Conversions into addq/subq
	B (Branches) Bcc.l(020) -> Bcc.w -> Bcc.b, jmp/jsr -> bra/bsr Bcc.w(000/010) -> B!cc.b, jmp

Example:

```

        beq.w   label
will be converted into ->
        bne.b   *+8
        jmp     label
if the distance until label is greater than
32766 bytes.

```

T (Total branch optimization)

```

Bcc.l(020) -> Bcc.w -> Bcc.b (forward branches)
Only active if 'B' is also selected.
WARNING! If you use this option together with a
listing file, then you can't rely on the line-
addresses in it.

```

L (Logical Shifts)

```

lsl #1,Dn -> add Dn,Dn
lsl.w/b #2,Dn -> add Dn,Dn + add Dn,Dn

```

P (PEA/LEA conversion)

```

move.l #x,An -> lea x,An
                -> lea (x,PC),An / lea x.w,An
move.l #x,-(SP) -> pea x -> pea (x,PC) / pea x.w

```

S (Special optimizations)

```

pea 0 -> clr.l -(SP)
add/sub #0,An / lea (0,An),An -> (removed)
(d,An,ZRn) -> (d,An) -> (An)
(d,PC,ZRn) -> (d,PC)

```

The following are not recommendable for a MC68000
accessing hardware registers:

```

move #0,<ea> -> clr <ea>
move.b #-1,<ea> -> st <ea>

```

M (MOVEM/FMOVEM empty register list)

```

movem ,<ea> / movem <ea>, -> (removed)
fmovem ,<ea> / fmovem <ea>, -> (removed)

```

D (MOVEM single register) since v4.30

```

movem -> move
Caution! This optimization affects the con-
dition code register. Only available if M-
optimization was selected too.

```

I (Ignore too large distances)

Distances, which are currently out of range will
not cause an error. This is sometimes useful for
assembling reassembler-outputs or when you're
sure that all distances will come into range
again, by optimization of the subsequent code.
BE CAUTIOUS!!! If a distance has not come into
range, PhxAss creates faulty code!

If OPT is not specified the assembler uses standard
optimization (OPT nrqb).

There are some short cuts for the most common optimizations:

```
OPT *   =   OPT nrqbt (standard + T)
OPT !   =   OPT nrqbtlpsmd (all optimizations)
```

Since v4.30:

```
OPT 1   =   OPT nrqb (standard)
OPT 2   =   OPT nrqbt (standard + T)
OPT 3   =   OPT nrqbtlpsmd (all optimizations)
```

1.11 Programmer Information

Comments
Labels
M68000 Instructions
Expressions
Assembler Directives
Compiler Compatibility
PhxOpts
Environment Variables

1.12 Comments

Comments start with a ';' or with an '*'.

Example:

```
; Comment text
    moveq    #0,d0
** This is a comment too **
    nop                                ; comment
    add.l   d0,d0                      * another comment
```

If no operand field is given, e.g. after the NOP instruction, the comment must be preceded by a ';'. Examples:

```
    nop    * comment                    -> Error!
    nop    comment                      -> Error!
```

1.13 Labels

Labels must start in the first column of a line. The colon after a label is optional. You must insert a blank or TAB between label and opcode, if you decide to omit the colon.

Example:

```
Label:  moveq    #0,d0
```

Local labels have a '\$' suffixed or are preceded by a '.' (since V3.30). They are only valid between two global labels.

Example:

```
Global1: add.w    d0,d1
         beq.s    local1$
         bpl.s    .local2
         rts
local1$: moveq   #-1,d0
.local2: rts
Global2:
```

The length for global and local labels is unlimited. Valid characters for the labels are:

'a' - 'z'

'A' - 'Z'

'0' - '9'

'_'

Since V4.15:

'.'

Since V4.30:

'À' - 'Ö' (192 - 214)

'Ø' - 'ö' (216 - 246)

'ø' - 'þ' (248 - 254, 255 is used internally)

'%' and '\$' are only valid in the middle of a label (V4.32).

The first character may be an '@' (providing the second character is non-numeric). Global labels cannot start with a digit.

The special '*'-symbol always contains the address of the current source code line. This enables instructions like: bra *+4

CAUTION! Forward references with '*' will be corrected by PhxAss, but backward references won't! I recommend to use labels, if you want to be really safe.

1.14 Executable M68000 instructions

General Format
Standard Addressing Modes
Extended Addressing Modes
Suppressed Registers (020+)
M68000 Instruction Overview

1.15 General Format

A line of an assembler source text has the general format:

```
<label>    <opcode>    <operands>
```

PhxAss recognizes all operations found in Motorola's M68000PM/AD Program-

mer's Reference Manual and all of the common additions and short forms like BHS instead of BCC, BLO instead of BCS, MOVE instead of MOVEA, ADD instead of ADDI, etc. . In the current version all MC68000, 68010, 68020, 68030, 68040, 68060, 68851, 68881 and 68882 instructions are completely supported.

Labels must start at the first column. Opcodes (M68000 instructions or assembler directives) and operands must have at least one preceding blank.

The operand field consists of one, two, three or four (68851) operands, separated by a comma. Embedded blanks are allowed since V4.10.

1.16 M68000 Standard Addressing Modes

The notational conventions used in this section are:

- EA - Effective address
- An - Address register n
- Dn - Data register n
- Xn.SIZE - Denotes index register n (data or address) and index size (W for Word or L for Longword)
- PC - Program counter
- dn - Displacement value, n bits wide
- () - Identify an indirect address in a register

Data Register Direct

Syntax: Dn
 Generation: EA = Dn
 Extension Words: 0

Address Register Direct

Syntax: An
 Generation: EA = An
 Extension Words: 0

Address Register Indirect

Syntax: (An)
 Generation: EA = (An)
 Extension Words: 0

Address Register Indirect with Postincrement

Syntax: (An)+
 Generation: EA = (An), An = An + SIZE
 Extension Words: 0

Address Register Indirect with Predecrement

Syntax: -(An)
 Generation: An = An - SIZE, EA = (An)
 Extension Words: 0

Address Register Indirect with Displacement (16-Bit)

Syntax: (d16,An) or d16(An)
 Generation: EA = (An) + d16
 Extension Words: 1

Address Register Indirect with Index (8-Bit Displacement)

Syntax: (d8,An,Xn.SIZE) or d8(An,Xn.SIZE)
 Generation: EA = (An) + (Xn) + d8
 Extension Words: 1

Program Counter Indirect with Displacement (16-Bit)
 Syntax: (d16,PC) or d16(PC)
 Generation: EA = (PC) + d16
 Extension Words: 1

Program Counter Indirect with Index (8-Bit Displacement)
 Syntax: (d8,PC,Xn.SIZE) or d8(PC,Xn.SIZE)
 Generation: EA = (PC) + (Xn) + d8
 Extension Words: 1

Absolute Short Addressing
 Syntax: (xxx).W or xxx.W
 Generation: EA given
 Extension Words: 1

Absolute Long Addressing
 Syntax: (xxx).L or xxx.L
 Generation: EA given
 Extension Words: 2

Immediate Data
 Syntax: #xxx
 Generation: Operand given
 Extension Words: 1 or 2

1.17 68020+ Extended Addressing Modes

The notational conventions used in this section are:

EA	- Effective address
An	- Address register n
Dn	- Data register n
Xn.SIZE*SCALE	- Denotes index register n (data or address), the index size (W or L), and a scale factor (1, 2, 4 or 8)
PC	- Program counter
dn	- Displacement value, n bits wide
bd	- Base displacement
od	- Outer displacement
()	- Identify an indirect address in a register
[]	- Identify an indirect address in memory

Address Register Indirect with Index (extension of standard format)
 Syntax: (d8,An,Xn.SIZE*SCALE)
 Generation: EA = (An) + (Xn)*SCALE + d8
 Extension Words: 1

Address Register Indirect with Index and Base Displacement
 Syntax: (bd,An,Xn.SIZE*SCALE)
 Generation: EA = (An) + (Xn)*SCALE + bd
 Extension Words: 1, 2 or 3

Memory Indirect Postindexed

Syntax: ([bd,An],Xn.SIZE*SCALE,od)
 Generation: EA = (bd + An) + Xn.SIZE*SCALE + od
 Extension Words: 1, 2, 3, 4 or 5

Memory Indirect Preindexed

Syntax: ([bd,An,Xn.SIZE*SCALE],od)
 Generation: EA = (bd + An + Xn.SIZE*SCALE) + od
 Extension Words: 1, 2, 3, 4 or 5

Program Counter Indirect with Index (extension of standard format)

Syntax: (d8,PC,Xn.SIZE*SCALE)
 Generation: EA = (PC) + (Xn)*SCALE + d8
 Extension Words: 1

Program Counter Indirect with Index and Base Displacement

Syntax: (bd,PC,Xn.SIZE*SCALE)
 Generation: EA = (PC) + (Xn)*SCALE + bd
 Extension Words: 1, 2 or 3

Program Counter Memory Indirect Postindexed

Syntax: ([bd,PC],Xn.SIZE*SCALE,od)
 Generation: EA = (bd + PC) + Xn.SIZE*SCALE + od
 Extension Words: 1, 2, 3, 4 or 5

Program Counter Memory Indirect Preindexed

Syntax: ([bd,PC,Xn.SIZE*SCALE],od)
 Generation: EA = (bd + An + Xn.SIZE*SCALE) + od
 Extension Words: 1, 2, 3, 4 or 5

The extended addressing modes have some ambiguities:

E.g. (0,A0) would be optimized to (A0) (one word), but maybe you want the zero to be a 32-bit base displacement and you also want a suppressed D7 register. This instruction would have the same effect when executing, but it consists of eight words instead of one.

Since PhxAss V3.70 you only have to write: (0.L,A0,ZD7)

1.18 68020+ Suppressed Registers

The Memory Indirect Post/Preindexed addressing modes allow the programmer to suppress really everything. This means you may for example change the standard format ([bd,An,Xn.SIZE*SCALE],od) into the following formats:

- o ([bd,An,Xn.SIZE*SCALE])
 - o ([An,Xn.SIZE*SCALE],od)
 - o ([bd],od)
 - o ([An])
 - o ([Xn.SIZE*SCALE])
 - o ([An],od)
- etc...

If you want to specify the number of a suppressed register you can use the Zero-register symbols (ZRn, ZPC). By utilizing Zero-register symbols and the displacement extensions .W and .L you should be able to generate any 68020 instruction bit-pattern you want (maybe helpful for reassemblers).

A .W/.L extension after the first displacement will tell PhxAss to switch to base displacement mode and to disable optimizing for the current instruction.

The suppressed registers are represented by the following symbols:

- o suppressed data register D0-D7: ZD0-ZD7
- o suppressed address register A0-A7: ZA0-ZA7
- o suppressed PC: ZPC

It is impossible to EQUUR suppressed registers!

1.19 M68000 Instructions supported by PhxAss

Integer Instructions for all processors
 Integer Instructions 010,020,030,040,060 only
 Integer Instructions 020,030,040,060 only
 Integer Instructions 040,060 only
 Integer Instructions 68060 only
 MOVEC Control Registers
 Floating Point Instructions 881,882,040,060
 Floating Point Instructions 040,060 only
 68851 PMMU Instructions
 68030 PMMU Instructions
 68040/060 PMMU Instructions

1.20 Integer Instructions (68000,68010,68020,68030,68040,68060)

ABCD	Dy, Dx	Add Decimal with Extend
ABCD	-(Ay), -(Ax)	
ADD.x	<ea>, Dn	Add
ADD.x	Dn, <ea>	
ADDA.x	<ea>, An	Add Address
ADDI.x	#<data>, <ea>	Add Immediate
ADDQ.x	#<data>, <ea>	Add Quick
ADDX.x	Dy, Dx	Add Extended
ADDX.x	-(Ay), -(Ax)	
AND.x	<ea>, Dn	And Logical
AND.x	Dn, <ea>	
ANDI.x	#<data>, <ea>	And Immediate
ANDI.x	#<data>, CCR	And Immediate to Condition Codes
ANDI.x	#<data>, SR	And Immediate to the Status Register
ASL/ASR.x	Dx, Dy	Arithmetic Shift Left/Right
ASL/ASR.x	#<data>, Dy	
ASL/ASR	<ea>	
B<cc>.x	<label>	Branch Conditionally
BCHG	Dn, <ea>	Test a Bit and Change
BCHG	#<data>, <ea>	
BCLR	Dn, <ea>	Test a Bit and Clear
BCLR	#<data>, <ea>	
BRA.x	<label>	Branch Always
BSET	Dn, <ea>	Test a Bit and Set
BSET	#<data>, <ea>	

BSR.x	<label>	Branch to Subroutine
BTST.x	Dn, <ea>	Test a Bit
BTST.x	#<data>, <ea>	
CHK.x	<ea>, Dn	Check Register Against Bounds
CLR.x	<ea>	Clear an Operand
CMP.x	<ea>, Dn	Compare
CMPA.x	<ea>, An	Compare Address
CMPI.x	#<data>, <ea>	Compare Immediate
CMPM.x	(Ay) +, (Ax) +	Compare Memory
DB<cc>	Dn, <label>	Test Condition, Decrement, and Branch
DIVS	<ea>, Dn	Signed Divide
DIVU	<ea>, Dn	Unsigned Divide
EOR.x	Dn, <ea>	Exclusive-OR Logical
EORI.x	#<data>, <ea>	Exclusive-OR Immediate
EORI.x	#<data>, CCR	Exclusive-OR Immediate to Cond. Codes
EORI.x	#<data>, SR	Exclusive-OR Immediate to Status Reg.
EXG	Rn, Rm	Exchange Registers
EXT.x	Dn	Sign Extend
ILLEGAL		Take Illegal Instruction Trap
JMP	<ea>	Jump
JSR	<ea>	Jump to Subroutine
LEA	<ea>, An	Load Effective Address
LINK	An, #<displacement>	Link and Allocate
LSL/LSR.x	Dx, Dy	Logical Shift Left/Right
LSL/LSR.x	#<data>, Dy	
LSL/LSR	<ea>	
MOVE.x	<ea>, <ea>	Move Data from Source to Destination
MOVEA.x	<ea>, An	Move Address
MOVE	<ea>, CCR	Move to Condition Codes
MOVE	<ea>, SR	Move to the Status Register
MOVE	SR, <ea>	Move from Status Register
MOVE	USP, An	Move User Stack Pointer
MOVE	An, USP	
MOVEM.x	<register list>, <ea>	Move Multiple Registers
MOVEM.x	<ea>, <register list>	
MOVEP.x	Dx, (d, Ay)	Move Peripheral Data (not 68060!)
MOVEP.x	(d, Ay), Dx	
MOVEQ	#<data>, Dn	Move Quick
MULS	<ea>, Dn	Signed Multiply
MULU	<ea>, Dn	Unsigned Multiply
NBCD	<ea>	Negate Decimal with Extend
NEG.x	<ea>	Negate
NEGX.x	<ea>	Negate with Extend
NOP		No Operation
NOT.x	<ea>	Logical Complement
OR.x	<ea>, Dn	Inclusive-OR Logical
OR.x	Dn, <ea>	
ORI.x	#<data>, <ea>	Inclusive-OR Immediate
ORI.x	#<data>, CCR	Inclusive-OR Immediate to Cond. Codes
PEA	<ea>	Push Effective Address
RESET		Reset External Devices
ROL/ROR.x	Dx, Dy	Rotate (without Extend) Left/Right
ROL/ROR.x	#<data>, Dy	
ROL/ROR	<ea>	
ROXL/ROXR.x	Dx, Dy	Rotate Left/Right with Extend
ROXL/ROXR.x	#<data>, Dy	
ROXL/ROXR	<ea>	

RTE		Return from Exception
RTR		Return and Restore Condition Codes
RTS		Return from Subroutine
SBCD	Dx, Dy	Subtract Decimal with Extend
SBCD	-(Ax), -(Ay)	
S<cc>	<ea>	Set According to Condition
STOP	#<data>	Load Status Register and Stop
SUB.x	<ea>, Dn	Subtract
SUB.x	Dn, <ea>	
SUBA.x	<ea>, An	Subtract Address
SUBI.x	#<data>, <ea>	Subtract Immediate
SUBQ.x	#<data>, <ea>	Subtract Quick
SUBX.x	Dx, Dy	Subtract with Extend
SWAP	Dn	Swap Register Halves
TAS	<ea>	Test and Set an Operand
TRAP	#<vector>	Take Trap Exception
TRAPV		Trap on Overflow
TST.x	<ea>	Test an Operand
UNLK	An	Unlink

Integer Condition Codes <cc>:

CC (HS)	carry clear (higher or same)	CS (LO)	carry set (lower)
EQ	equal	F	never true
GE	greater or equal	GT	greater than
HI	higher	LE	less or equal
LS	less or same	LT	less than
MI	negative	NE	not equal
PL	positive	T	always true
VC	overflow clear	VS	overflow set

1.21 Integer Instructions (68010,68020,68030,68040,68060)

BKPT	#<data>	Breakpoint
MOVE	CCR, <ea>	Move from the Condition Code Register
MOVEC	Rc, Rn	Move Control Registers
MOVEC	Rn, Rc	
MOVES	Rn, <ea>	Move Address Space
MOVES	<ea>, Rn	
RTD	#<displacement>	Return and Deallocate

1.22 Integer Instructions (68020,68030,68040,68060)

BFCHG	<ea>{offset:width}	Test Bit Field and Change
BFCLR	<ea>{offset:width}	Test Bit Field and Clear
BFEXTS	<ea>{offset:width}, Dn	Extract Bit Field Signed
BFEXTU	<ea>{offset:width}, Dn	Extract Bit Field Unsigned
BFFFO	<ea>{offset:width}, Dn	Find First One in Bit Field
BFINS	Dn, <ea>{offset:width}	Insert Bit Field
BFSET	<ea>{offset:width}	Test Bit Field and Set
BFTST	<ea>{offset:width}	Test Bit Field
CALLM	#<data>, <ea>	Call Module (68020 ONLY!)
CAS.x	Dc, Du, <ea>	Compare and Swap with Operand

CAS2.x	Dc1:Dc2,Du1:Du2,(Rn1):(Rn2)	(020-040 only!)
CHK2.x	<ea>,Rn	(020-040 only!) Check Register Against Bounds
CMP2.x	<ea>,Rn	(020-040 only!) Compare Register Against Bounds
DIVS.L	<ea>,Dq	Signed Divide
DIVS.L	<ea>,Dr:Dq	
DIVSL.L	<ea>,Dr:Dq	(020-040 only!)
DIVU.L	<ea>,Dq	Unsigned Divide
DIVU.L	<ea>,Dr:Dq	
DIVUL.L	<ea>,Dr:Dq	(020-040 only!)
EXTB.L	Dn	Sign Extend
LINK.L	An,#<displacement>	Link and Allocate
MULS.L	<ea>,Dl	Signed Multiply
MULS.L	<ea>,Dh:Dl	
MULU.L	<ea>,Dl	Unsigned Multiply
MULU.L	<ea>,Dh:Dl	
PACK	-(Ax),-(Ay),#<adjustment>	Pack BCD
PACK	Dx,Dy,#<adjustment>	
RTM	Rn	Return from Module (68020 ONLY!)
TRAP<cc>		Trap on Condition
TRAP<cc>.x	#<data>	
UNPK	-(Ax),-(Ay),#<adjustment>	Unpack BCD
UNPK	Dx,Dy,#<adjustment>	

1.23 Integer Instructions (68040,68060)

CINVL	<caches>,(An)	Invalidate Cache Lines
CINVP	<caches>,(An)	(<caches> = DC, IC, BC or NC)
CINVA	<caches>	
CPUSHL	<caches>,(An)	Push and Invalidate Cache Lines
CPUSHP	<caches>,(An)	
CPUSHA	<caches>	
MOVE16	(Ax)+,(Ay)+	Move 16 Bytes Block
MOVE16	xxx.L,(An)	
MOVE16	xxx.L,(An)+	
MOVE16	(An),xxx.L	
MOVE16	(An)+,xxx.L	

1.24 Integer Instructions (68060)

LPSTOP	#<data>	Low-Power Stop
HALT		Processor halted
PULSE		Send \$14 pulse on PSTx

Instructions that are not directly supported by the 68060, like DIVUL, DIVSL, CAS2, CHK2, CMP2, MOVEP, will be assembled without warning, because they are emulated by the "68060.library" (I hope... :-).

1.25 MOVEC Control Registers (Rc)

	68010	68020	68030	68040	68060
SFC Source Function Code	x	x	x	x	x
DFC Destination Function Code	x	x	x	x	x
USP User Stack Pointer	x	x	x	x	x
VBR Vector Base Register	x	x	x	x	x
CACR Cache Control Register		x	x	x	x
CAAR Cache Address Register		x	x		
MSP Master Stack Pointer		x	x	x	
ISP Interrupt Stack Pointer		x	x	x	
TC MMU Translation Control Register				x	x
ITT0 Instr. Transparent Translation Reg. 0				x	x
ITT1 Instr. Transparent Translation Reg. 1				x	x
DTT0 Data Transparent Translation Reg. 0				x	x
DTT1 Data Transparent Translation Reg. 1				x	x
MMUSR MMU Status Register				x	
URP User Root Pointer				x	x
SRP Supervisor Root Pointer				x	x
BUSCR Bus Control Register					x
PCR Processor Control Register					x

1.26 Floating Point Instructions (68881,68882,68040,68060)

Many of these instructions must be emulated for a 68040 or 68060, but PhxAss will assemble them without any warnings.

68040 emulated instructions:

FACOS, FASIN, FATAN, FCOS, FCOSH, FETOX, FETOXM1, FGETEXP, FGETMAN, FINT, FINTRZ, FLOG10, FLOG2, FLOGN, FLOGNP1, FMOD, FMOVECR, FREM, FSGLDIV, FSGLMUL, FSIN, FSINCOS, FSINH, FTAN, FTANH, FTENTOX, FTWOTOX

68060 emulated instructions:

FACOS, FASIN, FATAN, FCOS, FCOSH, FDB<cc>, FETOX, FETOXM1, FGETEXP, FGETMAN, FLOG10, FLOG2, FLOGN, FLOGNP1, FMOD, FMOVECR, FREM, FSGLDIV, FSGLMUL, FS<cc>, FSIN, FSINCOS, FSINH, FTAN, FTANH, FTENTOX, FTWOTOX

Monadic operations:

Fxxxx <ea>, FPn
 Fxxxx FPm, FPn
 Fxxxx FPn

FABS Floating-Point Absolute value
 FACOS Arc Cosine
 FASIN Arc Sine
 FATAN Arc Tangent
 FATANH Hyperbolic Arc Tangent
 FCOS Cosine
 FCOSH Hyperbolic Cosine
 FETOX e to x
 FETOXM1 e to x minus one
 FGETEXP Get Exponent
 FGETMAN Get Mantissa
 FINT Integer Part
 FINTRZ Integer Part, Round to Zero

FLOG10	log10
FLOG2	log2
FLOGN	loge
FLOGNP1	loge (x+1)
FNEG	Floating-Point Negate
FSIN	Sine
FSINH	Hyperbolic Sine
FSQRT	Floating-Point Square Root
FTAN	Tangent
FTANH	Hyperbolic Tangent
FTENTOX	10 to x
FTWOTOX	2 to x

Dyadic operations:

Fxxxx	<ea>,FPn
Fxxxx	FPm,FPn

FADD	Floating-Point Add
FCMP	Floating-Point Compare
FDIV	Floating-Point Divide
FMOD	Modulo Remainder
FMUL	Floating-Point Multiply
FREM	IEEE Remainder
FSCALE	Scale Exponent
FSGLDIV	Single Precision Divide
FSGLMUL	Single Precision Multiply
FSUB	Floating-Point Subtract

Special operations:

FB<cc>.x	<label>	Floating-Point Branch Conditionally
FDB<cc>	Dn,<label>	FP Test Cond., Decr., and Branch
FMOVE.x	<ea>,FPn	Move Floating-Point Data Register
FMOVE.x	FPm,<ea>	
FMOVE.P	FPm,<ea>{Dn}	
FMOVE.P	FPm,<ea>{#k}	
FMOVE.L	<ea>,FPcr	Move F.-Point System Control Register
FMOVE.L	FPcr,<ea>	(FPcr = FPCR, FPSR or FPIAR)
FMOVECR	#ccc,FPn	Move Constant ROM
FMOVEM	<list>,<ea>	Move Multiple F.-Point Data Registers
FMOVEM	Dn,<ea>	
FMOVEM	<ea>,<list>	
FMOVEM	<ea>,Dn	
FMOVEM.L	<list>,<ea>	Move Multiple F.-Point Control Regs.
FMOVEM.L	<ea>,<list>	(<list> = combin. of FPCR,FPSR,FPIAR)
FNOP		No Operation
FRESTORE	<ea>	Restore Internal Floating-Point State
FSAVE	<ea>	Save Internal Floating-Point State
FS<cc>	<ea>	Set According to Flt.-Point Condition
FSINCOS.x	<ea>,FPc:FPs	Simultaneous Sine and Cosine
FSINCOS	FPm,FPc:FPs	
FTRAP<cc>		Trap on Floating-Point Condition
FTRAP<cc>.x	#<data>	
FTST.x	<ea>	Test Floating-Point Operand
FTST	FPm	

Floating-Point Condition Codes <cc>:

F	false	EQ	equal
---	-------	----	-------

OGT	ordered greater than	OGE	ordered gt. than or equal
OLT	ordered less than	OLE	ordered less than or equal
OGL	ordered greater or less than	OR	ordered
UN	unordered	UNE	unordered or equal
UGT	unordered or greater than	UGE	unord. or gt. than or equal
ULT	unordered or less than	ULE	unord. or less than or equal
NE	not equal	T	true
SF	signaling false	SEQ	signaling equal
GT	greater than	GE	greater than or equal
LT	less than	LE	less than or equal
GL	greater than or less than	GLE	gt. or less than or equal
NGLE	not (gt. or less or equal)	NGL	not (greater or less than)
NLE	not (less than or equal)	NLT	not (less than)
NGE	not (greater than or equal)	NGT	not (greater than)
SNE	signaling not equal	ST	signaling true

1.27 Floating Point Instructions (68040,68060)

FSADD	Add Single Precision
FDADD	Add Double Precision
FSDIV	Single Precision Divide
FDDIV	Double Precision Divide
FSMOVE	Single Precision Move
FDMOVE	Double Precision Move
FSMUL	Single Precision Multiply
FDMUL	Double Precision Multiply
FSNEG	Single Precision Negate
FDNEG	Double Precision Negate
FSSQRT	Single Precision Square Root
FDSQRT	Double Precision Square Root
FSSUB	Subtract Single Precision
FDSUB	Subtract Double Precision

1.28 PMMU Instructions (68851)

PB<cc>.x	<label>	Branch on PMMU Condition
PDB<cc>	Dn,<label>	Test, Decr., and Branch on PMMU Cond.
PFLUSHA		Invalidate Entries in the ATC
PFLUSH	<fc>,#<mask>	
PFLUSHS	<fc>,#<mask>	
PFLUSH	<fc>,#<mask>,<ea>	
PFLUSHS	<fc>,#<mask>,<ea>	
PFLUSHR	<ea>	Invalidate ATC and RPT Entries
PLOADR	<fc>,<ea>	Load an Entry into the ATC
PLOADW	<fc>,<ea>	
PMOVE	<PMMU Register>,<ea>	Move PMMU Register
PMOVE	<ea>,<PMMU Register>	
PRESTORE	<ea>	PMMU Restore Function
PSAVE	<ea>	PMMU Save Function
PS<cc>	<ea>	Set on PMMU Condition
PTESTR	<fc>,<ea>,#<level>	Get Information About Logical Address
PTESTR	<fc>,<ea>,#<level>,An	

```

PTESTW      <fc>, <ea>, #<level>
PTESTW      <fc>, <ea>, #<level>, An
PTRAP<cc>                                     Trap on PMMU Condition
PTRAP<cc>.x #<data>

```

PMMU Condition Codes <cc>:

```

BS, BC      Bus Error
LS, LC      Limit Violation
SS, SC      Supervisor Only
AS, AC      Access Level Violation
WS, WC      Write Protected
IS, IC      Invalid Descriptor
GS, GC      Gate
CS, CC      Globally Sharable

```

PMMU Registers:

```

CRP, SRP, DRP, TC, BACx, BADx, AC, PSR, PCSR, CAL, VAL, SCC

```

1.29 PMMU Instructions (68030)

```

PFLUSHA                                     Flush Entry in the ATC
PFLUSH      <fc>, #<mask>
PFLUSH      <fc>, #<mask>, <ea>
PLOADR      <fc>, <ea>                      Load an Entry into the ATC
PLOADW      <fc>, <ea>
PMOVE       MRn, <ea>                       Move to/from MMU Registers
PMOVE       <ea>, MRn
PMOVEFD     <ea>, MRn
PTESTR      <fc>, <ea>, #<level>           Test a Logical Address
PTESTR      <fc>, <ea>, #<level>, An
PTESTW      <fc>, <ea>, #<level>
PTESTW      <fc>, <ea>, #<level>, An

```

PMMU Registers (MRn):

```

SRP, CRP, TC, MMUSR (PSR), TT0, TT1

```

1.30 PMMU Instructions (68040,68060)

```

PFLUSH      (An)                            Flush ATC Entries
PFLUSHN     (An)
PFLUSHA
PFLUSHAN

PTESTR      (An)                            Test a Logical Address
PTESTW      (An)                            (68040 only!)

PLPAR       (An)                            Translate Logical to Physical
PLPAW       (An)                            (68060 only!)

```

1.31 Expressions

Expressions consist of symbols and constants. Symbols can be absolute, relocatable or external. The arithmetic and logic operations for INTEGER expressions, supported by PhxAss, are (from highest to lowest precedence) :

- | | | | | | | |
|----|-----|----------------|--------|-----------------------|----|--------------|
| 1. | ~ | not (unary) | - | negation (unary) | | |
| 2. | << | shift left | >> | shift right | | |
| 3. | * | multiplication | / | division | // | modulo |
| 4. | & | and | | or ('!' also allowed) | ^ | exclusive or |
| 5. | - | subtraction | + | addition | | |
| 6. | () | parentheses | or [] | brackets | | |

For absolute symbols and constants (which are absolute too), all arithmetic operations are allowed.

If relocatables or externals occur in the expression, only subtraction and addition is possible with some restrictions:

reloc - abs	extern - abs	reloc - reloc	
reloc + abs	extern + abs	abs + reloc	abs + extern
(reloc-reloc)<<abs	(reloc-reloc)>>abs	(V3.95 feature)	

are defined, the others are illegal.

FLOAT expressions consist of floating point constants, absolute integer constants and symbols. The following operations and functions are valid for float expressions (V4.00 feature):

Binary:

+	plus	-	minus	*	multiplication
/	division	^	power		

Unary:

-	negation	sqr	square root	exp	e^x
log	nat. logarithm	sin	sine	cos	cosine
tan	tangent				

SQR, EXP, LOG, SIN, COS and TAN are functions and not case sensitive. They are usually introducing a term, e.g. "sin(3.14159)". But if, as in the last example, the term only consists of a single constant, it is also allowed to write "sin:3.14159". The ':' is required to separate the function name from a possible symbol name.

There are six types of constants:

Hexadecimal, preceded by a '\$', consists of '0'-'9' and 'A'-'F' (or 'a'-'f')

Decimal, consists of '0'-'9'

Float, has the format [+/-][integer][.fraction][E[+/-]exponent]

Octal, preceded by a '@', consists of '0'-'7'

Binary, preceded by a '%', consists of '0' and '1'

String, embedded by ' or ", consists of one to four characters.

The character '\ ' is an escape-symbol, which can generate the following codes:

\\	the '\'-character itself
\'	character #39 (single quote)
\"	character #34 (quote)

```

\0    character #0  (string terminator)
\n    character #10 (line feed)
\f    character #12 (form feed)
\b    character #8  (backspace)
\t    character #9  (tabulator)
\r    character #13 (carriage return)
\e    character #27 (escape)
\c    character #155(control sequence introducer)

```

" " and ' ' within a string will be replaced by " " and ' ' (V4.14).

1.32 Assembler Directives

The following paragraphs describe all directives that are supported by PhxAss. Important note! Directives must *not* start at the first column of a line or they will be treated as labels! (note for Seka users :-)

Directives supported by PhxAss:

BLK	Define Constant Block
BSS	Bss section
BSS	Allocate storage for Bss symbol
BSS_C	Chip-RAM Bss section
BSS_F	Fast-RAM Bss section
CLRFO	Reset FO-counter
CLRSO	Reset SO-counter
CNOP	Align the following code
CODE	Code section
CODE_C	Chip-RAM Code section
CODE_F	Fast-RAM Code section
COMMENT	Comment line
CSEG	Code section
DATA	Data section
DATA_C	Chip-RAM Data section
DATA_F	Fast-RAM Data section
DC	Define Constant
DCB	Define Constant Block
DEBUG	Store current address in Line Debug block
DS	Define Storage
DSEG	Data section
DSOURCE	Set complete source path for Line Debug block
DX	Define Storage
ECHO	Print string
ELSE	Define ELSE-part for conditional assembly
ELSEIF	Define ELSE-part for conditional assembly
EQU	Assign expression to symbol
EQU.x	Assign floating point expression to symbol
EQR	Assign register to symbol
EQURL	Assign register list to symbol (OMA)
END	End of source text
ENDC	End of conditional assembly
ENDIF	End of conditional assembly
ENDM	End of Macro definition
ENDR	End of REPT loop
EVEN	Align the following code to an even address

FAIL	Abort assembly
FAR	Enter Far mode
FEQUR	Assign FPU register to symbol
FEQURL	Assign FPU register list to symbol (OMA)
FILE	Destination file for absolute code
FO	Assign value of FO-counter to symbol
FPU	Enable FPU code generation
FREG	Assign FPU register list to symbol
GLOBAL	Allocate storage for global Bss symbol
IDNT	Set unit name
IFC	Cond.Ass.: Compares two strings for equality
IFD	Cond.Ass.: Test if a symbol is defined
IFEQ	Cond.Ass.: Test if expression is zero
IFGT	Cond.Ass.: Test if expression is greater than zero
IFGE	Cond.Ass.: Test if exp. is greater or equal to zero
IFLT	Cond.Ass.: Test is exp. is less than zero
IFLE	Cond.Ass.: Test if exp. is less or equal to zero
IFNC	Cond.Ass.: Compares two strings for difference
IFND	Cond.Ass.: Test if a symbol is undefined
IFNE	Cond.Ass.: Test if expression is not zero
IF	Cond.Ass.: Test if expression is not zero
IMAGE	Include binary file (AsmOne)
INCBIN	Include binary file
INCDIR	Set Include directory path
INCLUDE	Include another source file
INITNEAR	Initialize near mode base register
INT	Assign value of float expression to an integer SET-symbol
LINEDEBUG	Generate debug hunk for source level debugger
LIST	Next lines to listing file
LOAD	Destination address for absolute code
MACHINE	Set CPU type
MACRO	Macro definition
MC680x0	Set CPU type
MEXIT	Exit Macro
NEAR	Enter Near mode
NOLIST	Next lines are invisible in listing file
NREF	Import Near-symbol
OFFSET	Start Offset section
OPT	Change optimization mode
ORG	Set absolute code origin
OUTPUT	Define destination file name
PMMU	Enable 68851 code generation
PROCSTART	Start of C-function for DICE-Compiler
PROCEND	End of C-function for DICE-Compiler
PUBLIC	Import/Export symbol
REG	Assign register list to symbol
REPT	Repeat lines between REPT and ENDR
RESTORE	Reactivate the last saved section
RORG	Set offset to start of section
RS	Assign value of RS-counter to symbol
RSRESET	Reset RS-counter
RSSET	Set RS-counter
SAVE	Saves the state of the current section
SECTION	Set section for following code
SET	Change value of SET-symbol
SET.x	Change value of floating point SET-symbol
SETFO	Set FO-counter

SETSO	Set SO-counter
SFORM	Creates Motorola S-Record format
SO	Assign value of SO-counter to symbol
STYPE	Selects a specific S-Record format and length
SUBTTL	(no function)
SYMDEBUG	Global symbols are made visible for a debugger
TTL	Set unit name
TRACKDISK	Absolute code directly to disk
XDEF	Export symbol
XREF	Import symbol

1.33 EQU

```
symbol equ <expression>
symbol = <expression>
```

The expression will be assigned to the symbol.

1.34 EQU.x

```
symbol equ.x <float expression>
symbol =.x <float expression>
```

An equate with extension `.d`, `.f`, `.p`, `.s`, `.x` will assign the value of a floating point expression to the symbol. If you want to know more about float expressions, refer to Expressions.

This is a special PhxAss directive.

1.35 EQU.R

```
symbol equ.r <register>
```

This directive assigns a register (D0-D7, A0-A7 or SP) or (since v4.20) a register symbol to the specified symbol.

Since V3.00 a register symbol must be defined before the first reference.

1.36 REG

```
symbol reg <register list>
symbol equ.r <register list>
```

These directives assign the value of the register list to the symbol. Valid register lists contain several register names (see EQU.R) separated by the `'/'` character. The `'-'` character defines a range of registers. The following are valid register lists:

```
a1/a3-a5/d0/d2/d4
```

```
d0-d7/a2-a6
d1-3/d5-7/a0-1/a3-6 (since V3.56)
```

1.37 FREG

```
symbol freg <register list>
symbol fequrl <register list>
```

These directives assign a FPU register list to the specified symbol. Valid register lists contain the FPU registers FP0-FP7 separated by the '/' character. The '-' character defines a range of FPU registers. The following are valid FPU register lists:

```
fp1/fp3-fp5/fp0
fp0-fp7
```

1.38 FEQR

```
symbol feqr <fpu register>
```

This directive assigns an FPU register (FP0-FP7) or another register symbol to the specified symbol. The register symbol must be defined before the first reference.

1.39 SET

```
symbol set <absolute expression>
```

This directive assigns the value of the expression to the symbol. No relocatables or externals are allowed within the expression. A symbol defined by a SET directive may change its value by another SET. There are some set-symbols which are defined by PhxAss:

```
_PHXASS_ set 1
_VERSION_ set version<<16+revision
```

According to the connected processor and co-processor PhxAss will set `_MC68000_`, `_MC68010_`, `_MC68020_`, `_MC68030_`, `_MC68040_`, `_MC68060_`, `_MC68881_` and `_MC68882_`.

The following symbols will reflect the selected type of code generation for the different types of CPUs and co-processors, as defined by the directives MACHINE, FPU and PMMU:

```
__CPU : 68000, 68010, 68020, 68030, 68040, 68060
__FPU : 0 or FPU-Id 1-7
__MMU : 0 or 1 on PMMU code generation
```

NARG is zero outside a macro. Within a macro NARG is set to the number of specified arguments.

CARG is initialized by 1, whenever a macro was entered. It may

be used to indirectly select specific macro parameters, which can be done by using the special symbols `\.`, `\+` and `\-` (see also `MACRO` directive).

`__RS` always reflects the current RS-counter value.

1.40 SET.x

```
symbol set.x <float expression>
```

A SET with extension `.d`, `.f`, `.p`, `.s`, `.x` will assign the value of a floating point expression to the symbol. You may change its value by another SET, later in the source, provided that you don't change its type (e.g. "symbol SET.S" followed by "symbol SET.D"). This is a special PhxAss directive.

1.41 INT

```
symbol int <float expression>
```

The float expression will be evaluated and the result, without the fractional part, will be assigned to an integer symbol.

1.42 RSRESET,CLRSO

This directive resets the internal RS and SO structure offset counters.

1.43 RSSET,SETSO

```
rsset [<count>]
setso [<count>]
```

These directives set the internal RS and SO structure offset counters to the value of the `<count>` expression.

1.44 RS,SO

```
[symbol] rs.x [<count>]
[symbol] so.x [<count>]
```

RS or SO assigns the value of the internal RS/SO-counter to the symbol, then it increases the offset-counter by the extension size multiplied with `<count>`.

If `<count>` is missing, it defaults to zero. For valid extensions refer

to the DC directive.

The current value of the RS/SO-counter is also reflected by the `__RS` and `__SO` symbols.

1.45 CLRFO

This directive resets the internal frame offset counter FO.

1.46 SETFO

```
setfo    [<count>]
```

This directive sets the internal frame offset counter to the value of the `<count>` expression.

1.47 FO

```
[symbol] fo.x    [<count>]
```

FO decrements the internal frame offset counter by the extension size multiplied with `<count>`, then assigns this value to the given symbol (if present). If `<count>` is missing, it defaults to zero. For valid extensions refer to the DC directive.

The current FO-counter value is also reflected by the `__FO` symbol.

1.48 IDNT

```
idnt    <name>
ttl     <name>
```

These directives set the name of the object file unit which the assembler will generate. By default, it will be the name of the source file without the extension.

1.49 SUBTTL

Source texts containing `subttl` will cause no error with PhxAss, but for now it does completely nothing.

(To be honest, I've no idea what it should do! Please write me, if somebody knows it.)

1.50 COMMENT

```
comment text
```

You may write any text you like behind this directive.

1.51 LIST

The following source code will be written to the listing file.

1.52 NOLIST

The following source code will not be written to the listing file.

1.53 OPT

```
opt <optimize flags>
```

Changes optimization level. For a listing of all optimize flags, see Command line parameters.

This is a special PhxAss directive.

1.54 MACRO, ENDM

```
symbol macro
...text...
endm

macro symbol
...text...
endm
```

This directive assigns a macro to the specified symbol. The symbol may appear on the left or right side of the directive. The text between the MACRO and ENDM directives will be inserted into the source code when the assembler discovers this symbol. When invoking the macro, up to 35 arguments, separated by a commas, can be specified in the operand field. They are referenced in the macro text as '\1' through '\9' and (since V4.18) as '\a' through '\z' for the last 26.

'\0' is reserved for the extension of the macro symbol. Example:

```
bhs macro
bcc.\0 \1
endm
```

This macro can be called by: bhs.s label

".s" will be assigned to \0 and "label" will be assigned to \1. A "\@" within the macro is replaced by text of the form "nnn", where nnn is a unique three-digit number for each macro call.

Labels within a macro should consist of "\@", because defining labels twice is illegal.

There is a limitation for using macro parameters in string constants. Only \1 through \9 are allowed to avoid problems with escape symbols. Since v4.33 \0 is allowed too, so be careful with using the string-termination escape code in macros.

V4.33:

A macro parameter may be accessed indirectly by using \., \+ or \-. The number of the parameter is taken from the SET-symbol CARG. \+ postincrements CARG after the operation and \- post-decrements it. By using \. CARG remains unchanged.

Additionally < ... > may be used to indicate a larger range as a single indivisible macro parameter. Examples:

```
PRINT    <Hello World>
DCB      <"Test",0>
```

1.55 MEXIT

Upon encountering this directive within a macro, the assembler scans for the ENDM directive and leaves the macro.

1.56 END

In pass one the assembler ignores the rest of the source code and starts pass two. In pass two the assembler closes all files and terminates. By default the assembler terminates at end of file.

1.57 FAIL

The assembler displays the error "69 Assembly aborted !" and terminates.

1.58 ECHO

```
echo    <string>
```

The assembler echoes the string. If <string> isn't specified, only a newline is echoed.

This is a special PhxAss directive.

1.59 MACHINE

```
machine <processor-type>
```

This directive sets the `processor-type` for which the code will be generated. Valid `processor-types` are:
68000, 68010, 68020, 68030, 68040, 68060
MACHINE 68000 has the side effect of deactivating the 68851 code generated, activated by PMMU (v4.30).
The implementation of this directive may be different in other assemblers.

1.60 MC680x0

```
mc68000  
mc68010  
mc68020  
mc68030  
mc68040  
mc68060  
mc68881  
mc68882  
mc68851
```

Like MACHINE, this directive sets the `processor-type` for which the following code will be generated.

1.61 FPU

```
fpu [<cpID>]
```

This directive enables code generation for a MC68881/68882 coprocessor. By default the `<cpID>` is set to one, which should be the correct ID for most systems using a floating point coprocessor. Never set `<cpID>` to zero, because this is the constant ID for a PMMU. If you have set the `processor-type` to 68040 or 68060 you should not use this directive.
This is a special PhxAss directive.

1.62 PMMU

This directive enables code generation for a MC68851 Paged Memory Management Unit. PMMU only makes sense if you have set the `processor-type` to '68020'.
This is a special PhxAss directive.

1.63 SECTION

```
section <name>[,<type>[,<memflag>]]
```

The subsequent code will be placed in the section named <name>. There are three section types: CODE, DATA and BSS. CODE contains the executable M68000 instructions, DATA contains initialized data and BSS contains uninitialized data (set to zero before the program is started). By default <type> is set to CODE. The section will be loaded to the memory indicated by the <memflag> argument. This can be FAST or CHIP. By default the section will be loaded to the memory with the highest priority.

For compatibility reasons CODE_C, DATA_C and BSS_C are also recognized as section type since V3.56 (the ???_F-types since v4.30 too).

Creating a section lets the assembler change into relocatable mode. In this mode the following directives are illegal:
org, load, file, trackdisk.

1.64 CODE, CSEG

These directives correspond to: section "CODE",code

1.65 DATA, DSEG

These directives correspond to: section "DATA",data

1.66 CODE_C, CODE_F, DATA_C, DATA_F, BSS_C, BSS_F

See CODE, DATA or BSS. In addition a memflag will be set, which causes the section to be loaded to FAST (xxx_F) or to CHIP (xxx_C).

1.67 BSS

This directive corresponds to: section "BSS",bss

1.68 BSS

```
bss      symbol,<size>
```

BSS with arguments does not start a section. It defines a symbol to be in the BSS-section, reserves <size> bytes in this section and assigns the address of the first byte to the symbol.

This directive is for Aztec-C compatibility only.

1.69 GLOBAL

```
global    symbol,<size>
```

This directive does the same as BSS `symbol,<size>`. In addition GLOBAL will declare the symbol as XDEF (`ext_def`). It is for Aztec-C compatibility only.

1.70 OFFSET

```
offset    [<start offset>]
```

This directive indicates the beginning of a special offset-section. All the labels, which are declared in this section, will be treated as absolute offsets instead of addresses. `<start offset>` defaults to zero. This might be useful for declaring structure offsets with the `DS.x` directive. While writing programs for PhxAss you should prefer the faster `RSRESET`, `RSSET` and `RS.x` directives. OFFSET was mainly implemented for compatibility reasons.

1.71 RORG

```
rorg      <section offset>
```

This directive defines the offset of the subsequent code relative to the start of the current section. `<section offset>` must be positive.

1.72 INCDIR

```
incdir    <path1>[,<path2>,...]
```

This directive does the same like the `INCPATH` argument (see Command line arguments). Note that other assemblers don't accept multiple paths.

1.73 INCLUDE

```
include   <filename>
```

This directive causes PhxAss to suspend the assembling of the current file and to assemble the file named `<filename>`. When done, PhxAss continues assembling the original file. If PhxAss can't find the include file, it first searches in the include directory defined by the environment variable `PHXASSINC`. Then it searches in the include directories defined by `INCPATH` parameters (see Command line arguments). At last, the directories defined by `INCDIR` are searched.

1.74 INCBIN

```
incbin    <file name>
image     <file name>
```

This directive causes the assembler to include a binary file into the current section (e.g. graphics, samples or trigonometrical tables). The assembler searches in the same include directories like INCLUDE.

1.75 XREF

```
xref      symbol1[,symbol2,...]
```

This directive tells the assembler that the specified symbols are externally defined and will be inserted by the linker. Note that other assemblers may not support multiple symbols.

1.76 NREF

```
nref      symbol1[,symbol2,...]
```

This directive does the same like XREF, but the assembler is forced to use these symbols as near-data relocatables. This is a special PhxAss directive.

1.77 XDEF

```
xdef      symbol1[,symbol2,...]
```

This directive causes the assembler to add the names and values of the specified symbols to the external-block of the object file. The linker can read the values of these symbols and insert them into other object files.

Note that other assemblers may not support multiple symbols.

1.78 PUBLIC

```
public    symbol1[,symbol2,...]
```

When the specified symbols are defined in the current code, PUBLIC will do the same like XDEF. When the symbols are unknown, PUBLIC will do the same like XREF.

This directive is for Aztec-C compatibility only.

1.79 ORG

org address

Defines the origin of the subsequent code and lets the assembler change into absolute mode. Since V1.8 several ORG directives are allowed and each one can be seen as a new section. The following directives are illegal in absolute mode:

t11, code, cseg, section, offset, xref,
nref, xdef, public, idnt.

1.80 LOAD

load address

After assembling is done, the absolute code will be loaded to this address. By default the code will be loaded to the address which was specified as origin. Be cautious with this directive, because the destination memory will neither be checked nor allocated.

This is a special PhxAss directive (also known from SEKA).

1.81 FILE

file <filename>

After assembling is done, the absolute code will be written into the file named <filename>.

This is a special PhxAss directive.

1.82 SFORM

sform <filename>

After assembling is done, the absolute code will be written as a Motorola S-Record with the name <filename>.

You should always consider, that the S-Format supports only 24-Bit addresses.

This is a special PhxAss directive.

1.83 STYPE

stype <s-format>[,<record-length>]

<s-format> selects one of the following three S-Record formats:

- 1: S0-Header, S1-Data (16-bit addresses), S9-Trailer
 - 2: S0-Header, S2-Data (24-bit addresses), S8-Trailer (default format)
 - 3: S0-Header, S3-Data (32-bit addresses), S7-Trailer
-

The optional parameter <record-length> controls the number of character-pairs in the data records and must be a value between 16 and 255.

1.84 TRACKDISK

```
trackdisk <drive>,<startblock>[,<offset>]
```

After assembling is done, the absolute code will be written directly to floppy disk using the 'trackdisk.device'. <drive> is valid from 0 to 3. <startblock> is valid from 0 to 1759 (or 3519, if you have a HD drive). <offset>, which is zero by default, specifies the byte-offset within a block and is valid from 0 to 511.

This is a special PhxAss directive.

1.85 OUTPUT

```
output <filename>
```

Defines the name of the destination file and overwrites the default- or by the command line parameter TO specified name.

1.86 SYMDEBUG

```
symdebug
```

The names of all global labels of each section are stored to symbol data blocks. A debugger can use these names instead of addresses. Equivalent to the CLI parameter DS=SYMDEBUG/S.

1.87 LINEDEBUG

```
linedebug
```

PhxAss creates a linedebug block, which can tell a Source Level Debugger the right line in your source code for any address. The location of your source is stored in this block with a complete path, e.g. "Work:Programs/Assembler/Tools/Source/Test.asm" (this is, for example, not the case with SAS's ASM :-). LINEDEBUG is equivalent to the CLI parameter DL=LINEDEBUG/S.

Compilers should use the directives DEBUG and DSOURCE instead this option. A useful PD-Debugger with source level debugging capabilities is for example "PowerVisor v1.42", which can be found on Aminet dev/debug/pv142.lha or on the GoldFish-CD.

1.88 NEAR

```
near      [An[,<secnum>]]
```

This directive initializes the parameters used by the near-data model. Since v4.33 NEAR inclusive arguments may appear multiple times in the source text to select different base registers for some parts of the program.

You must not use 'NEAR An,0' before the first SECTION, CODE, DATA, etc. directive.

After initializing the small-data model, it can be switched on and off by NEAR and FAR without arguments. In this mode you are allowed to access near-symbols via 'NearSymbol(An)'. Absolute references will be automatically converted to Address Register Indirect, if possible. The first argument, the address-register, is valid from A0 to A6 and will be A4 by default. <secnum>, which defaults to -2, specifies the number of the section which will be accessed by Address Register Indirect mode.

If <secnum> is -1, all Data and Bss sections will be added to one large small data section. Either PhxAss will do this job immediately, when creating an executable file, or you must invoke your Linker with the correct small data option.

If <secnum> is -2, only the Data or Bss sections which were named "__MERGED", will be added to the small data section.

```
near      code
```

If the argument equals to the string "CODE" the assembler activates the near-code model. This will force all absolute XREF jumps into PC-relative mode.

Note that other assemblers don't accept any parameters for NEAR.

1.89 FAR

This directive deactivates the near-code/data model when active.

1.90 INITNEAR

This directive inserts two M68000 instructions into the code which will initialize the small-data model depending on the parameters set by the NEAR directive. The assembler will generate this code (10 bytes):

```
lea      SmallDataBase,An
lea      32766(An),An
```

This is a special PhxAss directive.

1.91 DC

```
label    dc.?    <expression>[,<expression>,...]
label    dc.b/w/l "string"[,...]
```

The DC (Define Constant) directive causes one or more fields of memory to be allocated and initialized. Each field has the same size, specified by the extension of the directive. Each byte, word or longword <expression> can be an expression and may contain forward references. The following extensions are valid:

.B	(1 byte)	Byte	.W	(2 bytes)	Word
.L	(4 bytes)	Longword	.F	(4 bytes)	Fast Flt. Point
.S	(4 bytes)	Single Precision	.D	(8 bytes)	Double Precision
.Q	(8 bytes)	Quadword (V3.42)	.X	(12 bytes)	Ext. Precision
.P	(12 bytes)	Packed BCD			

Note that other assemblers may not support the floating-point and quadword types.

1.92 DCB, BLK

```
label    dcb.x    <num>[,<fill>]
label    blk.x    <num>[,<fill>]
```

These directives allocate a block of memory having <num> entries. The available entry sizes are the same like with DC. The block will be initialized with <fill>, which is zero when missing. For valid extensions, refer to DC.

1.93 DS, DX

```
label    ds.x    <num>
label    dx.x    <num>
```

This directive allocates a block of memory having <num> entries and initializes each field with zero. See DCB, BLK.

1.94 CNOP

```
cnop    <offset>,<align>
```

This directive aligns the address of the following code to <align>. Then the <offset> is added. Example: `cnop 2,4`. This example would align the next address two bytes behind the next longword boundary. Note that an <align> larger than 8 makes no sense, if you're creating relocatable code (see AllocMem(), exec.library).

AVOID referencing an address before a cnop by using a label behind the cnop:

```
        lea    label-4,a0
        CNOP   0,4
label:
```

1.95 EVEN

This directive corresponds to `cnop 0,2` which will make the address word-aligned.

1.96 IFcond, ELSEIF, ELSE, ENDIF, ENDC

These directives support conditional assembling. The general form of the IF directive is:

```

    if<cond>    <expression> or symbol
    ...
    [else (or elseif)
    ...]
    endc (or endif)

```

PhxAss supports the following conditions:

IFC "string1", "string2"	compares two strings. This is useful within macros, when the strings contain macro-arguments '\x' .
IFD/IFND symbol	tests if the symbol is defined (undefined).
IFEQ/IFNE <exp>	tests if <exp> is zero (not zero).
IFGT/IFLT <exp>	tests if <exp> is greater (less) than zero.
IFGE/IFLE <exp>	tests if <exp> is greater (less) than or equal to zero.
IF <exp>	is an alias for IFNE.

1.97 PROCSTART,PROCEND

These directives are for compatibility with the DICE-C sytem. But currently they do nothing. For the future it should be possible to remove `LINK A5,#0 / UNLK A5` when A5 is not referenced between PROCSTART and PROCEND.

1.98 REPT/ENDR

```

    rept    <count>
    ...
    endr

```

The part of source code, embedded by REPT/ENDR, will be assembled <count> times. A negative <count> is illegal.

1.99 SAVE

```

    save

```

Saves the name and type of the current section, so that it can be reactivated by RESTORE later. Very useful in

macros. Example:

```
print    macro
         save
         section strings,data
\@       dc.b    \1,0
         restore
         lea    \@,a0
         bsr    printstring
         endm
```

1.100 RESTORE

```
restore
```

Reactivates the section which was last saved by the SAVE directive.

1.101 DEBUG

```
debug    <line number>
```

Links the line <line number> of a high level source (full path must be defined by DSOURCE) with the current address and appends this information to the Line Debug block. Very useful for compilers, which want to offer source level debugging. Don't set LINEDEBUG/S when using this directive!

1.102 DSOURCE

```
dsource  <source path>
```

Defines the full path of your high level source. E.g.:
"Work:Programs/C/Test/Source/HelloWorld.c".
See DEBUG for additional information.

1.103 Compiler Compatibility

A major reason for writing PhxAss was to create a program which can replace the very slow AS-assembler of Aztec-C. There are many directives for Aztec-compatibility, but since V3.30, where symbols preceded by a '.' are regarded as local symbols, it is nearly impossible to assemble Aztec compiler outputs. The only solution is to write a program which translates all '.nnn' symbols into '_nnn', for example.

Since introducing the new directives PROCSTART and PROCEND in V3.71, DICE-C sources are completely supported.

1.104 PhxOpts

PhxOpts from Johan Johanssen offers a GUI to predefine most options for PhxAss and save them either as a global or local options file. So any of your projects can get a local PHXOPTIONS file, which contains all options you don't want to specify with every invocation of PhxAss. If no local options file is present in your current directory, PhxAss will look for the global one in ENV:PhxAss.

PhxOpts requires the triton.library to work.

1.105 Environment Variables

PhxAss searches in ENV:PhxAss/ for environment variables. Currently there are two:

PHXASSINC Specifies the path where to look for include files, if they are not located in the current directory.
Note, that the location of PHXASSINC has changed in v4.20!
Before it was ENV:PHXASSINC.

PHXOPTIONS Contains several global predefined options, which will be passed to PhxAss when no local PHXOPTIONS in the current directory was found. PHXOPTIONS can be edited manually, but will be normally created by the PhxOpts GUI from Johan Johanssen, which should be in your PhxAss archive.
The options, which are passed to PhxAss via the command line, have priority and will overwrite those predefined ones.

1.106 Linker

You may use any linker which supports the standard Amiga DOS object file format. For example BLink, DLink, etc. - but I recommend that you use PhxLnk, of course :-). You will find it on Aminet in dev/asm, named PhxLnk4xx.lha.

Since V4.00, you only need a linker when you have more than a single module. PhxAss automatically generates an executable, if no external references are present.

Two features of PhxLnk are not implemented in PhxAss:

1. Generation of HUNK_RELOC32SHORT blocks (16-bit offsets)
2. Removing zero-bytes at the end of a Code or Data section (so called Code-Bss or Data-Bss sections)

If you want to use one of these features (which requires OS2.04 to run your program), you should set the NOEXE switch and invoke PhxLnk.

1.107 Assembler Errors

In the current version of PhxAss the following errors could occur:

- 01 Out of memory
 - 02 Unable to open utility.library
 - 03 Can't open timer.device
 - 04 DREL16 out of range
Your Small Data area is too large. 64k is the limit for all data and bss sections together.
 - 07 HEADINC: file name expected
Example: PhxAss HEADINC "dh0:file1,dh1:xdir/file2,"
 - 08 IncDir path name expected
Example: incdir "dir1","dir2",
Caused also by INCPATH.
 - 10 SMALLDATA: Illegal base register
Allowed are 2-6 for A2-A6. A4 is standard.
 - 11 MACHINE not supported
The current version of PhxAss supports 68000, 68010, 68020, 68030, 68040 and 68060.
 - 12 File doesn't exist
Unable to open your source code.
 - 13 Missing include file name
 - 14 Read error
 - 15 String buffer overflow
The length of a label, opcode or operand is limited to a length of 128 characters.
 - 16 Too many sections
Maximum is 250 sections.
 - 17 Symbol can't be made external
XDEF can only be used on absolute or relocatable symbols.
 - 18 Symbol was declared twice
Only SET symbols can be declared more than once.
 - 19 Unable to make XREF symbol
A symbol, which is already defined in the current source code, can't be an XREF at the same time. Or: A symbol which is already declared as XREF can't be defined.
 - 20 Illegal opcode extension
Legal: .b .w .l .s .f .d .x .p .q
 - 21 Illegal macro parameter
Possible parameters are: \0 (opcode extension), \1 - \9, \a - \z
-

and \@

- 22 Illegal characters in label
Refer to Labels in Programmer Information.
- 23 Unknown directive
The opcode is neither a 680x0-mnemonic nor an assembler directive or macro.
- 24 Too many parameters for a macro
35 parameters (\1 through \9 and \a through \z) are possible.
- 25 Can't open trackdisk.device
- 26 Argument buffer overflow
Arguments are in most cases limited to 128 characters.
- 27 Bad register list
Valid register lists: d0-d3 d3-d4/a2 d2/d3/a4-a6 d7 a0/d2 d2-6/a0-4
- 28 Missing label
The directive requires a label.
Example: EQU <exp> -> Error 28
- 29 Illegal separator for a register list
Valid separators are '-' and '/'.
- 30 SET, MACRO, XDEF, XREF and PUBLIC are illegal for a local symbol
- 31 Not a register (try d0-d7 or a0-a7 or sp)
- 32 Too many ')'
- 33 Unknown addressing mode
See Standard Addressing Modes and Extended Addressing Modes for a complete description of all addressing modes.
- 34 Addressing mode not supported
Example: move.b d0,a1 / move usp,d2 / clr.w (d3)+ -> Error 34
- 35 Can't use macro in operand
Macros must be used as opcodes.
- 36 Undefined symbol
- 37 Missing register
Example: mulu d0, -> Error 37
- 38 Need data-register
- 39 Need address-register
- 40 Word at odd address
Example: dc.b "Hallo"
dc.w 0 -> Error 40
Insert CNOP 0,2 or EVEN after string-constants.
-

-
- 41 Syntax error in operand
- 42 Relocatability error
Example: `move.l label(pc),d0` , where label is not a reloc. and/or label is not defined in the current section -> Error 42
- 43 Too large distance
Example: `move.w 50000(a0),d0` -> Error 43
Too large distance for a displacement by indirect addressing or branch. Short branches have a range of +126/-128 bytes. Long branches have a range of +32766/-32768 bytes.
- 44 Displacement expected
Example: `label: move.l label(a2),d1` -> Error 44
- 45 Valid address expected
A program address was expected.
- 46 Missing argument
- 47 Need numeric symbol
- 48 Displacement outside of section
Example: `bra label` , where label is not defined in the current section -> Error 48
- 49 Only one distance allowed
Expression can't contain several distances.
Example: `move.l #(label1-label2)+(label3-label4),d0` -> Error 49
- 50 Missing bracket/parenthesis
- 51 Expression stack overflow
A maximum of 128 arguments are allowed in one expression.
- 52 Unable to negate an address
- 53 Can't use distance and reloc in the same expression
Example: `move.l #(label1-label2)+label3,d0` -> Error 53
- 54 Shift error (wrong type or negative count)
Example: `l<<-1` -> Error 54
`label<<1` -> Error 54
- 55 Can't multiply an address
- 56 Overflow during multiplication
- 57 Can't divide an address
- 58 Division by zero
- 59 No logical operation allowed on addresses
- 60 Need two addresses to make a distance
- 61 Unable to sum addresses
- 62 Write error
- 63 Not a byte-, word- or long-string
Example: `dc.d "XYZ"` -> Error 63
-

-
- 64 Can't subtract a XREF
Valid operations with externals: `ext + abs` , `abs + ext` and `ext - abs`
- 65 Impossible in absolute mode
These directive can't be used in absolute mode:
`ttl`, `code`, `cseg`, `data`, `dseg`, `bss`, `section`, `xref`, `nref`, `xdef`, `public`
- 66 Unknown error (fatal program failure)
The assembler or its memory was corrupted by a faulty program running at the same time.
- 67 No externals in absolute mode
See 65.
- 68 Out of range
Example: `addq.l #9,d1` -> Error 68
- 69 Assembly aborted
Generated by the FAIL directive.
- 70 Missing ENDC/ENDIF
- 71 Missing macro name
- 72 Missing ENDM
- 73 Can't define macro within a macro
- 74 Unexpected ENDM
- 75 Unexpected ENDC/ENDIF
- 76 Impossible in relative mode
These directive can't be used in relative mode: `org`, `file`, `load`, `track-disk`.
- 77 Parameter buffer overflow
Macro parameters are limited to 127 characters.
- 78 Illegal REPT count
The initial count for REPT should not be negative.
- 79 Unable to create file
Maybe the destination disk is write-protected.
- 80 No reference list without a listing file
XREFS switch was specified without the LIST switch.
- 81 No address allowed here
Example: `ds.l label` -> Error 81
- 82 Illegal characters in symbol
See error 22.
- 83 Source code too large (max. 65535 lines)
- 84 No floating point without the appropriate math-libraries
-

To use floating point symbols, you must have the following libraries in your LIBS: directory:
mathtrans.library, mathieeedoubbas.library, mathieeedoubtrans.library

- 85 Overflow during float calculation
This happens usually when converting the result of a float expression into a float type with lower precision, e.g. FFP or Single Precision.
- 86 Illegal symbol type in float expression
Don't use relocatable symbols in float expressions.
- 89 Type of SET can't be changed
Example: symbol set.d 3.14159265
 symbol set.x -0.1 -> Error 89
The value of SET is changeable, but not its type!
- 90 Can't mix LOAD, FILE and TRACKDISK
Example: load \$70000
 file "mycode" -> Error 90
- 91 Near mode not activated
The near mode must be activated first, before using the INITNEAR directive.
- 92 Instruction not implemented in your machine
The instruction exists for another processor, but not for your one. Use MACHINE to change processor type.
- 93 Illegal scale factor
Example: move.w (a1,d2*3) -> Error 93
Valid scale factors are: 1, 2, 4 and 8
- 94 Missing operand
Example: move.l (a0)+ -> Error 94
- 95 Section doesn't exist
This error is caused by specifying an illegal section number in the NEAR directive.
- 96 Illegal RORG offset
The relative offset must not specify an address before the actual PC.
- 97 Immediate operand size error
Example: move.b #\$1234,d0 -> Error 97
- 98 Missing ENDR
Open repeat loop, when leaving the source code, an include file or macro.
- 99 Unexpected ENDR
No matching REPT discovered.
- 100 REPT nesting depth exceeded
The maximum nesting depth is 255.
- 101 Already a directive name
You tried to define a macro, whose name is already used by a built-in directive or instruction.
-

- 102 SAVE nesting depth exceeded
The maximum nesting depth is 8.
- 103 Unexpected RESTORE
No matching SAVE discovered.
- 104 Missing RESTORE
Missing a RESTORE when reaching the last line.

1.108 History / Literature

After six years of working with assemblers like SEKA, AS (Aztec-C) and A68k, I decided in December 1991 that I need a new, powerful assembler. First, I had the idea to buy O.M.A. or Devpac, but I don't like these modern assemblers with an integrated editor. Other reasons for starting the development of PhxAss were the chronic lack of money (I'm student) and the possibility to create an assembler which will satisfy all of my demands.

I completed the first version V1.00 at the 28th of January in 1992. From now on I used PhxAss to assemble itself (first I used A68k). It took me more than a year and 23 versions to reach V3.00 and nearly another two years and 52 versions for V4.00 (of course PhxAss was not my only project in this period).

Here is a list of my hardware and literature that made the development of PhxAss possible:

Hardware: My good old A1000 (Rev.1 with piggyback board from '85) with 68010 CPU, 2 MB Fast-RAM and a 33 MB Harddisk.
(since December '93 also:) A4000, 68040, 18 MB RAM, 3 GB hard disk.

Literature: Motorola MC68000/68008/68010/68HC000 8-/16-/32-Bit Micro-processor User's Manual (Prentice Hall)

Motorola MC68020 32-Bit Microprocessor User's Manual (Prentice Hall)

Motorola MC68040/68EC040/68LC040 Microprocessor User's Manual (Motorola)

Motorola MC68881/882 Floating-Point Coprocessor User's Manual (Prentice Hall)

Motorola MC68851 Paged Memory Management Unit User's Manual (Prentice Hall)

Motorola M68000,MC68020,MC68030,MC68040,MC68851,MC68881/882 Programmer's Reference Manual (Motorola)

Amiga ROM Kernel Reference Manual: Libraries & Devices (Addison-Wesley)

Amiga ROM Kernel Reference Manual: Includes & Autodocs (Addison-Wesley)

Amiga Intern (Data Becker)

Amiga Intern Band 2 (Data Becker)

The Amiga Guru Book (Taunusstein)

1.109 Acknowledgements

Thanks to the following persons, who intensively tested PhxAss and accelerated its development by constructive bug-reports:

Fabien Campagne (F)	
Tim Rühnen	SiliconSurfer@Blackbox.shnet.org
Wojciech Czyz (PL)	
Thomas Hagen Johansen (DK)	tjohansen@thj.adsp.sub.org
Matthias Bock	starfox@cow.mayn.de
Christian Bauer	cebix@ng-box.wwbnet.de
Dave Dustin (NZ)	dave@eclipsnz.manawatu.gen.nz
Richard Körber	shred@chessy.aworld.de
Christian Wasner	Christian.Wasner@hamburg.netsurf.de
Mark Knibbs (USA)	markk@msmail01.liffe.com
David Neale (GB)	david@reeve.demon.co.uk
Andy Church (USA)	achurch@binx.mbhs.edu
Volker Barthelmann	volker@vb.franken.de
Jorma Oksanen (SF)	tenu@sci.fi
Joop van de Wege (NL)	joop.vandewege@medew.ento.wau.nl
Carsten Schlote	schlote@stud.uni-frankfurt.de
Sam Jordan (CH)	jordsamo@htlchur.ch

The swedish catalogs were made by:

Marcus Geelnard (S) e4geeln@etek.chalmers.se

The italian catalogs were made by:

Simone Tellini (I) Simone.Tellini@f502.n332.z2.fidonet.org

The danish catalogs were made by:

Morten Holm (DK) mortenh@viking.roskildees.dk

The french catalogs were made by:

Georges Goncalves (F) kersten_emmrich@ramses.telesys-innov.fr

The dutch catalogs were made by:

Leon Woestenberg (NL) leon@stack.urc.tue.nl

The hungarian catalogs were made by:

Attila Tajti (H) tajtia@info.pmmf.hu

The norwegian catalogs were made by:

Arild Kvalbein (N)

Author of PhxOpts:
Johan Johanssen (S) d95-jjo@nada.kth.se

Another acknowledgement is going to Commodore and their former staff:

Thanks, for the only computer of the present time, which really makes fun to work with :-)

1.110 Known bugs in version V4.36

- o The Forward-Branch optimization (T-flag) doesn't correct the line-addresses in the listing file.
- o DC.B "xyz''abc" is converted to "xyz'abc".

If any bugs or questions occur, please write to :

My Address

1.111 My Address

SMail: Frank Wille
 Auf dem Dreische 45
 32049 Herford
 GERMANY

E-Mail: frank@phoenix.owl.de

World Wide Web: http://fiction.pb.owl.de/~frank/phxass_e.html

 _//
 \X/ A M I G A F O R E V E R !