

AdobeSM Customer Services

Manually Installing Adobe Type Manager™

In certain instances, it is necessary to replace files in the ATM™ setup. This tech note tells how to reinstall ATM without running the install program.

VERSIONS 1.0 THROUGH 2.5

From the ATM program disk, copy the following files to these directories:

ATMCNTRL . EXE to /[Windows directory]

ATM* . dll to /[Windows directory]/SYSTEM

ATMSYS . DRV to /[Windows directory]/SYSTEM

After completing the copy, open the SYSTEM.INI file in a text editor such as DOS Edit, Edlin or Windows Notepad. This step is necessary only if you have never installed ATM before.

Important: Always make a backup copy of any file you plan to modify—prior to modification.

In the [Boot] section of the SYSTEM.INI file, find the line that reads

```
SYSTEM . DRV=SYSTEM . DRV .
```

Change it to read

```
SYSTEM . DRV=ATMSYS . DRV
```

```
ATM . SYS . DRV=SYSTEM . DRV
```

Save the file, and start Windows. To edit in a Windows text editor, restart Windows.

Note: If you are using any other program that connects with Windows in a way similar to that described above, you must load the ATM lines after loading the other program. An example is *MoreFonts*. In this case, you must edit the lines to read this way:

```
SYSTEM . DRV=MFSYS . DRV
```

```
MF . SYSTEM . DRV=ATMSYS . DRV
```

```
ATM . SYTEM . DRV=SYSTEM . DRV
```

Some programs have different requirements for connecting with the Windows system. Consult your documentation for more detail.

If you do not have an ATM icon from a previous installation, you can create an icon.

- 1 Open the Main group in Windows Program Manager.
- 2 From the File Menu, select New, and click Program Item. Then select OK.
- 3 In the Program Items Properties Box, enter the following values:



Description: ATM Control Panel

Command Line: C:\[Windows directory]\ATMCNTRL.EXE

4 Then select OK. Open the ATM Control Panel, and select Add. Change the Target directory to C:\PSFONTS. The Target directory for Font Metrics Files will change to C:\PSFONTS\PFM.

Add the fonts again from a disk or from an already existing C:\PSFONTS\PFM directory. From the directories windows select either the disk drive containing your font disk or the C:\PSFONTS\PFM directory. A list of fonts will appear in the window next to your selection. Highlight the fonts by clicking and dragging on the list and selecting the Add button. Once the ATM Control Panel finishes processing the fonts, it returns to the original screen. To recognize any new fonts, all versions of ATM earlier than 2.5 require restarting Windows after exiting.

MANUALLY INSTALLING ATM 2.6

All files for ATM 2.6 are compressed; they require the EXPAND utility, which automatically installs with both DOS and Windows. You can find the files in your DOS or Windows directory or on Disk 1 of your Windows setup disks. Create a temporary directory on your hard disk, and copy ATM*. * from your ATM disks. Then use the EXPAND utility to expand the files as follows:

```
EXPAND ATMCNTRL.EX_ ATMCNTRL.EXE
EXPAND ATMSYS.DR_ ATMSYS.DRV
EXPAND ATM32.ND_ ATM32.DLL
EXPAND ATM16.ND_ ATM16.DLL
```

Then follow the installation instructions of ATM 1.0 to 2.5. Before restarting Windows, open the ATM.INI file, and add the following lines:

```
[Settings]
TmpDir=C:\psfonts\tmp
[MMFonts]
AdobeSansXMM=C:\psfonts\pfm\sansxmm.mmm,C:\psfonts\sansxmm.pfb
AdobeSerifMM=C:\psfonts\pfm\serifmm.mmm,C:\psfonts\serifmm.pfb
```

Save the ATM.INI file, and then exit Windows. Before reentering Windows, type this command:

```
MKDIR c:\psfonts\tmp
```

Reenter Windows to use ATM.