

## ANSI.SYS Escape Sequences for Screen Control

Escape sequence

ESC[H

ESC[xx;yyH

the default is 1.

ESC[xx;yyf

ESC[xxA

ESC[xxB

ESC[xxC

ESC[xxD

ESC[s

ESC[u

ESC[2J

ESC[K

ESC[xx;...xxm

## Sheet1

### Description

Move the cursor to row 1, column 1.

Move the cursor to row xx, column yy. If either xx or yy is omitted,

Move the cursor to row xx, column yy (same as ESC[xx;yyH).

Move the cursor up xx rows. If xx is omitted, the default is 1.

Move the cursor down xx rows. If xx is omitted, the default is 1.

Move the cursor forward (right) xx columns. If xx is omitted, the default is 1.

Move the cursor backward (left) xx columns. If xx is omitted, the default is 1.

Save the current cursor position.

Restore the last cursor position saved with ESC[s.

Clear the screen and move the cursor to row 1, column 1.

Clear all characters from the cursor to the end of the line.

Set text colors and attributes. Valid values for xx are

0

1

4

5

7

8

30

31

32

33

34

35

36

37

40

41

42

43

44

45

46

47

Turn all video attributes (bold, underscore, blink, reverse video, and concealed) off.

Make foreground colors bold.

Turn underscore on.

Turn blink on.

Reverse video.

Turn concealed attribute on.

Set foreground color to black.

Set foreground color to red.

Set foreground color to green.

Set foreground color to yellow.

Set foreground color to blue.

Set foreground color to magenta.

Set foreground color to cyan.

Set foreground color to white.

Set background color to black.

Set background color to red.

Set background color to green.

Set background color to yellow.

Set background color to blue.

Set background color to magenta.

Set background color to cyan.

Set background color to white.