

3.3 Release Notes: Workspace Manager

This file contains release notes for the 3.3 release of Workspace Manager.

Notes Specific to Release 3.3

New features and changes for 3.3

- You can set the Workspace Manager to automatically log out users on computers that have been idle for a period of time. To do this, add the **inactivity_timeout** property to the */* directory in the appropriate domain. The property should have an integer value which is the number of idle minutes before the user is logged out.
- In the disk initialization panel, Workspace allows the user to manually select the density of floppy disks on machines without autosensing capabilities (most Intel-based machines).
- Workspace now notifies users when their machine is running out of local disk space. There are two levels of warnings: the first occurs at 10 MB, and the second occurs at 2 MB. Although there is no UI to control this feature, there are a number of dwrites you can use to control the parameters:

- SwapCheckEnabled ([YES] / NO) - turns the feature on and off
- SwapCheckPeriod (number of seconds: [60]) - how often to check
- FirstSwapWarning (first threshold in kilobytes [10240])
- LastSwapWarning (last threshold in kilobytes [2048])

Note that this feature is designed to give you a good idea of when you're going to run out of space for your swap file to grow. It currently doesn't parse `/etc/swaptab` and check available space on all drives.

- If you have a hard disk drive attached to your computer that contains data in a format that NEXTSTEP doesn't recognize (for example, an HP/UX or NT file system), you can edit the **`/etc/fstab`** file in your NEXTSTEP file system to prevent the Workspace Manager from asking if want to initialize that disk each time you log in.

Normally, NEXTSTEP assumes that any disk containing data it doesn't recognize is unformatted. Each time you log into the NEXTSTEP workspace, a panel asks if you want to initialize the disk. If the disk is always attached to your computer and has real data on it, you may want to configure your computer so that this panel doesn't appear. To do this, edit the **`/etc/fstab`** file by adding an entry for the non-NEXTSTEP hard disk drive listing the file system type **ignore**. As an example, an **`fstab`** file with `sd0a` as your NEXTSTEP **root** disk and `sd1a` as an HP/UX disk you want NEXTSTEP to ignore might look like this:

```
/dev/sd0a / 4.3 rw,noquota,noauto 0 1
/dev/sd1a /HPUX ignore ro,noquota 0 2
```

Note that for an `ignore` file system type, the only parts of the entry that have any significance are the device (**`/dev/sd1a`**) and the file system type (**ignore**). For more information, see the UNIX manual page for **`fstab`**.

Major bugs fixed for 3.3

- Dock preferences don't screw up when dealing with screens larger than or smaller than 1120 x 832.

- Sometimes, floppies would appear as removable hard drives, and CD-ROMs would appear as floppies. Workspace now displays the appropriate icons.
- Workspace now behaves properly with mounted NFS filesystems greater than 2 gigabytes.