

MUIbase

COLLABORATORS

	<i>TITLE :</i> MUIbase		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		July 8, 2022	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	MUIbase	1
1.1	MUIbase	1
1.2	MUIbase/Copying	2
1.3	MUIbase/Registration	3
1.4	MUIbase/Distribution	5
1.5	MUIbase/Disclaimer	6
1.6	MUIbase/Third party material	6
1.7	MUIbase/Welcome to MUIbase	7
1.8	MUIbase/Getting started	9
1.9	MUIbase/Tutorial	11
1.10	MUIbase/Basic concepts	21
1.11	MUIbase/Projects	21
1.12	MUIbase/Tables	22
1.13	MUIbase/Records (concept)	22
1.14	MUIbase/Attributes	23
1.15	MUIbase/Attribute types	23
1.16	MUIbase/String type	24
1.17	MUIbase/Integer type	25
1.18	MUIbase/Real type	25
1.19	MUIbase/Bool type	25
1.20	MUIbase/Choice type	26
1.21	MUIbase/Date type	26
1.22	MUIbase/Time type	26
1.23	MUIbase/Memo type	27
1.24	MUIbase/Reference	27
1.25	MUIbase/Virtual	27
1.26	MUIbase/Button	28
1.27	MUIbase/Table of attribute types	28
1.28	MUIbase/Memory consumption	29
1.29	MUIbase/Relationships	29

1.30 MUIbase/One to one relationships	30
1.31 MUIbase/One to many relationships	30
1.32 MUIbase/Many to many relationships	31
1.33 MUIbase/User interface	32
1.34 MUIbase/Windows	33
1.35 MUIbase/Masks	34
1.36 MUIbase/Panels	34
1.37 MUIbase/Attribute objects	35
1.38 MUIbase/Text objects	35
1.39 MUIbase/Images	35
1.40 MUIbase/Space objects	35
1.41 MUIbase/Groups	36
1.42 MUIbase/Balance objects	36
1.43 MUIbase/Register groups	36
1.44 MUIbase/Managing projects	36
1.45 MUIbase/File format	37
1.46 MUIbase/Info	38
1.47 MUIbase/Clear project	38
1.48 MUIbase/Open project	38
1.49 MUIbase/Save project	39
1.50 MUIbase/Delete project	40
1.51 MUIbase/Close project	40
1.52 MUIbase/Swap records	40
1.53 MUIbase/Preferences	41
1.54 MUIbase/Record memory	42
1.55 MUIbase/Record delete requester	43
1.56 MUIbase/External editor for programming	43
1.57 MUIbase/Icon creation	43
1.58 MUIbase/Formats	44
1.59 MUIbase/Icon tool name	44
1.60 MUIbase/External editor	44
1.61 MUIbase/External viewer	45
1.62 MUIbase/Popups in cycle chain	45
1.63 MUIbase/Confirm save & reorg	46
1.64 MUIbase/Confirm quit	46
1.65 MUIbase/Program include directory	46
1.66 MUIbase/Program debug information	47
1.67 MUIbase/Program output file	47
1.68 MUIbase/Project dependent settings	47

1.69 MUIbase/MUI	48
1.70 MUIbase/Load and save preferences	48
1.71 MUIbase/Empty display image	49
1.72 MUIbase/Record-editing	50
1.73 MUIbase/Active object	50
1.74 MUIbase/Adding records	51
1.75 MUIbase/Changing records	51
1.76 MUIbase/Deleting records	53
1.77 MUIbase/Browsing records	54
1.78 MUIbase/Filter	54
1.79 MUIbase/Record filter	55
1.80 MUIbase/Filter expression	55
1.81 MUIbase/Changing filters	55
1.82 MUIbase/Filter examples	56
1.83 MUIbase/Reference filter	57
1.84 MUIbase/Order	58
1.85 MUIbase/Empty order	58
1.86 MUIbase/Order by attributes	58
1.87 MUIbase/Changing orders	59
1.88 MUIbase/Search for	60
1.89 MUIbase/Search requester	60
1.90 MUIbase/Forward-backward search	61
1.91 MUIbase/Search pattern examples	61
1.92 MUIbase/Import and Export	62
1.93 MUIbase/Import file format	62
1.94 MUIbase/Sample import file	63
1.95 MUIbase/Importing records	63
1.96 MUIbase/Exporting records	64
1.97 MUIbase/Data retrieval	65
1.98 MUIbase/Select-from-where queries	66
1.99 MUIbase/Query editor	66
1.100 MUIbase/Printing queries	68
1.101 MUIbase/Query examples	69
1.102 MUIbase/Structure editor	70
1.103 MUIbase/Table management	71
1.104 MUIbase/Creating tables	72
1.105 MUIbase/Changing tables	73
1.106 MUIbase/Deleting tables	73
1.107 MUIbase/Sorting tables	73

1.108MUIbase/Attribute management	74
1.109MUIbase/Creating attributes	74
1.110MUIbase/Type specific settings	75
1.111MUIbase/Label editor	76
1.112MUIbase/Changing attributes	77
1.113MUIbase/Deleting attributes	78
1.114MUIbase/Sorting attributes	78
1.115MUIbase/Display management	79
1.116MUIbase/Display field	79
1.117MUIbase/Panel editor	81
1.118MUIbase/Attribute object editor	82
1.119MUIbase/Text editor	86
1.120MUIbase/Image editor	86
1.121MUIbase/Space editor	87
1.122MUIbase/Group editor	87
1.123MUIbase/Register group editor	88
1.124MUIbase/Window editor	88
1.125MUIbase/Print structure	89
1.126MUIbase/Programming MUIbase	89
1.127MUIbase/Program editor	91
1.128MUIbase/Preprocessing	92
1.129MUIbase/#define	93
1.130MUIbase/#undef	93
1.131MUIbase/#include	94
1.132MUIbase/#if	94
1.133MUIbase/#ifdef	95
1.134MUIbase/#ifndef	95
1.135MUIbase/#elif	96
1.136MUIbase/#else	97
1.137MUIbase/#endif	97
1.138MUIbase/Programming language	98
1.139MUIbase/Why lisp?	98
1.140MUIbase/Lisp syntax	99
1.141MUIbase/Kinds of programs	99
1.142MUIbase/Name conventions	100
1.143MUIbase/Accessing record contents	100
1.144MUIbase/Data types for programming	101
1.145MUIbase/Constants	102
1.146MUIbase/Command syntax	103

1.147MUIbase/Defining commands	103
1.148MUIbase/DEFUN	104
1.149MUIbase/DEFUN*	105
1.150MUIbase/DEFVAR	105
1.151MUIbase/Program control functions	106
1.152MUIbase/PROGN	107
1.153MUIbase/PROG1	108
1.154MUIbase/LET	108
1.155MUIbase/SETQ	109
1.156MUIbase/SETQ*	110
1.157MUIbase/FUNCALL	110
1.158MUIbase/IF	111
1.159MUIbase/CASE	111
1.160MUIbase/COND	112
1.161MUIbase/DOTIMES	113
1.162MUIbase/DOLIST	114
1.163MUIbase/DO	115
1.164MUIbase/FOR ALL	116
1.165MUIbase/NEXT	116
1.166MUIbase/EXIT	117
1.167MUIbase/RETURN	118
1.168MUIbase/HALT	118
1.169MUIbase/ERROR	119
1.170MUIbase/Type predicates	119
1.171MUIbase/Type conversion functions	120
1.172MUIbase/STR	121
1.173MUIbase/MEMO	121
1.174MUIbase/INT	122
1.175MUIbase/REAL	123
1.176MUIbase/DATE	123
1.177MUIbase/TIME	124
1.178MUIbase/Boolean functions	124
1.179MUIbase/AND	125
1.180MUIbase/OR	125
1.181MUIbase/NOT	126
1.182MUIbase/Comparison functions	126
1.183MUIbase/Mathematical functions	127
1.184MUIbase/add	128
1.185MUIbase/sub	129

1.186MUIbase/1+	130
1.187MUIbase/1-	130
1.188MUIbase/mul	130
1.189MUIbase/fdiv	131
1.190MUIbase/DIV	131
1.191MUIbase/MOD	132
1.192MUIbase/MAX	132
1.193MUIbase/MIN	132
1.194MUIbase/ABS	133
1.195MUIbase/TRUNC	133
1.196MUIbase/ROUND	133
1.197MUIbase/RANDOM	134
1.198MUIbase/String functions	134
1.199MUIbase/LEN	136
1.200MUIbase/LEFTSTR	136
1.201MUIbase/RIGHTSTR	136
1.202MUIbase/MIDSTR	137
1.203MUIbase/SETMIDSTR	138
1.204MUIbase/INSMIDSTR	138
1.205MUIbase/INDEXSTR	139
1.206MUIbase/INDEXSTR*	139
1.207MUIbase/INDEXBRK	139
1.208MUIbase/INDEXBRK*	140
1.209MUIbase/REPLACESTR	140
1.210MUIbase/REMCHARS	141
1.211MUIbase/TRIMSTR	141
1.212MUIbase/WORD	142
1.213MUIbase/WORDS	142
1.214MUIbase/CONCAT	143
1.215MUIbase/CONCAT2	143
1.216MUIbase/UPPER	144
1.217MUIbase/LOWER	144
1.218MUIbase/ASC	145
1.219MUIbase/CHR	145
1.220MUIbase/LIKE	145
1.221MUIbase/SPRINTF	146
1.222MUIbase/Memo functions	149
1.223MUIbase/LINE	149
1.224MUIbase/LINES	150

1.225MUIbase/MEMOTOLIST	150
1.226MUIbase/LISTTOMEMO	150
1.227MUIbase/FILLMEMO	151
1.228MUIbase/FORMATMEMO	151
1.229MUIbase/INDENTMEMO	152
1.230MUIbase/List functions	152
1.231MUIbase/CONS	153
1.232MUIbase/LIST	154
1.233MUIbase/LENGTH	154
1.234MUIbase/FIRST	155
1.235MUIbase/REST	155
1.236MUIbase/LAST	155
1.237MUIbase/NTH	156
1.238MUIbase/APPEND	156
1.239MUIbase/REVERSE	157
1.240MUIbase/MAPFIRST	157
1.241MUIbase/SORTLIST	157
1.242MUIbase/SORTLISTGT	158
1.243MUIbase/Input requesting functions	159
1.244MUIbase/ASKFILE	159
1.245MUIbase/ASKDIR	160
1.246MUIbase/ASKSTR	160
1.247MUIbase/ASKINT	161
1.248MUIbase/ASKCHOICE	161
1.249MUIbase/ASKCHOICESTR	162
1.250MUIbase/ASKOPTIONS	163
1.251MUIbase/ASKBUTTON	164
1.252MUIbase/ASKMULTI	164
1.253MUIbase/I-O functions	166
1.254MUIbase/FOPEN	167
1.255MUIbase/FCLOSE	167
1.256MUIbase/stdout	168
1.257MUIbase/PRINT	168
1.258MUIbase/PRINTF	169
1.259MUIbase/FPRINTF	169
1.260MUIbase/FERROR	170
1.261MUIbase/FGETCHAR	170
1.262MUIbase/FGETCHARS	171
1.263MUIbase/FGETSTR	171

1.264MUIbase/FGETMEMO	172
1.265MUIbase/FPUTCHAR	172
1.266MUIbase/FPUTSTR	173
1.267MUIbase/FPUTMEMO	173
1.268MUIbase/FFLUSH	173
1.269MUIbase/Record functions	174
1.270MUIbase/NEW	175
1.271MUIbase/NEW*	175
1.272MUIbase/DELETE	176
1.273MUIbase/DELETE*	177
1.274MUIbase/DELETEALL	177
1.275MUIbase/GETMATCHFILTER	178
1.276MUIbase/SETMATCHFILTER	178
1.277MUIbase/RECNUM	179
1.278MUIbase/COPYREC	179
1.279MUIbase/Attribute functions	180
1.280MUIbase/ATTRNAME	180
1.281MUIbase/MAXLEN	180
1.282MUIbase/GETLABELS	181
1.283MUIbase/SETLABELS	181
1.284MUIbase/Table functions	182
1.285MUIbase/TABLENAME	183
1.286MUIbase/GETORDERSTR	183
1.287MUIbase/SETORDERSTR	184
1.288MUIbase/GETFILTERACTIVE	184
1.289MUIbase/SETFILTERACTIVE	185
1.290MUIbase/GETFILTERSTR	185
1.291MUIbase/SETFILTERSTR	186
1.292MUIbase/RECORDS	187
1.293MUIbase/RECORD	187
1.294MUIbase/SELECT	188
1.295MUIbase/Gui functions	189
1.296MUIbase/SETCURSOR	189
1.297MUIbase/GETDISABLED	190
1.298MUIbase/SETDISABLED	190
1.299MUIbase/GETWINDOWDISABLED	190
1.300MUIbase/SETWINDOWDISABLED	191
1.301MUIbase/GETWINDOWOPEN	191
1.302MUIbase/SETWINDOWOPEN	192

1.303MUIbase/Project functions	192
1.304MUIbase/PROJECTNAME	193
1.305MUIbase/CHANGES	193
1.306MUIbase/System functions	193
1.307MUIbase/EDIT	194
1.308MUIbase/EDIT*	195
1.309MUIbase/VIEW	195
1.310MUIbase/VIEW*	196
1.311MUIbase/SYSTEM	196
1.312MUIbase/STAT	197
1.313MUIbase/TACKON	197
1.314MUIbase/FILENAME	198
1.315MUIbase/DIRNAME	198
1.316MUIbase/TODAY	199
1.317MUIbase/NOW	199
1.318MUIbase/MESSAGE	199
1.319MUIbase/GC	200
1.320MUIbase/Pre-defined variables	200
1.321MUIbase/Pre-defined constants	200
1.322MUIbase/Functional parameters	201
1.323MUIbase/Type specifiers	202
1.324MUIbase/Semantics of expressions	203
1.325MUIbase/Function triggering	204
1.326MUIbase/onOpen	205
1.327MUIbase/onClose	205
1.328MUIbase/onChange	206
1.329MUIbase/New trigger	206
1.330MUIbase/Delete trigger	207
1.331MUIbase/Attribute trigger	208
1.332MUIbase/Programming virtual attributes	209
1.333MUIbase/ABConvert	210
1.334MUIbase/Menus	210
1.335MUIbase/Acknowledgments	214
1.336MUIbase/Author	214
1.337MUIbase/Function index	215
1.338MUIbase/Concept index	224

Chapter 1

MUIbase

1.1 MUIbase

MUIbase Version 1.3

MUIbase is a relational programmable database that uses MUI as user interface.

Copying

Your rights.

Welcome to MUIbase

MUIbase in brief.

Getting started

How to install & start MUIbase.

Tutorial

First steps for learning MUIbase.

Basic concepts

Some elementary definitions.

Managing projects

How to organize your projects.

Preferences

Customizing MUIbase.

Record-editing

Record manipulations and browsing.

Filter

Filtering records.

Order

Ordering records.

Search for
How to search for a record.

Import and Export
Data from/to other databases.

Data retrieval
How to query data from a project.

Structure editor
Setting up your own database.

Programming MUIbase
How to write MUIbase programs.

Appendix

ABConvert
Utility to convert projects from AmigaBase.

Menus
Description of all menu items.

Acknowledgments
People the author wants to thank.

Author
Who you should contact.

Function index
Programming functions and variables.

Concept index
Concepts.

(C) 1998-1999 Steffen Gutmann

1.2 MUIbase/Copying

MUIbase Copying Conditions

MUIbase is (C) 1998-1999 Steffen Gutmann. All rights reserved.

MUIbase is not public domain or free software. If you use MUIbase then you have to register your copy after a short while. You are allowed to install and run MUIbase without registration for a period of 4 weeks. After that time you have to register your copy of MUIbase or delete it from your system. Reinstalling MUIbase does not extend the license.

After registration you receive your personal MUIbase key-file which

enables all crippled features of MUIbase.

Reverse engineering of the MUIbase software protection is strictly forbidden.

Registration
How to register your copy.

Distribution
Giving MUIbase to others.

Disclaimer
This Software is "as is".

Third party material
External stuff MUIbase uses.

1.3 MUIbase/Registration

Registration
=====

The unregistered MUIbase version is crippled in several ways:

- * Only up to 5 tables per project.
- * Only up to 10 attributes per table.
- * Only up to 30 function definitions for programming per project.
- * No preprocessing for programming (#-directives).
- * No remembering of window dimensions in projects.
- * No images for structure editor.
- * No register groups for structure editor.

In the author's opinion the absence of these features doesn't make MUIbase unusable. You should be able to see the power of MUIbase within the 4 weeks testing period without these features.

After registration you will receive a key-file which enables the disabled features. The key-file is expected to work with all future versions of MUIbase.

Registration fee

The registration fee for MUIbase is DEM 60. Registration fee is accepted only in these currencies:

- * 40 USD (US dollar)
- * 30 EUR (Euro)
- * 60 DEM (Deutsche Mark)

The registration fee does not include a printed hard-copy of the manual. Please print the documentation on your own printer or use the online help (AmigaGuide or html) while working with MUIbase.

Payment methods

Cash

This is one of the preferred payment method and maybe the cheapest for you and me. Enclose the cash in two pieces of nonwhite paper to disguise it. Do not send coins.

Eurocheque

Write the cheque for 60 DEM or 30 EUR. Other currencies than DEM and EUR are not accepted here! You must write your card number on the back of the cheque, otherwise I can't cash it in.

Money transfer

Transfer 60 DEM or 30 EUR to my bank account Deutsche Bank 24, Germany, BLZ 380 707 24, account number 314 726 100.

If you have internet access then you can also transfer the money to my account and send me the registration by email or use the registration interface on the MUIbase home page <http://www.amigaworld.com/support/muibase>. This is probably the best way to register your MUIbase copy. I am checking my bank account almost every day, thus I will see your money pretty fast.

Postal Money Order

You can pay using postal money order, but you must mail or email me the registration form because it's possible that only your name is included with the PMO when I receive it, so I also need your address. Ask your local post office for more information.

Credit card via ShareIt.

This might be a good option for you if you want to order MUIbase by internet. Please see the instructions on the MUIbase web page <http://www.amigaworld.com/support/muibase> on how to use this registration method.

Ordering

The easiest way for ordering MUIbase is to fill in a registration form or to use the Register program, which asks you all the necessary information and creates an ASCII registration form. Blank registration forms are available in these formats:

- * Final Writer

* WordWorth

* ASCII

You'll find these files in the Register directory.

If you don't have a printer then create an ASCII registration form with the Register program and copy the necessary information to a piece of paper. The information I need is:

* your name

* address

* email address (if available)

* payment method and currency

* method of delivery

When you have filled in the registration form, please send it to me with your payment. My address is:

Steffen Gutmann
Wiesentalstr. 30
73312 Geislingen/Steige
GERMANY

Or send it by email to:

gutmann@ieee.org

Method of delivery

If you have an Internet email address, I will email you the key-file. Otherwise I will send you a 3.5" disk by post with the key-file and the latest version of MUIbase.

The latest version of MUIbase can always be down-loaded from Aminet or from

<http://www.amigaworld.com/support/muibase>.

1.4 MUIbase/Distribution

Distribution

=====

You are granted the right to share MUIbase with others, as long as you distribute the MUIbase archive exactly as you received it, with all associated files included. Registered users may not distribute their private file "MUIbase.key".

Under no circumstances may you charge more than a normal copying fee and shipping costs for distributing the MUIbase archive without express written consent from the copyright holder.

Permission is hereby granted, without written agreement and without license fees, to copy and distribute the MUIbase archive, provided that the above conditions are met, to

- * All who will distribute this software for free!
- * All free accessible INTERNET servers and PHONE boxes!
- * All Aminet sites
- * All others who do NOT take more than \$5.- for one disk that includes this software!
- * All others who do NOT take more than \$20.- for one CD that includes this software!

Distributing beta-versions of MUIbase is strictly prohibited.

1.5 MUIbase/Disclaimer

Disclaimer
=====

THIS SOFTWARE IS PROVIDED BY THE AUTHOR AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

1.6 MUIbase/Third party material

MUI
===

This application uses

MUI - MagicUserInterface

(c) Copyright 1993-1999 by Stefan Stuntz

MUI is a system to generate and maintain graphical user interfaces. With the aid of a preferences program, the user of an application has the ability to customize the outfit according to his personal taste.

MUI is distributed as shareware. To obtain a complete package containing lots of examples and more information about registration please look for a file called "muiXXusr.lha" (XX means the latest version number) on your local bulletin boards or on public domain disks.

If you want to register directly, feel free to send

DM 30.- or US\$ 20.-

to

Stefan Stuntz
Eduard-Spranger-Straße 7
80935 München
GERMANY

Support and online registration is available at

<http://www.sasg.com/>

BetterString & TextEditor

=====

MUIbase uses BetterString.mcc & TextEditor.mcc, (c) 1997-1999 by Allan Odgaard. See <http://www.diku.dk/students/duff/> for more info or latest version.

Additional custom classes

=====

MUIbase uses NList.mcc (C) 1996-1999 Gilles Masson.

Icons

=====

Some icons used in the MUIbase distribution are copied from the DefaultIcons set which is distributed e.g. on the Meeting Pearls CD 3, directory Contrib/DefaultIcons. These icons are Copyright by Michael-Wolfgang Hohmann and Angela Schmidt (for a more detailed Copyright description see MP3).

1.7 MUIbase/Welcome to MUIbase

Welcome to MUIbase

MUIbase is a fast and very flexible database for the Amiga. It is for users who want to manage data in a comfortable and easy way. MUIbase is able to manage any kind of data, e.g. addresses, CD series, movies, or your income and expense. The power of MUIbase lies in its clear and powerful graphical user interface and its programming capabilities. The latter makes it possible to automatically calculate and maintain nearly everything, starting from automatically summing up values, e.g. for calculating the total amount of income or the total amount of recorded time of a CD, up to automatically creating and printing letters for any purpose.

MUIbase is the successor of AmigaBase, a hierarchical programmable database which is still available but considered obsolete with the appearance of MUIbase. All registered users of AmigaBase can get a free upgrade to MUIbase by sending their AmigaBase registration number and return address to me (Email preferred).

MUIbase offers the following features:

- * Handling of multiple projects at the same time.
 - * Attributes can be of type string, memo (multi line text), integer, real, date, time, bool, choice (one item out of many items), reference (easy way to reference a record of another table), button (for starting MUIbase programs), and virtual (compute value on the fly).
 - * The string type can also manage lists of strings, files, and fonts. An OS 3.x datatype gadget allows displaying external images.
 - * Unlimited number of records.
 - * Dynamic loading of records. Records which are not needed may be flushed from memory (e.g. when memory is low).
 - * Programmability. With the easy and powerful MUIbase programming language complex tasks can be implemented. The language also includes a SELECT FROM WHERE query for easy and fast data retrieval.
 - * Ordering of records by any combinations of attributes.
 - * Flexible and powerful search and filter facility.
 - * Query editor which allows entering and managing of SELECT FROM WHERE queries. The queries can be saved and the results can be printed.
 - * Import and export facility.
 - * Uses MUI as user interface. The interface is highly customizable. External images can be included in the user interface.
 - * Portability. MUIbase development has been done under the idea of easy portability. The system/gui part has been separated from the
-

ANSI/C part such that porting MUIbase will result in only porting the system/gui part. The author is currently investigating a Java implementation of the user gui. This would make the database available for nearly all computer systems, including Linux, Windows, and MacOS.

The unregistered version of MUIbase is crippled in several ways. See [Registration](#), for a list of limitations in the unregistered version.

1.8 MUIbase/Getting started

Getting started

This chapter describes how to install MUIbase on your computer, what the hard- and software requirements are, and how to start MUIbase.

Installing MUIbase
=====

For installing MUIbase on your hard disk you need the Commodore Installer. This tool can be found in the Aminet under directory /pub/aminet/util/misc. The Installer may also be included in the MUIbase archive. Be sure to use Installer version 43.3 or up, otherwise the installation script may fail.

Before beginning the installation, make sure that your computer and your system software is compatible to MUIbase. See required hardware and required software sections.

Required hardware

You need an Amiga with an 68020 processor or higher, 2 MB of ram, and a hard disk with at least 2 MB of free space on it. For larger applications more hard disk space and ram is necessary.

Required software

MUIbase needs OS version 3.0 or up. It may also run under OS 2.x but there is no guarantee that all features will work properly there.

Additionally, MUIbase requires that MUI version 3.8 or higher is installed on your system.

Starting the installation

If you have received MUIbase as an archive file, unpack the archive

to a temporary directory. Do not unpack it to the target directory!

Double click the MUIbase installer script Install-MUIbase and follow its instructions. The script asks for a directory where the software should be copied to. Do not enter the directory where you have unpacked the MUIbase archive to.

The script is also capable of updating an existing MUIbase installation. In this case enter the directory where you have previously installed MUIbase. When updating an existing MUIbase installation all necessary files are replaced by new ones. This includes the sample projects in the Demos directory. Therefore do not place projects into this directory nor use one of the sample projects for managing your own data!

After a successful installation you can remove the MUIbase archive from your system and store it elsewhere, e.g. on a floppy disk.

Key-file

If you are a registered user of MUIbase and have received a key-file, you should move the key-file to one of the following directories:

- * directory-containing-the-MUIbase-executable
- * MUIbase:
- * KEYS:
- * KEYFILES:
- * S:

MUIbase will search in these directories for the file MUIbase.key and if found (and the key-file is valid) enable all crippled features.

Remember that the key-file contains your personal data and you are not allowed to give it away. Also do not modify the file in any way or MUIbase is likely to crash.

Please keep a safety copy of your key-file on one or two diskettes.

Starting MUIbase

=====

MUIbase can be started from Workbench or from CLI. From Workbench double click the MUIbase icon. You can also double click a MUIbase project icon. This starts MUIbase and the selected project is automatically loaded by MUIbase. It's also possible to mark several MUIbase projects by shift clicking them and double click the last project.

From CLI type MUIbase [FILE1 ...], where FILE1 ... are optional projects to be loaded by MUIbase.

Quitting MUIbase

=====

To quit MUIbase select menu item Project - Quit or close all opened projects.

1.9 MUIbase/Tutorial

Tutorial

The making of a family-tree database.

This chapter is a small tutorial describing how the basic things of MUIbase work. Within the tutorial a small project is developed that allows managing of your family tree. The project that results after applying all steps in this tutorial can be found in the Demos directory of your MUIbase installation.

How MUIbase works

=====

MUIbase could be said to operate in two different modes, record-editing and structure-editing mode.

The record-editing mode is where you change, add, or delete your records.

The structure-editor lets you edit how your database should look like and what tables and attributes it contains.

Besides this there is the program-editor where you write program functions that are executed either automatically when entering some data in an attribute or when pressing a program button.

Starting with a project, the structure-editor

=====

To create a database you first of all need to define it's contents. In MUIbase this is done in the structure-editor. To enter the structure-editor you either press RAMIGA-s (Right Amiga button and the letter s) or by choosing Structure Editor from the Project menu. There you will find three different sections:

Tables

In Tables you change, add, or delete the tables you need.

Attributes

In Attributes you change, add, or delete attributes. These attributes each belong in one of the above mentioned tables.

Display

In Display you design the looks of your database, how it should be displayed.

Adding a table

=====

First we need a table, press the New button just below the list view in the Table section. You will then get a requester which asks you to enter some data:

Name

This is where you enter the name of a table. The name must start with an uppercase letter and can consist of up to 20 characters. The name can be changed later. In this tutorial we set the name to Persontable since it's going to hold all the persons names in this database.

Number of records

A table can either consist of only one or of an unlimited number of records. In this case it should be set to unlimited since we are going to add more than one person.

Trigger functions

Any call from the user to add or delete records can be controlled by a program function, this is where you set which function to call. Since we don't have written any program functions yet, a look in any of the list-views will not show anything.

When this is done, just press the OK button and we have our first table, Persontable.

Adding an attribute

=====

Then we need a string attribute for that table, press New in the attributes-section. Attributes also need some settings:

Name

The same as for a table, first letter an uppercase one and altogether a maximum of 20 characters. This attribute we will set to Name since it's to contain the names of the persons we are about to add.

Type

Here we choose what type this attribute should be. There are a couple of different ones but for this attribute we use a string attribute.

Max length

Here you can define the maximum number of characters a user can enter for the string. We set this to 30.

Initial value

It's possible to have some attributes to use an initial value for every new record you add, here is where you enter what it should contain. Leave this line blank.

Trigger

An attribute could also trigger a program function to be executed. For example, if you enter a name then you can have a program to

check if this name already exists.

Displaying the project

=====

After pressing OK you now should notice some changes in the display section. Change the choice button on the top of the display section to Root window. There you see what the root window holds, currently Persontable. If you change the choice button back to Table mask you can see how this table, Persontable, is presented. Currently it's displayed as one panel with one attribute.

Now double-click on Panel(Persontable) at the top of the list in the display section and a window should appear, allowing you to set how this panel should be displayed:

Title

The title of a table can be different than what it's real name is. Our table is called Persontable but here we could set it to be THIS IS THE TABLE PERSONTABLE! if we prefer that better.

Background

The background can be changed to whatever suits your taste.

Gadgets

Here we can define what gadgets we want the panel to have.

Press OK and then double-click on Name in the list-view in the display section. That should bring up the window that contains the settings for how to display the string attribute Name.

Title

The same as for the panel. The string you enter here is what is really displayed when in record-editing mode.

Shortcut

Here you can set a letter that should be used together with RAMIGA to jump to this attribute, when in record-editing mode.

Home

Makes the cursor to jump to this attribute whenever a new record is added. In our case we will always or most of the time enter the name first in a new record, so set it.

Read only

Set this if the attribute should be read only. Leave it unset.

Weight

Decides how much of this attribute should be visible when competing for the space with other attributes. For example, if three 50-character strings resides in a window that only has room for 100 characters, then this number decides how much space the string gets relatively to the other ones. Leave it at 100.

Background

The same as for the panel.

Bubble help

Here you enter any text you think would be helpful to the user. The bubble help appears after holding the mouse still over an attribute for some seconds. Set this to If you need help, call the author at 112.

Leave the structure-editor (RAMIGA-s or Structure Editor in the Project menu) and go to record-editing mode, to see how the database looks in real life. You'll see the headline which is the string you may have entered in the display section for the panel. The record counter should say #0/0 since we haven't added any records yet. Thereafter is the filter button and the two step-buttons. Below all this you should have Name and the text you may have entered in the display section for this attribute. If you haven't changed any text at all when in the display section then the panel should be named Persontable, and the string attribute Name. Move the mouse above the string attribute Name and leave it there for a couple of seconds. If you entered something in the bubble help above then this text should appear in a bubble.

Adding two reference attributes

=====

Now we will add two reference attributes. Reference attributes are a bit different than other attributes. As their name might imply they refer to records. This will get more understandable as you try it out for yourself in just awhile.

Enter the structure-editor again and add two more attributes to Persontable. Press New in the attributes section, name it Father, and change it's type to Reference. A reference attribute has only one setting:

Set reference to

Tells which table the attribute it's about to refer to. Should already be pointing to Persontable, leave it that way and press Ok.

Add another attribute by pressing New in the attribute section and call it Mother. The attributes type should also be set to reference and point to table Persontable.

As you may have noticed there are now three attributes in the display section. Click on Father and then on the buttons up and down located just to the left. This will change where Father is positioned when looking at it while in record-editing mode. Put Father at the top, Name in the middle, and Mother at the bottom.

Then we just have to set what contents the reference attributes Father and Mother should display from the referenced records. Double-click on Father in the display section and then click on Extras. There we choose to display the string attribute Name, then we press Ok and repeat the procedure for Mother.

Adding records

=====

Now we should add some records. Leave the structure-editor and enter

record-editing mode. To add a new record you simply press RAMIGA-n or choose New record from the Table menu. The cursor should now automatically jump to the attribute we have set to Home earlier in the display section in the structure-editor. Add two records, one with your fathers name in Name and another one with your mothers name in Name. Thereafter you add another record with your own name in Name.

Now it's time to understand those reference attributes. By pressing on the list-view button on Father we get a list of all records this reference attribute could refer to. Choose your fathers name and do accordingly down below on the mothers list-view.

Now you should have three records, you, your father and your mother. In your record, your fathers name should be visible in Father at the top and your mothers name should be in Mother at the bottom. You can browse through the records by pressing ALT together with Cursor up/down.

But hey! My parents also has/had parents you say! So let's add another four records, the third generation. Just add the records one by one and write their names in Name. If you don't remember their names then just enter fathers father, mothers father or something like that instead. Then you browse through all the records and set Father and Mother to what they should contain. When this is done you should have at least seven records, your record, your parents records and your grandparents records.

Filter
=====

Since we now have some records to work with, we could try out the filter function. The filter can sort out records you don't want to display, they will still remain in the database itself but they will not be displayed.

To edit the filter you press LAMIGA-f or choose Change filter from the Table menu. When you have done so a strange looking window with loads of operators will appear. This is where you set what conditions a record must fulfill to get displayed.

In this small example we will use the LIKE command, which lets you do a joker comparison of an attribute. Press once on the LIKE button to the right and then double-click on Name in the list to the left and (LIKE Name) should appear in the string just above the Ok and Cancel buttons. Thereafter you type "*a*" so the whole string shows (LIKE Name "*a*"). This means that MUIbase should display all records that contain the letter a anywhere in Name.

Press Ok and you may notice that records with no a in Name, no longer are visible. Since the letter a is quite common in most languages and names, all records might still be visible but you can try other letters to make the filter function more clear. When you're done, go to record-editing mode.

As mentioned earlier there is a button on the panel that says F. This F indicates if the filter is on or off. Finally when you're done testing, turn the filter off so that all records are visible.

Queries

=====

Now that we have played with the filter function a bit, we might as well play around with the query feature that's in MUIbase. Queries can be used to display information from a database matching certain criteria.

Choose Queries from the Program menu or press RAMIGA-* to open the query editor. Now a window with some buttons on the top and two larger areas below appear. The string to the upper left is where you enter the name of what you want to call the query you make.

Run

Compiles and runs the query. It goes through the database and then displays the info according to your specifications.

Print

Prints out the result of the query.

Load and Save

Lets you load and save each of the queries.

The first large area is where you enter the query. The second large area is where the result is displayed.

Now let's produce a list of all those persons we tried to filter out previously. Type Persons with an a in their name in the string to the upper left. This is the title for this query. In the upper large area, type:

```
SELECT Name FROM Persontable WHERE (LIKE Name "*a*")
```

Now when you run this query, either by RAMIGA-r or by pressing the Run button, it will produce a list of all persons with the letter a in their name. Try changing the letter to see different results.

At this time we can introduce the AND command. Press the list-view button just to the left of the Run button, in the query editor. Then choose New and name it Persons with both letter a and s in their names. Then type

```
SELECT Name FROM Persontable WHERE
(AND (LIKE Name "*a*") (LIKE Name "*s*"))
```

Note that we are still using the LIKE command for choosing records containing the letters a or s in their names, but the AND command requires that BOTH LIKE criteria are met. Therefore, only records with BOTH the letters a and s in their name are displayed when the query is run.

Adding a table with a memo and a button attribute

=====

This was two ways of selecting and displaying the database. Another way of displaying data can be done by a program. In order to display data we can use an attribute type called memo.

Enter the structure-editor and press New in the table section. Name the new table Controltable and set it's number of records to Exactly one. Click and hold down the mouse button on the new table. Now drag it just a bit above the middle of Persontable and release the button. In the table section, Controltable should now be on top, and Persontable below of it.

Make sure that Controltable is activated, then press New in the attribute section. Set this new attributes type to Memo and give it the name Resultmemo. Press Ok and then add another attribute to Controltable by once again pressing New in the attribute section. This time, set it's type to Button and name it Pedigree.

To give the database a better look, click once on Pedigree in the display section and push it to the top by pressing the Up button once.

Programming MUIbase to do a pedigree

=====

Ok so now we have a button that can start a program and a memo to display data in. It's therefore time to enter the program-editor. This is done either by pressing RAMIGA-p or by choosing Edit from the Program menu. The editor has three buttons:

Compile & Close

Which does just that. It compiles the program and leaves the program-editor.

Compile

Compiles the programs but stays in the program-editor.

Undo

Undo all changes from the time you entered the program-editor.

As all program functions you write will reside in this one window, we will need to separate them from each other. In MUIbase this is done by the DEFUN command. Everything between the two parenthesis will be a part of the function pedigree in this example:

```
(DEFUN pedigree ()
; This is DEFUN's end parenthesis
)
```

With this in mind we now type in the first function which will produce a family tree of the current person in the database and place the result in Resultmemo. This pedigree function is in fact three functions:

- * pedigree which sets Controltable.Resultmemo by calling another function.
- * getpedigree which collects the pedigree to a list.
- * pedigree2memo which converts this list to the memo.

```

; The program pedigree

(DEFUN pedigree ()
  (SETQ Controltable.Resultmemo (pedigree2memo (getpedigree Persontable NIL ←
    ) 0 3))
)

; The program getpedigree

(DEFUN getpedigree (person:Persontable level:INT)
  (IF (AND person (OR (NULL level) (> level 0)))
    (LIST person.Name
      (getpedigree person.Father (1- level))
      (getpedigree person.Mother (1- level))
    )
  )
)

; The program pedigree2memo

(DEFUN pedigree2memo (pedigree:LIST indent:INT level:INT)
  (IF (> level 0)
    (+
      (pedigree2memo (NTH 1 pedigree) (+ indent 8) (1- level))
      (IF pedigree (SPRINTF "%*s%s\n" indent "" (FIRST pedigree)) "\n")
      (pedigree2memo (NTH 2 pedigree) (+ indent 8) (1- level))
    )
    ""
  )
)

```

Ok, so here we have the final program functions. Type this in and make sure that all the parenthesis are where they should be. Too many or too few parenthesis is the most common fault you'll get when MUIbase is pre-compiling your programs. The error message from MUIbase will probably be Syntax Error, in that case. Press Compile & Close and hopefully the window will close, which means that MUIbase couldn't find any faults in it while pre-compiling.

Don't worry too much if you don't understand all the commands at first. As with all programming languages it requires some time and practice to master.

Now we have a program to run, but first we have to assign the program function to the Pedigree button. This is done by entering the structure-editor, selecting Controltable in the table section and double-clicking on the Pedigree attribute in the attribute section. Then open the list-view Trigger. In this list, all your program functions will be listed, currently there should be three functions: pedigree, getpedigree and pedigree2memo. Double-click on pedigree as the program function the Pedigree button will trigger, then press Ok and leave the structure-editor.

Now if everything is done correctly, pushing the Pedigree button will produce a pedigree of the current person. Try changing person to

see some different pedigrees.

Programming MUIbase to list a person's children

=====

As the next addition to this database requires some more records, you should add your brothers and sisters. If you don't have any then write My faked sister 1, My faked brother 1 which of course should be set to have the same parents as you.

Then go to the program-editor and type the following for creating another program.

```

; The program children counts how many children a person has.
; First we define the variables we will use, i.e "children" is set to contain ←
  "\n\n".

(DEFUN children ()
  (LET ( (children "\n\n") (nrofchildren 0) (currentperson Persontable) )

    ; For all records in Persontable do the following:
    ; If the current person appears as father or mother in any of the records ←
      then:
    ;   add the name to the variable children
    ;   increase the nr of children - counter with 1.

    (FOR ALL Persontable DO
      (IF (OR (= currentperson Father) (= currentperson Mother))
        (
          (SETQ children (+ children Name "\n"))
          (SETQ nrofchildren (+ nrofchildren 1))
        )
      )
    )

    ; Then we write the result into the Controltable memo, Resultmemo.
    ; If the current person doesn't have any children then write one string.
    ; If he/she has children then write another string.

    (SETQ Controltable.Resultmemo
      (+ Persontable.Name (IF (> nrofchildren 0)
        (+ " is the proud parent of " (STR nrofchildren) " children(s).")
        " does not have any children (yet :-).")
      ))
    )

    ; If the current person has children then add their names.

    (IF (<> nrofchildren 0)
      (SETQ Controltable.Resultmemo
        (+ Controltable.Resultmemo "\n\n"
          (IF (= nrofchildren 1)
            "The childs name is:"
            "The children names are:")
        )
      )
    )
  )

```

```
        )
        children
    )
)

; This is the end parenthesis of the LET-command.
)

; This is the end parenthesis of DEFUN children.
)
```

To create variables, we use the LET command. Variables created with the LET command are local and only visible within the LET commands open and closing parenthesis. So any command that want to access these variables will have to be within these parenthesis.

All we need to execute this program is a new program button, so enter the structure-editor and add a button attribute in Controltable. Call it Children and choose children as the program function it should trigger.

To bring some order in the mask of Controltable it's now time to introduce groups. All objects can be ordered into vertically or horizontally aligned groups.

In the display section, click on Pedigree and shift-click on Children, thereafter you click on the Group button to the left. Now the two program buttons will be together in a vertically aligned group. However, we want this one to be horizontally aligned so double-click on the VGroup that has appeared in the display section. This will open a window that lets you change the settings for this group. Set the title to Programs and check the Horizontal button.

At this time we can remove the name of Resultmemo in Controltable. Double-click on Resultmemo in the display section and remove the name. Resultmemo will still exist but it's name won't be shown anymore.

To make things easier if we add more programs or attributes in the Controltable, we should place Resultmemo and the Programs group in a vertical group. Be sure of that you only have marked the group Programs and Resultmemo and then press on Group. This will put Programs and Resultmemo into a vertical group.

Leave the structure-editor and take a look at the result. Then press the Children button to see the number of children and their names of the current person.

This example could very well be extended into a full-grown pedigree-program. The only real limits are your fantasy and the size of your hard drive.

1.10 MUIbase/Basic concepts

Basic concepts

Before you start setting up your own database projects and entering data for them, you should now about some basic concepts MUIbase is built on.

Projects

MUIbase projects.

Tables

Basic data management.

Records

One row of a table.

Attributes

One column of a table.

Attribute types

Types available for attributes.

Table of attribute types

Summary about attribute types.

Memory consumption

How much space each type needs.

Relationships

Connecting tables.

User interface

Elements for layout.

1.11 MUIbase/Projects

Projects

=====

A MUIbase project consists of all relevant information you need for managing your data. This includes the project's user interface, the project's data you entered and the programs you wrote for the project.

A project can be loaded from, saved to, and deleted from disk. Any change you make to a project is only done in memory. At any time you can go back to the state of the last saved project by reloading it.

MUIbase is able to handle multiple projects at a time. Therefore it

is not necessary to start MUIbase twice just to load another project.

1.12 MUIbase/Tables

Tables

=====

MUIbase manages data in tables. A table is organized in rows and columns, where rows are called records and columns are called attributes.

See the following table for an example on how to structure a set of addresses in a table.

Name	Street	City
Steffen Gutmann	Wiesentalstr. 30	73312 Geislingen/Eybach
Charles Saltzman	University of Iowa	Iowa City 52242
Nicola Müller	21W. 59th Street	Westmont, Illinois 60559

There exists a special table kind which can hold exactly one record. A table of this kind is sometimes useful for controlling the database project, e.g. you can put buttons into this table for executing various actions, or a read-only attribute for displaying project related information. For an example suppose you have an account database where you store all your income and expense. An exactly-one table now could have a read-only attribute of type real for displaying the total balance.

Each table has two record pointers, a pointer to the record that is currently displayed in the user interface (called gui record pointer) and a pointer to the record that is the current one while executing a MUIbase program (called program record pointer).

You can define any number of tables for a MUIbase project. (Note: in the unregistered MUIbase version there is a limitation of 5 tables per project).

Tables can be added to, renamed, and deleted from a project.

1.13 MUIbase/Records (concept)

Records

=====

A record is one row of a table. It holds all information about one set, e.g. in a table that manages addresses, one record holds one address.

Each record has a record number that reflects the record's position in the table. This number may change when you add or delete records.

For each table a record called initial record exists that holds the default values for initializing new records. The initial record always has a record number of 0.

Records can be added to, changed, and deleted from a table. There is no upper limit on the total number of records for a table. The records are not necessarily held in memory but are loaded from and stored to disk when needed. Ok, there are two upper limits for the total number of records of one table. One comes from the fact that the record number must fit into a long value, which limits the total number of records to 4294967295. Another limitation is that for each record a small record is kept in memory. These limitations should make MUIbase still be usable for record numbers of 10,000 and more.

1.14 MUIbase/Attributes

Attributes
=====

An attribute defines one column of a table. It specifies the type and appearance of the corresponding column.

Attributes can be added to, renamed, and deleted from a table. There is no upper limit on the number of attributes per table. (Note: in the unregistered MUIbase version there is a limitation of 10 attributes per table).

For each attribute you have to specify a type that restricts the contents of this attribute. See the next section for a list of available attribute types.

1.15 MUIbase/Attribute types

Attribute types
=====

For attributes the following types are available:

String

Any single line of text. Can also be used to store font-names, filenames, and external images.

Integer

Ordinary numbers.

Real
Floating point numbers.

Bool
Boolean value.

Choice
One item out of many items.

Date
Date values.

Time
Time values.

Memo
Multi-line text.

Reference
Reference to another record.

Virtual
Compute value on the fly.

Button
For triggering MUIbase programs.

Some of the attribute types support a special value called NIL. This special value has the meaning of an undefined value, e.g. for a type of date it means an unknown date. The NIL value is similar to the NULL value of other database systems.

Please note that once you have set the type of an attribute, you cannot change it later.

1.16 MUIbase/String type

String attributes

String attributes can store any single line of text. Strings are the most often used attribute type in a database project. For example an address database will store the name, street, and city of a person each in its own string attribute.

For a string attribute you have to specify the maximum number of characters allowed in the string. This number does not directly affect the amount of memory or disk space that is used by this attribute because only the actual string contents are stored (other databases have called this feature compressed strings). If necessary the number can be changed after you have installed a string attribute.

String attributes can also be used to store font- and filenames.

For filenames external viewers can be launched to display the file contents. Furthermore an in-line image class allows displaying the image of a file.

String attributes do not support the NIL value.

1.17 MUIbase/Integer type

Integer attributes

Integer attributes store integral values in the range of -2147483648 to 2147483647. They are mostly used for storing quantities of any kind, e.g. the number of children of a person, or the number of song titles on a CD.

Integer attributes support the NIL value representing an undefined integer value.

1.18 MUIbase/Real type

Real attributes

Real attributes store floating point values in the range of -3.59e308 to +3.59e308. They are used for storing numbers of any kind, e.g. the amounts of money in an income/expense project.

For each real attribute you can specify the number of decimal places used for displaying the real value, though internally always the full precision is stored.

Real attributes support the NIL value representing an undefined real value.

1.19 MUIbase/Bool type

Bool attributes

Bool attributes store one bit of information. They are used for storing yes/no or true/false values, e.g. in a project managing invoices a bool attribute could store the has paid? information.

Bool attributes use TRUE and NIL as bool values. NIL in this case stands for a value of FALSE.

1.20 MUIbase/Choice type

Choice attributes

Choice attributes store one item out of an enumeration of items. For example, in an address project a choice attribute can be used for storing the state, where state is one out of USA, Canada, Germany, or others.

A choice attribute does not store the whole item string but the item number (index) in a record. The number of items and the items itself can be modified after the attribute has been created. However when making changes to a choice attribute, values in existing records are not changed to reflect the new situation.

Choice attributes do not support the NIL value.

1.21 MUIbase/Date type

Date attributes

Date attributes store ... ehm ... dates. For example, a date attribute can be used for storing birthdays.

The format for entering and displaying date values can be one of DD.MM.YYYY, MM/DD/YYYY, or YYYY-MM-DD, where DD, MM and YYYY are standing for two and four digit values representing the day, month and year of the date respectively.

Date attributes support the NIL value representing an undefined date.

1.22 MUIbase/Time type

Time attributes

Time attributes store times or periods of time. For example, a time attribute can be used for storing the durations of music titles on a CD.

The format for entering and displaying time values is fixed to HH:MM:SS where HH is a two digit value in the range of 0 to 23 representing the hours, MM a two digit value in the range of 0 to 59 representing the minutes, and SS a two digit value in the range of 0 to 59 representing the seconds.

Time attributes support the NIL value representing an undefined time.

1.23 MUIbase/Memo type

Memo attributes

Memo attributes store multi-line text of any size. Text size is handled dynamically which means that memory is only allocated for the actual text size. In a project managing movies for example, a memo attribute can be used to store summaries of the movies.

Memo attributes do not support the NIL value.

1.24 MUIbase/Reference

Reference attributes

Reference attributes are a special type of attributes, normally not found in other database systems. Reference attributes store a pointer to another record. The referenced record may reside in the same or in any other table than the reference attribute belongs to.

For example in a pedigree project two reference attributes can be used for storing pointers to the father and mother record. Or in a project managing CDs and music titles, a reference attribute in the table holding the music titles can be used to point to the records of the corresponding CDs.

For displaying a reference attribute, any attributes of the referenced record can be specified. Entering a reference attribute can be done by selecting a record from a list of records.

Reference attributes support the NIL value. Here a value of NIL stands for a pointer to the initial record of the referenced table.

1.25 MUIbase/Virtual

Virtual attributes

Virtual attributes are a special type of attributes that do not store any information in the database itself, but compute them on the fly when needed.

For example, in a project managing invoices where a real attribute holds the amounts of money excluding tax, a virtual attribute can be used to "store" the amounts of money with tax. Every time the value of the virtual attribute is needed, e.g. for displaying it, it is computed from the corresponding value without tax.

For displaying virtual attributes three kinds exists: bool, string and list. These three kinds allow showing the value of the virtual attribute as a TRUE/FALSE value, as a single line of text including numbers, dates, and times, or as a list of several single lines, e.g. for listing all music titles of a CD.

Virtual attributes support the NIL value standing for FALSE (bool kind), undefined (string kind), or empty (list kind).

1.26 MUIbase/Button

Buttons

Actually, buttons are not a real attribute type as they cannot store or display any information. Buttons are just used for triggering MUIbase programs.

The reason to keep them as an attribute type is because as an attribute buttons can be accessed by their attribute name. This allows to use the name of a button in a MUIbase program, e.g. to disable or enable the button. Another reason is that buttons have similar properties as attributes, e.g. trigger functions.

1.27 MUIbase/Table of attribute types

Table of attribute types

=====

The following table summarizes all available attributes types:

Type	Description	Nil allowed?
String	For strings of lengths 1..999. A string can also be used for storing filenames, font-names or one-string-out-of-n-strings. For filenames you can add a field where the contents of the file are displayed as an image.	No
Integer	For storing integer values.	Yes
Real	For floating point numbers.	Yes
Bool	TRUE or NIL.	Yes (NIL = FALSE)
Choice	One number out of n numbers. Numbers are represented by label strings.	No
Date	For storing a date value (1.1.0000 - 31.12.9999).	Yes
Time	For storing time values (00:00:00 - 23:59:59)	Yes
Memo	Multi-line text of unlimited length.	No
Reference	For storing a reference to a record	Yes (NIL means

	of another table.	initial record)
Virtual	For displaying results from a MUIbase program.	Yes
Button	For triggering a program function	No (N/A)

1.28 MUIbase/Memory consumption

Memory consumption
=====

Each attribute type needs a certain amount of memory for storing one value in a record. All types except virtual and button have in common that they need a 2 bytes header holding internal information. Additionally, type dependent space is needed for storing the actual value. The following table lists how much memory including a possible 2 byte header one value of the given type needs in memory and on disk.

Type	Memory space	Disk space
String	2 + 4 + STRING-LENGTH + 1	2 + STRING-LENGTH + 1
Integer	2 + 4	2 + 4
Real	2 + 8	2 + 8
Bool	2 + 0	2 + 0
Choice	2 + 2	2 + 2
Date	2 + 4	2 + 4
Time	2 + 4	2 + 4
Memo	2 + 4 + MEMO-LENGTH + 1	2 + MEMO-LENGTH + 1
Reference	2 + 4	2 + 4
Virtual	0	0
Buttons	0	0

Here STRING-LENGTH stands for the length of the string to be stored and MEMO-LENGTH for the text size of the memo to be stored.

1.29 MUIbase/Relationships

Relationships
=====

Up to now you know how to organize your information into tables with records and attributes. But you may also want to setup relationships between tables.

For example if you want to collect CDs in a database project you would have two tables, one for the CDs them-self and one for the music titles of the CDs. Of course you could also have all music titles within the CD table but then you would have a fixed number of music titles for each CD.

So having these two tables, you now need a link for each music title to the CD containing this title. This is called a relationship between the two tables. Normally you use a reference attribute for setting up such a relationship.

By installing a reference attribute into a table you automatically have a relationship between the table the attribute resides in and the table it refers to.

The following classes of relationships can be distinguished:

One to one relationships

Simple ones.

One to many relationships

Most often used ones.

Many to many relationships

Complex ones.

1.30 MUIbase/One to one relationships

One to one relationships

One to one relationships are very simple relationships where for each record you have one or zero partners in another or in the same table.

For example in a database project that manages your favorite movie actors you could setup a reference attribute called married with that shows the person the actor is married with. An actor that is currently not married does have a NIL value for this reference field.

Of course, no one prevents the user to set the married with references of several actors all to the same person. However by programming MUIbase it is possible to detect such cases and handle accordingly.

1.31 MUIbase/One to many relationships

One to many relationships

One to many relationships are useful for connecting a set of records to one record in another or the same table.

For example in a project managing your bank accounts you could have one table for all bank accounts and one table for all transactions. Now you surely want to know which transaction belongs to which account so you setup a reference attribute in the transaction table referring to the account table.

One to many relationships are the most often used ones. You can use them for managing any hierarchical-like structures, e.g. CDs with music titles, bank accounts with transactions, family trees, etc.

One to many relationships are also the basis for realizing many to many relationships as described in the next section.

1.32 MUIbase/Many to many relationships

Many to many relationships

Many to many relationships are used when you want a set of records to refer to another set of records.

For example in a project that manages movies and actors you would have two tables, one for the movies and the other one for the actors. Now for each movie you want to know the actors that took part in the movie. So you might think to setup a reference attribute in the actor table that refers to the movie table. But when doing this you could only have one movie referenced for each actor because there is only one reference field in the actor table. So what you need is an unlimited number of references from the actor table to the movie table.

This is done by adding a new table that just has two reference attributes, one pointing to the actor table and the other to the movie table. Now you can enter the relationships by adding new records to this table. For each movie-actor constellation you add a new record and specify the movie and actor by setting the corresponding reference fields.

If you want to know in which movies an actor took part then you only have to search for all records in the new table that refer to the actor in question and look at the movie records the found records refer to. Such a search can be done automatically by MUIbase and the result can be displayed in a list-view.

The following tables show an example of how to connect a set of actors to a set of movies.

	Title	Country
m1:	Batman	USA
m2:	Batman Returns	USA
m3:	Speechless	USA
m4:	Tequila Sunrise	USA
m5:	Mad Max	Australia

m6: Braveheart USA

Name

a1: Michael Keaton
 a2: Jack Nicholson
 a3: Kim Basinger
 a4: Danny DeVito
 a5: Michelle Pfeiffer
 a6: Geena Davis
 a7: Christopher Reeve
 a8: Mel Gibson
 a9: Kurt Russell
 a10: Sophie Marceau
 a11: Patrick McGoochan
 a12: Catherine McCormack
 a13: Christopher Walken

MovieRef ActorRef

m1	a1
m1	a2
m1	a3
m2	a1
m2	a4
m2	a5
m2	a13
m3	a1
m3	a6
m3	a7
m4	a8
m4	a5
m4	a9
m5	a8
m6	a8
m6	a10
m6	a11

From these tables you can find out for example that Mel Gibson took part in the movies *Tequila Sunrise*, *Mad Max*, and *Braveheart*, or that in movie *Batman* the actors Michael Keaton, Jack Nicholson, and Kim Basinger took part.

1.33 MUIbase/User interface

User interface

=====

MUIbase uses a graphical user interface (gui) organized in a hierarchical way for displaying record contents and for letting the user enter new data. Each project owns its own root window in which further gui elements (including sub windows) can be placed. The gui

elements are also called display objects.

A table is displayed in an own gui element called mask. A mask can display only one record at a time. Its layout and the attributes included in the mask are customizable by the user.

The following gui elements are available for designing a project's gui layout:

Windows

Root and sub windows.

Masks

Displays a table.

Panels

Controls a table.

Attribute objects

Shows a data item of one record.

Text objects

Static text descriptions.

Images

Static images for decoration.

Space objects

Layout and separator item.

Groups

Groups gui elements vertically and horizontally.

Balance objects

Dynamic sizing of group elements.

Register groups

Pages of gui elements.

1.34 MUIbase/Windows

Windows

Windows can be used to spread information of a project across several independent areas.

Each project automatically has its own root window. If needed, e.g. if the space of the root window exceeds, additional sub windows can be created. Sub windows can also have further sub windows.

For each sub window a window button is placed into the parent window allowing to open and close the sub window. The window button looks like a normal text button but has a small window icon showing the open/close state of the corresponding sub window.

Root windows do not have a parent window and therefore have no window button. Closing a root window means closing the whole project.

A window can have any other gui elements (except panels) as children. If no child has been added to a window then an empty display image (see

Empty display image
) is shown.

1.35 MUIbase/Masks

Masks

A mask is used to display the contents of a table. Only one record of the table can be shown at a time.

The mask may include a panel (see next section) for controlling the table. Other gui elements like attribute or text objects can be placed into a mask to show the record contents.

Masks cannot be placed inside other masks as this would lead to a hierarchy of masks and therefore to a hierarchy of tables which is not supported in MUIbase. If you want to setup a hierarchy of tables, use an 1:n relationship between two tables.

1.36 MUIbase/Panels

Panels

A panel is a small rectangular area placed at the top edge of a mask. A panel can display a title, e.g. the name of the corresponding table, a pair of numbers showing the record number of the current record and the total number of records, and several buttons for controlling the table, e.g. for displaying the next or previous record.

Only one panel can be defined for a mask. If you setup a panel for a mask then an additional border is drawn around the mask, otherwise no border is drawn.

1.37 MUIbase/Attribute objects

Attribute objects

Attribute objects are used to display the contents of one item of a record.

Depending on the type of the attribute the gui element is either a string gadget (types string, integer, real, date and time), a check-mark gadget (type bool), a cycle gadget or a set of radio buttons (type choice), an editor gadget (type memo), a pop-up list-view (type reference), a text, check-mark, or list-view gadget (type virtual) or a text or image button (type button). In some cases the gui element may also be a simple text gadget if the attribute object is set to read-only.

1.38 MUIbase/Text objects

Text objects

Text objects are used for describing the various field elements of a record mask or just to display some static text like copyright information somewhere in a window.

1.39 MUIbase/Images

Images

Images can be displayed anywhere in a window. An image can be an internal MUI graphic, a simple color field, or a pictures from an external file. The image size can be set to resize-able or fixed.

The image is static. If you would like to store images in a table you should use a string attribute (see
String type
).

Please note that images are not available in the unregistered version of MUIbase.

1.40 MUIbase/Space objects

Space objects

Space objects are used to insert space in the layout of a window or a table mask. A space object can have a vertical (or horizontal) bar for delimiting other gui elements.

1.41 MUIbase/Groups

Groups

Gui elements can be grouped into horizontal or vertical groups. A group places its children from left to right (horizontal group) or from top to bottom (vertical group).

A group can surround its child objects with a rectangular frame, an optional title can be displayed to the top of a group, and a flag controls whether space is inserted between the child objects or not.

1.42 MUIbase/Balance objects

Balance objects

Balance objects can be placed anywhere between other child objects into a window, mask, or group object. A balance object allows the user to control the weight values of the other child objects and therefore how much space each child gets.

1.43 MUIbase/Register groups

Register groups

A register group can be used to layout some gui elements into several pages that can be activated one at a time. This is useful if the user interface becomes large and you don't want to spread it over several windows.

1.44 MUIbase/Managing projects

Managing projects

In this chapter you find:

File format

MUIbase project file structure.

Info

Information about current project.

Clear project

Start a new project.

Open project

Load project from disk.

Save project

Save project to disk.

Delete project

Delete project from disk.

Close project

When the project is done.

Swap records

Learn about MUIbase memory management.

1.45 MUIbase/File format

File format

=====

A MUIbase project consists of several files stored under its own directory. From Workbench you will not notice the directory structure since double clicking a project icon will not open the directory but start MUIbase loading the project. From CLI however you can see the directory structure of a MUIbase project.

All files of a project are put into one directory which is created by saving a project. Do not remove or place any files or further directories in this directory! They will get lost when reorganizing the project.

The directory contains a file called Structure.mb where the descriptions of all tables, attributes, filters, etc. are stored. The record headers are also placed here. For each table you will find a file with the table's name. Here all records of a table are stored. Last but not least there is a file called .lock. Do not remove this

file. If you did it by accident then simply recreate it, the file contents are not important. This file is used for locking a project, that is, MUIbase first locks this file exclusively and then opens other files. If the locking fails, MUIbase knows that there is already a MUIbase application working on this project. Only one MUIbase application is allowed to work on the same project at a time since record files are opened in read/write mode and we don't want to have mixed data written by two or more applications. ;-)

1.46 MUIbase/Info

Info

====

MUIbase keeps some information about each project. Select menu item Project - Info to get information about the current project. The information you get consists of the project's name, the number of tables, the total number of records in all tables, and a value that shows how many bytes a reorganization of this project would gain. The gain is however only a rough estimate and should not be treated as an exact number. Especially if you have made many changes to the structure of the project (adding or removing attributes) then this value is far from accurate.

1.47 MUIbase/Clear project

Clear project

=====

To begin a new project select menu item Project - Clear - Project. This clears the current project and MUIbase opens an empty window displaying the MUIbase logo. After starting MUIbase without any projects you are automatically in this mode.

By selecting menu item Project - Clear - Records you start a new project using the structure of the current one. This means that everything except the record data of the current project is used for the new project.

If the current project at the time you selected one of the clear menu items has not been saved to disk then a safety requester appears asking for confirmation of the operation.

1.48 MUIbase/Open project

Open project

=====

MUIbase can handle any number of projects at a time. You are only limited by the size of your available memory. If you want to edit another project, select menu item Project - Open new. This opens a new project root window. You can now load a project for this window.

To load a project select menu item Project - Open - Project. This opens a file-requester where you can choose a project from. It's also possible to only load the structure of a project, that is, the whole project is loaded except the record data. To do this, select menu item Project - Open - Structure.

If you were editing a project at the time of choosing any of the above menu items and the project has not been saved then a safety requester appears asking for confirmation.

1.49 MUIbase/Save project

Save project

=====

All changes you make to a project are only done in memory. Thus if you want to make them permanent you have to save the project to disk. This is done by choosing menu item Project - Save. If your project doesn't have a name yet then a file-requester appears first asking for a filename.

The reason why MUIbase does not automatically save a project when you change it is that this way it is you who decides when to save a project and you can always go back to the last saved version of your project. This mechanism is similar to the COMMIT and ROLLBACK commands in SQL database systems.

If you save a project, all modified records are written to disk and the file Structure.mb is recreated. Before creating the new Structure.mb file, MUIbase first renames a possibly existing Structure.mb file to Structure.old to have a safety copy in case the save operation fails.

This mechanism guarantees fast load & save operations but it is not reorganization free. If you have modified many records then the physical place where the records lie and the resulting fragmentation may become disadvantageous. Therefore a menu item Project - Save & Reorg exists that does a save & reorganize operation. This operation may take some time depending on the number and size of the records. The save & reorganize operation creates a new directory and rewrites all project related files. The old directory is deleted on success.

Another good place to execute a reorganization is when you have done changes to the data-structure of a project, e.g. after you have installed a new attribute in a table. These changes are not applied

immediately to all records because it would take too much time to load each record, modify it, and save it back to disk. Therefore these changes are put on an internal todo list which is applied after loading a record. Applying this list to a record takes only little time. However the longer the list gets the more time it needs. Reorganizing a project causes the todo list to be applied to all records, so if you have made many changes to the project structure then reorganizing a project will shorten the time for loading records.

You can also save & reorganize a project to a new filename keeping the old project untouched. To do this select menu item Project - Save & Reorg As. MUIbase will prompt you to enter a new name for the project.

1.50 MUIbase/Delete project

Delete project
=====

MUIbase offers a menu item to delete a project. If you select Project - Delete, enter a filename in the file-requester and confirm the deletion in an additional safety requester then the specified project is deleted from disk.

MUIbase does nothing special here, it simply deletes the directory with all files in it. It is safe to do this in any other way, e.g. by using Workbench or an Amiga Shell.

1.51 MUIbase/Close project

Close project
=====

If you are done with a project you can close it by selecting menu item Project - Close. This removes the project from memory and closes all windows belonging to it. If the project contains changes that have not been saved then a safety requester appears offering to save, continue or cancel the operation.

For closing a project you can also select menu item Project - Save & Close which saves the project first if there were any changes and then closes it.

1.52 MUIbase/Swap records

Swap records

=====

MUIbase doesn't need to keep all records of a project in memory. Thus loading and saving of projects is much faster. When loading a project a record header is allocated for each record. The data itself is only loaded when needed, e.g. when it is displayed on the screen. The total number of records is still limited by available memory since each record header needs some few bytes of memory.

You can specify how much memory MUIbase should use for the records of a project. Choose one of the predefined values found in menu item Preferences - Record memory. MUIbase will not preallocate a block of the specified memory size, it only checks from time to time if the current size of allocated memory is larger than the specified value. The specified value is not a hard limit, only a suggestion. If MUIbase needs more memory then it will ignore the upper bound and allocate it.

If MUIbase runs out of memory or if the upper limit for the record memory size has been reached then MUIbase tries to free as much record memory as possible. In this case MUIbase may write modified records to disk to get the maximum available memory possible. You can also force MUIbase to do this by choosing menu item Project - Swap records.

If there is enough memory to hold all records in memory and you have specified an upper memory limit that is high enough (e.g. unlimited) then MUIbase never needs to swap out records.

MUIbase maintains a free list for each record file. If you delete a record then the record's file space is added to the free list. Also if you change a record and the record needs to be written to disk then the old file space is added to the free list. However MUIbase makes sure that by reloading you can always go back to the point of the last save operation. MUIbase will not trash areas which are free but where a record still sits that could be reached by reopening the project.

1.53 MUIbase/Preferences

Preferences

MUIbase offers several preferences items the user can set to his likes. This chapter shows what preferences items are available and gives general information about how the preferences system works.

Record memory
Size of record buffer.

Record delete requester
Safety requester when deleting records.

Ext. editor for prog.
Use your favorite editor for programming.

Icon creation
Create project icons.

Icon tool name
Tool name in project icons.

Formats
Real and date formats.

External editor
Specify your external editor.

External viewer
Specify your external viewer.

Popups in cycle chain
Include popup buttons in the cycle chain.

Confirm save & reorg
Safety requester when saving and reorganizing a project.

Confirm quit
Safety requester when quitting MUIbase.

Program include dir
Where to look for external include files.

Program debug info
Compile with or without debug information.

Program output file
Where program output goes.

Project dep. settings
Global versus project local preferences.

MUI
MUI's preferences.

Load and save prefs
Make settings permanent.

Empty display image
Image for empty windows.

1.54 MUIbase/Record memory

Record memory
=====

MUIbase does not need to keep all records of a project in memory. Instead it uses a buffer for holding only a small number of records. By choosing a value from menu item Preferences - Record memory you can set the size of this buffer. Each project has its own buffer, so if you have opened two projects each having a record buffer size of 1MB, MUIbase will use up to 2MB for the records of both projects.

MUIbase will not allocate the memory a priori, it uses a dynamic allocation scheme. Also, the buffer size you specify is not a hard limit. If MUIbase decides it needs more memory then it will try to allocate it.

Once the buffer gets full, or if MUIbase runs out of memory, all records are flushed from the buffer. This means that unchanged records are simply freed and changed records are first written to disk and then freed.

By giving MUIbase a higher value for the record buffer you will notice a speed increase in accessing the records because now since more records are held in memory fewer records have to be loaded from disk. If you set the record memory size to unlimited and all records fit into memory then MUIbase operates with optimal speed.

1.55 MUIbase/Record delete requester

Record delete requester
=====

You should check menu item Preferences - Record delete requester if you want MUIbase to pop up a safety requester asking for confirmation whenever you try to delete a record. Leave the item unchecked if records should be deleted silently. Default is checked.

1.56 MUIbase/External editor for programming

External editor for programming
=====

You can check menu item Preferences - External editor for programming if you always want to use the external editor for editing MUIbase programs. This means that whenever you open the program editor, the external editor is also started automatically. If you don't check this field then you can still launch the external editor by choosing the corresponding item in the editor's context menu. Default is unchecked.

1.57 MUIbase/Icon creation

Icon creation
=====

Check menu item Preferences - Icon creation if you want MUIbase to create an icon for each project. You can still paint and use your own icon for a project. MUIbase will not overwrite existing icon images as long as they are project icons. Default is checked.

1.58 MUIbase/Formats

Formats
=====

By selecting menu item Preferences - Set formats you can specify the formats used when displaying or printing real and date values. After selecting the menu item a new window appears containing the following items:

- * a field Real format for setting the decimal character of real values. You can choose between Decimal point and Decimal comma.
- * a field Date format for specifying how date values are output. You can choose between Day.Month.Year, Month/Day/Year and Year-Month-Day.
- * two buttons Ok and Cancel for leaving the window.

The initial values for real and date formats are determined according to the information found in the operating system's Locale library.

When you are done with all settings, press the Ok button to leave the window and update the display.

1.59 MUIbase/Icon tool name

Icon tool name
=====

By selecting menu item Preferences - Icon tool name you specify the tool name that should be executed when you double click a project icon. Normally you should specify the path to the MUIbase program, e.g. MUIbase:MUIbase which is the default.

1.60 MUIbase/External editor

External editor
=====

MUIbase's editor fields offer a special menu item where you can call an external editor for editing the text contents. The name of the editor and its parameters must be specified by selecting menu item Preferences - External editor. You should enter a command string that gets executed when calling the external editor. Use %f at the place where the filename normally stands. The %f string is replaced with the actual filename of the temporary file MUIbase creates before executing the command.

For example you can use CED %f -keepio for using CED as external editor (make sure that your default stack size is at least 8192 bytes in size, otherwise CED might crash).

Default is Ed %f.

1.61 MUIbase/External viewer

External viewer
=====

In MUIbase you can use strings for storing filenames. For displaying the contents of such a filename, an external viewer is needed. Normally this viewer uses the Amiga-OS datatype system for displaying pictures, showing animations, or playing music. To specify this viewer select menu item Preferences - External viewer.

Like for the external editor (see
External editor
) you have to
specify a command string here. Default is Multiview %f.

1.62 MUIbase/Popups in cycle chain

Popups in cycle chain
=====

In the graphical user interface entered in the structured editor there might exist popup buttons, e.g. file, font or listview popups beneath a string gadget. These buttons are usually not included in the cycle chain, that is, you can't use the Tab key to activate them. However if you check menu item Preferences - Popups in cycle chain then all popup buttons are include in the cycle chain.

Please note that changing the status of this menu item has only an effect after rebuilding the user interface, e.g. by switching to the

structure editor and back to the user interface.

1.63 MUIbase/Confirm save & reorg

Confirm save & reorg
=====

Saving and reorganizing a project can take quite some time depending on the size of the project. Therefore, if you select menu item Project - Save & Reorg or Project - Save & reorg as, a safety requester pops up asking for confirmation of this operation.

The requester only appears if menu item Preferences - Confirm save & reorg is checked, thus you can disable this requester by de-selecting the menu item.

1.64 MUIbase/Confirm quit

Confirm quit
=====

If you try to quit MUIbase and there are unsaved projects then MUIbase pops up a safety requester asking for confirmation. However if all projects have been saved, the program usually quits silently.

If you want MUIbase to always pop-up a requester when quitting then check menu item Preferences - Confirm quit. In this case you always get a safety requester when selecting menu item Project Quit. Nevertheless it is still possible to quit MUIbase silently by closing all projects.

1.65 MUIbase/Program include directory

Program include directory
=====

The programming feature of MUIbase allows to include external sources within the project's program (see

```
#include
for more
```

information). Menu item Program - Include directory allows to set a directory where MUIbase should search for such include files. Default is MUIBase:Include.

1.66 MUIbase/Program debug information

Program debug information

=====

For compiling a project's program, you can choose whether debug information should be included in the executable or not. If you compile without debug information and a run-time error occurs then an error description is generated but there is no information about where exactly the error occurred. If you compile with debug information then you also get the exact error location.

Use menu item Program - Debug information to turn debug information for compilation on and off. After changing this state, don't forget to recompile the project's program by choosing menu item Program - Compile.

1.67 MUIbase/Program output file

Program output file

=====

When executing a MUIbase program all output which is directed to stdout can be printed to a file. The filename has to be entered in the requester that appears when choosing menu item Program - Output file. Here, you can also specify if the file should be opened in appended mode or if it should be cleared before the first output happens. Besides traditional files, the Amiga-OS system allows several special filenames here, e.g.:

- * PRT: prints the output on your printer.
- * CON:////MUIbase output/CLOSE/WAIT prints the output in a Shell window.
- * CONSOLE: prints the output in the Shell window where MUIbase has been started from.

1.68 MUIbase/Project dependent settings

Project dependent settings

=====

MUIbase can manage several projects and for each project you can have your own set of preferences. Sometimes however it is desirable to have all projects sharing the same setting for one of the preferences items. This is realized by using a status flag for each preferences item which indicates whether each project has its own value for this field or if the value is shared among all projects.

By choosing menu item Preferences - Project dependent settings a

window with a list of several preferences items appears. All items in this list can be set either project dependent or global. The list contains the following items:

- * Record memory
- * Record delete requester
- * Formats
- * Confirm save & reorg
- * Program include directory
- * Program debug information
- * Program output file

The status flag of preferences items not included in this list cannot be changed and is either project dependent or global, e.g. the setting of preferences item icon tool name is always global since it doesn't make sense to have different icon tool names for different projects.

If you check the box to the right of a preferences item then this item is made project dependent, otherwise it is global. Project dependent settings are stored in the project file `Structure.mb`, whereas global settings are stored in a global preferences file.

1.69 MUIbase/MUI

MUI
===

Since MUIbase is a MUI application you can also specify the MUI preferences for this application by choosing menu item Preferences - MUI.

1.70 MUIbase/Load and save preferences

Loading and Saving of preferences
=====

The global preferences can be loaded and saved to disk. When MUIbase is started, it automatically loads its preferences from `ENV:MUIbase.prefs`.

MUIbase doesn't save its global preferences automatically. Thus, if you make changes to the global preferences and you want MUIbase to remember them after a restart then you have to save them by choosing

menu item Preferences - Save preferences. The global preferences are written to both ENVARC:MUIbase.prefs and ENV:MUIbase.prefs. The following items are stored:

- * Record memory size
- * Record delete requester
- * External editor for programming
- * Icon creation
- * Icon tool name
- * Formats
- * External editor
- * External viewer
- * Confirm save & reorg
- * Confirm quit
- * Program include directory
- * Program debug information
- * Program output file
- * Project dependent settings
- * Directory names for several file requesters
- * Default max length for new string attributes
- * Default text format for new attribute objects
- * Cursor position of program editor
- * Name of help file

There is also a menu item called Preferences - Load preferences. Choose this menu item in case you made changes to the preferences and want to go back to the previously saved version.

1.71 MUIbase/Empty display image

Empty display image

=====

If you start MUIbase without loading any projects then MUIbase opens a window with an empty display. The empty display usually consists of a image which is loaded from the file MUIbase:Images/EmptyWindow.iff.

By default this image is the MUIbase logo but you can replace it by copying your favorite picture to MUIbase:Images/EmptyWindow.iff. It is also possible to have no image for the empty display window, just make sure that the above filename doesn't exist. In this case MUIbase only prints the text Empty display in the window.

1.72 MUIbase/Record-editing

Record-editing

In this chapter you find:

Active object

Where your input goes.

Adding records

How to add new records to a table.

Changing records

How to edit record contents.

Deleting records

If you don't need a record any more.

Browsing records

How to view other records.

1.73 MUIbase/Active object

Active object

=====

MUIbase uses a cursor for displaying which object is the active one. If the active object is a string object then a normal block cursor appears, other objects get a special frame around them. You can cycle through the active objects by pressing the Tab or S-Tab keys.

The table in which the active object resides is called the active table. The panel of a table can be set to the active object. This ensures that you can always set a table to be the active one, although the table may not contain any other activate-able objects.

1.74 MUIbase/Adding records

Adding records

=====

If you select menu item Table - New record a new record is allocated in the active table. The record is initialized with the initial values for all attributes. It is also possible to duplicate the current record of the active table by selecting menu item Table - Duplicate record.

1.75 MUIbase/Changing records

Changing records

=====

To change the current record in a table you can activate any attribute object within the table's mask and enter a new value. For string, integer, real, date, time, and memo attributes you can use the usual editing commands.

An attribute object may have been configured as read-only. In this case you can't change its value (exception: string attribute with pop-up button).

String attributes with pop-up button

=====

If a string attribute has a pop-up button attached to it then you can press the pop-up button and get a requester to set the string contents, e.g. a file-requester for choosing a filename, or a list of strings to choose one from. The pop-up button can always be used to set the string attribute's value even if the attribute is set to read-only.

Right to the string field a V button might appear. Pressing this button calls an external viewer to display the file specified in the string field.

Entering bool values

=====

The checked state of bool attribute can be toggled with the left mouse button, or with the space bar if the object is the active one.

Entering choice values

=====

For choice attributes you can choose a value by clicking onto it, or by using the Cur-Up and Cur-Dn keys to browse through all choice labels.

Entering date values

=====

Date values can be entered in the format DD.MM.YYYY where DD, MM and YYYY are standing for two and four digit values representing the day, month and year of the date respectively. It is possible to omit the year value of a date. In this case the current year is appended to the input string.

By inserting a single integer value, a date value relatively to the current date can be specified, e.g. when entering 0 the today's date is used, or when entering -1 yesterday's date is used.

Entering time values

=====

Time values can be entered in the format HH:MM:SS where HH is a two digit value in the range of 0 to 23 representing the hours, MM a two digit value in the range of 0 to 59 representing the minutes, and SS a two digit value in the range of 0 to 59 representing the seconds.

It is possible to omit the number of hours and the number of minutes. In this case a value of 0 is used. E.g. if you enter 6:30 it is automatically expanded to 00:06:30.

Memo context menu

=====

Memo attributes have a context menu that offers further editing possibilities:

- * Cut, Copy, and Paste allow exchanging data with the clipboard.
- * Clear deletes all text in the memo.
- * Undo and Redo allow going back and forth the changes you made to the memo contents.
- * With Open text and Save text you can load and save the memo contents from/to a disk file.
- * External editor launches an external editor for editing the memo. See
 External editor
 , for more information about the external editor.

Entering reference values

=====

For reference attributes there are several options to enter a value:

- * To the right of a reference attribute you find a pop-up button which if pressed opens a list of records and two further buttons. Choose a record from the list to set the reference to this record, Initial to set the reference to the NIL value, or Current to set the reference to the current record of the referenced table.
 - * Use the context menu of the reference attribute to see further options to set the reference. You also find the corresponding
-

shortcuts there.

- The Previous and Next menu item set the reference to the previous or next record.
 - The Backward and Forward menu items will let you go 10 records backward or forward.
 - The Search for... menu item pops up a requester to enter a pattern for searching a record. If you don't check the All fields? box then the search is only done in the attribute which is first in the list of attributes that is used for ordering the referenced table. The reason why only this attribute is examined is because prefix searching can be done very efficient on this attribute as the attribute acts like an index. For more information about the search requester, see
 - Search for
 - .
 - Once you have entered a search pattern in the search requester, Search backward and Search forward can be used to find the previous or next matching record.
- * If the reference attribute object is the active object, you can enter a character to search for a record that has its contents of the first order attribute of the referenced table starting with this character. The search is done case insensitive. E.g. if you enter l then a search pattern of l* is used for searching the record. You can append further characters to the search buffer by typing them in uppercase, e.g. lASSIE would search for a record matching the string Lassie*.

Entering NIL value

=====

To enter the NIL value enter any invalid string for the given attribute type, e.g. if you enter xyz in an integer attribute then the value of this attribute is set to NIL. Please note that not all attribute types support the NIL value. See

- Table of attribute types
- for an overview of all attribute types.

1.76 MUIbase/Deleting records

Deleting records

=====

To delete the current record chose menu item Table - Delete record. Before deleting the record a safety requester may appear asking you for confirmation. You can enable and disable this requester in the preferences settings (see

- Record delete requester
-).

1.77 MUIbase/Browsing records

Browsing records

=====

To view other records than the currently displayed one, select one of the sub menu items in menu item Table - Goto record. You can go to the previous, next, first, or last record, jump several records backward or forward, or enter the record number of the record you want to view. The record number in this context is the number that is displayed in the corresponding panel for that record (see

Panels

).

The panel may also include two arrow buttons for going to the previous and next record.

Record browsing can be easily done using the CurUp and CurDn keys in combination with the Shift, Alt, and Ctrl keys. All possible combinations are listed in menu item Table - Goto record and in the following table:

	Alt	Ctrl-Alt	S-Alt
CurUp	Previous record	First record	Jump backward
CurDn	Next record	Last record	Jump forward

1.78 MUIbase/Filter

Filter

Filters can be used to hide records. This chapter describes what types of filters are available and how to use them.

MUIbase knows two types of filters, record filters and reference filters.

Record filter

Using a boolean expression as filter.

Reference filter

Using a record reference as filter.

1.79 MUIbase/Record filter

Record filter

=====

A record filter can be installed into a table to filter out records that are not of interest to you. Records that are filtered out are excluded in the table mask and thus the user can't see or browse to them.

Filter expression

How a filter looks like.

Changing filters

How to specify filter expressions.

Filter examples

Some examples.

1.80 MUIbase/Filter expression

Filter expression

A filter is defined by specifying a boolean expression that may contain calls to MUIbase programming functions. For each record of the table the filter is specified for, this expression is evaluated. If it returns NIL then the record is filtered out, otherwise it is included in the table mask.

Each table can have its own filter expression.

1.81 MUIbase/Changing filters

Changing filters

To change the filter of the current table select menu item Table - Change filter. This will open a window containing

* the name of the table you install the filter for in the window title.

- * a list of all attributes of the table that can be used in the filter expression. This list is placed in the left part of the window. If you double click a name then the name will be inserted into the filter expression at the current cursor position.
- * a cascade of buttons displaying MUIbase programming functions and operators. It is placed in the right part of the window. Click on one of the buttons to enter the corresponding function in the filter expression. Please note that the presented list of functions and operators is not complete. Other MUIbase functions not shown in one of the buttons must be entered by hand. Only those MUIbase functions can be used that don't have side effects, e.g. it is not possible to write data to a file within a filter expression.
- * a string input field to enter the filter expression. The attribute and function/operator names are inserted here. You can also directly input your filter expression.
- * two buttons Ok and Cancel to leave the window.

After you are done with the specification of the filter expression click on the Ok button to leave the window. The entered expression is now compiled and, if successful, the expression is evaluated for all records. Those records for which the boolean expression doesn't hold are then discarded in the table mask.

In case the expression doesn't compile you will get an error message displayed in the window title bar.

A filter can be turned on and off by clicking on the F button in the table's panel (if it is installed), or by pressing the F key when the panel is the active object. After you have specified a filter expression for a table the filter for this table is turned on automatically.

If you (re-)activate a filter then all records of the table are checked whether they match the filter or not.

If a filter is currently active and you change a (filter relevant) attribute in a record of this table then the match-filter state of this record is not recomputed and stays unchanged.

If you allocate a new record in a table with an activated filter then there is no check if the new record matches the filter and the new record has its match-filter state set to TRUE.

1.82 MUIbase/Filter examples

Filter examples

Here are some examples for valid filter expressions:

- * NIL filters out all records.
- * TRUE doesn't filter out any record.
- * 0 same as TRUE as for MUIbase all expressions not equal to NIL are considered as TRUE.
- * (> Amount 100.0) only displays records where the Amount attribute is greater than 100.0 (we assume here that the table has an attribute Amount of type real).
- * (NOT (LIKE Name "*x*")) filters out all records that have the letter x in the Name attribute (a string attribute).

Please note that MUIbase' programming language uses a lisp-like syntax. For more information about the programming language, see

Programming MUIbase

.

1.83 MUIbase/Reference filter

Reference filter

=====

Reference attributes can also have a filter behavior. This is useful e.g. for building a hierarchy of tables (like it is hard-wired in AmigaBase). As an example see the project Albums.

If the filter of a reference attribute is turned on then the following features are activated:

1. The user can only access records in the attribute's table that have the reference set to the current record of the referenced table.
2. If the referenced table changes its current record then also a new current record is searched and set for the attribute's table.
3. When allocating a new record the reference is automatically set to the current record of the referenced table.

Note: Cascading delete (like it is automatically done in AmigaBase) has to be implemented by the user himself (by using a delete trigger function).

Do not use the reference filter on cyclic graphs, e.g. self-referencing tables. It doesn't make sense and will only confuse the user.

1.84 MUIbase/Order

Order

For each table in your database you can specify in which order its records should be displayed. This chapter describes how you can specify an order and what consequences it has.

Empty order

If you don't want to order your records.

Order by attributes

How it works.

Changing orders

How to specify an order.

1.85 MUIbase/Empty order

Empty order

=====

By default each newly created table has an empty order. This means that if you enter a new record, the created record is inserted at the current position, that is, behind the current record of the table. If you change some fields of a record, the position of the record within the table leaves unchanged.

1.86 MUIbase/Order by attributes

Order by attributes

=====

Sometimes it is useful to have the records sorted by a certain attribute, e.g. by the Name attribute if the table has such one.

In MUIbase you can specify for each table a list of attributes by which its records should be sorted. All records are first sorted by the first attribute in this list. If two records are equal in an attribute then the next attribute in the list determines the order. For each attribute you can specify if the records should be sorted ascending or descending.

For determining the order of attributes the rules of the following table are used:

Type	Order relation
Integer	NIL < MIN_INT < ... < -1 < 0 < 1 < ... < MAX_INT
Choice	(Choice values are treated as integers)
Real	NIL < -HUGE_VAL < ... < -1.0 < 0.0 < 1.0 < ... < HUGE_VAL
String	NIL < "" < ... < "a" < "AA" < "b" < ...
Memo	(String comparison is done case insensitive)
Date	NIL < 1.1.0000 < ... < 31.12.9999
Time	NIL < 00:00:00 < ... < 23:59:59
Bool	NIL < TRUE
Reference	NIL < any_record (Records itself are not comparable for ordering)

If you have specified an order for a table then the records are automatically rearranged whenever you add a new record or change an order relevant field of a record.

1.87 MUIbase/Changing orders

Changing orders

=====

To specify an order list for the current table select menu item Table - Change order. This will open a window containing

- * the name of the table in the window title.
- * a list of all attributes of the table that can be used in the order list. This list is placed in the left part of the window. If you double click a name then the name will be inserted into the order list at the current cursor position.
- * the current list of attributes used for ordering. This list is placed in the right part of the window. The top item in this list is the first attribute of the order list. You can rearrange items by dragging them to other positions in the list. To add further attributes drag them from the attribute list to the order list. You can remove an attribute from the order list by dragging the item out of the order list and dropping it onto the attribute list.

Each entry in the order list has an arrow symbol pointing up or down on the left side. You can toggle the state of the arrow by double-clicking it. If an arrow is pointing up then the sorting order for this attribute is done ascending, if it is pointing down, it is done descending.

- * a Clear button to clear the order list.

* two buttons Ok and Cancel for leaving the window.

To enter a new order list, first press the Clear button. Then use drag & drop as described above to build up a new list of attributes. If you want to have an empty order then just don't add any attributes to the order list.

When you are done specifying the order list, press the Ok button. MUIbase will then reorder all records of the table. As this can need some time, a busy mouse pointer will appear.

1.88 MUIbase/Search for

Search for

For record browsing you can use a search requester to search for a specific record. The search feature uses a search pattern that you provide and checks all records for a successful match with this pattern. If it finds one then this record will be displayed in the table mask.

Search requester

How to enter a search pattern.

Forward-backward search

Go to the next/previous matching record.

Examples

Some search pattern examples.

1.89 MUIbase/Search requester

Search requester

=====

To open the search requester select menu item Table - Search for. This will open a window containing

* a string field for entering the search pattern. Use the characters * and ? as jokers. The character * matches any number of characters (including zero characters) whereas ? matches exactly one single character.

* a field Case sensitive. If you check it, search for uses case sensitive string comparison, otherwise case insensitive string

comparison is used.

- * a field All fields. If checked then all fields of a record are tested for a successful match with the search pattern. Otherwise only the attribute which has been the active one when the search requester has been opened is tested. In case the active object at the time when opening the search requester has not been an attribute object, this field is checked and disabled automatically.
- * two radio buttons for the search direction, Forward and Backward.
- * two radio buttons for specifying from which record the search should be started. First/last record will start the search from the first or last record depending on the search direction. Current record starts the search from the current record.
- * two buttons Search and Cancel for leaving the window.

After you have entered a search pattern and left the requester with the Search button MUIbase starts searching for a matching record. The comparison of an attribute field with the search pattern is always done string based, attribute fields of non-string types are therefore converted to strings first.

If a matching record is found, it is displayed as the current record in the table mask. Otherwise an Search pattern not found message appears.

If you search on an attribute that is used as the first attribute for ordering and your search pattern doesn't start with a joker (* or ?) then an improved search algorithm (binary search) is used that makes use of the record order. This can speed up the search drastically.

1.90 MUIbase/Forward-backward search

Forward/backward search
=====

Two further menu items allow to search for the next and the previous occurrence of the search pattern. Select menu item Table - Search forward for browsing to the next record that matches the search pattern, and Table - Search backward to go to the previous matching record.

1.91 MUIbase/Search pattern examples

Search pattern examples
=====

Here are some search pattern examples:

- * Lassie searches for records that have the string Lassie in one of the search attributes.
- * *x* searches for records that have the letter x in one of the search attributes.
- * ??? searches for records that have exactly three characters in one of the search attributes, e.g. a record with an entry UFO.

1.92 MUIbase/Import and Export

Import and Export

To share your records with other databases MUIbase offers a way to import and export records to and from other databases. Import and export is done by reading and writing ASCII files. Therefore the data you want to import must be in a special format described in the following section.

File format

How the format looks like.

Sample import file

An example.

Importing records

How to import records.

Exporting records

How to export records.

1.93 MUIbase/Import file format

File format

=====

For importing records into MUIbase all records of a table must be available in a single ASCII file. If you want to import records of several tables you must have several import files, one for each table.

An import file consists of lines and columns. Lines are separated by a record delimiter, columns by a field delimiter. The delimiters can be specified in the import and export requesters. As the record fields itself may already contain these delimiters it is possible to use double quotes around all fields to protect them.

The import file must have the following structure:

- * The first line contains the field names. For each name there must be an attribute with exactly the same name in the table where the records are imported to. If there is a name where no matching attribute can be found, an error message is generated.
- * The following lines contain one record each. As all fields must be given as ASCII strings they are automatically converted to the type of the destination attribute. For attributes of type boolean, the field must be either NIL or TRUE (case insensitive), otherwise an error message is generated. For attributes of type choice the exact label string must be specified (case sensitive). For reference attributes you have to specify the record number starting with 1. For all other types a value of NIL is used if the field cannot be converted to the required type.
- * If you decide to use double quotes then all record fields including the line with the field names must be surrounded by double quotes.

1.94 MUIbase/Sample import file

Sample import file

=====

The following sample import file uses \n and \t as record and field delimiter and double quotes around all fields. The file can be imported into a table with the following attributes:

- * Name (string)
- * NumChildrens (integer)
- * Feminine (bool)
- * Job (choice)
- * Notes (memo)

```
"Name" "NumChildrens" "Feminine" "Job" "Notes"
"Janet Jackson" "???" "TRUE" "Musician" "Latest CD: The velvet rope"
"Bernt Schiele" "???" "NIL" "Scientist" "Research interests:
Robotics, Autonomy and Computer Vision"
"Gerhard" "0" "NIL" "Precision mechanic" ""
```

1.95 MUIbase/Importing records

Importing records

=====

To import records into the active table select menu item Table - Import records. This will open a window containing

- * a string field for entering the import filename. Right to this field you find three buttons. Click on the first one to open a file requester for choosing the filename. The V button starts an external viewer to view the entered filename, and the E button starts an editor to edit the file contents.
- * two string fields for entering the record and field delimiter. You can enter a single character here or an escape code by typing \n, \t, \f, \??? (octal code), or \x?? (hex code).
- * a field Double quotes that can be checked to specify that the fields are surrounded by double quotes.
- * two buttons Import and Cancel for leaving the window.

If you press the Import button, MUIbase will load the specified file and import all found records. If everything is going fine, MUIbase will ask you after the import process if you really want to add the imported records to the table. At this point you can still cancel the operation.

If an error occurs while reading the import file then an error message is generated.

If you need a more sophisticated import routine it is recommended to write your own import routine as a MUIbase program.

1.96 MUIbase/Exporting records

Exporting records

=====

To export records from the active table select menu item Table - Export records. This will open a window containing

- * a string field for entering the export filename. Right to this field you find a pop-up button to open a file requester for choosing the filename.
- * two string fields for entering the record and field delimiter. You can enter a single character here or an escape code by typing \n, \t, \f, \??? (octal code), or \x?? (hex code).
- * a field Double quotes that can be checked to specify that the fields should be surrounded by double quotes.
- * a field Filter. If checked only the records that match the

currently installed record filter are written to the export file.

* two buttons Export and Cancel for leaving the window.

After you pressed the Export button, MUIbase will open the specified file and write out the records including a header line containing the attribute names. The export feature always writes all attribute fields of a table to the export file.

For a more customized export routine, you can use MUIbase' query editor (see

Data retrieval

) or you write your own export function as a

MUIbase program.

1.97 MUIbase/Data retrieval

Data retrieval

For data retrieval MUIbase offers two ways: the programming feature and the query editor.

The programming feature allows you to install buttons in table masks which, when pressed, call program functions. The usage of this feature is described in the structure editor chapter (see

Structure editor

)

and in the chapter about programming MUIbase (see

Programming MUIbase

).

This chapter describes the usage of the query editor, a requester where you can enter queries and view the output in a scrolling list-view.

Select-from-where queries

How a query looks like.

Query editor

How to enter and manage your queries.

Printing queries

Options when printing the result of a query.

Query examples

Some examples.

1.98 MUIbase/Select-from-where queries

Select-from-where queries

=====

MUIbase offers a select-from-where query similar to the one in SQL database systems. The query allows you to list the record contents from one or more tables. Only records matching certain criteria are included in the output. The (incomplete) syntax of an select-from-where query is

```
SELECT EXPRLIST FROM TABLELIST [WHERE TEST-EXPR]
[ORDER BY ORDERLIST]
```

where EXPRLIST is a comma separated list of expressions to be printed (usually the attribute names) or a simple star * matching all attributes of the specified tables, TABLELIST is a comma separated list of tables whose records are examined, TEST-EXPR is the expression that is tested for each set of records to be included in the output, and ORDERLIST is a comma separated list of attributes that defines the order for listing the output. Please note that the WHERE and ORDER BY fields are optional, denoted by the brackets [].

For example, the query

```
SELECT * FROM TABLE
```

lists the attribute contents of all records in the given table.

```
SELECT ATTR1 FROM TABLE WHERE (LIKE ATTR2 "*Madonna*")
```

lists the value of the ATTR1 field in all records of TABLE where the contents of field ATTR2 contain the word Madonna.

For more information about the select-from-where query including its full syntax, see

Programming MUIbase
, for more example see

Query examples

.

1.99 MUIbase/Query editor

Query editor

=====

For entering and running queries, open the query editor by choosing menu item Program - Queries. The query editor is able to manage several queries, however only one query is displayed at a time. The query editor window contains the following items:

- * a string input field with an attached pop-up button. The edit-able string field displays the name of the current query. By pressing the pop-up button, a list with further query names together with several buttons appear. You can select one of the listed queries to make it the current one, press the New button to create a new query, press the Duplicate button to get a copy of the activated query, click on the Sort button to sort the list of queries, or press the Delete button to delete the selected query. For leaving the pop-up window without changing anything, click on the pop-up button again.
- * a Run button that compiles and runs the query program and displays the output in the output list-view.
- * a Print button that opens a requester (see
 Printing queries
) for
printing the results.
- * two buttons Load and Save for loading and saving the current query program. If you save a query, the program text is written out in ASCII format and the first line holds the query name as a comment. The load function assumes the same format when reading a file. It is also possible to load and save queries by using the menu items in the context menu of the editor field for the query program. However, these menu items only save the program text and do not include the name of a query.
- * an editor field for entering the query program. Here you usually enter a select-from-where query. However, it is also possible to enter any expression of MUIbase' programming language. This can be useful if you want to do simple computations or update some fields of a table by using a simple program. Please note that MUIbase automatically surrounds your program expression with a pair of parenthesis, thus you can omit the outermost ones.
- * a list-view that displays the output after running the current query. The output is formatted into rows and columns. The title row holds the field names of the select-from-where query (usually the attribute names). The other rows hold the contents of the query result, one set of records per row. Each field entry is displayed in its own column. If you double click an entry in the list and this entry was generated by an attribute of type string or type reference then the selected record is displayed in the corresponding table mask. This is an easy way to jump to a certain record in a table mask.

The query editor is a non-modal requester. This means that you can leave the query editor open and still work with the rest of the application. You can close the query editor at any time by clicking on the close button in the window title bar.

1.100 MUIbase/Printing queries

Printing queries

=====

After you have run a query you can print the result to a file or printer by clicking on the Print button in the query editor. This will open a print requester containing the following items:

- * a field Delimiter where you specify how the columns should be separated. Spaces pads the fields with space characters. Padding is done on the left or on the right side depending on the type of the field (numbers are padded on the left, text on the right side). Tabs inserts exactly one tab character between the columns. This can be useful if you want to use the print requester for exporting records (see below).
 - * a field Font where you specify which font should be used for printing the output. NLQ stands for near letter quality which should print the output in better quality than Draft.
 - * a field Size where you define the character size. Pica prints in a large font (10 cpi), Elite in a medium font (12 cpi) and Condensed in a small font (17 cpi).
 - * a string field Init sequence where you can enter a string for initializing your printer. The contents of this field are written directly after opening the printer. For example you can use \33c as init sequence which resets your printer.
 - * a field Indent where you can enter a number of spaces that are used for indenting each output line.
 - * a field Headline that, if checked, prints the field names in the first line.
 - * a field Escape codes. If not checked the output of all escape codes is suppressed which means that the settings of the fields Font and Size are ignored and the contents of Init sequence are not printed. Suppressing the output of all escape codes is useful if you want to generate an ASCII file, e.g. for exporting records.
 - * a field Quotes that, if checked, surrounds all fields with double quotes.
 - * a field After printing where you can specify how the output should be finished. Form feed prints a form feed character \f. Line feeds prints a number of line feed characters \n. The number of line feeds can be entered in the string field to the right of the Line feeds button. Nothing doesn't write anything to the printer.
 - * a string field Output with an attached pop-up button. You can use the pop-up button to open a file requester for choosing a filename or directly enter the filename into the string field. For writing the output to your printer enter PRT:, for printing to a window enter CON:///MUIbase output/CLOSE/WAIT into the string field.
-

* two buttons Ok and Cancel for leaving the print requester.

After you are done with all settings, click on the Ok button to start the print job.

The print requester can also be used for exporting records to an ASCII file. To do this, specify Tabs in the Delimiter field, set the number of spaces in the Indent field to 0, check Headline, un-check Escape codes to suppress the font, size and init sequence settings, optionally check Quotes if you want the field contents to be surrounded by double quotes, check Nothing in the After printing field, and enter the output filename in the Output field. Using the query editor together with the print requester for exporting records can be much more powerful than using MUIbase' import/export feature (see

Import and Export

) since in the query editor any query can be entered whereas the export requester only uses a fixed query.

1.101 MUIbase/Query examples

Query examples

=====

To give you an impression of the power of the select-from-where queries this section gives you some sample queries.

Suppose we have two tables Person and Dog. Person has a string attribute Name, an integer attribute Age, and two reference attributes Father and Mother that refer to the father and mother records in table Person. The table contains the following records:

	Name	Age	Father	Mother
p1:	Steffen	26	p2	p3
p2:	Dieter	58	NIL	NIL
p3:	Marlies	56	NIL	NIL
p4:	Henning	57	NIL	NIL

Dog has a string attribute Name, a choice attribute Color and a reference attribute Owner that refers to the owner in the Person table. The table contains the following records:

	Name	Color	Owner
d1:	Boy	white	p3
d2:	Streuner	grey	NIL

Given these data the following sample select-from-where queries can be run:

```
SELECT * FROM Person
```


results to:

Name	Age	Father	Mother
Steffen	26	Dieter	Marlies
Dieter	58		
Marlies	56		
Henning	57		

(For the reference attributes the Name field of the referenced record is printed.)

```
SELECT Name "Child", Age,
       Father.Name "Father", Father.Age "Age",
       Mother.Name "Mother", Mother.Age "Age"
FROM Person WHERE (AND Father Mother)
```

results to:

Child	Age	Father	Age	Mother	Age
Steffen	26	Dieter	58	Marlies	56

```
SELECT Name, Color,
       (IF Owner Owner.Name "No owner") "Owner"
FROM Dogs
```

results to:

Name	Color	Owner
Boy	white	Marlies
Streuner	grey	No owner

```
SELECT a.Name, a.Age, b.Name, b.Age FROM Person a, Person b
WHERE (> a.Age b.Age)
```

results to:

a.Name	a.Age	b.Name	b.Age
Dieter	58	Steffen	26
Marlies	56	Steffen	26
Henning	57	Steffen	26
Dieter	58	Marlies	56
Henning	57	Marlies	56
Dieter	58	Henning	57

1.102 MUIbase/Structure editor

Structure editor

MUIbase has two different operating modes, the record-editing mode, where you enter and browse records, and the structure-editing mode where you define the structure, that is, the tables, attributes and appearance of a project. This chapter describes the structure editor and explains how to manage the structure of a project.

To switch from record-editing to structure-editing mode select menu item Structure editor in the Project menu. This will close all windows and open the structure editor window. To switch back to record-editing mode select menu item Project - Exit structure editor or simply close the structure editor by clicking on the close button in the window title bar.

The structure editor window is divided into three parts: in the upper left part there is a field Tables for managing the tables of the project, the lower left part is occupied by a field Attributes for managing the attributes of a table, and the right part is used by a field Display for managing the project's gui elements.

Table management

How to add, change and delete tables.

Attribute management

Adding, changing, and deleting attributes.

Display management

Managing the project's gui elements.

Print structure

Getting an overview of all tables and attributes.

1.103 MUIbase/Table management

Table management

=====

In the Tables field of the structure editor you can create, change, delete and sort tables.

Creating tables

How to add a table.

Changing tables

How to modify a table.

Deleting tables

How to remove a table.

Sorting tables

How to order the list of tables.

1.104 MUIbase/Creating tables

Creating tables

To create a new table press the New button in the Tables field. This will open the New table requester containing

- * a string field for entering the name of the table. Each table must have a unique name that starts with an uppercase letter followed by further letters, digits or underscore characters. Non-ASCII characters like German umlauts are not allowed. Please note that in the user interface for the table it is still possible to display any strings including strings with non-ASCII characters.

- * a field Number of records where you specify how many records the table is going to hold. Unlimited means that the table can hold any number of records, Exactly one means that the table can have only one record. The latter one is sometimes useful for controlling the project (see
Tables
).

- * a field Trigger functions where you can enter the names of two functions. In the New string field you enter the name of the function that should be called whenever the user wants to create a new record, the Delete string field holds the name of the function that should be called whenever the user wants to delete a record. You can use the pop-up buttons to the right of the string fields for choosing a function name from a list of all names. If you leave a field empty then default actions are executed (records are created automatically and records are deleted after an optional safety requester). For more information on how to use the trigger functions, including the arguments that are passed to them, see

Programming MUIbase

.

- * two buttons Ok and Cancel for leaving the requester.

When you are done with all settings, press the Ok button to create the new table. If you made an error somewhere, e.g. you entered an invalid name, a message window pops up giving you more information about the error you did. If everything goes fine, the New table requester will be closed and the new table is displayed in the structure editor's table list.

1.105 MUIbase/Changing tables

Changing tables

After you have created a new table you can still change it. Just double-click on the table's name and the Change table requester pops up. This requester is similar to the one when creating a table (see

Creating tables
) and allows you to make changes in any field by entering a new value.

When you are done with all changes, press the Ok button to leave the requester.

Please note that you can't change the number of records from Unlimited to Exactly one if the table already contains more than one record.

1.106 MUIbase/Deleting tables

Deleting tables

To delete a table, click on the table's name in the structure editor's table list, then press the Del button below the list. Before the table is actually deleted a safety requester pops up asking for confirmation. If you confirm this requester by pressing the Delete button, the table is deleted.

A problem occurs if the table is used somewhere in the project's program. In this case the table can't simply be deleted but all references to the table must be removed from the program. If the table you want to delete is used in the project's program then the program editor pops up and displays the first occurrence to the table. You should now modify the program such that no references to this table remain in the program. After you removed a reference you can jump to the next one by pressing the Compile button. At any point you can still cancel the whole operation by pressing the Undo button and closing the program editor.

1.107 MUIbase/Sorting tables

Sorting tables

For sorting the tables in the Tables field of the structure editor you have two choices. You can either order them by hand, that is, you

use drag & drop to rearrange a table, or you use the Sort button below the list-view which orders the tables alphabetically.

1.108 MUIbase/Attribute management

Attribute management

=====

In the Attributes field of the structure editor you can create, change, delete and sort the attributes of the active table in the Tables field.

Creating attributes

How to add an attribute.

Type specific settings

Settings depending on the type of an attribute.

Label editor

Specifying label strings, e.g. for choice attributes.

Changing attributes

How to modify an attribute.

Deleting attributes

How to remove an attribute.

Sorting attributes

How to order the list of attributes.

1.109 MUIbase/Creating attributes

Creating attributes

To create a new attribute for the active table press the New button in the Attribute field. This will open the New attribute requester containing

- * a string field for entering the name of the attribute. Each attribute in a table must have a unique name that starts with an uppercase letter followed by further letters, digits or underscore characters. Non-ASCII characters like German umlauts are not allowed. Please note that in the user interface it is still possible to display any strings including strings with non-ASCII characters for the attribute.

- * a choice field Type where you specify the type of the attribute. For more information on attribute types, see
Attribute types
.
- * a section below the Type field for specifying type specific settings. For more information about this section, see
Type specific settings
.
- * a field Trigger where you can enter the name of a function that should be called whenever the user wants to change the contents of the attribute field in a record. You can use the pop-up button to the right of the string field for choosing a name from a list of all function names. If you leave the field empty then a default action is executed, that is, the entered value is simply stored in the attribute field. For more information on how to use the trigger function, including the arguments that are passed to it, see
Programming MUIbase
.
- * two buttons Ok and Cancel for leaving the requester.

When you are done with all settings, press the Ok button to create the new attribute. If you made an error somewhere, e.g. you entered an invalid name, a message window pops up giving you more information about the error you did. If everything goes fine, the New attribute requester will be closed and the new attribute is displayed in the structure editor's attribute list.

1.110 MUIbase/Type specific settings

Type specific settings

In the type specific section the following settings can be specified:

- * For attributes of type string you have
 - an integer field Max length for entering the maximum string length for this attribute field.
 - a string field Initial value for specifying the value that is used for initializing the attribute field. Any string up to the specified maximum length can be entered here.
 - * For attributes of type integer, real, date, and time the type specific section offers
 - a field Initial value where you specify the value for initializing the attribute field. You can choose between NIL
-

and other. If you select other then you should enter the initial value into the string field to the right of other.

- a string field NIL string where you enter the string that should be displayed when the attribute field holds the NIL value.
- * For bool attributes the type specific section contains a field Initial value where you can choose between NIL and TRUE for the initial value.
- * The type specific section for choice attributes offers
 - a button Edit labels for opening the Edit labels window where you can enter the label strings for the choice field (see
 - Label editor
 -).
 - a choice field Initial value for specifying the value for initializing the attribute field.
- * For reference attributes the type specific section contains
 - a list-view displaying all tables for specifying to which table the reference should be made. Click on the table the attribute is going to reference.
 - a field Filter. If checked the reference filter of this attribute is turned on. See
 - Reference filter
 - , for more
 information about this feature.

Reference attributes always have the NIL value as initial value.

- * The type specific section for virtual attributes contains a string field Compute where you enter the name of a function that should be called for calculating the value of the attribute. You can use the attached pop-up button for selecting a name from a list of all function names.
- * Memo and button attributes do not have any type specific settings. The initial value for memo attributes is an empty string.

1.111 MUIbase/Label editor

Label editor

Whenever you have to define a list of labels, e.g. the list of labels for a choice attribute, the label editor comes into place. The label editor is a window containing:

- * a list-view displaying the current list of labels. You can click on a label to make it the active one. The active label is also displayed in the string field below the list-view. You can use drag & drop to rearrange the labels.
- * a string field Label that displays the active label and allows changing it. The changes do only have effect after you pressed the Return key. If there is currently no active label then pressing Return inserts new labels into the list.
- * a button New that deactivates the current label which allows entering new labels into the Label string field.
- * a button Remove that removes the active label from the list.
- * a button Sort for ordering the list of labels alphabetically.
- * two buttons Ok and Cancel for leaving the label editor.

After you entered all labels or made changes to them, press the Ok button to leave the window.

1.112 MUIbase/Changing attributes

Changing attributes

After you have created a new attribute it is still possible to change some settings of it. Just double-click on the attribute's name and the Change attribute requester pops up. This requester is similar to the one when creating an attribute (see

Creating attributes
) and allows

you to make changes in some fields. The fields that cannot be changed, e.g. the attribute type, are displayed ghosted.

The following notes should be taken into account when changing the an attribute.

- * The type of an attribute cannot be changed. If you ever want to change the type of an attribute, it is best to create a new one of the desired type and copy the record contents from the old attribute to the new one by entering a simple MUIbase program in the query editor (see

Query editor
)
 - * If you change the initial value of an attribute then only new records will get the new value for initializing the record.
 - * For choice attributes you should be careful when changing its labels. The labels are only used for displaying the choice field contents, internally, numbers are stored that are used as an index
-

into the list of labels. Thus, if you change the order of labels, you actually don't change the internal number but the label which is displayed for it! Therefore you should not change the order of labels after you created a choice attribute. Appending new labels to the end of the label list, however, doesn't make any problems. For a more flexible way of having a choice-like field where you can also change the order of labels, use a string attribute together with the List-view pop-up feature (see

Attribute object editor
).

* The referenced table of a reference attribute cannot be changed.

When you are done with all changes, press the Ok button to leave the requester.

1.113 MUIbase/Deleting attributes

Deleting attributes

To delete an attribute, click on it's name in the structure editor's attribute list and press the Del button below the list. Before the attribute is actually deleted a safety requester pops up asking for confirmation. If you confirm this requester by pressing the Delete button, the attribute is deleted.

A problem occurs if the attribute is used somewhere in the project's program. In this case the attribute can't simply be deleted but all references to it must be removed from the program. If the attribute you want to delete is used in the project's program then the program editor pops up and displays the first occurrence to this attribute. You should now modify the program such that no references to this attribute remain in the program. After you removed a reference you can jump to the next one by pressing the Compile button. At any point you can still cancel the whole operation by pressing the Undo button and closing the program editor.

1.114 MUIbase/Sorting attributes

Sorting attributes

For sorting the attributes in the Attributes field of the structure editor you have two choices. You can either order them by hand, that is, you use drag & drop to rearrange an attribute, or you use the Sort button below the list-view which orders the attributes alphabetically.

1.115 MUIbase/Display management

Display management

=====

In the Display field of the structure editor you specify how the database elements should be arranged in the user interface. The field consists of a choice field, a list-view and several buttons.

Display field
Overview of the elements in the display field.

Panel editor
Settings for a panel object.

Attribute object editor
Settings for an attribute object.

Text editor
Settings for a text object.

Image editor
Settings for an image object.

Space editor
Settings for a space object.

Group editor
Settings for a group object.

Register group editor
Settings for a register group object.

Window editor
Settings for a window object.

1.116 MUIbase/Display field

Display field

The display field contains the following items:

- * a choice item with two settings, Table mask and Root window. In Table mask you specify how the attributes of the active table are arranged in the user interface. In Root window you specify how the tables are arranged.
- * a list-view that displays the current specification of the user interface. The list is organized as a tree. Items that have an

arrow to its left are composite gui objects and can be opened and closed by double-clicking on the arrow symbol. A double-click on the item itself opens a window for editing its settings. All gui objects that have the same parent object are layed out in the same way (either vertically or horizontally). How the layout is done is determined by the parent gui object: tables, panels and windows layout their elements vertically, groups layout their elements according to the settings in the group editor (see Group editor).

- * a button Panel for adding a panel to the table. See

Panel editor
, for more information about setting up a panel.

- * a button Add for adding the active table or the active attribute (depending on the state of the display choice field) to the display list-view. Usually tables and attributes are added to the display list-view automatically when you create them.

- * a button Rem for removing the active item from the display list-view. If you remove a table then the whole table form is removed from the user interface, thus you can't see the table in the project's gui. If you remove an attribute from the display list-view then the attribute doesn't appear in the project's gui. This is useful for hiding attributes.

- * two buttons Up and Down for moving the active item one field up, respectively down, in the display list-view.

- * two buttons In and Out for moving the active item one hierarchical level down or up in the display list-view.

- * a button Text for adding a text object to the display list-view. See

Text editor
, for more information about setting up a text object.

- * a button Image for adding an image object (see Image editor).

- * a button Space for putting space between the other objects (see

Space editor

- * a button Balance for adding a balance object to the display list-view. The balance object is useful for controlling the size of the other gui objects.

- * a button Group for adding a group object to the display list-view. Before you press the Group button you can multi-select the items in the list-view that should be moved into the new group. See

Group editor
 , for more information about setting up a group
 object.

- * a button Window for adding a new window to the display list-view. As for group objects, you can multi-select the gui objects that should be moved into the new window. For more information about setting up a window, see
 Window editor
 .

For more information about the gui elements, including their usage,
 see

User interface
 .

1.117 MUIbase/Panel editor

Panel editor

When you add a panel to a table's mask, or when you double click an existing panel object in the display list-view, the Panel window pops up. This window contains the following items:

- * a string field Title for entering a title that should be displayed in the panel header.
- * a string field Font with a pop-up button for selecting a font for the title. If you leave the field empty, a default font is used.
- * a field Background with a check-mark field Default for specifying the background of the panel header. If you check the Default field then a default background is chosen. Otherwise you can click on the Background button to open a window for specifying the background setting (see the MUI docs for a description of this window).
- * a field Num/All. If checked the number of the current record and the number of all records are displayed in the right part of the panel header.
- * a field Filter that, if checked, adds a filter button to the panel header. With the filter button you can turn on and off the record filter of the table. If you don't check this field then the menu item Table - Change filter will also be disabled for this table, thus you can't enter a filter expression for the table. For more information about record filters, see
 Record filter
 .
- * a field Arrows for adding two arrow buttons to the table mask. The arrow buttons allows you to browse through the records of the

table. If you don't check this field then you can't browse the records of this table and all sub menu items of menu item Goto record and the menu items Search for, Search forward, and Search backward in menu Table are disabled.

- * two buttons Ok and Cancel for leaving the window.

After you are done with all settings, click on the Ok button to close the window.

1.118 MUIbase/Attribute object editor

Attribute object editor

When you add an attribute to the display list-view, a default gui object is created for it. To change the settings of the attribute object, double click on it and the Display attribute window is opened. This window contains several items depending on the type of the attribute. The following items are included for most attribute types:

- * a string field Title for entering a title that is displayed near the attribute object (or, for buttons, in the object itself). If you leave this field empty then no title is displayed.
 - * a choice field Title position for specifying where the title (if any) is placed relative to the attribute object. You can choose between Left, Right, Top, and Bottom.
 - * a string field Shortcut for entering a letter than can be used together with the Amiga key to activate the object.
 - * a field Home. If checked, this attribute object becomes the home object. The home object is used as the object where the cursor is set on whenever a new record is allocated. This is quite useful if you always want to start entering data into the same attribute whenever you create a new record. If you mark an attribute object as the home object then all other attribute objects in the same table are unmarked.
 - * a field Read only that, if checked, gives the object a read only status. This means that you can only read its contents but can't edit them. If you check this field then the settings of the fields Shortcut and Home are ignored.
 - * a choice field Format for specifying how the attribute contents should be presented in the object. You can choose between Center, Left and Right for displaying the contents centered, flushed left, or flushed right.
 - * a numerical field Weight for specifying the weight of the object. The value of this field determines how much space, relatively to the other objects, the object gets in the final window layout.
-

Usually the value of this field only affects the horizontal size of the object as the vertical one is fixed for most attribute types.

- * a field Font for selecting the font used for displaying the attribute contents. If you leave the field empty, a default font is used.
- * a field Background with a check-mark field Default for specifying how the background of the attribute should look like. If you check the Default field then a default background is used, otherwise you can click on the Background field to open a window for specifying the background settings (see the MUI docs for a description of this window).
- * an editor field Bubble help where you can enter text that should be displayed as the bubble help information for this attribute object.
- * two buttons Ok and Cancel for leaving the window.

If you are done with all settings, press the Ok button to leave the window.

Type specific settings

Besides the above items, the following type-specific items are present:

- * for attributes of type string there is an Extras page which contains:
 - a field Display picture that, if checked, attaches an image field to the string attribute for displaying the image whose filename is taken from the attribute contents. The image field is put above the string field. If you don't check this item then the settings of the fields Title at string field, Hide string field, and Size are meaningless.
 - a field Title at string field. If checked, the title of the attribute object is placed to the left of the string field, thus the image field gets more space in the window. If you don't check this field then the title is placed to the left of the image field.
 - a field Hide string field for removing the string field from the user interface. If checked, only the image field is displayed.
 - a field Size for specifying how size-handling is done for the image area. If Resize-able is active then the object can be resized and the object can become larger than the size of its image. Fixed sets the object's size to the size of the image. If the image sizes vary from record to record then the object is resized accordingly. Scroll-able adds two scrollers to the object allowing to view images that are larger than the

visible region. If Scaled is activated then the image is scaled to the size of the display object.

- a field File pop-up that, if checked, adds a pop-up button to the right of the string field. This buttons serves to open a file requester for choosing a filename.
- a field Font pop-up for adding a pop-up button that opens a font requester. This feature has been added according to a suggestion from Ralphie. Blame him if you find this feature useless. :-)
- a field List-view pop-up. If checked, a pop-up button is attached to the right of the string field for opening a list-view pop-up where you can choose a string from a list of strings. The list of strings can be specified in the label editor which is opened after pressing the Edit labels button to the right of the List-view pop-up field. For more information about the label editor, see
Label editor
.

Only one of the fields File pop-up, Font pop-up and List-view pop-up can be made active (MUI programmers know why).

- a field View that, if checked, adds a button to the right of the string field for launching an external viewer with the attribute contents as argument. This can be useful if you store filenames in the attribute and want to display the contents of a file by starting an external viewer. The external viewer can be specified in menu item Preferences - External viewer (see
External viewer
).
 - * for attributes of type choice there is a field Kind where you choose whether the attribute contents should be displayed by a Cycle button or by a set of Radio buttons. If you select Cycle button then you can set the title position to one of Left, Right, Top, or Bottom. If you select Radio buttons then two check mark items Frame and Horizontal allow drawing a border around the radio buttons and the specification of an horizontal layout.
 - * for attributes of type real there is an integer field Num decimals where you can enter the number of decimals for displaying the floating point values.
 - * for reference attributes there is an Extras page that contains the following items:
 - a list-view field Contents where you specify which contents of a referenced record should be displayed. You can multi-select several items in this list. If you select Record number then the record number of a referenced record is included in the display. The other items are the names of attributes in the referenced table.
-

- a text field `Items selected` that displays how many items have been selected in the above list-view.
- a field `Show`. If checked then the gui object for displaying the reference is created as a button. Clicking on this button will show you the referenced record in the table mask of the referenced table.
- a field `Filter` that, if checked, adds a button to the right of the reference field for turning on and off the reference filter for this attribute. See `Reference filter`, for more information about reference filters.

* for virtual attributes the attribute object editor contains:

- a choice field `Kind` where you specify how the contents of the virtual attribute should be displayed. You can choose between `Bool` that uses a check-mark field for displaying boolean values, `Text` that uses a text field for displaying one line of text (including date, time, and numerical values), and `List` which uses a list-view for displaying a list of lines (e.g. the result of a select-from-where query).
- if you set the `Kind` field to `Text` then two further fields are available: `Format` for specifying how the attribute contents should be presented and `Num decimals` for entering the number of decimals that should be used if the attribute contents are of type real.
- if the `Kind` field has been set to `List` then a field `Show titles` is available. If checked, the first line of the attribute contents is displayed as a title row in the list-view. Otherwise no title row is displayed and the first line is ignored.
- a field `Immediate` that, if checked, causes the virtual attribute to recompute its value whenever you switch the active record to another one. If not checked then the value of the virtual attribute is only computed when a MUIbase program needs its value, e.g. when you have installed a button somewhere in the user interface that reads the value of the virtual attribute when the button is pressed.

* For buttons there are the following additional fields:

- a choice field `Kind` where you choose between `Text button` and `Image button`.
 - if you set the button kind to `Text button` then further fields `Title`, `Font`, `Background` and `Default` appear for entering the text to be displayed in the button, the font used for displaying the text, and the background settings.
 - if the button kind has been set to `Image button` then a field `Image` for specifying the image to be displayed and a field
-

Size for specifying the size-handling of the image button are offered.

1.119 MUIbase/Text editor

Text editor

When you add a text object to the display list-view, or when you change one by double clicking on it, a window Text is opened. This window contains the following items:

- * a string field Title for entering the text that should be displayed.
- * a numerical field Weight for specifying the horizontal weight of the text object.
- * a choice field Font for specifying the font of the text. If you leave this field empty, a default font is used.
- * two fields Background and Default for specifying the background settings of the text object.
- * two buttons Ok and Cancel for leaving the window.

When you are done with all settings, press the Ok button to leave the window.

1.120 MUIbase/Image editor

Image editor

The image editor appears when you add a new image object or double click on an existing one. It contains the following items:

- * a field Weight for specifying the weight of the image object in the final window layout.
- * a field Image for specifying the image that should be displayed.
- * a field Size where you specify how resize-handling should be done. If you select Resize-able then the image object can be resized. Fixed sets the object size to the size of the displayed image.
- * two buttons Ok and Cancel for leaving the window.

When you are done with all settings, click on the Ok button to close

the window.

1.121 MUIbase/Space editor

Space editor

After you have added a space object to the display list-view, you can change its default settings by double clicking on it. This will open the Space window containing the following items:

- * a field Delimiter that, if checked, displays a vertical or horizontal bar (depending on the layout of the parent object) in the center of the space object. This is useful for separating parts in the window layout.
- * a numerical field Weight for specifying the weight of the object.
- * two fields Background and Default for specifying the background settings.
- * two buttons Ok and Cancel for leaving the window.

After you are done with all settings, press the Ok button to close the window.

1.122 MUIbase/Group editor

Group editor

After you have added a group object to the display list-view, you can change its settings by double clicking on it. This will open the Group window offering the following items:

- * a string field Title for entering a title string that should be displayed centered above the group. If you leave this field empty then no title is displayed.
 - * a numerical field Weight for specifying the weight of this object.
 - * two fields Background and Default for specifying the background settings.
 - * a field Border that, if activated, draws a border frame around the group.
 - * a field Horizontal. If checked, the layout of the group is done horizontally and the group is listed in the display list-view as HGroup. Otherwise the group is organized vertically and the
-

display list-view will show a VGroup for this group.

- * a field Spacing that, if checked, adds some space between the group's child objects. Otherwise no space is put between the objects.
- * two buttons Ok and Cancel for leaving the window.

When you are done with all settings, press the Ok button to leave the window.

1.123 MUIbase/Register group editor

Register group editor

Double click on a register group object in order to change its settings. This will open the Register group window offering the following items:

- * a numerical field Weight for specifying the weight of this object.
- * two fields Background and Default for specifying the background settings.
- * an area Labels for specifying the label of each register page. You should specify exactly the same number of labels as there are elements in the register group. For more information on how to enter and edit the labels, see
 Label editor
 .
- * two buttons Ok and Cancel for leaving the window.

When you are done with all settings, press the Ok button to leave the window.

1.124 MUIbase/Window editor

Window editor

To change the settings of a window object, double click on it. This will open the window editor containing the following items:

- * a string field Title where you enter a string that should be displayed in the window title bar and in the window button.
 - * a string field Shortcut where you enter the shortcut for
-

activating the window button.

- * a numerical field Weight for specifying the weight of the window button.
- * a field Font for selecting the font of the window button. If you leave the field empty, a default font is used.
- * two fields Background and Default for specifying the background settings of the window button.
- * a field Disabled that, if checked, creates the window button with a disabled state, that is, you can't click on it and therefore cannot use it to open or close the window. This can be useful if you don't want the user to open windows by himself but want to open them from within a MUIbase program.
- * two buttons Ok and Cancel for leaving the window.

When you are done with all settings, press the Ok button to close the window.

1.125 MUIbase/Print structure

Print structure
=====

Sometimes it is useful to get an overview of all tables and attributes of a project, e.g. when you want to write a MUIbase program. You can do this by selecting menu item Project - Print structure. This will ask you for a filename where the list of tables and attributes should be written to.

The output will first list the project name, followed by all tables in this project. For each table all attributes including their types are listed.

1.126 MUIbase/Programming MUIbase

Programming MUIbase

This chapter describes the programming language of MUIbase, including all available functions. This chapter, however, is not intended as a general guide about programming. You should be familiar with the basics about programming and should already have written some small programs.

Program editor
Where to enter a MUIbase program.

Preprocessing
Includes, conditional compilation, and constants.

Programming language
The syntax of expressions.

Functions

Defining commands
Function and variable definitions.

Program control functions
Loops, conditional expressions, and more.

Type predicates
Examining the type of an expression.

Type conversion functions
Converting types.

Boolean functions
AND, OR, and NOT.

Comparison functions
Comparing values of expressions.

Mathematical functions
Adding, Multiplying, etc.

String functions
Useful stuff for strings.

Memo functions
Useful stuff for memos.

List functions
List processing commands.

Input requesting functions
Asking the user for input.

I-O functions
File input and output commands.

Record functions
Useful stuff for records.

Attribute functions
Manipulating attributes.

Table functions
Manipulating tables.

Gui functions
Manipulating the user interface.

Project functions
Getting information about the project.

System functions
Operating system related functions.

Variables
Pre-defined variables.

Constants
Pre-defined constant values.

Useful information

Functional parameters
Using functions as arguments in function calls.

Type specifiers
Types for local variables.

Semantics of expressions
The meaning of an expression.

Function triggering
How to use trigger functions.

Function index
Index of all functions.

1.127 MUIbase/Program editor

Program editor

=====

To enter a program for a project, open the program editor by selecting menu item Program - Edit. This will open the Edit program window containing:

- * a text editor field where you edit the project program.
 - * a button Compile & close for compiling the program and, on successful compilation, leaving the program editor.
 - * a button Compile to compile the program. If your program contains an error somewhere then an error description is put into the window title and the cursor is set on the faulty location.
 - * a button Undo that undos all changes since the last successful
-

compilation.

The program editor is an asynchronous requester. You can leave the window open and still work with the rest of the application. You can close the editor at any time by clicking into its window close button. If you have done changes since the last successful compilation then a safety requester pops-up asking for confirmation to close the window.

You can also compile a project's program without opening the program editor by choosing menu item Program - Compile. This can be useful if you e.g. do changes to an external include file and want to incorporate these changes in the project's program.

1.128 MUIbase/Preprocessing

Preprocessing

=====

MUIbase programs are pre-processed similar to a C compiler preprocessing a C source file. This section describes how to use the preprocessing directives.

All directives start with a hash symbol # which should be the first character on a line. Space or tab characters can appear after the initial #.

```
#define
    Defining constants.

#undef
    Un-defining constants.

#include
    Including external files.

#if
    Conditional compilation.

#ifdef
    Conditional compilation.

#ifndef
    Conditional compilation.

#elif
    Conditional compilation.

#else
    Conditional compilation.

#endif
    Conditional compilation.
```

1.129 MUIbase/#define

#define

#define NAME STRING

Defines a new symbol with the given name and contents. The symbol STRING can be any text including spaces and ends at the end of line. If STRING does not fit on one line you can use further lines by using a backslash character \ at the end of each line (except for the last one). If the symbol NAME does occur in the remaining source code then it will be replaced by the contents of STRING.

Example: (PRINTF "X is %i" X) prints X is 1 (Occurrences of NAME in strings are not altered.)

The replacement of defined symbols is done syntactically which means that you can replace symbols with any text, e.g. you can define your own syntax like in the following example:

```
#define BEGIN (
#define END )

BEGIN defun test ()
    ...
END
```

The replacement string of a definition may contain another symbol that has been defined with the #define directive to allow nested definitions. However there is an upper limit of 16 nested definitions.

See also

```
#undef
,
#define
,
#ifndef
.
```

1.130 MUIbase/#undef

#undef

#undef NAME

Removes the definition of symbol NAME. If NAME has not been defined, nothing happens.

See also

```
#define
,
#ifdef
,
#endif
.
```

1.131 MUIbase/#include

```
#include
```

```
#include FILENAME
```

Reads in the contents of FILENAME (a string surrounded with double quotes) at this location. MUIbase searches in the current directory and in the directory specified in the preferences (see

```
Program include directory
) for loading the file. The file contents
are processed by the compiler as if they were part of the current
source code.
```

An external file may include one or more other external files. However there is a limit of 16 nested #include directives. To protect files from including them more than once, you can use conditional compilation.

Be careful when moving source code to external files! Debugging and tracking down errors is much harder for external files. Move only well tested and project independent code to external files.

1.132 MUIbase/#if

```
#if
```

```
#if CONST-EXPR
```

If the given constant expression results to non-NIL then the text up to the matching #else, #elif, or #endif is used for compilation, otherwise (the expression results to NIL) the text up to the matching #else, #elif, or #endif is discarded for compilation.

Currently you can only use TRUE and NIL as constant expressions.

See also

```
#ifdef
,
#endif
,
#elif
,
#else
,
#endif
.
```

1.133 MUIbase/#ifdef

```
-----
#ifdef
```

```
#ifdef NAME
```

If the given symbol has been defined with a #define directive then the text up to the matching #else, #elif, or #endif is used for compilation, otherwise it is discarded.

See also

```
#if
,
#endif
,
#elif
,
#else
,
#endif
.
```

1.134 MUIbase/#ifndef

```
-----
#ifndef
```

```
#ifndef NAME
```

If the given symbol has not been defined with a #define directive then the text up to the matching #else, #elif, or #endif is used for compilation, otherwise it is discarded.

See also

```
#if
,
#ifdef
,
#elif
,
#else
,
#endif
.
```

1.135 MUIbase/#elif

```
#elif
```

```
#elif CONST-EXPR
```

Any number of #elif directives may appear between an #if, #ifdef, or #ifndef directive and a matching #else or #endif directive. The lines following the #elif directive are used for compilation only if all of the following conditions hold:

- * The constant expression in the preceding #if directive evaluated to NIL, the symbol name in the preceding #ifdef is not defined, or the symbol name in the preceding #ifndef directive was defined.
- * The constant expression in all intervening #elif directives evaluated to NIL.
- * The current constant expression evaluates to non-NIL.

If the above conditions hold then subsequent #elif and #else directives are ignored up to the matching #endif.

See also

```
#if
,
#ifdef
,
#ifndef
,
#else
,
#endif
.
```

1.136 MUIbase/#else

```
-----
                #else
```

```
                #else
```

This inverts the sense of the conditional directive otherwise in effect. If the preceding conditional would indicate that lines are to be included, then lines between the #else and the matching #endif are ignored. If the preceding conditional indicates that lines would be ignored, subsequent lines are included for compilation.

Conditional directives and corresponding #else directives can be nested. However there is a maximum nesting count limit of 16 nested conditional directives

See also

```
                #if
                ,
                #ifdef
                ,
                #ifndef
                ,
                #elif
                ,
                #endif
                .
```

1.137 MUIbase/#endif

```
-----
                #endif
```

```
                #endif
```

Ends a section of lines begun by one of the conditional directives #if, #ifdef, or #ifndef. Each such directive must have a matching #endif.

See also

```
                #if
                ,
                #ifdef
                ,
                #ifndef
                ,
                #elif
                ,
                #else
                .
```

1.138 MUIbase/Programming language

Programming language

=====

MUIbase uses a programming language with a lisp-like syntax. Indeed several constructs and functions have been adopted from standard lisp. However, MUIbase is not fully compatible to standard lisp. Many functions are missing (e.g. destructive commands) and the meaning of some commands is different (e.g. the return command).

Why lisp?

The advantages of lisp.

Lisp syntax

Syntax of programming language.

Kinds of programs

Different kinds of programs used in MUIbase.

Name conventions

Name conventions for program symbols.

Accessing record contents

Using attributes and tables in programs.

Data types for programming

Available data types for programming.

Constants

Constant expressions.

Command syntax

Syntax for describing all commands.

1.139 MUIbase/Why lisp?

Why lisp?

The advantage of a lisp-like language is that you can program in both, a functional and an imperative way. Functional languages are getting quite popular in mathematical applications. The basic concept in functional languages is the use of expressions. Functions are defined in a mathematical way and recursion is used heavily.

Imperative programming languages (e.g. C, Pascal, Modula) use an imperative description on how to compute things. Here, the state is the basic concept (e.g. variables) and a program computes its output by going from one state to another (e.g. by assigning values to variables).

Lisp combines both techniques and therefore you can choose in which way you want to implement things. Use the one which is more appropriate for the specific problem or which you like more.

1.140 MUIbase/Lisp syntax

Lisp syntax

A lisp expression is either a constant, a variable, or a function application. For calling functions, lisp uses a prefix notation. The function and its arguments are surrounded by parenthesis. For example, to add two values a and b, you write

```
(+ a b)
```

All expressions return a value, e.g. in the above example the sum of a and b returned. Expressions can be nested, that is, you can place an expression as a sub-expression into another one.

Function evaluation is done by using a call-by-value scheme, this means that the arguments are evaluated first before a function is called.

If not stated otherwise, all functions are strict, that is, all arguments of a function are evaluated before the function is called. Some functions, however, are non-strict, e.g. IF, AND and OR. These functions may not evaluate all arguments.

1.141 MUIbase/Kinds of programs

Kinds of programs

MUIbase knows three kinds of programs. The first one is the project program kind. In a program of this kind you can define functions and global variables. The functions can be used as trigger functions for attributes. You define a project program in the program editor (see

```
Program editor  
)
```

The second kind is the query program kind. For this kind you can enter expressions only. An expression is allowed to contain global variables and calls to functions that are defined in the project

program. However, you cannot define new global variables or functions in a query program. Query programs are entered in the query editor (see

Query editor
).

The third kind of programs are filter expressions. Here you can only enter expressions that contain calls to pre-defined MUIbase functions. Not all pre-defined functions are available, only those that don't have a side effect, e.g. you cannot use a function that writes data to a file. Filter expressions are entered in the change filter requester (see

Changing filters
).

1.142 MUIbase/Name conventions

Name conventions

In a MUIbase program you can define symbols like functions and local or global variables. The names of these symbols must follow the following conventions:

- * the first character of a name must be a lowercase letter. This distinguishes program symbols from table and attribute names.
- * The following characters can be any letters, digits or underscore characters. Other characters like German umlauts are not allowed.

1.143 MUIbase/Accessing record contents

Accessing record contents

To access tables and attributes in a MUIbase program, you have to specify a path to them. A path is a dot separated list of components where each component is the name of a table or an attribute.

Paths can either be relative or absolute. Absolute paths are specified with a table name as the first component, followed by a list of attributes that lead to the final attribute you want to access. E.g. the absolute path `Person.Name` accesses the `Name` attribute in the current record of table `Person`, or the absolute path `Person.Father.Name` accesses the `Name` attribute in the record referenced by the `Father` field (a reference attribute to table `Person`).

Relative paths already have a current table to which they are relative. For example in a filter expression the current table is the

table for which you write the filter expression. The relative path for an attribute in the current table is simply the attribute name itself. For attributes that are not directly accessible from the current table but indirectly via a reference attribute, the same rules as for absolute paths apply.

It is not always clear if a specified path is a relative or an absolute one, e.g. suppose you are writing a filter expression for a table Foo that has an attribute Bar and there also exists a table Bar. Now entering Bar would be ambiguous, what is meant, the table or the attribute? Therefore all paths are first treated as relative ones. If no attribute is found for the specified path than the path is treated as global. In our example the attribute would be preferred.

But now, what if you want to access the table in the above example? Therefore the path must be given absolute. To indicate that a path is global you have to insert two colons in front of the path. In our example you would have to type `::Bar` for accessing the table.

To give you a better understanding of paths and their semantics, consider in our example that the Bar attribute in the Foo table is a reference to the Bar table, and the Bar table has an attribute Name. Now you can access the Name attribute by typing `Bar.Name` or `::Bar.Name`. Both expressions have a different meaning. `::Bar.Name` means to take the current record of table Bar and return the value of the Name attribute of this record, whereas `Bar.Name` takes the current record of table Foo, extracts the record reference of the Bar field and uses this record for getting the value of the Name attribute.

To make a more complete example, consider that table Bar has two records. One that contains Mats and one that contains Steffen in the Name field. The first record should be the current one. Furthermore table Foo has one record (the current one) whose Bar field refers to the second record of table Bar. Now `::Bar.Name` results to Mats and `Bar.Name` to Steffen.

1.144 MUIbase/Data types for programming

Data types for programming

The programming language of MUIbase knows of the following data types:

Type	Description
Bool	all expressions. Non-NIL expressions are treated as TRUE.
Integer	long integer, 32 bit, choice values are automatically converted to integers
Real	double, 64 bit
String	strings of arbitrary length

Memo	like strings but line oriented format
Date	date values
Time	time values
Record	pointer to a record
File	file descriptor for reading/writing
List	list of items, NIL is empty list.

All programming types support the NIL value.

1.145 MUIbase/Constants

Constants

The programming language of MUIbase can handle constant expressions which can be entered depending on the type of the expression:

Type	Description																						
Integer	Integer constants in the range of -2147483648 to 2147483647 can be specified as usual.																						
Real	Floating point constants in the range of -3.59e308 to 3.59e308 can be specified as usual, in scientific or non-scientific format. If you omit the decimal point then the number may not be treated as a real number but as an integer instead.																						
String	String constants are any character strings surrounded by double quotes, e.g. "sample string". Within the double quotes you can enter any characters except control characters or new lines. However there are special escape codes for entering such characters: <table style="margin-left: 40px;"> <tr> <td>\n</td> <td>new line (nl)</td> </tr> <tr> <td>\t</td> <td>horizontal tabulator (ht)</td> </tr> <tr> <td>\v</td> <td>vertical tabulator (vt)</td> </tr> <tr> <td>\b</td> <td>backspace (bs)</td> </tr> <tr> <td>\r</td> <td>carriage return (cr)</td> </tr> <tr> <td>\f</td> <td>form feed (ff)</td> </tr> <tr> <td>\\</td> <td>backslash character itself</td> </tr> <tr> <td>\"</td> <td>double quote</td> </tr> <tr> <td>\e</td> <td>escape code 033</td> </tr> <tr> <td>\NNN</td> <td>character with octal code NNN</td> </tr> <tr> <td>\xNN</td> <td>character with hex code NN</td> </tr> </table>	\n	new line (nl)	\t	horizontal tabulator (ht)	\v	vertical tabulator (vt)	\b	backspace (bs)	\r	carriage return (cr)	\f	form feed (ff)	\\	backslash character itself	\"	double quote	\e	escape code 033	\NNN	character with octal code NNN	\xNN	character with hex code NN
\n	new line (nl)																						
\t	horizontal tabulator (ht)																						
\v	vertical tabulator (vt)																						
\b	backspace (bs)																						
\r	carriage return (cr)																						
\f	form feed (ff)																						
\\	backslash character itself																						
\"	double quote																						
\e	escape code 033																						
\NNN	character with octal code NNN																						
\xNN	character with hex code NN																						
Memo	There are no constant values, just use a constant string instead.																						

Date	Constant date values can be specified in one of the formats DD.MM.YYYY, MM/DD/YYYY, or YYYY-MM-DD, where DD, MM and YYYY are standing for two and four digit values representing the day, month and year of the date respectively.
Time	Constant time values can be entered in the format HH:MM:SS, where HH is a two digit value in the range of 0 to 23 representing the hours, MM a two digit value in the range of 0 to 59 representing the minutes, and SS a two digit value in the range of 0 to 59 representing the seconds.

For some other pre-defined constant values, see

Pre-defined constants

.

1.146 MUIbase/Command syntax

Command syntax

In the remainder of this chapter, you will find the description of all commands and functions available for programming MUIbase. The following syntax is used for describing the commands:

- * text written in brackets [] is optional. If you omit the text inside the brackets then a default value is assumed.
- * text separated by a vertical bar | denotes several options, e.g. a | b means that you can specify either a or b.
- * text written in a font like VAR indicates a place-holder that can be filled with other expressions.
- * dots ... indicate that further expressions can follow.
- * all other text is obligatory.

1.147 MUIbase/Defining commands

Defining commands

=====

This section lists commands for defining functions and global variables. The commands are only available for project programs.

```

DEFUN
  Function definitions.

DEFUN*
  Function definitions.

DEFVAR
  Variable definitions.

```

1.148 MUIbase/DEFUN

```
DEFUN
```

```
-----
```

DEFUN defines a function with the specified name, a list of arguments that are passed to the function, and a list of expressions to evaluate.

```
(DEFUN NAME (VARLIST) EXPR ...)
```

The name of a function must start with a lowercase character, followed by further characters, digits or underscore characters (see

```

Name conventions
).

```

The parameters VARLIST specifies the arguments of the function:

```
VARLIST: VAR1 ...
```

where VAR1 ... are the names for the arguments. The names must follow the same rules as the function name.

It is also possible to add type specifiers to the arguments (see

```

Type specifiers
).

```

The function executes the expressions EXPR, ... one by one and returns the value of the last expression. The function may call further functions including itself. A self defined function can be called like calling a pre-defined function.

For example to count the number of elements of a list, you can define the following function:

```

(DEFUN len (l)
  (IF (= 1 NIL)
    0
    (+ 1 (len (REST l))))
)
)

```

Functions defined with DEFUN are listed in the pop-up list-views of table and attribute requesters (see
 Creating tables
 and
 Creating attributes
).

This command is only available for project programs.

See also

DEFUN*
 ,
 DEFVAR
 .

1.149 MUIbase/DEFUN*

DEFUN*

DEFUN* is the star version of DEFUN and has the same effect as DEFUN (see

 DEFUN
). The only difference is that functions defined with DEFUN* are not listed in the pop-up list-views when creating or changing tables and attributes. However, it is still possible to enter the function name in the corresponding string fields.

This command is only available for project programs.

See also

DEFUN
 ,
 DEFVAR
 .

1.150 MUIbase/DEFVAR

DEFVAR

(DEFVAR VAR [EXPR])

Defines a global variable with initial value of EXPR or NIL if EXPR is missing. The name of the variables must start with a lowercase letter followed by further letters, digits or underscore characters

(see
 Name conventions
).

You can also add a type specifier to the variable name (see
 Type specifiers
).

DEFVAR is only available for project programs. All DEFVAR commands should be placed on top of all function definitions.

Example: (DEFVAR x 42) defines a global variable x with value 42.

There are some pre-defined variables in MUIbase (see

 Pre-defined variables
).

See also

 DEFUN
 ,
 DEFUN*
 ,
 LET
 .

1.151 MUIbase/Program control functions

 Program control functions

=====

This section lists functions for program control, e.g. functions for defining local variables, loop functions, conditional program execution, loop control functions and more.

 PROGN
 Compound statement, returns last expression.

 PROG1
 Compound statement, returns first expression.

 LET
 Defining local variables.

 SETQ
 Setting the value of variables, attributes and tables.

 SETQ*
 Setting the value of variables, attributes and tables.

FUNCALL
Calling a function.

IF
If-then-else conditional program execution.

CASE
Switch-case conditional program execution.

COND
Powerful conditional program execution.

DOTIMES
Loop over a range of integer values.

DOLIST
Loop over a list.

DO
Generic loop.

FOR ALL
Loop over sets of records.

NEXT
Jumping to next loop run.

EXIT
Exiting a loop.

RETURN
Returning from a function.

HALT
Stopping program execution.

ERROR
Aborting program execution with an error message.

1.152 MUIbase/PROGN

PROGN

To evaluate several expressions one by another the PROGN construction can be used.

([EXPR ...])

executes EXPR ... one by one. Returns the result of the last expression (or NIL if no expression has been specified). In Lisp this construct is known as (PROGN [EXPR ...]).

Example: (1 2 3 4) results to 4.

See also

PROG1
.

1.153 MUIbase/PROG1

PROG1

Another way, besides the PROG1 function, to evaluate several expressions one by another is the PROG1 expression.

(PROG1 [EXPR ...])

executes EXPR ... and returns the value of the first expression (or NIL if no expression has been specified).

Example: (PROG1 1 2 3 4) results to 1.

See also

PROGN
.

1.154 MUIbase/LET

LET

LET defines a new block of local variables. This is useful, e.g., for defining local variables of a function. The syntax is

(LET (VARLIST) EXPR ...)

where VARLIST is a list of local variables.

VARLIST: VARSPEC ...

VARSPEC: (VAR EXPR) | VAR

Here VAR is the name of the variable and must start with a lowercase character, followed by further characters, digits or underscore characters (see

Name conventions
).

In the case of a (VAR EXPR) specification, the new variable is

initialized with the given expression. In the other case the new variable is set to NIL.

It is also possible to add type specifiers to the variables. (see

Type specifiers
).

After initializing all variables the list of expressions `EXPR ...` are evaluated and the value of the last one is returned.

For example, the following LET expression

```
(LET ((x 0) y (z (+ x 1)))
      (+ x z)
    )
```

results to 1.

See also

DOTIMES
,
DOLIST
,
DO
,
DEFVAR
.

1.155 MUIbase/SETQ

SETQ

The SETQ function sets values to variables, attributes and tables.

```
(SETQ LVALUE1 EXPR ...)
```

Sets LVALUE1 to the value of EXPR. The dots indicate assignments for further lvalues. An lvalue is either a variable, an attribute in a table, or a table. In case of a variable, the variable must have been previously defined (e.g. by a LET expression).

Setting the value of a table means setting its program or gui record pointer: (SETQ TABLE EXPR) sets the program record pointer of TABLE to the value of EXPR, (SETQ TABLE* EXPR) sets the gui record pointer of it and updates the display. For more information about program and gui record pointers, see

Tables
.

SETQ returns the value of the last expression.

Example: (SETQ a 1 b 2) assigns 1 to the variable a, 2 to the variable b and returns 2.

See also

```

SETQ*
,
LET
,
DEFVAR
,
Tables
,
Semantics of expressions
.

```

1.156 MUIbase/SETQ*

```

SETQ*
-----

```

SETQ* is the star version of SETQ (see SETQ) and has similar effects. The difference is that when assigning a value to an attribute, SETQ* calls the trigger function of that attribute (see

Attribute trigger) instead of directly assigning the value. In case no trigger function has been specified for an attribute, SETQ* behaves like SETQ and simply assigns the value to the attribute.

Example: (SETQ* Table.Attr 0) calls the trigger function of Table.Attr with an argument of 0.

Warning: With this function it is possible to write endless loops, e.g. if you have defined a trigger function for an attribute and this function calls SETQ* to set a value to itself.

See also

```

SETQ*
,
LET
,
DEFVAR
.

```

1.157 MUIbase/FUNCALL

FUNCALL

FUNCALL is used to call a function.

(FUNCALL FUN-EXPR [EXPR ...])

Calls the function FUN-EXPR with the given arguments. The expression FUN-EXPR can be any expression whose value is a pre-defined or user-defined function, e.g. a variable holding the function to call. If the number of arguments is not correct, an error message is generated.

FUNCALL returns the return value of the function call or NIL if FUN-EXPR is NIL.

For more information about functional expressions, see

Functional parameters

.

1.158 MUIbase/IF

IF

--

IF is a conditional operator.

(IF EXPR1 EXPR2 [EXPR3])

The expression EXPR1 is tested. If it results to non-NIL then the value of EXPR2 is returned else the value of EXPR3 (or NIL if not present) is returned.

This function is not strict, that is, only one expression of EXPR2 or EXPR3 will be evaluated.

See also

CASE

,

COND

.

1.159 MUIbase/CASE

CASE

CASE is similar to the switch statement in the C language.

```
(CASE EXPR [CASE ...])
```

Here EXPR is the selection expression and CASE ... are pairs consisting of:

```
CASE: (VALUE [EXPR ...])
```

where VALUE is a single expression or a list of expressions and EXPR ... are the expressions to be executed if one of the case expression matches.

The CASE expression first evaluates EXPR. Then each case pair is checked whether it (or one of the expressions in the list) matches the evaluated expression. If a matching case expression is found then the corresponding expressions are executed and the value of the last expression is returned. If no case matches, NIL is returned.

Example: (CASE 1 ((2 3 4) 1) (1 2)) returns 2.

See also

```
IF
,
COND
.
```

1.160 MUIbase/COND

```
COND
```

COND is, like IF, a conditional operator.

```
(COND [(TEST-EXPR [EXPR ...]) ...])
```

COND test the first expression of each list one by one. For the first one that does not result to NIL, the corresponding expressions EXPR ... are evaluated and the value of the last expression is returned.

If all tested expressions result to NIL then NIL is returned.

Example

```
(COND ((> 1 2) "1 > 2")
      ((= 1 2) "1 = 2")
      ((< 1 2) "1 < 2")
)
```

results to "1 < 2".

See also

IF
,
CASE
.

1.161 MUIbase/DOTIMES

DOTIMES

For simple loops the DOTIMES command can be used.

```
(DOTIMES (NAME INT-EXPR [RESULT-EXPR ...]) [LOOP-EXPR ...])
```

Here NAME is the name of a new variable which will be used in the loop. The name must start with a lowercase character, followed by further characters, digits or underscore characters (see

Name conventions
).

The number of times the loop is executed is given in INT-EXPR. In RESULT-EXPR ... expressions can be specified that are executed after terminating the loop. In LOOP-EXPR you specify the body of the loop, that is, the expressions that are evaluated in each loop run.

Before executing the loop, DOTIMES computes the value of INT-EXPR to determine the number of times the loop gets executed. Here INT-EXPR is evaluated only once at the start of the loop and must result to an integer value. Then DOTIMES sets the loop variable to the values of 0 to INT-EXPR-1 one by one for each loop run. First, the variable is initialized with zero and checked if it is already greater or equal to the value of EXPR. If INT-EXPR is negative or NIL or if the variable is greater or equal to the value of EXPR then the loop is terminated and the result expressions are evaluated. Otherwise the loop expressions are evaluated and the variable is incremented by one. Then the execution returns to the termination test and, possibly, does further loop runs.

The DOTIMES expression returns the value of the last result expression or NIL if no result expression has been given.

Example

```
(DOTIMES (i 50 i) (PRINT i))
```

Prints the numbers from 0 to 49 and returns the value 50.

See also

DOLIST
,

```

DO
,
FOR ALL
,
LET
.

```

1.162 MUIbase/DOLIST

```

DOLIST
-----

```

For loops through lists the DOLIST expression can be used.

```
(DOLIST (NAME LIST-EXPR [RESULT-EXPR ...]) [LOOP-EXPR ...])
```

Here NAME is the name of a new variable which will be used in the loop. The name must start with a lowercase character, followed by further characters, digits or underscore characters (see

```

Name conventions
).

```

In LIST-EXPR you specify the list over which the loop should be executed, RESULT-EXPR ... are expressions which are evaluated after terminating the loop, end LOOP-EXPR ... build the body of the loop.

Before executing the loop, DOLIST computes the value of LIST-EXPR. This expression is evaluated only once at the start of the loop and must result to a list value. Then DOTIMES sets the loop variable to the nodes of the list one by one for each loop run. First the loop variable is initialized to the first node of the list. If the list is already empty (NIL) then the loop is terminated and the result expressions are evaluated. Otherwise the loop expressions are evaluated and the variable is set to the next node of the list. Then the execution returns to the termination test and, possibly, does further loop runs.

The DOLIST expression returns the value of the last result expression or NIL if no result expression has been given.

Example

```
(DOLIST (i (SELECT * FROM Accounts)) (PRINT i))
```

Prints all records of table Accounts and returns NIL.

See also

```

DOTIMES
,
DO
,

```

```

FOR ALL
,
LET
.

```

1.163 MUIbase/DO

```
DO
```

```
--
```

With the DO expression arbitrary loops can be programmed.

```
(DO ([BINDING ...]) (TERM-EXPR [RESULT-EXPR ...]) [LOOP-EXPR ...])
```

where BINDING ... are the variable bindings, each of which is either:

- * a new name for a variable (which is initialized to NIL)
- * a list of the form: (NAME INIT [STEP]) where NAME is a name for the new variable, INIT is the initial value of the variable, and STEP is a step expression.

Furthermore, TERM-EXPR is the termination test expression, RESULT-EXPR ... are the result expressions (the default is nil) and LOOP-EXPR ... build the body of the loop.

The DO loop first initializes all local variables with the init expressions, then tests the termination expression. If it results to TRUE, the loop is terminated and the result expressions are evaluated. The value of the last result expression is returned. Otherwise the body of the loop (LOOP-EXPR ...) is executed and each variable is updated by the value of its step expression. Then the execution returns to test the terminating expression and so on.

Example

```
-----
```

```
(DO ((i 0 (+ i 1))) ((>= i 5) i) (PRINT i))
```

Prints the values 0, 1, 2, 3 and 4 and returns the value 5. Of course this is a quite complicated way to build a simple FOR loop. Therefore a simpler version exists, the DOTIMES expression.

See also

```

DOTIMES
,
DOLIST
,
FOR ALL
,
LET
.

```

1.164 MUIbase/FOR ALL

FOR ALL

The FOR ALL expression is used to loop over a list of records.

```
(FOR ALL TABLE-LIST [WHERE WHERE-EXPR] [ORDER BY ORDER-LIST] DO EXPR ...)
```

Here TABLE-LIST is a comma-separated list of tables, WHERE-EXPR an expression to test each set of records, ORDER-LIST a comma-separated list of expressions by which the record sets are ordered, and EXPR ... are the expressions that are executed for each record set.

FOR ALL first generates a list of all record sets for which the loop body should be executed. This is done like in the SELECT expression. Please see

```
SELECT
```

```
, for more information about how this list is
```

generated. For each element of this list the loop body EXPR ... is executed.

For example, summing up an attribute of a table can be done in the following way:

```
(SETQ sum 0)
(FOR ALL Accounts DO
  (SETQ sum (+ sum Accounts.Amount))
)
```

The FOR ALL expression returns NIL.

See also

```
SELECT
```

```
,
```

```
DOTIMES
```

```
,
```

```
DOLIST
```

```
,
```

```
DO
```

```
.
```

1.165 MUIbase/NEXT

NEXT

NEXT can be used for controlling DOTIMES, DOLIST, DO and FOR ALL

loops.

Calling NEXT in the body of a loop will jump to the next loop iteration. This can be used for skipping non-interesting loop runs, like e.g. in the following example:

```
(FOR ALL TABLE DO
  (IF NOT-INTERESTED-IN-THE-CURRENT-RECORD (NEXT))
  ...
)
```

See also

```
EXIT
,
DOTIMES
,
DOLIST
,
DO
,
FOR ALL
.
```

1.166 MUIbase/EXIT

```
EXIT
```

EXIT can be used to terminate a loop.

```
(EXIT [EXPR ...])
```

EXIT within a loop body will terminate the loop, execute the optional expressions EXPR ..., and return the value of the last expression (or NIL in case of no expression) as the return value of the loop. Possible return expressions of the loop as for example in

```
(DOTIMES (x 10 RET-EXPR ...) ...)
```

are not executed.

You may use the EXIT function for example to end a FOR ALL loop when you found the record you are interested in:

```
(FOR ALL TABLE DO
  (IF INTERESTED-IN-THE-CURRENT-RECORD (EXIT TABLE))
  ...
)
```

See also

```
NEXT
,
RETURN
```



```
    /
    HALT
    /
    DOTIMES
    /
    DOLIST
    /
    DO
    /
    FOR ALL
    .
```

1.167 MUIbase/RETURN

```
RETURN
```

Within a function definition you can return to the caller by using the RETURN command.

```
(RETURN [EXPR ...])
```

terminates the function, executes the optional expressions EXPR ..., and returns the value of the last expression (or NIL in case of no expression).

Example

```
(DEFUN find-record (name)
  (FOR ALL Table DO
    (IF (= Name name) (RETURN Table))
  )
)
```

The example searches a record whose Name attribute matches the given name. The function returns the first record found or NIL in case of no record found.

See also

```
    HALT
    /
    EXIT
    .
```

1.168 MUIbase/HALT

 HALT

HALT can be used to terminate program execution.

(HALT)

stops program execution silently.

See also

ERROR
 ,
 EXIT
 ,
 RETURN
 .

1.169 MUIbase/ERROR

 ERROR

For aborting program execution with an error message the ERROR function can be used.

(ERROR FMT [ARG ...])

stops program execution and pops up a requester with an error message. The error message is generated from FMT and the optional arguments ARG ... like in the SPRINTF function (see

SPRINTF
).

See also

HALT
 ,
 SPRINTF
 .

1.170 MUIbase/Type predicates

Type predicates
 =====

For each type a predicate is defined that returns TRUE if the supplied expression is of the specified type and NIL otherwise. The predicates are:

Predicate	Description
(STRP EXPR)	TRUE if EXPR is of type string, NIL otherwise.
(MEMOP EXPR)	TRUE if EXPR is of type memo, NIL otherwise.
(INTP EXPR)	TRUE if EXPR is of type integer, NIL otherwise.
(REALP EXPR)	TRUE if EXPR is of type real, NIL otherwise.
(DATEP EXPR)	TRUE if EXPR is of type date, NIL otherwise.
(TIMEP EXPR)	TRUE if EXPR is of type time, NIL otherwise.
(NULLP EXPR)	TRUE if EXPR is NIL (an empty list), NIL otherwise.
(CONSP EXPR)	TRUE if EXPR is a non-empty list, NIL otherwise.
(LISTP EXPR)	TRUE if EXPR is a list (may be NIL), NIL otherwise.
(RECP TABLE EXPR)	TRUE if EXPR is a record pointer of the given table. If EXPR is NIL then TRUE is returned (initial record). If TABLE is NIL then a check is done whether EXPR is a record pointer of any table.

1.171 MUIbase/Type conversion functions

Type conversion functions

=====

This section lists functions for converting values from one type to another one.

STR
Conversion to string.

MEMO
Conversion to memo.

INT
Conversion to integer.

REAL
Conversion to real.

DATE
Conversion to date.

TIME
Conversion to time.

1.172 MUIbase/STR

STR

STR can be used to convert an expression into a string representation.

(STR EXPR)

converts EXPR into a string representation. The type of EXPR determines the conversion:

Type	Return string
String	The string itself.
Memo	The whole memo text in one string.
Integer	String representation of integer value.
Real	String representation of real value. If EXPR is an attribute then the number decimals specified for this attribute are used, otherwise 2 decimals are used.
Choice	Label string of the choice attribute.
Date	String representation of date value.
Time	String representation of time value.
Bool	The string "TRUE"
NIL	User defined nil string if EXPR is an attribute, the string "NIL" otherwise.
Record	String representation of record number.
Others	String representation of internal address pointer.

See also

MEMO
,
SPRINTF
.

1.173 MUIbase/MEMO

MEMO

MEMO can be used to convert an expression into a memo.

(MEMO EXPR)

converts EXPR into a memo representation. It treats the expression like the STR function (see

STR

) but returns a memo text instead of a string.

See also

STR

.

1.174 MUIbase/INT

INT

INT is used to convert an expression into an integer.

(INT EXPR)

converts EXPR into an integer value. Possible conversions are:

Type	Return value
String	If the whole string represents an integer value then the string is converted into an integer. Leading and following spaces are ignored. If it does not represent an integer value, NIL is returned.
Memo	Same as for string.
Integer	The value itself.
Real	If the value lies within the integer range than the real value is rounded and returned, otherwise NIL is returned.
Choice	The internal number (starting with 0) of the current label.
Date	Number of days since 01.01.0000.
Time	Number of seconds since 00:00:00.
Record	Record number.
NIL	NIL

Others An error message is generated and program execution is aborted.

See also

REAL
,
ASC
.

1.175 MUIbase/REAL

REAL

REAL is used to convert an expression into a value of type real.

(REAL EXPR)

converts EXPR into a real. It treats the expression like the INT function (see

integer.
 INT
) but returns a value of type real instead of an

See also

INT
.

1.176 MUIbase/DATE

DATE

DATE is used to convert an expression into a date (with your best girl friend :-).

(DATE EXPR)

converts the given expression into a date (only one date guys, needs two good girl friends for getting more dates!) Possible conversions are:

Type Return value

String If the whole string represents a date value then the string is converted into a date value. Leading and following spaces are ignored.
 If it does not represent a date value, NIL is returned.

Memo Same as for string.

Integer	A date value is generated where the given integer represents the number of days since 01.01.0000. If the integer value is too great (date value would be greater than 31.12.9999) or negative then NIL is returned.
Real	Same as for integer.
Date	The value itself.
NIL	NIL
others	An error message is generated and program execution is aborted.

1.177 MUIbase/TIME

TIME

TIME is used to convert an expression into a time value.

(TIME EXPR)

converts the given expression into a time value. Possible conversions are:

Type	Return value
String	If the whole string represents a time value then the string is converted into a time value. Leading and following spaces are ignored. If it does not represent a time value, NIL is returned.
Memo	Same as for string.
Integer	A time value is generated where the given integer represents the number of seconds since 00:00:00. The integer value is taken modulo the number of seconds per day, e.g. (TIME 86400) results to 00:00:00.
Real	Same as for integer.
Time	The value itself.
NIL	NIL
others	An error message is generated and program execution is aborted.

1.178 MUIbase/Boolean functions

Boolean functions

=====

This section lists boolean operators.

AND
Conjunction of boolean values.

OR
Disjunction of boolean values.

NOT
Inverting a boolean value.

1.179 MUIbase/AND

AND

AND checks if all of its arguments are TRUE.

(AND [EXPR ...])

checks EXPR ... one by another until one expression evaluates to NIL. If all expressions evaluate to non-NIL then the value of the last expression is returned. Otherwise NIL is returned.

This function is non-strict which means that arguments of AND may not be evaluated, e.g. in (AND NIL (+ 1 2)) the expression (+ 1 2) is not evaluated since a NIL value has already been processed, however in (AND (+ 1 2) NIL) the expression (+ 1 2) gets evaluated.

See also

OR
,
NOT
.

1.180 MUIbase/OR

OR

OR checks if all of its arguments are NIL.


```
(OR [EXPR ...])
```

checks EXPR ... one by another until one expression evaluates to non-NIL. Returns the value of the first non-NIL expression or NIL if all expressions evaluate to NIL.

This function is non-strict which means that arguments of OR may not be evaluated, e.g. in (OR TRUE (+ 1 2)) the expression (+ 1 2) is not evaluated since a non-NIL value (here TRUE) has already been processed, however in (OR (+ 1 2) TRUE) the expression (+ 1 2) gets evaluated.

See also

```
AND
,
NOT
.
```

1.181 MUIbase/NOT

```
NOT
```

```
---
```

NOT is used to invert the value of a boolean expression.

```
(NOT EXPR)
```

results to TRUE if EXPR is NIL, NIL otherwise.

See also

```
AND
,
OR
.
```

1.182 MUIbase/Comparison functions

```
Comparison functions
```

```
=====
```

For comparing two values in a MUIbase program, use

```
(OP EXPR1 EXPR2)
```

where OP is in {=, <>, <, >, >=, <=, =*, <>*, <*, >*, >=*, <=*}. The star is used for special comparison (strings are compared case insensitive, records are compared by using the order defined by the user).

The following table shows all rules for comparing two values in a MUIbase program.

Type	Order relation
Integer	NIL < MIN_INT < ... < -1 < 0 < 1 < ... < MAX_INT
Real	NIL < -HUGE_VAL < ... < -1.0 < 0.0 < 1.0 < ... < HUGE_VAL
String:	NIL < "" < "Z" < "a" < "aa" < "b" < ... (case sensitive) NIL < * "" < * "a" < * "AA" < * "b" < ... (case insensitive)
Memo:	same as string
Date	NIL < 1.1.0000 < ... < 31.12.9999
Time	NIL < 00:00:00 < ... < 23:59:59
Bool	NIL < TRUE
Record:	NIL < any_record (records itself are not comparable with <) NIL < * rec1 < * rec2 (order specified by user)

See also

LIKE
.

1.183 MUIbase/Mathematical functions

Mathematical functions

=====

Here, some mathematical functions are listed.

+
Adding values.

-
Subtracting values.

1+
Increasing value.

1-
Decreasing value.

*
Floating point multiplication.

/
Floating point division.

DIV
Integer division.

MOD
Integer modulo.

MAX
Maximum expression.

MIN
Minimum expression.

ABS
Absolute value of an expression.

TRUNC
Truncating decimals of a real value.

ROUND
Rounding a real value.

RANDOM
Random number generator.

1.184 MUIbase/add

Adding values

For adding values, use

(+ EXPR ...)

Returns the sum of the arguments EXPR If any argument value is NIL then the result is NIL. If the values are of type real or integer then a real (or integer) value is the result.

You may also add strings or memos. In this case the result is the concatenation of the strings/memos.

If EXPR is of type date and the rest of the arguments are integers/real then the sum of integers/real are interpreted as a number of days and added to EXPR. If the resulting date is out of range (smaller than 1.1.0000 or greater than 31.12.9999) then NIL is the result.

If EXPR is of type time and the rest of the arguments are integers/real then the sum of integers/real are interpreted as a number of seconds and added to EXPR. However the rest of the arguments can also consist of expressions of type time. The resulting time value is computed modulo 24:00:00.

Examples

Expression	Value
(+ 1 2 3)	6
(+ 5 1.0)	6.0
(+ "Hello" " " "world!")	"Hello world!"
(+ 28.11.1968 +365 -28 -9)	22.10.1969
(+ 07:30:00 3600)	08:30:00
(+ 03:00:00 23:59:59)	02:59:59

See also

-
- ,
- 1+
- ,
- *
- ,
- CONCAT
- ,
- CONCAT2
- .

1.185 MUIbase/sub

Subtracting values

For subtracting values, use

(- EXPR1 EXPR2 ...)

Subtracts the sum of EXPR2 ... from EXPR1. Here the same rules apply as for adding values (see

+
) , except that strings and memos can't be subtracted.

(- EXPR) has a special meaning, it returns the negative value of EXPR (integer or real), e.g. (- (+ 1 2)) results to -3.

See also

- +
- ,
- 1-
- .

1.186 MUIbase/1+

```

--
--           1+

```

1+ increases an integer or real expression by one.

(1+ EXPR)

Returns the value of EXPR (integer or real) plus one. If EXPR is NIL then NIL is returned.

See also

```

+
'
1-
.

```

1.187 MUIbase/1-

```

--
--           1-

```

1- decreases an integer or real expression by one.

(1- EXPR)

Returns the value of EXPR (integer or real) minus one. If EXPR is NIL then NIL is returned.

See also

```

-
'
1+
.

```

1.188 MUIbase/mul

```

-----
-----           Multiplying values

```

For multiplying integer/real values, use

(* EXPR ...)

Returns the multiplication of the integer/real values EXPR If all arguments are integers then an integer is returned, otherwise the result is a value of type real.

See also

+
,
/
.

1.189 MUIbase/fdiv

Dividing values

For dividing integer/real values, use

(/ EXPR1 [EXPR2 ...])

Divides EXPR1 by the multiplication of the rest of the arguments. Returns a real value. On division by zero, NIL is returned.

See also

*
,
DIV
,
MOD
.

1.190 MUIbase/DIV

DIV

DIV is used for integer division.

(DIV INT1 INT2)

Returns the integer division of INT1 with INT2. For example, (DIV 5 3) results to 1.

See also

/
,
MOD
.

1.191 MUIbase/MOD

MOD

MOD is used for modulo calculation.

(MOD INT1 INT2)

Returns INT1 modulo INT2. For example, (MOD 5 3) results to 2.

See also

DIV

.

1.192 MUIbase/MAX

MAX

MAX returns the argument that has the largest value.

(MAX EXPR ...)

Returns the maximum value of the arguments EXPR ... (all integers or reals). If one of the expressions is NIL then NIL is returned.

See also

MIN

.

1.193 MUIbase/MIN

MIN

MIN returns the argument that has the smallest value.

(MIN EXPR ...)

Returns the minimum value of the arguments EXPR ... (all integers or reals). If one of the expressions is NIL then NIL is returned.

See also

MAX

.

1.194 MUIbase/ABS

ABS

ABS computes the absolute value of an expression.

(ABS EXPR)

Returns the absolute value of EXPR (integer or real). If EXPR is NIL then NIL is returned.

1.195 MUIbase/TRUNC

TRUNC

TRUNC truncates decimals of a real value.

(TRUNC REAL)

Returns the largest integer (as a real number) not greater than the specified real number. If REAL is NIL then NIL is returned.

Examples: (TRUNC 26.1) results to 26, (TRUNC -1.2) results to -2.

See also

ROUND
.

1.196 MUIbase/ROUND

ROUND

ROUND rounds a real value.

(ROUND REAL DIGITS)

Returns the specified real number rounded to DIGITS decimal digits. If REAL or DIGITS are NIL then NIL is returned.

Examples: (ROUND 70.70859 2) results to 70.71, (ROUND 392.36 -1) results to 392.0.

See also

TRUNC
.

1.197 MUIbase/RANDOM

RANDOM

RANDOM can be used to generate random numbers.

(RANDOM EXPR)

Returns a random number. On the first call the random number generator is initialized with a value generated from the current time. RANDOM generates a random number in the range of 0 ... EXPR, excluding the value of EXPR itself. The type of EXPR (integer or real) is the return type. If EXPR is NIL then NIL is returned.

Examples:

Example	Meaning
(RANDOM 10)	returns a value from 0 to 9,
(RANDOM 10.0)	returns a value from 0.0 to 9.99999...

1.198 MUIbase/String functions

String functions

=====

This section deals with functions useful for strings.

LEN
String length.

LEFTSTR
Left sub string.

RIGHTSTR
Right sub string.

MIDSTR
Individual sub string.

SETMIDSTR
Replacing a sub string.

INSMIDSTR
Inserting a string.

INDEXSTR
Searching for sub strings.

INDEXSTR*
Searching for sub strings.

INDEXBRK
Searching for characters.

INDEXBRK*
Searching for characters.

REPLACESTR
Replacing sub strings.

REMCHARS
Removing characters from string.

TRIMSTR
Removing leading and trailing spaces.

WORD
Extracting word in a string.

WORDS
Number of words in a string.

CONCAT
Concatenating strings.

CONCAT2
Concatenating strings.

UPPER
Upper case string.

LOWER
Lower case string.

ASC
ASCII value of character.

CHR
Character of ASCII value.

LIKE
Comparing strings.

SPRINTF
String formatting.

1.199 MUIbase/LEN

LEN

LEN computes the length of a string.

(LEN STR)

Returns the length of the given string or NIL if STR is NIL.

See also

WORDS
,
LINES
,
MAXLEN
.

1.200 MUIbase/LEFTSTR

LEFTSTR

LEFTSTR extracts a sub string out of a string.

(LEFTSTR STR LEN)

Returns the left part of the given string with at most LEN characters. If STR or LEN are NIL or if LEN is negative then NIL is returned.

Example: (LEFTSTR "Hello world!" 5) results to "Hello".

See also

RIGHTSTR
,
MIDSTR
,
WORD
,
LINE
.

1.201 MUIbase/RIGHTSTR

RIGHTSTR

RIGHTSTR extracts a sub string out of a string.

```
(RIGHTSTR STR LEN)
```

Returns the right part of the given string with at most LEN characters. If STR or LEN are NIL or if LEN is negative then NIL is returned.

Example: (RIGHTSTR "Hello world!" 6) results to "world!".

See also

```
LEFTSTR
,
MIDSTR
,
WORD
,
LINE
.
```

1.202 MUIbase/MIDSTR

```
MIDSTR
```

MIDSTR extracts a sub string out of a string.

```
(MIDSTR STR POS LEN)
```

Returns a part of the given string with at most LEN characters. If LEN is NIL then the number of returning characters is not restricted. The sub string starts at the POS-th position (starting with zero). If STR or LEN are NIL or if LEN is negative then NIL is returned. If POS is out of range, that is, negative or greater than the string length, NIL is returned.

Example: (MIDSTR "Hello world!" 3 5) results to "lo wo".

See also

```
LEFTSTR
,
RIGHTSTR
,
WORD
,
LINE
,
SETMIDSTR
,
INSMIDSTR
.
```

1.203 MUIbase/SETMIDSTR

SETMIDSTR

SETMIDSTR replaces a sub string in a string.

(SETMIDSTR STR INDEX SET)

Returns a copy of string STR where the sub string starting at INDEX is overwritten with string SET. The length of the returned string is greater or equal to the length of STR. If one of the arguments is NIL or if INDEX is out of range then NIL is returned.

Example: (SETMIDSTR "Hello world!" 6 "Melanie!") results to "Hello Melanie!".

See also

INSMIDSTR
,
REPLACESTR
.

1.204 MUIbase/INSMIDSTR

INSMIDSTR

INSMIDSTR is used to insert a sub string into a string.

(INSMIDSTR STR INDEX INSERT)

Returns a copy of string STR where the string INSERT has been inserted at the given index. If one of the arguments is NIL or if INDEX is out of range then NIL is returned.

Example: (INSMIDSTR "Hello world!" 6 "MUIbase-") results to "Hello MUIbase-world!".

See also

SETMIDSTR
,
REPLACESTR
.

1.205 MUIbase/INDEXSTR

INDEXSTR

INDEXSTR searches a string for the occurrence of a sub string.

(INDEXSTR STR SUBSTR)

Searches for the occurrence of SUBSTR in STR. String comparison is done case-sensitive. Returns the index (starting with 0) of the sub string in STR or NIL if the sub string is not present. If one of the arguments is NIL then NIL is returned.

Example: (INDEXSTR "Hello world!" "world") returns 6.

See also

INDEXSTR*
,
INDEXBRK
,
INDEXBRK*
.

1.206 MUIbase/INDEXSTR*

INDEXSTR*

INDEXSTR* has the same effect as INDEXSTR (see INDEXSTR) except that string comparison is done case-insensitive.

See also

INDEXSTR
,
INDEXBRK
,
INDEXBRK*
.

1.207 MUIbase/INDEXBRK

INDEXBRK

INDEXBRK is used to search for a character in a string.

```
(INDEXBRK STR BRKSTR)
```

Searches for the occurrence of a character from BRKSTR in STR. String comparison is done case-sensitive. Returns the index (starting with 0) of the first character found in STR or NIL if no character is found. If one of the arguments is NIL then NIL is returned.

Example: (INDEXBRK "Hello world!" "aeiou") returns 1.

See also

```
INDEXBRK*
/
INDEXSTR
/
INDEXSTR*
.
```

1.208 MUIbase/INDEXBRK*

```
INDEXBRK*
```

INDEXBRK* has the same effect as INDEXBRK (see INDEXBRK) except that string comparison is done case-insensitive.

See also

```
INDEXBRK
/
INDEXSTR
/
INDEXSTR*
.
```

1.209 MUIbase/REPLACESTR

```
REPLACESTR
```

REPLACESTR replaces sub strings by other strings.

```
(REPLACESTR STR SUBSTR REPLACESTR)
```

Replaces all occurrences of SUBSTR in STR by REPLACESTR. If any of the strings are NIL or SUBSTR is empty then NIL is returned.

Example: (REPLACESTR "From Freiburg to San Francisco" "Fr" "X")
results to "Xom Xeiburg to San Xancisco".

See also

```
SETMIDSTR
/
INSMIDSTR
/
REMCHARS
.
```

1.210 MUIbase/REMCHARS

REMCHARS

REMCHARS removes characters from a string.

(REMCHARS STR CHARS-TO-REMOVE)

Returns a copy of STR where all characters of CHARS-TO-REMOVE are removed from. If STR or CHARS-TO-REMOVE are NIL then NIL is returned.

Example: (REMCHARS YOUR-STRING " \t\n") removes all spaces, tabs and newline characters from YOUR-STRING.

See also

```
REPLACESTR
/
TRIMSTR
.
```

1.211 MUIbase/TRIMSTR

TRIMSTR

TRIMSTR removes leading and trailing spaces from a string.

(TRIMSTR STR)

Returns a copy of STR where all leading and trailing spaces have been removed.

Example: (TRIMSTR " I wrecked Selma's bike. ") results to "I wrecked Selma's bike."

See also

REMCHARS

.

1.212 MUIbase/WORD

WORD

WORD returns a word of a string.

(WORD STR NUM)

Returns the NUM-th word (starting with zero) of the given string. Words in a string are non-empty sub strings separated by space-like characters (e.g. space, tab or newline characters).

If STR or NUM are NIL, or if NUM is out of range, that is, less than zero or greater or equal to the number of words, then NIL is returned.

Example: (WORD "Therefore, I lend Selma my bike." 3) results to "Selma".

See also

WORDS

,

LINE

,

LEFTSTR

,

RIGHTSTR

,

MIDSTR

.

1.213 MUIbase/WORDS

WORDS

WORDS counts the number of words in a string.

(WORDS STR)

Returns the number of words of the given string or NIL if STR is NIL. Words are sub strings separated by space-like characters (e.g. space, tab, or newline characters).

Example: (WORDS "Actually, it wasn't really my bike.") results to 6.

See also

```
WORD
,
LINES
,
LEN
.
```

1.214 MUIbase/CONCAT

CONCAT

CONCAT concatenates strings.

```
(CONCAT [STR ...])
```

Returns the concatenation of the given list of strings where space characters have been inserted between the strings. If one of the strings is NIL, or the list is empty, then NIL is returned.

Example: (CONCAT "I" "thought" "it" "was" "an" "abandoned" "bike.") results to "I thought it was an abandoned bike."

See also

```
CONCAT2
,
+
,
SPRINTF
.
```

1.215 MUIbase/CONCAT2

CONCAT2

CONCAT2 concatenates strings.

```
(CONCAT2 INSERT [STR ...])
```

Returns the concatenation of the given list of strings. The strings will be separated with the given INSERT string. If INSERT is NIL, one of the strings is NIL, or the list is empty, then NIL is returned.

Example: (CONCAT2 "! " "But" "it" "wasn't!") results to "But! it! wasn't!".

See also

```
CONCAT
,
+
,
SPRINTF
.
```

1.216 MUIbase/UPPER

```
UPPER
```

UPPER converts a string to upper case.

```
(UPPER STR)
```

Returns a copy of the given string where all characters are converted to upper case. If STR is NIL then NIL is returned.

Example: (UPPER "Selma found a letter attached to my bike.") results to "SELMA FOUND A LETTER ATTACHED TO MY BIKE.".

See also

```
LOWER
.
```

1.217 MUIbase/LOWER

```
LOWER
```

LOWER converts a string to lower case.

```
(LOWER STR)
```

Returns a copy of the given string where all characters are converted to lower case. If STR is NIL then NIL is returned.

Example: (LOWER "The letter was from Silke.") results to "the letter was from silke.".

See also

```
UPPER
.
```

1.218 MUIbase/ASC

ASC

ASC converts a character to its ASCII code.

(ASC STR)

Returns the ASCII code of the first character of STR. If STR is empty, 0 is returned. If STR is NIL, NIL is returned.

Example: (ASC "A") results to 65.

See also

CHR

,

INT

.

1.219 MUIbase/CHR

CHR

CHR converts an ASCII code to a character.

(CHR INT)

Returns a string containing the character with ASCII code INT. If INT is 0, an empty string is returned. If INT is NIL or not in the range of ASCII characters (0..255) then NIL is returned.

Example: (CHR 67) results to "C".

See also

ASC

,

STR

.

1.220 MUIbase/LIKE

LIKE

LIKE compares strings.

(LIKE STR1 STR2)

Returns TRUE if STR1 matches STR2, NIL otherwise. The string STR2 may contain the joker characters '?' and '*' where '?' matches exactly one character and '*' matches a string of any length. String comparison is done case insensitive.

Example: (LIKE "Silke has been in France for one year." "*France*") results to TRUE.

See also

Comparison functions

.

1.221 MUIbase/SPRINTF

SPRINTF

SPRINTF formats a string with various data.

(SPRINTF FMT [EXPR ...])

SPRINTF takes a series of arguments, converts them to strings, and returns the formatted information as one string. The string FMT determines exactly what gets written to the return string and may contain two types of items: ordinary characters which are always copied verbatim and conversion specifiers which direct SPRINTF to take arguments from its argument list and format them. Conversion specifiers always begin with a % character.

Conversion specifiers always take the following form:

%[FLAGS] [WIDTH] [.PRECISION]TYPE

where

- * The optional FLAGS field controls output justification, sign character on numerical values, decimal points, and trailing blanks.
- * The optional WIDTH field specifies the minimum number of characters to print (the field width), with padding done with blanks or zeros.
- * The optional PRECISION field specifies either the minimum number of digits to be printed for types integer, string, bool, date and time, or the number of characters after the decimal point to be printed for values of type real.
- * The TYPE field specifies the actual type of the argument that SPRINTF will be converting, such as string, integer, real, etc.

Note that all of the above fields are optional except for TYPE. The

following tables list the valid options for these fields.

Flags field

-: The result is left justified, with padding done on the right using blanks. By default when - is not specified, the result is right justified with padding on the left with 0's or blanks.

+: The result will always have a - or + character prepended to it if it is a numeric conversion.

space:

Positive numbers begin with a space instead of a + character, but negative values still have a prepended -.

Width field

N: A minimum of N characters are output. If the conversion has less than N characters, the field is padded with blanks.

*: The width specifier is supplied in the argument list as an integer or real value, before the actual conversion argument. This value is limited to the range of 0 to 999.

Precision field

.N: For integer, string, bool, date and time values, N is the number of characters written from the converted item. For conversions of real values, N specifies the number of digits after the decimal point.

.*: The precision is supplied in the argument list as an integer or real value, before the actual conversion argument. This value is limited to the range of 0 to 999.

Type field

b: Converts a bool parameter to "TRUE" or "NIL".

i: Converts an integer value.

e: Converts a real number using the format [-]d.ddde+dd. Exactly one digit is before the decimal point, followed by an e, followed by an exponent. The number of digits after the decimal point is

determined by the precision field, or is 2 if precision is not specified. The decimal point will not appear if precision is 0.

f:

Converts a real value using the format [-]ddd.ddd. The number of digits after the decimal point is determined by the precision field, or is 2 if precision is not specified. The decimal point will not appear if precision is 0.

s:

Writes a string value until either the end of string is reached or the number of characters written equals the precision field.

d:

Converts a date value.

t:

Converts a time value.

%:

The character % is written, and no argument is converted.

SPRINTF returns the formatted string or NIL in case FMT is NIL.

Examples

Call	Result
(SPRINTF "Hello")	"Hello"
(SPRINTF "%s" "Hello")	"Hello"
(SPRINTF "%10s" "Hello")	" Hello"
(SPRINTF "%-10.10s" "Hello")	"Hello "
(SPRINTF "%010.3s" "Hello")	" Hel"
(SPRINTF "%-5.3b" TRUE)	"TRU "
(SPRINTF "%i" 3)	"3"
(SPRINTF "%03i" 3)	"003"
(SPRINTF "% 0+- 5.3i" 3)	" 003 "
(SPRINTF "%f" 12)	"12.00"
(SPRINTF "%10e 12.0)	" 1.20e+1"
(SPRINTF "%+-10.4f" 12.0)	"+12.0000 "
(SPRINTF "%10.5t" 12:30:00)	" 12:30"
(SPRINTF "%d" 28.11.1968)	"28.11.1968"
(SPRINTF "He%s %5.5s!" "llo"	
"world champion ship")	"Hello world!"

See also

```

PRINTF
,
STR
,
+
,
CONCAT
,
CONCAT2

```

1.222 MUIbase/Memo functions

Memo functions

=====

This section deals with functions useful for memos.

LINE
Extracting a line in a memo.

LINES
Number of lines in a memo.

MEMOTOLIST
Converting memo to list.

LISTTOMEMO
Converting list to memo.

FILLMEMO
Filling in a memo.

FORMATMEMO
Formatting a memo.

INDENTMEMO
Indenting a memo.

1.223 MUIbase/LINE

LINE

LINE extracts a line in a memo.

(LINE MEMO NUM)

Returns the NUM-th line (starting with zero) of the given memo. The line string will not have a terminating newline character. If MEMO or NUM are NIL or if NUM is out of range, that is, less than zero or greater or equal to the number of lines, then NIL is returned.

See also

LINES


```

,
WORD
.

```

1.224 MUIbase/LINES

```

LINES
-----

```

LINES returns the number of lines in a memo.

```
(LINES MEMO)
```

Returns the number of lines of the given memo or NIL if MEMO is NIL.

See also

```

LINE
,
WORDS
,
LEN
.

```

1.225 MUIbase/MEMOTOLIST

```

MEMOTOLIST
-----

```

MEMOTOLIST converts a memo to a list of strings.

```
(MEMOTOLIST MEMO)
```

Converts the given memo to a list. If MEMO is NIL then NIL is returned, otherwise a list is generated where each element contains one line of the memo.

Example: (MEMOTOLIST "My insurance\npays for\nthe wrecked bike.") results to ("My insurance" "pays for" "the wrecked bike.").

See also

```

LISTTOMEMO
.

```

1.226 MUIbase/LISTTOMEMO

LISTTOMEMO

LISTTOMEMO converts a list to a memo.

(LISTTOMEMO LIST)

Converts the given list to a memo. If LIST is NIL then NIL is returned, otherwise a memo is generated where each line consists of the string representation of the corresponding list element.

Example: (LISTTOMEMO (LIST "Silke" "lends me" "'my' bike" "till" 01.09.1998)) results to: "Silke\nlends me\n'my' bike\ntill\n01.09.1998".

See also

MEMOTOLIST

.

1.227 MUIbase/FILLMEMO

FILLMEMO

FILLMEMO fills in a memo with the results of expressions.

(FILLMEMO MEMO)

Creates a copy of the given memo where all substrings of the form \$(EXPR) are replaced by their results after evaluation.

Example: (FILLMEMO "(+ 1 1) is \$(+ 1 1).") results to "(+ 1 1) is 2."

Please use only small expressions in the memo as debugging and tracking down errors is not easy here.

See also

FORMATMEMO

,

INDENTMEMO

.

1.228 MUIbase/FORMATMEMO

FORMATMEMO

FORMATMEMO formats a memo.

(FORMATMEMO MEMO WIDTH FILL)

Formats MEMO to a memo with lines not longer than WIDTH characters. If FILL is non-NIL then spaces are used to pad the lines up to exactly WIDTH characters. The memo is processed section-wise. A section starts at the first non-white-space character. The line holding this character and all following lines up to the first line whose first character is a white-space are counted to this section. The whole section is then formatted word-wise, that is, as many words are put in one line as there is space for.

See also

FILLMEMO
,
INDENTMEMO
.

1.229 MUIbase/INDENTMEMO

INDENTMEMO

INDENTMEMO indents a memo by putting spaces to the left.

(INDENTMEMO MEMO INDENT)

Returns a copy of the given memo where each line is indented by INDENT space characters. If MEMO or INDENT is NIL then NIL is returned. If INDENT is negative, a value of 0 is used.

See also

FILLMEMO
,
FORMATMEMO
.

1.230 MUIbase/List functions

List functions

=====

This section lists functions for processing lists.

CONS

Elementary list constructor.

LIST
Generating a list of elements.

LENGTH
Getting number of list elements.

FIRST
Extracting first element of a list.

REST
Getting remainder of a list.

LAST
Extracting last element of a list.

NTH
Extracting n-th element of a list.

APPEND
Concatenating lists.

REVERSE
Reversing a list.

MAPFIRST
Applying a function to all list elements.

SORTLIST
Sorting elements of a list.

SORTLISTGT
Sorting elements of a list.

1.231 MUIbase/CONS

CONS

CONS builds a pair of expressions.

(CONS ELEM LIST)

Constructs a new list. The first element of the new list is ELEM, the rest are the elements of LIST (which should be a list or NIL). The list LIST is not copied, only a pointer is used to reference it!

Example: (CONS 1 (CONS 2 NIL)) results to (1 2).

The elements of a list can be of any type, e.g. it's also possible to have a list of lists (e.g. see

SELECT

). The CONS constructor can also be used to build pairs of elements, e.g. (CONS 1 2) is the pair with the two integers 1 and 2.

See also

```
LIST
/
FIRST
/
REST
.
```

1.232 MUIbase/LIST

```
LIST
```

LIST generates a list out of its arguments.

```
(LIST [ELEM ...])
```

takes the arguments ELEM ... and generates a list of it. This is equivalent to calling (CONS ELEM (CONS ... NIL)). Note that NIL alone stands for an empty list.

See also

```
CONS
/
LENGTH
.
```

1.233 MUIbase/LENGTH

```
LENGTH
```

LENGTH determines the length of a list.

```
(LENGTH LIST)
```

returns the length of the given list.

Example: (LENGTH (LIST "a" 2 42 3)) results to 4.

See also

```
LIST
.
```

1.234 MUIbase/FIRST

FIRST

FIRST extracts the first element in a list.

(FIRST LIST)

returns the first element of the given list. If LIST is empty (NIL) then NIL is returned.

See also

REST
,
LAST
,
NTH
,
CONS
.

1.235 MUIbase/REST

REST

REST returns the sub-list after the first element of a list.

(REST LIST)

returns the rest of the given list (the list without the first element). If LIST is empty (NIL) then NIL is returned.

Example: (REST (LIST 1 2 3)) results to (2 3).

See also

FIRST
,
CONS
.

1.236 MUIbase/LAST

LAST

LAST extracts the last element in a list.

(LAST LIST)

Returns the last element of the given list or NIL if LIST is NIL.

See also

FIRST

,

NTH

.

1.237 MUIbase/NTH

NTH

NTH extracts the n-th element of a list.

(NTH N LIST)

Returns the N-th element of the given list (starting with 0) or NIL if the element doesn't exist.

See also

FIRST

,

LAST

.

1.238 MUIbase/APPEND

APPEND

APPEND concatenates lists.

(APPEND [LIST ...])

returns the concatenation of LIST

Example: (APPEND (list 1 2) (list 3 4) (list 5)) results to (1 2 3 4 5).

See also

LIST

.

1.239 MUIbase/REVERSE

REVERSE

REVERSE reverses a list.

(REVERSE LIST)

returns the reverse list.

Example: (REVERSE (list 1 2 3)) results to (3 2 1).

1.240 MUIbase/MAPFIRST

MAPFIRST

MAPFIRST applies a function to all list elements.

(MAPFIRST FUNC LIST [...])

Builds a list whose elements are the result of the specified function called with the arguments of the given list elements one by one. The length of the returned list is as long as the length of the longest specified list. If one of the specified lists is too short then the list is padded with NIL elements.

Examples

Expression	Value
(MAPFIRST 1+ (LIST 1 2 3))	(2 3 4)
(MAPFIRST + (LIST 1 2 3) (LIST 2 3))	(3 5 NIL)

1.241 MUIbase/SORTLIST

SORTLIST

SORTLIST sorts the elements of a list.


```
(SORTLIST FUNC LIST)
```

Returns a copy of the specified list that has been sorted using the function FUNC for ordering. The order function must take two arguments one for each element and return an integer value less than zero if the first element is smaller than the second one, a value greater than zero if the first element is greater than the second one, and a value of zero if the two elements are equal.

Example for a string comparing function usable for sorting:

```
(DEFUN cmp_str (x y)
  (COND
    ((< x y) -1)
    (> x y) 1)
  (TRUE 0)
  )
)
```

Now you can sort a list by calling:

```
(SORTLIST cmp_str (LIST "hi" "fine" "great" "ok"))
```

which results to ("fine" "great" "hi" "ok").

See also

```
SORTLISTGT
,
MAPFIRST
.
```

1.242 MUIbase/SORTLISTGT

```
SORTLISTGT
```

SORTLIST sorts the elements of a list.

```
(SORTLISTGT GTFUNC LIST)
```

Like SORTLIST but here you specify an order function that returns a value not equal to NIL if the first element is greater than the second one, and NIL otherwise.

Example: (SORTLISTGT > (LIST "hi" "fine" "great" "ok")) result to ("fine" "great" "hi" "ok").

See also

```
SORTLIST
,
MAPFIRST
.
```

1.243 MUIbase/Input requesting functions

Input requesting functions

=====

For requesting information from the user, the following functions can be used.

ASKFILE
Requesting a filename.

ASKDIR
Requesting a directory name.

ASKSTR
Requesting a string.

ASKINT
Requesting an integer.

ASKCHOICE
Requesting one item out of many items.

ASKCHOICESTR
Requesting a string, offering predefined ones.

ASKOPTIONS
Requesting some items out of many items.

ASKBUTTON
Requesting the user to press a button.

ASKMULTI
Requesting several informations.

1.244 MUIbase/ASKFILE

ASKFILE

ASKFILE prompts the user for entering a filename.

(ASKFILE TITLE OKTEXT DEFAULT SAVEMODE)

Pops up a file-requester for entering a filename. The window title

can be set in `TITLE`, the text of the Ok button in `OKTEXT`, and the initial filename in `DEFAULT`. You may specify `NIL` for one of them to use default values. The last argument `SAVEMODE` (bool) allows setting the file-requester to a save mode. This mode should be used when asking for a filename to write something to.

`ASKFILE` returns the entered filename as string or `NIL` in case the user canceled the requester.

See also

```
ASKDIR
,
ASKSTR
.
```

1.245 MUIbase/ASKDIR

```
ASKDIR
```

`ASKDIR` prompts the user for entering a directory name.

```
(ASKDIR TITLE OKTEXT DEFAULT SAVEMODE)
```

Pops up a file-requester for entering a directory name. The arguments are used in the same way as in `ASKFILE` (see `ASKFILE`).

`ASKDIR` returns the entered directory name as string or `NIL` in case the user canceled the requester.

See also

```
ASKFILE
,
ASKSTR
.
```

1.246 MUIbase/ASKSTR

```
ASKSTR
```

`ASKSTR` prompts the user for entering a string.

```
(ASKSTR TITLE OKTEXT DEFAULT MAXLEN)
```

Pops up a requester asking for a string to enter. The window title,

the text of the Ok button, and the initial value can be set in TITLE, OKTEXT, and DEFAULT respectively (strings or NIL for default values), MAXLEN determines the maximum characters the user can enter.

ASKSTR returns the entered string or NIL in case the user canceled.

See also

```

ASKFILE
'
ASKDIR
'
ASKCHOICESTR
'
ASKINT
.

```

1.247 MUIbase/ASKINT

ASKINT

ASKINT prompts the user for entering an integer value.

(ASKINT TITLE OKTEXT DEFAULT MIN MAX)

Pops up a requester asking for an integer to enter. The window title and the text of the Ok button can be specified in TITLE and OKTEXT (strings or NIL for default values). In DEFAULT you pass the initial integer value or NIL to start with an empty editing field. In MIN and MAX you can set the integer range. Entered values outside this range are not accepted by the requester. Use NIL for default min and max values.

ASKINT returns the entered integer or NIL if the user canceled the requester.

See also

```

ASKSTR
.

```

1.248 MUIbase/ASKCHOICE

ASKCHOICE

ASKCHOICE prompts the user to select one item out of many items.

(ASKCHOICE TITLE OKTEXT CHOICES DEFAULT)

Pops up a requester allowing the user to choose one item out of many items. You can set the window title and the text of the Ok button in TITLE and OKTEXT (strings or NIL for default values). In CHOICES you specify a list of choices from which the user can choose one. The list items can be any expressions that can be converted to strings. The initial choice value can be set in DEFAULT which must be an integer index into the choice list (starting with index 0 for the first item). Use NIL for no initial choice.

ASKCHOICE returns the index of the chosen item or NIL if the user canceled the requester.

Example

```
(LET ((items (LIST "First Entry" 2 3.14 "Last entry"))) index)
  (SETQ index (ASKCHOICE "Choose one item" "Ok" items NIL))
  (IF index
    (PRINTF "User chose item num %i with contents <%s>\n"
      index (STR (NTH index items))
    )
  )
)
```

See also

```
ASKCHOICESTR
,
ASKOPTIONS
.
```

1.249 MUIbase/ASKCHOICESTR

ASKCHOICESTR

ASKCHOICESTR prompts the user for entering a string value offering several pre-defined ones.

```
(ASKCHOICESTR TITLE OKTEXT STRINGS DEFAULT)
```

Pops up a requester allowing the user to choose one string out of many strings or to enter any other string in a separate string field. You can set the window title and the text of the Ok button in TITLE and OKTEXT (strings or NIL for default values). In STRINGS you specify a list of strings from which the user can choose one. The initial value of the string field can be set in DEFAULT (string or NIL for an empty string field).

ASKCHOICESTR returns the chosen string or NIL if the user canceled the requester.

Example

```
)
)
```

1.251 MUIbase/ASKBUTTON

ASKBUTTON

ASKBUTTON prompts the user for pressing a button.

```
(ASKBUTTON TITLE TEXT BUTTONS CANCELTEXT)
```

Pops up a requester with the specified window title (string or NIL for a default title) and specified description text (string or NIL for no text). The function waits until the user presses one of the buttons specified in BUTTONS (list of strings) or the Cancel button. The text of the cancel button can be set in CANCELTEXT. If you specify NIL here then a default text based on the number of buttons you specified is used.

ASKBUTTON returns the number of the pressed button (starting with 0 for the first (leftmost) button) or NIL if the user pressed the Cancel button.

Examples

```
(LET ((buttons (LIST "At home" "In bed" "In front of my Amiga")) index)
  (SETQ index (ASKBUTTON "Please answer:"
    "Where do you want to be tomorrow?" buttons "Don't know"))
  )
(IF index
  (PRINTF "User chose: <%s>\n" (NTH index buttons))
  )
)
```

```
(ASKBUTTON "Info"
  "You have been playing with your\nAmiga for five hours now.\nGo to bed!"
  NIL NIL
)
```

See also

ASKCHOICE

.

1.252 MUIbase/ASKMULTI

ASKMULTI

ASKMULTI prompts the user to enter various kinds of information.

```
(ASKMULTI TITLE OKTEXT ITEMLIST)
```

ASKMULTI is a multi-purpose requester. It opens a window with the specified title, a set of gui objects for editing data, and two buttons (Ok and Cancel) for terminating the requester. The text of the Ok button can be set in OKTEXT (string or NIL for default text). The set of gui objects are specified in ITEMLIST which is a list of items where each item has one of the following forms:

```
(LIST TITLE "String" INITIAL [HELP])    for editing one line of text,
(LIST TITLE "Memo" INITIAL [HELP])      for editing multi-line text,
(LIST TITLE "Integer" INITIAL [HELP])   for editing an integer,
(LIST TITLE "Real" INITIAL [HELP])      for editing a real,
(LIST TITLE "Date" INITIAL [HELP])      for editing a date,
(LIST TITLE "Time" INITIAL [HELP])      for editing a time,
(LIST TITLE "Bool" INITIAL [HELP])      for a boolean field,
(LIST TITLE "Choice" INITIAL
  (LIST CHOICE ...) [HELP]
)                                          for a choice field.
(LIST TITLE "ChoiceList" INITIAL
  (LIST CHOICE ...) [HELP]
)                                          for selecting one item of a list.
(LIST TITLE "Options" INITIAL
  (LIST OPTION ...) [HELP]
)                                          for selecting several items of a list.
NON-LIST-EXPR                            for static text
```

The title (string or NIL for no title) will be displayed to the left of the gui object. If the initial value is NIL then a default value is used (e.g. an empty text field). For choice fields the initial value must be the index (starting with 0) for the initial active entry, for choice list fields the initial value may be NIL (no item is activated), and for options fields the initial value must be a list of integers representing the indices (starting with 0) of the items that are initially selected. The optional help field (string) can be used for giving more information to the user about the usage of the field.

ASKMULTI returns a list of result values which the user has edited and acknowledged by pressing the Ok button. Each result value of a field has the same format as the one for the initial value, e.g. for a choice list field the result value is the index of the selected item (or NIL if no item has been selected), or for an options field the result value is a list of integers representing the indices of the selected items. For static text a value of NIL is returned.

E.g. if you have specified a date field, a static text field, a choice field, an options field, and a string field with initial value "world", and the user has entered 11.11.1999, selected the choice entry with index number 2, selected the 3rd and 4th item in the options field, and left the string field untouched then the function returns the list (11.11.1999 NIL 2 (3 4) "world").

If the user cancels the requester, NIL is returned.

Example

```
(ASKMULTI "Please edit:" NIL (LIST
  (LIST "_Name" "String" ""))
  (LIST "_Birthday" "Date" NIL)
  (LIST "_Sex" "Choice" 0 (LIST "male" "female"))
  (LIST "_Has car?" "Bool" NIL)
  (LIST "_Likes", "Options" (LIST 0 2)
    (LIST "Beer" "Wine" "Whisky" "Wodka" "Schnaps"))
  ))
)
```

Please see also the project AskDemo.mb for further examples.

1.253 MUIbase/I-O functions

I/O functions

=====

This sections lists functions and variables for input and output (e.g. printing) of data.

```
FOPEN
  Opening a file for reading/writing.

FCLOSE
  Closing a file.

stdout
  Standard output file handle.

PRINT
  Printing an expression to stdout.

PRINTF
  Formatted printing to stdout.

FPRINTF
  Formatted printing to a file.

FERROR
  Error checking of a file.

FGETCHAR
  Reading the next input character from a file.

FGETCHARS
  Reading several input characters from a file.

FGETSTR
  Reading a string from a file.
```

FGETMEMO
Reading a memo from a file.

FPUTCHAR
Writing a character to a file.

FPUTSTR
Writing a string to a file.

FPUTMEMO
Writing a memo to a file.

FFLUSH
Flushing a file.

1.254 MUIbase/FOPEN

FOPEN

FOPEN opens a file for reading/writing.

(FOPEN FILENAME MODE)

Opens the file specified by FILENAME (string). The MODE parameter (string) controls the access mode. Use "w" to open a file for writing, "a" to append to a file, and "r" for reading from a file. You may also use other flags (or combination of flags) like "r+" for reading and writing. There is no check done that tests if you have specified a valid flag string. However if the file can't be opened, NIL is returned.

FOPEN returns a file handle on success. On failure NIL is returned. If FILENAME or MODE are NIL then NIL is returned.

Example: (FOPEN "PRT:" "w") opens and returns a file handle to the printer.

See also

FCLOSE
,
stdout
,
FFLUSH
.

1.255 MUIbase/FCLOSE

FCLOSE

FCLOSE closes a file.

(FCLOSE FILE)

Closes the given file. Returns 0 on success, NIL if an error has occurred. If FILE is NIL then 0 is returned (no error). After closing a file accessing the file handle is an illegal operation and results in aborting program execution with an error message.

See also

FOPEN
,
FFLUSH
.

1.256 MUIbase/stdout

stdout

The global variable stdout holds the file handle to MUIbase's standard output file. The output filename can be set in menu item Program - Output file. You may use PRT: here for sending the output to your printer, or CON:///Output/CLOSE/WAIT for printing into a console window.

On the first access of this variable (either directly, e.g. by calling (FPRINTF stdout ...), or indirectly, e.g. by calling (PRINTF ...)), this file is opened. The file is not pre-opened on program execution. This avoids opening the file when no output is generated, e.g. when you simply want to do some calculations and change some record contents.

If MUIbase can't open the program output file then execution is aborted and an error message is generated.

See also

FOPEN
,
PRINTF
.

1.257 MUIbase/PRINT

PRINT

PRINT converts an expression to a string and prints it.

(PRINT ELEM)

Converts the value of ELEM to a readable string and prints it to stdout. This function mainly exists for debug purposes.

See also

```
PRINTF
'
stdout
.
```

1.258 MUIbase/PRINTF

PRINTF

PRINTF prints a formatted string.

(PRINTF FORMAT [EXPR ...])

Formats a string using the given format string and arguments and prints it to stdout. Formatting is done like in SPRINTF (see SPRINTF).

PRINTF returns the number of output characters or NIL on failure. If FORMAT is NIL then NIL is returned.

Example: (PRINTF "%i days and %i week" 7 1) prints the string "7 days and 1 week" to stdout and returns 17.

See also

```
PRINT
'
FPRINTF
'
stdout
.
```

1.259 MUIbase/FPRINTF

FPRINTF

FPRINTF prints a formatted string to a file.

(FPRINTF FILE FORMAT [EXPR ...])

Formats a string using the given format string and arguments and prints it to the specified file. Formatting is done like in SPRINTF (see

 SPRINTF
).

FPRINTF returns the number of output characters or NIL on failure. If FILE is NIL then FPRINTF still returns the number of potentially written characters but no output is actually written. If FORMAT is NIL then NIL is returned.

See also

 PRINTF
 ,
 FOPEN
 .

1.260 MUIbase/FERROR

FERROR

FERROR checks if an file I/O error has occurred.

(FERROR FILE)

returns TRUE if an error for the given file has occurred, NIL otherwise.

See also

 FOPEN
 ,
 FCLOSE
 .

1.261 MUIbase/FGETCHAR

FGETCHAR

FGETCHAR reads a character from a file.

(FGETCHAR FILE)

Returns the next character from the given file as a string or NIL if FILE is NIL, end of file has been reached, or an error has happened. If the next character is a null character, an empty string is returned.

See also

```
FGETCHARS
/
FGETSTR
/
FPUTCHAR
.
```

1.262 MUIbase/FGETCHARS

FGETCHARS

FGETCHARS reads characters from a file.

(FGETCHARS NUM FILE)

returns a string containing the next NUM characters from the given file. If end of file has been reached before reading NUM characters or if a null character has been read then only these characters are returned. If NUM or FILE are NIL, NUM is negative, end of file has been reached before reading the first character, or a read error has happened then NIL is returned.

See also

```
FGETCHAR
/
FGETSTR
.
```

1.263 MUIbase/FGETSTR

FGETSTR

FGETSTR reads a string from a file.

(FGETSTR FILE)

returns the next line of the given file as a string or NIL if FILE is NIL, end of file has been reached, or an error happened. The end of a line is detected if either a newline character or a null character is read, or if end of file is detected. In either case the string does

not contain any newline characters.

See also

```
FGETCHAR
,
FGETCHARS
,
FGETMEMO
,
FPUTSTR
.
```

1.264 MUIbase/FGETMEMO

```
FGETMEMO
-----
```

FGETMEMO reads a memo from a file.

(FGETMEMO FILE)

returns a memo that contains the contents of the given file up to the next null character or up to the end of file. If FILE is NIL, end of file has been reached before reading any characters, or an error occurred then NIL is returned.

See also

```
FGETSTR
,
FPUTMEMO
.
```

1.265 MUIbase/FPUTCHAR

```
FPUTCHAR
-----
```

FPUTCHAR writes a character to a file.

(FPUTCHAR STR FILE)

Writes the first character of STR to the given file. If STR is empty, a null character is written, if STR or FILE are NIL, nothing happens. Returns STR or NIL in case an output error occurred.

See also

```
FPUTSTR
,
```

FGETCHAR

.

1.266 MUIbase/FPUTSTR

FPUTSTR

FPUTSTR writes a string to a file.

(FPUTSTR STR FILE)

Prints STR together with a newline character to the given file. If STR or FILE are NIL, nothing happens. Returns STR or NIL in case an output error occurred.

See also

FPUTCHAR

,

FPUTMEMO

,

FGETSTR

.

1.267 MUIbase/FPUTMEMO

FPUTMEMO

FPUTMEMO writes a memo to a file.

(FPUTMEMO MEMO FILE)

Prints MEMO to the given file. If MEMO or FILE are NIL, nothing happens. Returns MEMO or NIL in case an output error occurred.

See also

FPUTSTR

,

FGETMEMO

.

1.268 MUIbase/FFLUSH

FFLUSH

FFLUSH flushes pending data to a file.

(FFLUSH FILE)

Flushes all pending output for the given file. Returns 0 on success, NIL if an error occurred. If FILE is NIL then 0 is returned (no error).

See also

FOPEN
,
FCLOSE
.

1.269 MUIbase/Record functions

Record functions

=====

This section lists functions that deal with records.

NEW

Allocating new record.

NEW*

Allocating new record by calling trigger function.

DELETE

Deleting a record.

DELETE*

Deleting a record by calling trigger function.

DELETEALL

Deleting all records of a table.

GETMATCHFILTER

Getting the match-filter state of a record.

SETMATCHFILTER

Setting the match-filter state of a record.

RECNUM

Getting the record number of a record.

COPYREC

Copying the contents of a record.

1.270 MUIbase/NEW

NEW

NEW allocates a new record for a table.

(NEW TABLE INIT)

Allocates a new record in the given table. The parameter INIT specifies the record which should be used for initializing the new record. A value of NIL stands for the initial record.

NEW returns a record pointer to the new record.

The NEW function has the side effect of setting the program record pointer of the given table (see
Tables
) to the new record.

Example: (NEW table NIL) allocates a new record in the given table and initializes it with the initial record.

See also

NEW*
,
DELETE
,
Tables
.

1.271 MUIbase/NEW*

NEW*

NEW* is the star version of NEW (see
NEW
).

(NEW* TABLE INIT)

NEW* checks if you have specified a New trigger function for the given table (see

New trigger
) . If so then this trigger function is called for allocating the record and its result is returned. The INIT

parameter can be used to specify a record with which the new record should be initialized (use NIL for the initial record).

If no trigger function has been specified, the function behaves like the NEW function.

Warning: With this function it is possible to write endless loops, e.g. if you have defined a New trigger function for a table and this function calls NEW* to allocate the record.

See also

```
NEW
,
DELETE*
.
```

1.272 MUIbase/DELETE

DELETE

DELETE deletes a record in a table.

(DELETE TABLE REQUESTER)

Deletes the current program record of the given table after an optional delete requester. The first argument specifies the table for which the current program record should be deleted, the second argument is a boolean expression. If it is NIL then the record is deleted silently, if it is not NIL then the state of preferences menu item Record delete requester is checked. If it is not set, the record is deleted silently, otherwise the standard delete requester appears asking for confirmation. If the users cancels the delete operation then the record will not be deleted.

The return code of the DELETE function reflects the selected action. If it returns TRUE then the record has been deleted, otherwise (the user has canceled the operation) NIL is returned.

On deletion, DELETE sets the program record pointer (see Tables) of the specified table to NIL.

Example: (DELETE table NIL) deletes the current record in the given table silently.

See also

```
DELETE*
,
DELETEALL
,
NEW
```

```

,
Tables
.

```

1.273 MUIbase/DELETE*

```

DELETE*
-----

```

DELETE* is the star version of DELETE (see
DELETE
).

(DELETE* TABLE REQUESTER)

DELETE* checks if you have specified a Delete trigger function for the given table (see
Delete trigger
). If so then this trigger function is called for deleting the record and its result is returned. The REQUESTER parameter can be used to specify if the trigger function should pop up a confirmation requester before deleting the record.

If no trigger function has been specified, the function behaves like the DELETE function.

Warning: With this function it is possible to write endless loops, e.g. if you have defined a Delete trigger function for a table and this function calls DELETE* to delete the record.

See also

```

DELETE
,
DELETEALL
,
NEW*
.

```

1.274 MUIbase/DELETEALL

```

DELETEALL
-----

```

DELETEALL deletes all records of a table.

(DELETEALL TABLE[*])

Deletes all records of the specified table. If you add a star behind

the table name then only those records that match the current filter of the table are deleted. There is no safety requester before deleting the records.

DELETEALL returns TRUE on successful deletion of all records, otherwise NIL is returned. If TABLE is NIL then NIL is returned.

Example: (DELETEALL table*) deletes all records in the given table that match the filter of the table.

See also

```
DELETE
/
Tables
.
```

1.275 MUIbase/GETMATCHFILTER

GETMATCHFILTER

GETMATCHFILTER returns the match-filter state of a record.

(GETMATCHFILTER REC)

Returns TRUE if the specified record matches the filter of its table, NIL otherwise. If the filter of the table is currently not active then TRUE is returned. If REC is NIL (the initial record) then NIL is returned.

See also

```
SETMATCHFILTER
.
```

1.276 MUIbase/SETMATCHFILTER

SETMATCHFILTER

SETMATCHFILTER sets the match-filter state of a record.

(SETMATCHFILTER REC ON)

Changes the match-filter state of the specified record to the value of ON. SETMATCHFILTER returns the new match-filter state of the given record. The new state may be different from the expected one because setting the match-filter state to NIL does only work when the filter of the corresponding table is currently active, otherwise TRUE is returned.

Calling SETMATCHFILTER with a value of NIL for REC (the initial record) will always return NIL.

See also

GETMATCHFILTER

.

1.277 MUIbase/RECNUM

RECNUM

RECNUM returns the record number of a record.

(RECNUM RECORD)

Returns the record number of the given record. Please note that the numbering for records is different than e.g. for lists. For lists, strings and others the counting begins with zero, however for records it begins with 1 for the first record. The number 0 is reserved for the initial record. This seems to be inconsistent with the rest of the MUIbase programming functions, but it does really makes sense here as the record numbers are also used in the window display.

See also

RECORDS

,

INT

.

1.278 MUIbase/COPYREC

COPYREC

COPYREC copies records.

(COPYREC REC SOURCE)

Copies the contents of record SOURCE to record REC. If SOURCE is NIL then REC is set to the values of the initial record. If REC is NIL then an error message is generated.

COPYREC returns REC.

See also

NEW

.

1.279 MUIbase/Attribute functions

Attribute functions

=====

This section lists functions that work on attributes of a table.

ATTRNAME

Getting the name of an attribute.

MAXLEN

Maximum number of characters for a string attribute.

GETLABELS

Getting the labels of a choice or string attribute.

SETLABELS

Setting the list-view labels of a string attribute.

1.280 MUIbase/ATTRNAME

ATTRNAME

ATTRNAME returns the name of an attribute.

(ATTRNAME ATTR)

Returns a string containing the name of the specified attribute.

See also

TABLENAME

1.281 MUIbase/MAXLEN

MAXLEN

MAXLEN returns the maximum size of a string attribute.

(MAXLEN STRING-ATTR)

Returns the maximum number of characters that the given string attribute can hold.

See also

LEN

.

1.282 MUIbase/GETLABELS

GETLABELS

GETLABELS returns all labels of a choice or string attribute.

(GETLABELS ATTR)

Returns the labels of the given choice or string attribute. In case of a choice attribute, the labels you entered in the attribute requester (see

Type specific settings

) are returned, in case of a

string attribute, the labels you entered for the list-view pop-up (see

Attribute object editor

) are returned.

The labels are returned in one single string and are separated by newline characters.

For example, consider you have a choice attribute with the labels Car, House, and Oil. Then calling GETLABELS on that attribute will result to the string "Car\nHouse\nOil".

Note: you can easily convert the result string to a list by calling MEMOTOLIST (see

MEMOTOLIST

) on the result string.

See also

SETLABELS

.

1.283 MUIbase/SETLABELS

SETLABELS

SETLABELS is used to set the labels of a string attribute.

```
(SETLABELS ATTR STR)
```

Sets the labels of the string attribute ATTR to the labels listed in the STR argument. The STR argument consists of lines each of which holds one label. The labels replace the ones you have entered for the pop-up list-view in the attribute object editor (see

```
Attribute object editor
).
```

SETLABELS returns the value of its STR argument.

Example: (SETLABELS Table.String "My house\nis\nyour house") sets the list-view labels of the specifies string attribute to My house, is, and your house.

Note: you can easily convert a list of labels to the required string format by calling

```
LISTTOMEMO
on the list.
```

See also

```
GETLABELS
.
```

1.284 MUIbase/Table functions

```
Table functions
```

```
=====
```

```
TABLENAME
```

```
Getting the name of a table.
```

```
GETORDERSTR
```

```
Getting record order.
```

```
SETORDERSTR
```

```
Setting record order.
```

```
GETFILTERACTIVE
```

```
Getting record filter state.
```

```
SETFILTERACTIVE
```

```
Setting record filter state.
```

```
GETFILTERSTR
```

```
Getting record filter expression.
```

```
SETFILTERSTR
```

```
Setting record filter expression.
```

RECORDS
Number of records.

RECORD
Getting pointer to a record.

SELECT
Select-from-where queries.

1.285 MUIbase/TABLENAME

TABLENAME

TABLENAME returns the name of a table.

(TABLENAME TABLE)

Returns a string containing the name of the specified table.

See also

ATTRNAME

1.286 MUIbase/GETORDERSTR

GETORDERSTR

GETORDERSTR returns the record order of a table.

(GETORDERSTR TABLE)

Returns the current order expression of the given table. The returned string contains the attribute names used for ordering separated by spaces. Each attribute name is prepended by a + or a - sign indicating ascending or descending order. An empty string means no ordering.

Example

Consider a table Person which is ordered by the Attributes Name (ascending), Town (ascending), and Birthday (descending). Then (ORDERSTR Person) will result to the string "+Name +Town -Birthday".

See also

SETORDERSTR

.

1.287 MUIbase/SETORDERSTR

SETORDERSTR

SETORDERSTR sets the record order of a table.

(SETORDERSTR TABLE ORDER)

Sets the order of the given table to the attributes in the ORDER string. The ORDER string must contain the attribute names used for ordering separated by any number of spaces, tabs or newlines. Each attribute name may be prepended by a + or a - sign indicating ascending or descending order. If you omit this sign then ascending ordering is assumed.

SETORDERSTR returns TRUE if it has been able to set the new order, NIL otherwise, e.g. if an unknown attribute has been specified or the type of the attribute is not allowed for ordering. If you specify NIL for the ORDER argument then nothing happens and NIL is returned.

Note: For building the order string you should not directly write the attribute names into the string because when you change an attribute name then the order string will not be updated. Better use the ATTRNAME function (see
ATTRNAME
) to copy the attribute's name into the order string.

Example

Consider a table Person with the attributes Name, Town, and Birthday. Then (SETORDERSTR Person (SPRINTF "+%s" (ATTRNAME Person.Name))) will set the order of table Person using Name as (ascending) order attribute.

See also

GETORDERSTR

.

1.288 MUIbase/GETFILTERACTIVE

GETFILTERACTIVE

GETFILTERACTIVE returns the filter state of a table.

(GETFILTERACTIVE TABLE)

Returns TRUE if the filter of the specified table is currently activated and NIL otherwise.

See also

```
SETFILTERACTIVE
/
GETFILTERSTR
/
GETMATCHFILTER
.
```

1.289 MUIbase/SETFILTERACTIVE

SETFILTERACTIVE

SETFILTERACTIVE sets the filter state of a table.

(SETFILTERACTIVE TABLE BOOL)

Sets the filter state of the specified table. If BOOL is non-NIL then the filter is activated, otherwise it is deactivated.

SETFILTERACTIVE returns the new state of the filter. The new state may not be the expected one in case you activate the filter but an error condition occurs and the filter can't be activated. However deactivating the filter always succeeds.

See also

```
GETFILTERACTIVE
/
SETFILTERSTR
/
SETMATCHFILTER
.
```

1.290 MUIbase/GETFILTERSTR

GETFILTERSTR

GETFILTERSTR returns the record filter expression of a table.

(GETFILTERSTR TABLE)

Returns the record filter expression of the specified table as a

string. An empty string means that no filter expression has been set for this table.

See also

```
SETFILTERSTR
,
GETFILTERACTIVE
,
GETMATCHFILTER
.
```

1.291 MUIbase/SETFILTERSTR

```
SETFILTERSTR
```

SETFILTERSTR sets the record filter expression of a table.

```
(SETFILTERSTR TABLE FILTER-STR)
```

Sets the record filter expression of the specified table to the expression in the FILTER-STR argument. If the filter of the given table is currently active then the new filter expression is directly applied to all records and the match-filter state of all records are recomputed.

SETFILTERSTR returns TRUE if it has been able to compile the given filter string expression, otherwise NIL is returned. Note that you only get the result of the compilation. If the filter of the given table is currently active and recomputing all match-filter states of the corresponding records fails then you will not notice that from the result of this function. The recommended way to set a new filter expression is like follows:

```
(SETFILTERACTIVE Table NIL) ; always succeeds.
(IF (NOT (SETFILTERSTR Table filter-string))
  (ERROR "Can't set filter string for %s!" (TABLENAME Table))
)
(IF (NOT (SETFILTERACTIVE Table TRUE))
  (ERROR "Can't activate filter for %s!" (TABLENAME Table))
)
```

If SETFILTERSTR is called with a value of NIL for the FILTER-STR argument then nothing happens and NIL is returned.

Example: (SETFILTERSTR Table "> Value 0.0").

See also

```
GETFILTERSTR
,
SETFILTERACTIVE
,
SETMATCHFILTER
```

.

1.292 MUIbase/RECORDS

RECORDS

RECORDS returns the number of records in a table.

(RECORDS TABLE)

Returns the number of records in the given table. You may append a star to the table name for counting the number of records that match the filter of the table.

See also

RECORD
,
RECNUM
.

1.293 MUIbase/RECORD

RECORD

RECORD returns a record pointer for a given record number.

(RECORD TABLE NUM)

Returns the record pointer to the NUM-th record in the given table or NIL if a record with this number doesn't exist. You may add a star to the table name to get the NUM-th record that matches the record filter of the table.

Please note that record numbers start with 1 and record number 0 is used for the initial record.

See also

RECORDS
,
RECNUM
.

1.294 MUIbase/SELECT

SELECT

SELECT extracts and returns various data from records.

```
(SELECT [DISTINCT] EXPRLIST FROM TABLELIST
 [WHERE WHERE-EXPR] [ORDER BY ORDERLIST])
```

where EXPRLIST is either a simple star * or a list of expressions with optional titles separated by commas:

```
EXPRLIST:      * | EXPR "title", ...
```

and TABLELIST is a list of table names:

```
TABLELIST:     TABLE[*] [ident], ...
```

For each table in the table list you can specify an identifier. This can be very useful if a table occurs more than once in the table list (see example of comparing ages below). If you add a star to a table then only the records matching the currently defined filter of that table will be examined.

The orderlist has the following syntax:

```
ORDERLIST:     EXPR [ASC | DESC], ...
```

where EXPR, ... can be arbitrary expressions or field numbers. For example (SELECT Name FROM ... ORDER BY 1) will sort the result by the Name attribute. You may specify ASC or DESC for an ascending or descending order. If none of them are present then an ascending order is assumed.

How it works

The select-from-where query builds the (mathematical) cross product of all tables in the table list (it examines all sets of records in TABLE, ...) and checks the where-expression (if any). If the where-expression results to TRUE (or there is no where-expression) then a list is build whose elements are calculated by the expression list in the select-part. If you have specified a single star for the expression list then the list contains the values of all attributes belonging to tables in the table list (except virtual attributes and buttons).

The result of the query is a list of lists. The first list entry contains the title strings, the remaining ones contain the values of the from-list in the matching records.

Examples

See

Query examples
for some examples using the SELECT function.

See also

FOR ALL
.

1.295 MUIbase/Gui functions

Gui functions

=====

This section describes functions for manipulating gui elements.

SETCURSOR
Placing the cursor on a gui element.

GETDISABLED
Getting the disabled state of a gui element.

SETDISABLED
Setting the disabled state of a gui element.

GETWINDOWDISABLED
Getting the disabled state of a window.

SETWINDOWDISABLED
Setting the disabled state of a window.

GETWINDOWOPEN
Getting open/close state of a window.

SETWINDOWOPEN
Opening/closing of a window.

1.296 MUIbase/SETCURSOR

SETCURSOR

SETCURSOR sets the cursor on a gui element.

(SETCURSOR ATTR-OR-TABLE)

Sets the cursor on the given attribute or table gui object. The function also opens the window where the attribute/table resides in if

the window was not open.

SETCURSOR returns TRUE if everything went ok (window could be opened) or NIL on failure.

1.297 MUIbase/GETDISABLED

GETDISABLED

GETDISABLED returns the disabled state of an attribute.

(GETDISABLED ATTR)

Returns the disabled state of the specified attribute in the current record.

See also

SETDISABLED
,
GETWINDOWDISABLED
.

1.298 MUIbase/SETDISABLED

SETDISABLED

SETDISABLED sets the disabled state of an attribute.

(SETDISABLED ATTR BOOL)

Sets the disabled state of the specified attribute in the current record to the value of BOOL. Returns the new value of the disabled state.

See also

GETDISABLED
,
SETWINDOWDISABLED
.

1.299 MUIbase/GETWINDOWDISABLED

GETWINDOWDISABLED

GETWINDOWDISABLED returns the disabled state of a window.

(GETWINDOWDISABLED ATTR-OR-TABLE)

Returns the state of the disabled flag of the window in which the specified attribute or table resides. If the attribute or table resides in the root window then NIL is returned.

See also

SETWINDOWDISABLED
,
GETWINDOWOPEN
,
GETDISABLED
.

1.300 MUIbase/SETWINDOWDISABLED

SETWINDOWDISABLED

SETWINDOWDISABLED sets the disabled state of a window.

(SETWINDOWDISABLED ATTR-OR-TABLE DISABLED)

Sets the state of the disabled flag of the window button in which the specified attribute or table resides to the value of DISABLED. If you disable a window, the window is closed and the corresponding window button is disabled. You can't disable the root window of a project.

SETWINDOWDISABLED returns the new state of the window's disabled flag.

See also

GETWINDOWDISABLED
,
SETWINDOWOPEN
,
SETDISABLED
.

1.301 MUIbase/GETWINDOWOPEN

GETWINDOWOPEN

GETWINDOWOPEN returns the open state of a window.

(GETWINDOWOPEN ATTR-OR-TABLE)

Returns the open state of the window where the given attribute/table resides.

See also

SETWINDOWOPEN
,
GETWINDOWDISABLED
.

1.302 MUIbase/SETWINDOWOPEN

SETWINDOWOPEN

SETWINDOWOPEN opens and closes a window.

(SETWINDOWOPEN ATTR-OR-TABLE OPEN)

Opens or closes the window in which the given attribute/table resides. If OPEN is non-NIL then the window is opened, otherwise it is closed. You cannot close the root window of a project.

SETWINDOWOPEN returns the new open state of the window.

See also

GETWINDOWOPEN
,
SETWINDOWDISABLED
.

1.303 MUIbase/Project functions

Project functions

=====

This section lists functions dealing with projects.

PROJECTNAME
Getting the project name.

CHANGES

Getting number of changes made to current project.

1.304 MUIbase/PROJECTNAME**PROJECTNAME**

PROJECTNAME returns the project name.

(PROJECTNAME)

PROJECTNAME returns the name of the current project as a string or NIL if no name has been defined yet.

See also

CHANGES
.

1.305 MUIbase/CHANGES**CHANGES**

CHANGES returns the number of changes in the current project.

(CHANGES)

Returns an integer containing the number of changes since the last save operation of the current project.

See also

PROJECTNAME
.

1.306 MUIbase/System functions**System functions**
=====

This section lists functions accessing the operating system.

EDIT
 Launching external editor asynchronously.

EDIT*
 Launching external editor synchronously.

VIEW
 Launching external viewer asynchronously.

VIEW*
 Launching external viewer synchronously.

SYSTEM
 Calling external commands.

STAT
 Examining a file.

TACKON
 Creating pathname from dirname and filename.

DIRNAME
 Getting directory name from a path.

FILENAME
 Getting last component of a path.

TODAY
 Getting current date.

NOW
 Getting current time.

MESSAGE
 Showing messages to the user.

GC
 Forcing garbage collection.

1.307 MUIbase/EDIT

EDIT

EDIT launches the external editor.

(EDIT FILENAME)

Starts the external editor for editing the specified file. The external editor can be set in menu item Preferences - External editor (see

External editor
) . EDIT starts the external editor

asynchronously, that is, the function returns to the caller immediately.

EDIT returns TRUE if it was successful in starting the editor, else it returns NIL.

See also

```
EDIT*  
,  
VIEW  
,  
SYSTEM  
.
```

1.308 MUIbase/EDIT*

```
EDIT*  
-----
```

EDIT* is the star version of EDIT and has the same effect as EDIT (see

```
EDIT  
) . The only difference is that EDIT* starts the external editor synchronously and waits until the user exits the editor.
```

See also

```
EDIT  
,  
VIEW*  
,  
SYSTEM  
.
```

1.309 MUIbase/VIEW

```
VIEW  
----
```

VIEW launches the external viewer.

(VIEW FILENAME)

Starts the external viewer for displaying the specified file. The external viewer can be set in menu item Preferences - External viewer (see

```
External viewer  
) . VIEW starts the external viewer asynchronously, that is, the function returns to the caller immediately.
```

VIEW returns TRUE if it was successful in starting the viewer, else it returns NIL.

See also

```
VIEW*
,
EDIT
,
SYSTEM
.
```

1.310 MUIbase/VIEW*

```
VIEW*
```

VIEW* is the star version of VIEW and has the same effect as VIEW (see

```
VIEW
). The only difference is that VIEW* starts the external
viewer synchronously and waits until the user exits the viewer.
```

See also

```
VIEW
,
EDIT*
,
SYSTEM
.
```

1.311 MUIbase/SYSTEM

```
SYSTEM
```

SYSTEM calls an external program.

```
(SYSTEM FMT [ARG ...])
```

Calls an external program. The command line to call the program is generated from FMT and the optional arguments like in the SPRINTF function (see

```
SPRINTF
). SYSTEM waits until the called program exits.
If you don't want SYSTEM to wait then use a command line that starts
the program in the background.
```

SYSTEM returns TRUE on success and NIL on failure, e.g. when the

command line could not be executed or the called command returned an error code.

Example: (SYSTEM "run %s %s" "clock" "digital") launches the system's clock in digital mode.

See also

```

EDIT
/
EDIT*
/
VIEW
/
VIEW*
.

```

1.312 MUIbase/STAT

STAT

STAT examines a filename.

(STAT FILENAME)

Examines if the specified filename exists in the file system. STAT returns NIL if the filename could not be found, 0 if the filename exists and is a directory, and an integer value greater than 0 if the filename exists and is a regular file.

1.313 MUIbase/TACKON

TACKON

TACKON creates a pathname.

(TACKON DIRNAME FILENAME)

Joins DIRNAME and FILENAME to a pathname. TACKON knows how to deal with colons and slashes in DIRNAME. It returns the pathname as a string or NIL if DIRNAME or FILENAME is NIL.

Example: (TACKON "Sys:System" "CLI") results to "Sys:System/CLI".

See also

```

FILENAME
/
DIRNAME

```


.

1.314 MUIbase/FILENAME

FILENAME

FILENAME extracts the filename part of a path name.

(FILENAME PATH)

Extracts the last component of the given path name. There is no check whether PATH actually refers to a file, thus it is also possible to use FILENAME to get the name of a sub-directory. FILENAME returns its result as a string or NIL if PATH is NIL.

Example: (FILENAME "Sys:System/CLI") results to "CLI".

See also

DIRNAME

/

TACKON

.

1.315 MUIbase/DIRNAME

DIRNAME

DIRNAME extracts the directory part of a path name.

(DIRNAME PATH)

Extracts the directory part of the given path name. There is no check whether PATH actually refers to a file, thus it is also possible to use DIRNAME to get the name of a parent directory. DIRNAME returns its result as a string or NIL if PATH is NIL.

Example: (DIRNAME "Sys:System/CLI") results to "Sys:System".

See also

FILENAME

/

TACKON

.

1.316 MUIbase/TODAY

TODAY

TODAY returns the current date.

(TODAY)

Returns the current date as a date value.

See also

NOW

.

1.317 MUIbase/NOW

NOW

NOW returns the current time.

(NOW)

Returns the current time as a time value.

See also

TODAY

.

1.318 MUIbase/MESSAGE

MESSAGE

MESSAGE displays a message to the user.

(MESSAGE FMT [ARG ...])

Sets the window title of the pause/abort window (if it is open).
The title string is generated from FMT and the optional arguments like
in the SPRINTF function (see

SPRINTF

).

MESSAGE returns the formatted title string.

Example: (MESSAGE "6 * 7 = %i" (* 6 7)).

See also

```
PRINT
,
PRINTF
.
```

1.319 MUIbase/GC

GC
--

GC forces garbage collection.

(GC)

Forces garbage collection and returns NIL. Normally garbage collection is done automatically from time to time.

1.320 MUIbase/Pre-defined variables

Pre-defined variables

=====

MUIbase knows some pre-defined global variables.

In the current version there exists only one global variable: stdout
(see

```
stdout
).
```

1.321 MUIbase/Pre-defined constants

Pre-defined constants

=====

The following pre-defined constants can be used in any expression for programming.

Name	Type	Value	Comment
NIL	any	NIL	
TRUE	bool	TRUE	
RESET	string	"\33c"	
NORMAL	string	"\33[0m"	

ITON	string	"\33[3m"	
ITOFF	string	"\33[23m"	
ULON	string	"\33[4m"	
ULOFF	string	"\33[24m"	
BFON	string	"\33[1m"	
BFOFF	string	"\33[22m"	
ELITEON	string	"\33[2w"	
ELITEOFF	string	"\33[1w"	
CONDON	string	"\33[4w"	
CONDOFF	string	"\33[3w"	
WIDEON	string	"\33[6w"	
WIDEOFF	string	"\33[5w"	
NLQON	string	"\33[2\"z"	
NLQOFF	string	"\33[1\"z"	
INT_MAX	integer	2147483647	Maximum integer value
INT_MIN	integer	-2147483648	Minimum integer value
HUGE_VAL	real	1.797693e+308	Largest absolute real value
PI	real	3.14159265359	
OSVER	integer	<OS version>	
OSREV	integer	<OS revision>	
MBVER	integer	<MUIbase version>	
MBREV	integer	<MUIbase revision>	
LANGUAGE	string	depends	Default language.

See

Constants

, for more information about constants. For defining your own constants, use the #define preprocessing directive (see

```
#define
).
```

1.322 MUIbase/Functional parameters

Functional parameters

=====

You can pass a function as an argument to another function. This is useful for defining functions of higher order, e.g. for sorting or mapping a list.

To call a function that has been passed in an argument you have to use the FUNCALL function (see

```
FUNCALL
).
```

Example:

```

(DEFUN map (l fun)                # arguments: list and function
  (LET (res)                      # local variable res, initialized with NIL
    (DOLIST (i l)                 # for all items one by one
      (SETQ res
```

```

                (CONS (FUNCALL fun i) res)      # apply function and
            )                                     # build new list
        )
    (REVERSE res)                               # we need to reverse the new list
)

```

You can now use the map function for example to increment all items of a list of integers:

```
(map (LIST 1 2 3 4) 1+) results to ( 2 3 4 5 ).
```

See also

```

    FUNCALL
    ,
    MAPFIRST
    .

```

1.323 MUIbase/Type specifiers

Type specifiers

=====

It is possible to specify the type of a local variable by adding a type specifier behind the name. The following type specifiers exist:

Specifier	Description
:INT	for integers
:REAL	for reals
:STR	for strings
:MEMO	for memos
:DATE	for dates
:TIME	for times
:LIST	for lists
:FILE	for file handles
:FUNC	for functions of any type
:TABLE	for record pointers to TABLE

The type specifier appends the variable name as in the following example:

```
(LET (x:INT (y:REAL 0.0) z) ...)
```

The example defines three new variables *x*, *y* and *z*, where *x* is of type integer and initialized with *NIL*, *y* is of type real and initialized with 0.0, and *z* is an untyped variable initialized with *NIL*.

The advantage of the type specifiers is that the compiler can detect more type errors, e.g. if you have a function:

```
(DEFUN foo (x:INT) ...)
```

and call it with (foo "bar") then the compiler generates an error message. However, if you call foo with an untyped value, e.g. (foo (FIRST list)) then no error checking can be done at compile time because the type of (FIRST list) is unknown.

For reasons of speed no type checking is currently done at run time. It could be implemented but then would add a little overhead which is not really necessary as the wrong type will result in a type error sooner or later anyway.

Type specifiers for record pointers have another useful feature. If you tag a variable as a record pointer to a table then you can access all attributes of this table by using the variable name instead of the table name in the attribute path. E.g. if you have a table Foo with an attribute Bar, and you define a variable foo as:

```
(LET (foo:Foo)
```

then you can print the Bar attribute of the third record by using:

```
(SETQ foo (RECORD Foo 3)) (PRINT foo.Bar)
```

Note that in a select-from-where expression, variables defined in the from list automatically have a type of record pointer to the corresponding table.

1.324 MUIbase/Semantics of expressions

Semantics of expressions

=====

The semantics of expressions are very important for understanding what a program does. This section lists the semantics depending on syntactical expressions.

(FUNC [EXPR ...])

Evaluates EXPR ... and then calls the function FUNC (call by value). Returns the return value of the called function. In MUIbase there exists some non-strict functions, e.g. AND, OR and IF. These functions may not evaluate all expressions. For more information about non-strict functions, see

Lisp syntax

,

AND

,

OR

, and

IF

.

([EXPR ...])

Evaluates EXPR ... and returns the value of the last expression (see

PROGN
) . An empty expression () evaluates to NIL.

TABLE
Returns the program record pointer of the given table.

TABLE*
Returns the gui record pointer of the given table.

ATTRPATH
Returns the contents of the specified attribute. The attribute path specifies which record is used to extract the attribute value. For example Table.Attribute uses the program record of Table to extract the value of the attribute, Table.ReferenceAttribute.Attribute uses the program record of Table to extract the value of the reference attribute (which is a record pointer) and then uses this record to extract the value of Attribute.

LOCALVAR
Returns the contents of the local variable. Local variables can be defined e.g. with LET (see
LET
) .

LOCALVAR.ATTRPATH
Uses the record pointer of LOCALVAR to determine the value of the specified attribute.

1.325 MUIbase/Function triggering

Function triggering
=====

For automatic execution of MUIbase programs you can specify trigger functions for projects, tables and attributes which are called in specific cases. This section lists all available trigger possibilities.

onOpen
Trigger after opening a project.

onClose
Trigger when closing a project.

onChange
Trigger when changing a project.

New trigger
Trigger for allocating a new record.

Delete trigger

Trigger for deleting a record.

Attribute trigger

Trigger for changing an attribute.

Virtual attributes

How to write functions for virtual attributes.

1.326 MUIbase/onOpen

onOpen

After opening a project, MUIbase searches the project's program for a function called onOpen. If such a function exists then this function is called without any arguments.

Example

```
-----  
(DEFUN onOpen ()  
  (ASKBUTTON NIL "Thank you for opening me!" NIL NIL)  
)
```

See also

```
onClose  
,  
onChange  
, demo Trigger.mb.
```

1.327 MUIbase/onClose

onClose

Before closing a project, MUIbase searches the project's program for a function called onClose. If such a function exists then this function is called without any arguments. In the current version the result of the trigger function is ignored and the project is closed regardless of its return value.

If you do changes to the project in the onClose function then MUIbase will ask you for saving the project first before it is actually closed. If you use menu item Project - Save & Close for closing the project, the trigger function is called before saving the project, thus the changes are saved automatically.

Example

```

-----
(DEFUN onClose ()
  (ASKBUTTON NIL "Good bye!" NIL NIL)
)

```

See also

```

    onOpen
    ,
    onChange
    , demo Trigger.mb.

```

1.328 MUIbase/onChange

onChange

Whenever the user makes changes to a project or after saving a project, MUIbase searches the project's program for a function called onChange. If such a function exists then this function is called without any arguments. This can be used to count the changes a user does to a project.

Example

```

-----
(DEFUN onChange ()
  (SETQ Control.NumChanges (CHANGES))
)

```

In the above example Control.NumChanges could be a virtual attribute somewhere in an exactly-one-record table for displaying the project's number of changes.

See also

```

    onOpen
    ,
    onClose
    , demo Trigger.mb.

```

1.329 MUIbase/New trigger

New trigger

When the user wants to allocate a new record by selecting one of the menu items New record or Duplicate record and the New trigger of that table has been set to a MUIbase program function then this trigger

function is executed. The New trigger function can be set in the table requester (see

Creating tables
)

The trigger function receives NIL or a record pointer as the first and only argument. NIL means that the user wants to allocate a new record, a record pointer means that the user wants to duplicate this record. If the trigger function has more than one argument then these are initialized with NIL. The trigger function should allocate the new record by calling the NEW function (see

NEW
)

The result returned by the trigger function will be examined. If it returns a record pointer then this record will be displayed.

The New trigger is also called when a MUIbase program calls the NEW* function (see

NEW*
)

Sample New trigger function

```
(DEFUN newRecord (init)
  (PROG1
    (NEW Table init)
    ...
  )
)
```

See also

NEW*
,
Delete trigger
.

1.330 MUIbase/Delete trigger

Delete trigger

When the user wants to delete a record by selecting menu item Delete record and the Delete trigger of that table has been set to a MUIbase program function then this trigger function is executed. The Delete trigger function can be set in the table requester (see

Creating tables
)

The trigger function receives a boolean argument as its only argument. If the argument is non-NIL then the function should ask the user if he really wants to delete the record. If so, the function

should call DELETE (see
 DELETE
) for deleting the record.

The Delete trigger is also called when a MUIbase program calls the
 DELETE* function (see
 DELETE*
).

Sample Delete trigger function

```
-----
(DEFUN deleteRecord (requester)
  (DELETE Table requester)
)
```

See also

```
DELETE*
,
New trigger
.
```

1.331 MUIbase/Attribute trigger

Attribute trigger

In the attribute requester (see
 Creating attributes
) you can define
 a trigger function that is called whenever the user wants to change the
 attribute contents.

If you have defined such a trigger function for an attribute and the
 user changes the value of that attribute then the record contents are
 not automatically updated with the new value. Instead the value is
 passed to the trigger function as first argument. The trigger function
 can now check the value and may refuse it. To store the value in the
 record you have to use the SETQ function.

The trigger function should return the result of the SETQ call or
 the old value of the attribute if it decides to refuse the new one.

The trigger function is also called when a MUIbase program calls the
 SETQ* function (see
 SETQ*
) for setting a value to the attribute.

Sample attribute trigger function

```
-----
(DEFUN setAmount (amount)
  (IF SOME-EXPRESSION
```

```

        (SETQ Table.Amount amount)
        (ASKBUTTON NIL "Invalid value!" NIL NIL)
    )
    Table.Amount ; return current value
)

```

See also

SETQ*

1.332 MUIbase/Programming virtual attributes

Programming virtual attributes

In MUIbase virtual attributes are special attributes that calculate their value on the fly whenever it is needed. E.g. if you go to another record by clicking on one of the arrow buttons in a table's panel bar and a virtual attribute in that table has its Immediate flag (see

Attribute object editor

) set then the value of that attribute is

computed and displayed. For computing the value the attribute's Compute trigger function is called. This trigger function can be specified in the attribute requester (see

Type specific settings

).

The return value of this function defines the value of the virtual attribute. If you don't specify a Compute trigger function for a virtual attribute then the attribute's value is NIL.

You can also trigger the calculation of a virtual attribute by simply accessing it in an MUIbase program, so e.g. if you have a button that should compute the value of the virtual attribute, you only need to specify a function for the button like the following one:

```

(DEFUN buttonHook ()
  VIRTUAL-ATTR
)

```

You can also set a virtual attribute to any value by using the SETQ function:

```

(SETQ VIRTUAL-ATTR EXPR)

```

However if you access the virtual attribute after the SETQ call then the value of the virtual attribute is recomputed.

There is no caching of the value of a virtual attribute because it's not easy to know when the value has to be recomputed and when not. So you should access virtual attributes rarely and cache the value in local variables for further use yourself.

For an example on how to use virtual attributes please check the Movie.mb demo.

See also

Virtual
, demo Movie.db.

1.333 MUIbase/ABConvert

ABConvert

To convert an AmigaBase project to a MUIbase project a small utility called ABConvert exists. It loads an AmigaBase project created with AmigaBase version 2.0 or higher and saves it as an MUIbase project. For projects created by older AmigaBase versions, please load and save them with AmigaBase version 2.4 and then do the conversion.

A Solaris binary of ABConvert can be found in the solaris directory. If you have ever problems with low memory when using the Amiga version, run ABConvert on a Solaris box and your memory problems should be gone.

To run the conversion utility type ABConvert AB-FILE MB-FILE where AB-FILE is an existing AmigaBase project and MB-FILE is a new MUIbase project to be created.

Since MUIbase is a completely new database application, only the structures and datasets of AmigaBase are converted. Programs, filters, orders, etc. must be redone using MUIbase. For converting AmigaBase programs to MUIbase ones it is best to print all programs of the AmigaBase project and then use the guidelines described in the text file PortingABPrograms for converting the programs.

Please note, that the terms used in AmigaBase have been renamed in MUIbase, e.g. an AmigaBase record is now called table, a variable is now called attribute and a dataset is now called record.

MUIbase is relational. Therefore the hierarchy of an AmigaBase project has to be converted into tables. This is done by adding reference attributes to each table (except for the "root" table) which point to the "parent" record.

1.334 MUIbase/Menus

Menus

Menu Project

Info
Information about a project.

About
About MUIbase.

About MUI
About Magic User Interface.

Clear - Project
Start a new project.

Clear - Records
Delete all records.

Open new
Opens new root window.

Open - Project
Loads project.

Open - Structure
Loads project without records.

Save
Saves project to disk.

Save & Reorg
Saves and reorganizes a project.

Save & Reorg as
Saves and reorganizes with new filename.

Delete
Deletes project from disk.

Close
When your are done with a project.

Save & Close
Saves then closes project.

Swap records
Flush all records to disk.

Structure editor
Open structure editor.

Print structure
Getting an overview of all tables and attributes.

Quit
Exit MUIbase.

Menu Preferences

Record memory
Size of record buffer.

Record delete requester?
Safety requester when deleting records.

Ext editor for programming?
Use your favorite editor for programming.

Icon creation?
Create project icons.

Set icon tool name
Set tool name for project icons.

Set formats
Set real and date format.

Set external editor
Specify your external editor.

Set external viewer
Specify your external viewer.

Confirm save & reorg?
Safety requester when reorganizing a project.

Confirm quit?
Safety requester when quitting MUIbase.

Project dependent settings
Global versus project local preferences.

MUI
MUI's preferences.

Load preferences
Load preferences from disk.

Save preferences
Save preferences to disk.

Menu Table

New record
Adding a new record.

Duplicate record

Copying a record.

Delete record
If you don't need a record any more.

Goto Record
Browsing records.

Change filter
Specify a filter expression.

Change order
How to specify an order.

Search for
How to search for a record.

Search forward
Go to the next matching record.

Search backward
Go to the previous matching record.

Import records
How to import records.

Export records
How to export records.

Menu Program

Edit
Where to enter a MUIbase program.

Compile
Compiling a program.

Include directory
Where to look for external include files.

Debug information
Compile with or without debug information.

Output file
Where program output goes.

Queries
Open the query editor.

1.335 MUIbase/Acknowledgments

Acknowledgments

Thanks to:

- * Mats Granstrom for his long term beta testing of MUIbase, his ideas to improve it, and for writing the tutorial. Mats sometimes writes really funny emails. It's always a pleasure to read them.
- * Ralph Reuchlein (Ralphie) for huge bug report lists, tons of emails with ideas and suggestions, and his unlimited time for discussing them. Without his ideas (like e.g. the #-directives for programming) MUIbase would not be what it is today.

Ralphie also created and maintains the MUIbase home page
<http://www.amigaworld.com/support/muibase>.

- * Thomas Fricke for beta-testing and his images to improve the appearance of MUIbase. He is the one who painted the MUIbase and project icons, the MUIbase empty display image, the window open/closed images, and others.
- * André Schenk and Klaus Gessner for beta-testing and their knowledge about relational databases and SQL.
- * Allan Odgaard for his TextEditor class and his great support to improve it for MUIbase.
- * Oliver Roberts for beta testing and some very good bug reports, and for FlGP-Ed (see <http://www.nanunanu.org/~oliver/>).
- * Petri Nordlund for permission to use his registration files from Executive for MUIbase. If you don't know Executive yet, you should definitely check it out. It's available on Aminet.
- * Henning Thilemann for ideas and beta testing.

1.336 MUIbase/Author

Author

MUIbase is developed by:

Steffen Gutmann
Wiesentalstr. 30
73312 Geislingen/Eybach
GERMANY

Email: <gutmann@ieee.org>

1.337 MUIbase/Function index

Function index

#define
#define

#elif
#elif

#else
#else

#endif
#endif

#if
#if

#ifdef
#ifdef

#ifndef
#ifndef

#include
#include

#undef
#undef

*
mul

+
add

-
sub

-
fdiv

1+
1+

1-
1-

<
Comparison functions

<*

Comparison functions

<=

Comparison functions

<=*

Comparison functions

<>

Comparison functions

<>*

Comparison functions

=

Comparison functions

=*

Comparison functions

>

Comparison functions

>*

Comparison functions

>=

Comparison functions

>=*

Comparison functions

ABS

ABS

AND

AND

APPEND

APPEND

ASC

ASC

ASKBUTTON

ASKBUTTON

ASKCHOICE

ASKCHOICE

ASKCHOICESTR

ASKCHOICESTR

ASKDIR

ASKDIR

ASKFILE
ASKFILE

ASKINT
ASKINT

ASKMULTI
ASKMULTI

ASKOPTIONS
ASKOPTIONS

ASKSTR
ASKSTR

ATTRNAME
ATTRNAME

CASE
CASE

CHANGES
CHANGES

CHR
CHR

CONCAT
CONCAT

CONCAT2
CONCAT2

COND
COND

CONS
CONS

CONSP
Type predicates

COPYREC
COPYREC

DATE
DATE

DATEP
Type predicates

DEFUN
DEFUN

DEFUN*
DEFUN*

DEFVAR
DEFVAR

DELETE
DELETE

DELETE*
DELETE*

DELETEALL
DELETEALL

DIRNAME
DIRNAME

DIV
DIV

DO
DO

DOLIST
DOLIST

DOTIMES
DOTIMES

EDIT
EDIT

EDIT*
EDIT*

ERROR
ERROR

EXIT
EXIT

FCLOSE
FCLOSE

FERROR
FERROR

FFLUSH
FFLUSH

FGETCHAR
FGETCHAR

FGETCHARS
FGETCHARS

FGETMEMO
FGETMEMO

FGETSTR
FGETSTR

FILENAME
FILENAME

FILLMEMO
FILLMEMO

FIRST
FIRST

FOPEN
FOPEN

FOR ALL
FOR ALL

FORMATMEMO
FORMATMEMO

FPRINTF
FPRINTF

FPUTCHAR
FPUTCHAR

FPUTMEMO
FPUTMEMO

FPUTSTR
FPUTSTR

FUNCALL
FUNCALL

GC
GC

GETDISABLED
GETDISABLED

GETLABELS
GETLABELS

GETMATCHFILTER
GETMATCHFILTER

GETWINDOWDISABLED
GETWINDOWDISABLED

GETWINDOWOPEN
GETWINDOWOPEN

HALT
HALT

IF
 IF

INDENTMEMO
 INDENTMEMO

INDEXBRK
 INDEXBRK

INDEXBRK*
 INDEXBRK*

INDEXSTR
 INDEXSTR

INDEXSTR*
 INDEXSTR*

INSMIDSTR
 INSMIDSTR

INT
 INT

INTP
 Type predicates

LAST
 LAST

LEFTSTR
 LEFTSTR

LEN
 LEN

LENGTH
 LENGTH

LET
 LET

LIKE
 LIKE

LINE
 LINE

LINES
 LINES

LIST
 LIST

LISTP
 Type predicates

LISTTOMEMO
LISTTOMEMO

LOWER
LOWER

MAPFIRST
MAPFIRST

MAX
MAX

MAXLEN
MAXLEN

MEMO
MEMO

MEMOP
Type predicates

MEMOTOLIST
MEMOTOLIST

MESSAGE
MESSAGE

MIDSTR
MIDSTR

MIN
MIN

MOD
MOD

NEW
NEW

NEW*
NEW*

NEXT
NEXT

NOT
NOT

NOW
NOW

NTH
NTH

NULLP
Type predicates

onChange
 onChange

onClose
 onClose

onOpen
 onOpen

OR
 OR

PRINT
 PRINT

PRINTF
 PRINTF

PROG1
 PROG1

PROGN
 PROGN

PROJECTNAME
 PROJECTNAME

RANDOM
 RANDOM

REAL
 REAL

REALP
 Type predicates

RECNUM
 RECNUM

RECP
 Type predicates

REMCHARS
 REMCHARS

REPLACESTR
 REPLACESTR

REST
 REST

RETURN
 RETURN

REVERSE
 REVERSE

RIGHTSTR
RIGHTSTR

ROUND
ROUND

SETCURSOR
SETCURSOR

SETDISABLED
SETDISABLED

SETLABELS
SETLABELS

SETMATCHFILTER
SETMATCHFILTER

SETMIDSTR
SETMIDSTR

SETQ
SETQ

SETQ*
SETQ*

SETWINDOWDISABLED
SETWINDOWDISABLED

SETWINDOWOPEN
SETWINDOWOPEN

SORTLIST
SORTLIST

SORTLISTGT
SORTLISTGT

SPRINTF
SPRINTF

STAT
STAT

stdout
stdout

STR
STR

STRP
Type predicates

SYSTEM
SYSTEM

TACKON
TACKON

TIME
TIME

TIMEP
Type predicates

TODAY
TODAY

TRIMSTR
TRIMSTR

TRUNC
TRUNC

UPPER
UPPER

VIEW
VIEW

VIEW*
VIEW*

WORD
WORD

WORDS
WORDS

1.338 MUIbase/Concept index

Concept index

1:1 relationships
One to one relationships

1:n relationships
One to many relationships

ABConvert
ABConvert

Accessing record contents
Accessing record contents

Acknowledgments
Acknowledgments

- Active object
 - Active object
- Active table
 - Active object
- Attribute functions
 - Attribute functions
- Attribute management
 - Attribute management
- Attribute object editor
 - Attribute object editor
- Attribute objects
 - Attribute objects
- Attribute trigger
 - Attribute trigger
- Attribute types
 - Attribute types
- Attribute types (table)
 - Table of attribute types
- Attributes
 - Attributes
- Author
 - Author
- Balance objects
 - Balance objects
- BetterString
 - Third party material
- Bool attributes
 - Bool type
- Boolean functions
 - Boolean functions
- Browsing records
 - Browsing records
- Buttons
 - Button
- Change filter
 - Changing filters
- Change order
 - Changing orders

- Changing attributes
 - Changing attributes
- Changing tables
 - Changing tables
- Choice attributes
 - Choice type
- Clear project
 - Clear project
- Close project
 - Close project
- Command syntax
 - Command syntax
- Comparison functions
 - Comparison functions
- Confirm quit
 - Confirm quit
- Confirm save & reorg
 - Confirm save & reorg
- Constants
 - Constants
- Copying MUIbase
 - Copying
- Creating attributes
 - Creating attributes
- Creating tables
 - Creating tables
- Custom classes
 - Third party material
- Data retrieval
 - Data retrieval
- Data types for programming
 - Data types for programming
- Date attributes
 - Date type
- Defining commands
 - Defining commands
- Delete project
 - Delete project

- Delete record
 - Delete records
- Delete trigger
 - Delete trigger
- Deleting attributes
 - Delete attributes
- Deleting tables
 - Delete tables
- Disclaimer
 - Disclaimer
- Display field
 - Display field
- Display management
 - Display management
- Distribution
 - Distribution
- Duplicate record
 - Add records
- Empty display image
 - Empty display image
- Empty order
 - Empty order
- Entering bool values
 - Change records
- Entering choice values
 - Change records
- Entering date values
 - Change records
- Entering NIL value
 - Change records
- Entering reference values
 - Change records
- Entering time values
 - Change records
- Export records
 - Export records
- External classes
 - Third party material

External editor
External editor

External editor for programming
External editor for programming

External viewer
External viewer

File format
File format

File format for import and export
Import file format

Filename attributes
String type

Filter
Filter

Filter examples
Filter examples

Filter expression
Filter expression

Font-name attributes
String type

Formats
Formats

Forward-backward search
Forward-backward search

Function triggering
Function triggering

Functional parameters
Functional parameters

Group editor
Group editor

Groups
Groups

Gui functions
Gui functions

How to register
Registration

I-O functions
I-O functions

Icon creation
Icon creation

Icon tool name
Icon tool name

Icons
Third party material

Image attributes
String type

Image editor
Image editor

Images
Images

Import and Export
Import and Export

Import file example
Sample import file

Import records
Importing records

Info
Info

Initial record
Records (concept)

Input requesting functions
Input requesting functions

Installing MUIbase
Getting started

Integer attributes
Integer type

Kinds of programs
Kinds of programs

Label editor
Label editor

Lisp syntax
Lisp syntax

List functions
List functions

Many to many relationships
Many to many relationships

- Masks
 - Masks
- Mathematical functions
 - Mathematical functions
- Memo attributes
 - Memo type
- Memo context menu
 - Changing records
- Memo functions
 - Memo functions
- Memory consumption
 - Memory consumption
- Menus
 - Menus
- MUI
 - Third party material
- MUI preferences
 - MUI
- n:m relationships
 - Many to many relationships
- Name conventions for program symbols
 - Name conventions
- New attribute
 - Creating attributes
- New record
 - Adding records
- New table
 - Creating tables
- New trigger
 - New trigger
- onChange
 - onChange
- onClose
 - onClose
- One to many relationships
 - One to many relationships
- One to one relationships
 - One to one relationships

- onOpen
 - onOpen
- Open project
 - Open project
- Order
 - Order
- Panel editor
 - Panel editor
- Panels
 - Panels
- Popups in cycle chain
 - Popups in cycle chain
- Pre-defined constants
 - Pre-defined constants
- Pre-defined variables
 - Pre-defined variables
- Preferences
 - Preferences
- Preferences file
 - Load and save preferences
- Preprocessing
 - Preprocessing
- Print structure
 - Print structure
- Printing queries
 - Printing queries
- Program control functions
 - Program control functions
- Program debug information
 - Program debug information
- Program editor
 - Program editor
- Program include directory
 - Program include directory
- Program output file
 - Program output file
- Programming
 - Programming MUIbase

- Programming language
 - Programming language
- Programming virtual attributes
 - Programming virtual attributes
- Project dependent settings
 - Project dependent settings
- Project functions
 - Project functions
- Projects
 - Projects
- Query editor
 - Query editor
- Query examples
 - Query examples
- Quitting MUIbase
 - Getting started
- Real attributes
 - Real type
- Record delete requester
 - Record delete requester
- Record filter
 - Record filter
- Record functions
 - Record functions
- Record memory
 - Record memory
- Record-editing
 - Record-editing
- Records
 - Records (concept)
- Reference attributes
 - Reference
- Reference filter
 - Reference filter
- Register group editor
 - Register group editor
- Register groups
 - Register groups

- Registration
 - Registration
- Relationships
 - Relationships
- Reorganization
 - Save project
- Root window
 - Windows
- Save project
 - Save project
- Search for
 - Search for
- Search pattern examples
 - Search pattern examples
- Search requester
 - Search requester
- Select-from-where queries
 - Select-from-where queries
- Semantics of expressions
 - Semantics of expressions
- Sorting attributes
 - Sorting attributes
- Sorting tables
 - Sorting tables
- Space editor
 - Space editor
- Space objects
 - Space objects
- Starting MUIbase
 - Getting started
- String attributes
 - String type
- String functions
 - String functions
- Structure editor
 - Structure editor
- Swap records
 - Swap records

- System functions
 - System functions
- Table functions
 - Table functions
- Table management
 - Table management
- Tables
 - Tables
- Tabular display
 - Data retrieval
- Text editor
 - Text editor
- Text objects
 - Text objects
- TextEditor
 - Third party material
- Third party material
 - Third party material
- Time attributes
 - Time type
- Tutorial
 - Tutorial
- Type conversion functions
 - Type conversion functions
- Type predicates
 - Type predicates
- Type specific settings
 - Type specific settings
- Type specific settings for attribute objects
 - Attribute object editor
- Type specifiers
 - Type specifiers
- User interface
 - User interface
- Virtual attributes
 - Virtual
- Why lisp?
 - Why lisp?

Window editor
Window editor

Windows
Windows