

Lotus Chart: Align property

{button ,AL('H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) The horizontal alignment of a text value.

Data type

Integer (Enumerated)

Syntax

object.Font.Align = *alignmentvalue*

alignmentvalue = *object.Font.Align*

Legal values

| <u>Value</u> | <u>Description</u> |
|----------------|----------------------------------|
| \$DefaultAlign | Use current default alignment |
| \$LeftAlign | Align on the left margin |
| \$RightAlign | Align on the right margin |
| \$CenterAlign | Center the text |
| \$Justify | Use right and left justification |

Lotus Chart: AreaPlacement property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_AREAPLACEMENT_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The layout of series in an area chart.

Data type

Integer (Enumerated)

Syntax

areachart.AreaPlacement = *placementvalue*

placementvalue = *areachart*.AreaPlacement

Legal values

| <u>Value</u> | <u>Description</u> |
|--------------|---|
| \$InRows | Places each series in a separate row, one behind the other. (Available for 3D charts only.) |
| \$Stacked | Places each series stacked on the previous series. |
| \$Overlapped | Overlaps the series. |

Lotus Chart: AreValuesManual property

{button ,AL(`H_CHARTMAJORGRIDLINES_CLASS ',0)} [See list of classes](#)

(Read-write) Whether gridlines are placed manually.

Data type

Boolean

Syntax

chart.axis.MajorGridlines.AreValuesManual = *trueorfalse*

trueorfalse = *chart.axis.MajorGridlines.AreValuesManual*

Legal values

True (1) or False (0)

Usage

When AreValuesManual is True, you can specify the number of gridlines to display (using the Count property), and the value at which to show each individual grid line (using the Value property).

{button ,AL(`H_VALUE_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: BackColorIndex property

{button ,AL(`H_BACKGROUND_CLASS ;H_BORDER_CLASS ;H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) The color for the background of a filled object.

Data type

Integer

Syntax

object.BackColorIndex = *color*

color = *object*.BackColorIndex

Legal values

0..255

Usage

The number you specify is an index into the current color palette.

Use BackColorIndex to set the color for the background of a filled object. To set the color of the pattern, use the ForeColorIndex property. If the pattern is set to a solid color, then only the ForeColorIndex shows up.

{button ,AL(`H_FORECOLORINDEX_PROPERTY_MEMDEF ;H_PATTERN_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: BarClusterGapPercent property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_BARCLUSTERGAPPERCENT_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The space between clusters of bars, calculated as a percentage of the width of one bar.

Data type

Integer

Syntax

barchart.BarClusterGapPercent = *clusterpercent*

clusterpercent = *barchart*.BarClusterGapPercent

Legal values

0..100, with 0 leaving no space between the bars, and 100 leaving space equivalent to the width of a bar between the bars.

Lotus Chart: BarOverlapPercent property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_BAROVERLAPPERCENT_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The percentage of overlap of each bar in a bar chart. The percentage is calculated as the percent of the width of one bar.

Data type

Integer

Syntax

barchart.**BarOverlapPercent** = *overlappercent*

overlappercent = *barchart*.**BarOverlapPercent**

Legal values

0..100, with 0 showing no overlap between the bars, and 100 having the bars overlap entirely, so that each bar is placed directly on top of the next bar.

Lotus Chart: BarPlacement property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) How bar chart bars are organized.

Data type

Integer (Enumerated)

Syntax

barchart.**BarPlacement** = *placement*

placement = *barchart*.**BarPlacement**

Legal values

| <u>Value</u> | <u>Description</u> |
|--------------|--|
| \$InRows | Places each bar in a separate row, one behind the other. (Available for 3D charts only.) |
| \$Stacked | Places each bar stacked on the previous bar. |
| \$Clustered | Arranges bars next to each other, in groups. |

Lotus Chart: Bold property

{button ,AL(^H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to use a bold font for the specified text string.

Data type

Boolean

Syntax

object.Font.Bold = trueorfalse

trueorfalse = object.Font.Bold

Legal values

True (1) or False (0)

Lotus Chart: ColumnHeaders property

{button ,AL(`H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ',0)}

[See list of classes](#)

(Read-write) The headers of columns in a table.

Data type

ChartDataLabels

Syntax

chart.Table.ColumnHeaders(num).attribute = value

or

chart.NumberGrid.ColumnHeaders(num).attribute = value

value = chart.Table.ColumnHeaders(num).attribute

or

value = chart.NumberGrid.ColumnHeaders(num).attribute

Legal values

The values for *num* in ColumnHeaders can be between 1 and 300.

{button ,AL(`H_CHARTDATALABELS_CLASS ',0)} [See related topics](#)

Lotus Chart: ColumnTotals property

{button ,AL('H_CHARTNUMBERGRID_CLASS ',0)} [See list of classes](#)

(Read-write) A column showing the totals in a number grid.

Data type

ChartDataLabels

Syntax

chart.NumberGrid.ColumnTotals.attribute = value

value = chart.NumberGrid.ColumnTotals.attribute

{button ,AL('H_CHARTDATALABELS_CLASS ',0)} [See related topics](#)

Lotus Chart: ConnectPoints property

{button ,AL(^H_CHARTSERIES_CLASS',0)} [See list of classes](#)

(Read-write) Whether to connect the points in a series of a line chart.

Data type

Boolean

Syntax

chart.Series(*num*).ConnectPoints = *trueorfalse*

trueorfalse = *chart*.Series(*num*).ConnectPoints

Legal values

True (1) or False (0)

The values for *num* in the Series can be between 1 and 30.

Lotus Chart: ConnectStackedBarLines property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_ISSTACKED_CONNECTSTACKEDBARLINES_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) Whether to show lines connecting bars in a stacked bar chart.

Data type

Boolean

Syntax

chart.ConnectStackedBarLines = *trueorfalse*

trueorfalse = *chart.ConnectStackedBarLines*

Legal values

True (1) or False (0)

Lotus Chart: Count property

{button ,AL(^H_CHARTMAJORGRIDLINES_CLASS ',0)} [See list of classes](#)
(Read-write) The number of manually placed grid lines on the specified axis.

Data type

Integer

Syntax

number = *chart.axis*.MajorGridLines.Count

chart.axis.MajorGridLines.Count = *number*

Lotus Chart: CrossPointIsManual property

{button ,AL(`H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether the point at which the other axis crosses the current axis (the axis intercept) is set manually.

Data type

Boolean

Syntax

chart.axis.Scale.CrossPointIsManual = trueorfalse

trueorfalse = chart.axis.Scale.CrossPointIsManual

Legal values

True (1) or False (0)

{button ,AL(`H_CROSSPOINT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: CrossPoint property

{button ,AL('H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) The value at which the opposite axis is drawn. Also known as the axis intercept.

Data type

Double

Syntax

chart.axis.Scale.CrossPoint = *crosspoint*

crosspoint = *chart.axis.Scale.CrossPoint*

{button ,AL('H_CROSSPOINT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: DataArrangement property

{button ,AL(^H_CHARTNUMBERGRID_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to transpose the data in the number grid.

Data type

Integer (Enumerated)

Syntax

chart.NumberGrid.DataArrangement = arrangement

arrangement = chart.NumberGrid.DataArrangement

Legal values

| <u>Value</u> | <u>Definition</u> |
|--------------|-----------------------|
| \$ByColumns | Parse data columnwise |
| \$ByRows | Parse data rowwise |

Lotus Chart: DataLabels property

{button ,AL('H_CHARTSERIES_CLASS',0)} [See list of classes](#)

(Read-write) Value and percent labels that appear for each data point in a series.

Data type

ChartDataLabels

Syntax

chart.**Series**(*num*).**DataLabels**.*attribute* = *value*

value = *chart*.**Series**(*num*).**DataLabels**.*attribute*

{button ,AL('H_SHOWVALUELABELS_PROPERTY_MEMDEF ;H_SHOWPERCENTLABELS_PROPERTY_MEMDEF ;H_CHARTDATALABELS_CLASS',0)} [See related topics](#)

Lotus Chart: DataPoints property

{button ,AL(`H_CHARTSERIES_CLASS`,0)} [See list of classes](#)

{button ,AL(`H_EXAMPLE_SERIES_DATAPOINTS_PROPERTY_EXSCRIPT`,1)} [See example](#)

(Read-write) The data points in a chart series.

Data type

ChartDataPoint

Syntax

chart.Series(num).DataPoints(num).attribute = value

value = chart.Series(num).DataPoints(num).attribute

{button ,AL(`H_CHARTDATAPOINT_CLASS`,0)} [See related topics](#)

Lotus Chart: DepthPercent property

{button ,AL(^H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) The depth of each pie as a percentage of its radius. Available only for 3D pies.

Data type

Integer

Syntax

chart.Pies.DepthPercent = *value*

value = *chart.Pies.DepthPercent*

Legal values

1..100

Lotus Chart: Edge property

{button ,AL(`H_CHARTAXIS_CLASS ;H_CHARTDATAPOINT_CLASS ;H_CHARTGRIDLINES_CLASS ;H_CHARTGRIDLINE_CLASS ;H_CHARTLEGEND_CLASS ;H_CHARTMAJORGRIDLINES_CLASS ;H_CHARTMAJORGRIDLINE_CLASS ;H_CHARTNUMBERGRID_CLASS ;H_CHARTPLOTWALL_CLASS ;H_CHARTPLOT_CLASS ;H_CHARTREGRESSION_CLASS ;H_CHARTSERIES_CLASS ;H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ;H_CHARTTITLEBOX_CLASS ;H_CHARTTABLEGRIDLINES_CLASS ;H_CHARTTABLEGRIDLINE_CLASSES ',0)} [See list of classes](#)

(Read-write) The edge of an object.

Data type

Border

Syntax

object.**Edge**.*attribute* = *value*

value = *object*.**Edge**.*attribute*

{button ,AL(`H_BORDER_CLASS ',0)} [See related topics](#)

Lotus Chart: Elevation property

{button ,AL(^H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) The angle between the viewer's eye and the plane of the pie (at 90 degrees, the pie would appear to be two-dimensional). Available only for 3D pies.

Data type

Integer

Syntax

chart.Pies.Elevation = value

value = chart.Pies.Elevation

Legal values

5..85 degrees

Lotus Chart: EndPoint property

{button ,AL('H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)

(Read-Write) The last point for which to calculate the trend (regression) line.

Data type

Integer

Syntax

chart.Series(num).Regression.EndPoint = datapoint

datapoint = chart.Series(num).Regression.EndPoint

Legal values

datapoint can be any valid data point in the series.

Usage

If you do not set the endpoint, the default is the last point in the series.

{button ,AL('H_XAXISMINIMUM_PROPERTY_MEMDEF ;H_XAXISMAXIMUM_PROPERTY_MEMDEF ;H_STARTPOINT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Entries property

{button ,AL(`H_CHARTLEGEND_CLASS ',0)} [See list of classes](#)

{button ,AL(`H_EXAMPLE_LEGEND_ENTRIES_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-Write) The entries in the chart legend.

Data type

ChartLegendEntries

Syntax

chart.Legend.Entries(num).attribute = value

value = chart.Legend.Entries(num).attribute

{button ,AL(`H_CHARTLEGENDENTRIES_CLASS ',0)} [See related topics](#)

Lotus Chart: ExplodePercent property

{button ,AL(`H_CHARTPIESLICE_CLASS ',0)} [See list of classes](#)

(Read-write) The percentage to explode a single pie slice.

Data type

Integer

Syntax

chart.PieSlices(num).ExplodePercent = percent

percent = chart.PieSlices(num).ExplodePercent

Legal values

0..100

{button ,AL(`H_SLICEEXPLOSION_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Exponent property

{button ,AL(`H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to display the subtitle for the axis scale.

Data type

Boolean

Syntax

chart.axis.Scale.Exponent = *exponent*

exponent = *chart.axis.Scale.Exponent*

Legal values

True (1) or False (0)

{button ,AL(`H_SUBTITLEISMANUAL_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: FaceName property

{button ,AL('H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) The font to use for a text string.

Data type

String

Syntax

object.Font.FaceName = *font*

font = *object*.Font.FaceName

Lotus Chart: Fill property

{button ,AL(^H_CHARTDATAPOINT_CLASS ;H_CHARTLEGEND_CLASS ;H_CHARTPIESLICE_CLASS ;H_CHART
PLOTWALL_CLASS ;H_CHARTPLOT_CLASS ;H_CHARTSERIES_CLASS ;H_CHARTTABLEBASE_CLASS ;H_
CHARTTITLEBOX_CLASS ;H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLE_CLASS ',0)} [See list of classes](#)

(Read-write) The pattern and color used to fill a solid area (such as a plot, legend, or bar chart bars).

Data type

Background

Syntax

object.Fill.attribute = value

value = object.Fill.attribute

{button ,AL(^H_BACKGROUND_CLASS ;H_FORECOLORINDEX_PROPERTY_MEMDEF ;H_BACKCOLORINDEX_
PROPERTY_MEMDEF ;H_PATTERN_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: FirstHorizontal property

{button ,AL(`H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ',0)}

[See list of classes](#)

(Read-write) Attributes for the first horizontal line in a number grid or table under a chart.

Data type

ChartTableGridline

Syntax

chart.Table.FirstHorizontal.attribute = value

or

chart.NumberGrid.FirstHorizontal.attribute = value

value = chart.Table.FirstHorizontal.attribute

or

value = chart.NumberGrid.FirstHorizontal.attribute

{button ,AL(`H_CHARTTABLEGRIDLINE_CLASS ;H_INTERIORHORIZONTALS_PROPERTY_MEMDEF ;H_INTERIORVERTICALS_PROPERTY_MEMDEF ;H_FIRSTVERTICAL_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: FirstVertical property

{button ,AL(^H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ',0)}

[See list of classes](#)

(Read-write) Attributes for the first vertical line in a number grid or table under a chart.

Data type

ChartTableGridline

Syntax

chart.Table.FirstVertical.attribute = value

or

chart.NumberGrid.FirstVertical.attribute = value

value = chart.Table.FirstVertical.attribute

or

value = chart.NumberGrid.FirstVertical.attribute

{button ,AL(^H_CHARTTABLEGRIDLINE_CLASS ;H_INTERIORHORIZONTALS_PROPERTY_MEMDEF ;H_INTERIORVERTICALS_PROPERTY_MEMDEF ;H_FIRSTHORIZONTAL_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Font property

{button ,AL(^H_CHARTDATALABELS_CLASS ;H_CHARTLEGENDENTRIES_CLASS ;H_CHARTLEGEND_CLASS ;
H_CHARTPIETITLES_CLASS ;H_CHARTTEXTENTRY_CLASS ;H_CHARTTEXTLABELS_CLASS ;H_CHARTTE
XTLABEL_CLASS ;H_CHARTZAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The font of a text value.

Data type

Font

Syntax

object.**Font**.*attribute* = *value*

value = *object*.**Font**.*attribute*

Lotus Chart: ForeColorIndex property

{button ,AL(`H_BACKGROUND_CLASS ;H_BORDER_CLASS ;H_FONT_CLASS ',0)} [See list of classes](#)

{button ,AL(`H_EXAMPLE_FORECOLORINDEX_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The color for the pattern in a filled object.

Data type

Integer

Syntax

object.ForeColorIndex = *color*

color = *object*.ForeColorIndex

Legal values

0..255

Usage

The number you specify is an index into the current color palette.

Use ForeColorIndex to set the color of the pattern of a filled object. To set the background of the fill pattern, use the BackColorIndex property. If the pattern is set to a solid color, then only the ForeColorIndex shows up.

{button ,AL(`H_BACKCOLORINDEX_PROPERTY_MEMDEF ;H_PATTERN_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Format property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The format of numbers.

Data type

NumberFormat

Syntax

object.Format.attribute = value

value = object.Format.attribute

{button ,AL('H_NUMBERFORMAT_CLASS ',0)} [See related topics](#)

Lotus Chart: ApplyChartStyle method

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

Applies the specified style to the chart.

Syntax

chart.ApplyChartStyle(stylename)

Parameters

stylename

The name of the file containing the chart style, specified as a string.

Returns

Void

{button ,AL('H_SAVECHARTSTYLE_METHOD_MEMDEF ',0)} [See related topics](#)

Lotus Chart: DeletePicture method

{button ,AL(^H_CHARTSERIES_CLASS ;H_CHARTPLOT_CLASS',0)} [See list of classes](#)

Deletes the picture from the plot or specified bar chart series.

Syntax

chart.Plot.DeletePicture

or

chart.Series(*num*).DeletePicture

Returns

Void

{button ,AL(^H_PASTEPICTURE_METHOD_MEMDEF ;H_HASPICTURE_PROPERTY_MEMDEF ;H_PICTUREUNIT
S_PROPERTY_MEMDEF ;H_PICTURELAYOUT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: PastePicture method

{button ,AL(`H_CHARTSERIES_CLASS ;H_CHARTPLOT_CLASS',0)} [See list of classes](#)

Pastes the picture on the Clipboard into the plot or specified bar chart series.

Syntax

chart.Plot.PastePicture

or

chart.Series(*num*).PastePicture

Returns

Void

{button ,AL(`H_DELETEPICTURE_METHOD_MEMDEF ;H_HASPICTURE_PROPERTY_MEMDEF ;H_PICTUREUNITS_PROPERTY_MEMDEF ;H_PICTURELAYOUT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: SaveChartStyle method

{button ,AL(`H_CHARTBASE_CLASS ',0)} [See list of classes](#)

Saves the current look of the chart as a new style.

Syntax

chart.SaveChartStyle(*stylename*)

Parameters

stylename

The file name to assign to the chart style, specified as a string.

Returns

Void

{button ,AL(`H_APPLYCHARTSTYLE_METHOD_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Select method

Selects a chart part so the user can manipulate it.

Syntax

object.Select

Returns

Void

Usage

When writing a script to manipulate charts, you do not need to select a chart part using this method. Use the Select method to select a portion of the chart for user manipulation.

Lotus Chart: UpdateLinks method

{button ,AL(`H_CHARTBASE_CLASS ',0)} [See list of classes](#)

Updates all link values in the chart.

Syntax

chart.UpdateLinks

Returns

Void

Usage

Use this method when the LinkUpdateMethod property is set to \$LinkManual.

{button ,AL(`H_LINKUPDATEMETHOD_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Background class

The fill of a region.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------------|-----------------|
| ChartDataPoint | Fill |
| ChartLegend | Fill |
| ChartNumberGrid | Fill |
| ChartPieSlice | Fill |
| ChartPieSliceGroup | Fill |
| ChartPlot | Fill |
| ChartPlotWall | Fill |
| ChartSeries | Fill |
| ChartTable | Fill |
| ChartTableBase | Fill |
| ChartTitleBox | Fill |

Lotus Chart: Border class

The border around an object or a line edge.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|---------------------|-----------------|
| ChartAxis | Edge |
| ChartDataPoint | Edge |
| ChartGridline | Edge |
| ChartGridlines | Edge |
| ChartLegend | Edge |
| ChartMajorGridline | Edge |
| ChartMajorGridlines | Edge |
| ChartNumberGrid | Edge |
| ChartPlot | Edge |
| ChartPlotWall | Edge |
| ChartRegression | Edge |
| ChartSeries | Edge |
| ChartTable | Edge |
| ChartTableBase | Edge |
| ChartTableGridline | Edge |
| ChartTableGridlines | Edge |
| ChartTitleBox | Edge |

Lotus Chart: ChartAxisScale class

The numeric scale of an axis.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartAxis | Scale |

Lotus Chart: ChartAxis class

An axis of a chart.

Base class

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|---------------------------|
| ChartBase | XAxis, YAxis, SecondYAxis |

{button ,AL(`H_CHARTZAXIS_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartBase class

A chart of any type. This class contains all other chart classes.

Base classes

None

Usage

The way in which you create a chart differs depending on the application you're using. For information on creating a chart, search for "Charts, creating with LotusScript" in the help Index.

When you create a chart, you automatically create all the components of a chart.

Lotus Chart: ChartDataLabels class

A set of value labels in a chart.

Base class

None

Contained by

| <u>Class</u> | <u>Property</u> |
|-----------------|--|
| ChartBase | StackedTotalsLabels |
| ChartNumberGrid | ColumnHeaders, ColumnTotals, RowHeaders, RowTotals |
| ChartPies | PercentLabels, TextLabels, ValueLabels |
| ChartSeries | DataLabels |
| ChartTable | ColumnHeaders, RowHeaders |
| ChartTableBase | ColumnHeaders, RowHeaders |

Lotus Chart: ChartDataPoints class

The collection of all data markers for a specific chart series.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartSeries | DataPoints |

Usage

You cannot manipulate a collection of data points, you can only access attributes of individual points. To access an individual data point, use the ChartDataPoint class.

{button ,AL(`H_CHARTDATAPOINT_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartDataPoint class

A single data value in a chart series.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartSeries | DataPoints |

Usage

You access an individual data point using an index value, such as DataPoints(1), which represents the first data point.

Lotus Chart: ChartDataSource class

The link source of a chart subobject.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------------|-----------------|
| ChartLegend | DataLink |
| ChartLegendEntries | DataLink |
| ChartSeries | DataLink |
| ChartTextEntries | DataLink |
| ChartTextEntry | DataLink |
| ChartTextLabels | TickLabelsLink |
| ChartTitleBox | DataLink |

Lotus Chart: ChartGridlines class

A set of ruled lines on a chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|--|
| ChartAxis | MajorTickmarks, MinorGridlines, MinorTickmarks |

Usage

To access a single grid line, use the ChartGridline class.

Lotus Chart: ChartGridline class

A straight line on a chart.

Base classes

None

Usage

ChartGridline contains base attributes used both in the ChartMajorGridline and ChartTableGridline classes.

Lotus Chart: ChartLegendEntries class

The collection of text entries in a chart legend.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartLegend | Entries |

{button ,AL(`H_CHARTLEGEND_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartLegend class

The chart legend.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | Legend |

Usage

To access the entries of a chart legend, use the ChartLegendEntries class.

{button ,AL('H_CHARTLEGENDETRIES_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartMajorGridlines class

The collection of major grid lines on an axis.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartAxis | MajorGridlines |

Usage

To access an individual major grid line, use the ChartMajorGridline class.

{button ,AL('H_CHARTMAJORGRIDLINE_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartMajorGridline class

A major grid line on an axis.

Base classes

ChartGridline

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartAxis | MajorGridlines |

Usage

You access an individual major grid line using an index value, such as MajorGridlines(1), which represents the first major grid line.

To access the collection of all major gridlines, use the ChartMajorGridlines class.

{button ,AL(`H_CHARTGRIDLINES_CLASS ;H_CHARTMAJORGRIDLINES_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartNumberGrid class

A number grid chart.

Base classes

ChartTableBase

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | NumberGrid |

{button ,AL('H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartPieSlices class

The collection of slices in an individual pie chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | PieSlices |
| ChartPie | Slices |

Usage

You cannot manipulate a collection of pie slices, you can only access attributes of individual pie slices. To access an individual slice in a pie chart, use the ChartPieSlice class.

{button ,AL(`H_CHARTPIESLICE_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartPieSlice class

A single slice in an individual pie chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | PieSlices |

Lotus Chart: ChartPies class

The collection of pies in a pie chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | Pies |

Lotus Chart: ChartPieTitles class

A collection of pie titles or subtitles.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-------------------|
| ChartPies | Subtitles, Titles |

Usage

To access a single pie title or subtitle, use the ChartPieTitle class.

{button ,AL('H_CHARTPIETITLE_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartPieTitle class

An individual pie title or subtitle.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-------------------|
| ChartPies | Subtitles, Titles |

Usage

You access an individual pie title or subtitle using an index value, such as Titles(1), which represents the title in the first pie.

To access the collection of pie titles or subtitles, use the ChartPieTitles class.

{button ,AL(`H_CHARTPIETITLES_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartPlotWall class

The wall or floor of a 3D chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|---|
| ChartPlot | LeftWall, RightWall, PlatformFrontFace, PlatformRightFace, PlatformTopFace |

Lotus Chart: ChartPlot class

The plot area of a chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | Plot |

Lotus Chart: ChartRegression class

The regression (trend) line for a series.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartSeries | Regression |

Lotus Chart: ChartSeriesCollection class

The collection of data series in a chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | Series |

Usage

You cannot manipulate a collection of chart series, you can only access attributes of individual series. To access a single series, use the ChartSeries class.

{button ,AL('H_CHARTSERIES_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartSeries class

A single series in a chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | Series |

Usage

You access an individual series using an index value, such as Series(1), which represents the first series.

Lotus Chart: ChartTableBase class

The base class for number grids and tables under a chart.

Base classes

None

Usage

ChartTableBase contains base attributes used both in the ChartTable and ChartNumberGrid classes.

{button ,AL('H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLE_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartTableGridlines class

A set of grid lines in a chart table or number grid.

Base classes

ChartGridlines

Contained by

| <u>Class</u> | <u>Property</u> |
|-----------------|---|
| ChartNumberGrid | InteriorHorizontals, InteriorVerticals |
| ChartTable | InteriorHorizontals, InteriorVerticals |
| ChartTableBase | InteriorHorizontals, InteriorVerticals |

Usage

To access the first horizontal or first vertical grid line, use the ChartTableGridline class.

{button ,AL('H_CHARTGRIDLINES_CLASS ;H_CHARTTABLEGRIDLINE_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartTableGridline class

A single grid line in a table under a chart or number grid.

Base classes

ChartGridline

Contained by

| <u>Class</u> | <u>Property</u> |
|-----------------|--------------------------------|
| ChartNumberGrid | FirstHorizontal, FirstVertical |
| ChartTable | FirstHorizontal, FirstVertical |
| ChartTableBase | FirstHorizontal, FirstVertical |

Usage

To access the all grid lines other than the first horizontal or vertical, use the ChartTableGridlines class.

{button ,AL('H_CHARTGRIDLINES_CLASS ;H_CHARTTABLEGRIDLINES_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartTable class

A table under a chart.

Base classes

ChartTableBase

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | Table |

{button ,AL('H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLEBASE_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartTextEntries class

The entries in a note or title.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|---------------|-----------------|
| ChartTitleBox | Lines |

Usage

To access a single line of text in a note or title, use the ChartTextEntry class.

{button ,AL('H_CHARTTEXTENTRY_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartTextEntry class

A single entry in a chart note or title, or the title or subtitle of a chart axis.

Base classes

ChartTextLabel

Contained by

| <u>Class</u> | <u>Property</u> |
|---------------|-----------------|
| ChartAxis | Subtitle, Title |
| ChartTitleBox | Lines |

Usage

You access an individual entry in a line or note using an index value, such as Lines(1), which represents the first line in a title or note.

To access the collection of text entries in a title or note, use the ChartTextEntries class.

{button ,AL('H_CHARTTEXTENTRIES_CLASS ;H_CHARTTEXTLABEL_CLASS ',0)} [See related topics](#)

Lotus Chart: ChartTextLabels class

A collection of text labels.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartAxis | TickLabels |
| ChartZAxis | TickLabels |

Lotus Chart: ChartTextLabel class

A text label in a pie slice.

Base classes

None

Usage

ChartTextLabel contains base attributes used in the ChartTextEntry class.

Lotus Chart: ChartTitleBox class

A chart title or note.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | Note, Title |

Lotus Chart: ChartZAxis class

The z-axis of a 3D chart.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------|-----------------|
| ChartBase | ZAxis |

{button ,AL(`H_CHARTAXIS_CLASS ',0)} [See related topics](#)

Lotus Chart: Font class

The text style of an object.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|--------------------|-----------------|
| ChartDataLabels | Font |
| ChartLegend | Font |
| ChartLegendEntries | Font |
| ChartPieTitles | Font |
| ChartTextEntry | Font |
| ChartTextLabel | Font |
| ChartTextLabels | Font |
| ChartZAxis | Font |

Lotus Chart: NumberFormat class

The numeric format of an object.

Base classes

None

Contained by

| <u>Class</u> | <u>Property</u> |
|----------------------------|---|
| ChartAxis | Format |
| ChartBase | StackedTotalsFormat |
| ChartPies | PercentLabelFormat, ValueLabelFormat |
| ChartTableSeriesCollection | Format |

Lotus Chart: Background class members

Properties

BackColorIndex

ForeColorIndex

Pattern

Shape

Methods

None

Functions

None

Events

None

Lotus Chart: Border class members

Properties

BackColorIndex

ForeColorIndex

Pattern

Style

Width

Methods

None

Functions

None

Events

None

Lotus Chart: ChartAxisScale class members

Properties

[CrossPoint](#)
[CrossPointIsManual](#)
[Exponent](#)
[IsAscending](#)
[Maximum](#)
[MaximumIsManual](#)
[Minimum](#)
[MinimumIsManual](#)
[MinorInterval](#)
[MinorIntervalsManual](#)
[ScaleType](#)

Methods

None

Functions

None

Events

None

Lotus Chart: ChartAxis class members

Properties

[Edge](#) AS [Border](#)
[Format](#) AS [NumberFormat](#)
[MajorGridlines](#) AS [ChartMajorGridline](#)
[MajorGridlines](#) AS [ChartMajorGridlines](#)
[MajorTickmarkPlacement](#)
[MajorTickmarks](#) AS [ChartGridlines](#)
[MinorGridlines](#) AS [ChartGridlines](#)
[MinorTickmarkPlacement](#)
[MinorTickmarks](#) AS [ChartGridlines](#)
[Scale](#) AS [ChartAxisScale](#)
[Subtitle](#) AS [ChartTextEntry](#)
[SubtitlesManual](#)
[SubtitlePlacement](#)
[TickLabelCharWidth](#)
[TickLabelPlacement](#)
[TickLabels](#) AS [ChartTextLabels](#)
[TickLabelSkip](#)
[TickLabelWidthsManual](#)
[Title](#) AS [ChartTextEntry](#)
[Visible](#)

Methods

[Select](#)

Functions

None

Events

None

Lotus Chart: ChartBase class members

Properties

[AreaPlacement](#)
[BarClusterGapPercent](#)
[BarOverlapPercent](#)
[BarPlacement](#)
[ConnectStackedBarLines](#)
[Height](#)
[InsetLinesFromFrame](#)
[Is3D](#)
[IsDepthEffect](#)
[IsHorizontal](#)
[IsStacked](#)
[Legend AS \[ChartLegend\]\(#\)](#)
[LinePlacement](#)
[LinkUpdateMethod](#)
[Note AS \[ChartTitleBox\]\(#\)](#)
[NumberGrid AS \[ChartNumberGrid\]\(#\)](#)
[Pies AS \[ChartPies\]\(#\)](#)
[PieSlices AS \[ChartPieSlice\]\(#\)](#)
[Plot AS \[ChartPlot\]\(#\)](#)
[RadarLabelEachAxis](#)
[RadarUseIndependentScales](#)
[ScatterUseSeparateXValues](#)
[SecondYAxis AS \[ChartAxis\]\(#\)](#)
[Series AS \[ChartSeries\]\(#\)](#)
[SeriesParse](#)
[StackedTotalsAngle](#)
[StackedTotalsFormat AS \[NumberFormat\]\(#\)](#)
[StackedTotalsLabels AS \[ChartDataLabels\]\(#\)](#)
[Table AS \[ChartTable\]\(#\)](#)
[ThreeDElevation](#)
[ThreeDLateralRotation](#)
[ThreeDLightSource](#)
[ThreeDPlatform](#)
[ThreeDRowGapPercent](#)
[Title AS \[ChartTitleBox\]\(#\)](#)
[Type](#)
[UseCandlestickForHLCO](#)
[UseSmartLookColors](#)
[Width](#)
[X](#)
[XAxis AS \[ChartAxis\]\(#\)](#)
[Y](#)
[YAxis AS \[ChartAxis\]\(#\)](#)
[ZAxis AS \[ChartZAxis\]\(#\)](#)

Methods

[ApplyChartStyle](#)
[SaveChartStyle](#)
[Select](#)
[UpdateLinks](#)

Functions

None

Events

None

Lotus Chart: ChartDataLabels class members

Properties

Font AS Font

Visible

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartDataPoints class members

Properties

None

Methods

None

Functions

None

Events

None

Lotus Chart: ChartDataPoint class members

Properties

[Edge AS Border](#)

[Fill AS Background](#)

[Value](#)

Methods

[Select](#)

Functions

None

Events

None

Lotus Chart: ChartDataSource class members

Properties

Source

Methods

None

Functions

None

Events

None

Lotus Chart: ChartGridlines class members

Properties

Edge AS Border

Visible

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartGridline class members

Properties

Edge AS Border

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartLegendEntries class members

Properties

DataLink AS ChartDataSource

Font AS Font

Methods

None

Functions

None

Events

None

Lotus Chart: ChartLegend class members

Properties

DataLink AS ChartDataSource

Edge AS Border

Entries AS ChartLegendEntries

Fill AS Background

Font AS Font

Height

InsidePlot

Placement

Visible

Width

X

Y

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartMajorGridlines class members

Properties

AreValuesManual

Count

Edge AS Border

Visible

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartMajorGridline class members

Properties

Edge AS Border

Index

Value

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartNumberGrid class members

Properties

[ColumnHeaders](#) AS [ChartDataLabels](#)

[ColumnTotals](#) AS [ChartDataLabels](#)

[DataArrangement](#)

[Edge](#) AS [Border](#)

[Fill](#) AS [Background](#)

[FirstHorizontal](#) AS [ChartTableGridline](#)

[FirstVertical](#) AS [ChartTableGridline](#)

[Height](#)

[InteriorHorizontals](#) AS [ChartTableGridlines](#)

[InteriorVerticals](#) AS [ChartTableGridlines](#)

[RowHeaders](#) AS [ChartDataLabels](#)

[RowTotals](#) AS [ChartDataLabels](#)

[ShowUpperLeft](#)

[Width](#)

[X](#)

[Y](#)

Methods

[Select](#)

Functions

None

Events

None

Lotus Chart: ChartPieSlices class members

Properties

None

Methods

None

Functions

None

Events

None

Lotus Chart: ChartPieSlice class members

Properties

ExplodePercent

Fill AS Background

Visible

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartPies class members

Properties

[DepthPercent](#)
[Elevation](#)
[Height](#)
[LayoutIsManual](#)
[LayoutRowCount](#)
[LightAngle](#)
[PercentLabelFormat](#) AS [NumberFormat](#)
[PercentLabelPlacement](#)
[PercentLabels](#) AS [ChartDataLabels](#)
[ScaleType](#)
[ShadowPlacement](#)
[ShadowSize](#)
[SliceDirection](#)
[SliceExplosion](#)
[SliceSort](#)
[StartAngle](#)
[Subtitles](#) AS [ChartPieTitle](#)
[Subtitles](#) AS [ChartPieTitles](#)
[SubtitlesAreManual](#)
[TextLabels](#) AS [ChartDataLabels](#)
[Titles](#) AS [ChartPieTitle](#)
[Titles](#) AS [ChartPieTitles](#)
[UseBRange](#)
[UseCRange](#)
[UseSeparateLabelRanges](#)
[ValueLabelFormat](#) AS [NumberFormat](#)
[ValueLabelPlacement](#)
[ValueLabels](#) AS [ChartDataLabels](#)
[Width](#)
[X](#)
[Y](#)

Methods

[Select](#)

Functions

None

Events

None

Lotus Chart: ChartPieTitles class members

Properties

Font AS Font

Placement

Text

Visible

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartPieTitle class members

Properties

Text

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartPlotWall class members

Properties

Edge AS Border

Fill AS Background

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartPlot class members

Properties

Edge AS Border

Fill AS Background

HasPicture

Height

LeftWall AS ChartPlotWall

PlatformFrontFace AS ChartPlotWall

PlatformRightFace AS ChartPlotWall

PlatformTopFace AS ChartPlotWall

RadarHasPolygonalBoundary

RightWall AS ChartPlotWall

Visible

Width

X

Y

Methods

DeletePicture

PastePicture

Select

Functions

None

Events

None

Lotus Chart: ChartRegression class members

Properties

Edge AS Border

EndPoint

PlaceInNote

RSquared

Slope

StartPoint

Type

Visible

XAxisMaximum

XAxisMinimum

YIntercept

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartSeriesCollection class members

Properties

None

Methods

None

Functions

None

Events

None

Lotus Chart: ChartSeries class members

Properties

[ConnectPoints](#)
[DataLabels](#) AS [ChartDataLabels](#)
[DataLink](#) AS [ChartDataSource](#)
[DataPoints](#) AS [ChartDataPoint](#)
[Edge](#) AS [Border](#)
[Fill](#) AS [Background](#)
[HasData](#)
[HasPicture](#)
[Index](#)
[LabelAngle](#)
[LabelPlacement](#)
[MarkerSymbol](#)
[MarkerVisible](#)
[Name](#)
[PictureLayout](#)
[PictureUnits](#)
[Regression](#) AS [ChartRegression](#)
[ShowPercentLabels](#)
[ShowValueLabels](#)
[Type](#)
[Use2YAxis](#)
[Visible](#)

Methods

[DeletePicture](#)
[PastePicture](#)
[Select](#)

Functions

None

Events

None

Lotus Chart: ChartTableBase class members

Properties

ColumnHeaders AS ChartDataLabels

Edge AS Border

Fill AS Background

FirstHorizontal AS ChartTableGridline

FirstVertical AS ChartTableGridline

InteriorHorizontals AS ChartTableGridlines

InteriorVerticals AS ChartTableGridlines

RowHeaders AS ChartDataLabels

ShowUpperLeft

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartTableGridlines class members

Properties

[Edge AS Border](#)
[ShowInDataArea](#)
[ShowInHeaderArea](#)
[Visible](#)

Methods

[Select](#)

Functions

None

Events

None

Lotus Chart: ChartTableGridline class members

Properties

[Edge AS Border](#)
[ShowInDataArea](#)
[ShowInHeaderArea](#)
[Visible](#)

Methods

[Select](#)

Functions

None

Events

None

Lotus Chart: ChartTable class members

Properties

ColumnHeaders AS ChartDataLabels

Edge AS Border

Fill AS Background

FirstHorizontal AS ChartTableGridline

FirstVertical AS ChartTableGridline

InteriorHorizontals AS ChartTableGridlines

InteriorVerticals AS ChartTableGridlines

RowHeaders AS ChartDataLabels

ShowUpperLeft

Visible

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartTextEntries class members

Properties

[DataLink](#) AS [ChartDataSource](#)

Methods

None

Functions

None

Events

None

Lotus Chart: ChartTextEntry class members

Properties

DataLink AS ChartDataSource

Font AS Font

Rotation

Text

Visible

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartTextLabels class members

Properties

[Font AS Font](#)

[TickLabelsLink AS ChartDataSource](#)

[Visible](#)

Methods

[Select](#)

Functions

None

Events

None

Lotus Chart: ChartTextLabel class members

Properties

Font AS Font

Rotation

Text

Visible

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartTitleBox class members

Properties

DataLink AS ChartDataSource

Edge AS Border

Fill AS Background

Height

Lines AS ChartTextEntries

Lines AS ChartTextEntry

Placement

Visible

Width

X

Y

Methods

Select

Functions

None

Events

None

Lotus Chart: ChartZAxis class members

Properties

Font AS Font

TickLabels AS ChartTextLabels

TickLabelSkip

Visible

Methods

None

Functions

None

Events

None

Lotus Chart: Font class members

Properties

Align
BackColorIndex
Bold
FaceName
ForeColorIndex
Italic
Plain
Rotation
Size
StrikeThrough
Underline
VertAlign

Methods

None

Functions

None

Events

None

Lotus Chart: NumberFormat class members

Properties

ListSelection

Parentheses

Precision

Type

Methods

None

Functions

None

Events

None

Lotus Chart LotusScript A-Z

A
B
C
D
E
F
G
H
I
J
K
L
M

N
O
P
Q
R
S
T
U
V
W
X
Y
Z

A

[Align property](#)
[ApplyChartStyle method](#)
[AreaPlacement property](#)
[AreValuesManual property](#)

B

[BackColorIndex property](#)
[Background class](#)
[BarClusterGapPercent property](#)
[BarOverlapPercent property](#)
[BarPlacement property](#)
[Bold property](#)
[Border class](#)

C

[ChartAxis class](#)
[ChartAxisScale class](#)
[ChartBase class](#)
[ChartDataLabels class](#)
[ChartDataPoint class](#)
[ChartDataPoints class](#)
[ChartDataSource class](#)
[ChartGridline class](#)
[ChartGridlines class](#)
[ChartLegend class](#)

[ChartLegendEntries class](#)
[ChartMajorGridline class](#)
[ChartMajorGridlines class](#)
[ChartNumberGrid class](#)
[ChartPies class](#)
[ChartPieSlice class](#)
[ChartPieSlices class](#)
[ChartPieTitle class](#)
[ChartPieTitles class](#)
[ChartPlot class](#)
[ChartPlotWall class](#)
[ChartRegression class](#)
[ChartSeries class](#)
[ChartSeriesCollection class](#)
[ChartTable class](#)
[ChartTableBase class](#)
[ChartTableGridline class](#)
[ChartTableGridlines class](#)
[ChartTextEntries class](#)
[ChartTextEntry class](#)
[ChartTextLabel class](#)
[ChartTextLabels class](#)
[ChartTitleBox class](#)
[ChartZAxis class](#)
[ColumnHeaders property](#)
[ColumnTotals property](#)
[ConnectPoints property](#)
[ConnectStackedBarLines property](#)
[Count property](#)
[CrossPoint property](#)
[CrossPointsManual property](#)

D

[DataArrangement property](#)
[DataLabels property](#)
[DataLink property](#)
[DataPoints property](#)
[DeletePicture method](#)
[DepthPercent property](#)

E

[Edge property](#)
[Elevation property](#)
[EndPoint property](#)
[Entries property](#)
[ExplodePercent property](#)
[Exponent property](#)

F

[FaceName property](#)
[Fill property](#)
[FirstHorizontal property](#)
[FirstVertical property](#)
[Font property](#)
[Font class](#)

[ForeColorIndex property](#)
[Format property](#)

H

[HasData property](#)
[HasPicture property](#)
[Height property](#)

I

[Index property](#)
[InsetLinesFromFrame](#)
[InsidePlot property](#)
[InteriorHorizontal property](#)
[InteriorVertical property](#)
[Is3D property](#)
[IsAscending property](#)
[IsDepthEffect property](#)
[IsHorizontal property](#)
[IsStacked property](#)
[Italic property](#)

L

[LabelAngle property](#)
[LabelPlacement property](#)
[LayoutIsManual property](#)
[LayoutRowCount property](#)
[LeftWall property](#)
[Legend property](#)
[LightAngle property](#)
[LinePlacement property](#)
[Lines property](#)
[LinkUpdateMethod property](#)
[ListSelection property](#)

M

[MajorGridlines property](#)
[MajorTickmarkPlacement property](#)
[MajorTickmarks property](#)
[MarkerSymbol property](#)
[MarkerVisible property](#)
[Maximum property](#)
[MaximumIsManual property](#)
[Maximum property](#)
[Minimum property](#)
[MinimumIsManual property](#)
[MinorGridlines property](#)
[MinorInterval property](#)
[MinorIntervalsManual property](#)
[MinorTickmarkPlacement property](#)
[MinorTickmarks property](#)

N

[Name property](#)

[Note property](#)
[NumberFormat class](#)
[NumberGrid property](#)

P

[Parentheses property](#)
[PastePicture method](#)
[Pattern property](#)
[PercentLabelFormat property](#)
[PercentLabelPlacement property](#)
[PercentLabels property](#)
[PictureLayout property](#)
[PictureUnits property](#)
[Pies property](#)
[PieSlices property](#)
[PlaceInNote property](#)
[Placement property](#)
[Plain property](#)
[PlatformFrontFace property](#)
[PlatformRightFace property](#)
[PlatformTopFace property](#)
[Plot property](#)
[Precision property](#)

R

[RadarHasPolygonalBoundary property](#)
[RadarLabelEachAxis property](#)
[RadarUseIndependentScales property](#)
[Regression property](#)
[RightWall property](#)
[Rotation property](#)
[RowHeaders property](#)
[RowTotals property](#)
[RSquared property](#)

S

[SaveChartStyle method](#)
[Scale property](#)
[ScaleType property](#)
[ScatterUseSeparateXValues property](#)
[SecondYAxis property](#)
[Select method](#)
[Series property](#)
[SeriesParse property](#)
[ShadowPlacement property](#)
[ShadowSize property](#)
[Shape property](#)
[ShowInDataArea property](#)
[ShowInHeaderArea property](#)
[ShowPercentLabels property](#)
[ShowUpperLeft property](#)
[ShowValueLabels property](#)
[Size property](#)
[SliceDirection property](#)
[SliceExplosion property](#)

[SliceSort property](#)
[Slope property](#)
[Source property](#)
[StackedTotalsAngle property](#)
[StackedTotalsFormat property](#)
[StackedTotalsLabels property](#)
[StartAngle property](#)
[StartPoint property](#)
[StrikeThrough property](#)
[Style property](#)
[Subtitle property](#)
[SubtitlesManual property](#)
[SubtitlePlacement property](#)
[Subtitles property](#)
[SubtitlesAreManual property](#)

T

[Table property](#)
[Text property](#)
[TextLabelPlacement property](#)
[TextLabels property](#)
[ThreeDElevation property](#)
[ThreeDLateralRotation property](#)
[ThreeDLightSource property](#)
[ThreeDPlatform property](#)
[ThreeDRowGapPercent property](#)
[TickLabelCharWidth property](#)
[TickLabelPlacement property](#)
[TickLabels property](#)
[TickLabelSkip property](#)
[TickLabelsLink property](#)
[TickLabelWidthsManual property](#)
[Title property \(ChartBase class\)](#)
[Title property \(ChartAxis class\)](#)
[Titles property](#)
[Type property \(NumberFormat class\)](#)
[Type property \(ChartRegression class\)](#)
[Type property \(ChartBase and ChartSeries class\)](#)

U

[Underline property](#)
[UpdateLinks method](#)
[Use2YAxis property](#)
[UseBRange property](#)
[UseCandlestickForHLCO property](#)
[UseCRange property](#)
[UseSeparateLabelRanges property](#)
[UseSmartLookColors property](#)

V

[Value property](#)
[ValueLabelFormat property](#)
[ValueLabelPlacement property](#)
[ValueLabels property](#)
[VertAlign property](#)

Visible property

W

Width property (Border class)

Width property (ChartLegend, ChartNumberGrid, ChartPies, ChartPlot, and ChartTitleBox classes)

X

X property

XAxis property

XAxisMaximum property

XAxisMinimum property

Y

Y property

YAxis property

YIntercept property

Z

ZAxis property

Lotus Chart Classes

[Background](#)

[Border](#)

[ChartAxis](#)

[ChartAxisScale](#)

[ChartBase](#)

[ChartDataLabels](#)

[ChartDataPoint](#)

[ChartDataPoints](#)

[ChartDataSource](#)

[ChartGridline](#)

[ChartGridlines](#)

[ChartLegend](#)

[ChartLegendEntries](#)

[ChartMajorGridline](#)

[ChartMajorGridlines](#)

[ChartNumberGrid](#)

[ChartPies](#)

[ChartPieSlice](#)

[ChartPieSlices](#)

[ChartPieTitle](#)

[ChartPieTitles](#)

[ChartPlot](#)

[ChartPlotWall](#)

[ChartRegression](#)

[ChartSeries](#)

[ChartSeriesCollection](#)

[ChartTable](#)

[ChartTableBase](#)

[ChartTableGridline](#)

[ChartTableGridlines](#)

[ChartTextEntries](#)

[ChartTextEntry](#)

[ChartTextLabel](#)

[ChartTextLabels](#)

[ChartTitleBox](#)

[ChartZAxis](#)

[Font](#)

[NumberFormat](#)

Lotus Chart Methods

ApplyChartStyle

DeletePicture

PastePicture

SaveChartStyle

Select

UpdateLinks

Lotus Chart Properties

A
B
C
D
E
F
G
H
I
J
K
L
M

N
O
P
Q
R
S
T
U
V
W
X
Y
Z

A

Align
AreaPlacement
AreValuesManual

B

BackColorIndex
BarClusterGapPercent
BarOverlapPercent
BarPlacement
Bold

C

ColumnHeaders
ColumnTotals
ConnectPoints
ConnectStackedBarLines
Count
CrossPoint
CrossPointsManual

D

DataArrangement
DataLabels
DataLink

DataPoints
DepthPercent

E

Edge
Elevation
EndPoint
Entries
ExplodePercent
Exponent

F

FaceName
Fill
FirstHorizontal
FirstVertical
Font
ForeColorIndex
Format

H

HasData
HasPicture
Height

I

Index
InsetLinesFromFrame
InsidePlot
InteriorHorizontals
InteriorVerticals
Is3D
IsAscending
IsDepthEffect
IsHorizontal
IsStacked
Italic

L

LabelAngle
LabelPlacement
LayoutIsManual
LayoutRowCount
LeftWall
Legend
LightAngle
LinePlacement
Lines
LinkUpdateMethod
ListSelection

M

[MajorGridlines](#)
[MajorTickmarkPlacement](#)
[MajorTickmarks](#)
[MarkerSymbol](#)
[MarkerVisible](#)
[Maximum](#)
[MaximumIsManual](#)
[Minimum](#)
[MinimumIsManual](#)
[MinorGridlines](#)
[MinorInterval](#)
[MinorIntervalsManual](#)
[MinorTickmarkPlacement](#)
[MinorTickmarks](#)

N

[Name](#)
[Note](#)
[NumberGrid](#)

P

[Parentheses](#)
[Pattern](#)
[PercentLabelFormat](#)
[PercentLabelPlacement](#)
[PercentLabels](#)
[PictureLayout](#)
[PictureUnits](#)
[Pies](#)
[PieSlices](#)
[PlaceInNote](#)
[Placement](#)
[Plain](#)
[PlatformFrontFace](#)
[PlatformRightFace](#)
[PlatformTopFace](#)
[Plot](#)
[Precision](#)

R

[RadarHasPolygonalBoundary](#)
[RadarLabelEachAxis](#)
[RadarUseIndependentScales](#)
[Regression](#)
[RightWall](#)
[Rotation](#)
[RowHeaders](#)
[RowTotals](#)
[RSquared](#)

S

[Scale](#)
[ScaleType](#)
[ScatterUseSeparateXValues](#)

[SecondYAxis](#)
[Series](#)
[SeriesParse](#)
[ShadowPlacement](#)
[ShadowSize](#)
[Shape](#)
[ShowInDataArea](#)
[ShowInHeaderArea](#)
[ShowPercentLabels](#)
[ShowUpperLeft](#)
[ShowValueLabels](#)
[Size](#)
[SliceDirection](#)
[SliceExplosion](#)
[SliceSort](#)
[Slope](#)
[Source](#)
[StackedTotalsAngle](#)
[StackedTotalsFormat](#)
[StackedTotalsLabels](#)
[StartAngle](#)
[StartPoint](#)
[StrikeThrough](#)
[Style](#)
[Subtitle](#)
[SubtitlePlacement](#)
[Subtitles](#)
[SubtitlesAreManual](#)

T

[Table](#)
[Text](#)
[TextLabelPlacement](#)
[TextLabels](#)
[ThreeDElevation](#)
[ThreeDLateralRotation](#)
[ThreeDLightSource](#)
[ThreeDPlatform](#)
[ThreeDRowGapPercent](#)
[TickLabelCharWidth](#)
[TickLabelPlacement](#)
[TickLabels](#)
[TickLabelSkip](#)
[TickLabelsLink](#)
[TickLabelWidthsManual](#)
[Title \(ChartBase class\)](#)
[Title \(ChartAxis class\)](#)
[Titles](#)
[Type \(ChartBase and ChartSeries class\)](#)
[Type \(NumberFormat class\)](#)
[Type \(ChartRegression class\)](#)

U

[Underline](#)
[Use2YAxis](#)
[UseBRange](#)

[UseCandlestickForHLCO](#)
[UseCRange](#)
[UseSeparateLabelRanges](#)
[UseSmartLookColors](#)

V

[Value](#)
[ValueLabelFormat](#)
[ValueLabelPlacement](#)
[ValueLabels](#)
[VertAlign](#)
[Visible](#)

W

[Width \(Border class\)](#)
[Width \(ChartLegend, ChartNumberGrid, ChartPies, ChartPlot, and ChartTitleBox classes\)](#)

X

[X](#)
[XAxis](#)
[XAxisMaximum](#)
[XAxisMinimum](#)

Y

[Y](#)
[YAxis](#)
[YIntercept](#)

Z

[ZAxis](#)

Lotus Chart: DataLink property

```
{button ,AL(`H_CHARTLEGENDENTRIES_CLASS ;H_CHARTPIETITLE_CLASS ;H_CHARTTEXTENTRIES_CLASS  
;H_CHARTTEXTENTRY_CLASS ;H_CHARTSERIES_CLASS ;H_CHARTTITLEBOX_CLASS ;H_CHARTLEGEN  
D_CLASS ',0)} See list of classes
```

(Read-write) The link source of a chart subobject.

Data type

ChartDataSource

Syntax

object.DataLink.attribute = value

value = object.DataLink.attribute

Usage

You use the DataLink property to specify the source of the information for the current object. For example, you can specify the source for the text of a chart title using the following syntax:

chart.Title.DataLink.Source = sourcestring

You specify the source for the text of the first line of the chart title using this syntax:

chart.Title.Lines(1).DataLink.Source = sourcestring

```
{button ,AL(`H_CHARTDATASOURCE_CLASS ;H_SOURCE_PROPERTY_MEMDEF ',0)} See related topics
```

Lotus Chart: ScaleType property

{button ,AL(^H_CHARTAXISSCALE_CLASS ;H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The type of scaling to use for an axis or pie charts.

Data type

Integer (Enumerated)

Syntax

chart.axis.Scale.ScaleType = *scalingtype*

or

chart.Pies.ScaleType = *scalingtype*

scalingtype = *chart.axis.Scale.ScaleType*

or

scalingtype = *chart.Pies.ScaleType*

Legal values

For axis scales:

| <u>Value</u> | <u>Description</u> |
|----------------|-----------------------------|
| \$LinearScale | Uses standard, linear scale |
| \$PercentScale | Uses a 100% scale |
| \$LogScale | Uses a logarithmic scale |

For pie charts:

| <u>Value</u> | <u>Description</u> |
|-----------------|---|
| \$Unscaled | Shows all pies the same size |
| \$ScaleByArea | Scales the pies by using greater area for larger pies |
| \$ScaleByHeight | Scales the pies by using greater height for larger pies, for 3D pie charts only |

Lotus Chart: Scale property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The scale of the axis.

Data type

ChartAxisScale

Syntax

chart.axis.**Scale**.*attribute* = *value*

value = *chart.axis*.**Scale**.*attribute*

{button ,AL('H_CHARTAXISSCALE_CLASS ',0)} [See related topics](#)

Lotus Chart: ScatterUseSeparateXValues property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether scatter chart series use separate x values. If true, each plotted series is associated with its own range of x-values.

Data type

Boolean

Syntax

chart.ScatterUseSeparateXValues = trueorfalse

trueorfalse = chart.ScatterUseSeparateXValues

Legal values

True (1) or False (0)

Lotus Chart: SecondYAxis property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Specifies the attributes for the 2nd y-axis in a chart.

Data type

ChartAxis

Syntax

chart.SecondYAxis.attribute = value

value = chart.SecondYAxis.attribute

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See related topics](#)

Lotus Chart: SeriesParse property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether individual series correspond to rows, columns, or arbitrary ranges of the data source.

Data type

Integer (Enumerated)

Syntax

chart.SeriesParse = *parsevalue*

parsevalue = *chart*.SeriesParse

Legal values

| <u>Value</u> | <u>Description</u> |
|----------------|------------------------------------|
| \$ByColumns | Series data is stored in columns |
| \$ByRows | Series data is stored in rows |
| \$Individually | Series data is stored individually |

Lotus Chart: Series property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_SERIES_DATAPOINTS_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The series in a chart.

Data type

ChartSeries

Syntax

chart.Series(num).attribute = value

value = chart.Series(num).attribute

Legal values

1..30 for specifying a single series.

{button ,AL('H_CHARTSERIES_CLASS ',0)} [See related topics](#)

Lotus Chart: ShadowPlacement property

{button ,AL(^H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The placement of the shadow in a 3D pie.

Data type

Integer (Enumerated)

Syntax

chart.Pies.ShadowPlacement = placementvalue

placementvalue = chart.Pies.ShadowPlacement

Legal values

| <u>Value</u> | <u>Description</u> |
|---------------|---|
| \$ShadowNone | Show no shadow |
| \$ShadowFront | Show a shadow in front of the pie chart |
| \$ShadowRight | Show a shadow to the right of the pie chart |
| \$ShadowLeft | Show a shadow to the left of the pie chart |

{button ,AL(^H_SHADOWSIZE_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: ShadowSize property

{button ,AL(^H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The size of the shadow to show in a pie chart.

Data type

Integer (Enumerated)

Syntax

chart.Pies.ShadowSize = *shadowsize*

shadowsize = *chart.Pies.ShadowSize*

Legal values

| <u>Value</u> | <u>Description</u> |
|----------------|-------------------------------|
| \$ShortShadow | Display a small shadow |
| \$MediumShadow | Display a medium-sized shadow |
| \$LongShadow | Display a large shadow |

Usage

This value takes effect only when the ShadowPlacement property is not set to ShadowNone.

{button ,AL(^H_SHADOWPLACEMENT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Shape property

{button ,AL(^H_BACKGROUND_CLASS ',0)} [See list of classes](#)

Note Provided for compatibility; to be implemented in a future release.

Lotus Chart: ShowInDataArea property

{button ,AL('H_CHARTTABLEGRIDLINES_CLASS ;H_CHARTTABLEGRIDLINE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to show gridlines in the data area of a number grid or table under a chart.

Data type

Boolean

Syntax

chart.NumberGrid.gridline.ShowInDataArea = trueorfalse

or

chart.Table.gridline.ShowInDataArea = trueorfalse

trueorfalse = chart.Table.gridline.ShowInDataArea

or

trueorfalse = chart.NumberGrid.gridline.ShowInDataArea

Legal values

True (1) or False (0)

Usage

The values for *gridline* can be FirstHorizontal, FirstVertical, InteriorHorizontal, or InteriorVertical. For example, to turn off gridlines in the data area for the first vertical line in a table under a chart, you'd use a statement like the following:

```
mychart.Table.FirstVertical.ShowInDataArea = False
```

{button ,AL('H_SHOWINHEADERAREA_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: ShowInHeaderArea property

{button ,AL(`H_CHARTTABLEGRIDLINES_CLASS ;H_CHARTTABLEGRIDLINE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to show gridlines in the data area of a number grid or table under a chart.

Data type

Boolean

Syntax

chart.NumberGrid.gridline.ShowInHeaderArea = trueorfalse

or

chart.Table.gridline.ShowInHeaderArea = trueorfalse

trueorfalse = chart.Table.gridline.ShowInHeaderArea

or

trueorfalse = chart.NumberGrid.gridline.ShowInHeaderArea

Legal values

True (1) or False (0)

Usage

The values for *gridline* can be FirstHorizontal, FirstVertical, InteriorHorizontal, or InteriorVertical. For example, to turn off gridlines in the header area for the interior vertical lines in a table under a chart, you'd use a statement like the following:

```
mychart.Table.InteriorVerticals.ShowInHeaderArea = False
```

{button ,AL(`H_SHOWINDATAAREA_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: ShowPercentLabels property

{button ,AL(`H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to show percent labels for each series in a chart.

Data type

Boolean

Syntax

chart.Series(*num*).ShowPercentLabels = *trueorfalse*

trueorfalse = *chart*.Series(*num*).ShowPercentLabels

Legal values

True (1) or False (0)

{button ,AL(`H_SHOWVALUELABELS_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: ShowUpperLeft property

```
{button ,AL(^H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ',0)}
```

[See list of classes](#)

(Read-write) Whether to show the lines around the upper-left corner of the number grid or table under a chart.

Data type

Boolean

Syntax

chart.NumberGrid.ShowUpperLeft = trueorfalse

or

chart.Table.ShowUpperLeft = trueorfalse

trueorfalse = chart.NumberGrid.ShowUpperLeft

or

trueorfalse = chart.Table.ShowUpperLeft

Legal values

True (1) or False (0)

Lotus Chart: ShowValueLabels property

{button ,AL(`H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to show value labels for each series in a chart.

Data type

Boolean

Syntax

chart.Series(*num*).ShowValueLabels = *trueorfalse*

trueorfalse = *chart*.Series(*num*).ShowValueLabels

Legal values

True (1) or False (0)

{button ,AL(`H_SHOWPERCENTLABELS_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Size property

{button ,AL('H_FONT_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_SIZE_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The size of the text string.

Data type

Integer

Syntax

object.Font.Size = *size*

size = *object*.Font.Size

Usage

The integer value specifies the font size in points.

Lotus Chart: SliceDirection property

{button ,AL(`H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The direction of pie slices.

Data type

Integer (Enumerated)

Syntax

chart.Pies.SliceDirection = *direction*

direction = *chart.Pies.SliceDirection*

Legal values

| <u>Value</u> | <u>Description</u> |
|--------------------|--------------------------------------|
| \$CounterClockwise | Display pie slices counter-clockwise |
| \$Clockwise | Display pie slices clockwise |

{button ,AL(`H_STARTANGLE_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: SliceExplosion property

{button ,AL(`H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The amount to explode the slices in a pie chart.

Data type

Integer

Syntax

chart.Pies.SliceExplosion = *explodevalue*

explodevalue = *chart.Pies.SliceExplosion*

Legal values

0..100, with 0 meaning the slices are not exploded at all, and 100 showing the slices completely exploded (with the innermost tips of the slices at the outer edge of the pie).

{button ,AL(`H_EXPLODEPERCENT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: SliceSort property

{button ,AL('H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) How to sort the slices by size in a pie chart.

Data type

Integer (Enumerated)

Syntax

chart.Pies.SliceSort = sortmethod

sortmethod = chart.Pies.SliceSort

Legal values

| <u>Value</u> | <u>Description</u> |
|--------------------|--|
| \$Unsorted | Do not sort the pies (show slices in the order used in the data) |
| \$SortIndividually | Sort each pie separately by size |
| \$SortByFirst | Sort all pies by the size order in the first pie |
| \$SortByLast | Sort all pies by the size order in the last pie |

Lotus Chart: Slope property

{button ,AL(^H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)

(Read-only) The slope of the regression line.

Data type

Double

Syntax

slopevalue = **chart.Series(num).Regression.Slope**

Lotus Chart: StackedTotalsAngle property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The angle at which to display totals on a stacked bar chart.

Data type

Integer

Syntax

chart.StackedTotalsAngle = *degrees*

degrees = *chart*.StackedTotalsAngle

Legal values

0..360 degrees

Lotus Chart: StackedTotalsFormat property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The format to use when showing totals values for bars in a stacked bar chart.

Data type

NumberFormat

Syntax

chart.StackedTotalsFormat.*attribute* = *value*

value = *chart*.StackedTotalsFormat.*attribute*

{button ,AL('H_NUMBERFORMAT_CLASS ',0)} [See related topics](#)

Lotus Chart: StackedTotalsLabels property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The labels used to mark the totals in a stacked bar chart.

Data type

ChartDataLabels

Syntax

chart.**StackedTotalsLabels**.*attribute* = *value*

value = *chart*.**StackedTotalsLabels**.*attribute*

{button ,AL('H_CHARTDATALABELS_CLASS ',0)} [See related topics](#)

Lotus Chart: StartAngle property

{button ,AL(`H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The location at which the first slice in the pie displays.

Data type

Integer

Syntax

chart.Pies.StartAngle = *angle*

angle = *chart.Pies.StartAngle*

Legal values

0..360 degrees

{button ,AL(`H_SLICEDIRECTION_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: StartPoint property

{button ,AL('H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)

(Read-write) The first point at which to calculate the trend (regression) line.

Data type

Integer

Syntax

chart.Series(*num*).Regression.StartPoint = *startingindex*

startingindex = *chart*.Series(*num*).Regression.StartPoint

Legal values

1..8192

Usage

The value you use for the StartPoint is the data point index for the starting data value.

{button ,AL('H_ENDPOINT_PROPERTY_MEMDEF ;H_XAXISMINIMUM_PROPERTY_MEMDEF ;H_XAXISMAXIMUM_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: StrikeThrough property

{button ,AL(^H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) Whether text displays with a strike-through line.

Data type

Boolean

Syntax

object.Font.StrikeThrough = trueorfalse

trueorfalse = object.FontStrikeThrough

Legal values

True (1) or False (0)

Lotus Chart: Style property

{button ,AL('H_BORDER_CLASS ',0)} [See list of classes](#)

(Read-write) The line style of the border around an object.

Data type

Integer (Enumerated)

Syntax

object.Edge.Style = *style*

style = *object.Edge.Style*

Legal values

| <u>Value</u> | <u>Value</u> |
|----------------------|------------------------|
| \$Solid | \$DashShortShortShort |
| \$Dash | \$LongLongDashShort |
| \$Dot | \$SpacedLongDash |
| \$LongDash | \$SpacedDashShort |
| \$DashDotDot | \$DashDotDotDash |
| \$DashDot | \$ExtraLongDash |
| \$DotDot | \$ShortLongDash |
| \$DashDashDash | \$DashDashSpace |
| \$DashDotDotDot | \$DotShortDashDashLong |
| \$SpacedDash | \$DoubleLine |
| \$DashDash | \$SpacedDot |
| \$DashDashShortShort | \$Invisible |
| \$LongDashDash | \$DefaultLineStyle |
| \$DashShortDash | |

Lotus Chart: SubtitleIsManual property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) Whether the axis subtitle is specified manually or derived from the data.

Data type

Boolean

Syntax

chart.axis.SubtitleIsManual = *trueorfalse*

trueorfalse = *chart.axis.SubtitleIsManual*

Legal values

True (1) or False (0)

{button ,AL('H_EXPONENT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: SubtitlePlacement property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_SUBTITLEPLACEMENT_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The placement of axis subtitles.

Data type

Integer (Enumerated)

Syntax

chart.axis.SubtitlePlacement = *placement*

placement = *chart.axis.SubtitlePlacement*

Legal values

| <u>Values</u> | <u>Description</u> |
|--------------------|----------------------------------|
| \$SubtitleBeneath | Place subtitle beneath the title |
| \$SubtitleAdjacent | Place subtitle next to the title |

Lotus Chart: SubtitlesAreManual property

{button ,AL('H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) Whether the pie chart subtitles are specified manually or are derived from the data.

Data type

Boolean

Syntax

chart.Pies.SubtitlesAreManual = trueorfalse

trueorfalse = chart.Pies.SubtitlesAreManual

Legal values

True (1) or False (0)

Lotus Chart: Subtitles property

{button ,AL(^H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The subtitles showing the totals for a pie chart.

Data type

ChartPieTitles (the collection of all subtitles)

ChartPieTitle (a single subtitle)

Syntax

chart.Pies.Subtitles.attribute = value

or

chart.Pies.Subtitles(num).attribute = value

value = chart.Pies.Subtitles.attribute

or

value = chart.Pies.Subtitles(num).attribute

{button ,AL(^H_CHARTPIETITLES_CLASS ;H_CHARTPIETITLE_CLASS ',0)} [See related topics](#)

Lotus Chart: Subtitle property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_TITLE_SUBTITLE_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) Specifies the attributes of the axis subtitle.

Data type

ChartTextEntry

Syntax

chart.axis.Subtitle.attribute = value

value = chart.axis.Subtitle.attribute

{button ,AL('H_CHARTTEXTENTRY_CLASS ',0)} [See related topics](#)

Lotus Chart: Table property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) A data table that displays under a chart.

Data type

ChartTable

Syntax

chart.Table.attribute = attribute

attribute = chart.Table.attribute

{button ,AL('H_NUMBERGRID_PROPERTY_MEMDEF ;H_CHARTTABLE_CLASS',0)} [See related topics](#)

Lotus Chart: TextLabelPlacement property

{button ,AL('H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) The placement of text labels for a pie slice.

Data type

Integer (Enumerated)

Syntax

chart.Pies.TextLabelPlacement = *placementvalue*

placementvalue = *chart.Pies.TextLabelPlacement*

Legal values

| <u>Value</u> | <u>Description</u> |
|-----------------|---|
| \$LabelsOutside | Places labels outside slices. |
| \$LabelsInside | Places labels inside slices, where they'll fit. |

Lotus Chart: TextLabels property

{button ,AL('H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) The text labels associated with a pie chart.

Data type

ChartDataLabels

Syntax

chart.Pies.TextLabels.attribute = attribute

attribute = chart.Pies.TextLabels.attribute

{button ,AL('H_CHARTDATALABELS_CLASS',0)} [See related topics](#)

Lotus Chart: Text property

{button ,AL(^H_CHARTPIETITLES_CLASS ;H_CHARTPIETITLE_CLASS ;H_CHARTTEXTENTRY_CLASS ;H_CHARTTEXTLABEL_CLASS ',0)} [See list of classes](#)

(Read-write) The string in a line of text.

Data type

String

Syntax

object.Text = textvalue

textvalue = object.Text

Lotus Chart: ThreeDElevation property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read and write) The amount of elevation used to display a 3D chart. Available only for bar charts, area charts, line charts, and mixed charts.

Data type

Integer

Syntax

chart.ThreeDElevation = elevationvalue

elevationvalue = chart.ThreeDElevation

Legal values

5..85 degrees

Usage

The ThreeDElevation is the angle between the viewer's eye and the x-y plane on which the chart is drawn.

Lotus Chart: ThreeDLateralRotation property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The clockwise rotation about the chart's y-axis. Available only for 3D bar charts, area charts, line charts, and mixed charts.

Data type

Integer

Syntax

chart.ThreeDLateralRotation = *rotation*

rotation = *chart*.ThreeDLateralRotation

Legal values

5..85 degrees

Lotus Chart: ThreeDLightSource property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The direction of the light source in a 3D chart or with-depth chart. Available only for 3D or with-depth bar charts, area charts, line charts, and mixed charts.

Data type

Integer (Enumerated)

Syntax

chart.ThreeDLightSource = *direction*

direction = *chart*.ThreeDLightSource

Legal values

| <u>Value</u> | <u>Description</u> |
|--------------|--|
| \$LightLeft | Places the light source to the left of the chart. |
| \$LightRight | Places the light source to the right of the chart. |

Lotus Chart: ThreeDPlatform property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The size of the platform in a 3D chart. Available only for 3D bar charts, area charts, line charts, and mixed charts.

Data type

Integer (Enumerated)

Syntax

chart.ThreeDPlatform = *size*

size = *chart*.ThreeDPlatform

Legal values

| <u>Value</u> | <u>Description</u> |
|---------------|---------------------------------------|
| \$NoFloor | Do not display a platform floor |
| \$SmallFloor | Display a small platform floor |
| \$MediumFloor | Display a medium-sized platform floor |
| \$LargeFloor | Display a large platform floor |

Lotus Chart: ThreeDRowGapPercent property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The space between rows in a 3D line chart, bar chart, area chart, or mixed chart. You specify the gap between rows (series) as a percent of the width of markers in one row.

Data type

Integer

Syntax

chart.ThreeDRowGapPercent = *percentage*

percentage = *chart.ThreeDRowGapPercent*

Legal values

0..100

Lotus Chart: TickLabelCharWidth property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The maximum number of characters of a single tick label. Used only if TickLabelWidthIsManual is True.

Data type

Integer

Syntax

chart.axis.TickLabelCharWidth = *charwidth*

charwidth = *chart.axis.TickLabelCharWidth*

{button ,AL('H_TICKLABELWIDTHISMANUAL_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: TickLabelPlacement property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The placement of the tick labels.

Data type

Integer (Enumerated)

Syntax

chart.axis.TickLabelPlacement = *placementvalue*

placementvalue = *chart.axis.TickLabelPlacement*

Legal values

| <u>Value</u> | <u>Description</u> |
|--------------|---|
| \$Automatic | Use automatic layout |
| \$Staggered | Stagger tick labels so they fit, if necessary |
| \$Rotated | Rotate tick labels so they fit, if necessary |
| \$Skip | Skip a specified number of tick labels |
| \$Slant | Slant tick labels so they fit, if necessary |
| \$Scaled | Scale tick labels so they all fit |

Usage

To specify the number of tick labels to skip when using the Skip enumeration value, use the TickLabelSkip property.

{button ,AL('H_TICKLABELSKIP_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: TickLabelSkip property

{button ,AL('H_CHARTAXIS_CLASS ;H_CHARTZAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The number of tick marks to skip, when display tick mark labels.

Data type

Integer

Syntax

chart.axis.TickLabelSkip = *skipnumber*

skipnumber = *chart.axis.TickLabelSkip*

{button ,AL('H_TICKLABELPLACEMENT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: TickLabelsLink property

{button ,AL('H_CHARTTEXTLABELS_CLASS',0)} [See list of classes](#)

(Read-write) The link source of a tick label.

Data type

ChartDataSource

Syntax

mychart.axis.TickLabelsLink.attribute = value

value = mychart.axis.TickLabelsLink.attribute

{button ,AL('H_CHARTDATASOURCE_CLASS ;H_SOURCE_PROPERTY_MEMDEF ;H_DATALINK_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: TickLabels property

{button ,AL('H_CHARTZAXIS_CLASS ;H_CHARTAXIS_CLASS',0)} [See list of classes](#)

(Read-write) The labels for the axis tick marks.

Data type

ChartTextLabels

Syntax

chart.axis.TickLabels.attribute = attribute

attribute = chart.axis.TickLabels.attribute

{button ,AL('H_CHARTTEXTLABELS_CLASS ',0)} [See related topics](#)

Lotus Chart: TickLabelWidthsManual property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) Whether the width of the tick mark labels is set manually. When True, then the TickLabelCharWidth property applies.

Data type

Boolean

Syntax

chart.axis.TickLabelWidthsManual = trueorfalse

trueorfalse = chart.axis.TickLabelWidthsManual

Legal values

True (1) or False (0)

{button ,AL('H_TICKLABELCHARWIDTH_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Titles property

{button ,AL('H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The titles for pies in a pie chart.

Data type

ChartPieTitles (the collection of all pie titles in the pie chart)

ChartPieTitle (a single pie title)

Syntax

chart.Pies.Titles.attribute = attribute

or

chart.Pies.Titles(num).attribute = attribute

attribute = chart.Pies.Titles.attribute

or

attribute = chart.Pies.Titles(num).attribute

{button ,AL('H_CHARTPIETITLES_CLASS ;H_CHARTPIETITLE_CLASS ',0)} [See related topics](#)

Lotus Chart: Title property (ChartAxis class)

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_TITLE_SUBTITLE_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) Specifies the attributes of the title of a chart axis.

Data type

ChartTextEntry

Syntax

chart.axis.Title.attribute = value

value = chart.axis.Title.attribute

{button ,AL('H_CHARTTEXTENTRY_CLASS ',0)} [See related topics](#)

Lotus Chart: Title property (ChartBase class)

{button ,AL(`H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL(`H_EXAMPLE_TITLE_CHART_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) Specifies the attributes of the chart title.

Data type

ChartTitleBox

Syntax

value = chart.Title.attribute

chart.Title.attribute = value

{button ,AL(`H_CHARTTITLEBOX_CLASS ',0)} [See related topics](#)

Lotus Chart: Type property (ChartRegression class)

{button ,AL('H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)

(Read-write) The type of regression (trend) line for the series.

Data type

Integer (Enumerated)

Syntax

chart.Series(*num*).Regression.Type = *type*

type = *chart*.Series(*num*).Regression.Type

Legal values

| <u>Value</u> | <u>Description</u> |
|-------------------------|-----------------------------|
| \$NoRegression | No regression line |
| \$LinearRegression | Linear regression line |
| \$ExponentialRegression | Exponential regression line |
| \$LogRegression | Logarithmic regression line |
| \$PowerRegression | Power regression line |

Lotus Chart: Type property (ChartBase and ChartSeries classes)

{button ,AL('H_CHARTBASE_CLASS ;H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_TYPE_CHART_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The type of the chart or series.

Data type

Integer (Enumerated)

Syntax

chart.Type = *type*

or

chart.Series(num).Type = *type*

type = *chart.Type*

or

type = *chart.Series(num).Type*

Legal values

| <u>Value</u> | <u>Description</u> |
|---------------|---|
| \$Line | Line chart |
| \$Bar | Bar chart |
| \$Area | Area chart |
| \$Scatter | Scatter (XY) chart (not available as a series type) |
| \$HLCO | HLCO chart (not available as a series type) |
| \$Mixed | Mixed chart (not available as a series type) |
| \$Pie | Pie chart (single) (not available as a series type) |
| \$MultiplePie | Pie chart (multiple) (not available as a series type) |
| \$Radar | Radar chart (not available as a series type) |
| \$NumberGrid | Number grid (not available as a series type) |

The default chart and series type is a bar chart.

Lotus Chart: Type property (NumberFormat class)

{button ,AL(^H_NUMBERFORMAT_CLASS ',0)} [See list of classes](#)

(Read-write) The type of formatting to use on a number.

Data type

Integer (Enumerated)

Syntax

object.Type = *formattype*

formattype = *object.Type*

Legal values

| <u>Value</u> | <u>Value</u> |
|--------------|----------------|
| \$General | \$Scientific |
| \$Number | \$Fixed |
| \$Custom | \$Comma |
| \$Date | \$Percent |
| \$String | \$Currency |
| \$Time | \$ISO Currency |

Lotus Chart: Underline property

{button ,AL(^H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) Whether text displays with an underline.

Data type

Boolean

Syntax

object.Font.Underline = trueorfalse

trueorfalse = object.Font.Underline

Legal values

True (1) or False (0)

Lotus Chart: Use2YAxis property

{button ,AL(^H_CHARTSERIES_CLASS',0)} [See list of classes](#)

(Read-write) Whether to display the series on the 2nd y-axis.

Data type

Boolean

Syntax

chart.**Series**(*num*).**Use2YAxis** = *trueorfalse*

trueorfalse = *chart*.**Series**(*num*).**Use2YAxis**

Legal values

True (1) or False (0)

Lotus Chart: UseBRange property

{button ,AL(^H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) Whether to use a worksheet range containing values that specify the colors for each slice in a pie chart. Can be used only with a single pie chart.

Data type

Boolean

Syntax

chart.Pies.UseBRange = trueorfalse

trueorfalse = chart.Pies.UseBRange

Legal values

True (1) or False (0)

Lotus Chart: UseCandlestickForHLCO property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to create a candlestick HLCO chart.

Data type

Boolean

Syntax

chart.UseCandlestickForHLCO = trueorfalse

trueorfalse = chart.UseCandlestickForHLCO

Legal values

True (1) or False (0)

Lotus Chart: UseCRange property

{button ,AL(^H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) Whether to use a C range in a worksheet to specify which pie chart slices should not show a percentage. Available only with single pie charts.

Data type

Boolean

Syntax

chart.Pies.UseCRange = trueorfalse

trueorfalse = chart.Pies.UseCRange

Legal values

True (1) or False (0)

Lotus Chart: UseSeparateLabelRanges property

{button ,AL(^H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) Whether to match each pie with a separate range of data labels. For multiple pies only.

Data type

Boolean

Syntax

chart.Pies.UseSeparateLabelRanges = trueorfalse

trueorfalse = chart.Pies.UseSeparateLabelRanges

Legal values

True (1) or False (0)

Lotus Chart: UseSmartLookColors property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to use colors specified in SmartMasters in the chart.

Data type

Boolean

Syntax

chart.UseSmartLookColors = *trueorfalse*

trueorfalse = *chart*.UseSmartLookColors

Legal values

True (1) or False (0)

Lotus Chart: ValueLabelFormat property

{button ,AL('H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The format to use for value labels of pie chart slices.

Data type

NumberFormat

Syntax

chart.Pies.ValueLabelFormat.attribute = value

value = chart.Pies.ValueLabelFormat.attribute

{button ,AL('H_NUMBERFORMAT_CLASS ',0)} [See related topics](#)

Lotus Chart: ValueLabelPlacement property

{button ,AL('H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The placement of slice value labels.

Data type

Integer (Enumerated)

Syntax

chart.Pies.ValueLabelPlacement = placement

placement = chart.Pies.ValueLabelPlacement

Legal values

| <u>Value</u> | <u>Description</u> |
|-----------------|--|
| \$LabelsDefault | Use default position |
| \$LabelsOutside | Put labels outside of slices |
| \$LabelsInside | Put labels inside slices, where possible |

{button ,AL('H_VALUETAGS_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: ValueLabels property

{button ,AL('H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The value labels in a pie chart.

Data type

ChartDataLabels

Syntax

chart.Pies.ValueLabels.attribute = value

value = *chart.Pies.ValueLabels.attribute*

{button ,AL('H_CHARTDATALABELS_CLASS ',0)} [See related topics](#)

Lotus Chart: Value property

{button ,AL(^H_CHARTDATAPOINT_CLASS ;H_CHARTMAJORGRIDLINE_CLASS ',0)} [See list of classes](#)

(Read-write) The value of the specified data point or major grid line.

Data type

Double

Syntax

chart.Series(num).datapoint.Value = pointValue

or

chart.axis.MajorGridlines.Value = pointValue

pointValue = chart.Series(num).datapoint.Value

or

pointValue = chart.axis.MajorGridlines.Value

Lotus Chart: VertAlign property

{button ,AL(^H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) The vertical alignment of the text.

Note Provided for compatibility; to be implemented in a future release.

Lotus Chart: Visible property

```
{button ,AL('H_CHARTAXIS_CLASS ;H_CHARTDATALABELS_CLASS ;H_CHARTGRIDLINES_CLASS ;H_CHARTLEGEND_CLASS ;H_CHARTMAJORGRIDLINES_CLASS ;H_CHARTPIESLICE_CLASS ;H_CHARTPIETITLES_CLASS ;H_CHARTPLOT_CLASS ;H_CHARTTABLEGRIDLINES_CLASS ;H_CHARTTABLEGRIDLINE_CLASS ;H_CHARTTABLE_CLASS ;H_CHARTTEXTENTRY_CLASS ;H_CHARTTEXTLABELS_CLASS ;H_CHARTTEXTLABEL_CLASS ;H_CHARTTITLEBOX_CLASS ;H_CHARTZAXIS_CLASS ;H_CHARTSERIES_CLASS ;H_CHARTREGRESSION_CLASS ',0)} See list of classes
```

```
{button ,AL('H_EXAMPLE_VISIBLE_PROPERTY_EXSCRIPT',1)} See example
```

(Read-write) Whether the object displays in the chart.

Data type

Boolean

Syntax

object.Visible = *trueorfalse*

trueorfalse = *object.Visible*

Legal values

True (1) or False (0)

Lotus Chart: Width property (Border class)

```
{button ,AL(`H_BORDER_CLASS ;H_CHARTLEGEND_CLASS ;H_CHARTNUMBERGRID_CLASS ;H_CHARTPIES_CLASS ;H_CHARTPLOT_CLASS ;H_CHARTTITLEBOX_CLASS '0)} See list of classes
```

```
{button ,AL(`H_EXAMPLE_WIDTH_PROPERTY_EXSCRIPT',1)} See example
```

(Read-write) The width of the object's border.

Data type

Integer (Enumerated)

Syntax

object.Edge.Width = *value*

value = *object*.Edge.Width

Legal values

| <u>Value</u> | <u>Description</u> |
|---------------|-------------------------|
| \$NoBorder | Do not display a border |
| \$ThinBorder | Show a thin border |
| \$ThickBorder | Show a thick border |

```
{button ,AL(`H_HEIGHT_PROPERTY_MEMDEF ;H_X_PROPERTY_MEMDEF ;H_Y_PROPERTY_MEMDEF '0)}  
See related topics
```

Lotus Chart: Width property (ChartBase, ChartLegend, ChartNumberGrid, ChartPies, ChartPlot, and ChartTitleBox classes)

{button ,AL('H_CHARTBASE_CLASS ;H_CHARTLEGEND_CLASS ;H_CHARTNUMBERGRID_CLASS ;H_CHARTPIES_CLASS ;H_CHARTPLOT_CLASS ;H_CHARTTITLEBOX_CLASS ',0)} [See list of classes](#)

(Read-write) The width of the object.

Data type

Long

Syntax

object.Width = *value*

value = *object.Width*

Usage

For the ChartBase class, this property is read-only.

{button ,AL('H_HEIGHT_PROPERTY_MEMDEF ;H_X_PROPERTY_MEMDEF ;H_Y_PROPERTY_MEMDEF ',0)}
[See related topics](#)

Lotus Chart: XAxisMaximum property

{button ,AL('H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)

(Read-write) The maximum value at which to display the trend (regression) line.

Data type

Double

Syntax

chart.Series(*num*).Regression.XAxisMaximum = *maximum*

maximum = *chart*.Series(*num*).Regression.XAxisMaximum

{button ,AL('H_XAXISMINIMUM_PROPERTY_MEMDEF ;H_ENDPOINT_PROPERTY_MEMDEF ;H_STARTPOINT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: XAxisMinimum property

{button ,AL('H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)

(Read-write) The minimum value at which to display the trend (regression) line.

Data type

Double

Syntax

chart.Series(num).Regression.XAxisMinimum = minimum

minimum = chart.Series(num).Regression.XAxisMinimum

{button ,AL('H_XAXISMAXIMUM_PROPERTY_MEMDEF ;H_ENDPOINT_PROPERTY_MEMDEF ;H_STARTPOINT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: XAxis property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Specifies the attributes of the x-axis in a chart.

Data type

ChartAxis

Syntax

chart.XAxis.attribute = value

value = chart.XAxis.attribute

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See related topics](#)

Lotus Chart: X property

{button ,AL(`H_CHARTBASE_CLASS ;H_CHARTLEGEND_CLASS ;H_CHARTNUMBERGRID_CLASS ;H_CHARTPIES_CLASS ;H_CHARTPLOT_CLASS ;H_CHARTTITLEBOX_CLASS ',0)} [See list of classes](#)

(Read-write) The x-placement of the top-left corner of the object.

Data type

Long

Syntax

object.X = placementvalue

placementvalue = object.X

Usage

For the ChartBase class, this property is read-only.

{button ,AL(`H_HEIGHT_PROPERTY_MEMDEF ;H_WIDTH_PROPERTY_MEMDEF ;H_Y_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: YAxis property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The y-axis in a chart.

Data type

ChartAxis

Syntax

chart.YAxis.attribute = value

value = chart.YAxis.attribute

Lotus Chart: YIntercept property

{button ,AL(^H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)

(Read-only) The Y-intercept of the trend (regression) line.

Data type

Double

Syntax

chart.Series(num).Regression.YIntercept = interceptvalue

Lotus Chart: Y property

{button ,AL(`H_CHARTBASE_CLASS ;H_CHARTLEGEND_CLASS ;H_CHARTNUMBERGRID_CLASS ;H_CHARTPIES_CLASS ;H_CHARTPLOT_CLASS ;H_CHARTTITLEBOX_CLASS ',0)} [See list of classes](#)

(Read-write) The y-placement of the top-left corner of the object.

Data type

Long

Syntax

object.Y = placementvalue

placementvalue = object.Y

Usage

For the ChartBase class, this property is read-only.

{button ,AL(`H_HEIGHT_PROPERTY_MEMDEF ;H_X_PROPERTY_MEMDEF ;H_WIDTH_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: ZAxis property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The z-axis in a 3D chart.

Data type

ChartAxis

Syntax

chart.ZAxis.attribute = value

value = chart.ZAxis.attribute

' Example: AreaPlacement property

' Specify that the chart is an area chart

```
myChart.Type = $Area
```

' set the placement of the series to stacked

```
myChart.AreaPlacement = $Stacked
```

' Example: BarClusterGapPercent property

' Set the type of the chart to bar chart

```
myChart.Type = $Bar
```

' Set the bar cluster gap value to 50%

```
myChart.BarClusterGapPercent = 50
```

```
' Example: BarOverlapPercent property  
  
' Set the type of the chart to bar chart  
  
myChart.Type = $Bar  
  
' Set the bar overlap value to 50%  
  
myChart.BarOverlapPercent = 50
```

```
' Example: ForeColorIndex property
' Set the pattern color for the plot to the color at the index
' 200 in the current palette
mychart.Plot.Fill.Pattern = 15
mychart.Plot.Fill.ForeColorIndex = 200
```



```
' Example: Is3D property
' Adds 3D to a line chart
myChart.Type = $Line
myChart.Is3D = TRUE
```

' Example: IsAscending property

' Set the IsAscending property of the Y-axis

```
myChart.YAxis.Scale.IsAscending = TRUE
```

```
' Example: IsStacked and ConnectStackedBarLines properties  
' Set the type to stacked bar chart
```

```
myChart.Type = $Bar  
myChart.IsStacked = TRUE
```

```
' Show connecting lines
```

```
myChart.ConnectStackedBarLines = TRUE
```

```
' Example: Legend and Entries properties

' Set the individual legend entry values

myChart.Legend.Entries(1).Text = "Chocolate"

myChart.Legend.Entries(2).Text = "Vanilla"

myChart.Legend.Entries(3).Text = "Strawberry"
myChart.Legend.Visible = True
```

```
' Example: Lines and Note properties
```

```
' Specify the text for the first two lines of the note
```

```
myChart.Note.Lines(1).Text = "Collected in June"
```

```
myChart.Note.Lines(1).Font.Size = 12
```

```
myChart.Note.Lines(2).Text = "By John Smith"
```

```
myChart.Note.Lines(2).Font.Size = 10
```

```
myChart.Note.Visible = True
```

```
' Example: PercentLabels and PercentLabelPlacement property
```

```
' Display percent labels inside pie slices
```

```
myChart.Pies.PercentLabels.Visible = True
```

```
myChart.Pies.PercentLabelPlacement = $LabelsInside
```

```
' Example: Series and DataPoints properties

' Specify that the chart is a bar chart

myChart.Type = $Bar

' Enter data in the chart
for i = 1 to 10
    for j = 1 to 10
        myChart.Series(i).DataPoints(j).Value = i * (j + i)
    next j
next i
```

```
' Example: Size property
' Sets the size of the first line of the title
' to 12 points, and makes it bold
myChart.Title.Lines(1).Font.Size = 12
myChart.Title.Lines(1).Font.Bold = True
```



```
' Example: SubtitlePlacement property
' Specify the text for the XAxis title and subtitle

myChart.XAxis.Title.Text = "Sales"

myChart.XAxis.Subtitle.Text = "Per Quarter"

' Place the subtitle beneath the title

myChart.XAxis.SubtitlePlacement = $SubtitleBeneath
```

```
' Example: Title property

' Specify the text for the first line of the title

' and make the title visible

myChart.Title.Lines(1).Text = "Sales Projections"

myChart.Title.Lines(1).Font.Size = 12

myChart.Title.Visible = TRUE
```

```
' Example: Title and Subtitle properties
' Specify the text for the XAxis title and make it visible

myChart.XAxis.Title.Text = "Sales"

myChart.XAxis.Title.Visible = TRUE

' Specify the text for the XAxis subtitle and make it visible

myChart.XAxis.Subtitle.Text = "Per Quarter"

myChart.XAxis.Subtitle.Visible = TRUE
```

' Example: Type property (ChartBase and ChartSeries classes)

' Specify that the chart is a mixed chart

```
myChart.Type = $Mixed
```

' Set the four series to different types

```
myChart.Series(1).Type = $Bar
```

```
myChart.Series(2).Type = $Area
```

```
myChart.Series(3).Type = $Line
```

```
myChart.Series(4).Type = $Area
```

```
' Example: Visible property  
  
' Specify the text for the first line of the title  
  
' and make the title visible  
  
myChart.Title.Lines(1).Text = "Sales Projections"  
  
myChart.Title.Visible = TRUE
```

```
' Example: Width property

' Add a thick border to the title

myChart.Title.Lines(1).Text = "Sales Projections"

myChart.Title.Edge.Width = $ThickBorder
```

Lotus Chart: HasData property

{button ,AL(^H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

(Read-only) Whether the series has data associated with it, or just style and options settings.

Data type

Boolean

Syntax

trueorfalse = *chart*.**Series**(*num*).**HasData**

Legal values

True (1) or False (0)

Lotus Chart: HasPicture property

{button ,AL(`H_CHARTPLOT_CLASS ;H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

(Read-only) Whether a picture is applied to the series or plot.

Data type

Boolean

Syntax

trueorfalse = *chart*.**Series**(*num*).**HasPicture**

or

trueorfalse = *chart*.**Plot**.**HasPicture**

Legal values

True (1) or False (0)

{button ,AL(`H_PASTEPICTURE_METHOD_MEMDEF ;H_DELETEPICTURE_METHOD_MEMDEF ;H_PICTUREUNITS_PROPERTY_MEMDEF ;H_PICTURELAYOUT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Height property

{button ,AL(^H_CHARTBASE_CLASS ;H_CHARTLEGEND_CLASS ;H_CHARTNUMBERGRID_CLASS ;H_CHARTPIES_CLASS ;H_CHARTPLOT_CLASS ;H_CHARTTITLEBOX_CLASS ',0)} [See list of classes](#)

(Read-write) The height of the object.

Data type

Long

Syntax

object.Height = heightvalue

heightvalue = object.Height

Usage

Height is read-only for the ChartBase class.

{button ,AL(^H_WIDTH_PROPERTY_MEMDEF ;H_X_PROPERTY_MEMDEF ;H_Y_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Index property

{button ,AL(^H_CHARTMAJORGRIDLINE_CLASS ;H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

(Read-only) The index of the current series or major gridline.

Data type

Integer

Syntax

index = *chart*.**Series**(*num*).**Index**

or

index = *chart.axis*.**MajorGridlines**(*num*).**Index**

Lotus Chart: InsetLinesFromFrame property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to display a space between lien chart lines and the plot frame or to have the lines extend all the way to the frame.

Data type

Integer

Syntax

chart.Legend.InsetLinesFromFrame = trueorfalse

trueorfalse = chart.Legend.InsetLinesFromFrame

Legal values

True (1) or False (0)

Lotus Chart: InsidePlot property

{button ,AL(^H_CHARTLEGEND_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to display the legend inside the plot boundary.

Data type

Boolean

Syntax

chart.Legend.InsidePlot = trueorfalse

trueorfalse = chart.Legend.InsidePlot

Legal values

True (1) or False (0)

Lotus Chart: InteriorHorizontal property

{button ,AL(`H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ',0)}

[See list of classes](#)

(Read-write) The interior horizontal rules in a number grid or table under a chart.

Data type

ChartTableGridlines

Syntax

chart.Table.InteriorHorizontal.attribute = value

or

chart.NumberGrid.InteriorHorizontal.attribute = value

value = chart.Table.InteriorHorizontal.attribute

or

value = chart.NumberGrid.InteriorHorizontal.attribute

{button ,AL(`H_CHARTTABLEGRIDLINES_CLASS ;H_INTERIORVERTICALS_PROPERTY_MEMDEF ;H_FIRSTVERTICAL_PROPERTY_MEMDEF ;H_FIRSTHORIZONTAL_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: InteriorVerticals property

{button ,AL(`H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ',0)}

[See list of classes](#)

(Read-write) The interior vertical rules in a number grid or table under a chart.

Data type

ChartTableGridlines

Syntax

chart.Table.InteriorVerticals.attribute = value

or

chart.NumberGrid.InteriorVerticals.attribute = value

value = chart.Table.InteriorVerticals.attribute

or

value = chart.NumberGrid.InteriorVerticals.attribute

{button ,AL(`H_CHARTTABLEGRIDLINES_CLASS ;H_INTERIORHORIZONTALS_PROPERTY_MEMDEF ;H_FIRST
VERTICAL_PROPERTY_MEMDEF ;H_FIRSTHORIZONTAL_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Is3D property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('h_example_is3d_property_exscript',1)} [See example](#)

(Read-Write) Whether the chart is a three-dimensional chart.

Data type

Boolean

Syntax

chart.Is3D = *trueorfalse*

trueorfalse = *chart.Is3D*

Legal values

True (1) or False (0)

Lotus Chart: IsAscending property

{button ,AL(^H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

{button ,AL(^H_EXAMPLE_ISASCENDING_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) Whether axis values display in ascending or descending order.

Data type

Boolean

Syntax

chart.axis.Scale.IsAscending = *ascendingValue*

ascendingValue = *chart.axis.Scale.IsAscending*

Legal values

True (1) or False (0)

Lotus Chart: IsDepthEffect property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether the chart displays with a depth effect.

Data type

Boolean

Syntax

chart.IsDepthEffect = trueorfalse

trueorfalse = chart.IsDepthEffect

Legal values

True (1) or False (0)

Lotus Chart: IsHorizontal property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether the chart uses a horizontal or vertical orientation.

Data type

Boolean

Syntax

chart.IsHorizontal = trueorfalse

trueorfalse = chart.IsHorizontal

Legal values

True (1) or False (0)

Usage

Use the IsHorizontal class with bar, line, area, scatter, HLCO, or mixed charts.

Lotus Chart: IsStacked property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_ISSTACKED_CONNECTSTACKEDBARLINES_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) Whether the chart is a stacked chart.

Data type

Boolean

Syntax

chart.IsStacked = *trueorfalse*

trueorfalse = *chart*.IsStacked

Legal values

True (1) or False (0)

Usage

The IsStacked property applies to bar charts, line charts, area charts, mixed charts, and radar charts.

Lotus Chart: Italic property

{button ,AL(^H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to display the text in italics.

Data type

Boolean

Syntax

object.Font.TextItalic = *trueorfalse*

trueorfalse = *object.Font.TextItalic*

Legal values

True (1) or False (0)

Lotus Chart: LabelAngle property

{button ,AL(^H_CHARTSERIES_CLASS',0)} [See list of classes](#)

(Read-write) The angle at which to display series labels.

Data type

Integer

Syntax

chart.Series(*num*).LabelAngle = *angle*

angle = *chart*.Series(*num*).LabelAngle

Legal values

You can enter any integer from 0 to 360 for the angle.

Lotus Chart: LabelPlacement property

{button ,AL(^H_CHARTSERIES_CLASS',0)} [See list of classes](#)

(Read-write) The placement of series labels.

Data type

Integer (Enumerated)

Syntax

chart.Series(*num*).LabelPlacement = *placementValue*

placementValue = *chart*.Series(*num*).LabelPlacement

Legal values

| <u>Value</u> | <u>Description</u> |
|----------------|--|
| \$LabelsCenter | Places labels centered on the data point. (For bar, line, area, and scatter series.) |
| \$LabelsRight | Places labels to the right of the data point. (For line and scatter series.) |
| \$LabelsBelow | Places labels below the data point. (For bar, line, area, and scatter series.) |
| \$LabelsLeft | Places labels to the left of the data point. (For line and scatter series.) |
| \$LabelsAbove | Places labels above the data point. (For bar, line, area, and scatter series.) |

Lotus Chart: LayoutsManual property

{button ,AL('H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) Whether the layout of multiple pies is controlled manually or automatically. If LayoutsManual is False, then the setting of LayoutRowCount is ignored.

Data type

Boolean

Syntax

chart.Pies.LayoutsManual = trueorfalse

trueorfalse = chart.Pies.LayoutsManual

Legal values

True (1) or False (0)

{button ,AL('H_LAYOUTROWCOUNT_PROPERTY_MEMDEF',0)} [See related topics](#)

Lotus Chart: LayoutRowCount property

{button ,AL('H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) The number of pies to be plotted in each row of pies in a multiple pie chart. If LayoutIsManual is False, then the setting of LayoutRowCount is ignored.

Data type

Integer

Syntax

chart.Pies.LayoutRowCount = numberofpies

numberofpies = chart.Pies.LayoutRowCount

Legal values

1..30

{button ,AL('H_LAYOUTISMANUAL_PROPERTY_MEMDEF',0)} [See related topics](#)

Lotus Chart: LeftWall property

{button ,AL('H_CHARTPLOT_CLASS ',0)} [See list of classes](#)

(Read-write) The left wall of the platform of a 3D chart or a chart with depth.

Data type

ChartPlotWall

Syntax

chart.Plot.LeftWall.attribute = value

value = chart.Plot.LeftWall.attribute

{button ,AL('H_CHARTPLOTWALL_CLASS ;H_RIGHTWALL_PROPERTY_MEMDEF ;H_PLATFORMFRONTFACE_PROPERTY_MEMDEF ;H_PLATFORMTOPFACE_PROPERTY_MEMDEF ;H_PLATFORMRIGHTFACE_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Legend property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_LEGEND_ENTRIES_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The legend in a chart.

Data type

ChartLegend

Syntax

chart.Legend.attribute = value

value = chart.Legend.attribute

Lotus Chart: LightAngle property

{button ,AL(^H_CHARTPIES_CLASS',0)} [See list of classes](#)

(Read-write) The angle at which to show the shadow behind a 3D pie chart.

Data type

Integer

Syntax

chart.Pies.LightAngle = angle

angle = chart.Pies.LightAngle

Lotus Chart: LinePlacement property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) How to arrange the lines in a line chart.

Data type

Integer (Enumerated)

Syntax

linechart.LinePlacement = *placementvalue*

placementvalue = *linechart.LinePlacement*

Legal values

| <u>Value</u> | <u>Description</u> |
|--------------|--|
| \$InRows | Places lines in separate rows (for 3D line charts only). |
| \$Stacked | Stacks lines on top of each other. |
| \$Overlapped | Displays lines so the series overlap. |

Lotus Chart: Lines property

{button ,AL(^H_CHARTTITLEBOX_CLASS ',0)} [See list of classes](#)

{button ,AL(^H_EXAMPLE_LINES_NOTE_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The lines of text in a chart title or note.

Data type

ChartTextEntries (the collection of lines)

ChartTextEntry (a single line)

Syntax

chart.Title.Lines.attribute = value

or

chart.Note.Lines.attribute = value

or

chart.Title.Lines(num).attribute = value

or

chart.Note.Lines(num).attribute = value

value = chart.Title.Lines.attribute

or

value = chart.Note.Lines.attribute

or

value = chart.Title.Lines(num).attribute

or

value = chart.Note.Lines(num).attribute

Legal values

To specify a single line of text, enter an integer between 1 and 3, inclusive, for *num*.

{button ,AL(^H_CHARTTEXTENTRIES_CLASS ;H_CHARTTEXTENTRY_CLASS ',0)} [See related topics](#)

Lotus Chart: LinkUpdateMethod property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-Write) Whether to update chart links manually or automatically.

Data type

Integer (Enumerated)

Syntax

chart.LinkUpdateMethod = *method*

method = *chart.LinkUpdateMethod*

Legal values

| <u>Value</u> | <u>Description</u> |
|-----------------|--|
| \$LinkAutomatic | Update links automatically, whenever the source changes. |
| \$LinkManual | Update links only when the UpdateLinks method is called. |

{button ,AL('H_UPDATELINKS_METHOD_MEMDEF ',0)} [See related topics](#)

Lotus Chart: ListSelection property

{button ,AL(`H_NUMBERFORMAT_CLASS ',0)} [See list of classes](#)

(Read-write) The format choice for a numeric format type (such as the type of currency or the style of the date).

Data type

Long

Syntax

object.ListSelection = *selection*

selection = *object*.ListSelection

Legal values

The actual values depend on the format type.

{button ,AL(`H_TYPE_NUMBERFORMAT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: MajorGridlines property

{button ,AL(`H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The major grid lines for an axis.

Data type

ChartMajorGridlines (the collection of grid lines)

ChartMajorGridline (a single grid line)

Syntax

chart.axis.MajorGridlines.attribute = value

or

chart.axis.MajorGridlines(num).attribute = value

value = chart.axis.MajorGridlines.attribute

or

value = chart.axis.MajorGridlines(num).attribute

Legal values

To specify a single gridline, enter an integer between 1 and 3000, inclusive, for *num*.

{button ,AL(`H_CHARTMAJORGRIDLINES_CLASS ;H_CHARTMAJORGRIDLINE_CLASS ',0)} [See related topics](#)

Lotus Chart: MajorTickmarkPlacement property

{button ,AL(^H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) Where to place the major tick marks.

Data type

Integer (Enumerated)

Syntax

chart.axis.MajorTickmarkPlacement = *placement*

placement = *chart.axis*.MajorTickmarkPlacement

Legal values

| <u>Value</u> | <u>Description</u> |
|--------------|---------------------------|
| TicksInside | Inside the plot lines |
| TicksOutside | Outside the plot lines |
| TicksAcross | Across the plot lines |
| NoTicks | Do not display tick marks |

Lotus Chart: MajorTickmarks property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The major tick marks on an axis.

Data type

ChartGridlines

Syntax

chart.axis.MajorTickmarks.attribute = value

value = chart.axis.MajorTickmarks.attribute

{button ,AL('H_CHARTGRIDLINES_CLASS ',0)} [See related topics](#)

Lotus Chart: MarkerSymbol property

{button ,AL(^H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

(Read-write) The symbols used for series markers in scatter charts, line charts, and radar charts.

Data type

Integer (Enumerated)

Syntax

chart.Series(num).MarkerSymbol = symbol

symbol = chart.Series(num).MarkerSymbol

Legal values

| <u>Value</u> | <u>Value</u> |
|-------------------|--------------------|
| \$SquareMarker | \$HDiamondMarker |
| \$DiamondMarker | \$HTriangleMarker |
| \$TriangleMarker | \$HCircleMarker |
| \$CircleMarker | \$HStarMarker |
| \$StarMarker | \$HDTriangleMarker |
| \$DTriangleMarker | \$XMarker |
| \$XSquareMarker | \$CrossMarker |
| \$CSquareMarker | \$AsteriskMarker |
| \$ASquareMarker | \$UYMarker |
| \$UYSquareMarker | \$HorizLineMarker |
| \$HLSquareMarker | \$VertLineMarker |
| \$VSquareMarker | \$HSCircleMarker |
| \$HSquareMarker | \$RBulletMarker |
| \$CCircleMarker | \$SCircleMarker |

Lotus Chart: MarkerVisible property

{button ,AL(^H_CHARTSERIES_CLASS',0)} [See list of classes](#)

(Read-write) Whether to show markers for the specified series.

Data type

Boolean

Syntax

chart.Series(num).MarkerVisible = trueorfalse

trueorfalse = chart.Series(num).MarkerVisible

Legal values

True (1) or False (0)

Lotus Chart: MaximumIsManual property

{button ,AL(`H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to set the maximum value of the axis manually.

Data type

Boolean

Syntax

chart.axis.Scale.MaximumIsManual = trueorfalse

trueorfalse = chart.axis.Scale.MaximumIsManual

Legal values

True (1) or False (0)

{button ,AL(`H_MAXIMUM_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Maximum property

{button ,AL('H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) The maximum value of the axis.

Data type

Double

Syntax

chart.axis.Scale.Maximum = *maximumvalue*

maximumvalue = *chart.axis.Scale.Maximum*

{button ,AL('H_MAXIMUMISMANUAL_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: MinimumIsManual property

{button ,AL(`H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to set the minimum value of the axis manually.

Data type

Boolean

Syntax

chart.axis.Scale.MinimumIsManual = trueorfalse

trueorfalse = chart.axis.Scale.MinimumIsManual

Legal values

True (1) or False (0)

{button ,AL(`H_MINIMUM_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Minimum property

{button ,AL(`H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) The minimum value of the axis.

Data type

Double

Syntax

chart.axis.Scale.Minimum = *minimumvalue*

minimumvalue = *chart.axis.Scale.Minimum*

{button ,AL(`H_MINIMUMISMANUAL_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: MinorGridlines property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The minor grid lines for an axis.

Data type

ChartGridLines

Syntax

chart.axis.MinorGridlines.attribute = value

value = chart.axis.MinorGridlines.attribute

{button ,AL('H_CHARTGRIDLINES_CLASS ',0)} [See related topics](#)

Lotus Chart: MinorIntervallsManual property

{button ,AL(^H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether the minor tick interval is set manually.

Data type

Boolean

Syntax

chart.axis.Scale.MinorIntervallsManual = trueorfalse

trueorfalse = chart.axis.Scale.MinorIntervallsManual

Legal values

True (1) or False (0)

Lotus Chart: MinorInterval property

{button ,AL(^H_CHARTAXISSCALE_CLASS ',0)} [See list of classes](#)

(Read-write) The interval between minor tick marks on an axis.

Data type

Double

Syntax

chart.axis.Scale.MinorInterval = *intervalnumber*

intervalnumber = *chart.axis.Scale.MinorInterval*

Lotus Chart: MinorTickmarkPlacement property

{button ,AL(^H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-Write) Where to place the minor tickmarks.

Data type

Integer (Enumerated)

Syntax

chart.axis.MinorTickmarkPlacement = placement

placement = chart.axis.MinorTickmarkPlacement

Legal values

| <u>Value</u> | <u>Description</u> |
|----------------|---------------------------|
| \$TicksInside | Inside the plot lines |
| \$TicksOutside | Outside the plot lines |
| \$TicksAcross | Across the plot lines |
| \$NoTicks | Do not display tick marks |

Lotus Chart: MinorTickmarks property

{button ,AL('H_CHARTAXIS_CLASS ',0)} [See list of classes](#)

(Read-write) The minor ticks on an axis.

Data type

ChartGridlines

Syntax

chart.axis.MinorTickmarks.attribute = value

value = chart.axis.MinorTickmarks.attribute

{button ,AL('H_CHARTGRIDLINES_CLASS ',0)} [See related topics](#)

Lotus Chart: Name property

{button ,AL(^H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

(Read-only) The name of the current series.

Data type

String

Syntax

name = *chart*.Series(*num*).Name

Lotus Chart: Note property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_LINES_NOTE_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The chart note.

Data type

ChartTitleBox

Syntax

chart.Note.attribute = value

value = chart.Note.attribute

{button ,AL('H_CHARTTITLEBOX_CLASS ',0)} [See related topics](#)

Lotus Chart: NumberGrid property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) A number grid chart.

Data type

ChartNumberGrid

Syntax

chart.NumberGrid.attribute = value

value = chart.NumberGrid.attribute

{button ,AL('H_CHARTNUMBERGRID_CLASS ',0)} [See related topics](#)

Lotus Chart: Parentheses property

{button ,AL(^H_NUMBERFORMAT_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to show parentheses around the value.

Data type

Boolean

Syntax

object.Parentheses = *trueorfalse*

trueorfalse = *object.Parentheses*

Legal values

True (1) or False (0)

Lotus Chart: Pattern property

{button ,AL(^H_BACKGROUND_CLASS ;H_BORDER_CLASS ',0)} [See list of classes](#)

(Read-write) The pattern used to fill the wall of a 3D plot, or a border or background.

Data type

Integer (Enumerated)

Syntax

object.Pattern = *value*

value = *object*.Pattern

Legal values

| Value | Value |
|--------------------------|----------------------|
| \$NoFill | \$DottedSquarehatch |
| \$SolidForeground | \$WideSquareHatch |
| \$SolidBackground | \$DarkestGray |
| \$DoubleRightHatch | \$SecondDarkestGray |
| \$TripleRightHatch | \$ThirdDarkestGray |
| \$DoubleCoarseRightHatch | \$FourthDarkestGray |
| \$SingleCoarseRightHatch | \$FifthLightestGray |
| \$SingleRightHatch | \$FourthLightestGray |
| \$BroadRightHatch | \$ThirdLightestGray |
| \$VertHatch | \$SecondLightestGray |
| \$VertCoarseHatch | \$LightestGray |
| \$DoubleLeftHatch | \$Checkers |
| \$TripleLeftHatch | \$FineCheckers |
| \$DoubleCoarseLeftHatch | \$BroadLeftHatch |
| \$SingleCoarseLeftHatch | \$SingleLeftHatch |
| \$HorizHatch | \$GradVertFG2BG |
| \$HorizCoarseHatch | \$GradVertBG2FG |
| \$CrossHatch | \$GradHorizFG2BG |
| \$CoarseCrossHatch | \$GradHorizBG2FG |
| \$WideCrossHatch | \$GradFSlashFG2BG |
| \$FineCrossHatch | \$GradFSlashBG2FG |
| \$SquareHatch | \$GradBSlashFG2BG |
| \$CoarseSquareHatch | \$GradBSlashBG2FG |

Lotus Chart: PercentLabelFormat property

{button ,AL('H_CHARTPIES_CLASS ',0)} [See list of classes](#)

(Read-write) The format used for percent labels in a pie chart.

Data type

NumberFormat

Syntax

chart.Pies.PercentLabelFormat.attribute = value

value = chart.Pies.PercentLabelFormat.attribute

{button ,AL('H_NUMBERFORMAT_CLASS ',0)} [See related topics](#)

Lotus Chart: PercentLabelPlacement property

{button ,AL('H_CHARTPIES_CLASS',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_PERCENTLABELS_PERCENTLABELPLACEMENT_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The placement of the percent labels in pie slices.

Data type

Integer (Enumerated)

Syntax

chart.Pies.PercentLabelPlacement = *value*

value = *chart.Pies.PercentLabelPlacement*

Legal values

| <u>Value</u> | <u>Description</u> |
|-----------------|------------------------------------|
| \$LabelsDefault | Places labels at default position. |
| \$LabelsOutside | Places labels outside pie slices. |
| \$LabelsInside | Places labels inside pie slices. |

Lotus Chart: PercentLabels property

{button ,AL('H_CHARTPIES_CLASS',0)} [See list of classes](#)

{button ,AL('H_EXAMPLE_PERCENTLABELS_PERCENTLABELPLACEMENT_PROPERTY_EXSCRIPT',1)} [See example](#)

(Read-write) The percent labels in a pie chart.

Data type

ChartDataLabels

Syntax

chart.Pies.PercentLabels.attribute = value

value = chart.Pies.PercentLabels.attribute

{button ,AL('H_CHARTDATALABELS_CLASS',0)} [See related topics](#)

Lotus Chart: PictureLayout property

{button ,AL('H_CHARTSERIES_CLASS',0)} [See list of classes](#)

(Read-write) How to display a bitmap pasted into a bar series.

Data type

Integer (Enumerated)

Syntax

chart.Series(*num*).PictureLayout = *value*

value = *chart*.Series(*num*).PictureLayout

Legal values

| <u>Value</u> | <u>Description</u> |
|---------------------|--|
| \$IsoStackedPicture | Maintain the correct aspect ratio for the picture. |
| \$StretchedPicture | Stretch the picture to fill the bar. |
| \$StackedPicture | Fill the bars with pictures, with one picture equal the number of units specified in PictureUnits. |

{button ,AL('H_PICTUREUNITS_PROPERTY_MEMDEF ;H_PASTEPICTURE_METHOD_MEMDEF ;H_HASPICTURE_PROPERTY_MEMDEF ;H_DELETEPICTURE_METHOD_MEMDEF',0)} [See related topics](#)

Lotus Chart: PictureUnits property

{button ,AL(`H_CHARTSERIES_CLASS ',0)} [See list of classes](#)

(Read-write) The number of units to use when stacking pictures in a bar series.

Data type

Double

Syntax

chart.Series(*num*).PictureUnits = *number*

number = *chart*.Series(*num*).PictureUnits

Usage

When the PictureLayout is \$StackedPicture, then each picture is equal to the units specified in this property.

{button ,AL(`H_PICTURELAYOUT_PROPERTY_MEMDEF ;H_PASTEPICTURE_METHOD_MEMDEF ;H_HASPICTURE_PROPERTY_MEMDEF ;H_DELETEPICTURE_METHOD_MEMDEF ',0)} [See related topics](#)

Lotus Chart: PieSlices property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The slices in a pie chart.

Data type

ChartPieSlices

Syntax

chart.PieSlices(num).attribute = value

value = chart.PieSlices(num).attribute

{button ,AL('H_CHARTPIESLICE_CLASS ',0)} [See related topics](#)

Lotus Chart: Pies property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The pies in a pie chart.

Data type

ChartPies class

Syntax

chart.Pies.attribute = value

value = chart.Pies.attribute

{button ,AL('H_CHARTPIES_CLASS ',0)} [See related topics](#)

Lotus Chart: PlacelnNote property

{button ,AL('H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)
(Read-write) Whether to display the regression results in the chart note.

Data type

Boolean

Syntax

chart.Series(num).Regression.PlacelnNote = trueorfalse

trueorfalse = chart.Series(num).Regression.PlacelnNote

Legal values

True (1) or False (0)

Lotus Chart: Placement property

{button ,AL(^H_CHARTLEGEND_CLASS ;H_CHARTPIETITLES_CLASS ;H_CHARTTITLEBOX_CLASS ',0)} [See list of classes](#)

(Read-write) The placement of the legend, title, pie titles, or note.

Data type

Integer (Enumerated)

Syntax

chart.Legend.Placement = placement

or

chart.Title.Placement = placement

or

chart.Note.Placement = placement

or

chart.Pies.Titles.Placement = placement

or

chart.Pies.Subtitles.Placement = placement

placement = chart.Legend.Placement

or

placement = chart.Title.Placement

or

placement = chart.Note.Placement

or

placement = chart.Pies.Titles.Placement

or

placement = chart.Pies.Subtitles.Placement

Legal values

For titles, notes, and legends:

| <u>Value</u> | <u>Description</u> |
|-------------------|--|
| \$Northwest | Places the object in the top-left corner of the chart frame. |
| \$North | Places the object at the top of the chart frame. |
| \$Northeast | Places the object in the top-right corner of the chart frame. |
| \$West | Places the object on the left side of the chart frame. |
| \$East | Places the object on the right side of the chart frame. |
| \$SouthWest | Places the object in the bottom-left corner of the chart frame. |
| \$South | Places the object at the bottom of the chart frame. |
| \$SouthEast | Places the object in the bottom-right corner of the chart frame. |
| \$CustomPlacement | Allows the object to be placed manually. |

For pie titles and subtitles:

| <u>Value</u> | <u>Description</u> |
|--------------|-------------------------------|
| \$TitleAbove | Places object above the pies. |
| \$TitleBelow | Places object below the pies. |

Lotus Chart: Plain property

{button ,AL(^H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) Whether the text is shown without any special formatting (such as bold, italics, underlining).

Data type

Boolean

Syntax

object.Font.Plain = trueorfalse

trueorfalse = object.Font.Plain

Legal values

True (1) or False (0)

Lotus Chart: PlatformFrontFace property

{button ,AL('H_CHARTPLOT_CLASS ',0)} [See list of classes](#)

(Read-write) The front face of a 3D chart.

Data type

ChartPlotWall

Syntax

chart.Plot.PlatformFrontFace.attribute = value

value = chart.Plot.PlatformFrontFace.attribute

{button ,AL('H_CHARTPLOTWALL_CLASS ;H_RIGHTWALL_PROPERTY_MEMDEF ;H_LEFTWALL_PROPERTY_MEMDEF ;H_PLATFORMTOPFACE_PROPERTY_MEMDEF ;H_PLATFORMRIGHTFACE_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: PlatformRightFace property

{button ,AL('H_CHARTPLOT_CLASS ',0)} [See list of classes](#)

(Read-write) The right face of a 3D chart.

Data type

ChartPlotWall

Syntax

chart.Plot.PlatformRightFace.attribute = value

value = chart.Plot.PlatformRightFace.attribute

{button ,AL('H_CHARTPLOTWALL_CLASS ;H_RIGHTWALL_PROPERTY_MEMDEF ;H_LEFTWALL_PROPERTY_MEMDEF ;H_PLATFORMFRONTFACE_PROPERTY_MEMDEF ;H_PLATFORMTOPFACE_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: PlatformTopFace property

{button ,AL('H_CHARTPLOT_CLASS ',0)} [See list of classes](#)

(Read-write) The top face of a 3D or with-depth chart.

Data type

ChartPlotWall

Syntax

chart.Plot.PlatformTopFace.attribute = value

value = chart.Plot.PlatformTopFace.attribute

{button ,AL('H_CHARTPLOTWALL_CLASS ;H_RIGHTWALL_PROPERTY_MEMDEF ;H_LEFTWALL_PROPERTY_MEMDEF ;H_PLATFORMFRONTFACE_PROPERTY_MEMDEF ;H_PLATFORMRIGHTFACE_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Plot property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) The plot of the chart.

Data type

ChartPlot

Syntax

chart.Plot.attribute = value

value = chart.Plot.attribute

{button ,AL('H_CHARTPLOT_CLASS ',0)} [See related topics](#)

Lotus Chart: Precision property

{button ,AL(^H_NUMBERFORMAT_CLASS ',0)} [See list of classes](#)

(Read-write) The precision with which to display the number.

Data type

Integer

Syntax

object.Precision = *value*

value = *object.Precision*

Lotus Chart: RadarHasPolygonalBoundary property

{button ,AL('H_CHARTPLOT_CLASS ',0)} [See list of classes](#)

(Read-write) Whether the radar chart uses a polygonal or circular plot.

Data type

Boolean

Syntax

radarchart.Plot.RadarHasPolygonalBoundary = trueorfalse

trueorfalse = radarchart.Plot.RadarHasPolygonalBoundary

Legal values

True (1) or False (0)

Lotus Chart: RadarLabelEachAxis property

{button ,AL(^H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to show data labels on each axis in a radar chart.

Data type

Boolean

Syntax

radarchart.RadarLabelEachAxis = trueorfalse

trueorfalse = radarchart.RadarLabelEachAxis

Legal values

True (1) or False (0)

Lotus Chart: RadarUseIndependentScales property

{button ,AL('H_CHARTBASE_CLASS ',0)} [See list of classes](#)

(Read-write) Whether to use separate scales for each axis in a radar chart.

Data type

Boolean

Syntax

radarchart.RadarUseIndependentScales = trueorfalse

trueorfalse = radarchart.RadarUseIndependentScales

Legal values

True (1) or False (0)

Lotus Chart: Regression property

{button ,AL('H_CHARTSERIES_CLASS',0)} [See list of classes](#)

(Read-write) The regression (trend) line for a series.

Data type

ChartRegression

Syntax

chart.Series(num).Regression.attribute = value

value = chart.Series(num).Regression.attribute

{button ,AL('H_CHARTREGRESSION_CLASS ;H_SLOPE_PROPERTY_MEMDEF ;H_RSQUARED_PROPERTY_M
EMDEF ;H_YINTERCEPT_PROPERTY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: RightWall property

{button ,AL('H_CHARTPLOT_CLASS ',0)} [See list of classes](#)

(Read-write) The right wall of the plot in a 3D or with-depth chart.

Data type

ChartPlotWall

Syntax

chart.Plot.RightWall.attribute = value

value = chart.Plot.RightWall.attribute

{button ,AL('H_CHARTPLOTWALL_CLASS ;H_LEFTWALL_PROPERTY_MEMDEF ;H_PLATFORMFRONTFACE_P
ROPERTY_MEMDEF ;H_PLATFORMTOPFACE_PROPERTY_MEMDEF ;H_PLATFORMRIGHTFACE_PROPER
TY_MEMDEF ',0)} [See related topics](#)

Lotus Chart: Rotation property

{button ,AL('H_CHARTTEXTENTRY_CLASS ;H_CHARTTEXTLABEL_CLASS ;H_FONT_CLASS ',0)} [See list of classes](#)

(Read-write) The angle at which to display text.

Note Provided for compatibility; to be implemented in a future release.

Lotus Chart: RowHeaders property

{button ,AL(`H_CHARTNUMBERGRID_CLASS ;H_CHARTTABLEBASE_CLASS ;H_CHARTTABLE_CLASS ',0)}

[See list of classes](#)

(Read-write) The headers for rows in a number grid or data table.

Data type

ChartDataLabels (collection of row headers)

Syntax

chart.Table.RowHeaders.attribute = value

or

chart.NumberGrid.RowHeaders.attribute = value

value = chart.Table.RowHeaders.attribute

or

value = chart.NumberGrid.RowHeaders.attribute

{button ,AL(`H_CHARTDATALABELS_CLASS ',0)} [See related topics](#)

Lotus Chart: RowTotals property

{button ,AL('H_CHARTNUMBERGRID_CLASS ',0)} [See list of classes](#)

(Read-write) The row totals in a number grid.

Data type

ChartDataLabels (collection of row totals)

Syntax

chart.NumberGrid.RowTotals.attribute = value

value = chart.NumberGrid.RowTotals.attribute

{button ,AL('H_CHARTDATALABELS_CLASS ',0)} [See related topics](#)

Lotus Chart: RSquared property

{button ,AL(^H_CHARTREGRESSION_CLASS ',0)} [See list of classes](#)

(Read-only) The RSquared value for a regression line.

Data type

Double

Syntax

rsquaredValue = **chart.Series(num).Regression.RSquared**

Lotus Chart: Source property

{button ,AL(^H_CHARTDATASOURCE_CLASS ',0)} [See list of classes](#)

(Read-write) The name of the file and the link containing the data.

Data type

String

Syntax

object.Source = *link*

link = *object*.Source

