

MUIRexx

COLLABORATORS

	<i>TITLE :</i> MUIRexx	
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>
WRITTEN BY		April 16, 2022
<i>SIGNATURE</i>		

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	MUIRexx	1
1.1	MUIRexx.guide	1
1.2	MUIRexx.guide/Update Information	2
1.3	MUIRexx.guide/Version 2.2	2
1.4	MUIRexx.guide/Version 2.1	3
1.5	MUIRexx.guide/Version 2.0	4
1.6	MUIRexx.guide/Introduction	4
1.7	MUIRexx.guide/Disclaimer	5
1.8	MUIRexx.guide/Conditions	6
1.9	MUIRexx.guide/Requirements	6
1.10	MUIRexx.guide/Registration	7
1.11	MUIRexx.guide/Installation	8
1.12	MUIRexx.guide/Command Reference	8
1.13	MUIRexx.guide/Standard Commands	9
1.14	MUIRexx.guide/quit	10
1.15	MUIRexx.guide/hide	10
1.16	MUIRexx.guide/show	10
1.17	MUIRexx.guide/info	10
1.18	MUIRexx.guide/help	11
1.19	MUIRexx.guide/Windows	11
1.20	MUIRexx.guide/window	12
1.21	MUIRexx.guide/endwindow	13
1.22	MUIRexx.guide/Groups	14
1.23	MUIRexx.guide/group	14
1.24	MUIRexx.guide/endgroup	16
1.25	MUIRexx.guide/Menus	16
1.26	MUIRexx.guide/menu	17
1.27	MUIRexx.guide/endmenu	17
1.28	MUIRexx.guide/item	18
1.29	MUIRexx.guide/Objects	19

1.30	MUIRexx.guide/space	20
1.31	MUIRexx.guide/label	21
1.32	MUIRexx.guide/view	21
1.33	MUIRexx.guide/gauge	23
1.34	MUIRexx.guide/meter	24
1.35	MUIRexx.guide/text	25
1.36	MUIRexx.guide/button	28
1.37	MUIRexx.guide/switch	28
1.38	MUIRexx.guide/image	29
1.39	MUIRexx.guide/check	31
1.40	MUIRexx.guide/cycle	31
1.41	MUIRexx.guide/radio	33
1.42	MUIRexx.guide/string	33
1.43	MUIRexx.guide/popasl	35
1.44	MUIRexx.guide/poplist	36
1.45	MUIRexx.guide/slider	36
1.46	MUIRexx.guide/popslider	39
1.47	MUIRexx.guide/knob	39
1.48	MUIRexx.guide/list	39
1.49	MUIRexx.guide/dirlist	42
1.50	MUIRexx.guide/volumelist	45
1.51	MUIRexx.guide/object	47
1.52	MUIRexx.guide/Misc	50
1.53	MUIRexx.guide/request	51
1.54	MUIRexx.guide/aslrequest	51
1.55	MUIRexx.guide/method	52
1.56	MUIRexx.guide/setvar	53
1.57	MUIRexx.guide/getvar	53
1.58	MUIRexx.guide/application	53
1.59	MUIRexx.guide/Example Macro	54
1.60	MUIRexx.guide/MUI Format Sequences	55
1.61	MUIRexx.guide/MUI Image Specifications	56
1.62	MUIRexx.guide/MUI List Format	57
1.63	MUIRexx.guide/Attribute TAGs	58
1.64	MUIRexx.guide/MagicUserInterface	59
1.65	MUIRexx.guide/Acknowledgements	59
1.66	MUIRexx.guide/History	60
1.67	MUIRexx.guide/Concept Index	61
1.68	MUIRexx.guide/Command Index	64

Chapter 1

MUIRexx

1.1 MUIRexx.guide

MUIRexx

This is Edition 4 of the MUIRexx documentation,
22 September 1996, for MUIRexx Version 2.2.

Author: Russ Leighton <russ@sneezy.lancaster.ca.us>

Update Information

Read this first.

Introduction

A brief encounter.

Registration

My plea for support.

Installation

Pretty simple actually.

Command Reference

The mysteries revealed.

Example Macro

Just to peak your interest.

MUI Format Sequences

Making fancy text strings.

MUI Image Specifications

How to get little MUI images.

MUI List Format

How to get your directory lists just right.

Attribute TAGs

Now to really complicate things...

MagicUserInterface

The heart of MUIRexx.

Acknowledgements

Could not have done it without you.

History

What has been done so far.

Concept Index

Look it up here.

Command Index

Where is that command anyway?

1.2 MUIRexx.guide/Update Information

Update Information

Version 2.2

Version 2.1

Version 2.0

1.3 MUIRexx.guide/Version 2.2

Version 2.2

=====

This release removes some bugs (see
History
) and adds a TITLE option
for
list
objects. This much requested addition allows lists to have
titles (a string that remains at the top of the list). Context
sensitive menus can now be created by simply defining a

```

menu
  inside a

```

```

group
  definition.  An option (SPEC) has been added to the
popasl
  and

```

```

poplist
  objects to allow specification of the popbutton object.  Also,
a parse routine has been written to replace the builtin parse routine
in MUI.  This effectivly allows for arbitrary length command lines (up
to the limit imposed by 'ARexx').

```

Note that as of this release I am now making 'MUIRexx' "supportware", that is if you would like to show your support for further development (and also enhance the prospect of getting support) then please consider registering (see

```

  Registration
  ).

```

1.4 MUIRexx.guide/Version 2.1

```

Version 2.1
=====

```

```

This release is a minor update to version 2.0 (see
Version 2.0
).

```

Changes / additions include a more general 'view' command (HELP, NODE options as well as settable attributes), and new commands - 'aslrequest' that allows use of a standard ASL file requester within scripts and 'poplist' for creation of string gadgets with attached popup lists. Virtual groups are now supported (through the addition of the 'group' options SCROLL and VIRTUAL) The 'image' object has been changed and icon images (specified with the ICON option) now use an external MUI class (which is included and must be installed). Also, the 'list' command has been extended for better list handling. General improvements have been made including nonvolatile TAG string values (strings passed as TAG values are stored in allocated memory), string arrays for TAG values, and string formatting ('\n' for carriage returns and '\xxx' for octal specification of characters).

Additionally, the previous documentation neglected to mention a feature of the 'list' object supporting multicolumn lists. Strings inserted into lists may consist of several strings separated with commas. If the 'list' is given a format (with the LIST_FORMAT attribute TAG) then these strings will be displayed in the appropriate column (as defined by the format).

1.5 MUIRexx.guide/Version 2.0

Version 2.0

=====

This version of 'MUIRexx' is a major update from the previous version. I decided to designate this release a major update since a lot has changed (see

History

) and most likely any scripts written for previous versions will break under this version. I apologize for any inconvenience this causes, but it was necessary to make major changes to implement some new capabilities. One of the biggest changes is that most options now require a keyword, so if you find that gadgets are missing (or even whole groups) then it is probably because a keyword is missing (like the LABEL keyword for example). Please have a look at the included example scripts to get an idea of how things should now look. Also, AmigaDOS 3.0 or better is now required because of the need for datatypes.library.

Some other major changes and additions include:

- * Multiple labels specified in a comma delimited list (used to be specified as multiple arguments separated by space)
- * Attribute TAGS can be set and retrieved, greatly improving flexibility and eliminating the need for some options (which have been removed, e.g. WEIGHT)
- * New 'object' command for creation of generalized objects based on MUI internal and external classes as well as BOOPSI classes (also eliminated the need for some built-in objects, like 'scale')
- * New 'method' command to allow creation of class methods which greatly enhances flexibility and eliminates need for some commands (which have been removed, e.g. 'muiset', 'config')
- * Drag and drop operations are fully support for some objects
- * Internal variables may be set or retrieved for passing data conveniently between 'ARexx' scripts

Note that if a script does fail then most likely the application will still be running (even if no window is open). In this case just issue the

```
quit
command to the application port.
```

1.6 MUIRexx.guide/Introduction

Introduction

'MUIRexx' is a program which serves as an interface between 'ARexx' (Copyright (C) 1987, William S. Hawes) and MagicUserInterface (Copyright (C) 1993-96, Stefan Stuntz). 'MUIRexx' does not provide complete access to all of the capabilities of MagicUserInterface (MUI), however, quite a lot of capability is implemented in 'MUIRexx' such as notification, icon buttons, application objects (objects that react to icons dropped on them), and drag/drop objects, as well as many standard MUI objects. Complete graphical user interfaces as well as full applications can be developed using 'MUIRexx' and 'ARexx' macros. Additionally, it is also possible to dynamically change or add objects after the application has been created.

Since MUI is an object oriented extension it was felt that the general flavor of object oriented programming (OOP) should be retained in the 'ARexx' implementation. Therefore, the command structure has a familiar OOP look to it which is somewhat of a departure from normal 'ARexx' programming construction.

Disclaimer

A not so standard disclaimer.

Conditions

Not too bad really.

Requirements

At the very least you need this.

1.7 MUIRexx.guide/Disclaimer

Disclaimer

=====

Basically, I am not in any way responsible if anything bad happens to you because of using this software. Say, for example, a mad MUI hater breaks into your house and smashes up your computer because you are using 'MUIRexx' then I am not responsible ;-)

Anyway, I hate disclaimers because the implication is that our society has become so pitiful that we feel we have to protect ourselves with legal disclaimers even though we, as freeware contributors, are providing a service for no charge. Therefore, I implore, if you are a person who is inclined to use/abuse the legal system in anyway that would cause harm to someone who is only trying to contribute to the community then please do not use this software.

1.8 MUIRexx.guide/Conditions

Conditions

=====

Actually, there aren't any concerning usage. I do not require anything from you to use this software, however, please consider registering 'MUIRexx' (see

Registration

). I have put quite a lot of effort into this so I would appreciate some feedback. If you discover any bugs tell me about them. If you have any ideas let me know. If you write any interesting applications send them my way. I can be reached by way of the following email address.

Russ Leighton <russ@sneezy.lancaster.ca.us>

Also, it should be understood that I retain the copyright to the software 'MUIRexx' and as such do not give permission to anyone to sell or claim this software as their own. I do not, however, make any such claim to the scripts provided or to any scripts written that make use of 'MUIRexx'. The full distribution may be freely distributed, provided that the original distribution remains intact. Also, no fee may be charged for the software except for any nominal media and/or shipping charge. Additionally, this software (including all distribution contents) may not be included on any commercial disks (including disk magazines and cover disks) without the author's expressed permission. Exceptions to this rule includes any disks/CDROMs distributed by Cronus (Fred Fish) or Aminet. A limited distribution of 'MUIRexx' (binary and readme file only) may be distributed with software, with prior consent, provided that I am given due credit and that the software package be provided to me at no cost.

1.9 MUIRexx.guide/Requirements

Requirements

=====

The minimum system requirements needed to use 'MUIRexx' are as follows.

- * An Amiga! (any should do)
- * Version 3.0 of the Amiga operating system or higher
- * MUI 3.0 or better (see
MagicUserInterface
)
- * Icon.mcc custom class (included in the distribution)
- * ARexx (running of course)

Additionally, to run the included macros the following may be needed.

- * rexxsupport.library (needed by all the scripts)
- * some default icons and tools (take a look at the 'deficon.rexx' script)

The following are nice-to-have but not absolutely necessary.

- * A graphics card for high resolution and lots of colors
- * NewIcons ((C) Nicola Salmoria/Philip A. Vedovatti/Eric Sauvageau) for 256 color icons (great for thumbnail previews of images)
- * PictIcon ((C) Chad Randall) to generate those 256 color icons

1.10 MUIRexx.guide/Registration

Registration

As of version 2.2, 'MUIRexx' is now being distributed as "supportware". I am requesting that you consider registering 'MUIRexx' as a show of support for further development. Also, I will give registered users priority consideration for support and suggested changes/additions to 'MUIRexx'. I will continue to distribute updates periodically and will provide them without any crippled features, but I will offer more frequent updates to registered users.

To register please send the following information and cash, check, or money order of 15 US\\$\$ to

Russell Leighton
44614 Rodin Ave.
Lancaster, CA USA
93535

Registration information:

Name: _____
Address: _____
(optional) _____

Email: _____

Computer: _____
Memory: _____
OS version: _____
MUI version: _____
Comments: _____

1.11 MUIRexx.guide/Installation

Installation

Just copy the contents of the archive to any desired location and assign MUIREXX: to that directory (needed by the included macros).

Also, the external MUI class, Icon.mcc, must be copied to MUI:Libs/MUI. I recommend using the supplied install script which will install the class and all supporting files.

'MUIRexx' may be started either from a CLI or from the WorkBench. The command line syntax for 'MUIRexx' is:

```
-> [run] MUIRexx <script> PORT <portname> HELP <guidename>
```

If <SCRIPT> is specified then the corresponding 'ARexx' script will be executed, otherwise, the code will wait until it receives a command, presumably from a subsequently executed 'ARexx' command or script. The PORT option will set the 'MUIRexx' host address to <PORTNAME>. If not given then the host address will be MUIREXX. The HELP option specifies an AmigaGuide® file to be used for online help (see the NODE argument descriptions for selected gadgets).

To use 'MUIRexx' from the WorkBench a project icon must be supplied with the application startup script. The icon name should be the startup script name with the file extension .INFO replacing .REXX. Alternatively, a tooltype SCRIPT may be set to the name of the script to be executed on startup. The full path should be specified if the icon is not located in the same directory as the script. The default tool for the icon should be set to 'MUIRexx' (with the full path included if 'MUIRexx' is not in the global path). A tooltype PORT may be specified to set the host address name for the application. If this tooltype is not specified then the name will be set to the icon name (minus the .INFO extension). Also, a tooltype HELP may be included to specify the AmigaGuide® file as above. It is also recommended that the value for the stack size be set at a reasonable level (whatever that is). If problems occur running a script try setting the stack higher.

1.12 MUIRexx.guide/Command Reference

Command Reference

This chapter is included as a reference to the commands available for use in 'ARexx' macros.

Each command template is given in the standard DOS ReadArg form.

That is each argument name is given separated by commas with flags specified (separated by a /). Within an 'ARexx' script command arguments should be separated by space (not commas). The flag definitions are as follows:

Flag	Definition
/K	Keyword required.
/A	Argument required.
/F	Final argument. The remainder of the line will be set to this argument.
/M	Multiple arguments (separated by space).
/S	Switch argument.

Note that some string arguments shown in the examples are surrounded by two sets of quotes (consisting of a pair of single quotes and a pair of double quotes). The general rule of thumb is if the argument is the final argument (indicated by a /F in the command template) then only a single pair of quotes is necessary. Otherwise, if the string contains spaces then the two sets of quotes are necessary. The reason for this is that 'ARexx' tries to interpret every token it encounters. If the token is surrounded by quotes then the token is interpreted by removing the quotes and leaving the enclosed string intact. Likewise, the DOS ReadArgs function (used by 'MUI' to parse incoming 'ARexx' command lines) parses arguments separated by spaces, therefore, strings with spaces must be enclosed by quotes (hence, the need for the two sets of quotes). An exception is if the argument is designated as the final argument in which case the ReadArgs function will set the remainder of the command line as the final argument.

Standard Commands

Provided with all MUI apps

Windows

The parent of all

Groups

The layout

Menus

What is on the menu today?

Objects

The children

Misc

Those commands that don't fit above

1.13 MUIRexx.guide/Standard Commands

Standard Commands

=====

These commands are standard with all MUI applications.

quit

hide

show

info

help

1.14 MUIRexx.guide/quit

-- Command: quit FORCE/S

This command will end the 'MUIRexx' application, closing windows and freeing all associated memory. Note that if a script fails 'MUIRexx' may still actually be running. Use this command to end the process by using an inline 'ARexx' command (e.g. issue 'rx "address [portname] quit"' from a shell).

1.15 MUIRexx.guide/hide

-- Command: hide

Hides (iconifies) the application.

1.16 MUIRexx.guide/show

-- Command: show

Shows (pops up) an iconified application.

1.17 MUIRexx.guide/info

```
-- Command: info ITEM/A
According to the given parameter the result string is filled with
the following contents (or something reasonably close):

* "title" - Name of the ARexx port

* "author" - "Russell Leighton"

* "copyright" - "Copyright ©1995-1996, Russell Leighton"

* "description" - "MUI Rexx interface."

* "version" - "$VER: MUIRexx 2.2"

* "base" - Name of the ARexx port

* "screen" - Name of the public screen
```

1.18 MUIRexx.guide/help

```
-- Command: help FILE/A
A list of all 'ARexx' commands available for the application is
written into the given file. In addition to the default commands
an MUI application can (and of course should) support many
application specific commands. The help list will contain these
commands as well.
```

1.19 MUIRexx.guide/Windows

Windows

=====

These commands are used for window creation and disposal. At least one window is required.

window

Begin window definition

endwindow

End window definition

1.20 MUIRexx.guide/window

```
-- Command: window ID/K, COMMAND/K, PORT/K, TITLE/K, CLOSE/S, ←
ATTRS/K/M
```

This command begins the definition of a window. All group and initial object definitions must be placed between a 'window' and 'endwindow' pair. The arguments are optional.

- * ID [I..] - an id can be assigned to a window for later reference. The id can be any combination of up to 5 characters.
- * COMMAND [I..] - if given, a close gadget will be attached to the window. If the null string is specified then the window will simply be disposed when the close gadget is selected, otherwise, the command string given will be executed. The command will be issued to the host port specified by the PORT argument. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the window title (see the TITLE argument description). Also, note that it is up to the programmer to insure that the window is in fact closed, presumably by the macro that is specified in this argument.
- * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the close gadget is selected. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. This, in fact, would be a way to dispose of the window or even the application itself.
- * TITLE [I..] - the window may be given a title which will be displayed in the windows title bar.
- * CLOSE [.S.] - if this switch is given and an id specified (see ID argument) for an existing window then the window will be closed.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with the window command are:

TAG_Name =	TAG_id	Flags	Type
Window_Activate =	0x80428d2f	/* V4 isg	BOOL */
Window_AltHeight =	0x8042cce3	/* V4 i.g	LONG */
Window_AltLeftEdge =	0x80422d65	/* V4 i.g	LONG */
Window_AltTopEdge =	0x8042e99b	/* V4 i.g	LONG */


```

Window_AltWidth =          0x804260f4 /* V4  i.g LONG */
Window_AppWindow =        0x804280cf /* V5  i.. BOOL */
Window_Backdrop =         0x8042c0bb /* V4  i.. BOOL */
Window_Borderless =       0x80429b79 /* V4  i.. BOOL */
Window_DepthGadget =      0x80421923 /* V4  i.. BOOL */
Window_DragBar =          0x8042045d /* V4  i.. BOOL */
Window_Height =           0x80425846 /* V4  i.g LONG */
Window_IsSubWindow =      0x8042b5aa /* V4  isg BOOL */
Window_LeftEdge =         0x80426c65 /* V4  i.g LONG */
Window_NoMenus =          0x80429df5 /* V4  is.  BOOL */
Window_Open =             0x80428aa0 /* V4  .sg BOOL */
Window_PublicScreen =     0x804278e4 /* V6  isg STRPTR */
Window_ScreenTitle =      0x804234b0 /* V5  isg STRPTR */
Window_SizeGadget =       0x8042e33d /* V4  i.. BOOL */
Window_SizeRight =        0x80424780 /* V4  i.. BOOL */
Window_Sleep =            0x8042e7db /* V4  .sg BOOL */
Window_TopEdge =          0x80427c66 /* V4  i.g LONG */
Window_UseBottomBorderScroller = 0x80424e79 /* V13 is.  BOOL */
Window_UseLeftBorderScroller = 0x8042433e /* V13 is.  BOOL */
Window_UseRightBorderScroller = 0x8042c05e /* V13 is.  BOOL */
Window_Width =            0x8042dcae /* V4  i.g LONG */
InnerBottom =             0x8042f2c0 /* V4  i.g LONG */
InnerLeft =               0x804228f8 /* V4  i.g LONG */
InnerRight =              0x804297ff /* V4  i.g LONG */
InnerTop =                0x80421eb6 /* V4  i.g LONG */

```

Note: Consult MUI:Developer/Autodocs/MUI_Window.doc and
MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID DOCK ATTRS InnerBottom 0 InnerLeft 0 InnerRight 0 InnerTop 0
.
.
.
endwindow

window ID DOCK ATTRS Window_Open
say result

```

1.21 MUIRexx.guide/endwindow

-- Command: endwindow

This command ends the definition of a window. All group and initial object definitions must be placed between a 'window' and 'endwindow' pair. The defined window will be opened after issuing this command.

1.22 MUIRexx.guide/Groups

Groups

=====

The following commands are used for group creation. Some arguments can be used after the groups window is opened to change or retrieve settings. In the argument descriptions the keywords are followed by a pair of [] containing indicator letters. If the letter I is indicated then the argument is valid during creation. If the letter S is indicated then the argument can be set after the groups window is open. If the letter G is indicated then the argument can be retrieved.

group

endgroup

1.23 MUIRexx.guide/group

-- Command: group ID/K, COMMAND/K, PORT/K, FRAME/S, HORIZ/S, REGISTER/S, VIRTUAL/S, SCROLL/S, LABEL=LABELS/K, ATTRS/K/M
This command begins the definition of a group. Groups are defined by placement of other groups and objects between a 'group' and 'endgroup' pair. The arguments are optional.

- * ID [I..] - an id can be assigned to a group for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the group has been previously created then the group will be placed into a temporary state where objects can be added or existing objects changed. The 'endgroup' command will terminate this temporary state and cause the affected window to be updated. Note that only gadgets can be added or changed, not groups. In this manner a window's contents may be dynamically altered. In particular, object settings that can only be specified when they are initially created (those arguments indicated with a I) can be changed utilizing this feature.
- * COMMAND [I..] - if given, then the command will be issued to the port (specified by the PORT option) if an object is dropped on the group either by drag&drop or from the Workbench. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the object name (as specified by the LABEL of the dropped object or the fully qualified file name of the icon if dropped from the Workbench). Note that this capability is not available for register or virtual groups.
- * PORT [I..] - a specific host port may be specified by this

argument. The defined command will be issued to this port whenever an object is dropped on the group. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself.

- * FRAME [I..] - if this switch is given then a frame will be rendered for the group.
 - * HORIZ [I..] - if this switch is given then the group will be arranged horizontally. If not specified then the group will be arranged vertically.
 - * REGISTER [I..] - if this switch is given then the group will be defined as a register group (i.e. a group consisting of pages of objects or groups). The LABELS argument must be given if this switch is specified.
 - * VIRTUAL [I..] - if this switch is given then the group will be defined as a virtual group (i.e. a group whose contents can be larger than the display region). This option will result in a virtual group with no scroll bars. The virtual group can be scrolled, however, by using the mouse (i.e. press and hold down the left mouse button while in the group and move past the edges or if you have a middle mouse button press and hold it while in the group and just move the mouse).
 - * SCROLL [I..] - if this switch is given then the group will be defined as a virtual group (i.e. a group whose contents can be larger than the display region). This option will result in a virtual group with scroll bars. The virtual group can be scrolled with the scroll bar gadgets or alternatively with the mouse as described above.
 - * LABEL=LABELS [ISG] - either a group title or register labels are specified with this option. Multiple labels are separated by commas. If the REGISTER switch was given then the labels correspond to the page titles. For each label specified there must be a corresponding group or object defined. If the REGISTER switch was not given then the first label will be rendered as a group title. For register groups, if the group was previously created (and its window is open) then the current page may be set by issuing the group command, with an existing ID, and a label corresponding to the page to be activated. Also, if an ID and the REGISTER switch are given without a label then the currently displayed page label will be returned in the 'ARexx' variable RESULT (if 'options results' was specified in the 'ARexx' script).
 - * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see
Attribute TAGs
).
-

Some useful TAGs for use with the group command are:

TAG_Name =	TAG_id	Flags	Type
Group_ActivePage =	0x80424199 /*	V5	isg LONG */
Group_Columns =	0x8042f416 /*	V4	is. LONG */
Group_Horiz =	0x8042536b /*	V4	i.. BOOL */
Group_HorizSpacing =	0x8042c651 /*	V4	isg LONG */
Group_PageMode =	0x80421a5f /*	V5	i.. BOOL */
Group_Rows =	0x8042b68f /*	V4	is. LONG */
Group_SameHeight =	0x8042037e /*	V4	i.. BOOL */
Group_SameSize =	0x80420860 /*	V4	i.. BOOL */
Group_SameWidth =	0x8042b3ec /*	V4	i.. BOOL */
Group_Spacing =	0x8042866d /*	V4	is. LONG */
Group_VertSpacing =	0x8042e1bf /*	V4	isg LONG */

Note: Consult MUI:Developer/Autodocs/MUI_Group.doc and
MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID MDIR
    group ID REG REGISTER LABELS 'Directory, Buffers, Volumes, Mirror'
    .
    .
    .
endwindow

group ID REG REGISTER
say result

```

1.24 MUIRexx.guide/endgroup

-- Command: endgroup

This command ends the definition of a group. Groups are defined by placement of other groups and objects between a 'group' and 'endgroup' pair.

1.25 MUIRexx.guide/Menus

Menus

=====

The following commands are used for menu creation.

```

    menu

    endmenu

    item

```

1.26 MUIRexx.guide/menu

-- Command: menu ID/K, LABEL/K, ATTRS/K/M

This command begins the definition of a menu. Menus are defined by placement of other menus and menu items between a 'menu' and 'endmenu' pair. If a menu is defined within a window definition (i.e. between a WINDOW and ENDWINDOW pair), but outside any group definitions then the menu will be added to the window menu strip. If a menu is defined within a group then a context sensitive menu will be created for the group (i.e. when the mouse pointer is over the group and the right mouse button is pressed then a popup menu will be displayed). Note that only one menu may be defined for a context sensitive menu (all others will be ignored).

- * ID [I..] - an id can be assigned to a menu for later reference. The id can be any combination of up to 5 characters.
- * LABEL [I..] - the menu must be given a label which will be displayed in the menu bar of the window.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with the menu command are:

TAG_Name =	TAG_id	Flags Type
Menu_Enabled =	0x8042ed48	/* V8 isg BOOL */

Note: Consult MUI:Developer/Autodocs/MUI_Menu.doc, MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

1.27 MUIRexx.guide/endmenu

-- Command: endmenu

This command ends the definition of a menu. Menus are defined by placement of other menus and menu items between a 'menu' and 'endmenu' pair.

1.28 MUIRexx.guide/item

-- Command: item ID/K, COMMAND/K, PORT/K, LABEL/K, ATTRS/K/M

This command defines a menu item. This command is only valid between a 'menu' and 'endmenu' pair.

- * ID [I..] - an id can be assigned to a menu item for later reference. The id can be any combination of up to 5 characters.
- * COMMAND [I..] - if given, the command will be executed whenever the menu item is selected. The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the string given for the menu item (see the LABEL argument description).
- * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the menu item is selected. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
- * LABEL [I..] - this is the text for the menu item (which must be given).
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with the item command are:

TAG_Name =	TAG_id	Flags	Type
Menuitem_Checked =	0x8042562a /*	V8 isg	BOOL */
Menuitem_Checkit =	0x80425ace /*	V8 isg	BOOL */
Menuitem_Enabled =	0x8042ae0f /*	V8 isg	BOOL */
Menuitem_Exclude =	0x80420bc6 /*	V8 isg	LONG */
Menuitem_Shortcut =	0x80422030 /*	V8 isg	STRPTR */
Menuitem_Title =	0x804218be /*	V8 isg	STRPTR */
Menuitem_Toggle =	0x80424d5c /*	V8 isg	BOOL */

Note: Consult MUI:Developer/Autodocs/MUI_Menuitem.doc and
MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```
window TITLE ' "MUIRexx Demo" ' COMMAND ' "quit" ' PORT DEMO
  menu LABEL ' "Project" '
    .
    .
    .
    item ATTRS Menuitem_Title '-1' /* item separator bar */
    item COMMAND ' "quit" ' PORT DEMO LABEL 'Quit'
  endmenu
  .
  .
  .
endwindow
```

1.29 MUIRexx.guide/Objects

Objects

=====

The following commands are used to create and manipulate objects. Some arguments can be used after the object's window is opened to change or retrieve settings. Also, issuing an object command with only an ID argument will return a result in the 'ARexx' variable RESULT (if 'options results' was specified in the 'ARexx' script). In the argument descriptions the keywords are followed by a pair of [] containing indicator letters. If the letter I is indicated then the argument is valid during creation. If the letter S is indicated then the argument can be set after the objects window is open. If the letter G is indicated then the argument can be retrieved.

space

label

view

gauge

meter

text

button

switch

```
image
check
cycle
radio
string
popasl
poplist
slider
popslider
knob
list
dirlist
volumelist
object
```

1.30 MUIRexx.guide/space

```
-- Command: space BAR/S, HORIZ/S, VALUE
This object will place some white space into the current location.
A consequence of placing space is that the window will be sizable
in the associated direction. The arguments are optional.

* BAR [I..] - if this switch is given then a bar will be
  rendered in the center of the space.

* HORIZ [I..] - if this switch is given then the space will be a
  horizontal space (best used within a horizontal group)
  otherwise the space will be vertical.

* VALUE [I..] - this argument, if given, specifies the minimum
  amount of space. The default value is zero.
```

Example use of this command:

```
window
.
.
.
group HORIZ
  button LABEL 'OK'
```



```

        space BAR 0
        button LABEL 'Cancel'
    endgroup
endwindow

```

1.31 MUIRexx.guide/label

-- Command: label LEFT/S, CENTER/S, SINGLE/S, DOUBLE/S, LABEL/F/A
 This object is a simple label that can be used in conjunction with another object for clarification of the other objects purpose.

- * LEFT [I..] - this switch will force the label to be left justified.
- * CENTER [I..] - this switch will force the label to be centered.
- * SINGLE [I..] - this switch will cause extra vertical space to be added to the label to center it about the same space occupied by an object with a single width frame.
- * DOUBLE [I..] - this switch will cause extra vertical space to be added to the label to center it about the same space occupied by an object with a double width frame.
- * LABEL [I..] - this is the text for the label (which must be the last argument and may contain spaces).

Example use of this command:

```

window
.
.
.
  group HORIZ
    label '"string:"'
    string ID STR1
  endgroup
endwindow

```

1.32 MUIRexx.guide/view

-- Command: view ID/K, HELP/K, NODE/K, FILE/K, STRING/K/F, ATTRS/ ↔
 K/M

This specifies a view object.

- * ID [I..] - an id can be assigned to a view for later reference. The id can be any combination of up to 5

characters.

- * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated view object. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
- * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the view object and presses the help button on the keyboard then the guide file will be displayed at the node location.
- * FILE [I..] - If this argument is given then the view contents will be retrieved from the specified file.
- * STRING [I..] - this is the view content string. Note that the string may contain any of the special formatting sequences (see MUI Format Sequences). Also, if this argument is given then it must be the last specified.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with the gauge command are:

TAG_Name =	TAG_id	Flags Type
Floattext_Justify =	0x8042dc03	/* V4 isg BOOL */
Floattext_SkipChars =	0x80425c7d	/* V4 is. STRPTR */
Floattext_TabSize =	0x80427d17	/* V4 is. LONG */
Floattext_Text =	0x8042d16a	/* V4 isg STRPTR */

Note: Consult MUI:Developer/Autodocs/MUI_Floattext.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID LHA TITLE ' "Archive List" '
  view ID LVIEW FILE ' "ram:t/lha.out" '
  .
  .
  .
endwindow

view ID LVIEW ATTRS Floattext_Text
say import (d2c(result))

```

1.33 MUIRexx.guide/gauge

-- Command: gauge ID/K, HELP/K, NODE/K, LABEL/K, ATTRS/K/M
Gauge objects are created with this command.

- * ID [I..] - an id can be assigned to a gauge for later reference. The id can be any combination of up to 5 characters.
- * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated gauge. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
- * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the gauge and presses the help button on the keyboard then the guide file will be displayed at the node location.
- * LABEL [I..] - if given this label will be displayed in the gauge. A format specifier '%ld' may be included in the string which will be replaced by the current gauge level.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see
Attribute TAGs
).

Some useful TAGs for use with the gauge command are:

TAG_Name =	TAG_id	Flags	Type
Gauge_Current =	0x8042f0dd	/* V4 isg	LONG */
Gauge_Divide =	0x8042d8df	/* V4 isg	BOOL */
Gauge_Horiz =	0x804232dd	/* V4 i..	BOOL */
Gauge_InfoText =	0x8042bf15	/* V7 isg	STRPTR */
Gauge_Max =	0x8042bcdb	/* V4 isg	LONG */

Note: Consult MUI:Developer/Autodocs/MUI_Gauge.doc and
MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window TITLE "Test" COMMAND "quit" PORT DEMO
.
.
.
group
  slider ID SLDR
  gauge ID GAUG LABEL "level %ld" ATTRS Gauge_Horiz TRUE
  object CLASS "Scale.mui"
.
.
.

```

```

    group HORIZ
      group
        label DOUBLE ' "Hue:" '
        label DOUBLE ' "Saturation:" '
      endgroup
      group
        gauge ID HUE ATTRS Gauge_Max 16384,
                    Gauge_Divide 262144,
                    Gauge_Horiz TRUE
        gauge ID SAT ATTRS Gauge_Max 16384,
                    Gauge_Divide 262144,
                    Gauge_Horiz TRUE
      endgroup
    endgroup
  endgroup
endwindow

method ID SLDR Notify Numeric_Value EveryTime,
          @GAUG 3 Set Gauge_Current TriggerValue

```

1.34 MUIRexx.guide/meter

-- Command: meter ID/K, HELP/K, NODE/K, LABEL/K, ATTRS/K/M
 Meter objects are created with this command.

- * ID [I..] - an id can be assigned to a meter for later reference. The id can be any combination of up to 5 characters.
- * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated meter. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
- * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the meter and presses the help button on the keyboard then the guide file will be displayed at the node location.
- * LABEL [I..] - if given this label will be displayed in the meter.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with the meter command are:

TAG_Name =	TAG_id	Flags	Type
------------	--------	-------	------

```

Numeric_Default =          0x804263e8 /* V11 isg LONG */
Numeric_Format =          0x804263e9 /* V11 isg STRPTR */
Numeric_Max =             0x8042d78a /* V11 isg LONG */
Numeric_Min =             0x8042e404 /* V11 isg LONG */
Numeric_Reverse =         0x8042f2a0 /* V11 isg BOOL */
Numeric_RevLeftRight =    0x804294a7 /* V11 isg BOOL */
Numeric_RevUpDown =       0x804252dd /* V11 isg BOOL */
Numeric_Value =           0x8042ae3a /* V11 isg LONG */

```

Note: Consult MUI:Developer/Autodocs/MUI_Numeric.doc and
MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window TITLE "Test" COMMAND "quit" PORT DEMO
.
.
.
group
  group HORIZ
    knob ID KNOB HELP "an example knob gadget" NODE "knob"
    meter ID METR NODE "meter" LABEL 'meter'
  endgroup
endgroup
endwindow

method ID KNOB Notify Numeric_Value EveryTime,
          @METR 3 Set Numeric_Value TriggerValue

```

1.35 MUIRexx.guide/text

```
-- Command: text ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, PRESS/S ←
```

APP/S, DROP/S, ICON/K, PICT/K, TRANS/S, LABEL/K/F, ATTRS/K/M
Text gadget objects are created with this command. Text, button and switch gadgets are essentially identical with the only difference being the base object class to create each type of object. All options are identical for these objects.

- * ID [I..] - an id can be assigned to a gadget for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the object has been previously created, then the label will be returned in RESULT (if OPTIONS RESULTS is specified in the script).
- * COMMAND [IS.] - if given, the command will be executed whenever the gadget is pressed (PRESS switch specified or default for no switch), an icon is dropped (APP switch), or another object is dropped (DROP switch) on the gadget. The command will be issued to the host port specified by the PORT

argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the gadget label (see the LABEL argument description), an icon name (if an icon was dropped on the gadget), or another objects label (if an object is dropped on the gadget). Additionally, if the gadget is an icon (specified by the ICON argument) and a command is not specified but a port is (see PORT argument description) then the command will be set to the default tool of the icon. For example, if the icons default tool is 'MultiView' then the command string will be set to 'MultiView %s'. Note that commands may be defined after the gadget has been created. In this way different commands may be defined for each action.

- * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the gadget is activated. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
 - * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated gadget. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
 - * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the gadget and presses the help button on the keyboard then the guide file will be displayed at the node location.
 - * PRESS [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if the object is pressed.
 - * APP [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if an icon is dropped on the object from the Workbench.
 - * DROP [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if another object is dropped on the object through a drag and drop operation.
 - * ICON [I..] - the name of an icon may be specified with this argument. If given then the gadget image will be set to the
-

icon image. Note that the name of the icon should not be specified with a ".info".

- * PICT [I..] - the name of a picture may be specified with this argument. If given then the gadget image will be set to the picture content. Any picture with an associated installed datatype may be used.
- * TRANS [I..] - if this flag is given then the background color of the picture (defined with the PICT option) will be transparent.
- * LABEL [ISG] - the label for the gadget is given by this argument. Note that the string may contain any of the special formatting sequences (see MUI Format Sequences).
Additionally, even though the label is not displayed for icon gadgets it may still be used in the command string (see COMMAND argument above).
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags	Type
Text_Contents =	0x8042f8dc	/* V4 isg	STRPTR */
Text_HiChar =	0x804218ff	/* V4 i..	char */
Text_PreParse =	0x8042566d	/* V4 isg	STRPTR */
Text_SetMax =	0x80424d0a	/* V4 i..	BOOL */
Text_SetMin =	0x80424e10	/* V4 i..	BOOL */
Text_SetVMax =	0x80420d8b	/* V11 i..	BOOL */
ControlChar =	0x8042120b	/* V4 isg	char */
CycleChain =	0x80421ce7	/* V11 isg	LONG */
Disabled =	0x80423661	/* V4 isg	BOOL */
Draggable =	0x80420b6e	/* V11 isg	BOOL */
FixHeight =	0x8042a92b	/* V4 i..	LONG */
FixHeightTxt =	0x804276f2	/* V4 i..	STRPTR */
FixWidth =	0x8042a3f1	/* V4 i..	LONG */
FixWidthTxt =	0x8042d044	/* V4 i..	STRPTR */
HorizDisappear =	0x80429615	/* V11 isg	LONG */
HorizWeight =	0x80426db9	/* V4 isg	WORD */
MaxHeight =	0x804293e4	/* V11 i..	LONG */
MaxWidth =	0x8042f112	/* V11 i..	LONG */
Selected =	0x8042654b	/* V4 isg	BOOL */
ShowMe =	0x80429ba8	/* V4 isg	BOOL */
ShowSelState =	0x8042caac	/* V4 i..	BOOL */
VertDisappear =	0x8042d12f	/* V11 isg	LONG */
VertWeight =	0x804298d0	/* V4 isg	WORD */
Weight =	0x80421d1f	/* V4 i..	WORD */

Note: Consult MUI:Developer/Autodocs/MUI_Text.doc, MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID MRX1 TITLE 'demo' COMMAND 'window ID MRX1 CLOSE' PORT DEMO
  text LABEL 'A demonstration of MUIRexx'
  button ID BUT COMMAND 'out %s' HELP 'button 1' LABEL 'button 1'
  switch ID SWCH LABEL 'switch'
  .
  .
  .
endwindow

switch ID SWCH ATTRS Selected
say result

```

1.36 MUIRexx.guide/button

```

-- Command: button ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, PRESS ←
/S,
APP/S, DROP/S, ICON/K, PICT/K, TRANS/S, LABEL/K/F, ATTRS/K/M

```

Button gadget objects are created with this command. Text, button and switch gadgets are essentially identical with the only difference being the base object class to create each type of object. All options are identical for these objects. Refer to the

```

text
command for descriptions of the options.

```

1.37 MUIRexx.guide/switch

```

-- Command: switch ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, PRESS ←
/S,
APP/S, DROP/S, ICON/K, PICT/K, TRANS/S, LABEL/K/F, ATTRS/K/M

```

Switch gadget objects are created with this command. Text, button and switch gadgets are essentially identical with the only difference being the base object class to create each type of object. The switch gadget also differs in that its select state toggles with each press. All options are identical for these objects. Refer to the

```

text
command for descriptions of the
options.

```


1.38 MUIRexx.guide/image

```
-- Command: image ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, SPEC/K ←  
                /  
                STRING/K, ATTRS/K/M
```

Image gadget objects are created with this command. Check and image gadgets are essentially identical with the only difference being that check gadgets toggle their select state and images do not. All options are identical for these objects.

- * ID [I..] - an id can be assigned to a gadget for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the gadget has been previously created, then the select state string will be returned in RESULT (if OPTIONS RESULTS is specified in the script).
- * COMMAND [IS.] - if given, the command will be executed whenever the gadget is pressed. The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the string given for the gadget select state (see the STRINGS argument description).
- * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the gadget is activated. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
- * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated gadget. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
- * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the gadget and presses the help button on the keyboard then the guide file will be displayed at the node location.
- * SPEC [I..] - this argument is used to specify a MUI image specification (see MUI Image Specifications). If not given

then the image 'MUII_CheckMark' will be used.

- * STRING=STRINGS [ISG] - strings may be defined, by this option, that will be returned depending on the select state of the gadget (for check gadgets). The first defines the unselected string and the second defines the selected. If not specified then the unselected string will be set to 0 and the selected string will be set to 1. Note that for image gadgets the first string will always be returned.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags	Type
ControlChar =	0x8042120b	/* V4	isg char */
CycleChain =	0x80421ce7	/* V11	isg LONG */
Disabled =	0x80423661	/* V4	isg BOOL */
FixHeight =	0x8042a92b	/* V4	i.. LONG */
FixHeightTxt =	0x804276f2	/* V4	i.. STRPTR */
FixWidth =	0x8042a3f1	/* V4	i.. LONG */
FixWidthTxt =	0x8042d044	/* V4	i.. STRPTR */
HorizDisappear =	0x80429615	/* V11	isg LONG */
HorizWeight =	0x80426db9	/* V4	isg WORD */
MaxHeight =	0x804293e4	/* V11	i.. LONG */
MaxWidth =	0x8042f112	/* V11	i.. LONG */
Selected =	0x8042654b	/* V4	isg BOOL */
ShowMe =	0x80429ba8	/* V4	isg BOOL */
VertDisappear =	0x8042d12f	/* V11	isg LONG */
VertWeight =	0x804298d0	/* V4	isg WORD */
Weight =	0x80421d1f	/* V4	i.. WORD */

Note: Consult MUI:Developer/Autodocs/MUI_Image.doc, MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID MRX1 TITLE 'demo' COMMAND 'window ID MRX1 CLOSE' PORT DEMO
  group
    check ID CHK1 STRINGS 'no,yes' ATTRS Selected TRUE
    image SPEC '4:MUI:Images/WD/13pt/PopUp.mf0'
    .
    .
    .
  endgroup
endwindow

```

1.39 MUIRexx.guide/check

-- Command: check ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, SPEC/K ↔

STRING=STRINGS/K, ATTRS/K/M

Check gadget objects are created with this command. Check and image gadgets are essentially identical with the only difference being that check gadgets toggle their select state and images do not. All options are identical for these objects. Refer to the

image

command for descriptions of the options.

1.40 MUIRexx.guide/cycle

-- Command: cycle ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, LABEL=LABELS/K, ATTRS/K/M

Cycle gadget objects are created with this command. Cycle and radio gadgets are essentially identical with the only difference being the base object class to create each type of object. All options are identical for these objects.

- * ID [I..] - an id can be assigned to a gadget for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the gadget has been previously created, then the currently selected label will be returned in RESULT (if OPTIONS RESULTS is specified in the script).
- * COMMAND [IS.] - if given, the command will be executed whenever the gadget is selected. The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the gadget active label (see the LABELS argument description).
- * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the gadget is activated. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.

- * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated gadget. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
- * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the gadget and presses the help button on the keyboard then the guide file will be displayed at the node location.
- * LABELS [ISG] - a series of strings (separated by commas) may be specified by this argument. These strings are used as the labels for the gadget object. The currently displayed label may be retrieved by issuing the gadget command with an existing ID. Also, the selected label may be set by issuing the gadget command with an existing ID and label. Note that the labels may contain any of the special formatting sequences (see
 MUI Format Sequences
).
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see
 Attribute TAGs
).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags Type
Cycle_Active =	0x80421788 /* V4	isg LONG */
Radio_Active =	0x80429b41 /* V4	isg LONG */
ControlChar =	0x8042120b /* V4	isg char */
CycleChain =	0x80421ce7 /* V11	isg LONG */
Disabled =	0x80423661 /* V4	isg BOOL */
FixHeight =	0x8042a92b /* V4	i.. LONG */
FixHeightTxt =	0x804276f2 /* V4	i.. STRPTR */
FixWidth =	0x8042a3f1 /* V4	i.. LONG */
FixWidthTxt =	0x8042d044 /* V4	i.. STRPTR */
HorizDisappear =	0x80429615 /* V11	isg LONG */
HorizWeight =	0x80426db9 /* V4	isg WORD */
MaxHeight =	0x804293e4 /* V11	i.. LONG */
MaxWidth =	0x8042f112 /* V11	i.. LONG */
Selected =	0x8042654b /* V4	isg BOOL */
ShowMe =	0x80429ba8 /* V4	isg BOOL */
VertDisappear =	0x8042d12f /* V11	isg LONG */
VertWeight =	0x804298d0 /* V4	isg WORD */
Weight =	0x80421d1f /* V4	i.. WORD */

Note: Consult MUI:Developer/Autodocs/MUI_Cycle.doc, MUI_Radio.doc, MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID PAGE TITLE ' "Character Definition"'
  group HORIZ
    group
      label SINGLE 'Name:'
      label SINGLE 'Sex:'
    endgroup
    group
      string ID NAME CONTENT 'Frodo'
      cycle ID SEX LABELS 'male,female'
    endgroup
  endgroup
  space 2
  group REGISTER LABELS 'Race,Class,Armor,Level'
    group FRAME
      radio ID RACE LABELS 'Human,Elf,Dwarf,Hobbit,Gnome'
    endgroup
    .
    .
    .
endwindow

cycle ID SEX
say result
radio ID RACE
say result

```

1.41 MUIRexx.guide/radio

```

-- Command: radio ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K,
  LABEL=LABELS/K, ATTRS/K/M

```

Radio gadget objects are created with this command. Cycle and radio gadgets are essentially identical with the only difference being the base object class to create each type of object. All options are identical for these objects. Refer to the

cycle

command for descriptions of the options.

1.42 MUIRexx.guide/string

```

-- Command: string ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K,
  CONTENT/K/F, ATTRS/K/M

```

String gadget objects are created with this command. String and popasl gadgets are essentially identical with the only difference being the base object class to create each type of object. All options are identical for these objects.

- * ID [I..] - an id can be assigned to a string gadget for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the string gadget has been previously created, then the current string gadget content will be returned in RESULT (if OPTIONS RESULTS is specified in the script).
- * COMMAND [IS.] - if given, the command will be executed whenever the string is entered (i.e. a carriage return is hit while the gadget is active). The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the string gadget contents (see the CONTENT argument description).
- * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the string gadget is activated. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
- * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated string gadget. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
- * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the string gadget and presses the help button on the keyboard then the guide file will be displayed at the node location.
- * CONTENT [ISG] - the contents of the string gadget is given by this argument.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see
Attribute TAGs
).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags Type
String_Accept =	0x8042e3e1	/* V4 isg STRPTR */
String_AdvanceOnCR =	0x804226de	/* V11 isg BOOL */

```

String_BufferPos =          0x80428b6c /* V4  .sg LONG */
String_Contents =          0x80428ffd /* V4  isg STRPTR */
String_DisplayPos =        0x8042ccb5 /* V4  .sg LONG */
String_Format =            0x80427484 /* V4  i.g LONG */
String_Integer =           0x80426e8a /* V4  isg ULONG */
String_MaxLen =            0x80424984 /* V4  i.g LONG */
String_Reject =            0x8042179c /* V4  isg STRPTR */
String_Secret =            0x80428769 /* V4  i.g BOOL */
ControlChar =              0x8042120b /* V4  isg char */
CycleChain =               0x80421ce7 /* V11 isg LONG */
Disabled =                 0x80423661 /* V4  isg BOOL */
FixHeight =                0x8042a92b /* V4  i.. LONG */
FixHeightTxt =             0x804276f2 /* V4  i.. STRPTR */
FixWidth =                 0x8042a3f1 /* V4  i.. LONG */
FixWidthTxt =              0x8042d044 /* V4  i.. STRPTR */
HorizDisappear =           0x80429615 /* V11 isg LONG */
HorizWeight =              0x80426db9 /* V4  isg WORD */
MaxHeight =                0x804293e4 /* V11 i.. LONG */
MaxWidth =                 0x8042f112 /* V11 i.. LONG */
Selected =                 0x8042654b /* V4  isg BOOL */
ShowMe =                   0x80429ba8 /* V4  isg BOOL */
VertDisappear =            0x8042d12f /* V11 isg LONG */
VertWeight =               0x804298d0 /* V4  isg WORD */
Weight =                   0x80421d1f /* V4  i.. WORD */

```

Note: Consult MUI:Developer/Autodocs/MUI_String.doc,
MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID MAIN TITLE "ShowIcon"
  group HORIZ
    button "parent" WEIGHT 0 COMMAND "showicon /"
    string ID STRG COMMAND "dirlist ID LIST PATH %s" PORT SHOW
  endgroup
  .
  .
  .
  popasl ID 104 HELP "this is an example popasl gadget"
endwindow

string ID STRG
say result

```

1.43 MUIRexx.guide/popasl

```

-- Command: popasl ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, SPEC/ ←
K,
CONTENT/K/F, ATTRS/K/M

```

Popasl gadget objects are created with this command. String and popasl gadgets are essentially identical with the only difference being the base object class to create each type of object. The

most notable difference is that the popasl object has an attached button that allows the user to bring up an ASL file requestor. The selected file is placed into the string content. All options are identical for these objects with the exception of the SPEC option (used to specify the popbutton image specification). Refer to the

string
command for descriptions of these options.

- * SPEC [I..] - this argument is used to specify a MUI image specification (see MUI Image Specifications) for the popbutton. If not given then the image 'MUUI_PopUp' will be used.

1.44 MUIRexx.guide/poplist

-- Command: poplist ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, SPEC ←
/K,

CONTENT/K/F, LABELS/K, ATTRS/K/M

Poplist gadget objects are created with this command. String and poplist gadgets are essentially identical with the only difference being the base object class to create each type of object. The most notable difference is that the poplist object has an attached button that allows the user to bring up a list of strings (specified with the LABELS option). All options are identical for these objects with the exception of the SPEC option (used to specify the popbutton image specification) and the LABELS option. Refer to the

string
command for descriptions of these options.

- * SPEC [I..] - this argument is used to specify a MUI image specification (see MUI Image Specifications) for the popbutton. If not given then the image 'MUUI_PopUp' will be used.
- * LABELS [ISG] - a series of strings (separated by commas) may be specified by this argument. These strings are used as the labels for the poplist object.

1.45 MUIRexx.guide/slider

-- Command: slider ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, ATTRS ←
/K/M

Slider gadget objects are created with this command. Slider, popslider and knob gadgets are essentially identical with the only difference being the base object class to create each type of object. All options are identical for these objects.

- * ID [I..] - an id can be assigned to a slider gadget for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the slider gadget has been previously created, then the current slider level will be returned in RESULT (if OPTIONS RESULTS is specified in the script).
 - * COMMAND [IS.] - if given, the command will be executed whenever the slider gadget is changed. The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the slider gadget level. Caution must be taken since movement of the slider can result in a lot of commands. If the command is at all time consuming the result will be very sluggish slider action.
 - * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the slider gadget is activated. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
 - * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated slider gadget. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
 - * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the slider gadget and presses the help button on the keyboard then the guide file will be displayed at the node location.
 - * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see
Attribute TAGs
).
-

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags	Type
Slider_Horiz =	0x8042fad1	/* V11 isg	BOOL */
Slider_Level =	0x8042ae3a	/* V4 isg	LONG */
Slider_Max =	0x8042d78a	/* V4 isg	LONG */
Slider_Min =	0x8042e404	/* V4 isg	LONG */
Slider_Quiet =	0x80420b26	/* V6 i..	BOOL */
Slider_Reverse =	0x8042f2a0	/* V4 isg	BOOL */
Numeric_Default =	0x804263e8	/* V11 isg	LONG */
Numeric_Format =	0x804263e9	/* V11 isg	STRPTR */
Numeric_Max =	0x8042d78a	/* V11 isg	LONG */
Numeric_Min =	0x8042e404	/* V11 isg	LONG */
Numeric_Reverse =	0x8042f2a0	/* V11 isg	BOOL */
Numeric_RevLeftRight =	0x804294a7	/* V11 isg	BOOL */
Numeric_RevUpDown =	0x804252dd	/* V11 isg	BOOL */
Numeric_Value =	0x8042ae3a	/* V11 isg	LONG */
ControlChar =	0x8042120b	/* V4 isg	char */
CycleChain =	0x80421ce7	/* V11 isg	LONG */
Disabled =	0x80423661	/* V4 isg	BOOL */
FixHeight =	0x8042a92b	/* V4 i..	LONG */
FixHeightTxt =	0x804276f2	/* V4 i..	STRPTR */
FixWidth =	0x8042a3f1	/* V4 i..	LONG */
FixWidthTxt =	0x8042d044	/* V4 i..	STRPTR */
HorizDisappear =	0x80429615	/* V11 isg	LONG */
HorizWeight =	0x80426db9	/* V4 isg	WORD */
MaxHeight =	0x804293e4	/* V11 i..	LONG */
MaxWidth =	0x8042f112	/* V11 i..	LONG */
Selected =	0x8042654b	/* V4 isg	BOOL */
ShowMe =	0x80429ba8	/* V4 isg	BOOL */
VertDisappear =	0x8042d12f	/* V11 isg	LONG */
VertWeight =	0x804298d0	/* V4 isg	WORD */
Weight =	0x80421d1f	/* V4 i..	WORD */

Note: Consult MUI:Developer/Autodocs/MUI_Slider.doc, MUI_Numeric.doc, MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID DEMO
.
.
.
group HORIZ
  space HORIZ
  group
    knob ID KNOB HELP ' "an example knob gadget" '
    popslider ID PSLD HELP ' "an example popup slider gadget" '
  endgroup
  meter ID METR NODE ' "meter" ' LABEL ' "meter" '
  space HORIZ
endgroup
slider ID SLDR ATTRS Slider_Level 50
gauge ID GAUG NODE ' "gauge" ' LABEL ' "level %ld" ' ATTRS Gauge_Horiz ↔
  TRUE
object CLASS ' "Scale.mui" '

```

endwindow

1.46 MUIRexx.guide/popslider

```
-- Command: popslider ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K,
ATTRS/K/M
```

Popslider gadget objects are created with this command. Slider, popslider and knob gadgets are essentially identical with the only difference being the base object class to create each type of object. Specifically, while unselected the gadget displays the current numeric value in a button. If selected then a slider pops up allowing selection of a new value. All options are identical for these objects. Refer to the

slider

command for descriptions

of the options.

1.47 MUIRexx.guide/knob

```
-- Command: knob ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, ATTRS/K ↔
/M
```

Knob gadget objects are created with this command. Slider, popslider and knob gadgets are essentially identical with the only difference being the base object class to create each type of object. All options are identical for these objects. Refer to the

slider

command for descriptions of the options.

1.48 MUIRexx.guide/list

```
-- Command: list ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, TITLE/K ↔
```

```
    /
PRESS/S, APP/S, DROP/S, POS/K, INSERT/S, NODUP/S, TOGGLE/S,
ATTRS/K/M, STRING=STRINGS/K/F
```

List objects are created with this command.

- * ID [I..] - an id can be assigned to a list for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the list object has been previously created, then the

currently selected line will be returned in RESULT (if OPTIONS RESULTS is specified in the script). If multiple lines are selected then each line will be returned with each list command. The line entry in the list will be deselected. A null string ("") will be returned if no lines are selected (or the last selected line has been reached).

- * COMMAND [IS.] - if given, the command will be executed whenever an item in the list is double clicked (PRESS switch specified or default for no switch), an icon is dropped (APP switch), or another object is dropped (DROP switch) on the list. The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the list selected text line, an icon name (if an icon was dropped on the list), or another objects label (if an object is dropped on the list). Note that commands may be defined after the gadget has been created. In this way different commands may be defined for each action.
 - * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the list is activated. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
 - * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated list. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
 - * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the list and presses the help button on the keyboard then the guide file will be displayed at the node location.
 - * TITLE [IS.] - this argument is used to specify a title for the list. A title will be shown at the top of the list and will remain even if the list scrolled. Note that the format of the title will be the same as for the string entries (see the STRING option description below).
 - * PRESS [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if a line in the list is double clicked.
-

- * APP [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if an icon is dropped on the list from the Workbench.
- * DROP [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if another object is dropped on the list through a drag and drop operation.
- * POS [.SG] - if this argument is given and a string is specified (with the STRING argument) then the string will be inserted at this position. Special values (see List.mui Autodoc entry for MUIA_List_Insert) may be used. If no string is given then the string located at the given position will be returned in the 'ARexx' variable RESULT. If a null string is given (by specifying the STRING option with no string or "") then the string at this position will be removed.
- * INSERT [.S.] - if this switch is given then any string supplied by the STRING argument will be inserted into the current list. If no position is specified (with the POS argument) then the string will be inserted at the current DropMark (see List.mui Autodoc entry for MUIA_List_DropMark).
- * NODUP [IS.] - if this switch is given then no duplicate strings will be displayed.
- * TOGGLE [.S.] - if this switch is given then the select state of each displayed string will be toggled.
- * STRING [ISG] - a string to be entered into the list may be specified by this argument. Note that the string may contain any of the special formatting sequences (see

MUI Format Sequences

). Additionally, multicolumn lists may be created. A string may, in fact, consist of several strings separated with commas. If the list is given a format (with the LIST_FORMAT attribute TAG) then these strings will be displayed in the appropriate column (as defined by the format, see

MUI List Format

). Prepending the string with an equals symbol (=) will force the string to be interpreted literally thereby allowing commas within a string.

- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see
 - Attribute TAGs

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags Type
------------	--------	------------

```

List_Active =                0x8042391c /* V4  isg LONG */
List_AdjustHeight =         0x8042850d /* V4  i.. BOOL */
List_AdjustWidth =         0x8042354a /* V4  i.. BOOL */
List_AutoVisible =         0x8042a445 /* V11 isg BOOL */
List_DragSortable =        0x80426099 /* V11 isg BOOL */
List_DropMark =            0x8042aba6 /* V11 ..g LONG */
List_Entries =             0x80421654 /* V4  ..g LONG */
List_First =               0x804238d4 /* V4  ..g LONG */
List_Format =              0x80423c0a /* V4  isg STRPTR */
List_InsertPosition =      0x8042d0cd /* V9  ..g LONG */
List_MinLineHeight =      0x8042d1c3 /* V4  i.. LONG */
List_Quiet =               0x8042d8c7 /* V4  .s. BOOL */
List_ShowDropMarks =      0x8042c6f3 /* V11 isg BOOL */
List_Title =               0x80423e66 /* V6  isg char * */
List_Visible =             0x8042191f /* V4  ..g LONG */
Listview_ClickColumn =    0x8042d1b3 /* V7  ..g LONG */
Listview_DefClickColumn = 0x8042b296 /* V7  isg LONG */
Listview_DoubleClick =    0x80424635 /* V4  i.g  BOOL */
Listview_DragType =       0x80425cd3 /* V11 isg LONG */
Listview_Input =          0x8042682d /* V4  i.. BOOL */
Listview_MultiSelect =    0x80427e08 /* V7  i.. LONG */
Listview_ScrollerPos =    0x8042b1b4 /* V10 i.. BOOL */
Listview_SelectChange =   0x8042178f /* V4  ..g BOOL */
CycleChain =              0x80421ce7 /* V11 isg LONG */
Disabled =                0x80423661 /* V4  isg BOOL */
HorizDisappear =          0x80429615 /* V11 isg LONG */
HorizWeight =             0x80426db9 /* V4  isg WORD */
ShowMe =                  0x80429ba8 /* V4  isg BOOL */
VertDisappear =          0x8042d12f /* V11 isg LONG */
VertWeight =              0x804298d0 /* V4  isg WORD */
Weight =                  0x80421d1f /* V4  i.. WORD */

```

Note: Consult MUI:Developer/Autodocs/MUI_List.doc, MUI_Listview.doc, MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window ID DEMO
  list ID ALST ATTRS List_Format "MIW=25 BAR,MIW=25 BAR,MIW=25"
  list ID BLST
  .
  .
  .
endwindow
list ID ALST INSERT POS 0 STRING '"column 1,column 2,column 3"'
list ID BLST INSERT POS 0 STRING '"=this one, that one"'

```

1.49 MUIRexx.guide/dirlist

```

-- Command: dirlist ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, ←
PRESS/S,
APP/S, DROP/S, PATH/K, PATTERN/K, REREAD/S ,TOGGLE/S,

```

ATTRS/K/M

Dirlist objects are created with this command.

- * ID [I..] - an id can be assigned to a dirlist for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the dirlist has been previously created, then the currently selected file (with path) will be returned in RESULT (if OPTIONS RESULTS is specified in the script). If multiple files are selected then each file name (with path) will be returned with each dirlist command. The file name entry in the list will be deselected. A null string ("") will be returned if no files are selected (or the last selected file has been reached).
 - * COMMAND [IS.] - if given, the command will be executed whenever an item in the dirlist is double clicked (PRESS switch specified or default for no switch), an icon is dropped (APP switch), or another object is dropped (DROP switch) on the dirlist. The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the dirlist selected line, an icon name (if an icon was dropped on the list), or another objects label (if an object is dropped on the list). Note that commands may be defined after the gadget has been created. In this way different commands may be defined for each action.
 - * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the dirlist is activated. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
 - * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated dirlist. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
 - * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the dirlist and presses the help button on the keyboard then the guide file will be displayed at the node location.
-

- * PRESS [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if a line in the dirlist is double clicked.
- * APP [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if an icon is dropped on the dirlist from the Workbench.
- * DROP [IS.] - if this flag is given then the specified command (given in the COMMAND option) will will issued if another object is dropped on the dirlist through a drag and drop operation.
- * PATH [ISG] - at creation this argument specifies the initial directory path. When the dirlist command is issued with just the ID argument a fully qualified path name is returned for the file or directory selected in the listview.
- * PATTERN [IS.] - this argument sets the accept pattern for the directory list. Any standard AmigaDOS pattern may be given. Note that if a path is set (see PATH argument) or the directory is reread (see REREAD argument) then this pattern will be reflected.
- * REREAD [.S.] - if this switch is given then the dirlist will be updated with the current directory.
- * TOGGLE [.S.] - if this switch is given then the select state of each displayed file will be toggled.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags	Type
Dirlist_Directory =	0x8042ea41	/* V4 isg	STRPTR */
Dirlist_DrawersOnly =	0x8042b379	/* V4 is.	BOOL */
Dirlist_FilesOnly =	0x8042896a	/* V4 is.	BOOL */
Dirlist_FilterDrawers =	0x80424ad2	/* V4 is.	BOOL */
Dirlist_MultiSelDirs =	0x80428653	/* V6 is.	BOOL */
Dirlist_NumBytes =	0x80429e26	/* V4 ..g	LONG */
Dirlist_NumDrawers =	0x80429cb8	/* V4 ..g	LONG */
Dirlist_NumFiles =	0x8042a6f0	/* V4 ..g	LONG */
Dirlist_RejectIcons =	0x80424808	/* V4 is.	BOOL */
Dirlist_SortDirs =	0x8042bbb9	/* V4 is.	LONG */
Dirlist_SortHighLow =	0x80421896	/* V4 is.	BOOL */
Dirlist_SortType =	0x804228bc	/* V4 is.	LONG */
Dirlist_Status =	0x804240de	/* V4 ..g	LONG */
List_Active =	0x8042391c	/* V4 isg	LONG */
List_AdjustHeight =	0x8042850d	/* V4 i..	BOOL */
List_AdjustWidth =	0x8042354a	/* V4 i..	BOOL */
List_AutoVisible =	0x8042a445	/* V11 isg	BOOL */
List_DragSortable =	0x80426099	/* V11 isg	BOOL */


```

List_DropMark =          0x8042aba6 /* V11 ..g LONG */
List_Entries =          0x80421654 /* V4  ..g LONG */
List_First =           0x804238d4 /* V4  ..g LONG */
List_Format =           0x80423c0a /* V4  isg STRPTR */
List_InsertPosition =  0x8042d0cd /* V9  ..g LONG */
List_MinLineHeight =   0x8042d1c3 /* V4  i.. LONG */
List_Quiet =            0x8042d8c7 /* V4  .s. BOOL */
List_ShowDropMarks =   0x8042c6f3 /* V11 isg BOOL */
List_Title =            0x80423e66 /* V6  isg char * */
List_Visible =          0x8042191f /* V4  ..g LONG */
Listview_ClickColumn = 0x8042d1b3 /* V7  ..g LONG */
Listview_DefClickColumn = 0x8042b296 /* V7  isg LONG */
Listview_DoubleClick = 0x80424635 /* V4  i.g  BOOL */
Listview_DragType =     0x80425cd3 /* V11 isg LONG */
Listview_Input =        0x8042682d /* V4  i.. BOOL */
Listview_MultiSelect = 0x80427e08 /* V7  i.. LONG */
Listview_ScrollerPos = 0x8042b1b4 /* V10 i.. BOOL */
Listview_SelectChange = 0x8042178f /* V4  ..g BOOL */
CycleChain =            0x80421ce7 /* V11 isg LONG */
Disabled =              0x80423661 /* V4  isg BOOL */
HorizDisappear =        0x80429615 /* V11 isg LONG */
HorizWeight =           0x80426db9 /* V4  isg WORD */
ShowMe =                0x80429ba8 /* V4  isg BOOL */
VertDisappear =         0x8042d12f /* V11 isg LONG */
VertWeight =            0x804298d0 /* V4  isg WORD */
Weight =                0x80421d1f /* V4  i.. WORD */

```

Note: Consult MUI:Developer/Autodocs/MUI_List.doc, MUI_Listview.doc,
MUI_Dirlist.doc, MUI_Area.doc and
MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window TITLE "MUIRexx Demo" COMMAND "quit" PORT DEMO
  dirlist ID DIR1 PATH "ram:" PRESS APP DROP,
    COMMAND "dirlist ID DIR1 PATH %s" PORT DEMO NODE "dirlist",
    ATTRS Frame Frame_Text Listview_DragType ←
      Listview_DragType_Immediate
  .
  .
  .
endwindow

dirlist ID DIR1 ATTRS Dirlist_Directory
say result

```

1.50 MUIRexx.guide/volumelist

-- Command: volumelist ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K,
ATTRS/K/M
volumelist objects are created with this command.

- * ID [I..] - an id can be assigned to a volumelist for later reference. The id can be any combination of up to 5 characters. If the id is given without any other arguments, and the volumelist has been previously created, then the currently selected volume will be returned in RESULT (if OPTIONS RESULTS is specified in the script).
- * COMMAND [IS.] - if given, the command will be executed whenever an item in the volumelist is double clicked. The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell. The command text may contain a format specifier ('%s') in which case before issuing the command the format specifier will be replaced by the volumelist selected item.
- * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the volumelist is activated. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
- * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated volumelist. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
- * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the volumelist and presses the help button on the keyboard then the guide file will be displayed at the node location.
- * ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see
Attribute TAGs
).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags Type
List_Active =	0x8042391c	/* V4 isg LONG */
List_AdjustHeight =	0x8042850d	/* V4 i.. BOOL */
List_AdjustWidth =	0x8042354a	/* V4 i.. BOOL */
List_AutoVisible =	0x8042a445	/* V11 isg BOOL */
List_DragSortable =	0x80426099	/* V11 isg BOOL */
List_DropMark =	0x8042aba6	/* V11 ..g LONG */

```

List_Entries =          0x80421654 /* V4  ..g LONG */
List_First =           0x804238d4 /* V4  ..g LONG */
List_Format =          0x80423c0a /* V4  isg STRPTR */
List_InsertPosition =  0x8042d0cd /* V9  ..g LONG */
List_MinLineHeight =  0x8042d1c3 /* V4  i.. LONG */
List_Quiet =           0x8042d8c7 /* V4  .s. BOOL */
List_ShowDropMarks =  0x8042c6f3 /* V11 isg BOOL */
List_Title =           0x80423e66 /* V6  isg char * */
List_Visible =         0x8042191f /* V4  ..g LONG */
Listview_ClickColumn = 0x8042d1b3 /* V7  ..g LONG */
Listview_DefClickColumn = 0x8042b296 /* V7  isg LONG */
Listview_DoubleClick = 0x80424635 /* V4  i.g  BOOL */
Listview_DragType =    0x80425cd3 /* V11 isg LONG */
Listview_Input =       0x8042682d /* V4  i.. BOOL */
Listview_MultiSelect = 0x80427e08 /* V7  i.. LONG */
Listview_ScrollerPos = 0x8042b1b4 /* V10 i.. BOOL */
Listview_SelectChange = 0x8042178f /* V4  ..g BOOL */
CycleChain =           0x80421ce7 /* V11 isg LONG */
Disabled =             0x80423661 /* V4  isg BOOL */
HorizDisappear =       0x80429615 /* V11 isg LONG */
HorizWeight =          0x80426db9 /* V4  isg WORD */
ShowMe =               0x80429ba8 /* V4  isg BOOL */
VertDisappear =        0x8042d12f /* V11 isg LONG */
VertWeight =           0x804298d0 /* V4  isg WORD */
Weight =               0x80421d1f /* V4  i.. WORD */

```

Note: Consult MUI:Developer/Autodocs/MUI_List.doc, MUI_Listview.doc, MUI_Volumelist.doc, MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

window TITLE 'MUIRexx Demo' COMMAND 'quit' PORT DEMO
  volumelist,
    COMMAND 'dirlist ID DIR1 PATH %s' PORT DEMO NODE 'volumelist ←
      " ",
    ATTRS Weight 50
  .
  .
  .
endwindow

```

1.51 MUIRexx.guide/object

```

-- Command: object ID/K, COMMAND/K, PORT/K, HELP/K, NODE/K, CLASS ←
  /K,
  TRIG/K, VAL/K, BOOPSI/S, ATTRS/K/M

```

Objects from MUI internal, external and BOOPSI classes are created with this command. Note that while this is a very powerful and flexible command it can easily result in the unexpected, including system crashes, so beware.

- * ID [I..] - an id can be assigned to an object for later reference. The id can be any combination of up to 5 characters.
- * COMMAND [IS.] - if given, the command will be executed whenever the object is triggered (see the TRIG and VAL options). The command will be issued to the host port specified by the PORT argument. Note that the command is run asynchronously (as a detached process) and only inherits the global path if 'MUIRexx' is started from a shell.
- * PORT [I..] - a specific host port may be specified by this argument. The defined command will be issued to this port whenever the object is triggered. If the port is defined as COMMAND then the command will be issued to a DOS shell (global path will be in affect only if 'MUIRexx' was run from a shell). If this argument is not given but a command is defined then the port will be defined as the port for 'ARexx' (i.e. it will be assumed that the command is an 'ARexx' script). Note that the port may be defined as the port of the application itself. In this manner objects within an application can be linked as well as to objects in another application.
- * HELP [I..] - with this argument help text may be defined which will be displayed as balloon help whenever the pointer is over the associated object. Of course, this is dependant on whether the user set up balloon help in the MUI preference settings.
- * NODE [I..] - this argument is used to specify a node in the guide file given in the command line argument HELP for 'MUIRexx'. If the user positions the mouse pointer over the object and presses the help button on the keyboard then the guide file will be displayed at the node location.
- * CLASS [I..] - this argument allows specification of the object class. The class may be any internal or external MUI or BOOPSI (see the BOOPSI option) gadget class.
- * TRIG [I..] - this argument allows specification of a notification trigger TAG. By default the trigger is the MUIA Pressed TAG.
- * VAL [I..] - this argument allows specification of a notification trigger value. By default the value is FALSE.
- * BOOPSI [I..] - if this switch is given then the object will be created from a BOOPSI gadget class. BOOPSI objects will, by default, have the following TAG ids and values set:

TAG	value
GA_Left	0
GA_Top	0
GA_Width	0
GA_Height	0

ICA_TARGET ICTARGET_IDCMP

* ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags	Type
Boopsi_MaxHeight =	0x8042757f	/* V4	isg ULONG */
Boopsi_MaxWidth =	0x8042bcb1	/* V4	isg ULONG */
Boopsi_MinHeight =	0x80422c93	/* V4	isg ULONG */
Boopsi_MinWidth =	0x80428fb2	/* V4	isg ULONG */
Boopsi_Remember =	0x8042f4bd	/* V4	i.. ULONG */
Boopsi_Smart =	0x8042b8d7	/* V9	i.. BOOL */
Boopsi_TagDrawInfo =	0x8042bae7	/* V4	isg ULONG */
Boopsi_TagScreen =	0x8042bc71	/* V4	isg ULONG */
Boopsi_TagWindow =	0x8042e11d	/* V4	isg ULONG */
ControlChar =	0x8042120b	/* V4	isg char */
CycleChain =	0x80421ce7	/* V11	isg LONG */
Disabled =	0x80423661	/* V4	isg BOOL */
Draggable =	0x80420b6e	/* V11	isg BOOL */
FillArea =	0x804294a3	/* V4	is. BOOL */
FixHeight =	0x8042a92b	/* V4	i.. LONG */
FixHeightTxt =	0x804276f2	/* V4	i.. STRPTR */
FixWidth =	0x8042a3f1	/* V4	i.. LONG */
FixWidthTxt =	0x8042d044	/* V4	i.. STRPTR */
HorizDisappear =	0x80429615	/* V11	isg LONG */
HorizWeight =	0x80426db9	/* V4	isg WORD */
MaxHeight =	0x804293e4	/* V11	i.. LONG */
MaxWidth =	0x8042f112	/* V11	i.. LONG */
Selected =	0x8042654b	/* V4	isg BOOL */
ShowMe =	0x80429ba8	/* V4	isg BOOL */
ShowSelState =	0x8042caac	/* V4	i.. BOOL */
VertDisappear =	0x8042d12f	/* V11	isg LONG */
VertWeight =	0x804298d0	/* V4	isg WORD */
Weight =	0x80421d1f	/* V4	i.. WORD */

Note: Consult MUI:Developer/Autodocs/MUI_Boopsi.doc, MUI_Area.doc and MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```
WHEEL_Hue = 0x84000001
WHEEL_Saturation = 0x84000002
WHEEL_Screen = 0x84000009
```

```
window TITLE ' "MUIRexx Demo" ' COMMAND ' "quit" ' PORT DEMO
  group HORIZ
    group
      label DOUBLE ' "Hue:" '
      label DOUBLE ' "Saturation:" '
    endgroup
  group
    gauge ID HUE ATTRS Gauge_Max 16384,
```

```

                                Gauge_Divide 262144,
                                Gauge_Horiz TRUE
    gauge ID SAT ATTRS Gauge_Max 16384,
                                Gauge_Divide 262144,
                                Gauge_Horiz TRUE
    endgroup
endgroup
object ID BOOP BOOPSI CLASS '"colorwheel.gadget"',
    ATTRS Boopsi_MinWidth 30,
        Boopsi_MinHeight 30,
        Boopsi_Remember WHEEL_Hue,
        Boopsi_Remember WHEEL_Saturation,
        Boopsi_TagScreen WHEEL_Screen,
        WHEEL_Screen 0,
        WHEEL_Saturation 0,
        FillArea TRUE
    .
    .
    .
endwindow

method ID BOOP Notify WHEEL_Hue EveryTime,
    @HUE 4 Set Gauge_Current TriggerValue
method ID BOOP Notify WHEEL_Saturation EveryTime,
    @SAT 4 Set Gauge_Current TriggerValue

```

1.52 MUIRexx.guide/Misc

Misc

====

These commands don't fit any of the previous categories so here they are.

request

aslrequest

method

setvar

getvar

application

1.53 MUIRexx.guide/request

-- Command: request ID/K, TITLE/K, GADGETS/K, FILE/K, STRING/F
This command will bring up a standard 'MUI' requester. Note that this command is synchronous. That is once it is issued it will not return a result until the user has selected a gadget. Once a gadget has been selected then a number will be returned in the 'ARexx' variable RESULT (assuming 'options results' was specified in the script). The first gadget will return a 1, the second a 2, and so on. The last gadget, however, will return a 0 (this is by convention since the last gadget is typically a CANCEL or equivalent gadget).

- * ID - this argument specifies a window ID. If specified then the requester will be centered in the window.
- * TITLE - this argument specifies the requester title (placed in the title bar of the requester window).
- * GADGETS - this argument specifies the gadget labels. The labels are given as a single string with a vertical bar, | used to separate each label. Additionally, each label can contain an underscore, _ prior to any character. The character will be the keyboard shortcut to activate the associated gadget.
- * FILE - if given, this argument specifies the file to get the contents for the requester. All line breaks in the file will be included. Note that this argument overrides the STRING argument.
- * STRING - this argument specifies the string to display in the requester.

Example use of this command:

```
request ID MDIR GADGETS ' "OK|Cancel" ' "Delete selected entries?"'
```

1.54 MUIRexx.guide/aslrequest

-- Command: aslrequest ID/K, TITLE/K, ATTRS/K/M
This command will bring up a standard ASL file requester. Note that this command is synchronous. That is once it is issued it will not return a result until the user has selected a file/directory or canceled. Once a file/directory has been selected then the fully path-qualified name will be returned in the 'ARexx' variable RESULT (assuming 'options results' was specified in the script).

- * ID - this argument specifies a window ID. If specified then the requester will be associated with the window.

- * TITLE - this argument specifies the requester title (placed in the title bar of the requester window).
- * ATTRS [ISG] - with this option any ASL attribute TAGs may be set (refer to AmigaDOS RKMs for details).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id
ASLFR_InitialLeftEdge	0x80080003
ASLFR_InitialTopEdge	0x80080004
ASLFR_InitialWidth	0x80080005
ASLFR_InitialHeight	0x80080006
ASLFR_InitialFile	0x80080008
ASLFR_InitialDrawer	0x80080009
ASLFR_InitialPattern	0x8008000A
ASLFR_DoSaveMode	0x8008002C
ASLFR_DoMultiSelect	0x8008002D
ASLFR_DoPatterns	0x8008002E
ASLFR_DrawersOnly	0x8008002F
ASLFR_RejectIcons	0x8008003C
ASLFR_RejectPattern	0x8008003D
ASLFR_AcceptPattern	0x8008003E
ASLFR_FilterDrawers	0x8008003F

1.55 MUIRexx.guide/method

```
-- Command: method ID/K, ARGS/M
```

This command allows construction of class methods (ala the domethod function). While this command is very powerful it is also quite complicated and possibly dangerous (can result in system crashes).

Care should be taken by consulting the autodocs describing the method to be constructed.

- * ID - this argument specifies the ID of the reference object for the method. If it is not given then the application object will be used.
- * ARGS - these arguments are the remaining arguments passed to the domethod function. The arguments may be TAG ids or TAG values (see Attribute TAGs). TAG values may also be object pointers which are specified by preceding an object ID with an @.

Example use of this command:

```
method Application_AboutMUI 0          /* bring up about_MUI requester */
method Application_OpenConfigWindow /* open MUI settings program */

/* an example notification method */
```



```
method ID BOOP Notify WHEEL_Hue EveryTime,
    @HUE 4 Set Gauge_Current TriggerValue
```

1.56 MUIRexx.guide/setvar

-- Command: setvar NAME/A, VALUE/F

This command will set an internal 'MUIRexx' variable to any value (stored as a string) which can be retrieved or reset later within the same application (not necessarily the same script). This ability can be used to pass information between 'ARexx' scripts used in the same application.

* NAME - this argument defines the variable name.

* VALUE - this argument defines the value of the variable and can consist of any characters.

1.57 MUIRexx.guide/getvar

-- Command: getvar NAME/A

This command will retrieve an internal 'MUIRexx' variable. The value will be placed into the 'ARexx' variable RESULT (assuming OPTIONS RESULTS was specified in the calling script).

* NAME - this argument specifies the variable name.

1.58 MUIRexx.guide/application

-- Command: application ATTRS/K/M

This command allows attributes to be set and retrieved for the application object.

* ATTRS [ISG] - with this option any MUIA attribute TAGs may be set or retrieved (see Attribute TAGs).

Some useful TAGs for use with this command are:

TAG_Name =	TAG_id	Flags	Type
Application_Active =	0x804260ab	/* V4 isg	BOOL */

```

Application_Author =          0x80424842 /* V4  i.g STRPTR */
Application_Base =          0x8042e07a /* V4  i.g STRPTR */
Application_Copyright =     0x8042ef4d /* V4  i.g STRPTR */
Application_Description =   0x80421fc6 /* V4  i.g STRPTR */
Application_DoubleStart =   0x80423bc6 /* V4  ..g BOOL */
Application_Iconified =     0x8042a07f /* V4  .sg BOOL */
Application_Sleep =         0x80425711 /* V4  .s.  BOOL */
Application_Title =         0x804281b8 /* V4  i.g STRPTR */
Application_Version =       0x8042b33f /* V4  i.g STRPTR */

```

Note: Consult MUI:Developer/Autodocs/MUI_Application.doc and
MUI:Developer/C/Include/libraries/mui.h

Example use of this command:

```

application ATTRS Application_Iconified TRUE      /* forces ↔
    iconification */

application ATTRS Application_Version
say result

```

1.59 MUIRexx.guide/Example Macro

Example Macro

```

/* A simple example based on one of the demos supplied with MUI */
options results

Selected =          0x8042654b /* V4  isg BOOL */
Slider_Level =      0x8042ae3a /* V4  isg LONG */

TRUE = 1

address PAGES

window ID PAGE TITLE "Character Definition" COMMAND 'quit' PORT PAGES
  group HORIZ
    group
      label SINGLE 'Name:'
      label SINGLE 'Sex:'
    endgroup
    group
      string ID NAME CONTENT 'Frodo'
      cycle ID SEX LABELS 'male,female'
    endgroup
  endgroup

space 2
group REGISTER LABELS 'Race,Class,Armor,Level'
  group FRAME
    radio ID RACE LABELS 'Human,Elf,Dwarf,Hobbit,Gnome'
  endgroup

```

```

group FRAME
    radio ID CLAS LABELS 'Warrior,Rogue,Bard,Monk,Magician,Archmage'
endgroup

group
    group HORIZ
        group
            label SINGLE 'Cloak:'
            label SINGLE 'Shield:'
            label SINGLE 'Gloves:'
            label SINGLE 'Helmet:'
        endgroup
        group
            check ID CHK1 ATTRS Selected TRUE
            check ID CHK2 ATTRS Selected TRUE
            check ID CHK3 ATTRS Selected TRUE
            check ID CHK4 ATTRS Selected TRUE
        endgroup
    endgroup
endgroup

group
    group HORIZ
        group
            label DOUBLE 'Experience:'
            label DOUBLE 'Strength:'
            label DOUBLE 'Dexterity:'
            label DOUBLE 'Condition:'
            label DOUBLE 'Intelligence:'
        endgroup
        group
            slider ATTRS Slider_Level 3
            slider ATTRS Slider_Level 42
            slider ATTRS Slider_Level 24
            slider ATTRS Slider_Level 39
            slider ATTRS Slider_Level 74
        endgroup
    endgroup
endgroup

endgroup
endwindow
exit

```

1.60 MUIRexx.guide/MUI Format Sequences

MUI Format Sequences

Whenever MUI prints strings, they may contain some special character sequences defining format, color and style of the text.

- * '\n' Start a new line. With this character you can e.g. create multi line buttons.

- * '\033-' Disable text engine, following chars will be printed without further parsing.
- * '\033u' Set the soft style to underline.
- * '\033b' Set the soft style to bold.
- * '\033i' Set the soft style to italic.
- * '\033n' Set the soft style back to normal.
- * '\033<n>' Use pen number n (2..9) as front pen. n must be a valid DrawInfo pen as specified in "intuition/screens.h".
- * '\033c' Center current (and following) line(s). This sequence is only valid at the beginning of a string or after a newline character.
- * '\033r' Right justify current (and following) line(s). This sequence is only valid at the beginning of a string or after a newline character.
- * '\033l' Left justify current (and following) line(s). This sequence is only valid at the beginning of a string or after a newline character.
- * '\033I[<s>]' Draw MUI image with specification <s> (see

MUI Image Specifications
).

1.61 MUIRexx.guide/MUI Image Specifications

MUI Image Specifications

MUI Image specifications always starts with a digit, followed by a ':', followed by some parameters. Currently, the following things are defined:

- * "0:<x>" where <x> is between MUII_BACKGROUND and MUII_FILLBACK2 identifying a builtin pattern.
 - * "1:<x>" where <x> identifies a builtin standard image. Don't use this, use "6:<x>" instead.
 - * "2:<r>,<g>," where <r>, <g> and are 32-bit RGB color values specified as 8-digit hex string (e.g. 00000000 or ffffffff). Kick 2.x users will get an empty image.
 - * "3:<n>" where <n> is the name of an external boopsi image class.
-

- * "4:<n>" where <n> is the name of an external MUI brush.
- * "5:<n>" where <n> is the name of an external picture file that should be loaded with datatypes. Kick 2.x users will get an empty image.
- * "6:<x>" where <x> is between MUII_WindowBack (0) and MUII_Count-1 (41) identifying a preconfigured image/background.

1.62 MUIRexx.guide/MUI List Format

MUI List Format

MUI has the ability to handle multi column lists. To define how many columns should be displayed and how they should be formatted, you specify a format string.

This format string must contain one entry for each column you want to see. Entries are separated by commas with each line parsed via `dos.library/ReadArgs()`.

The template for a single entry looks like this:

DELTA=D/N, PREPARSE=P/K, WEIGHT=W/N, MINWIDTH=MIW/N, MAXWIDTH=MAW/N, COL=C/N, BAR/S

- * DELTA - Space in pixel between this column and the next. the last displayed column ignores this setting. Defaults to 4.
- * PREPARSE - A preparse value for this column. Setting this e.g. to `'\033c'` would make the column centered (see MUI Format Sequences).
- * WEIGHT - The weight of the column. As with MUI's group class, columns are layouted with a minimum size, a maximum size and weight. A column with a weight of 200 would gain twice the space than a column with a weight of 100. Defaults to 100.
- * MINWIDTH - Minimum percentage width for the current column. If your list is 200 pixel wide and you set this to 25, your column will at least be 50 pixel. The special value -1 for this parameter means that the minimum width is as wide as the widest entry in this column. This ensures that every entry will be completely visible (as long as the list is wide enough). Defaults to -1.
- * MAXWIDTH - Maximum percentage width for the current column. If your list is 200 pixel wide and you set this to 25, your column will not be wider as 50 pixel. The special value -1 for this parameter means that the maximum width is as wide as the widest entry in this column. Defaults to -1.

- * COL - This value adjusts the number of the current column. This allows you to adjust the order of your columns. Defaults to current entry number (0,1,...)
- * BAR - Since muimaster.library V11, you can enable a vertical bar between this and the next column by using this switch.

If your list object gets so small there is not enough place for the minwidth of a column, this column will be hidden completely and the remaining space is distributed between the remaining columns. This is not true if the column is the first column, in this case the entries will simply be clipped.

Note: You will have as many columns in your list as entries in the format string (i.e. number of commas + 1). Empty entries, e.g. with a format string of ",,,," are perfectly ok.

The default list format is an empty string (""), this means a one column list without special formatting.

For a dirlist object the column data, starting at column zero (0), is the file name, size, date, time, protection, and comment.

1.63 MUIRexx.guide/Attribute TAGs

Attribute TAGs

While the capability to specify arbitrary attributes allows for much flexibility it also can lead to unexpected results. It is recommended that before using a TAG that the MUI autodocs be referenced in order to clearly understand the effect the TAG will have. All TAGs are set by specifying a TAG id and value pair. Any number of TAG pairs may be given. TAG ids should be given as hexadecimal numbers (preceded by a '0x'), although decimal numbers may also be used. Typically, TAG ids should be assigned to an 'ARexx' variable for script clarity. TAG values may be either decimal numbers, hexadecimal numbers, strings (the value will be assumed to be a string if it is not recognized as a number) or string arrays (specified by starting with a period (.) and separating each string with a comma (,)). A TAG value can be forced to be interpreted as a string by prepending the string with an equal symbol (=). Note that all TAGs indicated with an 'i' flag can be set at object creation. The 's' flag indicates a TAG that can be set after object creation and the 'g' indicates a TAG that can be retrieved. To retrieve a TAG value just specify the TAG id alone. The TAG value will be returned in the 'ARexx' variable RESULT.

For commands that allow specification of attribute TAGs some example TAGs are given with the command description. However, it may be possible (even probable) that other TAGs may be usable. It is therefore highly recommended that the MUI class autodocs be consulted. These autodocs may be found in the MUI developers archive.

1.64 MUIRexx.guide/MagicUserInterface

MagicUserInterface

This application uses

MUI - MagicUserInterface

(C) Copyright 1993-96 by Stefan Stuntz

MUI is a system to generate and maintain graphical user interfaces. With the aid of a preferences program, the user of an application has the ability to customize the outfit according to his personal taste.

MUI is distributed as shareware. To obtain a complete package containing lots of examples and more information about registration please look for a file called "muiXXusr.lha" (XX means the latest version number) on your local bulletin boards or on public domain disks.

If you want to register directly, feel free to send

DM 30.- or US\$ 20.-

to

Stefan Stuntz

Eduard-Spranger-Straße 7

80935 München

GERMANY

Support and online registration is available at

<http://www.sasg.com/>

1.65 MUIRexx.guide/Acknowledgements

Acknowledgements

- * William S. Hawes for development of ARexx.
- * Stefan Stuntz for MagicUserInterface (MUI).
- * Tom Ekström for Iconographics

* All those responsible for the development of the Amiga.

1.66 MUIRexx.guide/History

History

v1.0	2/13/96	-	initial release
v1.1	2/24/96	-	fixed enforcer hits added support for menus added a MUI settings command
	2/25/96	-	improved group/menu syntax checking
v1.2i	3/10/96	-	added support for drag and drop
	3/14/96	-	added options to set MUIA attributes removed unnecessary options (e.g. WEIGHT)
v2.0	3/20/96	-	added variable storage (set and get)
	3/22/96	-	MUIA attributes are now gettable
	3/23/96	-	added support for dragging multiselected items removed Cyclechain TAG (add using ATTRS) removed SELECT option from check gadget
	3/24/96	-	added switch gadget list objects are now dropable group objects are now dropable
	3/26/96	-	stack size now set for commands
	3/28/96	-	added method command
	3/30/96	-	added object gadget removed scale gadget (use object instead)
	3/31/96	-	added support for setting app attributes/methods if started from WB then icon is set added support for multicolumn lists removed dirlist DIR and FORMAT options (use ATTRS)
	4/1/96	-	removed config and muiset commands (use method)
	4/2/96	-	added support for boopsi objects
	4/5/96	-	added support for datatype images
v2.1	5/19/96	-	TAG strings now nonvolatile
	5/22/96	-	generalized view command added aslrequest command
	5/27/96	-	improved list drag&drop behavior
	6/17/96	-	added poplist command
	6/25/96	-	added format sequences for strings
	7/20/96	-	added support for new Icon.mcc class changed behavior of image and check gadgets
	8/22/96	-	added support for virtual groups
v2.1a	9/1/96	-	minor bug fixed (popasl contents were not stored in config file)
	9/4/96	-	minor bug fixed (prevented pub screen closure)
	9/5/96	-	minor update to Icon.mcc (see docs)
v2.1b	9/7/96	-	fixed bug (enforcer hit)
	9/9/96	-	fixed bug (MUIA_Cycle_Active now works at cycle object creation, thanks to Hartmut Goebel)
v2.2	9/22/96	-	added list TITLE option
	9/25/96	-	slider, popslider and knob now return value (per documentation)
	9/27/96	-	format specifiers now work for all objects

- (I think)
- 9/29/96 - context menus for groups added
can now specify image for popasl/poplist objects
(SPEC option)
 - 10/1/96 - parse routine added to replace MUI REXX command
line parse
 - 10/25/96- fixed bug in string, popasl, poplist objects
(MUIA_String_MaxLen now works, thanks to Bob Sisk)

1.67 MUIRexx.guide/Concept Index

Concept Index

ARexx	Introduction
ASL file requester	aslrequest
Bars	space
Beginning a group definition	group
Beginning a menu definition	menu
Beginning a window definition	window
Changing group settings	Groups
Changing object settings	Objects
Check gadget select state	check
Closing a window	window
Cycle gadget labels	cycle
Deiconifying an application	show
Dirlist path	

	dirlist
Dock gadgets	text
Dynamic object creation	group
Ending a group definition	endgroup
Ending a menu definition	endmenu
Ending a window definition	endwindow
Ending MUIRexx	quit
Failed script	quit
Features of MUIRexx	Introduction
Gadget label	text
Gauge label	gauge
Getting help on an application	help
Group frame	group
Icon gadgets	text
Iconifying an application	hide
Information on MUIRexx	info
Installing MUIRexx	Installation
Label justification	label
MagicUserInterface	Introduction
Menu item definition	

	item
Meter label	meter
Minimum system requirements Requirements	
Opening a window	endwindow
Popasl gadget content	popasl
Popasl gadget content	poplist
Popasl gadget weight	poplist
Popasl gadget weight	popasl
Radio gadget labels	radio
Radio gadget weight	radio
Register groups	group
Registering MUIRexx	Registration
Requester contents	request
Requester gadgets	request
Requester title	request
Retrieving group settings	Groups
Retrieving object settings	Objects
String gadget content	string
Terminating an application	window
Text color	

	MUI Format Sequences
Text format	MUI Format Sequences
Text justification	MUI Format Sequences
Text style	MUI Format Sequences
Updates of MUIRexx	Update Information
View string	view
View string file	view
Virtual groups	group
Window sizing	space
Window title	window

1.68 MUIRexx.guide/Command Index

Command Index

application	application
aslrequest	aslrequest
button	button
check	check
cycle	cycle
dirlist	

	dirlist
endgroup	endgroup
endmenu	endmenu
endwindow	endwindow
gauge	gauge
getvar	getvar
group	group
help	help
hide	hide
image	image
info	info
item	item
knob	knob
label	label
list	list
menu	menu
meter	meter
method	method
object	object
popas1	

	popasl
poplist	poplist
popslider	popslider
quit	quit
radio	radio
request	request
setvar	setvar
show	show
slider	slider
space	space
string	string
switch	switch
text	text
view	view
volumelist	volumelist
window	window
