

termRexx

COLLABORATORS

	<i>TITLE :</i> termRexx		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		February 8, 2023	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	termRexx	1
1.1	termRexx.guide	1
1.2	termRexx.guide/Changes	2
1.3	termRexx.guide/term_and_ARexx	2
1.4	termRexx.guide/Command_execution	3
1.5	termRexx.guide/Stopping_a_command	5
1.6	termRexx.guide/Commands	6
1.7	termRexx.guide/ACTIVATE	15
1.8	termRexx.guide/ADDITEM	15
1.9	termRexx.guide/BAUD	17
1.10	termRexx.guide/BEEPSCREEN	18
1.11	termRexx.guide/CALLMENU	18
1.12	termRexx.guide/CAPTURE	19
1.13	termRexx.guide/CLEAR	20
1.14	termRexx.guide/CLEARSCREEN	21
1.15	termRexx.guide/CLOSE	21
1.16	termRexx.guide/CLOSEDEVICE	22
1.17	termRexx.guide/CLOSEREQUESTER	22
1.18	termRexx.guide/DEACTIVATE	23
1.19	termRexx.guide/DELAY	24
1.20	termRexx.guide/DIAL	24
1.21	termRexx.guide/DUPLEX	25
1.22	termRexx.guide/EXECTOOL	26
1.23	termRexx.guide/FAULT	26
1.24	termRexx.guide/GETATTR	27
1.25	termRexx.guide/GETCLIP	28
1.26	termRexx.guide/HANGUP	29
1.27	termRexx.guide/HELP	30
1.28	termRexx.guide/OPEN	31
1.29	termRexx.guide/OPENDEVICE	31

1.30	termRexx.guide/OPENREQUESTER	32
1.31	termRexx.guide/PARITY	33
1.32	termRexx.guide/PASTECLIP	33
1.33	termRexx.guide/PRINT	34
1.34	termRexx.guide/PROTOCOL	35
1.35	termRexx.guide/PUTCLIP	35
1.36	termRexx.guide/QUIT	36
1.37	termRexx.guide/READ	37
1.38	termRexx.guide/RECEIVEFILE	38
1.39	termRexx.guide/REDIAL	39
1.40	termRexx.guide/REMITEM	40
1.41	termRexx.guide/REQUESTFILE	40
1.42	termRexx.guide/REQUESTNOTIFY	42
1.43	termRexx.guide/REQUESTNUMBER	42
1.44	termRexx.guide/REQUESTRESPONSE	43
1.45	termRexx.guide/REQUESTSTRING	44
1.46	termRexx.guide/RESETSCREEN	45
1.47	termRexx.guide/RESETSTYLES	45
1.48	termRexx.guide/RESETTEXT	46
1.49	termRexx.guide/RX	46
1.50	termRexx.guide/SAVE	47
1.51	termRexx.guide/SAVEAS	48
1.52	termRexx.guide/SELECTITEM	48
1.53	termRexx.guide/SEND	49
1.54	termRexx.guide/SENDBREAK	50
1.55	termRexx.guide/SENDFILE	50
1.56	termRexx.guide/SETATTR	52
1.57	termRexx.guide/SPEAK	52
1.58	termRexx.guide/STOPBITS	53
1.59	termRexx.guide/TEXTBUFFER	53
1.60	termRexx.guide/TIMEOUT	54
1.61	termRexx.guide/WAIT	54
1.62	termRexx.guide/WINDOW	55
1.63	termRexx.guide/Attributes	57
1.64	termRexx.guide/Wanted!	71
1.65	termRexx.guide/Index	71

Chapter 1

termRexx

1.1 termRexx.guide

'term' 3.4 - A terminal program for Amiga computers

Copyright © 1990-1993 Olaf Barthel & MXM

You may make and distribute verbatim copies of this documentation if the contents are unchanged or the author has agreed to any changes made.

No guarantee of any kind is given that the program described in this document are 100% reliable. You are using this material on your own risk.

The program 'term' and the data received/sent by it must not be used for the following purposes:

1. The construction, development, production or testing of weapons or weapon systems of any kind.
2. The construction, development, production or use of plants/installations which include the processing of radioactive/fissionable material.
3. The training of persons to deal with the abovesaid actions.

'term' may be included with commercial programs as long as no money is made by including it in the distribution (this also applies to inclusion in AmigaDOS Enhancer kits, on Workbench/Extras disks or A3x00 hard disk drives).

You must not make any money by distributing 'term'. A small copy fee for data media (US\$ 5 maximum) or the inclusion of 'term' in Public-Domain collections such as Fred Fish's Amiga Library of Freely Distributable Software is permitted though.

Changes

The new ARexx interface

term and ARexx	A brief introduction
Command execution	How to execute commands
Stopping a command	How to pull the brakes
Commands	A table of supported commands
Attributes	A table of available attributes
Wanted!	ARexx sample programs wanted
Index	Contents index

1.2 termRexx.guide/Changes

Changes

Previous 'term' releases would use a different ARexx host interface implementation. In order to conform to Commodore-endorsed user interface style guidelines it was redesigned from scratch for version 3.0. The design and implementation of the ARexx host interface was suggested by the 'Amiga User Interface Style Guide' and strongly influenced by Martin Taillefer's 'TurboText' ARexx host interface.

Not a simple command has 'survived' the revision, the new implementation is no longer compatible with its predecessors, so existing ARexx programs will have to be adapted or even entirely rewritten.

'term' no longer distinguishes explicitly between asynchronous and synchronous commands (i.e. commands which force the main program to wait and commands which need not bother the main program as the ARexx handler process is able to execute them). As of this writing it is safe to assume that almost any command will be processed by the main program, exceptions are noted.

1.3 termRexx.guide/term_and_ARexx

term and ARexx

This document describes the ARexx(tm) (1) commands supported by 'term'. This is not intended to be an introduction to the language itself. Rexx was developed by Mike F. Cowlshaw on an IBM/SP system and ported to the Amiga by William S. Hawes.

ARexx (or Amiga Rexx) is a commercial product which is included with the AmigaDOS 2.0 Enhancer Package. If you need a good introduction and description of the language, try to get a hold of the book 'The REXX Language A Practical Approach to Programming' by M.F. Cowlshaw, available from Prentice-Hall International, Inc.

The section entitled
 Command_execution
 gives a brief introduction
how to write and run ARexx commands. For more information refer to the Release 2 Users Manual 'Using the System Software'.

By default 'term' opens an ARexx host by the name of TERM (accessible via address term). If more than a single 'term' process is running on your machine, the name of the host will be adapted to the number of the program (i.e. the first program will use TERM, the second one will use TERM.1, the third one TERM.2, etc.). The default name can be overridden by invoking the program with certain parameters (see main program documentation). The name of the host is displayed in the status window (see main program documentation).

----- Footnotes -----

(1) ARexx is a registered trademark of Wishful Thinking Development Corp.

1.4 termRexx.guide/Command_execution

Command execution

In order to invoke any command supported by 'term' one usually has to address the host explicitly:

```
/* Address the 'term' host. */  
  
ADDRESS term  
  
/* Invoke the 'beepscreen' command. */  
  
BEEPSCREEN
```

However, if an ARexx program is invoked directly by the 'term' main program, the program will by default address the main program it was invoked by.

Most commands will return results or error codes on failure. To enable result codes, one has to use the options results command. The results returned by commands will be placed in the result variable:

```
/* We assume that the program will address the host it was invoked from.
 *
 * Enable command results.
 */
```

```
OPTIONS RESULTS
```

```
/* Request a string from the user. */
```

```
REQUESTSTRING DEFAULT 'anything' PROMPT 'Enter anything'
```

```
/* Did the user cancel the requester? */
```

```
IF rc ~= 0 THEN
  SAY 'user cancelled requester'
ELSE
  SAY result /* Output the result . */
```

Failure codes will always be returned in the rc variable (see previous example).

In case of failure (variable rc >= 10), 'term' will leave an error code in the term.lasterror variable:

```
/* Enable command results. */

OPTIONS RESULTS

/* Produce an error by not supplying any arguments. */

STOPBITS

/* Display the error code. */

SAY term.lasterror
```

Rexx tries to tokenize any command parameters, this process involves promoting them to all upper case letters and checking for illegal characters. This feature inhibits the use of the : (colon) and blank space characters in parameter names unless the corresponding arguments are enclosed in quotes. To make things even more complicated, the parser will not always accept parameters to contain blank spaces. If a command template accepts the entire command line (such as TEXT/K/F) a parameter can include any number of blank spaces. A command template to accept just a single parameter (such as TEXT/K) requires double quotes if blank spaces are included. Text such as tea or coffee? thus becomes '"tea or coffee?'" .

```
/* The following command will fail to send the file 'ram:foobar' as the colon
 * in the path name will cause an error:
 */
```

```
SENDFILE ram:foobar
```

```
/* Here is how to do it correctly: */
```

```
SENDFILE 'ram:foobar'

/* The following command will fail to send the file 'foo bar' as the
 * file name is treated as two single files:
 */

SENDFILE foo bar

/* The next line will still fail to send the file 'foo bar'
 * as the ARexx parser will split the argument into two
 * parameters.
 */

SENDFILE 'foo bar'

/* Here is how to do it correctly: */

SENDFILE '"foo bar"'

/* The following command will not transmit the string 'Hello sailor'
 * across the serial line as the single words will be capitalized,
 * they will be transmitted as 'HELLO SAILOR':
 */

SEND Hello sailor

/* Here is how to do it correctly: */

SEND 'Hello sailor'
```

1.5 termRexx.guide/Stopping_a_command

Stopping a command

Programs and commands sometimes fail to do what the user is expecting them to do which makes it necessary to bring program/command execution to a stop. A common ARexx program to call no external functions or host commands one can be halted in the following ways:

1. Executing the HI command (located in the SYS:rexxc drawer) from Shell. This command will attempt stop all currently running ARexx programs.
2. If the ARexx program to be executed runs in an environment to sport an output window, activate the window and press the Control + C keys. A break signal will be sent to the ARexx program, causing it to stop as soon as possible.

With host environments such as 'term' it may not always be possible to abort a command using the simple measures described above. As for 'term' any command to wait (such as the

```
READ
```

```
,
```

```

    DELAY
    or
    WAIT
    commands)

```

can be aborted by sending 'term' itself a break signal in the following fashion:

1. If the 'term' program is still attached to a Shell output window, activate the window and press the Control + D keys.
2. If the 'term' program was invoked from a Shell but is no longer attached to it, enter status command term from Shell, remember the number printed, then enter break <number> with <number> being the number returned by the status command.
3. Press the hotkey combination configured in the program hotkey settings (see main program documentation). The default is Right Shift + Left Shift + Escape. This will cause a break signal to be sent to the 'term' program.

1.6 termRexx.guide/Commands

Commands

The commands supported by 'term' are listed in a table of the following form:

Format:

The command name with its possible calling parameters. In this table parameters are enclosed in brackets and braces, separated by commas and vertical bars; do not type these special characters along with the parameters!:

< > (Angle brackets)

Angle brackets enclose parameters whose contents must not be omitted in order to make the command work properly.

[] (Square brackets)

Square brackets enclose optional parameters.

{ } (Curly braces)

Curly braces enclose items which can be repeated a number of times, such as file name lists.

| (Vertical bar)

Vertical bars separate alternative, mutually exclusive options.

, (Comma)

Commas separate multiple applicable options.

Template:

The command template, similar to the command templates employed by AmigaDOS Shell commands. Possible templates are:

<Parameter>/A

The parameter must always be included in order to get accepted.

<Option>/K

The option's keyword must be given.

<Option>/S

This option works as a switch. If this option keyword is included the switch is on, else it is off.

<Option>/N

A numeric parameter is expected.

<Option>/M

Multiple parameters are accepted.

<Text>/F

The text must be the final parameter on the command line.

, (Comma)

Indicates that the command takes no parameters.

Purpose:

Briefly describes what the command will do.

Specifications:

Describes the command and its possible uses in more detail.

Result:

The type of the command result code if any.

Warning:

If the command can return with a warning and when.

Example:

An example code fragment to illustrate how to use the command. Commands and keywords are given in upper case, the names of variables and command arguments are given in lower case. Where a single command line would not fit into a single line on the screen, an ellipsis ('...') is meant to join the broken line.

Table of commands in alphabetical order:

ACTIVATE

Activate the application

ADDITEM

Add an item to a list

BAUD

Set the serial transfer speed

BEEPSCREEN
Give a visual/audible report

CALLMENU
Invoke a menu function

CAPTURE
Activate printer or file capture

CLEAR
Clear a list or the text buffer

CLEARSCREEN
Clear the terminal screen

CLOSE
Terminate printer or file capture

CLOSEDEVICE
Release the serial driver

CLOSEREQUESTER
Close the currently open requester window

DEACTIVATE
Deactivate the application

DELAY
Delay command execution

DIAL
Dial a list or a single phone number

DUPLEX
Set the terminal duplex mode

EXECTOOL
Execute a program

FAULT
Return the string associated with a error code

GETATTR
Query an application attribute

GETCLIP
Get the contents of the clipboard

HANGUP
Hang up the line

HELP
Get help on a single command or invoke online-help

OPEN
Open a configuration/phonebook file

OPENDEVICE
 (Re-)Open the serial driver

OPENREQUESTER
 Open a certain requester window

PARITY
 Set the terminal parity mode

PASTECLIP
 Insert the clipboard contents into the input stream

PRINT
 Print the contents of a list

PROTOCOL
 Set the serial handshaking protocol

PUTCLIP
 Send text to the clipboard

QUIT
 Terminate the application

READ
 Read text from the terminal

RECEIVEFILE
 Receive files through the XPR protocol

REDIAL
 Redial the current dialing list

REMITEM
 Remove an item from a list

REQUESTFILE
 Requester a number of file names from the user

REQUESTNOTIFY
 Notify the user with a message

REQUESTNUMBER
 Requester a numeric value from the user

REQUESTRESPONSE
 Requester a response value from the user

REQUESTSTRING
 Requester a string value from the user

RESETSCREEN
 Reset the terminal screen

RESETSTYLES
 Reset the terminal text rendering styles

RESETTEXT	Reset the terminal text font
RX	Execute an ARexx command
SAVE	Save configuration/phonebook to a file
SAVEAS	Save configuration/phonebook to a file
SELECTITEM	Select an item from a list
SEND	Send text across the serial line
SEENDBREAK	Send a break signal across the serial line
SENDFILE	Send files through the XPR protocol
SETATTR	Set an application attribute
SPEAK	Speak a text
STOPBITS	Set the serial stop bits
TEXTBUFFER	Lock or unlock the text buffer
TIMEOUT	Set the command timeout
WAIT	Wait for certain text to be received
WINDOW	Manipulate the characteristics of a window

Table of commands in functional groups:

Commands dealing with text buffer and capturing

CAPTURE	Activate printer or file capture
CLEAR	Clear a list or the text buffer

CLOSE
Terminate printer or file capture

OPEN
Open a configuration/phonebook file

PRINT
Print the contents of a list

SAVE
Save configuration/phonebook to a file

SAVEAS
Save configuration/phonebook to a file

TEXTBUFFER
Lock or unlock the text buffer

WINDOW
Manipulate the characteristics of a window

Commands dealing with serial I/O

BAUD
Set the serial transfer speed

CLOSEDEVICE
Release the serial driver

DIAL
Dial a list or a single phone number

DUPLEX
Set the terminal duplex mode

HANGUP
Hang up the line

OPENDEVICE
(Re-)Open the serial driver

PARITY
Set the terminal parity mode

PROTOCOL
Set the serial handshaking protocol

READ
Read text from the terminal

REDIAL
Redial the current dialing list

SENDERBREAK

Send a break signal across the serial line

STOPBITS

Set the serial stop bits

WAIT

Wait for certain text to be received

TIMEOUT

Set the command timeout

Commands dealing with lists

ADDITEM

Add an item to a list

CLEAR

Clear a list or the text buffer

DIAL

Dial a list or a single phone number

REMITEM

Remove an item from a list

SELECTITEM

Select an item from a list

SENDFILE

Send files through the XPR protocol

WAIT

Wait for certain text to be received

Commands dealing with the clipboard

GETCLIP

Get the contents of the clipboard

PASTECLIP

Insert the clipboard contents into the input stream

PRINT

Print the contents of a list

PUTCLIP

Send text to the clipboard

Commands dealing with file transfers

RECEIVEFILE

Receive files through the XPR protocol

SENDFILE

Send files through the XPR protocol

Commands dealing with terminal I/O

BEEPSCREEN

Give a visual/audible report

CLEARSCREEN

Clear the terminal screen

READ

Read text from the terminal

RESETSCREEN

Reset the terminal screen

RESETSTYLES

Reset the terminal text rendering styles

RESETTEXT

Reset the terminal text font

SEND

Send text across the serial line

Commands dealing with windows and requesters

ACTIVATE

Activate the application

CALLMENU

Invoke a menu function

CLOSEREQUESTER

Close the currently open requester window

DEACTIVATE

Deactivate the application

OPENREQUESTER

Open a certain requester window

REQUESTFILE

Requester a number of file names from the user

REQUESTNOTIFY

Notify the user with a message

REQUESTNUMBER

Requester a numeric value from the user

REQUESTRESPONSE
Requester a response value from the user

REQUESTSTRING
Requester a string value from the user

WINDOW
Manipulate the characteristics of a window

Commands dealing with program attributes

GETATTR
Query an application attribute

SETATTR
Set an application attribute

Commands dealing with program execution

EXECTOOL
Execute a program

RX
Execute an ARexx command

Commands dealing with file I/O

OPEN
Open a configuration/phonebook file

PRINT
Print the contents of a list

SAVE
Save configuration/phonebook to a file

SAVEAS
Save configuration/phonebook to a file

Miscellaneous commands

DELAY
Delay command execution

FAULT
Return the string associated with a error code

HELP

	Get help on a single command or invoke online-help
QUIT	Terminate the application
SPEAK	Speak a text

1.7 termRexx.guide/ACTIVATE

The ACTIVATE command

Format:

```
ACTIVATE
```

Template:

```
'
```

Purpose:

De-iconifies the program, brings the main window to the front and makes it active.

Specifications:

The program can be put to sleep using the DEACTIVATE command, to

bring it back to proper operation, use the ACTIVATE command. If this command is invoked while the program is not asleep, it will cause the main window to be brought to the front and activated.

Result:

```
-
```

Warning:

```
-
```

Example:

```
/* This is how the main programm can be (re-)activated: */
```

```
ACTIVATE
```

1.8 termRexx.guide/ADDITEM

The ADDITEM command

Format:

```
ADDITEM [To] <Upload|Download|Dial|Wait> [Before|After] [Phone  
<Entry number, name or wildcard pattern>] [Name <Name>]
```

Template:

TO/A,BEFORE/S,AFTER/S,PHONE/K/F,NAME/K/F

Purpose:

Inserts an item (a name, a phone number, text, etc.) before or after the currently selected list item.

Specifications:

'term' maintains a number of lists, these are:

Upload list

The list of files to be uploaded.

Download list

The list of files the program has downloaded.

Dial list

The list of phone numbers or phone book entries to be dialed.

Wait list

The list of texts the

WAIT

command is to wait for.

New items can be added to the list with the ADDITEM command. The upload list expects the names of files the

SENDFILE

command is to

transfer. It makes little sense to add files names to the download list as the 'term' main program maintains it and adds the names of files received to it, but it is still possible. The wait list expects text lines the

WAIT

command will look for in the terminal input stream.

The dial list accepts a number of different parameters:

Phonebook entry numbers

These are passed using the Phone parameter which should be a numeric value as it is used as an index to pick the corresponding entry from the phone book.

Phonebook entry names

These are also passed using the Phone parameter which can be a proper name or a wildcard pattern.

Phone numbers

These are passed using the Name parameter.

List item can be inserted before or after the currently selected list item (see

SELECTITEM

command). The default is to insert them after the currently selected list item.

Result:

-

Warning:

-

Example:

```
/* Enable result codes. */  
  
OPTIONS RESULTS  
  
/* Get a file name from the user. */  
  
REQUESTFILE TITLE '"Select a file to upload"'  
  
/* Add the file name to the upload list. */  
  
IF rc = 0 THEN ADDITEM TO upload NAME result  
  
/* Add phonebook entry #2 to the dial list. */  
  
ADDITEM TO dial PHONE 2  
  
/* Add all phonebook entries whose names start  
* with an 'a' to the dial list.  
*/  
  
ADDITEM TO dial PHONE a#?  
  
/* Add a plain phone number to the dial list. */  
  
ADDITEM TO dial NAME 424242
```

1.9 termRexx.guide/BAUD

The BAUD command

Format:

```
BAUD [Rate] <Baud rate in bits per second>
```

Template:

```
RATE/A/N
```

Purpose:

Sets the serial line transfer speed

Specifications:

Sets the serial line transfers speed to some defined value. The rate parameter passed in will be matched against all valid baud rates supported by 'term', the closest value will be used.

Result:

-

Warning:

-

Example:

```
/* Change the serial transfer speed to 2400 bps. */  
  
BAUD 2400
```

1.10 termRexx.guide/BEEPSCREEN

The BEEPSCREEN command

Format:

```
BEEPSCREEN
```

Template:

,

Purpose:

'Beeps' the terminal screen.

Specifications:

Invokes a bell signal, as configured in the program settings.

Result:

-

Warning:

-

Example:

```
/* Invoke a bell signal. */  
  
BEEPSCREEN
```

1.11 termRexx.guide/CALLMENU

The CALLMENU command

Format:

```
CALLMENU [Title] <Title text or wildcard pattern>
```

Template:

```
TITLE/A/F
```

Purpose:

Invokes the function associated with a menu item.

Specifications:

Calls a pull-down menu function just as if the user had selected it using the mouse. The Title parameter can be any valid menu item name or a wildcard pattern. In the latter case, only the first menu item to match the pattern will be called.

Result:

-

Warning:

If no matching menu item was to be found.

Example:

```
/* Invoke the 'About...' menu item. */  
  
CALLMENU abou#?
```

1.12 termRexx.guide/CAPTURE

The CAPTURE command

Format:

```
CAPTURE [To] <Printer|File> [Name <File name>]
```

Template:

```
TO/A,NAME/K
```

Purpose:

Starts a file or printer capture.

Specifications:

If a capture is not already in progress will open a capture file or start capturing incoming terminal text to the printer. If the File argument is given and the Name parameter is omitted, will prompt for the name of a file to capture to.

If to capture to a given file, will append the captured text. If user is to select a file to capture to, will ask whether to append the text to the file or to overwrite it.

Result:

-

Warning:

In case user was to select a file and aborted the selection.

Example:

```
/* Open a named capture file. */  
  
CAPTURE TO file NAME 'ram:capture file'  
  
/* Close the capture file, ask the user for a file name. */  
  
CLOSE FILE  
CAPTURE TO file
```

```
/* Capture to the printer. */  
  
CAPTURE TO printer
```

1.13 termRexx.guide/CLEAR

The CLEAR command

Format:

```
CLEAR [From] <Upload|Download|Dial|Wait|Buffer> [Force]
```

Template:

```
FROM/A, FORCE/S
```

Purpose:

Clears the contents of a global list or the text buffer.

Specifications:

This command serves to clear the contents of the lists to be maintained using the

```
ADDITEM
```

```
,
```

```
REMITEM
```

```
,
```

```
SELECTITEM
```

```
, etc. commands
```

and to purge the contents of the text buffer. In the latter case the program will prompt for confirmation in case the buffer still holds any lines. This confirmation can be suppressed by using the Force parameter.

Result:

```
-
```

Warning:

In case the user did not confirm to clear the buffer.

Example:

```
/* Clear the wait list. */  
  
CLEAR FROM wait  
  
/* Clear the buffer, ask for a confirmation. */  
  
CLEAR FROM buffer  
  
/* If no confirmation was given, clear it by force. */  
  
IF rc ~= 0 THEN CLEAR FROM buffer FORCE
```


1.14 termRexx.guide/CLEARSCREEN

The CLEARSCREEN command

Format:

```
CLEARSCREEN
```

Template:

```
,
```

Purpose:

```
Clears the terminal screen
```

Specifications:

```
Clears the terminal screen and positions the cursor in the top  
left corner.
```

Result:

```
-
```

Warning:

```
-
```

Example:

```
/* Clear the terminal screen. */  
  
CLEARSCREEN
```

1.15 termRexx.guide/CLOSE

The CLOSE command

Format:

```
CLOSE [From] <Printer|File|All>
```

Template:

```
FROM/A
```

Purpose:

```
Terminates file and/or printer capture.
```

Specifications:

```
Terminates a capture process as started with the  
CAPTURE  
command.
```

```
Will terminate printer capture, file capture or both.
```

Result:

```
-
```

Warning:

```
-
```

Example:

```
/* Terminate both file and printer capture. */  
  
CLOSE ALL
```

1.16 termRexx.guide/CLOSEDEVICE

The CLOSEDEVICE command

Format:

```
CLOSEDEVICE
```

Template:

```
,
```

Purpose:

Release the current serial device driver

Specifications:

Frees the serial device driver for use with other applications. The driver can be reopened (or a different device driver can be selected) using the
OPENDEVICE
command.

Result:

```
-
```

Warning:

```
-
```

Example:

```
/* Release the serial device driver, all serial I/O  
* will be halted.  
*/  
  
CLOSEDEVICE
```

1.17 termRexx.guide/CLOSEREQUESTER

The CLOSEREQUESTER command

Format:

```
CLOSEREQUESTER
```

Template:

```
,
```

Purpose:

Closes the currently open requester window

Specifications:

Will close any currently open requester window, such as the dialing window, the phone book, the serial settings window, etc. Will not close windows such as the file transfer window or the text/numeric input windows.

Result:

-

Warning:

-

Example:

```
/* Close the currently open requester window,  
 * whatever it may be.  
 */
```

```
CLOSEREQUESTER
```

1.18 termRexx.guide/DEACTIVATE

The DEACTIVATE command

Format:

```
DEACTIVATE
```

Template:

,

Purpose:

Iconifies the program.

Specifications:

Puts the application to sleep. Requires Workbench to be running, so an AppIcon can be put on the Workbench backdrop. This command will be ignored if the application has already been put to sleep. To wake the application up, use the

```
ACTIVATE  
command.
```

Result:

-

Warning:

-

Example:

```
/* Iconify the program. */
```

```
DEACTIVATE
```

1.19 termRexx.guide/DELAY

The DELAY command

Format:

```
DELAY [MIC|MICROSECONDS <Number>] [[SEC|SECONDS] <Number>]
      [MIN|MINUTES <Number>] [QUIET]
```

Template:

```
MIC=MICROSECONDS/K/N,SEC=SECONDS/N,MIN=MINUTES/K/N,QUIET/S
```

Purpose:

Delays program execution for a couple of microseconds, seconds and minutes.

Specifications:

Will cause both the program to make the call and the application to wait for a certain period of time. Unless the QUIET option is in effect will process and display data received from the serial line.

Result:

-

Warning:

If command was aborted before the timeout had elapsed.

Example:

```
/* Wait for five seconds. */
DELAY 5

/* Wait for one second and seven microseconds. */
DELAY MIC 7 SEC 5
```

1.20 termRexx.guide/DIAL

The DIAL command

Format:

```
DIAL [[Num] <Phone number>]
```

Template:

```
NUM/F
```

Purpose:

Dials the provided phone number. If no phone number was given, will dial the numbers and phone book entries stored in the dial

list.

Specifications:

This command will build a dialing list from the available sources and pass it to the dialing function which is to schedule the dialing process and perform any login-actions. Available sources are the Num parameter which will cause the command to dial only this single number or the dial list whose contents will be used if the Num parameter is omitted.

This command will return as soon as the dialing process has been initiated.

Result:

-

Warning:

-

Example:

```
/* Dial a single phone number. */  
  
DIAL 424242  
  
/* Wait a bit and abort the dialing process. */  
  
DELAY 5  
CLOSEREQUESTER  
  
/* Clear the dialing list, then add all the phonebook entries  
* to the list.  
*/  
  
CLEAR FROM dial  
ADDITEM TO dial PHONE #?  
  
/* Dial the dial list. */  
  
DIAL
```

1.21 termRexx.guide/DUPLEX

The DUPLEX command

Format:

```
DUPLEX [Full|Half|Echo]
```

Template:

```
FULL/S, HALF=ECHO/S
```

Purpose:

Sets the serial line duplex mode.

Specifications:

Sets the serial line duplex mode, this can be either full duplex or half duplex (local echo).

Result:

-

Warning:

-

Example:

```
/* Enable local terminal echo. */
```

```
DUPLEX ECHO
```

1.22 termRexx.guide/EXECTOOL

The EXECTOOL command

Format:

```
EXECTOOL [Console] [Async] [Port] [Command] <File name>
```

Template:

```
CONSOLE/S,ASYNC/S,PORT/S,COMMAND/A/F
```

Purpose:

Executes a program.

Specifications:

Will load and execute an AmigaDOS program. The Console parameter will cause an output file or window to be opened, the Async parameter will cause the command to return as soon as the execution process has been launched. The Port parameter will cause the current ARexx host port name to be passed to the tool on the command line.

Result:

-

Warning:

-

Example:

```
/* Launch the 'Dir' command. */
```

```
EXECTOOL CONSOLE COMMAND 'dir c:'
```

1.23 termRexx.guide/FAULT

The FAULT command

Format:

```
FAULT [Code] <Error code>
```

Template:

```
CODE/A/N
```

Purpose:

Returns the descriptive text associated with an error code as returned by 'term'.

Specifications:

'term' will return error codes in the term.lasterror variable. In order to get the descriptive text associated with an error code, use this command. All internal Rexx and AmigaDOS errors codes are supported as well as the error codes special to 'term'.

Result:

The error description associated with the error code.

Warning:

-

Example:

```
/* Enable command results. */  
  
OPTIONS RESULTS  
  
/* Get the text associated with error #1001. */  
  
FAULT 1001  
  
/* Output the result. */  
  
SAY result
```

1.24 termRexx.guide/GETATTR

The GETATTR command

Format:

```
GETATTR [Object] <Name> [Field] <Name> [Stem <Name>] [Var <Name>]
```

Template:

```
OBJECT/A, FIELD, STEM/K, VAR/K
```

Purpose:

Obtains information on an application attribute.

Specifications:

Obtains information on an object, if possible will store it in the result variable. If a stem or simple variable name is given using the Stem or Var parameters will store the information in this variable. If no Field parameter is given, will store the entire object contents which requires that the Stem parameter is given.

For a list of valid attributes see the section entitled
Attributes

.

Result:

Returns information either in result variable or in the supplied
Stem or Var variable.

Warning:

-

Example:

```
/* Enable command results. */

OPTIONS RESULTS

/* Query the name of the ARexx host we are communicating with. */

GETATTR OBJECT term FIELD arexx

/* Output the result. */

SAY result

/* Same as above, but using a different syntax. */

GETATTR term.arexx
SAY result

/* Store the entire contents of the phone book in a
 * stem variable.
 */

GETATTR phonebook STEM book

/* Output the phonebook contents. */

SAY 'phone book contains' book.count 'entries'

DO i = 0 TO book.count - 1
  SAY 'entry #' i

      SAY 'name      :' book.i.name
      SAY 'number   :' book.i.number
      SAY 'comment  :' book.i.commenttext
      SAY 'username:' book.i.username
END i
```

1.25 termRexx.guide/GETCLIP

The GETCLIP command

Format:

GETCLIP [Unit <Number>]

Template:

UNIT/K/N

Purpose:

Retrieves the contents of the clipboard.

Specifications:

Obtains the contents of the clipboard and returns it in the result variable. Will optionally read from the given clipboard unit, but uses the unit number selected in the application settings by default. Note that a string returned can be up to 65,536 characters long!

Result:

Contents of the clipboard if it contains any text.

Warning:

If clipboard does not contain any text.

Example:

```
/* Enable command results. */  
  
OPTIONS RESULTS  
  
/* Get the primary clipboard contents. */  
  
GETCLIP  
  
/* Output the contents. */  
  
IF rc ~= 0 THEN  
    SAY 'clipboard does not contain any text'  
ELSE  
    SAY result
```

1.26 termRexx.guide/HANGUP

The HANGUP command

Format:

HANGUP

Template:

,

Purpose:

Hang up the serial line.

Specifications:

Hangs up the serial line, executes logoff and cleanup operations.

Result:

-

Warning:

-

Example:

```
/* Hang up the line, whether the program is online or not. */  
  
HANGUP
```

1.27 termRexx.guide/HELP

The HELP command

Format:

```
HELP [[Command] <Name>] [Prompt]
```

Template:

```
COMMAND,PROMPT/S
```

Purpose:

Returns the template of a command or invokes the online help system.

Specifications:

This command will either return the template associated with a 'term' ARexx command specified using the Command parameter or invoke the AmigaGuide(tm) help system.

Result:

Command template if requested.

Warning:

-

Example:

```
/* Enable command results. */  
  
OPTIONS RESULTS  
  
/* Query the template associated with the 'selectitem' command. */  
  
HELP selectitem  
  
/* Output the result. */  
  
SAY result  
  
/* Invoke the online help. */  
  
HELP PROMPT
```

1.28 termRexx.guide/OPEN

The OPEN command

Format:

```
OPEN [Name <File name>] [TO] <Translations|Functionkeys|Cursorkeys|
Fastmacros|Hotkeys|Speech|Sound|Buffer|Configuration|Phone>
```

Template:

```
NAME/K, TO/A
```

Purpose:

Reads data from a disk file.

Specifications:

This command reads the contents of a disk file and stores the information either in the configuration, the phone book or the text buffer. If text is read into the text buffer it will be appended to the existing text. If no file name is given will prompt the user to select a file.

Result:

-

Warning:

If user was requested to select a file and cancelled the selection.

Example:

```
/* Load the configuration from a file. */
OPEN NAME 'ram:term.prefs' TO configuration
/* Add text to the text buffer. */
OPEN TO buffer
```

1.29 termRexx.guide/OPENDEVICE

The OPENDEVICE command

Format:

```
OPENDEVICE [Name <Device name>] [Unit <Number>]
```

Template:

```
NAME/K, UNIT/K/N
```

Purpose:

(Re-)Opens the serial device driver.

Specifications:

(Re-)Opens the previously released (see CLOSEDEVICE command) device

driver or a different device driver/unit if the corresponding Device and Unit parameters are given.

Result:

-

Warning:

-

Example:

```
/* Release the serial device driver. */  
  
CLOSEDEVICE  
  
/* Open a different device driver. */  
  
OPENDEVICE DEVICE 'duart.device' UNIT 5
```

1.30 termRexx.guide/OPENREQUESTER

The OPENREQUESTER command

Format:

```
OPENREQUESTER [REQUESTER]  
<Serial|Modem|Screen|Terminal|Emulation|Clipboard|
```

```
Capture|Commands|Misc|Path|Transfer|Translations|Functionkeys|Cursorkeys|  
Fastmacros|Hotkeys|Speech|Sound|Phone>
```

Template:

```
REQUESTER/A
```

Purpose:

Opens a requester window.

Specifications:

Opens a requester window. Only a single window can be open at a time. The window opened can be closed using the

```
CLOSEREQUESTER  
command.
```

Result:

-

Warning:

-

Example:

```
/* Open the phonebook window. */  
  
OPENREQUESTER phone
```

1.31 termRexx.guide/PARITY

The PARITY command

Format:

```
PARITY [Even|Odd|None|Mark|Space]
```

Template:

```
EVEN/S, ODD/S, NONE/S, MARK/S, SPACE/S
```

Purpose:

Sets the serial line parity mode.

Specifications:

Sets the serial line parity mode.

Result:

-

Warning:

-

Example:

```
/* Set the parity mode. */  
  
PARITY NONE
```

1.32 termRexx.guide/PASTECLIP

The PASTECLIP command

Format:

```
PASTECLIP [Unit <Number>]
```

Template:

```
UNIT/K/N
```

Purpose:

Feed the contents of the clipboard into the input stream.

Specifications:

Feeds the contents of the clipboard into the input stream. Obtains the data either from the given clipboard unit or from the default unit configured in the program settings.

Result:

-

Warning:

If clipboard does not contain any text.

Example:

```
/* Paste the contents of clipboard #2. */  
  
PASTECLIP UNIT 2
```

1.33 termRexx.guide/PRINT

The PRINT command

Format:

```
PRINT [From]  
<Screentext|Clipboard|Buffer|Dial|Wait|Upload|Download> [TO <File  
name>] [Serial|Modem|Screen|Terminal|User|Comment| Size|Date|Attr]
```

Template:

```
FROM/A, TO/K, SERIAL/S, MODEM/S, SCREEN/S, TERMINAL/S, USER/S,  
COMMENT/S, SIZE/S, DATE/S, ATTR/S
```

Purpose:

Prints the contents of the screen, the clipboard, the textbuffer or one of the lists.

Specifications:

Outputs the contents of the screen, the clipboard, the textbuffer or one of the lists (see

ADDITEM

command) to a file or the

printer. If the To parameter is omitted, will output the data to the printer. The parameters Serial through Attr control what will be printed:

Screentext, Clipboard, Buffer, Wait list

Options have no effect on the output.

Dial list

Responds to the Serial, Modem, Screen, Terminal, User and Comment parameters. The printout will contain information on the corresponding settings.

Upload list, Download list

Responds to the Comment, Size, Date and Attr parameters. The printout will contain information on the corresponding file attributes. Note: if any of these parameters are given, only the base file names will be printed along with the corresponding information.

Result:

-

Warning:

If user cancelled print operation.

Example:

```
/* Clear the dialing list, then add the entire phone book to it. */  
  
CLEAR dial  
additem to dial phone #?  
  
/* Send the contents of the dial list to a disk file. */  
  
PRINT FROM dial TO 'ram:phonebook' SERIAL MODEM SCREEN...  
...TERMINAL USER COMMENT
```

1.34 termRexx.guide/PROTOCOL

The PROTOCOL command

Format:

```
PROTOCOL [None|RTSCTS|RTSCTSDTR]
```

Template:

```
NONE/S,RTSCTS/S,RTSCTSDTR/S
```

Purpose:

Sets the serial line handshaking protocol.

Specifications:

Sets the serial line handshaking protocol. See the main program documentation for details.

Result:

-

Warning:

-

Example:

```
/* Set the handshaking protocol. */  
  
PROTOCOL NONE
```

1.35 termRexx.guide/PUTCLIP

The PUTCLIP command

Format:

```
PUTCLIP [Unit <Unit>] [TEXT] <Text to store>
```

Template:

UNIT/K/N,TEXT/A/F

Purpose:

Stores text in the clipboard.

Specifications:

Stores the provided text in the clipboard. Will store it in the given clipboard unit if the Unit parameter is given. Will use the unit number configured in the program settings otherwise.

Result:

-

Warning:

-

Example:

```
/* Store a short string in the clipboard. Note: can
 * only be up to 65,536 characters long.
 */
```

```
PUTCLIP 'hello sailor!'
```

1.36 termRexx.guide/QUIT

The QUIT command

Format:

QUIT [Force]

Template:

FORCE/S

Purpose:

Terminates the application.

Specifications:

Terminates program execution, will ask for a confirmation to leave unless the Force parameter is used.

Result:

-

Warning:

If user did not confirm termination.

Example:

```
/* Try to terminate the program, ask for confirmation. */
```

```
QUIT
```

```
/* If no confirmation was given terminate by force. */
```

```
IF rc ~= 0 THEN QUIT FORCE
```

1.37 termRexx.guide/READ

The READ command

Format:

```
READ [Num <Number of bytes>] [CR] [Noecho] [Verbatim] [[Prompt]
<Prompt text>]
```

Template:

```
NUM/K/N, CR/S, NOECHO/S, VERBATIM/S, PROMPT/K/F
```

Purpose:

Reads a number of bytes or a string from the serial line.

Specifications:

If Num parameter is given will read a number of bytes from the serial line (note: only a maximum of 65,536 bytes can be read). The command will return when the read request has been satisfied, the timeout (settable using the

```
TIMEOUT
```

command) has elapsed or the command was aborted.

If the CR parameter is given will handle simple line editing functions (Backspace, Control-X) and return a string as soon as the Carriage return key is pressed, the timeout (settable using the

```
TIMEOUT
```

command) has elapsed or the command is aborted.

The Noecho parameter will cause 'term' not to echo typed characters back to the remote. Note that in order to see any input on the local side the remote is to echo the characters typed back.

If present, the Prompt text will be sent across the serial line, much the same as if it had been sent using the

```
SEND
```

command.

This command pays attention to the current character translation table for incoming characters. If the characters are to be read without any changes made one has to use the Verbatim parameter.

Result:

The string read.

Warning:

If command was cancelled, no input was made or, if the CR parameter is used, the timeout elapsed.

Example:

```
/* Enable command results. */

OPTIONS RESULTS

/* Set the read timeout to five seconds. */

TIMEOUT 5

/* Read seven bytes. */

READ NUM 7

/* Output the result. */

IF rc ~= 0 THEN
    SAY 'no data was read'
ELSE
    SAY result

/* Turn the timeout off. */

TIMEOUT OFF

/* Prompt for input. */

READ CR PROMPT 'Enter a line of text:'

/* Output the result. */

IF rc ~= 0 THEN
    SAY 'no input was made'
ELSE
    SAY result
```

1.38 termRexx.guide/RECEIVEFILE

The RECEIVEFILE command

Format:

```
RECEIVEFILE [Mode <ASCII|Text|Binary>] [Name <File name>]
```

Template:

```
MODE/K,NAME/K
```

Purpose:

Receive one or more files using the XPR protocol.

Specifications:

Receives one or more files using the currently configured XPR protocol. The Mode parameter determines the file transfer mode (either plain ASCII, Text mode or binary file mode), if omitted the file(s) will be received in binary mode. Some file transfer protocols do not require any file names to be given as they have

their own means to determine the names of the files to be received. However, a file name parameter can be given. If omitted the file transfer protocol will prompt the user for a file name if necessary.

The names of all files received are placed on the download list for processing. The list will be cleared before the transfer is started.

Result:

-

Warning:

If user cancelled file selection.

Example:

```
/* Start to receive a file in text mode. */  
  
RECEIVEFILE MODE text
```

1.39 termRexx.guide/REDIAL

The REDIAL command

Format:

REDIAL

Template:

,

Purpose:

Redials the numbers remaining in the currently configured dialing list.

Specifications:

Redials the numbers which still remain in the dialing list built either by the phone book or by the
DIAL
command. Note that this
command will return as soon as the dialing process is initiated.

Result:

-

Warning:

If dialing list is empty.

Example:

```
/* Redial the list. */  
  
REDIAL  
  
/* Successful? */
```

```
IF rc ~= 0 THEN SAY 'dialing list is empty'
```

1.40 termRexx.guide/REMITEM

The REMITEM command

Format:

```
REMITEM [From] <Upload|Download|Dial|Wait> [Name <Name or  
wildcard>]
```

Template:

```
FROM/A,NAME/K/F
```

Purpose:

Removes one or more items from a list.

Specifications:

Removes one or more items from a list. If no Name parameter is given will remove the currently selected list item (selectable using the

```
SELECTITEM
```

command). The Name parameter can be a proper name or a wildcard pattern.

Note: Cannot remove named items from the dial list.

Result:

-

Warning:

If no list item would match the name pattern.

Example:

```
/* Remove the currently selected item from the wait list. */
```

```
REMITEM FROM wait
```

```
/* Remove all items from the wait list which end with 'z'. */
```

```
REMITEM FROM wait NAME '#?z'
```

1.41 termRexx.guide/REQUESTFILE

The REQUESTFILE command

Format:

```
REQUESTFILE [Title <Title text>] [Path <Path name>] [File <File  
name>] [Pattern <Wildcard pattern>] [Multi] [Stem|Name <Variable
```

name>]

Template:

TITLE/K,PATH/K,FILE/K,PATTERN/K,MULTI/S,STEM=NAME/K

Purpose:

Requests one or more file names from the user.

Specifications:

Requests one or more file names from the user. Will present a file requester with given title text and preset path, file name and pattern values. If only a single file name is to be requested will place the result in the result variable. The Multi parameter allows multiple files to be selected, the number of files selected and the file names will be placed in the variable specified using the Stem parameter.

Result:

The name of the file selected will be placed in the result variable. If multiple file were selected, will place the following information in the supplied stem variable:

<Variable name>.COUNT
The number of files selected.

<Variable name>.0 through <Variable name>.n-1
The file names selected.

Warning:

If user cancelled selection.

Example:

```
/* Enable command results. */  
  
OPTIONS RESULTS  
  
/* Request a single file name from the user. */  
  
REQUESTFILE TITLE '"select a file"'  
  
/* Output the result. */  
  
IF rc ~= 0 THEN  
    SAY 'no file was selected'  
ELSE  
    SAY result  
  
/* Request several files. */  
  
REQUESTFILE TITLE 'select several files' MULTI STEM names  
  
/* Output the result. */  
  
IF rc ~= 0 THEN  
    SAY 'no files were selected'  
ELSE DO  
    SAY 'files selected:' names.count
```

```
        DO i = 0 TO names.count - 1
          SAY names.i
        END
      END
```

1.42 termRexx.guide/REQUESTNOTIFY

The REQUESTNOTIFY command

Format:

```
REQUESTNOTIFY [Title <Title text>] [Prompt] <Prompt text>
```

Template:

```
TITLE/K,PROMPT/A/F
```

Purpose:

Notify the user with a message.

Specifications:

Opens a requester to notify the user, the prompt text can include line feed characters ('0A'X), the user will be able to answer the requester by clicking on a Continue button.

Result:

-

Warning:

-

Example:

```
/* Notify the user. */

REQUESTNOTIFY TITLE '"Important information"' ...
...PROMPT 'This message is important'
```

1.43 termRexx.guide/REQUESTNUMBER

The REQUESTNUMBER command

Format:

```
REQUESTNUMBER [Default <Default number>] [Prompt <Prompt text>]
```

Template:

```
DEFAULT/K/N,PROMPT/K/F
```

Purpose:

Requests a numeric value from the user

Specifications:

Requests a numeric value from the user, will display the provided prompt text or a default text and present the provided default number, so user can simply hit return to accept the defaults.

Result:

The number the has entered.

Warning:

If user cancelled requester.

Example:

```
/* Enable command results. */  
  
OPTIONS RESULTS  
  
/* Requester a single number. */  
  
REQUESTNUMBER DEFAULT 42 PROMPT 'Enter the answer'  
  
/* Output the result. */  
  
IF rc ~= 0 THEN  
    SAY 'no number was entered'  
ELSE  
    SAY result
```

1.44 termRexx.guide/REQUESTRESPONSE

The REQUESTRESPONSE command

Format:

```
REQUESTRESPONSE [Title <Title text>] [Options <Options string>]  
[Prompt] <Prompt text>
```

Template:

```
TITLE/K,OPTIONS/K,PROMPT/A/F
```

Purpose:

Request a response from user.

Specifications:

Requests a response from the user, uses provided title and prompt text and a number of options. If no options are specified will use Yes|No as the defaults.

Result:

For Options passed as Yes|Perhaps|No will return 1 for Yes, 2 for Perhaps and return a warning for No.

Warning:

If user selected negative choice.

Example:

```
/* Enable command results. */
```

```
OPTIONS RESULTS

/* Request a response. */

REQUESTRESPONSE PROMPT 'Are you indecisive?' ...
...OPTIONS '"Yes|Don't know|No"'

/* Look at the response. */

IF rc ~= 0 THEN
    SAY 'Not indecisive'
ELSE DO
    IF result = 0 THEN
        SAY 'Indecisive'
    ELSE
        SAY 'Probably indecisive'
END
```

1.45 termRexx.guide/REQUESTSTRING

The REQUESTSTRING command

Format:

```
REQUESTSTRING [Secret] [Default <String>] [Prompt <Text>]
```

Template:

```
SECRET/S,DEFAULT/K,PROMPT/K/F
```

Purpose:

Requests a string from the user.

Specifications:

Requests a string from the user, will display the provided prompt text or a default text and present the provided default string, so user can simply hit return to accept the defaults.

If the Secret parameter is provided, will not display the characters typed.

Result:

The text the user entered.

Warning:

If user cancelled the requester.

Example:

```
/* Enable command results. */

OPTIONS RESULTS

/* Request a secret string. */

REQUESTSTRING SECRET DEFAULT '"hello sailor!'" ...
```



```
...PROMPT 'Enter secret message'  
  
/* Output the result. */  
  
IF rc ~= 0 THEN  
    SAY 'no text was entered'  
ELSE  
    SAY result
```

1.46 termRexx.guide/RESETSCREEN

The RESETSCREEN command

Format:

```
RESETSCREEN
```

Template:

```
,
```

Purpose:

Resets the terminal screen to defaults.

Specifications:

Resets the terminal screen to defaults, this includes clearing the screen, moving the cursor to the home position and resetting text, text rendering styles and colours.

Result:

```
-
```

Warning:

```
-
```

Example:

```
/* Reset the terminal screen. */  
  
RESETSCREEN
```

1.47 termRexx.guide/RESETSTYLES

The RESETSTYLES command

Format:

```
RESETSTYLES
```

Template:

```
,
```

Purpose:

Resets the text rendering styles to defaults.

Specifications:

Resets the text rendering styles to defaults, turning off inverse video, boldface, italics, etc. modes.

Result:

-

Warning:

-

Example:

```
/* Reset the text rendering styles. */  
  
RESETSTYLES
```

1.48 termRexx.guide/RESETTEXT

The RESETTEXT command

Format:

RESETTEXT

Template:

,

Purpose:

Reset the terminal text to defaults.

Specifications:

Reset the terminal text to defaults, this includes switching back from graphics text or G1 mode.

Result:

-

Warning:

-

Example:

```
/* Reset the terminal text. */  
  
RESETTEXT
```

1.49 termRexx.guide/RX

The RX command

Format:

RX [Console] [Async] [Command] <Command name>

Template:

```
CONSOLE/S,ASYNC/S,COMMAND/A/F
```

Purpose:

Invokes an ARexx macro file.

Specifications:

Invokes an ARexx macro file, if Console argument specified opens a console output window, else uses NIL:, if Async argument specified executes the macro asynchronously.

Result:

-

Warning:

-

Example:

```
/* Launch the 'term' command shell. */  
  
RX CONSOLE ASYNC 'term:cmdshell.term'
```

1.50 termRexx.guide/SAVE

The SAVE command

Format:

```
SAVE [From] <Translations|Functionkeys|  
Cursorkeys|Fastmacros|Hotkeys|Speech|  
Sound|Buffer|Configuration|Phone| Screentext|Screenimage>
```

Template:

```
FROM/A
```

Purpose:

Saves data to a disk file.

Specifications:

Saves data to a disk file, will prompt for a file name to save to.
See

```
SAVEAS  
command for more information.
```

Result:

-

Warning:

If user cancels save operation.

Example:

```
/* Save the terminal screen contents to an  
* IFF-ILBM file.  
*/
```

SAVE FROM screenimage

1.51 termRexx.guide/SAVEAS

The SAVEAS command

Format:

```
SAVEAS [Name <File name>] [From]
<Translations|Functionkeys|Cursorkeys|
Fastmacros|Hotkeys|Speech|Sound|Buffer|
Configuration|Phone|Screentext| Screenimage>
```

Template:

```
NAME/K, FROM/A
```

Purpose:

Saves data to a disk file.

Specifications:

Saves data to a disk file, will prompt for a filename to save to if none is provided. Will save either parts of the program configuration or the phone book contents (Phonebook parameter), the contents of the terminal screen as plain ASCII text (Screentext parameter) or the contents of the terminal screen as an IFF-ILBM-file (Screenimage parameter).

Result:

-

Warning:

If user cancels save operation.

Example:

```
/* Save the program configuration to a file. */
SAVEAS NAME 'ram:term.prefs' FROM configuration
```

1.52 termRexx.guide/SELECTITEM

The SELECTITEM command

Format:

```
SELECTITEM [Name <Name>] [From] <Upload|Download|Dial|Wait>
[Next|Prev|Previous|Top|Bottom]
```

Template:

```
NAME/K, FROM/A, NEXT/S, PREV=PREVIOUS/S, TOP/S, BOTTOM/S
```

Purpose:

Select an item from a list.

Specifications:

Selects an item from a list, returns the item name in the result variable. The Top parameter will select the first list item, Bottom the last item. The Previous parameter will select the previous list item, Next the next successive item. Instead of using a positioning parameter, it is also possible to use a wildcard pattern or name with the Name parameter. The first list item to match the name will be selected.

Note: cannot be used with the dial list.

Result:

Returns the list item in the result variable.

Warning:

If end of list reached.

Example:

```
/* Enable command results. */  
  
OPTIONS RESULTS  
  
/* Output the contents of the download list. */  
  
SELECTITEM FROM download TOP  
  
DO WHILE rc = 0  
    SAY result  
    SELECTITEM FROM download NEXT  
END
```

1.53 termRexx.guide/SEND

The SEND command

Format:

```
SEND [Noecho] [Local] [Byte <ASCII code>] [Text] <Text>
```

Template:

```
NOECHO/S, LOCAL/S, BYTE/K/N, TEXT/A/F
```

Purpose:

Sends the provided text to the serial line, executes embedded command sequences.

Specifications:

Sends the provided text to the serial line, executes embedded command sequences (see main program documentation). To send a single byte, use the Byte parameter. The Noecho parameter will suppress terminal output. The Local parameter will cause the text to be output only locally in the terminal window, it will not be

sent across the serial line.

Result:

-

Warning:

-

Example:

```
/* Send some text to the serial line. */  
  
SEND 'This is some text.\r\n'  
  
/* Send a single byte (a null) to the serial line. */  
  
SEND BYTE 0  
  
/* Execute an embedded command (send a break signal). */  
  
SEND '\x'
```

1.54 termRexx.guide/SENDBREAK

The SENDBREAK command

Format:

SENDBREAK

Template:

'

Purpose:

Send a break signal across the serial line.

Specifications:

Send a break signal across the serial line.

Result:

-

Warning:

-

Example:

```
/* Send a break signal. */  
  
SENDBREAK
```

1.55 termRexx.guide/SENDFILE

The SENDFILE command

Format:

```
SENDFILE [Mode <ASCII|Text|Binary>] [Names] {File names}
```

Template:

```
MODE/K,NAMES/M
```

Purpose:

Transfers files using the currently selected file transfer protocol.

Specifications:

Transfers one or more files using the currently configured XPR protocol. The Mode parameter determines the file transfer mode (either plain ASCII, Text mode or binary file mode), if omitted the file(s) will be sent in binary mode. Some file transfer protocols do not require any file names to be given as they have their own means to determine the names of the files to be sent. However, a file name parameter can be given. If omitted the file transfer protocol will prompt the user for a file name if necessary. Several file names can be given if necessary, they will be transferred along with the file names stored in the upload list. The file transfer process will remove any files successfully transferred from the upload list, leaving only those behind which were not to be transferred correctly.

Files whose names do not include a fully qualified path name are expected to reside in the default upload directory as specified in the main program paths settings.

Result:

-

Warning:

If user cancels file selection.

Example:

```
/* Prompt for files to be uploaded. */  
  
SENDFILE  
  
/* Send a single file. */  
  
SENDFILE 'c:list'  
  
/* Clear the upload list, add a single file name. */  
  
CLEAR upload  
ADDITEM TO upload NAME 'c:dir'  
  
/* Transfer the file. */  
  
SENDFILE
```

1.56 termRexx.guide/SETATTR

The SETATTR command

Format:

```
SETATTR [Object] <Name> [Field] <Name> [Stem <Name>] [Var <Name>]
```

Template:

```
OBJECT/A, FIELD, STEM/K, VAR
```

Purpose:

Sets a certain application attribute.

Specifications:

Sets a certain application attribute, retrieves the information from the supplied stem or simple variable. For a list of valid attributes, see the section entitled
Attributes
.

Result:

-

Warning:

-

Example:

```
/* Set the transfer speed. */  
  
SETATTR serialprefs baudrate 2400
```

1.57 termRexx.guide/SPEAK

The SPEAK command

Format:

```
SPEAK [Text] <Text>
```

Template:

```
TEXT/A/F
```

Purpose:

Speaks the provided text using the Amiga speech synthesizer.

Specifications:

Speaks the provided text using the Amiga speech synthesizer, requires that speech support is enabled.

Result:

-

Warning:

-

Example:

```
/* Say something sensible. */  
  
SPEAK 'something sensible'
```

1.58 termRexx.guide/STOPBITS

The STOPBITS command

Format:

```
STOPBITS [0|1]
```

Template:

```
0/S,1/S
```

Purpose:

Sets the serial line stop bits.

Specifications:

Sets the serial line stop bits.

Result:

-

Warning:

-

Example:

```
/* Set the serial line stop bits. */  
  
STOPBITS 1
```

1.59 termRexx.guide/TEXTBUFFER

The TEXTBUFFER command

Format:

```
TEXTBUFFER [Lock|Unlock]
```

Template:

```
LOCK/S,UNLOCK/S
```

Purpose:

Locks or unlocks the text buffer contents.

Specifications:

Locks or unlocks the text buffer contents, similar to the effect of the corresponding main menu entry.

Result:

-

Warning:

-

Example:

```
/* Lock the text buffer. */  
  
TEXTBUFFER LOCK
```

1.60 termRexx.guide/TIMEOUT

The TIMEOUT command

Format:

```
TIMEOUT [[Sec|Seconds] <Number>] [Off]
```

Template:

```
SEC=SECONDS/N, OFF/S
```

Purpose:

Sets the serial read timeout.

Specifications:

Sets the timeout the
WAIT
and
READ
commands will wait until they
exit.

Result:

-

Warning:

-

Example:

```
/* Set the read timeout. */  
  
TIMEOUT SEC 5
```

1.61 termRexx.guide/WAIT

The WAIT command

Format:

```
WAIT [Noecho] [[Text] <Text>]
```

Template:

```
NOECHO/S,TEXT/F
```

Purpose:

Waits for a certain sequence of characters to be received from the serial line.

Specifications:

Wait for text to be received from the serial line. If no text to wait for is provided wait for either item of the wait list to appear. The Noecho parameter suppresses terminal output. Note that text comparison does not consider the case of characters (in respect to the ECMA Latin 1 character set).

Result:

Returns the string found.

Warning:

If timeout has elapsed before any matching text was received.

Example:

```
/* Enable command results. */

OPTIONS RESULTS

/* Set the read timeout. */

TIMEOUT SEC 30

/* Wait for a single line of text. */

WAIT 'some text'

/* Clear the wait list, add a few items. */

CLEAR wait
ADDITEM TO wait NAME 'foo'
ADDITEM TO wait NAME 'bar'

/* Wait for the text to appear. */

WAIT

/* Output the result. */

IF rc ~= 0 THEN
    SAY 'no text was received'
ELSE
    SAY result
```

1.62 termRexx.guide/WINDOW

The WINDOW command

Format:

```
WINDOW [Names] {<Buffer|Review|Packet|Fastmacros| Status|Main>}  
[Open|Close] [Activate] [Min|Max] [Front|Back] [Top|Bottom|Up|Down]
```

Template:

```
NAMES/A/M, OPEN/S, CLOSE/S, ACTIVATE/S, MIN/S, MAX/S, FRONT/S, BACK/S,  
TOP/S, BOTTOM/S, UP/S, DOWN/S
```

Purpose:

Manipulates the aspects of a window.

Specifications:

Manipulates the aspects of a window. Not all windows will support all available commands. The windows supported are:

Buffer

The text buffer window and screen. Supports the Open, Close, Activate and Front commands.

Review

The review window. Supports the Open, Close, Activate, Min, Max, Front, Back, Top, Bottom, Up, and Down commands.

Packet

The packet window. Supports the Open, Close, Activate, Min, Max, Front and Back commands.

Fastmacros

The fast! macro window. Supports the Open, Close, Activate, Min, Max, Front and Back commands.

Status

The status window. Supports the Open, Close, Activate, Front and Back commands.

Main

The main program window. Supports the Open, Close, Activate, Front and Back commands.

Result:

-

Warning:

-

Example:

```
/* Open all available windows. */
```

```
WINDOW buffer review packet fastmacros status main OPEN
```

1.63 termRexx.guide/Attributes

Attributes

Several of the application's internal variables are can be accessed and modified using the

GETATTR

and

SETATTR

commands. Information is

available on the objects and their associated fields explained below. Each line consists of the object and field name and the type of the available data:

Numeric data

```
<Object>.<Field>  
    Numeric
```

The information is a numeric value.

Text data

```
<Object>.<Field>  
    Text
```

The information is a text string.

Boolean data

```
<Object>.<Field>  
    Boolean
```

The information is a boolean value and can be ON or OFF.

Mapped codes

```
<Object>.<Field>  
    <Value 1> ... <Value n>
```

The information can be one of the given values.

The TERM object (read-only)

TERM.VERSION

Text

The 'term' program revision.

TERM.SCREEN

Text

The name of the public screen the 'term' main window has been opened on.

TERM.SESSION.ONLINE

Boolean

Whether the program is currently online or not.

TERM.SESSION.SESSIONSTART

Text

Time and date when the 'term' program was started.

TERM.SESSION.BYTESSENT

Numeric

TERM.SESSION.BYTESRECEIVED

Numeric

TERM.SESSION.CONNECTMESSAGE

Text

The message issued by the modem when the connection was established.

TERM.SESSION.BBSNAME

Text

TERM.SESSION.BBSNUMBER

Text

TERM.SESSION.BBSCOMMENT

Text

TERM.SESSION.USERNAME

Text

TERM.SESSION.ONLINEMINUTES

Numeric

The number of minutes the program is currently connected to a BBS.

TERM.SESSION.ONLINECOST

Numeric

The cost of the connection to the BBS.

TERM.AREXX

Text

The name of the ARexx host port the program is communicating with.

TERM.LASTEROR

Numeric

The code corresponding to the error the last command has caused.

TERM.TERMINAL.ROWS

Numeric

The number of available terminal screen rows.

TERM.TERMINAL.COLUMNS

Numeric

The number of available terminal screen columns.

TERM.BUFFER.SIZE

Numeric

The size of the text buffer.

The PHONEBOOK object (read-only)

Available fields are:

PHONEBOOK.COUNT

Numeric

The number of entries in the phonebook. The single phonebook entries can be accessed as PHONEBOOK.0... through PHONEBOOK.n-1....

PHONEBOOK.n.NAME

Text

PHONEBOOK.n.NUMBER

Text

PHONEBOOK.n.COMMENTTEXT

Text

PHONEBOOK.n.USERNAME

Text

PHONEBOOK.n.PASSWORDTEXT

Text

The SERIALPREFS object

Available fields are:

SERIALPREFS.BAUDRATE

Numeric

SERIALPREFS.BREAKLENGTH

Numeric

The break signal length in microseconds.

SERIALPREFS.BUFFERSIZE

Numeric

SERIALPREFS.DEVICENAME

Text

SERIALPREFS.UNIT

Numeric

SERIALPREFS.BITSPERCHAR

Numeric

The number of bits per transferred char. This can be either seven

or eight.

SERIALPREFS.PARITYMODE
NONE EVEN ODD MARK SPACE.

SERIALPREFS.STOPBITS
Numeric

The number of stop bits to be used. This can be either 0 or 1.

SERIALPREFS.HANDSHAKINGMODE
NONE RTSCTS RTSCTSDSR

SERIALPREFS.DUPLEXMODE
HALF FULL

SERIALPREFS.XONXOFF
Boolean

SERIALPREFS.HIGHSPEED
Boolean

SERIALPREFS.SHARED
Boolean

SERIALPREFS.STRIPBIT8
Boolean

SERIALPREFS.CARRIERCHECK
Boolean

SERIALPREFS.PASSXONXOFFTHROUGH
Boolean

SERIALPREFS.QUANTUM
Numeric

The MODEMPREFS object

Available fields are:

MODEMPREFS.MODEMINITTEXT
Text

MODEMPREFS.MODEMEXITTEXT
Text

MODEMPREFS.MODEMHANGUPTTEXT
Text

MODEMPREFS.DIALPREFIXTEXT
Text

MODEMPREFS.DIALSUFFIXTEXT
Text

MODEMPREFS.NOCARRIERTEXT

Text

MODEMPREFS.NODIALTONETEXT

Text

MODEMPREFS.CONNECTTEXT

Text

MODEMPREFS.VOICETEXT

Text

MODEMPREFS.RINGTEXT

Text

MODEMPREFS.BUSYTEXT

Text

MODEMPREFS.OKTEXT

Text

MODEMPREFS.ERRORTEXT

Text

MODEMPREFS.REDIALDELAY

Numeric

The redial delay in seconds

MODEMPREFS.DIALRETRIES

Numeric

MODEMPREFS.DIALTIMEOUT

Numeric

The dial timeout in seconds

MODEMPREFS.CONNECTAUTOBAUD

Boolean

MODEMPREFS.HANGUPDROPSDTR

Boolean

MODEMPREFS.REDIALAFTERHANGUP

Boolean

MODEMPREFS.NOCARRIERISBUSY

Boolean

MODEMPREFS.CONNECTLIMIT

Numeric

Time limit in minutes.

MODEMPREFS.CONNECTLIMITMACRO

Text

MODEMPREFS.TIMETOCONNECT

Numeric

The SCREENPREFS object

Available fields are:

SCREENPREFS.COLOURMODE
TWO FOUR EIGHT SIXTEEN

SCREENPREFS.FONTNAME
Text

SCREENPREFS.FONTSIZE
Numeric

SCREENPREFS.MAKESCREENPUBLIC
Boolean

SCREENPREFS.SHANGHAIWINDOWS
Boolean

SCREENPREFS.BLINKING
Boolean

SCREENPREFS.FASTERLAYOUT
Boolean

SCREENPREFS.TITLEBAR
Boolean

SCREENPREFS.STATUSLINEMODE
DISABLED STANDARD COMPRESSED

SCREENPREFS.USEPUBSCREEN
Boolean

SCREENPREFS.PUBSCREENNAME
Text

SCREENPREFS.ONLINEDISPLAY
TIME COST BOTH

The TERMINALPREFS object

Available fields are:

TERMINALPREFS.BELLMODE
NONE VISIBLE AUDIBLE BOTH SYSTEM

TERMINALPREFS.ALERTMODE
NONE BELL SCREEN BOTH

TERMINALPREFS.EMULATIONMODE
INTERNAL ATOMIC TTY EXTERNAL HEX

TERMINALPREFS.FONTMODE
STANDARD IBM IBMRAW

TERMINALPREFS.SENDCRMODE
IGNORE CR CRLF

TERMINALPREFS.SENDLFMODE
IGNORE LF LFCR

TERMINALPREFS.RECEIVECRMODE
IGNORE CR CRLF

TERMINALPREFS.RECEIVELFMODE
IGNORE LF LFCR

TERMINALPREFS.NUMCOLUMNS
Numeric

TERMINALPREFS.NUMLINES
Numeric

TERMINALPREFS.KEYMAPNAME
Text

TERMINALPREFS.EMULATIONNAME
Text

TERMINALPREFS.FONTNAME
Text

TERMINALPREFS.FONTSIZE
Numeric

The EMULATIONPREFS object

Available fields are:

EMULATIONPREFS.CURSORMODE
STANDARD APPLICATION

EMULATIONPREFS.NUMERICMODE
STANDARD APPLICATION

EMULATIONPREFS.CURSORWRAP
Boolean

EMULATIONPREFS.LINEWRAP
Boolean

EMULATIONPREFS.INSERTMODE
Boolean

EMULATIONPREFS.NEWLINEMODE
Boolean

EMULATIONPREFS.FONTSCALEMODE
NORMAL HALF

EMULATIONPREFS.SCROLLMODE

JUMP SMOOTH

EMULATIONPREFS.DESTRUCTIVEBACKSPACE
Boolean

EMULATIONPREFS.SWAPBSDELETE
Boolean

EMULATIONPREFS.PRINTERENABLED
Boolean

EMULATIONPREFS.ANSWERBACKTEXT
Text

EMULATIONPREFS.CLSRESETSCURSOR
Boolean

The CLIPBOARDPREFS object

Available fields are:

CLIPBOARDPREFS.UNIT
Numeric

CLIPBOARDPREFS.LINEDELAY
Numeric

Paste line delay in 1/100 seconds.

CLIPBOARDPREFS.CHARDELAY
Numeric

Paste character delay in 1/100 seconds.

CLIPBOARDPREFS.LINEPROMPTTEXT
Text

CLIPBOARDPREFS.SENDTIMEOUT
Numeric

Timeout in 1/100 seconds.

CLIPBOARDPREFS.TEXTPACING
DIRECT ECHO ANYECHO PROMPT DELAY KEYBOARD

CLIPBOARDPREFS.INSERTPREFIXTEXT
Text

CLIPBOARDPREFS.INSERTSUFFIXTEXT
Text

The CAPTUREPREFS object

Available fields are:

CAPTUREPREFS.LOGACTIONS
Boolean

CAPTUREPREFS.LOGFILENAME
Text

CAPTUREPREFS.LOGCALLS
Boolean

CAPTUREPREFS.CALLLOGFILENAME
Text

CAPTUREPREFS.MAXBUFFERSIZE
Numeric

CAPTUREPREFS.BUFFER
Boolean

CAPTUREPREFS.BUFFERSAVEPATH
Text

CAPTUREPREFS.CONNECTAUTOCAPTURE
Boolean

CAPTUREPREFS.AUTOCAPTUREDATE
NAME, INCLUDE

CAPTUREPREFS.CAPTUREFILTER
Boolean

CAPTUREPREFS.CAPTUREPATH
Text

CAPTUREPREFS.OPENBUFFERWINDOW
TOP, END

CAPTUREPREFS.REMEMBERBUFFERWINDOW
Boolean

CAPTUREPREFS.OPENBUFFERSCREEN
TOP, END

CAPTUREPREFS.REMEMBERBUFFERSCREEN
Boolean

CAPTUREPREFS.BUFFERSCREENPOSITION
LEFT, MID, RIGHT

CAPTUREPREFS.BUFFERWIDTH
Numeric

The COMMANDPREFS object

Available fields are:

COMMANDPREFS.STARTUPMACROTEXT
Text

COMMANDPREFS.LOGOFFMACROTEXT

Text

COMMANDPREFS.UPLOADMACROTEXT

Text

COMMANDPREFS.DOWNLOADMACROTEXT

Text

The MISCPREFS object

Available fields are:

MISCPREFS.PRIORITY

Numeric

MISCPREFS.BACKUPCONFIG

Boolean

MISCPREFS.OPENFASTMACROPANEL

Boolean

MISCPREFS.RELEASEDEVICE

Boolean

MISCPREFS.OVERRIDEPATH

Boolean

MISCPREFS.AUTOUPLOAD

Boolean

MISCPREFS.SETARCHIVEDBIT

Boolean

MISCPREFS.COMMENTMODE

IGNORE FILETYPE SOURCE

MISCPREFS.TRANSFERICONS

Boolean

MISCPREFS.CREATEICONS

Boolean

MISCPREFS.SIMPLEIO

Boolean

MISCPREFS.TRANSFERPERFMETER

Boolean

The PATHPREFS object

Available fields are:

PATHPREFS.ASCIIUPLOADPATH

Text

PATHPREFS.ASCIIDOWNLOADPATH

Text

PATHPREFS.TEXTUPLOADPATH
Text

PATHPREFS.TEXTDOWNLOADPATH
Text

PATHPREFS.BINARYUPLOADPATH
Text

PATHPREFS.BINARYDOWNLOADPATH
Text

PATHPREFS.CONFIGPATH
Text

PATHPREFS.EDITORNAME
Text

PATHPREFS.HELPPFILENAME
Text

The TRANSFERPREFS object

Available fields are:

TRANSFERPREFS.DEFAULTLIBRARY
Text

TRANSFERPREFS.ASCIIUPLOADLIBRARY
Text

TRANSFERPREFS.INTERNALASCIIUPLOAD
Boolean

TRANSFERPREFS.ASCIIDOWNLOADLIBRARY
Text

TRANSFERPREFS.INTERNALASCIIDOWNLOAD
Boolean

TRANSFERPREFS.QUIETTRANSFER
Boolean

TRANSFERPREFS.TEXTUPLOADLIBRARY
Text

TRANSFERPREFS.TEXTDOWNLOADLIBRARY
Text

TRANSFERPREFS.BINARYUPLOADLIBRARY
Text

TRANSFERPREFS.BINARYDOWNLOADLIBRARY
Text

The PROTOCOLPREFS object

This object features no fields, it contains a single line of text:
the XPR protocol options.

The TRANSLATIONPREFS object

Indices referring to the ascii codes range from 0 to 255, available
fields are:

TRANSLATIONPREFS.n.SEND
Text

TRANSLATIONPREFS.n.RECEIVE
Text

The FUNCTIONKEYPREFS object

Key indices range from 1 to 10 (representing F1 through F10),
available fields are:

FUNCTIONKEYPREFS.n
Text

FUNCTIONKEYPREFS.SHIFT.n
Text

FUNCTIONKEYPREFS.ALT.n
Text

FUNCTIONKEYPREFS.CONTROL.n
Text

The CURSORKEYPREFS object

Available fields are:

CURSORKEYPREFS.UPTTEXT
Text

CURSORKEYPREFS.RIGHTTEXT
Text

CURSORKEYPREFS.DOWNTEXT
Text

CURSORKEYPREFS.LEFTTEXT
Text

CURSORKEYPREFS.SHIFT.UPTTEXT
Text

CURSORKEYPREFS.SHIFT.RIGHTTEXT
Text

CURSORKEYPREFS.SHIFT.DOWNTEXT
Text

CURSORKEYPREFS.SHIFT.LEFTTEXT
Text

CURSORKEYPREFS.ALT.UPTEXT
Text

CURSORKEYPREFS.ALT.RIGHTTEXT
Text

CURSORKEYPREFS.ALT.DOWNTEXT
Text

CURSORKEYPREFS.ALT.LEFTTEXT
Text

CURSORKEYPREFS.CONTROL.UPTEXT
Text

CURSORKEYPREFS.CONTROL.RIGHTTEXT
Text

CURSORKEYPREFS.CONTROL.DOWNTEXT
Text

CURSORKEYPREFS.CONTROL.LEFTTEXT
Text

The FASTMACROPREFS object

FASTMACROPREFS.COUNT
Numeric

The number of fast macros available, entries range from
FASTMACROPREFS.0... to FASTMACROPREFS.n-1...

FASTMACROPREFS.n.NAME
Text

FASTMACROPREFS.n.CODE
Text

The HOTKEYPREFS object

Available fields are:

HOTKEYPREFS.TERMSCREENTOFRONTTEXT
Text

HOTKEYPREFS.BUFFERSCREENTOFRONTTEXT
Text

HOTKEYPREFS.SKIPDIAENTRYTEXT
Text

HOTKEYPREFS.ABORTAREXX
Text

HOTKEYPREFS.COMMODITYPRIORITY
Numeric

HOTKEYPREFS.HOTKEYSENABLED
Boolean

The SPEECHPREFS object

Available fields are:

SPEECHPREFS.RATE
Numeric

SPEECHPREFS.PITCH
Numeric

SPEECHPREFS.FREQUENCY
Numeric

SPEECHPREFS.SEXMODE
MALE FEMALE

SPEECHPREFS.VOLUME
Numeric

SPEECHPREFS.SPEECH
Boolean

The SOUNDPREFS object

Available fields are:

SOUNDPREFS.BELLNAME
Text

SOUNDPREFS.CONNECTNAME
Text

SOUNDPREFS.DISCONNECTNAME
Text

SOUNDPREFS.GOODTRANSFERNAME
Text

SOUNDPREFS.BADTRANSFERNAME
Text

SOUNDPREFS.RINGNAME
Text

SOUNDPREFS.VOICENAME
Text

SOUNDPREFS.PRELOAD
Boolean

The CONSOLEPREFS object

This object features no fields, it contains a single line of text:
the console output window specification.

The FILEPREFS object

Available fields are:

FILEPREFS.TRANSFERPROTOCOLNAME
Text

FILEPREFS.TRANSLATIONFILENAME
Text

FILEPREFS.MACROFILENAME
Text

FILEPREFS.CURSORFILENAME
Text

FILEPREFS.FASTMACROFILENAME
Text

1.64 termRexx.guide/Wanted!

Wanted!

As of this writing only a single example ARexx program is included in the 'term' distribution (see the Rexx drawer). However, it is desirable to include more sample programs so more users will be able to take advantage of the ARexx interface.

If you wish to share your programs with the 'term' user community, send them (including documentation) to:

Olaf Barthel
Brabeckstrasse 35
D-30559 Hannover

Federal Republic of Germany

Internet: olsen@sourcery.han.de

1.65 termRexx.guide/Index

Index

, (Comma)	Commands
, (Comma)	Commands
< > (Angle brackets)	Commands
<Option>/K	Commands
<Option>/M	Commands
<Option>/N	Commands
<Option>/S	Commands
<Parameter>/A	Commands
<Text>/F	Commands
{ } (Curly braces)	Commands
ACTIVATE	ACTIVATE
ADDITEM	ADDITEM
BAUD	BAUD
BEEPSCREEN	BEEPSCREEN
CALLMENU	CALLMENU
CAPTURE	CAPTURE
CAPTUREPREFS	Attributes
CLEAR	CLEAR
CLEARSCREEN	CLEARSCREEN

CLIPBOARDPREFS	Attributes
CLOSE	CLOSE
CLOSEDEVICE	CLOSEDEVICE
CLOSEREQUESTER	CLOSEREQUESTER
COMMANDPREFS	Attributes
CONSOLEPREFS	Attributes
CURSORKKEYPREFS	Attributes
DEACTIVATE	DEACTIVATE
DELAY	DELAY
DIAL	DIAL
Dial list	ADDITEM
Download list	ADDITEM
DUPLEX	DUPLEX
EMULATIONPREFS	Attributes
Example:	Commands
EXECTOOL	EXECTOOL
FASTMACROPREFS	Attributes
FAULT	FAULT
FILEPREFS	Attributes

Format :	Commands
FUNCTIONKEYPREFS	Attributes
GETATTR	GETATTR
GETCLIP	GETCLIP
HANGUP	HANGUP
HELP	HELP
HOTKEYPREFS	Attributes
MISCPREFS	Attributes
MODEMPREFS	Attributes
OPEN	OPEN
OPENDEVICE	OPENDEVICE
OPENREQUESTER	OPENREQUESTER
PARITY	PARITY
PASTECLIP	PASTECLIP
PATHPREFS	Attributes
PHONEBOOK	Attributes
PRINT	PRINT
PROTOCOL	PROTOCOL
PROTOCOLPREFS	Attributes

Purpose:	Commands
PUTCLIP	PUTCLIP
QUIT	QUIT
READ	READ
RECEIVEFILE	RECEIVEFILE
REDIAL	REDIAL
REMITEM	REMITEM
REQUESTFILE	REQUESTFILE
REQUESTNOTIFY	REQUESTNOTIFY
REQUESTNUMBER	REQUESTNUMBER
REQUESTRESPONSE	REQUESTRESPONSE
REQUESTSTRING	REQUESTSTRING
RESETSCREEN	RESETSCREEN
RESETSTYLES	RESETSTYLES
RESETTEXT	RESETTEXT
Result:	Commands
RX	RX
SAVE	SAVE
SAVEAS	SAVEAS

SCREENPREFS	Attributes
SELECTITEM	SELECTITEM
SEND	SEND
SEENDBREAK	SEENDBREAK
SENDFILE	SENDFILE
SERIALPREFS	Attributes
SETATTR	SETATTR
SOUNDPREFS	Attributes
SPEAK	SPEAK
Specifications:	Commands
SPEECHPREFS	Attributes
STOPBITS	STOPBITS
Template:	Commands
TERM	Attributes
TERMINALPREFS	Attributes
TEXTBUFFER	TEXTBUFFER
TIMEOUT	TIMEOUT
TRANSFERPREFS	Attributes
TRANSLATIONPREFS	Attributes

Upload list

ADDITEM

WAIT

WAIT

Wait list

ADDITEM

Warning:

Commands

WINDOW

WINDOW

[] (Square brackets)

Commands

| (Vertical bar)

Commands
