

**ch\_nfsc**

<b>COLLABORATORS</b>
----------------------

	<i>TITLE :</i> ch_nfsc		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		July 25, 2024	

<b>REVISION HISTORY</b>
-------------------------

NUMBER	DATE	DESCRIPTION	NAME

# Contents

<b>1</b>	<b>ch_nfsc</b>	<b>1</b>
1.1	ch_nfsc.guide	1
1.2	ch_nfsc.guide/COPYING	1
1.3	ch_nfsc.guide/DISCLAIMER	3
1.4	ch_nfsc.guide/Limitations	3
1.5	ch_nfsc.guide/Overview	5
1.6	ch_nfsc.guide/Requirements	6
1.7	ch_nfsc.guide/Installation	6
1.8	ch_nfsc.guide/ch_nfsmount	7
1.9	ch_nfsc.guide/ch_nfsc	8
1.10	ch_nfsc.guide/Parameters	8
1.11	ch_nfsc.guide/Common	9
1.12	ch_nfsc.guide/Less Common	10
1.13	ch_nfsc.guide/Special	10
1.14	ch_nfsc.guide/Tuning	11
1.15	ch_nfsc.guide/ARexxPort	12
1.16	ch_nfsc.guide/Debugging	12
1.17	ch_nfsc.guide/ch_nfscctl	13
1.18	ch_nfsc.guide/Examples	15
1.19	ch_nfsc.guide/FAQ	16
1.20	ch_nfsc.guide/Reporting Bugs	18
1.21	ch_nfsc.guide/Implementat. Notes	19
1.22	ch_nfsc.guide/Thanks	20
1.23	ch_nfsc.guide/History	21
1.24	ch_nfsc.guide/Concept Index	24

# Chapter 1

## ch\_nfsc

### 1.1 ch\_nfsc.guide

#### Preface

\*\*\*\*\*

This document describes the NFS client 'ch\_nfsc' Version 1.04 and related commands. It gives some general information and describes how to install and use it.

Some legal stuff. \* Read this before use \*.

COPYING	Copyright stuff.
DISCLAIMER	Use at your own risk.
Limitations	Known Bugs, problems and limitations.

#### In medias res.

Overview	Introductional information.
Requirements	What's required?
Installation	Short overview about installation.
ch_nfsmount	Usage information about 'ch_nfsmount'.
ch_nfsc	Information about 'ch_nfsc' arguments.
ch_nfscctl	Usage information about 'ch_nfscctl'.
Examples	Some example mounts.
FAQ	Questions and answers.
Reporting Bugs	How to reach the author.
Implementat. Notes	Information about implementation details.
Thanks	Many people helped, here's their hall of fame.
History	A look back.
Concept Index	Direct way do various concepts.

### 1.2 ch\_nfsc.guide/COPYING

#### Ch\_nfs client

\*\*\*\*\*

---

COPYING

=====

The files

bin/ch_chmod	bin/ch_die	bin/ch_mknod
bin/ch_nfsc	bin/ch_nfsctl	bin/ch_nfsmount
bin/ch_setowner		
db/ch_nfstab		
doc/ch_chmod.doc	doc/ch_die.doc	
doc/ch_mknod.doc	doc/ch_setowner.doc	
dvi/ch_nfsc.dvi	dvi/ch_nfsc_a4.dvi	
help/ch_nfsc	help/ch_nfsutil	

are

Copyright (C) 1993, 1994 Carsten Heyl  
All rights reserved.

The files

doc/showmount.doc  
showmount/showmount.8  
showmount/showmount.c

are

Copyright (C) 1993 Rick Sladkey <jrs@world.std.com>

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You may freely copy this archive as long as it's contents are left unmodified. This package is freely distributable, but still copyrighted by Carsten Heyl.

Permission is granted to include this package in Public-Domain collections, especially in Fred Fish's Amiga Disk Library (including CD ROM versions of it). The distribution file may be uploaded to Bulletin Board Systems or FTP servers. If you want to distribute this program you *must* use the original distribution archive.

Permission is granted to the AmiTCP/IP Group, Network Solutions Development Inc. to distribute the following files of 'ch\_nfsc' with 'AmiTCP/IP 4.0 demo' and 'Commercial AmiTCP/IP 4.0'.

bin/ch\_chmod, bin/ch\_die, bin/ch\_mknod, bin/ch\_nfsc,  
bin/ch\_nfsctl, bin/ch\_nfsmount, bin/ch\_setowner,  
db/ch\_nfstab, doc/ch\_chmod.doc, doc/ch\_die.doc,  
doc/ch\_mknod.doc, doc/ch\_setowner.doc, dvi/ch\_nfsc.dvi,  
dvi/ch\_nfsc\_a4.dvi, help/ch\_nfsutil, help/ch\_nfsc

---

## 1.3 ch\_nfsc.guide/DISCLAIMER

Information about warranty

=====

THIS CODE IS PROVIDED "AS IS" WITH NO WARRANTIES OF ANY KIND, EITHER EXPRESSED OR IMPLIED. THE ENTIRE RISK OF USING THIS CODE, PROGRAM OR INFORMATION IS ASSUMED BY THE USER. IN NO EVENT WILL THE AUTHOR BE LIABLE FOR ANY DAMAGES, DIRECT, INDIRECT, INCIDENTAL, SPECIAL OR CONSEQUENTIAL, RESULTING FROM USING THIS CODE, PROGRAM OR INFORMATION, EVEN IF HE (THE AUTHOR) HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

This program uses code from the Sun RPC 4.0 distribution containing the following note:

Sun RPC is a product of Sun Microsystems, Inc. and is provided for unrestricted use provided that this legend is included on all tape media and as a part of the software program in whole or part. Users may copy or modify Sun RPC without charge, but are not authorized to license or distribute it to anyone else except as part of a product or program developed by the user.

SUN RPC IS PROVIDED AS IS WITH NO WARRANTIES OF ANY KIND INCLUDING THE WARRANTIES OF DESIGN, MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, OR ARISING FROM A COURSE OF DEALING, USAGE OR TRADE PRACTICE.

Sun RPC is provided with no support and without any obligation on the part of Sun Microsystems, Inc. to assist in its use, correction, modification or enhancement.

SUN MICROSYSTEMS, INC. SHALL HAVE NO LIABILITY WITH RESPECT TO THE INFRINGEMENT OF COPYRIGHTS, TRADE SECRETS OR ANY PATENTS BY SUN RPC OR ANY PART THEREOF.

In no event will Sun Microsystems, Inc. be liable for any lost revenue or profits or other special, indirect and consequential damages, even if Sun has been advised of the possibility of such damages.

Sun Microsystems, Inc.  
2550 Garcia Avenue  
Mountain View, California 94043

## 1.4 ch\_nfsc.guide/Limitations

Known limitations, problems and bugs

=====

---

## Limitations

-----

1. Unix gids/uids > 0xFFFF will be mapped to <nobody> (0) on Amiga.
2. Filename parsing is a compromise between amiga and unix path usage.

Examples:

- 'dir1/../dir2' becomes 'dir1'
- 'dir1//dir2' becomes 'dir1'
- 'dir1/../../dir2' becomes ''
- 'dir1./dir2' becomes 'dir1/dir2'

This makes using some unix symbolic links possible but may lead to confusion if mixed syntax is used.

3. The following DOS packets (actions) for file handlers are not supported by 'ch\_nfsc':

'LOCK\_RECORD'

'FREE\_RECORD'

This can't be implemented with NFS alone. Possibly it can be implemented using the Lock Manager protocol via RPC. If someone is able to submit me any material about this protocol I may be able to support these.

'ADD\_NOTIFY'

'REMOVE\_NOTIFY'

Impossible via NFS if you're not the only user (correct me).

'SERIALIZE\_DISK'

Of any use for NFS?

## Problems

-----

1. Filename and directory parsing is done without regard to soft links. That means 'a/b/c/d///' will always give 'a/b' even if 'c' is a symbolic link pointing to another dir or even to file. The conversion will be done without even touching 'c' or 'd'.
2. Expect confusion when using '.' and '..' as normal filenames on the nfs handler.

## Known bugs

-----

1. As of version 1.02 'ch\_nfsc' will not return filenames longer than 30 characters on Examine() calls so they will be missing if listing directories on the NFS volume. This limit may be stretched to 106 characters using the 'LONG\_FILENAMES' option. But notice that this lead to crashes when using programs which can't deal with filenames of that length. One of these programs is the ASL Filerequester. There is currently no way to access or even list files with filename lengths exceeding 106 characters. I plan to

remove that limitation in the future by mapping long filenames to unique and shorter ones but don't expect that in the near future.

2. As of version 1.02 'ch\_nfsc' is able to use the credentials (uid, gid(s), umask) of the current user as set e.g. using the 'login' utility of 'AmiTCP'. Due to internal cache related restrictions of 'ch\_nfsc' a new user may be able to view filenames and file permissions of files he shouldn't have access to. He may be able to list the file's permission but he won't be able to access the file's contents.

For related information, see Implementat. Notes.

## 1.5 ch\_nfsc.guide/Overview

General introductional information

=====

This is a NFS client implementing NFS Version 2. You should be able to remote mount any partition exported by a Version 2 NFS server. 'AmiTCP' >= 3.0 is required to run this software.

This program or a previous version has been run on various kinds of machines ranging from A500, A1000, A2000, A3000 to A4000.

The main machines to test were:

- Machine/Processor,MHz/OS Version/AmiTCP Version/Link Hardware
- A3000/68040,35 MHz 68030,16 MHz/2.04/3.0/Clone NE2000 Ethernetcard via GoldenGate II bridgecard
- A3000/68030,25 MHz/2.1/3.0/Clone NE2000 Ethernetcard via Crosslink bridgecard

Tested NFS servers are:

- Interface(s)/Machine/OS
- Ethernet/Sparc clone running SunOS 4.1.1 NFS Server
- CSLIP, 14.4,.../Sun/SunOS 4.1.3 (CD-ROM)
- CSLIP, 14.4k,.../wuarchive:/archive
- CSLIP, 14.4k,.../Sun/SunOS
- Ethernet/386/Linux 0.99.14s
- Ethernet/Sparc-Station 2/Solaris 2.3
- ???/PC-Clone/DOS, SOSS 3.2
- Ethernet/486, 33 MHz/UHC SysV.4



- Ethernet/486DX2-66/FreeBSD V1.0.2
- CSLIP V2.6, 14.4k/Sun Sparc 10/SunOS 4.1.3
- Ethernet/DEC/Ultrix

(If you have problems with a special configuration, please tell, see Reporting Bugs.)

## 1.6 ch\_nfsc.guide/Requirements

Requirements  
=====

Hardware  
-----

The client should run on any Amiga. A minimum of 300 KBytes should be available to run a single client. If you plan to use multiple mounts at once think about making 'ch\_nfsc' resident, it should be pure. Around 110K is needed for stack (30000 Bytes) and code (ca. 80 KBytes). The stack size needed will hopefully be reduced in the future.

Software  
-----

'AmiTCP' >= 3.0 is required.

The NFS Server you want to mount must support NFS Version 2.0 which is currently most widely used.

## 1.7 ch\_nfsc.guide/Installation

Short installation guide  
=====

To use 'ch\_nfsc' you have to take the following steps:

1. Copy the binaries ('ch\_nfsc', 'ch\_nfsmount' , 'ch\_nfscclnt', ...) to a directory in your path, e.g. 'AmiTCP:bin'.
2. Create a file 'AmiTCP:db/ch\_nfstab'. This file contains information about the NFS volumes to mount, their local names and additional options, for all possible options see Parameters. Each line describes a different volume to mount. Lines containing a '#' will be ignored from '#' to the end of the line. The general structure is

```
<hostname>:<remote device> <local device> [<additional options>]
```

e.g.  
 nfsserver:/usr/users/ch nfs: user ch

For more examples see Examples.

3. Use 'ch\_nfsmount' to actually mount the specified volume, e.g.

```
ch_nfsmount nfs:
```

For details see ch\_nfsmount.

## 1.8 ch\_nfsc.guide/ch\_nfsmount

'ch\_nfsmount' usage information

=====

'Ch\_nfsmount' is used to actually mount a NFS partition on your amiga. It needs a file describing the machine to mount from ('host'), the directory/partition to mount ('remote device') and the name the partition is locally known as ('local device'). This file is normally 'AmiTCP:db/ch\_nfstab' but may be specified on the commandline, for examples see Examples. The argument template of 'ch\_nfsmount' is

```
DEVICE,ALL/S,LIST/S,VERBOSE/S,FROM/K,OPTIONS/F
```

Before you can mount a partition from a remote host, this host must export the partition. This is usually done with an entry in '/etc/exports'. If you don't trust this program you may export it read only.

'DEVICE'

The device to mount, this is the 'local device' as specified in the 'ch\_nfstab' file.

'ALL/S'

Mount all devices listed in the 'ch\_nfstab' file.

'LIST/S'

Do not mount a device but display the contents of the 'ch\_nfstab' file.

'VERBOSE/S'

Display the actual parameters as given to 'ch\_nfsc' when mounting a volume.

'FROM <alternative 'ch\_nfstab' file>'

Use an alternative 'ch\_nfstab' file.

'OPTIONS/F'

The rest of the line are legal options of 'ch\_nfsc' to specify e.g. the 'UMASK' or 'USER'. for details see ch\_nfsc.

## 1.9 ch\_nfsc.guide/ch\_nfsc

Information about 'ch\_nfsc' arguments.

=====

This section describes the arguments which may be given to 'ch\_nfsc' via 'ch\_fstab' or 'ch\_nfsmount'.

Parameters	Parameters overview.
Common	Common command line parameters.
Less common	Less common command line parameters.
Special	Special command line parameters.
Tuning	How to get more speed.
ARexxPort	The integrated ARexx port.
Debugging	How to help locating bugs.

## 1.10 ch\_nfsc.guide/Parameters

Parameters overview

-----

REMOTE_DEVICE/A	Host to mount from and device to mount.
LOCAL_DEVICE	Local device name.
USER/K	Explicit user for NFS requests.
UMASK	Explicit umask, used when creating files.
MNT_USER/K	User when mounting the partition.
MR	
MAX_READSIZE	Maximum number of data bytes used in RPC 'read'.
MD	
MAX_READDIRSIZE	Maximum number of data bytes used in RPC 'readdir'.
MW	
MAX_WRITESIZE	Maximum number of data bytes used in RPC 'write'.
B=BUFFERS	Initial number of 512 Byte buffers, default is 32.
ACTO	
ATTRCACHE_TIMEOUT	Timeout in seconds of cached attributes.
DCTO	
DIRCACHE_TIMEOUT	Timeout in seconds of cached dir entries.
RPCTO	
RPC_TIMEOUT	Maximum time to wait for RPC completion.
NO_TIMEOUTREQ/S	Don't use timeout requester.
SM/S	
SLOW_MEDIUM/S	Indicate 'using a slow transfer medium'.
ASYNC_RPC/S	Activate experimental asynchronous RPC.
LONG_FILENAMES/S	Set maximum filename length from 30 to 106 chars.

Debug version parameters

-----

DEBUG/K/N	Set debug level.
SERDEBUG/K/N	Set debug level, use serial port.
PARDEBUG/K/N	Set debug level, use parallel port.

## 1.11 ch\_nfsc.guide/Common

### Common command line parameters

---

#### 'REMOTE\_DEVICE/A'

Host and device to mount, template is '<hostname>:<devicename>',  
e.g. 'wuarchive.wustl.edu:/archive'  
Algorithm used to split: '<hostname><first ':'><devicename>'  
No further changes are made to these strings, they are used as got  
from the split above.

(Note: for some servers you may need to use 'host:dev:' or  
'host:dev:\'.')

#### 'LOCAL\_DEVICE'

Name the remote partition is locally known as, e.g. "wustl:".

#### 'USER/K'

Set explicit username used for later NFS requests. Default is the  
user belonging to the task doing the io request (see 'login'  
program of 'AmitTCP'). The name used must be a valid user listed in  
amitcp:db/passwd.

(Note: no passwd checking is done, so it's easy to fake a user)

#### 'UMASK/K/N'

Octal umask used for all NFS requests dealing with file/directory  
creation, this number is octal in standard unix notation. The  
template is 0<user mask><group mask><others mask> where <mask>  
consists of flags for read, write and execute in this order. If  
the corresponding umask bit is set the same file mode bit will be  
reset, e.g.

#### '0077'

Remove read/write/execute permission for group and others.

#### '0022'

Remove write permission for group and others Default is the  
umask belonging to the task doing the io request

#### 'BUFFERS/K/N'

Initial number of 512 Byte buffers, default is 32. The number of  
buffers may be changed using the command 'AddBuffers'.

#### 'NO\_TIMEOUTREQ/S'

Don't use timeout requester when encountering a RPC timeout but  
return an immediate error.

---

## 1.12 ch\_nfsc.guide/Less Common

Less common command line parameters

---

`'MNT_USER/K'`

User used when mounting the partition, default in unix notation:  
user root (0), group wheel (0) The name used must be a valid user  
listed in `amitcp:db/passwd`.

(Note: No `passwd` checking is done, so it's easy to fake a user.)

Debug versions only:

.....

`'DEBUG/N/K'`

Set debug level `n`, this number controls what information will be  
written to a log file `"t:nfsh.log_<Tasknumber>"`

- level 0: write all information
- level 1: write warnings and errors
- level 2: write only errors
- level 3: write no log messages at all default is level 2

`'SERDEBUG/K/N'`

Same as `'DEBUG'` but writes output to serial interface at 9600 baud  
if not caught.

`'PARDEBUG/K/N'`

Same as `'DEBUG'` but writes output to parallel interface.

(Note: Only one of `'DEBUG'`, `'SERDEBUG'` or `'PARDEBUG'` may be given on  
startup.)

## 1.13 ch\_nfsc.guide/Special

Special command line parameters (tuning and troubleshooting)

---

`'MR=MAX_READSIZE/K/N'`

`'MD=MAX_READDIRSIZE/K/N'`

`'MW=MAX_WRITESIZE/K/N'`

Defaults: 8192 bytes, for information when to use this, see FAQ.

`'ATTRCACHE_TIMEOUT/K/N'`

Maximum time to cache attributes (Default: 30 secs).

(Note: When mounting readonly devices on slow links (e.g. SLIP)  
you may set this to several minutes.)

`'DIRCACHE_TIMEOUT/K/N'`

---

Maximum time to cache directory structure (Default: 60 secs).

(Note: When mounting readonly devices on slow links (e.g. SLIP) you may set this to several minutes.)

`'SLOW_MEDIUM/S'`

Give the handler a hint that the medium used is a slow one. This is currently only used to use a different memory distribution between various buffers. It does not make much sense to use this Option alone. It should be accompanied with one of the 2 above.

`'RPC_TIMEOUT/K/N'`

Maximum time that must be passed before an RPC call is considered as "timed out" (default: 25 seconds).

(Note: Within this time the RPC call is retried every `RPC_TIMEOUT/5` seconds, on slow links (e.g. SLIP) you may set this to a higher value to reduce unnecessary retries.)

`'ASYNC_RPC/S'`

Activate experimental asynchronous RPC code. This should give some speed on some configurations, this will only have impact on reads or writes.

`'LONG_FILENAMES/S'`

Set the maximum filename length of filenames returned by `Examine()` from 30 to 106 chars. This may cause problems on some programs, see see Limitations.

## 1.14 ch\_nfsc.guide/Tuning

How to improve speed

-----

When designing the NFS Client I had fast links in mind (ethernet, ...) but a high degree of people seem to try to use it on slow links like SLIP on direct links and even over modems. Directory walks and listings may be very slow on these configurations. To get faster response time for successive directory accesses you may try to increase `'ATTRCACHE_TIMEOUT'` and `'DIRCACHE_TIMEOUT'` and activate `'SLOW_MEDIUM'`. They default to 30 resp. 60 seconds which may not be sufficient for modem links see Special :-). To increase cache size use `'addbuffers'`.

Currently the only way to flush these caches is to reduce cache memory via `'addbuffers'`. Beware that you may get old information when setting these values too high and other NFS Clients change files/directories on the same server you use or you may run low on memory!

If you mount a read-only volume (e.g. a CD-ROM) it should be possible to set these values to several minutes without problems. They may be set on startup of `'ch_nfsc'`, see Special, or via `'ch_nfscctl'`.

Another way one can try to improve read/write speed by using asynchronous RPC which may be enabled with ASYNC\_RPC on startup of 'ch\_nfsc', see Special, or via 'ch\_nfscctl'.

Please tell me about your experiences! see Reporting Bugs.

## 1.15 ch\_nfsc.guide/ARexxPort

The integrated ARexx port.

-----

'Ch\_nfsc' has an integrated ARexx port which may be used to set or query miscellaneous parameters. The port name is 'CH\_NFSC' followed by an unique number. All commands have the form 'SET <something> <value>' or 'GET <something>'. The command 'GET COMMANDS' may be used to get a list of all commands and whether they support get or set. For examples see source code of 'ch\_nfscctl.rexx'.

## 1.16 ch\_nfsc.guide/Debugging

How to help locating bugs

-----

'Ch\_nfsc' is able to log all its actions into a file  
't:nfsh.log\_<tasknumber>'.

This behaviour will be activated by one of the following:

- supplying 'DEBUG 0' on the commandline when starting 'ch\_nfsc'
- running 'ch\_nfscctl device: set\_debug 0' from the CLI

This will make all device accesses slow because a huge amount of data will be written to the log file.

Repeat your actions to reproduce the bug and make a copy of the log file after that. If you want to access the log file you need to shut off debugging so that 'ch\_nfsc' closes the log file. This can be done with

```
ch_nfscctl device: set_debug 3
```

After that you will be able to access the log file in t:.

(For alternatives See ch\_nfscctl.)

## 1.17 ch\_nfsc.guide/ch\_nfscctl

'ch\_nfscctl' usage information  
=====

'Ch\_nfscctl' is used to set/query various parameters of a running NFS client 'ch\_nfsc'. Since Version 0.007 it is an ARexx script. The communication is done via ARexx with port CH\_NFSC<number>.

The usage template in general is:

ch\_nfscctl <devicename> <arguments>

Currently supported commands: (Run 'ch\_nfscctl' without arguments for usage message.)

'GET\_ALL'

Display all actual settings.

'DIE'

Preliminary support for removing the handler from memory. The handler will refuse to remove itself from memory if open locks or file handles exist. In this case you will get a 'object in use' error.

\*Warning: It's possible to crash your machine with this command.\*

'FLUSH\_DEBUG'

This command will force the handler to flush all buffered debug data to the log file.

'SET\_DEBUG <debug level>'

Set new debug level, controls what to write into log file, possible values are

- level 0: write all information
- level 1: write warnings and errors
- level 2: write only errors
- level 3: write no log messages at all

'GET\_DEBUG'

Display current debug level.

'SET\_UMASK <new octal umask>'

Set umask to new value, e.g. 'SET\_UMASK 007' (for description of format see unix book or see ch\_nfsc).

'GET\_UMASK'

Get current setting of umask.

'SET\_USER'

Set effective user for NFS accesses to new value, e.g. 'SET\_USER root'.



(Note: No password checking is done, so it's easy to fake a user.)

`'GET_USER'`

Get information about current effective user for NFS accesses.

`'SET_MAX_READSIZE'`

`'SET_MR'`

`'GET_MAX_READSIZE'`

`'GET_MR'`

Set/get maximum number of bytes requested from the NFS server in one 'read' call. Possible values are from 256 to 8192, the default value is 8192.

`'SET_MAX_READDIRSIZE'`

`'SET_MD'`

`'GET_MAX_READDIRSIZE'`

`'GET_MD'`

Set/get maximum number of bytes requested from the NFS server in one 'readdir' call. Possible values are from 256 to 8192, the default value is 8192.

`'SET_MAX_WRITESIZE'`

`'SET_MW'`

`'GET_MAX_WRITESIZE'`

`'GET_MW'`

Set/get maximum number of bytes written to the NFS server in one 'write' call. Possible values are from 256 to 8192, the default value is 8192.

`'SET_WRITEBUFFERLIMIT'`

`'SET_WL'`

`'GET_WRITEBUFFERLIMIT'`

`'GET_WL'`

'ch\_nfsc' internally buffers data written to the handler (delayed write). This options sets/gets the maximum number of bytes of a single Write() getting buffered. Blocks longer than this number will never get buffered. Set this to 0 to disable write buffer.

`'SET_ATTRCACHE_TIMEOUT'`

`'SET_ACTO'`

`'GET_ATTRCACHE_TIMEOUT'`

`'GET_ACTO'`

Set/get maximum time in seconds a cached attribute will remain valid. The default value is 30 seconds.

`'SET_DIRCACHE_TIMEOUT'`

`'SET_DCTO'`

`'GET_DIRCACHE_TIMEOUT'`

`'GET_DCTO'`

Set/get maximum time in seconds a cached directory entry will remain valid. The default value is 60 seconds.

`'SET_RPC_TIMEOUT'`

`'SET_RPCTO'`

`'GET_RPC_TIMEOUT'`

`'GET_RPCTO'`

Set/get maximum time in seconds that must be passed before a RPC

call is considered as "timed out", The default value is 25 seconds. (On slow links (e.g. SLIP) you may set this to a higher value to reduce unnecessary timeouts and retries.)

(Note: Within this time the RPC call is retried every RPC\_TIMEOUT/5 seconds.)

```
'SET_TIMEOUTREQ <0 or 1>'
```

```
'SET_TR <0 or 1>'
```

```
'GET_TIMEOUTREQ'
```

```
'GET_TR'
```

Disable/enable timeout requester flag resp. query current setting.

```
'SET_SLOW_MEDIUM <0 or 1>'
```

```
'SET_SM <0 or 1>'
```

```
'GET_SLOW_MEDIUM'
```

```
'GET_SM'
```

Disable/enable slow medium flag resp. query current setting.

```
'SET_ASYNC_RPC <0 or 1>'
```

```
'SET_ARPC <0 or 1>'
```

```
'GET_ASYNC_RPC'
```

```
'GET_ARPC'
```

Disable/enable asynchronous RPC resp. query current setting.

#### Examples

-----

1. Change the effective user for NFS accesses to user 'ftp', the NFS partition is mounted as 'NFS:'.

```
ch_nfscctl NFS: set_user ftp
```

2. Query all settings.

```
ch_nfscctl NFS: get_all
```

## 1.18 ch\_nfsc.guide/Examples

Some examples

=====

Example 'AmiTCP:db/ch\_nfstab' file:

```
#
# REMOTE DEVICE, LOCAL DEVICE, OPTIONS/F
#

wuarchive.wustl.edu:/archive      wustl:
work-machine:/home                nfs-home: USER ch UMASK 0027
# Note: We assume that the archive below is read only.
wuarchive.wustl.edu:/archive      wustl-arc: ATTRCACHE_TIMEOUT 600 \
DIRCACHE_TIMEOUT 600
```

(Note: The '\\' above indicates that the full entry must be written in a single line.)

## Example 1

-----

Mount the directory `"/archive"` of host `"wuarchive.wustl.edu"` as local partition `"wustl:"`.

```
ch_nfsmount wustl:
```

## Example 2

-----

Mount the directory `"/home"` of host `"work-machine"` as local partition `"nfs-home:"`.

Do all NFS accesses (reading/writing/creating) as user `'ch'` using the group specified for `'ch'` in the `amitcp 'passwd'` file. Members of the same group as `'ch'` should be able to read or execute but not write the files we create but others should not get anything.

```
ch_nfsmount nfs-home:
```

## Example 3

-----

Do the same as Example 1 above but here we assume that the archive is read only so that raising cache timeouts will not harm.

```
ch_nfsmount wustl-arc:
```

## Example 4

-----

Do the same as Example 3 but over a slow line, e.g. a modem. This also shows how to add extra arguments via command line.

```
ch_nfsmount wustl-arc: slow_medium buffers 500
```

(Note: NFS is not the best choice when reading files over a slow line. I did some work to get better performance through local caches but you should use `'ftp'` or better `'ncftp'` for file transfers if possible.)

## 1.19 ch\_nfsc.guide/FAQ

Some questions and answers

=====

`'Q.1'`

Normal file and directory browsing is o.k. but some programs are really slow when accessing files via NFS.

`'A.1'`

Some programs do their IO (reads/writes) in very small pieces. The handler tries to buffer writes for files opened with `MODE_NEWFILE`

and tries to read ahead but if that's not possible each separate read or write action will result in the synchronous call of the read/write procedure on the NFS server. This is certainly slow but don't blame me for poorly written software. You may also try to increase the buffer memory used with 'addbuffers'. One of the programs that don't behave well when used on a NFS mounted partition is SAS/C 6.3. It does a lot of it's write IO doing Seek()/Write() pairs for small data portions.

'Q.2'

Everything else works o.k. but I always/sometimes get RPC Timeouts (Error code 1005) when

- a. listing large directories
- b. reading files > ca. 8K
- c. writing files > ca. 8K

'A.2'

Try to set the respective maximum transfer size as a startup option see Special or via 'ch\_nfscctl' see ch\_nfscctl.

'ethernet:'

Start with 1000 bytes and test that and if that's o.k. try to get more closer to the maximum possible number. Please report what you get!

'On slip lines:'

Start with 800 bytes.

'Reason:'

Try to avoid IP fragmentation, because your server/router(s) may have problems with this and in case of the loss of one piece the whole (fragmented) IP packet has to be re-transmitted. Another reason may be your local ethernet card being too slow. Try to get the SANA II statistics from it and look for overruns

'Q.5.'

'C:Type' works for me but some programs (e.g. less 1.6z) report 'not a regular file' and don't show the file contents.

'A.5.'

This problem needs further observation. My guess: These programs may have problems with extra permissions (group/other) returned by Examine().

'Q.6'

When I start the NFS Client I get an error code without any explanation.

'A.6.'

Ch\_nfsc should display an error requester before returning an error code. You may however suppress requesters by using a 'noreq' utility ore setting the \_NOREQ variable when using the 'csh'.

'Q.7'

---

I start 'ch\_nfsc' with debug option but 'list' lists a length of 0.

'A.7'

Due to speed considerations a big buffer is used when writing debug information into a file. Use the 'FLUSH\_DEBUG' option of 'ch\_nfscctl' to flush buffer, see ch\_nfscctl.

'Q.8'

When listing files or directories on NFS mounted volumes the Time is off a few hours.

'A.8'

Did you set the timezone environment variable 'TZ' to your correct timezone? But note that the value of 'TZ' is read when the NFS volume is mounted. So changing 'TZ' does not have impact on running NFS clients.

'Q.9'

When a listing a directory containing filenames beyond 30 resp. 106 characters these files are not listed.

'A.9'

For more information, see Limitations.

## 1.20 ch\_nfsc.guide/Reporting Bugs

How to reach the author.

=====

If you find a bug please send me a detailed report so I will be able to understand it and possibly reconstruct or reproduce and fix it. If possible send me a copy of the log-file see Debugging.

```
*****
* STOP *
*****
```

Before you send a mail please make sure it contains more than "Hey, I tested your program. But sometimes it does not function."

Just take the time to re-read your mail and try to answer the following:

1. Would YOU be able to get any useful information from YOUR mail?
2. Does it contain enough information about the used hardware/software and enough details on the problem?

If you think you supplied sufficient information please send it to me.

My current email address is ch@irb.informatik.uni-dortmund.de. If that's no longer valid you may try to reach me via snail mail:

Carsten Heyl  
 Unterer Markt 4  
 49477 Ibbenbueren  
 Germany

Feel free to add suggestions for improvements and the like ... I'm open to new ideas but can't make promises.

## 1.21 ch\_nfsc.guide/Implementat. Notes

General information about this implementation  
 =====

General  
 -----

First of all I hope you will find this program useful.  
 The RPC library used is based on Sun's RPC 4.0 distribution, see  
 DISCLAIMER. Prior to version 1.0 the RPC library used was ported by  
 Jarno Rajahalme <Jarno.Rajahalme@hut.fi>, a member of the AmiTCP group,  
 with some small changes by me. As of Version 1.0 of 'ch\_nfsc' the RPC  
 library as distributed with 'AmiTCP' 3.0 is used. The mount/nfs stubs  
 were generated by my port of the rpcgen program of the Sun TI  
 (Transport Independant) rpc distribution. That version of rpcgen should  
 be included in the 'AmiTCP' 3.0 distribution.

Implementation assumptions  
 -----

1. This NFS handler will only properly function with nfs servers  
 which use '.' and '..' for directory linking or emulate that  
 behaviour.
2. It is not legal to make a memory copy of a file lock for locks  
 obtained from this handler (doing this is considered illegal (see  
 'AmigaDOS Manual') but nevertheless done by some programs).
3. The Amiga FS's are case insensitive but Unix Filesystems are case  
 sensitive. The algorithm to find a file is currently as follows:
  - a. A lookup for exactly the given name is made.
  - b. If not succesful: A ReadDir is made on the given 'dir' and  
 the first (caseinsensitive) match will be found (if any).

Note that this may be slow on large directories, so avoid  
 different case if possible. The procedure above is only  
 necessary when opening or listing files, it is \*NOT\*  
 necessary for reads or writes on open files.

4. The nfs-server must support '..' as a name for parent directory  
 ('nfsproc\_lookup\_2(<dir-handle>, "..")' must return parent dir).

5. 'Lookup' fileid and 'getattr' fileid must match.

User/group ids on my amiga?

-----

As of AmigaOS 3.0 the amiga knows about user and group information for files. This includes information about extra protection bits for others and group and information about the owner (UID/GID) of a file. Since I could not find any public information about this I gathered all information from others' sources and from the 3.0 includes.

Here is the information I got. The amiga seems to use other defaults than unix so some remapping needs to be done:

'amiga'

```

UID 0      - user "nobody"
UID 1-65534 - normal user ids
UID 65535  - user "root"

GID 0      - group "nobody"
GID 1-65534 - normal group ids
GID 65535  - group "wheel"
```

'unix'

```

uid 0      - user "root"
uid 1-65534 - normal user ids
uid 65535  - user "nobody" (-1)

uid 0      - group "wheel"
uid 1-65534 - normal group ids
uid 65535  - group "daemon" (nobody, -1)
```

So the obvious conversions will be applied when necessary.

(Note: User/group id's from 'AmiTCP:db/passwd' resp. 'AmiTCP:db/group' will \*NOT\* be converted.)

What gets cached/buffered and how

-----

'Ch\_nfsc' does a caching of

- file/directory attributes (normally valid for 30 secs, see Tuning.)
- Some directory structure information (normally valid for 60 secs, see Tuning.)
- 'Write()'s' less or equal than WRITEBUFFERLIMIT (default: 16K) are buffered to reduce net use and increase speed for programs doing writes in small pieces.  
(Note: Only files opened with MODE\_NEWFILE will be write buffered)
- Small reads will be satisfied from a read buffer if possible.

## 1.22 ch\_nfsc.guide/Thanks

Thanks and acknowledgements  
=====

Lot's of people did their best to test this program and to locate bugs  
but as always:

\*Bugs will still remain, use at your own risk!\*

First I have to thank the AmiTCP group for porting a public  
available TCP/IP stack to the amiga and for answering  
questions/locating bugs. Without their effort I wouldn't had even think  
about writing this software.

Members of the group are Tomi Ollila <Tomi.Ollila@hut.fi>, Pekka  
Pessi <Pekka.Pessi@hut.fi>, Markus  
Peuhkuri <Markus.Peuhkuri@hut.fi> and Jarno  
Rajahalme <Jarno.Rajahalme@hut.fi> .

Thanks go to the following for their help in reporting and locating  
bugs and problems and sending information and suggestions: (I hope I  
didn't miss one.)

Stefan G. Berg, Kenneth Scott Bethke, Mike Bond, Joe Elliot, Michael  
D. Fischer, Peter Haumer, Joerg Cyril Hoehle, Holger Hofstaette, Arve  
Hjoennevaag, Oliver Huf, Kim-Minh Kaplan, Lee S. Kilpatrick, Magnus  
Lilja, Charles Macmillan, Rudolf Neuhaus, Clive Nicolson, Ross  
Niebergall, Stephen Norris, Timo Rossi, K. Raquel Sanborn, Matthias  
Scheler, Barnon "Barry" Tigner, Christian Wolf

Thanks go to Randell Jesup and Chris Hooper for answering questions  
and sending information about special DOS packets.

Thanks go to Ralph Babel for his book 'The Amiga Guru Book' and the  
information parts of his mails.

(Even if I don't like the index of that book it's very useful to get  
information not found anywhere else.)

Special thanks go to Marcus Kommnick for his help and patience in  
testing various hardware and software components sometimes with life  
spawns of few minutes :-)) and for cross-reading the documentation.

## 1.23 ch\_nfsc.guide/History

History  
=====

'1.04'

\* Updated/modified for AmiTCP 4.0

\* All stuff compiled with SAS/C 6.51 now.

\* ch\_nfsmount now checks for resident ch\_nfsc (thanks to Peter

---



Haumer)

'1.02BETA'

- \* too long filenames are skipped on examine now (see known bugs)
- \* introduced LONG\_FILENAMES parameter (106 characters instead of 30)
- \* added AmiTCP3.0b2 usergroup support (no need to set USER/UMASK anymore, setting USER/UMASK via startup option disables this feature)
- \* fixed EXAMINE\_ALL bug returning wrong error code and wrong filename lengths
- \* added ED\_OWNER support to EXAMINE\_ALL
- \* ch\_nfsmount sets stack for client now (thanks to Joerg Cyril Hoehle)
- \* small bug fixes (dir cache, GET\_WL/GWT\_MW, read-only flag)

'1.01BETA'

- \* fixed bug when writing 0 bytes
- \* fixed 2 bugs in buffer stuff (these might lead to data loss!)
- \* recognizing timezone now
- \* make shutting off ASYNC\_RPC true

'1.0BETA'

- \* AMITCP 3.0
- \* async support
- \* ch\_nfsmount: fix fstab parsing bug, test for device/volume before mounting now
- \* added ARexx port, added short parameters
- \* some small fixes

'0.007'

- \* internal version

'Version 0.006 (BETA)'

- \* fixed wrong assertion if early mount failure
  - \* re-activated "invalid argument" requester
  - \* fixed time conversion bug
-

- \* fixed ch\_nfsmount bug if ALL option was used (may crash machine/process)
- \* fixed freed memory reference if illegal passwd entry
- \* fixed timer problem when mount failed

'Version 0.005 (BETA)'

- \* fixed memory leaks in Lock(), dir\_DelEntry(), CBuildFullName(), do\_act\_Parent()
- \* fixed 2 subtle/serious memory bugs filename handling stuff
- \* added file type check to READ\_LINK
- \* fixed delete/write mapping of SetProtection
- \* located FComp problem, packet arguments were modified, fixed now
- \* (rough) memory limit is now adjustable via AddBuffers
- \* added preliminary die support (use at your own risk)
- \* added SLOWMEDIUM hint
- \* mapped Amiga "nobody"/"nogroup" to unix "-1"
- \* amiga guide doc's

'Version 0.004 (BETA)'

- \* special BETA release
- \* some minor memory enhancements
- \* added serial/parallel debug options
- \* action CURRENT\_VOLUME supported now
- \* find\_update: make error message if open on non-file ffs like

'Version 0.003 (BETA)'

- \* third release, to BETA testers only
  - \* added RPCTimeout parameter
  - \* changed ch\_nfscctl to ReadArgs()
  - \* hopefully fixed assign-bug
  - \* some speedup to dir cache lookup
  - \* added read ahead buffer
  - \* made error conversion context sensitive -> better error reporting
-

```
* Requester now shows programname instead of "Background CLI"

* main(): Added explicit stack size check on startup

* some documentation fixes

* added a timer for automatic buffer/cache flushes

`Version 0.002 (BETA)`
  * second release, to BETA testers only

  * added some support for slow lines (see Tuning)

  * much more configuration parameters (too much?)

  * Read(): avoid extra nfs call on EOF

  * Lock(): fixed error reporting bug ("not found" was reported
    as "out of memory")

  * return volumename on root lock now (thanks to Timo Rossi)

  * fixed serious memory bug in FIND_OUTPUT if second open on
    exclusive          write is tried

  * fixed path parsing bug (a leading "/" is now always found and
    considered illegal)

  * fixed path parsing bug regarding "..", "/".." is now
    identical to amiga notation "/"

  * improved detection of illegal FIB contents presented to
    ExNext()

  * added write buffer for small write speedup

  * added debug parameters for maximal read/write/readdir size

  * minor changes/fixes

  * fixed error reporting bug (most RPC errors were reported as
    "out of memory" in 0.001)

  * added RPC Timeout requester

`Version 0.001 (BETA)`
  * first public release
```

## 1.24 ch\_nfsc.guide/Concept Index

Concept Index

\*\*\*\*\*

---

ch\_nfstab  
Author  
DISCLAIMER  
Debugging  
Installation  
Questions and answers.  
Thanks  
Timezone  
Tuning  
UMask

Installation  
Reporting Bugs  
DISCLAIMER  
Debugging  
Installation  
FAQ  
Thanks  
FAQ  
Tuning  
Common