



Help for PerCnt

[Properties](#)

[Events](#)

Registration Information

Order Form

Getting Custom Controls Written

Description

PerCnt is a Visual Basic custom control that makes status (percentage) bar display easy.

File Name

PERCNT2.VBX

Object Type

Percent

Distribution Note When you develop and distribute an application that uses PerCnt, you should install the file PERCNT2.VBX into the users Windows SYSTEM directory. PerCnt has version information built into it. So, during installation, you should ensure that you are not overwriting a newer version of PerCnt.

Properties

All of the properties that apply to this control are in this table. Properties that have special meaning for this control or that only apply to this control are marked with an asterisk (*).

<u>BackColor</u>	<u>FontItalic</u>	<u>Name</u>
<u>*BevelBar</u>	<u>FontName</u>	<u>Parent</u>
<u>*BevelInner</u>	<u>FontSize</u>	<u>*Percent</u>
<u>*BevelOuter</u>	<u>FontStrikethru</u>	<u>Tag</u>
<u>*BevelWidthBar</u>	<u>FontUnderline</u>	<u>*TextBackColor</u>
<u>*BevelWidth</u>	<u>ForeColor</u>	<u>*TextForeColor</u>
<u>*Border</u>	<u>Height</u>	<u>*ThreeD</u>
<u>*BorderWidth</u>	<u>hWnd</u>	<u>Top</u>
<u>Enabled</u>	<u>Index</u>	<u>Visible</u>
<u>FontBold</u>	<u>Left</u>	<u>Width</u>

Percent is the default value for the control.

BevelBar Property

[See Also](#)

[Example](#)

Description

Determines the 3-D style of the percentage bar.

Usage

*[form.]***BevelBar** [= *integer*]

Remarks

The value of this property determines the style of the percentage bar. If the [ThreeD](#) property is set to False, this property is ignored. This property may be one of four values:

Value	Description
0	Normal bar
1	Raised percentage bar (3-D)
2	Inset percentage bar (3-D)
3	Lowered percentage bar (3-D)

Data Type

Integer (enumerated)

See Also

Properties:

[BevelInner](#)

[BevelOuter](#)

[BevelWidthBar](#)

[Percent](#)

[ThreeD](#)



Bevel Example

In this example, the program will styles of the bevels used. To try this example, paste the code into the Declarations section of a form that contains a four horizontal scroll bars (one for BevelBar, one for BevelInner, and one for BevelOuter, and one to control the percentage bar), three labels (which show the properties), and a PerCnt control. Press F5. Play with the scroll bars to see things change.

```
Sub Form_Load ()
    Me.BackColor = RGB(192, 192, 192)

    HScroll11.Value = 0
    HScroll11.Min = 0
    HScroll11.Max = 3

    HScroll12.Value = 0
    HScroll12.Min = 0
    HScroll12.Max = 3

    HScroll13.Value = 0
    HScroll13.Min = 0
    HScroll13.Max = 3

    HScroll14.Value = 50
    HScroll14.Min = 0
    HScroll14.Max = 100

    Percent1.BorderWidth = 3
    Percent1.BevelWidth = 2
    Percent1.BevelWidthBar = 2
    Percent1.ThreeD = True
    Percent1.BackColor = RGB(192, 192, 192)

    Call HScroll11_Change
    Call HScroll12_Change
    Call HScroll13_Change
    Call HScroll14_Change
End Sub

Sub HScroll11_Change ()
    Percent1.BevelBar = HScroll11.Value
    Label1.Caption = "BevelBar:" & Format$(HScroll11.Value)
End Sub

Sub HScroll11_Scroll ()
    Call HScroll11_Change
End Sub

Sub HScroll12_Change ()
    Percent1.BevelInner = HScroll12.Value
    Label2.Caption = "BevelInner:" & Format$( HScroll12.Value )
End Sub

Sub HScroll12_Scroll ()
    Call HScroll12_Change
End Sub
```

```
Sub HScroll3_Change ()
    Percent1.BevelOuter = HScroll3.Value
    Label3.Caption = "BevelOuter:" & Format$( HScroll3.Value )
End Sub
```

```
Sub HScroll3_Scroll ()
    Call HScroll3_Change
End Sub
```

```
Sub HScroll4_Change ()
    Percent1.Percent = HScroll4.Value
End Sub
```

```
Sub HScroll4_Scroll ()
    Call HScroll4_Change
End Sub
```

BevelInner Property

[See Also](#)

[Example](#)

Description

Determines the 3-D style of the border immediately surrounding the percentage area.

Usage

[*form.*][*control.*]**BevelInner**[= *integer*]

Remarks

The value of this property determines the style of the percentage bar's border. If the [ThreeD](#) property is set to False, this property is ignored. This property may be one of four values:

Value	Description
0	Normal frame
1	Raised frame (3-D)
2	Inset frame (3-D)
3	Lowered frame (3-D)

Data Type

Integer (enumerated)

See Also

Properties:

[BevelBar](#)

[BevelOuter](#)

[BevelWidth](#)

[BorderWidth](#)

[ThreeD](#)

BevelOuter Property

[See Also](#)

[Example](#)

Description

Determines the 3-D style of the border (if any) surrounding the control.

Usage

[*form.*][*control.*]**BevelWidth**[= *integer*]

Remarks

The value of this property determines the style of the control's border. If the [ThreeD](#) property is set to False, this property is ignored. This property may be one of four values:

Value	Description
0	Normal frame
1	Raised frame (3-D)
2	Inset frame (3-D)
3	Lowered frame (3-D)

Data Type

Integer (enumerated)

See Also

Properties:

[BevelBar](#)

[BevelInner](#)

[BevelWidth](#)

[BorderWidth](#)

[ThreeD](#)

BevelWidth Property

[See Also](#)

[Example](#)

Description

Determines the width of the inner and outer borders (bevels).

Usage

*[form.]***BevelWidth** [= *integer*]

Remarks

The value of this property determines the width of the inner border (if any, see [BevelInner](#)) and the outer border (if any, see [Border](#) and [BevelOuter](#)). This is always measured in pixels.

Data Type

Integer

See Also

Properties:

[BevelInner](#)

[BevelOuter](#)

[Border](#)

[BorderWidth](#)



Width Properties Example

In this example, the program will vary the width of bevels. To try this example, paste the code into the Declarations section of a form that contains four horizontal scroll bars, three labels, and a PerCnt control (make this control wide). Press F5. Play with the scroll bar to see things change.

```
Sub Form_Load ()
    HScroll11.Value = 2
    HScroll11.Min = 0
    HScroll11.Max = 10

    HScroll12.Value = 2
    HScroll12.Min = 0
    HScroll12.Max = 10

    HScroll13.Value = 2
    HScroll13.Min = 0
    HScroll13.Max = 10

    HScroll14.Value = 50
    HScroll14.Min = 0
    HScroll14.Max = 100

    Percent1.BevelInner = 1
    Percent1.BevelOuter = 3
    Percent1.BevelBar = 3
    Percent1.Percent = 50

    Call HScroll11_Change
    Call HScroll12_Change
    Call HScroll13_Change
End Sub

Sub HScroll11_Change ()
    Percent1.BevelWidth = HScroll11.Value
    Label1.Caption = "BevelWidth:" & Format$( HScroll11.Value )
End Sub

Sub HScroll11_Scroll ()
    Call HScroll_Change
End Sub

Sub HScroll12_Change ()
    Percent1.BevelWidthBar = HScroll12.Value
    Label2.Caption = "BevelWidthBar:" & Format$( HScroll12.Value )
End Sub

Sub HScroll12_Scroll ()
    Call HScroll12_Change
End Sub

Sub HScroll13_Change ()
    Percent1.BevelWidthBar = HScroll13.Value
    Label3.Caption = "BorderWidth:" & Format$( HScroll13.Value )
End Sub
```

```
Sub HScroll3_Scroll ()  
    Call HScroll3_Change  
End Sub
```

```
Sub HScroll4_Change ()  
    Percent1.Percent = HScroll4.Value  
End Sub
```

```
Sub HScroll4_Scroll ()  
    Call HScroll4_Change  
End Sub
```

BevelWidthBar Property

[See Also](#)

[Example](#)

Description

Determines the width of the 3-D effect (if any) of the percentage bar.

Usage

*[form.]***BevelWidthBar** [= *integer*]

Remarks

The value of this property determines the width of the 3-D effect (if any, see [BevelBar](#)). This is always measured in pixels.

Data Type

Integer

See Also

Properties:

[BevelBar](#)

[ThreeD](#)

Border Property

[See Also](#)

[Example](#)

Description

Determines whether or not there is a border around the control.

Usage

[*form.*][*control.*]**Border**[= *integer*]

Remarks

The value of this property determines whether or not the control has a border. This property may be one of two values:

Value	Description
0	No border
1	Single width border

Data Type

Integer (enumerated)

See Also

Properties:

[BevelOuter](#)

[ThreeD](#)



Border and ThreeD Properties Example

In this example, the program will vary the width of the bars. To try this example, paste the code into the Declarations section of a form that contains two check boxes, two labels, and a PerCnt control (make this control wide). Press F5. Play with the check boxes to see things change.

```
Sub Form_Load ()
    Check1.Value = 0
    Check2.Value = 0

    Percent1.BevelInner = 3
    Percent1.BevelOuter = 3
    Percent1.BevelBar = 3
    Percent1.BevelWidth = 2
    Percent1.BevelWidthBar = 2
    Percent1.BorderWidth = 3

    Call Check1_Change
    Call Check2_Change
End Sub

Sub Check1_Change ()
    Percent1.Border = Check1.Value
    If Check1.Value <> 0 Then
        Label1.Caption = "Border"
    Else
        Label1.Caption = "No Border"
    End If
End Sub

Sub Check2_Change ()
    Percent1.ThreeD = Check2.Value
    If Check2.Value <> 0 Then
        Label2.Caption = "ThreeD"
    Else
        Label2.Caption = "No NoThreeD"
    End If
End Sub
```

BorderWidth Property

[See Also](#)

[Example](#)

Description

Determines the distance between the inner border and the outer border.

Usage

[*form.*][*control.*]**BorderWidth**[= *integer*]

Remarks

The value of this property determines the distance between the outer border (if any, see [Border](#) and [BevelOuter](#)) and the inner border (if any, see [BevelInner](#)). This is always measured in pixels.

Data Type

Integer

See Also

Properties:

[BevelInner](#)

[BevelOuter](#)

[ThreeD](#)

Percent Property

[See Also](#)

[Example](#)

Description

Sets the value of the status (percentage) bar.

Usage

[form.][*control.*]**Percent**[= *integer*]

Remarks

This property determines how much of the status (percent) bar is full and what value is displayed in the center of the box. This property can range from 0 to 100.

This property is the default value of the control.

Data Type

Integer

See Also

Properties:

[BevelBar](#)

[BevelWidthBar](#)



Percent Property Example

In this example, the program will show the percentage bar going up and down. To try this example, paste the code into the Declarations section of a form that contains two command buttons and a PerCnt control. Press F5. Play with the buttons.

```
Sub Form_Load ()
    Command1.Caption = "Up"
    Command2.Caption = "Down"
End Sub
```

```
Sub Command1_Click ()
    Dim I As Integer

    For I = 0 To 100
        Percent1.Percent = I
    Next I
End Sub
```

```
Sub Command2_Click ()
    Dim I As Integer

    For I = 100 To 0 Step -1
        Percent1.Percent = I
    Next I
End Sub
```

TextBackColor Property

[See Also](#)

Description

Sets the color of the text when it's in the background.

Usage

*[form.]***TextBackColor** [= *color*]

Remarks

This property determines what color the text is when it's on the right side of the percentage bar.

Data Type

Color

See Also

Properties:

[Percent](#)

[TextForeColor](#)

TextForeColor Property

[See Also](#)

Description

Sets the color of the text when it's in the foreground.

Usage

`[form.][control.]TextForeColor[= color]`

Remarks

This property determines what color the text is when it's on the left side of the percentage bar (i.e., contained within it).

Data Type

Color

See Also

Properties:

[Percent](#)

[TextBackColor](#)

ThreeD Property

[See Also](#)

[Example](#)

Description

Determines whether or not 3-D effects are used.

Usage

*[form.]***ThreeD** [= *boolean*]

Remarks

If this property is set to False, all of the Bevel and Border description properties are ignored. In this case, PerCnt either draws a plain, thin border, or nothing at all (this depends on the [Border](#) property).

If this property is set to True (the default), all of the properties affect the appearance of PerCnt.

Data Type

Integer (boolean)

See Also

Properties:

[BevelBar](#)

[BevelInner](#)

[BevelOuter](#)

[BevelWidth](#)

[BevelWidthBar](#)

[Border](#)

[BorderWidth](#)

Events

All of the events that apply to this control are in this table. Events that have special meaning for this control or that only apply to this control are marked with an asterisk (*).

Click

DbClick

Registration Information

Credits

PerCnt was written by James Shields. Inquiries can be sent to 71231,2066 on CompuServe, or mabry@halcyon.com on Internet. If you must send something via U.S. Mail, the address is:

Mabry Software
Post Office Box 31926
Seattle, WA 98103-1926

Registration

You can register this program by sending \$10 (\$12 for international orders) and your address. CompuServe members may register by sending \$5 and their account number (the registered version will be E-mailed to you). CompuServe members may also register this package by going to the SWREG forum. PerCnt is registered there. PerCnts registration ID number is 966.

For your convenience, an [order form](#) has been provided that you can print out directly from help.

Source Code and Registration

Source code (which includes a registered copy) to this control is available for \$25 (\$30 for international orders). With source code you get a registered version of the control. If you are a CompuServe member, you may get the source code in the Software Registration forum (GO SWREG) for \$20. It's registration number is 1004.

Credit Card Orders

You can order this program with Mastercard, Visa, American Express, or Discover from Public (software) Library by calling 800-2422-PsL or 713-524-6394 or by FAX to 713-524-6398 or by CompuServe E-mail to 71355,470. You can also mail credit card orders to PsL at Post Office Box 35705; Houston, TX 77235-5705. THESE NUMBERS ARE FOR CREDIT CARDS ONLY.

PerCnt's ID number for this service is 11100. This is good for both the normal registered version, and the source code version.

Any questions about the status of the shipment of the order, refunds, registration options, product details, technical support, volume discounts, dealer pricing, site licenses, etc., must be directed to Mabry Software at 206-634-1443 or FAX at 206-632-0272.

To ensure that you get the latest version, PsL will notify us the day of your order and we will ship the product directly to you.

© Copyright 1993-1994 by James Shields





PerCnt Order Form

Use the Print Topic.. command from the File menu to print this order form.

Mail this form to: Mabry Software
 Post Office Box 31926
 Seattle, WA 98103-1926
 Phone: 206-634-1443
 Fax: 206-632-0272
 BBS: WinDev BBS 206-634-0783
 CompuServe: 71231,2066
 Internet: mabry@halcyon.com

Where did you get this copy of PerCnt?

Ship to:

Phone:

Fax:

E-Mail:

Disk Size: (circle one) 3½ 5¼

qty ordered _____ REGISTRATION
 \$10 each, postpaid (check or money order in hard currency). Foreign addresses add \$2.00 shipping. No additional shipping charges to Canada or Mexico.

qty ordered _____ SOURCE CODE AND REGISTRATION
 \$25 each, postpaid (check or money order in hard currency). Foreign addresses add \$5.00 shipping. No additional shipping charges to Canada or Mexico.

Getting Custom Controls Written

If you or your organization would like to have custom controls written, you can contact me at the following:

James Shields
Mabry Software
Post Office Box 31926
Seattle, WA 98103-1926
Phone: 206-634-1443
Fax: 206-632-0272
BBS: WinDev BBS 206-634-0783
CompuServe: 71231,2066
Internet: mabry@halcyon.com

