

Manuál PHP

Stig Sæther Bakken

Alexander Aulbach

Egon Schmid

Jim Winstead

Lars Torben Wilson

Rasmus Lerdorf

Andrei Zmievski

Jouni Ahto

Sestavil

Stig Sæther Bakken

Egon Schmid

27-04-2002

Copyright © 1997, 1998, 1999, 2000, 2001, 2002 PHP Documentation Group

Copyright

Tento manuál je © Copyright 1997, 1998, 1999, 2000, 2001, 2002 by the PHP Documentation Group. Seznam členů této skupiny je na titulní straně tohoto manuálu.

Tento manuál lze redistribuovat podle podmínek GNU General Public License publikované Free Software Foundation; buď verzí 2 této Licence, nebo (dle vašeho uvážení) kterékoliv pozdější verze.

Manuál PHP

Stig Sæther Bakken, Alexander Aulbach, Egon Schmid, Jim Winstead, Lars Torben Wilson, Rasmus Lerdorf, Andrei Zmievski a Jouni Ahto

Sestavil Stig Sæther Bakken

Sestavil Egon Schmid

Vydáno 27-04-2002

Copyright © 1997, 1998, 1999, 2000, 2001, 2002 PHP Documentation Group

Copyright

Tento manuál je © Copyright 1997, 1998, 1999, 2000, 2001, 2002 by the PHP Documentation Group. Seznam členů této skupiny je na titulní straně tohoto manuálu.

Tento manuál lze redistribuovat podle podmínek GNU General Public License publikované Free Software Foundation; buď verzi 2 této Licence, nebo (dle vašeho uvážení) kterékoliv pozdější verze.

Obsah

Úvod	i
About this Manual.....	i
I. Začínáme	1
1. Introduction	1
What is PHP?.....	2
What can PHP do?	2
2. Instalace	5
General Installation Considerations	6
Unix/HP-UX installs	6
Unix/Linux installs	8
Using Packages	8
Unix/Mac OS X installs.....	8
Using Packages	8
Compiling for OS X server.....	8
Compiling for MacOS X client.....	10
Unix/OpenBSD installs	10
Using Ports.....	11
Using Packages	11
Unix/Solaris installs.....	11
Required software	11
Using Packages	12
Installation on UNIX systems	12
Apache Module Quick Reference.....	12
Building	13
Installation on Windows systems	13
Windows InstallShield	13
Manual Installation Steps.....	14
Building from source	16
Preparations.....	16
Putting it all together	17
Compiling.....	18
Installation of Windows extensions	18
Servers-CGI/Commandline	20
Testing.....	20
Benchmarking	21
Servers-Apache.....	21
Details of installing PHP with Apache on Unix	21
Installing PHP on Windows with Apache 1.3.x.....	24
Servers-Caudium	25
Servers-fhttpd	25
Servers-IIS/PWS.....	26
Windows and PWS/IIS 3	26
Windows and PWS 4 or newer	27
Windows NT/2000/XP and IIS 4 or newer	27
Servers-Netscape and iPlanet	28
Installing PHP with Netscape on Sun Solaris	28
Installing PHP with Netscape on Windows	31
Servers-OmniHTTPd Server	32
OmniHTTPd 2.0b1 and up for Windows	32

Servers-Oreilly Website Pro	33
Oreilly Website Pro 2.5 and up for Windows	33
Servers-Xitami.....	33
Xitami for Windows.....	33
Servers-Other web servers.....	34
Problems?	34
Read the FAQ.....	34
Other problems.....	34
Bug reports.....	34
Complete list of configure options	34
Configure Options in PHP 4	35
Database options	35
Graphics options.....	38
Misc options	39
PHP options.....	45
Server options.....	46
XML options	47
3. Configuration	48
The configuration file	49
General Configuration Directives	50
Safe Mode Configuration Directives.....	55
Debugger Configuration Directives	55
Extension Loading Directives	55
mSQL Configuration Directives	56
Postgres Configuration Directives	56
SESAM Configuration Directives.....	56
Sybase Configuration Directives.....	57
Sybase-CT Configuration Directives	57
Informix Configuration Directives.....	58
BC Math Configuration Directives	59
Browser Capability Configuration Directives	59
Multi-Byte String Configuration Directives	59
Exif Configuration Directives	60
4. Security	61
General considerations	62
Installed as CGI binary	62
Possible attacks	63
Case 1: only public files served	63
Case 2: using --enable-force-cgi-redirect.....	63
Case 3: setting doc_root or user_dir	64
Case 4: PHP parser outside of web tree	64
Installed as an Apache module	65
Filesystem Security	65
Database Security	67
Designing Databases.....	68
Connecting to Database	68
Encrypted Storage Model	68
SQL Injection.....	69
Avoiding techniques	72
Error Reporting.....	73
Using Register Globals.....	74
User Submitted Data.....	76

Hiding PHP	76
Keeping Current	77
II. Reference jazyka	78
5. Základní syntaxe	78
Opuštění HTML	79
Oddělování instrukcí	79
Komentáře	79
6. Types	81
Introduction	82
Booleans	82
Syntax	82
Converting to boolean	83
Integers	84
Syntax	84
Integer overflow	84
Converting to integer	85
From booleans	85
From floating point numbers	85
From strings	86
From other types	86
Floating point numbers	86
Strings	87
Syntax	87
Single quoted	87
Double quoted	88
Heredoc	88
Variable parsing	90
Simple syntax	90
Complex (curly) syntax	90
String access by character	91
Useful functions	92
String conversion	92
Arrays	93
Syntax	93
Specifying with array()	93
Creating/modifying with square-bracket syntax	93
Useful functions	94
Array do's and don'ts	94
Why is <code>\$foo[bar]</code> wrong?	94
So why is it bad then?	95
Examples	95
Objects	99
Object Initialization	99
Resource	99
Freeing resources	99
NULL	100
Syntax	100
Type Juggling	100
Type Casting	101
7. Proměnné	103
Základy	104

Předdefinované proměnné	105
Kontext ("scope") proměnné	106
Variable variables	109
Variables from outside PHP.....	109
HTML Forms (GET and POST)	109
IMAGE SUBMIT variable names	110
HTTP Cookies	111
Environment variables	111
Dots in incoming variable names.....	112
Determining variable types	112
8. Konstanty	113
9. Výrazy	116
10. Operátory	120
Aritmetické operátory	121
Operátory přiřazení.....	121
Bitové operátory	122
Operátory porovnání.....	122
Operátory řízení chyb	123
Prováděcí operátory.....	124
Inkrementační/Dekrementační operátory	124
Logické operátory.....	125
Priorita operátorů.....	126
Řetězcové operátory	126
11. Řídicí struktury	128
if.....	129
else	129
elseif	130
Alternativní syntaxe řídicích struktur	130
while	131
do..while.....	132
for.....	133
foreach.....	134
break	137
continue.....	137
switch.....	138
declare.....	140
Ticks.....	141
return.....	142
require()	142
include().....	143
require_once().....	147
include_once()	147
12. Funkce	148
Uživatelsky definované funkce	149
Argumenty funkcí.....	149
Předávání argumentů odkazem	149
Implicitní hodnoty argumentů.....	150
Seznam argumentů proměnné délky	151
Návratové hodnoty	151
old_function	152
Funkce v proměnných	152
13. Classes and Objects.....	154

class	155
extends	157
Constructors	158
::	160
parent	161
Serializing objects - objects in sessions	162
The magic functions __sleep and __wakeup	163
References inside the constructor	164
14. Vysvětlení referencí (odkazů)	168
Co jsou reference	169
Co reference dělají	169
Co reference nejsou	170
Předávání referencí (odkazem)	170
Vracení referencí	171
Odnastavení odkazů	172
Další výskyt referencí	172
odkazy global	172
\$this	172
III. Vlastnosti	174
15. Zpracování chyb	174
16. Tvorba a úpravy obrázků	179
17. HTTP autentikace a PHP	181
18. Cookies	184
19. Zpracování uploadu souborů	186
Uploading metodou POST	187
Častá úskalí	189
Uploading více souborů	189
Podpora metody PUT	190
20. Použití vzdálených souborů	192
21. Obsluha spojení	195
22. Persistentní databázová spojení	197
23. Bezpečný režim	200
Funkce omezené/deaktivované v bezpečném režimu	202
IV. Reference funkcí	205
I. Funkce specifické pro Apache	205
apache_lookup_uri	206
apache_note	206
ascii2ebcdic	206
ebcdic2ascii	207
getallheaders	207
virtual	208
II. Funkce pro práci s poli	209
array	210
array_count_values	211
array_diff	211
array_flip	212
array_intersect	212
array_keys	212
array_merge	213
array_merge_recursive	214
array_multisort	214

array_pad	215
array_pop	216
array_push	216
array_rand	217
array_reverse	217
array_shift	218
array_slice	218
array_splice	219
array_unique	220
array_unshift	220
array_values	221
array_walk	221
arsort	222
asort	223
compact	223
count	224
current	225
each	225
end	226
extract	226
in_array	228
key	229
krsort	229
ksort	230
list	230
natcasesort	231
natsort	231
next	232
pos	233
prev	233
range	233
reset	234
rsort	234
shuffle	234
sizeof	235
sort	235
uasort	236
uksort	236
usort	237
III. Aspell funkce	240
aspell_check	241
aspell_check_raw	241
aspell_new	241
aspell_suggest	242
IV. BCMath funkce pro výpočty s libovolnou přesností	243
bcadd	244
bccomp	244
bcddiv	244
bcmmod	244
bcmul	244
bcpow	245
bcscale	245

bcsqrt	245
bcsb	245
V. Bzip2 Compression Functions	246
bzclose	248
bzcompress	248
bzdecompress	248
bzerrno	249
bzerror	249
bzerrstr	250
bzflush	250
bzopen	250
bzread	251
bzwrite	251
VI. Kalendářové funkce	253
easter_date	254
easter_days	254
FrenchToJD	255
GregorianToJD	255
JDDayOfWeek	255
JDMonthName	256
JDToFrench	256
JDToGregorian	256
JDToJewish	257
JDToJulian	257
jdtounix	257
JewishToJD	257
JulianToJD	258
unixtojd	258
VII. CCVS API Funkce	259
ccvs_add	260
ccvs_auth	260
ccvs_command	260
ccvs_count	260
ccvs_delete	261
ccvs_done	261
ccvs_init	261
ccvs_lookup	262
ccvs_new	262
ccvs_report	262
ccvs_return	263
ccvs_reverse	263
ccvs_sale	263
ccvs_status	263
ccvs_textvalue	264
ccvs_void	264
VIII. Funkce na podporu COM ve Windows	265
com_get	266
com_invoke	266
com_load	266
com_propget	266
com_propput	266
com_propset	266

com_set.....	267
IX. Funkce pro práci s třídami/objekty	268
call_user_method.....	271
class_exists	271
get_class	271
get_class_methods.....	272
get_class_vars.....	272
get_declared_classes.....	272
get_object_vars.....	272
get_parent_class	273
is_subclass_of.....	274
method_exists	274
X. ClibPDF functions.....	275
cpdf_add_annotation	279
cpdf_add_outline	279
cpdf_arc	279
cpdf_begin_text	280
cpdf_circle.....	280
cpdf_clip.....	280
cpdf_close.....	281
cpdf_closepath.....	281
cpdf_closepath_fill_stroke.....	281
cpdf_closepath_stroke	281
cpdf_continue_text	281
cpdf_curveto	282
cpdf_end_text	282
cpdf_fill.....	282
cpdf_fill_stroke.....	283
cpdf_finalize	283
cpdf_finalize_page.....	283
cpdf_global_set_document_limits.....	283
cpdf_import_jpeg	284
cpdf_lineto.....	284
cpdf_moveto	284
cpdf_newpath.....	285
cpdf_open	285
cpdf_output_buffer	285
cpdf_page_init	285
cpdf_place_inline_image.....	286
cpdf_rect.....	286
cpdf_restore	286
cpdf_rlineto.....	287
cpdf_rmoveto.....	287
cpdf_rotate.....	287
cpdf_rotate_text.....	288
cpdf_save	288
cpdf_save_to_file.....	288
cpdf_scale.....	288
cpdf_set_action_url	289
cpdf_set_char_spacing	289
cpdf_set_creator	289
cpdf_set_current_page.....	289

cpdf_set_font	289
cpdf_set_font_directories	290
cpdf_set_font_map_file	290
cpdf_set_horiz_scaling	290
cpdf_set_keywords	291
cpdf_set_leading	291
cpdf_set_page_animation	291
cpdf_set_subject	291
cpdf_set_text_matrix	292
cpdf_set_text_pos	292
cpdf_set_text_rendering	292
cpdf_set_text_rise	292
cpdf_set_title	293
cpdf_set_viewer_preferences	293
cpdf_set_word_spacing	293
cpdf_setdash	293
cpdf_setflat	293
cpdf_setgray	294
cpdf_setgray_fill	294
cpdf_setgray_stroke	294
cpdf_setlinecap	294
cpdf_setlinejoin	294
cpdf_setlinewidth	295
cpdf_setmiterlimit	295
cpdf_setrgbcolor	295
cpdf_setrgbcolor_fill	295
cpdf_setrgbcolor_stroke	295
cpdf_show	296
cpdf_show_xy	296
cpdf_stringwidth	296
cpdf_stroke	296
cpdf_text	297
cpdf_translate	297
XI. Crack functions	298
crack_check	300
crack_closedict	300
crack_getlastmessage	300
crack_opendict	301
XII. Funkce pro práci s CURL, Client URL Library	302
curl_close	303
curl_exec	303
curl_init	303
curl_setopt	303
curl_version	306
XIII. Cybercash platební funkce	307
cybercash_base64_decode	308
cybercash_base64_encode	308
cybercash_decr	308
cybercash_encr	308
XIV. Crédit Mutuel CyberMUT functions	309
cybermut_creerformulairecm	310
cybermut_creerreponsecm	310

cybermut_testmac	310
XV. Cyrus IMAP administration functions	312
cyrus_authenticate	313
cyrus_bind	313
cyrus_close	313
cyrus_connect	313
cyrus_query	314
cyrus_unbind	314
XVI. Character type functions	315
ctype_alnum	316
ctype_alpha	316
ctype_cntrl	316
ctype_digit	316
ctype_graph	316
ctype_lower	317
ctype_print	317
ctype_punct	317
ctype_space	317
ctype_upper	318
ctype_xdigit	318
XVII. Database (dbm-style) abstraction layer functions	319
dba_close	323
dba_delete	323
dba_exists	323
dba_fetch	323
dba_firstkey	324
dba_insert	324
dba_nextkey	324
dba_open	325
dba_optimize	325
dba_popen	325
dba_replace	326
dba_sync	326
XVIII. Date and Time functions	327
checkdate	328
date	328
getdate	330
gettimeofday	331
gmdate	331
gmmktime	332
gmstrftime	332
localtime	332
microtime	333
mktime	334
strftime	335
strptime	337
time	338
XIX. dBase functions	339
dbase_add_record	340
dbase_close	340
dbase_create	340
dbase_delete_record	341

dbase_get_record	341
dbase_get_record_with_names	341
dbase_numfields	342
dbase_numrecords	342
dbase_open	342
dbase_pack	343
dbase_replace_record	343
XX. DBM Funkce	344
dblist	345
dbmclose	345
dbmdelete	345
dbmexists	345
dbmfetch	345
dbmfirstkey	345
dbminsert	346
dbmnextkey	346
dbmopen	346
dbmreplace	347
XXI. dbx functions	348
dbx_close	349
dbx_compare	349
dbx_connect	350
dbx_error	351
dbx_query	352
dbx_sort	355
XXII. DB++ Functions	356
dbplus_add	360
dbplus_aql	360
dbplus_chdir	360
dbplus_close	361
dbplus_curr	361
dbplus_errcode	361
dbplus_errno	362
dbplus_find	362
dbplus_first	363
dbplus_flush	363
dbplus_freealllocks	363
dbplus_freelock	364
dbplus_freerlocks	364
dbplus_getlock	365
dbplus_getunique	365
dbplus_info	365
dbplus_last	366
dbplus_lockrel	366
dbplus_next	366
dbplus_open	367
dbplus_prev	367
dbplus_rchperm	368
dbplus_rcreate	368
dbplus_rcrtexact	369
dbplus_rcrtlike	369
dbplus_resolve	369

dbplus_restorepos	370
dbplus_rkeys	370
dbplus_ropen	370
dbplus_rquery	371
dbplus_rename	371
dbplus_rsecindex	371
dbplus_runlink	372
dbplus_rzap	372
dbplus_savepos	372
dbplus_setindex	373
dbplus_setindexbynumber	373
dbplus_sql	373
dbplus_tcl	374
dbplus_tremove	374
dbplus_undo	375
dbplus_undoprepere	375
dbplus_unlockrel	375
dbplus_unselect	376
dbplus_update	376
dbplus_xlockrel	376
dbplus_xunlockrel	377
XXIII. Direct IO functions	378
dio_close	379
dio_fcntl	379
dio_open	379
dio_read	380
dio_seek	380
dio_stat	380
dio_truncate	381
dio_write	381
XXIV. Adresářové funkce	382
chdir	383
dir	383
closedir	383
getcwd	383
opendir	383
readdir	384
rewinddir	384
XXV. DOM XML funkce	386
xmldoc	387
xmldocfile	387
xmldata	387
XXVI. .NET functions	388
dotnet_load	389
XXVII. Error Handling and Logging Functions	390
error_log	391
error_reporting	392
restore_error_handler	393
set_error_handler	393
trigger_error	396
user_error	396
XXVIII. FrontBase Functions	398

fbsql_affected_rows.....	399
fbsql_autocommit.....	399
fbsql_change_user	399
fbsql_close.....	400
fbsql_commit.....	400
fbsql_connect.....	400
fbsql_create_blob	401
fbsql_create_clob.....	401
fbsql_create_db.....	402
fbsql_data_seek	403
fbsql_database	403
fbsql_database_password	404
fbsql_db_query	404
fbsql_db_status	405
fbsql_drop_db.....	405
fbsql_errno.....	405
fbsql_error	406
fbsql_fetch_array	407
fbsql_fetch_assoc	407
fbsql_fetch_field.....	408
fbsql_fetch_lengths.....	409
fbsql_fetch_object	409
fbsql_fetch_row	410
fbsql_field_flags	410
fbsql_field_len	411
fbsql_field_name	411
fbsql_field_seek.....	412
fbsql_field_table	412
fbsql_field_type	412
fbsql_free_result.....	413
fbsql_get_autostart_info	413
fbsql_hostname.....	413
fbsql_insert_id	414
fbsql_list_dbs.....	414
fbsql_list_fields.....	415
fbsql_list_tables.....	416
fbsql_next_result	416
fbsql_num_fields	416
fbsql_num_rows	417
fbsql_password.....	417
fbsql_pconnect.....	417
fbsql_query	418
fbsql_read_blob	419
fbsql_read_clob	420
fbsql_result	420
fbsql_rollback	421
fbsql_select_db	421
fbsql_set_lob_mode.....	422
fbsql_set_transaction	422
fbsql_start_db	422
fbsql_stop_db	423
fbsql_tablename.....	423

fbsql_username	423
fbsql_warnings	424
XXIX. filePro funkce	425
filepro	426
filepro_fieldcount	426
filepro_fieldname	426
filepro_fieldtype	426
filepro_fieldwidth	426
filepro_retrieve	426
filepro_rowcount	427
XXX. Filesystemové funkce	428
basename	429
chgrp	429
chmod	429
chown	430
clearstatcache	430
copy	430
delete	431
dirname	431
diskfreespace	431
fclose	432
feof	432
fflush	432
fgetc	432
fgetcsw	433
fgets	433
fgetss	434
file	434
file_exists	435
fileatime	435
filectime	435
filegroup	436
fileinode	436
filemtime	436
fileowner	437
fileperms	437
filesize	437
filetype	437
flock	438
fopen	438
fpassthru	440
fputs	440
fread	440
fscanf	441
fseek	441
fstat	442
ftell	442
ftruncate	443
fwrite	443
is_dir	443
is_executable	443
is_file	444

is_link	444
is_readable	444
is_uploaded_file	444
is_writable	445
link	445
linkinfo	445
lstat	446
mkdir	446
move_uploaded_file	447
pclose	447
popen	447
readfile	448
readlink	448
realpath	449
rename	449
rewind	449
rmdir	449
set_file_buffer	450
stat	450
symlink	451
tempnam	451
tmpfile	452
touch	452
umask	452
unlink	453
XXXI. Forms Data Format functions	454
fdf_add_template	456
fdf_close	456
fdf_create	456
fdf_get_file	457
fdf_get_status	457
fdf_get_value	457
fdf_next_field_name	457
fdf_open	457
fdf_save	458
fdf_set_ap	458
fdf_set_encoding	459
fdf_set_file	459
fdf_set_flags	459
fdf_set_javascript_action	459
fdf_set_opt	459
fdf_set_status	460
fdf_set_submit_form_action	460
fdf_set_value	460
XXXII. FriBiDi functions	461
fribidi_log2vis	462
XXXIII. FTP functions	463
ftp_cdup	465
ftp_chdir	465
ftp_close	465
ftp_connect	465
ftp_delete	466

ftp_exec	466
ftp_fget	466
ftp_fput	466
ftp_get.....	466
ftp_get_option.....	467
ftp_login	467
ftp_mdtm	468
ftp_mkdir	468
ftp_nlist.....	468
ftp_pasv	468
ftp_put.....	468
ftp_pwd.....	469
ftp_quit	469
ftp_rawlist.....	469
ftp_rename	469
ftp_rmdir.....	470
ftp_set_option	470
ftp_site	471
ftp_size	471
ftp_systype.....	471
XXXIV. Funkce pro práci s funkcemi	472
call_user_func.....	473
create_function	473
func_get_arg	475
func_get_args.....	476
func_num_args	476
function_exists.....	477
register_shutdown_function	477
XXXV. GNU Gettext.....	478
bindtextdomain	479
dcgettext	479
dgettext	479
gettext	479
textdomain	480
XXXVI. GMP functions	481
gmp_abs.....	482
gmp_add	482
gmp_and	482
gmp_clrbit.....	482
gmp_cmp	482
gmp_com	482
gmp_div	483
gmp_div_q	483
gmp_div_qr.....	483
gmp_div_r.....	484
gmp_divexact.....	484
gmp_fact	484
gmp_gcd	484
gmp_gcdext	485
gmp_hamdist	485
gmp_init.....	485
gmp_intval	486

gmp_invert.....	486
gmp_jacobi.....	486
gmp_legendre.....	486
gmp_mod.....	487
gmp_mul.....	487
gmp_neg.....	487
gmp_or.....	487
gmp_perfect_square.....	487
gmp_popcount.....	488
gmp_pow.....	488
gmp_powm.....	488
gmp_prob_prime.....	488
gmp_random.....	488
gmp_scan0.....	488
gmp_scan1.....	489
gmp_setbit.....	489
gmp_sign.....	489
gmp_sqrt.....	489
gmp_sqrtrm.....	489
gmp_strval.....	490
gmp_sub.....	490
gmp_xor.....	490
XXXVII. HTTP funkce.....	491
header.....	492
headers_sent.....	492
setcookie.....	493
XXXVIII. Hyperwave functions.....	495
hw_Array2Objrec.....	499
hw_changeobject.....	499
hw_Children.....	499
hw_ChildrenObj.....	499
hw_Close.....	499
hw_Connect.....	500
hw_connection_info.....	500
hw_Cp.....	500
hw_Deleteobject.....	500
hw_DocByAnchor.....	501
hw_DocByAnchorObj.....	501
hw_Document_Attributes.....	501
hw_Document_BodyTag.....	501
hw_Document_Content.....	502
hw_Document_SetContent.....	502
hw_Document_Size.....	502
hw_dummy.....	502
hw_EditText.....	503
hw_Error.....	503
hw_ErrorMsg.....	503
hw_Free_Document.....	503
hw_GetAnchors.....	504
hw_GetAnchorsObj.....	504
hw_GetAndLock.....	504
hw_GetChildColl.....	504

hw_GetChildCollObj.....	504
hw_GetChildDocColl	505
hw_GetChildDocCollObj	505
hw_GetObject.....	505
hw_GetObjectByQuery	506
hw_GetObjectByQueryColl	506
hw_GetObjectByQueryCollObj	506
hw_GetObjectByQueryObj	506
hw_GetParents.....	507
hw_GetParentsObj.....	507
hw_getrellink.....	507
hw_GetRemote	507
hw_GetRemoteChildren	508
hw_GetSrcByDestObj	508
hw_GetText	508
hw_getusername.....	509
hw_Identify.....	509
hw_InCollections.....	510
hw_Info.....	510
hw_InsColl	510
hw_InsDoc.....	510
hw_insertanchors	510
hw_InsertDocument	511
hw_InsertObject	511
hw_mapid	511
hw_Modifyobject	512
hw_Mv.....	514
hw_New_Document	514
hw_Objrec2Array	514
hw_Output_Document	515
hw_pConnect.....	515
hw_PipeDocument	515
hw_Root	516
hw_setlinkroot	516
hw_stat.....	516
hw_Unlock	516
hw_Who	517
XXXIX. Hyperwave API functions	518
hw_api_attribute	520
hw_api_attribute->key	520
hw_api_attribute->langdepvalue	520
hw_api_attribute->value	520
hw_api_attribute->values	520
hw_api->checkin	520
hw_api->checkout	521
hw_api->children.....	522
hw_api->content.....	522
hw_api_content->mimetype	522
hw_api_content->read	522
hw_api->copy	523
hw_api->dbstat	523
hw_api->dcstat	523

hw_api->dstanchors.....	523
hw_api->dstofsrcanchors.....	523
hw_api_error->count.....	524
hw_api_error->reason.....	524
hw_api->find.....	524
hw_api->ftstat.....	524
hwapi_hgcsp.....	525
hw_api->hwstat.....	525
hw_api->identify.....	525
hw_api->info.....	525
hw_api->insert.....	526
hw_api->insertanchor.....	526
hw_api->insertcollection.....	526
hw_api->insertdocument.....	527
hw_api->link.....	527
hw_api->lock.....	527
hw_api->move.....	528
hw_api_content.....	528
hw_api->object.....	528
hw_api_object->assign.....	529
hw_api_object->attreditable.....	529
hw_api_object->count.....	529
hw_api_object->insert.....	530
hw_api_object.....	530
hw_api_object->remove.....	530
hw_api_object->title.....	530
hw_api_object->value.....	530
hw_api->objectbyanchor.....	531
hw_api->parents.....	531
hw_api_reason->description.....	531
hw_api_reason->type.....	531
hw_api->remove.....	532
hw_api->replace.....	532
hw_api->setcommittedversion.....	533
hw_api->srcanchors.....	533
hw_api->srcsofdst.....	533
hw_api->unlock.....	533
hw_api->user.....	534
hw_api->userlist.....	534
XL. ICAP funkce.....	535
icap_close.....	536
icap_delete_event.....	536
icap_fetch_event.....	536
icap_list_alarms.....	537
icap_list_events.....	537
icap_open.....	537
icap_snooze.....	538
icap_store_event.....	538
XLI. iconv functions.....	540
iconv.....	541
iconv_get_encoding.....	541
iconv_set_encoding.....	541

ob_iconv_handler	541
XLII. Image functions	543
exif_imagetype	544
exif_read_data	544
exif_thumbnail	547
getimagesize	547
image2wbmp	548
imagealphablending	549
imagearc	549
imagechar	549
imagecharup	550
imagecolorallocate	550
imagecolorat	550
imagecolorclosest	551
imagecolorclosestalpha	551
imagecolorclosesthw	551
imagecolordeallocate	551
imagecolorexact	552
imagecolorexactalpha	552
imagecolorresolve	552
imagecolorresolvealpha	553
imagecolorset	553
imagecolorsforindex	553
imagecolorstotal	553
imagecolortransparent	554
imagecopy	554
imagecopymerge	554
imagecopymergegray	554
imagecopyresampled	555
imagecopyresized	555
imagecreate	556
imagecreatefromgd	556
imagecreatefromgd2	556
imagecreatefromgd2part	557
imagecreatefromgif	557
imagecreatefromjpeg	558
imagecreatefrompng	558
imagecreatefromstring	559
imagecreatefromwbmp	559
imagecreatefromxbm	560
imagecreatefromxpm	560
imagecreatetruecolor	560
imagedashedline	560
imagedestroy	561
imageellipse	561
imagefill	561
imagefilledarc	561
imagefilledellipse	562
imagefilledpolygon	562
imagefilledrectangle	562
imagefilltoborder	563
imagefontheight	563

imagefontwidth.....	563
imageftbbox.....	563
imagefttext.....	564
imagegammaconvert.....	564
imagegd	564
imagegd2	564
imagegif	565
imageinterlace.....	566
imagejpeg	566
imageline	567
imageloadfont	567
imagepalettecopy	568
imagepng	568
imagepolygon	568
imagesbbox.....	568
ImagePSCopyFont.....	569
imagepsencodefont	569
imagepsextendfont.....	570
imagepsfreefont	570
imagepsloadfont	570
imagepslantfont.....	571
imagepstext.....	571
imagerectangle.....	572
imagesetbrush	572
imagesetpixel	572
imagesetstyle	573
imagesetthickness	573
imagesettile.....	574
imagestring	574
imagestringup	574
imagesx.....	575
imagesy.....	575
imagetruecolortopalette	575
imaggftbbox.....	575
imaggfttext.....	576
imagetypes	577
imagewbmp	578
iptcembed	578
jpeg2wbmp	578
png2wbmp	579
read_exif_data	579
XLIII. IMAP, POP3 and NNTP functions	580
imap_8bit.....	581
imap_alerts	581
imap_append.....	581
imap_base64.....	582
imap_binary.....	582
imap_body	582
imap_bodystruct	583
imap_check.....	583
imap_clearflag_full.....	583
imap_close.....	584

imap_createmailbox	584
imap_delete.....	585
imap_deletemailbox	586
imap_errors.....	586
imap_expunge.....	586
imap_fetch_overview	587
imap_fetchbody	588
imap_fetchheader	588
imap_fetchstructure	589
imap_get_quota	590
imap_getmailboxes.....	591
imap_getsubscribed.....	592
imap_header	592
imap_headerinfo.....	592
imap_headers.....	594
imap_last_error.....	594
imap_listmailbox	594
imap_listsubscribed.....	595
imap_mail.....	595
imap_mail_compose.....	595
imap_mail_copy	596
imap_mail_move	597
imap_mailboxmsginfo.....	597
imap_mime_header_decode	598
imap_msgno	599
imap_num_msg	599
imap_num_recent	599
imap_open	599
imap_ping.....	601
imap_popen	601
imap_qprint.....	602
imap_renamemailbox	602
imap_reopen	602
imap_rfc822_parse_adrlist	603
imap_rfc822_parse_headers	603
imap_rfc822_write_address	604
imap_scanmailbox	604
imap_search.....	604
imap_set_quota.....	605
imap_setacl.....	606
imap_setflag_full	606
imap_sort	607
imap_status	608
imap_subscribe.....	608
imap_thread	609
imap_uid	609
imap_undelete.....	609
imap_unsubscribe.....	609
imap_utf7_decode	610
imap_utf7_encode	610
imap_utf8.....	610
XLIV. Informix functions.....	611

ifx_affected_rows	613
ifx_blobinfile_mode	613
ifx_byteasvarchar	613
ifx_close	614
ifx_connect	614
ifx_copy_blob	615
ifx_create_blob	615
ifx_create_char	615
ifx_do	615
ifx_error	616
ifx_errormsg	616
ifx_fetch_row	616
ifx_fieldproperties	617
ifx_fieldtypes	618
ifx_free_blob	618
ifx_free_char	619
ifx_free_result	619
ifx_get_blob	619
ifx_get_char	619
ifx_getsqlca	619
ifx_htmltbl_result	620
ifx_nullformat	621
ifx_num_fields	621
ifx_num_rows	621
ifx_pconnect	621
ifx_prepare	622
ifx_query	622
ifx_textasvarchar	624
ifx_update_blob	624
ifx_update_char	624
ifxus_close_slob	624
ifxus_create_slob	624
ifxus_free_slob	625
ifxus_open_slob	625
ifxus_read_slob	625
ifxus_seek_slob	625
ifxus_tell_slob	626
ifxus_write_slob	626
XLV. InterBase functions	627
ibase_blob_add	628
ibase_blob_cancel	628
ibase_blob_close	628
ibase_blob_create	628
ibase_blob_echo	629
ibase_blob_get	629
ibase_blob_import	629
ibase_blob_info	630
ibase_blob_open	630
ibase_close	630
ibase_commit	630
ibase_connect	631
ibase_errormsg	632

ibase_execute.....	632
ibase_fetch_object.....	632
ibase_fetch_row.....	633
ibase_field_info.....	633
ibase_free_query.....	634
ibase_free_result.....	634
ibase_num_fields.....	634
ibase_pconnect.....	634
ibase_prepare.....	635
ibase_query.....	635
ibase_rollback.....	635
ibase_timefmt.....	636
ibase_trans.....	636
XLVI. Ingres II functions.....	637
ingres_autocommit.....	638
ingres_close.....	638
ingres_commit.....	638
ingres_connect.....	639
ingres_fetch_array.....	640
ingres_fetch_object.....	641
ingres_fetch_row.....	642
ingres_field_length.....	642
ingres_field_name.....	643
ingres_field_nullable.....	643
ingres_field_precision.....	644
ingres_field_scale.....	644
ingres_field_type.....	644
ingres_num_fields.....	645
ingres_num_rows.....	645
ingres_pconnect.....	646
ingres_query.....	646
ingres_rollback.....	648
XLVII. IRC Gateway Functions.....	649
ircg_channel_mode.....	650
ircg_disconnect.....	650
ircg_fetch_error_msg.....	650
ircg_get_username.....	650
ircg_html_encode.....	651
ircg_ignore_add.....	651
ircg_ignore_del.....	651
ircg_is_conn_alive.....	651
ircg_join.....	652
ircg_kick.....	652
ircg_lookup_format_messages.....	652
ircg_msg.....	652
ircg_nick.....	652
ircg_nickname_escape.....	653
ircg_nickname_unescape.....	653
ircg_notice.....	653
ircg_part.....	653
ircg_pconnect.....	653
ircg_register_format_messages.....	654

ircg_set_current	655
ircg_set_file	655
ircg_set_on_die.....	656
ircg_topic	656
ircg_whois	656
XLVIII. Java	657
java_last_exception_clear.....	659
java_last_exception_get.....	659
XLIX. LDAP functions	660
ldap_8859_to_t61	663
ldap_add	663
ldap_bind	664
ldap_close	664
ldap_compare	664
ldap_connect.....	665
ldap_count_entries.....	666
ldap_delete.....	666
ldap_dn2ufn.....	666
ldap_err2str.....	666
ldap_errno.....	667
ldap_error	668
ldap_explode_dn.....	668
ldap_first_attribute.....	668
ldap_first_entry.....	669
ldap_first_reference.....	669
ldap_free_result	669
ldap_get_attributes.....	670
ldap_get_dn	670
ldap_get_entries.....	671
ldap_get_option	671
ldap_get_values	672
ldap_get_values_len	673
ldap_list	673
ldap_mod_add	674
ldap_mod_del	674
ldap_mod_replace.....	675
ldap_modify.....	675
ldap_next_attribute	675
ldap_next_entry	675
ldap_next_reference.....	676
ldap_parse_reference.....	676
ldap_parse_result.....	676
ldap_read	677
ldap_rename	677
ldap_search.....	677
ldap_set_option.....	679
ldap_set_rebind_proc	680
ldap_sort	681
ldap_start_tls.....	681
ldap_t61_to_8859.....	681
ldap_unbind.....	682
L. Mailové funkce	683

ezmlm_hash.....	684
mail.....	684
L.I. mailparse functions	686
mailparse_determine_best_xfer_encoding	687
mailparse_msg_create	687
mailparse_msg_extract_part.....	687
mailparse_msg_extract_part_file.....	688
mailparse_msg_free.....	688
mailparse_msg_get_part.....	689
mailparse_msg_get_part_data	689
mailparse_msg_get_structure	690
mailparse_msg_parse	690
mailparse_msg_parse_file	691
mailparse_rfc822_parse_addresses	691
mailparse_stream_encode.....	692
mailparse_uudecode_all	692
L.II. Mathematical Functions.....	694
abs.....	695
acos	695
acosh	695
asin.....	695
asinh.....	696
atan	696
atan2	696
atanh	696
base_convert	697
bindec	697
ceil	697
cos.....	698
cosh.....	698
decbin	698
dechex	698
decoct.....	699
deg2rad	699
exp	699
expm1	699
floor.....	700
getrandmax	700
hexdec	700
hypot.....	701
is_finite	701
is_infinite	701
is_nan.....	702
lcg_value.....	702
log.....	702
log10	702
log1p.....	702
max	703
min.....	703
mt_getrandmax	704
mt_rand.....	704
mt_srand	704

number_format	705
octdec	706
pi	706
pow	706
rad2deg	707
rand	707
round	708
sin	708
sinh	709
sqrt	709
srand	709
tan	709
tanh	710
LIII. Multi-Byte String Functions	711
mb_convert_encoding	718
mb_convert_kana	718
mb_convert_variables	719
mb_decode_mimeheader	720
mb_decode_numericentity	720
mb_detect_encoding	721
mb_detect_order	721
mb_encode_mimeheader	722
mb_encode_numericentity	723
mb_ereg	724
mb_ereg_match	724
mb_ereg_replace	725
mb_ereg_search	726
mb_ereg_search_getpos	726
mb_ereg_search_getregs	727
mb_ereg_search_init	727
mb_ereg_search_pos	728
mb_ereg_search_regs	728
mb_ereg_search_setpos	729
mb_eregi	729
mb_eregi_replace	730
mb_get_info	730
mb_http_input	731
mb_http_output	731
mb_internal_encoding	731
mb_language	732
mb_output_handler	732
mb_parse_str	733
mb_preferred_mime_name	733
mb_regex_encoding	734
mb_send_mail	734
mb_split	735
mb_strcut	735
mb_strimwidth	736
mb_strlen	736
mb_strpos	736
mb_strrpos	737
mb_strwidth	737

mb_substitute_character.....	738
mb_substr	738
LIV. MCAL functions.....	739
mcal_append_event	741
mcal_close	741
mcal_create_calendar	741
mcal_date_compare.....	741
mcal_date_valid.....	741
mcal_day_of_week.....	741
mcal_day_of_year	742
mcal_days_in_month.....	742
mcal_delete_calendar	742
mcal_delete_event	742
mcal_event_add_attribute.....	742
mcal_event_init	743
mcal_event_set_alarm	743
mcal_event_set_category.....	743
mcal_event_set_class.....	743
mcal_event_set_description.....	744
mcal_event_set_end.....	744
mcal_event_set_recur_daily	744
mcal_event_set_recur_monthly_mday	744
mcal_event_set_recur_monthly_wday	744
mcal_event_set_recur_none	745
mcal_event_set_recur_weekly.....	745
mcal_event_set_recur_yearly	745
mcal_event_set_start	745
mcal_event_set_title	746
mcal_expunge.....	746
mcal_fetch_current_stream_event.....	746
mcal_fetch_event.....	747
mcal_is_leap_year	748
mcal_list_alarms.....	748
mcal_list_events	748
mcal_next_recurrence.....	748
mcal_open.....	749
mcal_popen.....	749
mcal_rename_calendar	749
mcal_reopen	749
mcal_snooze	750
mcal_store_event	750
mcal_time_valid	750
mcal_week_of_year.....	750
LV. Mcrypt Encryption Functions	751
mcrypt_cbc	756
mcrypt_cfb.....	756
mcrypt_create_iv	756
mcrypt_decrypt.....	757
mcrypt_ecb	757
mcrypt_enc_get_algorithms_name.....	758
mcrypt_enc_get_block_size	758
mcrypt_enc_get_iv_size	758

mcrypt_enc_get_key_size	758
mcrypt_enc_get_modes_name	759
mcrypt_enc_get_supported_key_sizes	759
mcrypt_enc_is_block_algorithm	759
mcrypt_enc_is_block_algorithm_mode	759
mcrypt_enc_is_block_mode	759
mcrypt_enc_self_test	760
mcrypt_encrypt	760
mcrypt_generic	761
mcrypt_generic_deinit	761
mcrypt_generic_end	761
mcrypt_generic_init	762
mcrypt_get_block_size	762
mcrypt_get_cipher_name	762
mcrypt_get_iv_size	763
mcrypt_get_key_size	763
mcrypt_list_algorithms	763
mcrypt_list_modes	764
mcrypt_module_close	765
mcrypt_module_get_algo_block_size	765
mcrypt_module_get_algo_key_size	765
mcrypt_module_get_supported_key_sizes	765
mcrypt_module_is_block_algorithm	766
mcrypt_module_is_block_algorithm_mode	766
mcrypt_module_is_block_mode	766
mcrypt_module_open	766
mcrypt_module_self_test	767
mcrypt_ofb	767
mdecrypt_generic	768
LVI. Mhash funkce	769
mhash	770
mhash_count	770
mhash_get_block_size	770
mhash_get_hash_name	770
mhash_keygen_s2k	771
LVII. Microsoft SQL Server functions	772
mssql_bind	773
mssql_close	773
mssql_connect	773
mssql_data_seek	773
mssql_execute	774
mssql_fetch_array	774
mssql_fetch_assoc	774
mssql_fetch_batch	775
mssql_fetch_field	775
mssql_fetch_object	775
mssql_fetch_row	776
mssql_field_length	776
mssql_field_name	776
mssql_field_seek	777
mssql_field_type	777
mssql_free_result	777

mssql_get_last_message.....	777
mssql_guid_string.....	777
mssql_init	778
mssql_min_error_severity	778
mssql_min_message_severity	778
mssql_next_result.....	778
mssql_num_fields.....	779
mssql_num_rows	779
mssql_pconnect	779
mssql_query.....	780
mssql_result.....	780
mssql_rows_affected	780
mssql_select_db.....	780
LVIII. Ming functions for Flash.....	782
ming_setcubicthreshold.....	784
ming_setscale	784
ming_useswfversion	784
SWFAction	784
SWFBitmap.....	794
SWFBitmap->getHeight.....	796
SWFBitmap->getWidth.....	796
SWFbutton.....	797
swfbutton_keypress	800
SWFbutton->addAction	800
SWFbutton->addShape.....	800
SWFbutton->setAction.....	801
SWFbutton->setdown	801
SWFbutton->setHit.....	801
SWFbutton->setOver.....	802
SWFbutton->setUp.....	802
SWFDisplayItem	802
SWFDisplayItem->addColor.....	803
SWFDisplayItem->move.....	803
SWFDisplayItem->moveTo.....	804
SWFDisplayItem->multColor	804
SWFDisplayItem->remove.....	805
SWFDisplayItem->Rotate	806
SWFDisplayItem->rotateTo	806
SWFDisplayItem->scale.....	808
SWFDisplayItem->scaleTo	808
SWFDisplayItem->setDepth	809
SWFDisplayItem->setName.....	809
SWFDisplayItem->setRatio	809
SWFDisplayItem->skewX.....	811
SWFDisplayItem->skewXTo	811
SWFDisplayItem->skewY.....	812
SWFDisplayItem->skewYTo	812
SWFFill	813
SWFFill->moveTo.....	813
SWFFill->rotateTo	813
SWFFill->scaleTo.....	814
SWFFill->skewXTo.....	814

SWFFill->skewYTo.....	814
SWFFont.....	815
swffont->getwidth	815
SWFGradient.....	816
SWFGradient->addEntry.....	817
SWFMorph.....	818
SWFMorph->getshape1	819
SWFMorph->getshape2	819
SWFMovie	820
SWFMovie->add	820
SWFMovie->nextframe.....	821
SWFMovie->output.....	821
SWFMovie->remove	822
SWFMovie->save	822
SWFMovie->setbackground.....	822
SWFMovie->setdimension	823
SWFMovie->setframes.....	823
SWFMovie->setrate	823
SWFMovie->streammp3	824
SWFShape	824
SWFShape->addFill	825
SWFShape->drawCurve.....	827
SWFShape->drawCurveTo.....	828
SWFShape->drawLine	828
SWFShape->drawLineTo	829
SWFShape->movePen.....	829
SWFShape->movePenTo.....	829
SWFShape->setLeftFill	830
SWFShape->setLine.....	830
SWFShape->setRightFill.....	832
SWFSprite	832
SWFSprite->add	834
SWFSprite->nextframe.....	834
SWFSprite->remove	834
SWFSprite->setframes	835
SWFText.....	835
SWFText->addString.....	836
SWFText->getWidth.....	836
SWFText->moveTo	837
SWFText->setColor.....	837
SWFText->setFont.....	837
SWFText->setHeight.....	838
SWFText->setSpacing	838
SWFTextField.....	838
SWFTextField->addstring	839
SWFTextField->align	840
SWFTextField->setbounds	840
SWFTextField->setcolor	840
SWFTextField->setFont	841
SWFTextField->setHeight.....	841
SWFTextField->setindentation.....	841
SWFTextField->setLeftMargin	842

SWFTextField->setLineSpacing	842
SWFTextField->setMargins	842
SWFTextField->setname	843
SWFTextField->setrightMargin	843
LIX. Smíšené funkce.....	844
connection_aborted.....	845
connection_status	845
connection_timeout	845
define	845
defined	846
die	846
eval.....	847
exit	847
get_browser	848
highlight_file.....	849
highlight_string.....	850
ignore_user_abort.....	850
iptcparse.....	850
leak	851
pack.....	851
show_source	852
sleep.....	852
uniqid.....	853
unpack.....	853
usleep.....	854
LX. mnoGoSearch Functions.....	855
udm_add_search_limit	856
udm_alloc_agent.....	856
udm_api_version	857
udm_cat_list	857
udm_cat_path	858
udm_check_charset	859
udm_check_stored	860
udm_clear_search_limits.....	860
udm_close_stored.....	860
udm_crc32.....	860
udm_errno.....	861
udm_error	861
udm_find.....	861
udm_free_agent	862
udm_free_ispell_data	862
udm_free_res	862
udm_get_doc_count	863
udm_get_res_field	863
udm_get_res_param	864
udm_load_ispell_data.....	864
udm_open_stored	866
udm_set_agent_param.....	867
LXI. mSQL functions	870
mysql	871
mysql_affected_rows.....	871
mysql_close	871

mysql_connect.....	871
mysql_create_db.....	872
mysql_createdb.....	872
mysql_data_seek.....	872
mysql_dbname.....	872
mysql_drop_db.....	873
mysql_dropdb.....	873
mysql_error.....	873
mysql_fetch_array.....	873
mysql_fetch_field.....	874
mysql_fetch_object.....	874
mysql_fetch_row.....	875
mysql_field_seek.....	875
mysql_fieldflags.....	875
mysql_fieldlen.....	875
mysql_fieldname.....	875
mysql_fieldtable.....	876
mysql_fieldtype.....	876
mysql_free_result.....	876
mysql_freeresult.....	876
mysql_list_dbs.....	876
mysql_list_fields.....	877
mysql_list_tables.....	877
mysql_listdbs.....	877
mysql_listfields.....	877
mysql_listtables.....	877
mysql_num_fields.....	878
mysql_num_rows.....	878
mysql_numfields.....	878
mysql_numrows.....	878
mysql_pconnect.....	878
mysql_query.....	879
mysql_regcase.....	879
mysql_result.....	880
mysql_select_db.....	880
mysql_selectdb.....	880
mysql_tablename.....	880
LXII. MySQL Funkce.....	882
mysql_affected_rows.....	884
mysql_change_user.....	884
mysql_close.....	884
mysql_connect.....	885
mysql_create_db.....	886
mysql_data_seek.....	886
mysql_db_name.....	887
mysql_db_query.....	888
mysql_drop_db.....	888
mysql_errno.....	888
mysql_error.....	889
mysql_escape_string.....	890
mysql_fetch_array.....	890
mysql_fetch_assoc.....	891

mysql_fetch_field	892
mysql_fetch_lengths	893
mysql_fetch_object	893
mysql_fetch_row	894
mysql_field_flags	894
mysql_field_len	895
mysql_field_name	895
mysql_field_seek	896
mysql_field_table	896
mysql_field_type	896
mysql_free_result	897
mysql_get_client_info	897
mysql_get_host_info	897
mysql_get_proto_info	898
mysql_get_server_info	898
mysql_insert_id	898
mysql_list_dbs	899
mysql_list_fields	900
mysql_list_tables	900
mysql_num_fields	901
mysql_num_rows	901
mysql_pconnect	901
mysql_query	902
mysql_result	903
mysql_select_db	904
mysql_tablename	904
mysql_unbuffered_query	905
LXIII. Mohawk Software session handler functions	906
msession_connect	907
msession_count	907
msession_create	907
msession_destroy	907
msession_disconnect	908
msession_find	908
msession_get	908
msession_get_array	908
msession_getdata	909
msession_inc	909
msession_list	909
msession_listvar	909
msession_lock	909
msession_plugin	910
msession_randstr	910
msession_set	910
msession_set_array	911
msession_setdata	911
msession_timeout	911
msession_uniq	911
msession_unlock	912
LXIV. muscat functions	913
muscat_close	914
muscat_get	914

muscat_give	914
muscat_setup	915
muscat_setup_net	915
LXV. Network Functions	917
checkdnssr	918
closelog	918
debugger_off	918
debugger_on	918
define_syslog_variables	918
fsockopen	919
gethostbyaddr	920
gethostbyname	920
gethostbyname1	921
getmxrr	921
getprotobyname	921
getprotobyname	921
getservbyname	921
getservbyport	922
ip2long	922
long2ip	923
openlog	923
pfsockopen	924
socket_get_status	924
socket_set_blocking	925
socket_set_timeout	925
syslog	926
LXVI. Ncurses terminal screen control functions	928
ncurses_addch	933
ncurses_addchnstr	933
ncurses_addchstr	933
ncurses_addnstr	933
ncurses_addstr	934
ncurses_assume_default_colors	934
ncurses_attroff	934
ncurses_atron	935
ncurses_attrset	935
ncurses_baudrate	935
ncurses_beep	936
ncurses_bkgd	936
ncurses_bkgdset	936
ncurses_border	937
ncurses_can_change_color	937
ncurses_cbreak	937
ncurses_clear	938
ncurses_clrtobot	938
ncurses_clrtoeol	939
ncurses_color_set	939
ncurses_curs_set	939
ncurses_def_prog_mode	940
ncurses_def_shell_mode	940
ncurses_define_key	941
ncurses_delay_output	941

ncurses_delch	941
ncurses_deleteln	942
ncurses_delwin	942
ncurses_doupdate	942
ncurses_echo.....	943
ncurses_echochar.....	943
ncurses_end	943
ncurses_erase.....	944
ncurses_erasechar	944
ncurses_filter.....	945
ncurses_flash.....	945
ncurses_flushinp	945
ncurses_getch	945
ncurses_getmouse.....	946
ncurses_halfdelay	947
ncurses_has_colors	947
ncurses_has_ic.....	947
ncurses_has_il.....	948
ncurses_has_key	948
ncurses_hline	949
ncurses_inch	949
ncurses_init.....	949
ncurses_init_color.....	950
ncurses_init_pair.....	950
ncurses_insch.....	950
ncurses_insdelln	950
ncurses_insertln	951
ncurses_insstr	951
ncurses_instr	951
ncurses_isendwin.....	952
ncurses_keyok	952
ncurses_killchar	952
ncurses_longname	953
ncurses_mouseinterval.....	953
ncurses_mousemask	954
ncurses_move	955
ncurses_mvaddch.....	955
ncurses_mvaddchnstr.....	956
ncurses_mvaddchstr.....	956
ncurses_mvaddnstr	956
ncurses_mvaddstr	957
ncurses_mvcur	957
ncurses_mvdclch	957
ncurses_mvgetch	958
ncurses_mvhline	958
ncurses_mvinch	958
ncurses_mvvline	959
ncurses_mvwdaddstr	959
ncurses_napms.....	959
ncurses_newwin.....	960
ncurses_nl	960
ncurses_nocbreak	960

ncurses_noecho.....	961
ncurses_nonl.....	961
ncurses_noqiflush.....	961
ncurses_noraw.....	962
ncurses_putp.....	962
ncurses_qiflush.....	962
ncurses_raw.....	963
ncurses_refresh.....	963
ncurses_resetty.....	964
ncurses_savetty.....	964
ncurses_scr_dump.....	964
ncurses_scr_init.....	965
ncurses_scr_restore.....	965
ncurses_scr_set.....	965
ncurses_scr1.....	966
ncurses_slk_attr.....	966
ncurses_slk_attroff.....	966
ncurses_slk_attron.....	966
ncurses_slk_attrset.....	967
ncurses_slk_clear.....	967
ncurses_slk_color.....	967
ncurses_slk_init.....	968
ncurses_slk_noutrefresh.....	968
ncurses_slk_refresh.....	969
ncurses_slk_restore.....	969
ncurses_slk_touch.....	969
ncurses_standend.....	969
ncurses_standout.....	970
ncurses_start_color.....	970
ncurses_termattrs.....	970
ncurses_termname.....	971
ncurses_timeout.....	971
ncurses_typeahead.....	971
ncurses_ungetch.....	972
ncurses_ungetmouse.....	972
ncurses_use_default_colors.....	973
ncurses_use_env.....	973
ncurses_use_extended_names.....	973
ncurses_vidattr.....	974
ncurses_vline.....	974
ncurses_wrefresh.....	974
LXVII. Lotus Notes functions.....	976
notes_body.....	977
notes_copy_db.....	977
notes_create_db.....	977
notes_create_note.....	978
notes_drop_db.....	978
notes_find_note.....	979
notes_header_info.....	979
notes_list_msgs.....	980
notes_mark_read.....	980
notes_mark_unread.....	981

notes_nav_create	981
notes_search	982
notes_unread.....	982
notes_version.....	983
LXVIII. Unified ODBC functions	984
odbc_autocommit	986
odbc_binmode	986
odbc_close	987
odbc_close_all	987
odbc_columnprivileges.....	987
odbc_columns.....	988
odbc_commit	988
odbc_connect.....	989
odbc_cursor	989
odbc_do	989
odbc_error.....	990
odbc_errormsg.....	990
odbc_exec	990
odbc_execute	990
odbc_fetch_array	991
odbc_fetch_into	991
odbc_fetch_object.....	993
odbc_fetch_row	993
odbc_field_len	993
odbc_field_name.....	993
odbc_field_num	994
odbc_field_precision.....	994
odbc_field_scale	994
odbc_field_type	994
odbc_foreignkeys.....	995
odbc_free_result	995
odbc_gettypeinfo	996
odbc_longreadlen	996
odbc_next_result.....	997
odbc_num_fields.....	997
odbc_num_rows.....	997
odbc_pconnect.....	997
odbc_prepare	998
odbc_primarykeys	998
odbc_procedurecolumns.....	999
odbc_procedures.....	999
odbc_result	1000
odbc_result_all	1000
odbc_rollback	1001
odbc_setoption.....	1001
odbc_specialcolumns.....	1002
odbc_statistics.....	1002
odbc_tableprivileges	1003
odbc_tables	1004
LXIX. Oracle 8 functions.....	1005
OCIBindByName	1008
OCICancel	1009

OCICollAppend.....	1009
OCICollAssign	1009
OCICollAssignElem.....	1010
OCICollGetElem	1010
OCICollMax	1010
OCICollSize	1011
OCICollTrim	1011
OCIColumnIsNULL.....	1011
OCIColumnName.....	1011
OCIColumnPrecision	1012
OCIColumnScale.....	1013
OCIColumnSize	1013
OCIColumnType	1014
OCIColumnTypeRaw	1015
OCICommit	1015
OCIDefineByName	1015
OCIError.....	1016
OCIExecute	1016
OCIFetch	1016
OCIFetchInto.....	1017
OCIFetchStatement	1017
OCIFreeCollection	1018
OCIFreeCursor	1018
OCIFreeDesc	1018
OCIFreeStatement	1019
OCIInternalDebug	1019
OCILoadLob.....	1019
OCILogOff	1019
OCILogon.....	1020
OCINewCollection	1021
OCINewCursor	1022
OCINewDescriptor.....	1023
OCINLogon.....	1025
OCINumCols.....	1027
OCIParse.....	1028
OCIPLogon.....	1028
OCIResult	1028
OCIRollback.....	1028
OCIRowCount	1029
OCISaveLob	1029
OCISaveLobFile.....	1030
OCIServerVersion.....	1030
OCISetPrefetch.....	1030
OCIStatementType	1030
OCIWriteLobToFile	1031
LXX. OpenSSL funkce	1033
openssl_free_key	1034
openssl_get_privatekey.....	1034
openssl_get_publickey.....	1034
openssl_open	1034
openssl_seal.....	1035
openssl_sign	1036

openssl_verify	1036
LXXI. Oracle functions	1038
Ora_Bind	1039
Ora_Close	1039
Ora_ColumnName	1039
Ora_ColumnSize	1040
Ora_ColumnType	1040
Ora_Commit	1040
Ora_CommitOff	1040
Ora_CommitOn	1041
Ora_Do	1041
Ora_Error	1041
Ora_ErrorCode	1042
Ora_Exec	1042
Ora_Fetch	1042
Ora_Fetch_Into	1042
Ora_GetColumn	1043
Ora_Logoff	1043
Ora_Logon	1043
Ora_Numcols	1044
Ora_Numrows	1044
Ora_Open	1044
Ora_Parse	1044
Ora_pLogon	1045
Ora_Rollback	1045
LXXII. Ovrimos SQL functions	1046
ovrimos_close	1047
ovrimos_commit	1047
ovrimos_connect	1047
ovrimos_cursor	1048
ovrimos_exec	1048
ovrimos_execute	1048
ovrimos_fetch_into	1048
ovrimos_fetch_row	1049
ovrimos_field_len	1050
ovrimos_field_name	1050
ovrimos_field_num	1050
ovrimos_field_type	1051
ovrimos_free_result	1051
ovrimos_longreadlen	1051
ovrimos_num_fields	1051
ovrimos_num_rows	1052
ovrimos_prepare	1052
ovrimos_result	1053
ovrimos_result_all	1053
ovrimos_rollback	1054
LXXIII. Output Control funkce	1056
flush	1057
ob_end_clean	1057
ob_end_flush	1057
ob_get_contents	1057
ob_get_length	1058

ob_implicit_flush.....	1058
ob_start	1058
LXXIV. Object property and method call overloading.....	1060
overload	1062
LXXV. PDF funkce	1063
pdf_add_annotation	1068
pdf_add_outline	1068
pdf_arc	1068
pdf_begin_page	1068
pdf_circle	1068
pdf_clip	1069
pdf_close	1069
pdf_close_image	1069
pdf_closepath	1069
pdf_closepath_fill_stroke	1070
pdf_closepath_stroke	1070
pdf_continue_text	1070
pdf_curveto	1070
pdf_end_page	1071
pdf_endpath	1071
pdf_execute_image	1071
pdf_fill	1072
pdf_fill_stroke	1072
pdf_get_image_height	1072
pdf_get_image_width	1072
pdf_get_parameter	1072
pdf_get_value	1073
pdf_lineto	1073
pdf_moveto	1073
pdf_open	1073
pdf_open_gif	1074
pdf_open_image_file	1074
pdf_open_jpeg	1075
pdf_open_memory_image	1075
pdf_open_png	1076
pdf_open_tiff	1076
pdf_place_image	1077
pdf_put_image	1077
pdf_rect	1077
pdf_restore	1077
pdf_rotate	1078
pdf_save	1078
pdf_scale	1078
pdf_set_border_color	1078
pdf_set_border_dash	1079
pdf_set_border_style	1079
pdf_set_char_spacing	1079
pdf_set_duration	1079
pdf_set_font	1080
pdf_set_horiz_scaling	1080
pdf_set_info	1080
pdf_set_leading	1081

pdf_set_parameter	1081
pdf_set_text_matrix	1081
pdf_set_text_pos	1082
pdf_set_text_rendering	1082
pdf_set_text_rise	1082
pdf_set_transition	1082
pdf_set_value	1083
pdf_set_word_spacing	1083
pdf_setdash	1083
pdf_setflat	1083
pdf_setgray	1083
pdf_setgray_fill	1084
pdf_setgray_stroke	1084
pdf_setlinecap	1084
pdf_setlinejoin	1084
pdf_setlinewidth	1084
pdf_setmiterlimit	1085
pdf_setrgbcolor	1085
pdf_setrgbcolor_fill	1085
pdf_setrgbcolor_stroke	1085
pdf_show	1086
pdf_show_boxed	1086
pdf_show_xy	1086
pdf_skew	1086
pdf_stringwidth	1087
pdf_stroke	1087
pdf_translate	1087
LXXVI. Funkce pro práci s Verisign Payflow Pro	1088
pfpro_cleanup	1089
pfpro_init	1089
pfpro_process	1089
pfpro_process_raw	1090
pfpro_version	1091
LXXVII. PHP volby & informace	1092
assert	1093
assert_options	1093
dl	1093
extension_loaded	1094
get_cfg_var	1094
get_current_user	1094
get_extension_funcs	1094
get_included_files	1095
get_loaded_extensions	1095
get_magic_quotes_gpc	1096
get_magic_quotes_runtime	1096
get_required_files	1096
getenv	1097
getlastmod	1098
getmyinode	1098
getmypid	1099
getmyuid	1099
getrusage	1099

ini_alter.....	1099
ini_get.....	1100
ini_restore.....	1100
ini_set.....	1100
php_logo_guid.....	1100
php_sapi_name.....	1101
php_uname.....	1101
phpcredits.....	1102
phpinfo.....	1103
phpversion.....	1104
putenv.....	1104
set_magic_quotes_runtime.....	1104
set_time_limit.....	1104
zend_logo_guid.....	1105
LXXVIII. POSIX functions.....	1106
posix_ctermid.....	1107
posix_getcwd.....	1107
posix_getegid.....	1107
posix_geteuid.....	1107
posix_getgid.....	1107
posix_getgrgid.....	1107
posix_getgrnam.....	1108
posix_getgroups.....	1108
posix_getlogin.....	1108
posix_getpgid.....	1108
posix_getpgrp.....	1108
posix_getpid.....	1109
posix_getppid.....	1109
posix_getpwnam.....	1109
posix_getpwuid.....	1110
posix_getrlimit.....	1111
posix_getsid.....	1111
posix_getuid.....	1111
posix_isatty.....	1111
posix_kill.....	1112
posix_mkfifo.....	1112
posix_setegid.....	1112
posix_seteuid.....	1112
posix_setgid.....	1113
posix_setpgid.....	1113
posix_setsid.....	1113
posix_setuid.....	1113
posix_times.....	1114
posix_ttyname.....	1114
posix_uname.....	1114
LXXIX. PostgreSQL functions.....	1116
pg_affected_rows.....	1120
pg_cancel_query.....	1120
pg_client_encoding.....	1120
pg_close.....	1121
pg_connect.....	1121
pg_connection_busy.....	1122

pg_connection_reset	1122
pg_connection_status	1122
pg_convert	1122
pg_copy_from	1123
pg_copy_to	1123
pg_dbname	1123
pg_delete	1123
pg_end_copy	1124
pg_escape_bytea	1124
pg_escape_string	1125
pg_fetch_array	1125
pg_fetch_object	1126
pg_fetch_result	1128
pg_fetch_row	1128
pg_field_is_null	1129
pg_field_name	1129
pg_field_num	1130
pg_field_prtlen	1130
pg_field_size	1130
pg_field_type	1131
pg_free_result	1131
pg_get_result	1131
pg_host	1131
pg_insert	1132
pg_last_error	1132
pg_last_notice	1133
pg_last_oid	1133
pg_lo_close	1133
pg_lo_create	1134
pg_lo_export	1134
pg_lo_import	1134
pg_lo_open	1135
pg_lo_read	1135
pg_lo_read_all	1136
pg_lo_seek	1136
pg_lo_tell	1136
pg_lo_unlink	1136
pg_lo_write	1137
pg_metadata	1137
pg_num_fields	1137
pg_num_rows	1138
pg_options	1138
pg_pconnect	1138
pg_port	1139
pg_put_line	1139
pg_query	1140
pg_result_error	1140
pg_result_status	1140
pg_select	1141
pg_send_query	1141
pg_set_client_encoding	1142
pg_trace	1142

pg_tty	1143
pg_untrace	1143
pg_update	1143
LXXX. Process Control Functions	1145
pcntl_exec	1147
pcntl_fork	1147
pcntl_signal	1147
pcntl_waitpid	1149
pcntl_wexitstatus	1149
pcntl_wifexited	1150
pcntl_wifsignaled	1150
pcntl_wifstopped	1150
pcntl_wstopsig	1150
pcntl_wtermsig	1151
LXXXI. Funkce Spouštění Programů	1152
escapeshellarg	1153
escapeshellcmd	1153
exec	1153
passthru	1154
system	1154
LXXXII. Printer functions	1156
printer_abort	1157
printer_close	1157
printer_create_brush	1157
printer_create_dc	1158
printer_create_font	1158
printer_create_pen	1159
printer_delete_brush	1160
printer_delete_dc	1160
printer_delete_font	1160
printer_delete_pen	1160
printer_draw_bmp	1160
printer_draw_chord	1161
printer_draw_ellipse	1162
printer_draw_line	1162
printer_draw_pie	1163
printer_draw_rectangle	1164
printer_draw_roundrect	1165
printer_draw_text	1165
printer_end_doc	1166
printer_end_page	1166
printer_get_option	1166
printer_list	1167
printer_logical_fontheight	1167
printer_open	1168
printer_select_brush	1168
printer_select_font	1169
printer_select_pen	1170
printer_set_option	1170
printer_start_doc	1172
printer_start_page	1172
printer_write	1172

LXXXIII. Pspell Functions	1174
pspell_add_to_personal	1175
pspell_add_to_session	1175
pspell_check	1175
pspell_clear_session	1176
pspell_config_create	1176
pspell_config_ignore	1177
pspell_config_mode	1177
pspell_config_personal	1178
pspell_config_repl	1179
pspell_config_runtogether	1179
pspell_config_save_repl	1180
pspell_new	1180
pspell_new_config	1181
pspell_new_personal	1181
pspell_save_wordlist	1182
pspell_store_replacement	1183
pspell_suggest	1183
LXXXIV. GNU Readline	1185
readline	1186
readline_add_history	1186
readline_clear_history	1186
readline_completion_function	1186
readline_info	1187
readline_list_history	1187
readline_read_history	1187
readline_write_history	1187
LXXXV. GNU Recode funkce	1188
recode	1189
recode_file	1189
recode_string	1189
LXXXVI. Regular Expression Functions (Perl-Compatible)	1190
Pattern Modifiers	1192
Pattern Syntax	1193
preg_grep	1217
preg_match	1218
preg_match_all	1219
preg_quote	1221
preg_replace	1222
preg_replace_callback	1224
preg_split	1224
LXXXVII. qtdom functions	1226
qdom_error	1227
qdom_tree	1227
LXXXVIII. Regular Expression Functions (POSIX Extended)	1228
ereg	1230
ereg_replace	1230
eregi	1232
eregi_replace	1232
split	1232
spliti	1233
sql_regcase	1234

LXXXIX. Funkce pro práci se semaforey a sdílenou pamětí.....	1235
sem_acquire.....	1236
sem_get.....	1236
sem_release.....	1236
shm_attach.....	1237
shm_detach.....	1237
shm_get_var.....	1237
shm_put_var.....	1237
shm_remove.....	1238
shm_remove_var.....	1238
XC. SESAM database functions	1239
sesam_affected_rows.....	1244
sesam_commit.....	1244
sesam_connect.....	1245
sesam_diagnostic.....	1245
sesam_disconnect.....	1247
sesam_errormsg.....	1248
sesam_execimm.....	1248
sesam_fetch_array.....	1249
sesam_fetch_result.....	1250
sesam_fetch_row.....	1251
sesam_field_array.....	1253
sesam_field_name.....	1255
sesam_free_result.....	1255
sesam_num_fields.....	1255
sesam_query.....	1256
sesam_rollback.....	1257
sesam_seek_row.....	1258
sesam_settransaction.....	1259
XCI. Session handling functions.....	1261
session_cache_expire.....	1266
session_cache_limiter.....	1266
session_decode.....	1266
session_destroy.....	1267
session_encode.....	1268
session_get_cookie_params.....	1268
session_id.....	1268
session_is_registered.....	1268
session_module_name.....	1269
session_name.....	1269
session_readonly.....	1270
session_register.....	1270
session_save_path.....	1271
session_set_cookie_params.....	1271
session_set_save_handler.....	1271
session_start.....	1273
session_unregister.....	1274
session_unset.....	1274
session_write_close.....	1274
XCII. Funkce pro práci se sdílenou pamětí.....	1276
shmop_close.....	1277
shmop_delete.....	1277

shmop_open.....	1277
shmop_read.....	1278
shmop_write	1278
shmop_size	1279
XCIII. Shockwave Flash functions	1280
swf_actiongeturl	1282
swf_actiongotoframe	1282
swf_actiongotolabel.....	1282
swf_actionnextframe	1282
swf_actionplay.....	1282
swf_actionprevframe	1282
swf_actionsettarget	1283
swf_actionstop.....	1283
swf_actiontogglequality	1283
swf_actionwaitforframe.....	1283
swf_addbuttonrecord	1283
swf_addcolor	1284
swf_closefile	1284
swf_definebitmap	1286
swf_definefont	1286
swf_defineline.....	1286
swf_definepoly	1286
swf_definerect.....	1287
swf_definetext.....	1287
swf_endbutton	1287
swf_enddoaction.....	1287
swf_endshape	1288
swf_endsymbol.....	1288
swf_fontsize.....	1288
swf_fontslant	1288
swf_fonttracking.....	1288
swf_getbitmapinfo	1288
swf_getfontinfo.....	1289
swf_getframe	1289
swf_labelframe	1289
swf_lookat	1289
swf_modifyobject.....	1290
swf_mulcolor.....	1290
swf_nextid	1290
swf_oncondition	1291
swf_openfile	1291
swf_ortho	1291
swf_ortho2.....	1292
swf_perspective	1292
swf_placeobject	1292
swf_polarview	1293
swf_popmatrix	1293
swf_posround	1293
swf_pushmatrix	1293
swf_removeobject.....	1293
swf_rotate	1294
swf_scale	1294

swf_setfont	1294
swf_setframe.....	1294
swf_shapearc	1294
swf_shapecurveto	1295
swf_shapecurveto3	1295
swf_shapefillbitmapclip.....	1295
swf_shapefillbitmaptile.....	1295
swf_shapefilloff	1296
swf_shapefillsolid	1296
swf_shapelinesolid	1296
swf_shapelineto	1296
swf_shapemoveto	1296
swf_showframe.....	1297
swf_startbutton	1297
swf_startdoaction.....	1297
swf_startshape	1297
swf_startsymbol.....	1297
swf_textwidth	1298
swf_translate.....	1298
swf_viewport	1298
XCIV. SNMP functions	1299
snmp_get_quick_print	1300
snmp_set_quick_print.....	1300
snmpget.....	1301
snmprealwalk.....	1301
snmpset	1301
snmpwalk.....	1302
snmpwalkoid.....	1302
XCV. Socket functions.....	1304
socket_accept.....	1307
socket_bind.....	1307
socket_close.....	1308
socket_connect	1308
socket_create	1308
socket_create_listen.....	1309
socket_create_pair	1309
socket_fd_alloc.....	1310
socket_fd_clear.....	1310
socket_fd_free	1311
socket_fd_isset	1311
socket_fd_set	1312
socket_fd_zero.....	1312
socket_getopt.....	1313
socket_getpeername	1313
socket_getsockname	1314
socket_iovec_add.....	1314
socket_iovec_alloc.....	1315
socket_iovec_delete.....	1315
socket_iovec_fetch	1316
socket_iovec_free	1316
socket_iovec_set.....	1317
socket_last_error.....	1317

socket_listen	1318
socket_read	1318
socket_readv	1319
socket_recv	1319
socket_recvfrom	1320
socket_recvmsg	1320
socket_select	1321
socket_send	1321
socket_sendmsg	1322
socket_sendto	1322
socket_set_nonblock	1323
socket_setopt	1323
socket_shutdown	1324
socket_strerror	1324
socket_write	1325
socket_writev	1326
XCVI. Funkce pro práci s řetězci	1327
addslashes	1328
addslashes	1328
bin2hex	1328
chop	1328
chr	1329
chunk_split	1329
convert_cyr_string	1330
count_chars	1330
crc32	1331
crypt	1331
echo	1331
explode	1332
get_html_translation_table	1333
get_meta_tags	1333
hebrew	1334
hebrevc	1334
htmlentities	1334
htmlspecialchars	1335
implode	1335
join	1336
levenshtein	1336
ltrim	1337
md5	1337
metaphone	1337
nl2br	1338
ord	1338
parse_str	1338
print	1339
printf	1339
quoted_printable_decode	1339
quotemeta	1339
rtrim	1340
setlocale	1340
similar_text	1340
soundex	1341

sprintf.....	1341
sscanf.....	1342
str_pad.....	1343
str_repeat.....	1344
str_replace.....	1344
strcasecmp.....	1344
strchr.....	1345
strcmp.....	1345
strcspn.....	1345
strip_tags.....	1346
stripslashes.....	1346
stripslashes.....	1346
stristr.....	1346
strlen.....	1347
strnatcasecmp.....	1347
strnatcmp.....	1347
strncasecmp.....	1348
strncmp.....	1348
strpos.....	1349
strrchr.....	1349
strrev.....	1350
strrpos.....	1350
strspn.....	1351
strstr.....	1351
strtok.....	1352
strtolower.....	1352
strtoupper.....	1353
strtr.....	1353
substr.....	1354
substr_count.....	1355
substr_replace.....	1355
trim.....	1356
ucfirst.....	1356
ucwords.....	1356
wordwrap.....	1357
XCVII. Sybase functions.....	1359
sybase_affected_rows.....	1360
sybase_close.....	1360
sybase_connect.....	1360
sybase_data_seek.....	1361
sybase_fetch_array.....	1361
sybase_fetch_field.....	1361
sybase_fetch_object.....	1362
sybase_fetch_row.....	1362
sybase_field_seek.....	1362
sybase_free_result.....	1363
sybase_get_last_message.....	1363
sybase_min_client_severity.....	1363
sybase_min_error_severity.....	1363
sybase_min_message_severity.....	1364
sybase_min_server_severity.....	1364
sybase_num_fields.....	1364

sybase_num_rows.....	1364
sybase_pconnect.....	1364
sybase_query	1365
sybase_result.....	1365
sybase_select_db	1365
XCVIII. URL Functions	1367
base64_decode.....	1368
base64_encode.....	1368
parse_url	1368
rawurldecode	1368
rawurlencode	1369
urldecode	1369
urlencode	1370
XCIX. Variable Functions.....	1371
doubleval.....	1372
empty	1372
floatval	1372
get_defined_vars.....	1373
get_resource_type.....	1373
gettype	1374
import_request_variables.....	1375
intval	1375
is_array	1376
is_bool	1376
is_callable.....	1376
is_double.....	1376
is_float	1376
is_int	1377
is_integer	1377
is_long	1377
is_null	1377
is_numeric	1378
is_object.....	1378
is_real	1378
is_resource.....	1378
is_scalar	1379
is_string	1379
isset	1380
print_r	1380
serialize.....	1381
settype.....	1382
strval	1383
unserialize.....	1383
unset.....	1385
var_dump	1387
var_export.....	1388
C. vpopmail functions	1390
vpopmail_add_alias_domain.....	1391
vpopmail_add_alias_domain_ex	1391
vpopmail_add_domain	1391
vpopmail_add_domain_ex	1392
vpopmail_add_user.....	1392

vpopmail_alias_add.....	1393
vpopmail_alias_del.....	1393
vpopmail_alias_del_domain.....	1394
vpopmail_alias_get.....	1394
vpopmail_alias_get_all.....	1395
vpopmail_auth_user.....	1395
vpopmail_del_domain.....	1396
vpopmail_del_domain_ex.....	1396
vpopmail_del_user.....	1397
vpopmail_error.....	1397
vpopmail_passwd.....	1398
vpopmail_set_user_quota.....	1398
CI. W32api functions.....	1400
w32api_deftype.....	1401
w32api_init_dtype.....	1401
w32api_invoke_function.....	1401
w32api_register_function.....	1402
w32api_set_call_method.....	1402
CII. WDDX funkce.....	1404
wddx_add_vars.....	1405
wddx_deserialize.....	1405
wddx_packet_end.....	1405
wddx_packet_start.....	1405
wddx_serialize_value.....	1405
wddx_serialize_vars.....	1406
CIII. XML parser functions.....	1407
utf8_decode.....	1416
utf8_encode.....	1416
xml_error_string.....	1416
xml_get_current_byte_index.....	1416
xml_get_current_column_number.....	1417
xml_get_current_line_number.....	1417
xml_get_error_code.....	1417
xml_parse.....	1418
xml_parse_into_struct.....	1418
xml_parser_create.....	1422
xml_parser_create_ns.....	1422
xml_parser_free.....	1422
xml_parser_get_option.....	1423
xml_parser_set_option.....	1423
xml_set_character_data_handler.....	1424
xml_set_default_handler.....	1424
xml_set_element_handler.....	1425
xml_set_end_namespace_decl_handler.....	1426
xml_set_external_entity_ref_handler.....	1426
xml_set_notation_decl_handler.....	1427
xml_set_object.....	1428
xml_set_processing_instruction_handler.....	1429
xml_set_start_namespace_decl_handler.....	1430
xml_set_unparsed_entity_decl_handler.....	1430
CIV. XMLRPC functions.....	1432
xmlrpc_decode.....	1433

xmlrpc_decode_request	1433
xmlrpc_encode	1433
xmlrpc_encode_request	1434
xmlrpc_get_type	1434
xmlrpc_parse_method_descriptions	1435
xmlrpc_server_add_introspection_data	1435
xmlrpc_server_call_method	1436
xmlrpc_server_create	1436
xmlrpc_server_destroy	1437
xmlrpc_server_register_introspection_callback	1437
xmlrpc_server_register_method	1438
xmlrpc_set_type	1438
CV. XSLT funkce	1440
xslt_closelog	1441
xslt_create	1441
xslt_errno	1441
xslt_error	1441
xslt_fetch_result	1441
xslt_free	1442
xslt_openlog	1442
xslt_output_begintransform	1442
xslt_output_endtransform	1443
xslt_process	1443
xslt_run	1444
xslt_set_sax_handler	1444
xslt_transform	1445
CVI. YAZ functions	1446
yaz_addinfo	1448
yaz_ccl_conf	1448
yaz_ccl_parse	1448
yaz_close	1449
yaz_connect	1449
yaz_database	1450
yaz_element	1450
yaz_errno	1450
yaz_error	1450
yaz_hits	1451
yaz_itemorder	1451
yaz_present	1453
yaz_range	1453
yaz_record	1453
yaz_scan	1454
yaz_scan_result	1455
yaz_search	1455
yaz_sort	1456
yaz_syntax	1457
yaz_wait	1457
CVII. Funkce pro práci s YP/NIS	1459
yp_err_string	1460
yp_errno	1460
yp_first	1460
yp_get_default_domain	1461

yp_master	1461
yp_match	1462
yp_next	1462
yp_order.....	1463
CVIII. Zip File Functions (Read Only Access)	1464
zip_close	1466
zip_entry_close.....	1466
zip_entry_compressedsize	1466
zip_entry_compressionmethod.....	1466
zip_entry_filesize.....	1466
zip_entry_name	1467
zip_entry_open	1467
zip_entry_read	1467
zip_open	1468
zip_read	1468
CIX. Zlib Compression Functions	1469
gzclose	1471
gzcompress	1471
gzdeflate.....	1471
gzencode	1471
gzeof	1472
gzfile	1472
gzgetc.....	1473
gzgets	1473
gzgetss	1473
gzinflate	1474
gzopen.....	1474
gzpassthru	1474
gzputs.....	1475
gzread	1475
gzrewind	1475
gzseek	1476
gztell	1476
gzuncompress	1476
gzwrite	1476
readgzfile	1477
V. Extending PHP 4.0.....	1478
24. Overview	1478
What Is Zend? and What Is PHP?	1479
25. Extension Possibilities	1480
External Modules.....	1481
Built-in Modules.....	1481
The Zend Engine	1482
26. Source Layout	1483
Extension Conventions	1485
Macros	1485
Memory Management	1485
Directory and File Functions.....	1486
String Handling	1486
Complex Types	1486
27. PHP's Automatic Build System	1487

28. Creating Extensions	1490
Compiling Modules	1492
29. Using Extensions	1494
30. Troubleshooting	1496
31. Source Discussion	1498
Module Structure	1499
Header File Inclusions	1499
Declaring Exported Functions	1499
Declaration of the Zend Function Block	1500
Declaration of the Zend Module Block	1501
Creation of get_module()	1503
Implementation of All Exported Functions	1503
Summary	1504
32. Accepting Arguments	1505
Determining the Number of Arguments	1506
Retrieving Arguments	1507
Old way of retrieving arguments (deprecated)	1509
Dealing with a Variable Number of Arguments/Optional Parameters	1510
Accessing Arguments	1512
Dealing with Arguments Passed by Reference	1515
Assuring Write Safety for Other Parameters	1516
33. Creating Variables	1518
Overview	1519
Longs (Integers)	1521
Doubles (Floats)	1522
Strings	1522
Booleans	1523
Arrays	1523
Objects	1526
Resources	1527
Macros for Automatic Global Variable Creation	1531
Creating Constants	1531
34. Duplicating Variable Contents: The Copy Constructor	1533
35. Returning Values	1535
36. Printing Information	1538
zend_printf()	1539
zend_error()	1539
Including Output in phpinfo()	1539
Execution Information	1540
37. Startup and Shutdown Functions	1542
38. Calling User Functions	1544
39. Initialization File Support	1547
40. Where to Go from Here	1550
41. Reference: Some Configuration Macros	1552
config.m4	1553
42. API Macros	1554

VI. FAQ: Často zodpovídané otázky	1556
43. Obecné informace	1556
44. E-mailové konference (mailing lists)	1559
45. Získání PHP	1562
46. Záležitosti databází	??
47. Instalace	??
48. Sestavovací (kompilační) problémy	??
49. Používání PHP	??
50. PHP a HTML	??
51. PHP a COM	??
52. PHP a jiné jazyky	??
53. Přejít z PHP 2 na PHP 3	??
54. Přejít z PHP 3 na PHP 4	??
55. Ostatní otázky.....	??
VII. Dodatky.....	??
A. Historie PHP a souvisejících projektů.....	??
Historie PHP	??
PHP/FI	??
PHP 3	??
PHP 4	??
Historie projektů souvisejících s PHP	??
PEAR	??
PHP Quality Assurance Initiative	??
PHP-GTK.....	??
Knihy o PHP	??
Ostatní publikace o PHP.....	??
B. Použití PHP z příkazové řádky	??
C. Přejít z PHP 3 na PHP 4.....	??
Co se změnilo v PHP 4.....	??
Současný běh PHP 3 a PHP 4.....	??
Převod konfiguračních souborů	??
Chování parseru	??
Hlášení chyb	??
Změny konfigurace	??
Přídavné varovné zprávy	??
Inicializátory	??
empty(" 0 ")	??
Chybějící funkce.....	??
Funkce chybějící kvůli konceptuálním změnám.....	??
Zavržené funkce a rozšíření	??
Změněný status funkce unset()	??
Rozšíření PHP 3	??
Substituce za proměnné v řetězcích	??
Cookies	??
Obsluha globálních proměnných.....	??
D. Přejít z PHP/FI 2 na PHP 3.....	??
O nekompatibilitách v 3.0	??
Otvírací/uzavírací značky (start/end tags)	??
syntaxe if..endif	??
syntaxe while	??
Typy výrazů	??

Chybové zprávy se změnily	??
Zkrácené vyhodnocení logických výrazů	??
Návratové hodnoty TRUE/FALSE	??
Jiné nekompatibility	??
E. Ladění (debugging) PHP	??
O debuggeru	??
Použití debuggeru	??
Protokol debuggeru	??
F. Extending PHP 3	??
Adding functions to PHP 3	??
Function Prototype	??
Function Arguments	??
Variable Function Arguments	??
Using the Function Arguments	??
Memory Management in Functions	??
Setting Variables in the Symbol Table	??
Returning simple values	??
Returning complex values	??
Using the resource list	??
Using the persistent resource table	??
Adding runtime configuration directives	??
Calling User Functions	??
HashTable *function_table	??
pval *object	??
pval *function_name	??
pval *retval	??
int param_count	??
pval *params[]	??
Reporting Errors	??
E_NOTICE	??
E_WARNING	??
E_ERROR	??
E_PARSE	??
E_CORE_ERROR	??
E_CORE_WARNING	??
E_COMPILE_ERROR	??
E_COMPILE_WARNING	??
E_USER_ERROR	??
E_USER_WARNING	??
E_USER_NOTICE	??
E_ALL	??
G. Seznam aliasů funkcí	??
H. Seznam vyhrazených slov	??
I. List of Resource Types	??
J. O tomto manuálu	??
Formáty	??
O uživatelských poznámkách	??
Jak najít více informací o PHP	??
Jak pomoci zlepšit dokumentaci	??
Jak generujeme formáty	??
K. missing stuff	??

Úvod

PHP, což znamená "PHP: Hypertext Preprocessor", je skriptovací jazyk vkládaný do HTML. Velká část jeho syntaxe je vypůjčená z C, Javy a Perlu. Několik vlastností je specifických pro PHP. Cílem tohoto jazyka je je umožnit webovým vývojářům rychle psát dynamicky generované stránky.

About this Manual

Tento manuál je napsán v XML s použitím DocBook XML DTD (<http://www.nwalsh.com/docbook/xml/>), s DSSSL (<http://www.jclark.com/dsssl/>) (Document Style and Semantics Specification Language) použitým na formátování. Nástroje použité na formátování HTML, TeX a RTF verzí jsou Jade (<http://www.jclark.com/jade/>), napsaný Jamesem Clarkem (<http://www.jclark.com/bio.htm>) a The Modular DocBook Stylesheets (<http://nwalsh.com/docbook/dsssl/>) napsané Normanem Walshem (<http://nwalsh.com/>). Systém dokumentace PHP udržuje Stig Sæther Bakken (<mailto:stig@php.net>).

Tento manuál si můžete stáhnout v různých jazycích a formátech, včetně PDF, prostého textu, HTML, WinHelpu a RTF z <http://www.php.net/docs.php>.

Denní snímky HTML verzí manuálu, včetně překladů, jsou k dispozici na <http://www.php.net/download-docs.php>.

Další informace o downloadu XML zdrojového kódu této dokumentace najdete na <http://cvs.php.net/>. Dokumentace je uložena v `phpdoc` modulu.

Část I. Začínáme

Kapitola 1. Introduction

What is PHP?

PHP (recursive acronym for "PHP: Hypertext Preprocessor") is a widely-used Open Source general-purpose scripting language that is especially suited for Web development and can be embedded into HTML.

Simple answer, but what does that mean? An example:

Příklad 1-1. An introductory example

```
<html>
  <head>
    <title>Example</title>
  </head>
  <body>

    <?php
      echo "Hi, I'm a PHP script!";
    ?>

  </body>
</html>
```

Notice how this is different from a script written in other languages like Perl or C -- instead of writing a program with lots of commands to output HTML, you write an HTML script with some embedded code to do something (in this case, output some text). The PHP code is enclosed in special start and end tags that allow you to jump into and out of "PHP mode".

What distinguishes PHP from something like client-side JavaScript is that the code is executed on the server. If you were to have a script similar to the above on your server, the client would receive the results of running that script, with no way of determining what the underlying code may be. You can even configure your web server to process all your HTML files with PHP, and then there's really no way that users can tell what you have up your sleeve.

The best things in using PHP are that it is extremely simple for a newcomer, but offers many advanced features for a professional programmer. Don't be afraid reading the long list of PHP's features. You can jump in, in a short time, and start writing simple scripts in a few hours.

Although PHP's development is focused on server-side scripting, you can do much more with it. Read on, and see more in the What can PHP do? section.

What can PHP do?

Anything. PHP is mainly focused on server-side scripting, so you can do anything any other CGI program can do, such as collect form data, generate dynamic page content, or send and receive cookies. But PHP can do much more.

There are three main fields where PHP scripts are used.

- Server-side scripting. This is the most traditional and main target field for PHP. You need three things to make this work. The PHP parser (CGI or server module), a webserver and a web browser. You need to run the webserver, with a connected PHP installation. You can access the PHP program output with a web browser, viewing the PHP page through the server. See the installation instructions section for more information.
- Command line scripting. You can make a PHP script to run it without any server or browser. You only need the PHP parser to use it this way. This type of usage is ideal for scripts regularly executed using cron (on *nix or Linux) or Task Scheduler (on Windows). These scripts can also be used for simple text processing tasks. See the section about Command line usage of PHP for more information.
- Writing client-side GUI applications. PHP is probably not the very best language to write windowing applications, but if you know PHP very well, and would like to use some advanced PHP features in your client-side applications you can also use PHP-GTK to write such programs. You also have the ability to write cross-platform applications this way. PHP-GTK is an extension to PHP, not available in the main distribution. If you are interested in PHP-GTK, visit it's own website (<http://gtk.php.net/>).

PHP can be used on all major operating systems, including Linux, many Unix variants (including HP-UX, Solaris and OpenBSD), Microsoft Windows, Mac OS X, RISC OS, and probably others. PHP has also support for most of the web servers today. This includes Apache, Microsoft Internet Information Server, Personal Web Server, Netscape and iPlanet servers, O'Reilly Website Pro server, Caudium, Xitami, OmniHTTPd, and many others. For the majority of the servers PHP has a module, for the others supporting the CGI standard, PHP can work as a CGI processor.

So with PHP, you have the freedom of choosing an operating system and a web server. Furthermore, you also have the choice of using procedural programming or object oriented programming, or a mixture of them. Although not every standard OOP feature is realized in the current version of PHP, many code libraries and large applications (including the PEAR library) are written only using OOP code.

With PHP you are not limited to output HTML. PHP's abilities includes outputting images, PDF files and even Flash movies (using libswf and Ming) generated on the fly. You can also output easily any text, such as XHTML and any other XML file. PHP can autogenerate these files, and save them in the file system, instead of printing it out, forming a server-side cache for your dynamic content.

One of the strongest and most significant feature in PHP is its support for a wide range of databases. Writing a database-enabled web page is incredibly simple. The following databases are currently supported:

Adabas D	Ingres	Oracle (OCI7 and OCI8)
dBase	InterBase	Ovrimos
Empress	FrontBase	PostgreSQL
FilePro (read-only)	mSQL	Solid
Hyperwave	Direct MS-SQL	Sybase
IBM DB2	MySQL	Velocis
Informix	ODBC	Unix dbm

We also have a DBX database abstraction extension allowing you to transparently use any database supported by that extension. Additionally PHP supports ODBC, the Open Database Connection standard, so you can connect to any other database supporting this world standard.

PHP also has support for talking to other services using protocols such as LDAP, IMAP, SNMP, NNTP, POP3, HTTP, COM (on Windows) and countless others. You can also open raw network sockets and interact using any other protocol. PHP has support for the WDDX complex data exchange between virtually all Web programming languages. Talking about interconnection, PHP has support for instantiation of Java objects and using them transparently as PHP objects. You can

also use our CORBA extension to access remote objects.

PHP has extremely useful text processing features, from the POSIX Extended or Perl regular expressions to parsing XML documents. For parsing and accessing XML documents, we support the SAX and DOM standards. You can use our XSLT extension to transform XML documents.

While using PHP in the ecommerce field, you'll find the Cybercash payment, CyberMUT, VeriSign Payflow Pro and C CVS functions useful for your online payment programs.

At last but not least, we have many other interesting extensions, the mnoGoSearch search engine functions, the IRC Gateway functions, many compression utilities (gzip, bz2), calendar conversion, translation...

As you can see this page is not enough to list all the features and benefits PHP can offer. Read on in the sections about installing PHP, and see the function reference part for explanation of the extensions mentioned here.

Kapitola 2. Instalace

General Installation Considerations

Before installing first, you need to know what do you want to use PHP for. There are three main fields you can use PHP, as described in the What can PHP do? section:

- Server-side scripting
- Command line scripting
- Client-side GUI applications

For the first and most common form, you need three things: PHP itself, a web server and a web browser. You probably already have a web browser, and depending on your operating system setup, you may also have a web server (eg. Apache on Linux or IIS on Windows). You may also rent webspace at a company. This way, you don't need to set up anything on your own, only write your PHP scripts, upload it to the server you rent, and see the results in your browser. You can find a list of hosting companies at <http://hosts.php.net/>.

While setting up the server and PHP on your own, you have two choices for the method of connecting PHP to the server. For many servers PHP has a direct module interface (also called SAPI). These servers include Apache, Microsoft Internet Information Server, Netscape and iPlanet servers. Many other servers have support for ISAPI, the Microsoft module interface (OmniHTTPd for example). If PHP has no module support for your web server, you can always use it as a CGI processor. This means you set up your server to use the command line executable of PHP (`php.exe` on Windows) to process all PHP file requests on the server.

If you are also interested to use PHP for command line scripting (eg. write scripts autogenerating some images for you offline, or processing text files depending on some arguments you pass to them), you always need the command line executable. For more information, read the section about writing command line PHP applications. In this case, you need no server and no browser.

With PHP you can also write client side GUI applications using the PHP-GTK extension. This is a completely different approach than writing web pages, as you do not output any HTML, but manage windows and objects within them. For more information about PHP-GTK, please visit the site dedicated to this extension (<http://gtk.php.net/>). PHP-GTK is not included in the official PHP distribution.

From now on, this section deals with setting up PHP for web servers on Unix and Windows with server module interfaces and CGI executables.

Downloading PHP, the source code, and binary distributions for Windows can be found at <http://www.php.net/>. We recommend you to choose a mirror (<http://www.php.net/mirrors.php>) nearest to you for downloading the distributions.

Unix/HP-UX installs

This section contains notes and hints specific to installing PHP on HP-UX systems.

Příklad 2-1. Installation Instructions for HP-UX 10

From: paul_mckay@clearwater-it.co.uk
04-Jan-2001 09:49

(These tips are for PHP 4.0.4 and Apache v1.3.9)

So you want to install PHP and Apache on a HP-UX 10.20 box?

1. You need gzip, download a binary distribution from
<http://hpux.connect.org.uk/ftp/hpux/Gnu/gzip-1.2.4a/gzip-1.2.4a-sd-10.20.depot.Z>
uncompress the file and install using swinstall
2. You need gcc, download a binary distribution from
<http://gatekeep.cs.utah.edu/ftp/hpux/Gnu/gcc-2.95.2/gcc-2.95.2-sd-10.20.depot.gz>
gunzip this file and install gcc using swinstall.
3. You need the GNU binutils, you can download a binary distribution from
<http://hpux.connect.org.uk/ftp/hpux/Gnu/binutils-2.9.1/binutils-2.9.1-sd-10.20.depot.gz>
gunzip and install using swinstall.
4. You now need bison, you can download a binary distribution from
<http://hpux.connect.org.uk/ftp/hpux/Gnu/bison-1.28/bison-1.28-sd-10.20.depot.gz>
install as above.
5. You now need flex, you need to download the source from one of the
<http://www.gnu.org/mirrors>. It is in the <filename>non-gnu</filename> directory of the ftp site.
Download the file, gunzip, then tar -xvf it. Go into the newly created flex directory and do a ./configure, then a make, and then a make install

If you have errors here, it's probably because gcc etc. are not in your PATH so add them to your PATH.

Right, now into the hard stuff.

6. Download the PHP and apache sources.

7. gunzip and tar -xvf them.

We need to hack a couple of files so that they can compile ok.

8. Firstly the configure file needs to be hacked because it seems to lose track of the fact that you are a hpux machine, there will be a better way of doing this but a cheap and cheerful hack is to put
lt_target=hpux10.20
on line 47286 of the configure script.

9. Next, the Apache GuessOS file needs to be hacked. Under
apache_1.3.9/src/helpers change line 89 from
"echo "hp\${HPUXMACH}-hpux\${HPUXVER}"; exit 0"
to:
"echo "hp\${HPUXMACH}-hp-hpux\${HPUXVER}"; exit 0"

10. You cannot install PHP as a shared object under HP-UX so you must compile it as a static, just follow the instructions at the Apache page.

11. PHP and apache should have compiled OK, but Apache won't start. you need to create a new user for Apache, eg www, or apache. You then change lines 252 and 253 of the conf/httpd.conf in Apache so that instead of
User nobody
Group nogroup

```
you have something like
User www
Group sys
```

This is because you can't run Apache as nobody under hp-ux.
Apache and PHP should then work.

Hope this helps somebody,
Paul Mckay.

Unix/Linux installs

This section contains notes and hints specific to installing PHP on Linux distributions.

Using Packages

Many Linux distributions have some sort of package installation system, such as RPM. This can assist in setting up a standard configuration, but if you need to have a different set of features (such as a secure server, or a different database driver), you may need to build PHP and/or your webserver. If you are unfamiliar with building and compiling your own software, it is worth checking to see whether somebody has already built a packaged version of PHP with the features you need.

Unix/Mac OS X installs

This section contains notes and hints specific to installing PHP on Mac OS X Server.

Using Packages

There are a few pre-packaged and pre-compiled versions of PHP for Mac OS X. This can help in setting up a standard configuration, but if you need to have a different set of features (such as a secure server, or a different database driver), you may need to build PHP and/or your web server yourself. If you are unfamiliar with building and compiling your own software, it's worth checking whether somebody has already built a packaged version of PHP with the features you need.

Compiling for OS X server

There are two slightly different versions of Mac OS X, client and server. The following is for OS X Server.

Příklad 2-2. Mac OS X server install

1. Get the latest distributions of Apache and PHP
2. Untar them, and run the configure program on Apache like so.

```
./configure --exec-prefix=/usr \
```

```
--localstatedir=/var \
--mandir=/usr/share/man \
--libexecdir=/System/Library/Apache/Modules \
--iconsdir=/System/Library/Apache/Icons \
--includedir=/System/Library/Frameworks/Apache.framework/Versions/1.3/Headers \
--enable-shared=max \
--enable-module=most \
--target=apache
```

4. You may also want to add this line:

```
setenv OPTIM=-O2
```

If you want the compiler to do some optimization.

5. Next, go to the PHP 4 source directory and configure it.

```
./configure --prefix=/usr \
--sysconfdir=/etc \
--localstatedir=/var \
--mandir=/usr/share/man \
--with-xml \
--with-apache=/src/apache_1.3.12
```

If you have any other additions (MySQL, GD, etc.), be sure to add them here. For the --with-apache string, put in the path to your apache source directory, for example "/src/apache_1.3.12".

6. make

7. make install

This will add a directory to your Apache source directory under src/modules/php4.

8. Now, reconfigure Apache to build in PHP 4.

```
./configure --exec-prefix=/usr \
--localstatedir=/var \
--mandir=/usr/share/man \
--libexecdir=/System/Library/Apache/Modules \
--iconsdir=/System/Library/Apache/Icons \
--includedir=/System/Library/Frameworks/Apache.framework/Versions/1.3/Headers \
--enable-shared=max \
--enable-module=most \
--target=apache \
--activate-module=src/modules/php4/libphp4.a
```

You may get a message telling you that libmodphp4.a is out of date. If so, go to the src/modules/php4 directory inside your apache source directory and run this command:

```
ranlib libmodphp4.a
```

Then go back to the root of the apache source directory and run the above configure command again. That'll bring the link table up to date.

9. make

10. make install

11. copy and rename the php.ini-dist file to your "bin" directory from your PHP 4 source directory:

```
cp php.ini-dist /usr/local/bin/php.ini

or (if you don't have a local directory)

cp php.ini-dist /usr/bin/php.ini
```

Other examples for Mac OS X client

(<http://www.stepwise.com/Articles/Workbench/Apache-1.3.14-MacOSX.html>) and Mac OS X server (<http://www.stepwise.com/Articles/Workbench/Apache-1.3.14-MacOSX.html>) are available at Stepwise (<http://www.stepwise.com/>).

Compiling for MacOS X client

Those tips are graciously provided by Marc Liyanage (<http://www.entropy.ch/software/macosx>).

The PHP module for the Apache web server included in Mac OS X. This version includes support for the MySQL and PostgreSQL databases.

NOTE: Be careful when you do this, you could screw up your Apache web server!

Do this to install:

- 1. Open a terminal window
- 2. Type "wget <http://www.diax.ch/users/liyanage/software/macosx/libphp4.so.gz>", wait for download to finish
- 3. Type "gunzip libphp4.so.gz"
- 4. Type "sudo apxs -i -a -n php4 libphp4.so"

Now type "sudo open -a TextEdit /etc/httpd/httpd.conf" TextEdit will open with the web server configuration file. Locate these two lines towards the end of the file: (Use the Find command)

```
#AddType application/x-httpd-php .php
#AddType application/x-httpd-php-source .phps
```

Remove the two hash marks (#), then save the file and quit TextEdit.

Finally, type "sudo apachectl graceful" to restart the web server.

PHP should now be up and running. You can test it by dropping a file into your "Sites" folder which is called "test.php". Into that file, write this line: "<?php phpinfo() ?>".

Now open up `127.0.0.1/~your_username/test.php` in your web browser. You should see a status table with information about the PHP module.

Unix/OpenBSD installs

This section contains notes and hints specific to installing PHP on OpenBSD (<http://www.openbsd.org/>).

Using Ports

This is the recommended method of installing PHP on OpenBSD, as it will have the latest patches and security fixes applied to it by the maintainers. To use this method, ensure that you have a recent ports tree (<http://www.openbsd.org/ports.html>). Then simply find out which flavors you wish to install, and issue the **make install** command. Below is an example of how to do this.

Příklad 2-3. OpenBSD Ports Install Example

```
$ cd /usr/ports/www/php4
$ make show VARNAME=FLAVORS
  (choose which flavors you want from the list)
$ env FLAVOR="imap gettext ldap mysql gd" make install
$ /usr/local/sbin/php4-enable
```

Using Packages

There are pre-compiled packages available for your release of OpenBSD (<http://www.openbsd.org/>). These integrate automatically with the version of Apache installed with the OS. However, since there are a large number of options (called *flavors*) available for this port, you may find it easier to compile it from source using the ports tree. Read the `packages(7)` (<http://www.openbsd.org/cgi-bin/man.cgi?query=packages>) manual page for more information in what packages are available.

Unix/Solaris installs

This section contains notes and hints specific to installing PHP on Solaris systems.

Required software

Solaris installs often lack C compilers and their related tools. The required software is as follows:

- gcc (recommended, other C compilers may work)
- make
- flex
- bison
- m4

- autoconf
- automake
- perl
- gzip
- tar

In addition, you will need to install (and possibly compile) any additional software specific to your configuration, such as Oracle or MySQL.

Using Packages

You can simplify the Solaris install process by using pkgadd to install most of your needed components.

Installation on UNIX systems

This section will guide you through the general configuration and installation of PHP on Unix systems. Be sure to investigate any sections specific to your platform or web server before you begin the process.

Prerequisite knowledge and software:

- Basic UNIX skills (being able to operate "make" and a C compiler, if compiling)
- An ANSI C compiler (if compiling)
- flex (for compiling)
- bison (for compiling)
- A web server
- Any module specific components (such as gd, pdf libs, etc.)

There are several ways to install PHP for the Unix platform, either with a compile and configure process, or through various pre-packaged methods. This documentation is mainly focused around the process of compiling and configuring PHP.

The initial PHP setup and configuration process is controlled by the use of the commandline options of the `configure` script. This page outlines the usage of the most common options, but there are many others to play with. Check out the Complete list of configure options for an exhaustive rundown. There are several ways to install PHP:

- As an Apache module
- As an `httpd` module
- For use with AOLServer, NSAPI, `phttpd`, `Pi3Web`, `Roxen`, `thttpd`, or `Zeus`.
- As a CGI executable

Apache Module Quick Reference

PHP can be compiled in a number of different ways, but one of the most popular is as an Apache module. The following is a quick installation overview.

Příklad 2-4. Quick Installation Instructions for PHP 4 (Apache Module Version)

```

1. gunzip apache_1.3.x.tar.gz
2. tar xvf apache_1.3.x.tar
3. gunzip php-x.x.x.tar.gz
4. tar xvf php-x.x.x.tar
5. cd apache_1.3.x
6. ./configure --prefix=/www
7. cd ../php-x.x.x
8. ./configure --with-mysql --with-apache=../apache_1.3.x --enable-track-vars
9. make
10. make install
11. cd ../apache_1.3.x
12. ./configure --activate-module=src/modules/php4/libphp4.a
13. make
14. make install
15. cd ../php-x.x.x
16. cp php.ini-dist /usr/local/lib/php.ini
17. Edit your httpd.conf or srm.conf file and add:
    AddType application/x-httpd-php .php

18. Use your normal procedure for restarting the Apache server. (You must
    stop and restart the server, not just cause the server to reload by
    use a HUP or USR1 signal.)

```

Building

When PHP is configured, you are ready to build the CGI executable. The command **make** should take care of this. If it fails and you can't figure out why, see the Problems section.

Installation on Windows systems

This section applies to Windows 95/98/Me and Windows NT/2000/XP. Do not expect PHP to work on 16 bit platforms such as Windows 3.1. Sometimes we refer to the supported Windows platforms as Win32.

There are two main ways to install PHP for Windows: either manually or by using the InstallShield installer.

If you have Microsoft Visual Studio, you can also build PHP from the original source code.

Once you have PHP installed on your Windows system, you may also want to load various extensions for added functionality.

Windows InstallShield

The Windows PHP installer available from the downloads page at <http://www.php.net/>, this installs the CGI version of PHP and, for IIS, PWS, and Xitami, configures the web server as well. Also note, that while the InstallShield installer is an easy way to make PHP work, it is restricted in many aspects, as automatic setup of extensions for example is not supported.

Install your selected HTTP server on your system and make sure that it works.

Run the executable installer and follow the instructions provided by the installation wizard. Two types of installation are supported - standard, which provides sensible defaults for all the settings it can, and advanced, which asks questions as it goes along.

The installation wizard gathers enough information to set up the `php.ini` file and configure the web server to use PHP. For IIS and also PWS on NT Workstation, a list of all the nodes on the server with script map settings is displayed, and you can choose those nodes to which you wish to add the PHP script mappings.

Once the installation has completed the installer will inform you if you need to restart your system, restart the server, or just start using PHP.

Varování

Be aware, that this setup of PHP is not secure. If you would like to have a secure PHP setup, you'd better go on the manual way, and set every option carefully. This automatically working setup gives you an instantly working PHP installation, but it is not meant to be used on online servers.

Manual Installation Steps

This install guide will help you manually install and configure PHP on your Windows webserver. You need to download the zip binary distribution from the downloads page at <http://www.php.net/>. The original version of this guide was compiled by Bob Silva (mailto:bob_silva@mail.umesd.k12.or.us), and can be found at <http://www.umesd.k12.or.us/php/win32install.html>.

This guide provides manual installation support for:

- Personal Web Server 3 and 4 or newer
- Internet Information Server 3 and 4 or newer
- Apache 1.3.x
- OmniHTTPd 2.0b1 and up
- O'Reilly Website Pro
- Xitami
- Netscape Enterprise Server, iPlanet

PHP 4 for Windows comes in two flavours - a CGI executable (`php.exe`), and several SAPI modules (for example: `php4isapi.dll`). The latter form is new to PHP 4, and provides significantly improved performance and some new functionality.

Varování

The SAPI modules have been significantly improved in the 4.1 release, however, you may find that you encounter possible server errors or other server modules such as ASP failing, in older systems.

If you choose one of the SAPI modules and use Windows 95, be sure to download the DCOM update from the Microsoft DCOM pages

(<http://download.microsoft.com/msdownload/dcom/95/x86/en/dcom95.exe>). For the ISAPI module, an ISAPI 4.0 compliant Web server is required (tested on IIS 4.0, PWS 4.0 and IIS 5.0). IIS 3.0 is *NOT* supported. You should download and install the Windows NT 4.0 Option Pack with IIS 4.0 if you want native PHP support.

The following steps should be performed on all installations before the server specific instructions.

- Extract the distribution file to a directory of your choice. `c:\php\` is a good start.
- You need to ensure that the DLLs which PHP uses can be found. The precise DLLs involved depend on which web server you use and whether you want to run PHP as a CGI or as a server module. `php4ts.dll` is always used. If you are using a server module (e.g. ISAPI or Apache) then you will need the relevant DLL from the `sapi` folder. If you are using any PHP extension DLLs then you will need those as well. To make sure that the DLLs can be found, you can either copy them to the system directory (e.g. `winnt\system32` or `windows\system`) or you can make sure that they live in the same directory as the main PHP executable or DLL your web server will use (e.g. `php.exe`, `php4apache.dll`).

The PHP binary, the SAPI modules, and some extensions rely on external DLLs for execution.

Make sure that these DLLs in the distribution exist in a directory that is in the Windows PATH.

The best bet to do it is to copy the files below into your system directory, which is typically:

```
c:\windows\system for Windows 9x/ME
c:\winnt\system32 for Windows NT/2000
c:\windows\system32 for Windows XP
```

The files to copy are:

`php4ts.dll`, if it already exists there, overwrite it

The files in your distribution's 'dlls' directory. If you have them already installed on your system, overwrite them on

Download the latest version of the Microsoft Data Access Components (MDAC) for your platform, especially if you use Microsoft Windows 9x/NT4. MDAC is available at <http://www.microsoft.com/data/>.

- Copy your chosen ini file (see below) to your '%WINDOWS%' directory on Windows 9x/Me or to your '%SYSTEMROOT%' directory under Windows NT/2000/XP and rename it to `php.ini`. Your '%WINDOWS%' or '%SYSTEMROOT%' directory is typically:

```
c:\windows for Windows 9x/ME/XP
c:\winnt or c:\winnt40 for NT/2000 servers
```

There are two ini files distributed in the zip file, `php.ini-dist` and `php.ini-optimized`. We advise you to use `php.ini-optimized`, because we optimized the default settings in this file for performance, and security. The best is to study all the ini settings and set every element manually yourself. If you would like to achieve the best security, then this is the way for you, although PHP works fine with these default ini files.

- Edit your new `php.ini` file:
 - You will need to change the 'extension_dir' setting to point to your `php-install-dir`, or where

you have placed your `php_*.dll` files. ex: `c:\php\extensions`

- If you are using OmniHTTpd, do not follow the next step. Set the 'doc_root' to point to your webserver's document_root. For example: `c:\apache\htdocs` or `c:\webroot`
- Choose which extensions you would like to load when PHP starts. See the section about Windows extensions, about how to set up one, and what is already built in. Note that on a new installation it is advisable to first get PHP working and tested without any extensions before enabling them in `php.ini`.
- On PWS and IIS, you can set the `browscap.ini` to point to:
`c:\windows\system\inetsrv\browscap.ini` on Windows 9x/Me,
`c:\winnt\system32\inetsrv\browscap.ini` on NT/2000, and
`c:\windows\system32\inetsrv\browscap.ini` on XP.
- Note that the `mibs` directory supplied with the Windows distribution contains support files for SNMP. This directory should be moved to `DRIVE:\usr\mibs` (DRIVE being the drive where PHP is installed.)
- If you're using NTFS on Windows NT, 2000 or XP, make sure that the user running the webserver has read permissions to your `php.ini` (e.g. make it readable by Everyone).
- For PWS give execution permission to the webroot:
 - Start PWS Web Manager
 - Edit Properties of the "Home"-Directory
 - Select the "execute"-Checkbox

Building from source

Before getting started, it is worthwhile answering the question: "Why is building on Windows so hard?" Two reasons come to mind:

1. Windows does not (yet) enjoy a large community of developers who are willing to freely share their source. As a direct result, the necessary investment in infrastructure required to support such development hasn't been made. By and large, what is available has been made possible by the porting of necessary utilities from Unix. Don't be surprised if some of this heritage shows through from time to time.
2. Pretty much all of the instructions that follow are of the "set and forget" variety. So sit back and try follow the instructions below as faithfully as you can.

Preparations

Before you get started, you have a lot to download...

- For starters, get the Cygwin toolkit from the closest cygwin (<http://sources.redhat.com/cygwin/download.html>) mirror site. This will provide you most of the popular GNU utilities used by the build process.
- Download the rest of the build tools you will need from the PHP site at <http://www.php.net/extra/win32build.zip>.

- Get the source code for the DNS name resolver used by PHP at http://www.php.net/extra/bindlib_w32.zip. This is a replacement for the `resolv.lib` library included in `win32build.zip`.
- If you don't already have an unzip utility, you will need one. A free version is available from InfoZip (<http://www.cdrom.com/pub/infozip/UnZip.html>).

Finally, you are going to need the source to PHP 4 itself. You can get the latest development version using anonymous CVS (<http://www.php.net/anoncv.php>). If you get a snapshot (<http://snaps.php.net/>) or a source (<http://www.php.net/downloads.php>) tarball, you not only will have to untar and unzip it, but you will have to convert the bare linefeeds to crlf's in the `*.dsp` and `*.dsw` files before Microsoft Visual C++ will have anything to do with them.

Poznámka: Place the `zend` and `TSRM` directories inside the `php4` directory in order for the projects to be found during the build process.

Putting it all together

- Follow the instructions for installing the unzip utility of your choosing.
- Execute `setup.exe` and follow the installation instructions. If you choose to install to a path other than `c:\cygnus`, let the build process know by setting the Cygwin environment variable. On Windows 95/98 setting an environment variable can be done by placing a line in your `autoexec.bat`. On Windows NT, go to My Computer => Control Panel => System and select the environment tab.

Varování

Make a temporary directory for Cygwin to use, otherwise many commands (particularly bison) will fail. On Windows 95/98, `mkdir c:\TMP`. For Windows NT, `mkdir %SystemDrive%\tmp`.

- Make a directory and unzip `win32build.zip` into it.
- Launch Microsoft Visual C++, and from the menu select Tools => Options. In the dialog, select the directories tab. Sequentially change the dropdown to Executables, Includes, and Library files, and ensure that `cygwin\bin`, `win32build\include`, and `win32build\lib` are in each list, respectively. (To add an entry, select a blank line at the end of the list and begin typing). Typical entries will look like this:

- `c:\cygnus\bin`
- `c:\php-win32build\include`
- `c:\php-win32build\lib`

Press OK, and exit out of Visual C++.

- Make another directory and unzip `bindlib_w32.zip` into it. Decide whether you want to have debug symbols available (bindlib - Win32 Debug) or not (bindlib - Win32 Release). Build the appropriate configuration:

- For GUI users, launch VC++, and then select File => Open Workspace and select bindlib. Then select Build=>Set Active Configuration and select the desired configuration. Finally select Build=>Rebuild All.
- For command line users, make sure that you either have the C++ environment variables registered, or have run **vcvars.bat**, and then execute one of the following:
 - **msdev bindlib.dsp /MAKE "bindlib - Win32 Debug"**
 - **msdev bindlib.dsp /MAKE "bindlib - Win32 Release"**
- At this point, you should have a usable `resolv.lib` in either your Debug or Release subdirectories. Copy this file into your `win32build\lib` directory over the file by the same name found in there.

Compiling

The best way to get started is to build the standalone/CGI version.

- For GUI users, launch VC++, and then select File => Open Workspace and select php4ts. Then select Build=>Set Active Configuration and select the desired configuration. Finally select Build=>Rebuild All.
- For command line users, make sure that you either have the C++ environment variables registered, or have run **vcvars.bat**, and then execute one of the following:
 - **msdev php4ts.dsp /MAKE "php4ts - Win32 Debug_TS"**
 - **msdev php4ts.dsp /MAKE "php4ts - Win32 Release_TS"**
- At this point, you should have a usable `php.exe` in either your Debug_TS or Release_TS subdirectories.

Repeat the above steps with `php4isapi.dsp` (which can be found in `sapi\isapi`) in order to build the code necessary for integrating PHP with Microsoft IIS.

Installation of Windows extensions

After installing PHP and a webserver on Windows, you will probably want to install some extensions for added functionality. The following table describes some of the extensions available. You can choose which extensions you would like to load when PHP starts by uncommenting the `'extension=php_*.dll'` lines in `php.ini`. You can also load a module dynamically in your script using `dl()`.

The DLLs for PHP extensions are prefixed with `'php_'` in PHP 4 (and `'php3_'` in PHP 3). This prevents confusion between PHP extensions and their supporting libraries.

Poznámka: In PHP 4.0.6 Bcmath, Calendar, COM, FTP, MySQL, ODBC, PCRE, Session, WDDX and XML support is *built in*. You don't need to load any additional extensions in order to use these functions. See your distributions `README.txt` or `install.txt` for a list of built in modules.

Poznámka: Some of these extensions need extra DLLs to work. Couple of them can be found in the distribution package, in the 'dlls' folder but some, for example Oracle (php_oci8.dll) require DLLs which are not bundled with the distribution package.

Copy the bundled DLLs from 'DLLs' folder to your Windows PATH, safe places are:

c:\windows\system for Windows 9x/Me
 c:\winnt\system32 for Windows NT/2000
 c:\windows\system32 for Windows XP

If you have them already installed on your system, overwrite them only if something doesn't work correctly (Before overwriting them, it is a good idea to make a backup of them, or move them to another folder - just in case something goes wrong).

Tabulka 2-1. PHP Extensions

Extension	Description	Notes
php_bz2.dll	bzip2 compression functions	None
php_calendar.dll	Calendar conversion functions	Built in since PHP 4.0.3
php_cpdf.dll	ClibPDF functions	None
php_crack.dll	Crack functions	None
php3_crypt.dll	Crypt functions	unknown
php_ctype.dll	ctype family functions	None
php_curl.dll	CURL, Client URL library functions	Requires: libeay32.dll, ssleay32.dll (bundled)
php_cybercash.dll	Cybercash payment functions	None
php_db.dll	DBM functions	Deprecated. Use DBA instead (php_dba.dll)
php_dba.dll	DBA: DataBase (dbm-style) Abstraction layer functions	None
php_dbase.dll	dBase functions	None
php3_dbm.dll	Berkeley DB2 library	unknown
php_domxml.dll	DOM XML functions	Requires: libxml2.dll (bundled)
php_dotnet.dll	.NET functions	None
php_exif.dll	Read EXIF headers from JPEG	None
php_fbsql.dll	FrontBase functions	None
php_fdf.dll	FDF: Forms Data Format functions.	Requires: fdfk.dll (bundled)
php_filepro.dll	filePro functions	Read-only access
php_ftp.dll	FTP functions	Built-in since PHP 4.0.3
php_gd.dll	GD library image functions	None
php_gettext.dll	Gettext functions	Requires: gnu_gettext.dll (bundled)
php_hyperwave.dll	HyperWave functions	None

Extension	Description	Notes
php_iconv.dll	ICONV charset conversion	Requires: iconv-1.3.dll (bundled)
php_ifx.dll	Informix functions	Requires: Informix libraries
php_iisfunc.dll	IIS management functions	None
php_imap.dll	IMAP POP3 and NNTP functions	PHP 3: php3_imap4r1.dll
php_ingres.dll	Ingres II functions	Requires: Ingres II libraries
php_interbase.dll	InterBase functions	Requires: gds32.dll (bundled)
php_java.dll	Java extension	Requires: jvm.dll (bundled)
php_ldap.dll	LDAP functions	Requires: libsasl.dll (bundled)
php_mhash.dll	Mhash Functions	None
php_ming.dll	Ming functions for Flash	None
php_msql.dll	mSQL functions	Requires: msql.dll (bundled)
php3_msql1.dll	mSQL 1 client	unknown
php3_msql2.dll	mSQL 2 client	unknown
php_mssql.dll	MSSQL functions	Requires: ntwdblib.dll (bundled)
php3_mysql.dll	MySQL functions	Built-in in PHP 4
php3_nsmail.dll	Netscape mail functions	unknown
php3_oci73.dll	Oracle functions	unknown
php_oci8.dll	Oracle 8 functions	Requires: Oracle 8 client libraries
php_openssl.dll	OpenSSL functions	Requires: libeay32.dll (bundled)
php_oracle.dll	Oracle functions	Requires: Oracle 7 client libraries
php_pdf.dll	PDF functions	None
php_pgsql.dll	PostgreSQL functions	None
php_printer.dll	Printer functions	None
php_sablot.dll	XSLT functions	Requires: sablot.dll (bundled)
php_snmp.dll	SNMP get and walk functions	NT only!
php_sybase_ct.dll	Sybase functions	Requires: Sybase client libraries
php_yaz.dll	YAZ functions	None
php_zlib.dll	ZLib compression functions	None

Servers-CGI/Commandline

The default is to build PHP as a CGI program. This creates a commandline interpreter, which can be used for CGI processing, or for non-web-related PHP scripting. If you are running a web server PHP has module support for, you should generally go for that solution for performance reasons. However, the CGI version enables Apache users to run different PHP-enabled pages under different user-ids. Please make sure you read through the Security chapter if you are going to run PHP as a CGI.

Testing

If you have built PHP as a CGI program, you may test your build by typing **make test**. It is always a good idea to test your build. This way you may catch a problem with PHP on your platform early instead of having to struggle with it later.

Benchmarking

If you have built PHP 3 as a CGI program, you may benchmark your build by typing **make bench**. Note that if Safe Mode is on by default, the benchmark may not be able to finish if it takes longer than the 30 seconds allowed. This is because the `set_time_limit()` can not be used in safe mode. Use the `max_execution_time` configuration setting to control this time for your own scripts. **make bench** ignores the configuration file.

Poznámka: **make bench** is only available for PHP 3.

Servers-Apache

This section contains notes and hints specific to Apache installs of PHP, both for Unix and Windows versions.

Details of installing PHP with Apache on Unix

You can select arguments to add to the **configure** on line 8 below from the Complete list of configure options. The version numbers have been omitted here, to ensure the instructions are not incorrect. You will need to replace the 'xxx' here with the correct values from your files.

Příklad 2-5. Installation Instructions (Apache Shared Module Version) for PHP 4

```
1. gunzip apache_xxx.tar.gz
2. tar -xvf apache_xxx.tar
3. gunzip php-xxx.tar.gz
4. tar -xvf php-xxx.tar
5. cd apache_xxx
6. ./configure --prefix=/www --enable-module=so
7. make
8. make install
9. cd ../php-xxx
10. ./configure --with-mysql --with-apxs=/www/bin/apxs
11. make
12. make install
```

If you decide to change your configure options after installation you only need to repeat the last three steps. You only need to restart apache for the new module to take effect. A recompile of Apache is not needed.

11. `cp php.ini-dist /usr/local/lib/php.ini`

You can edit your .ini file to set PHP options. If you prefer this file in another location, use `--with-config-file-path=/path` in step 8.

12. Edit your `httpd.conf` or `srm.conf` file and check that these lines are present and not commented out:

```
AddType application/x-httpd-php .php
```

```
LoadModule php4_module      libexec/libphp4.so
```

You can choose any extension you wish here. .php is simply the one we suggest. You can even include .html, and .php3 can be added for backwards compatibility.

The path on the right hand side of the `LoadModule` statement must point to the path of the PHP module on your system. The above statement is correct for the steps shown above.

13. Use your normal procedure for starting the Apache server. (You must stop and restart the server, not just cause the server to reload by use a HUP or USR1 signal.)

Depending on your Apache install and Unix variant, there are many possible ways to stop and restart the server. Below are some typical lines used in restarting the server, for different apache/unix installations. You should replace `/path/to/` with the path to these applications on your systems.

1. Several Linux and SysV variants:
`/etc/rc.d/init.d/httpd restart`

2. Using `apachectl` scripts:
`/path/to/apachectl stop`
`/path/to/apachectl start`

3. `httpdctl` and `httpsdctl` (Using OpenSSL), similar to `apachectl`:
`/path/to/httpsdctl stop`
`/path/to/httpsdctl start`

4. Using `mod_ssl`, or another SSL server, you may want to manually stop and start:
`/path/to/apachectl stop`
`/path/to/apachectl startssl`

The locations of the `apachectl` and `http(s)ctl` binaries often vary. If your system has `locate` or `whereis` or `which` commands, these can assist you in finding your server control programs.

Different examples of compiling PHP for apache are as follows:


```
./configure --with-apxs --with-pgsql
```

This will create a `libphp4.so` shared library that is loaded into Apache using a `LoadModule` line in Apache's `httpd.conf` file. The PostgreSQL support is embedded into this `libphp4.so` library.

```
./configure --with-apxs --with-pgsql=shared
```

This will create a `libphp4.so` shared library for Apache, but it will also create a `pgsql.so` shared library that is loaded into PHP either by using the extension directive in `php.ini` file or by loading it explicitly in a script using the `dl()` function.

```
./configure --with-apache=/path/to/apache_source --with-pgsql
```

This will create a `libmodphp4.a` library, a `mod_php4.c` and some accompanying files and copy this into the `src/modules/php4` directory in the Apache source tree. Then you compile Apache using `--activate-module=src/modules/php4/libphp4.a` and the Apache build system will create `libphp4.a` and link it statically into the `httpd` binary. The PostgreSQL support is included directly into this `httpd` binary, so the final result here is a single `httpd` binary that includes all of Apache and all of PHP.

```
./configure --with-apache=/path/to/apache_source --with-pgsql=shared
```

Same as before, except instead of including PostgreSQL support directly into the final `httpd` you will get a `pgsql.so` shared library that you can load into PHP from either the `php.ini` file or directly using `dl()`.

When choosing to build PHP in different ways, you should consider the advantages and drawbacks of each method. Building as a shared object will mean that you can compile apache separately, and don't have to recompile everything as you add to, or change, PHP. Building PHP into apache (static method) means that PHP will load and run faster. For more information, see the Apache webpage on DSO support (<http://www.apache.org/docs/dso.html>).

Poznámka: Apache's default `http.conf` currently ships with a section that looks like this: User nobody Group "#-1" Unless you change that to "Group nogroup" or something like that ("Group daemon" is also very common) PHP will not be able to open files.

Installing PHP on Windows with Apache 1.3.x

There are two ways to set up PHP to work with Apache 1.3.x on Windows. One is to use the CGI binary (php.exe), the other is to use the Apache module DLL. In either case you need to stop the Apache server, and edit your `srm.conf` or `httpd.conf` to configure Apache to work with PHP.

It is worth noting here that now the SAPI module has been made more stable under windows, we recommend it's use above the CGI binary, since it is more transparent and secure.

Although there can be a few variations of configuring PHP under Apache, these are simple enough to be used by the newcomer. Please consult the Apache Docs for further configuration directives.

If you unzipped the PHP package to `c:\php\` as described in the Manual Installation Steps section, you need to insert these lines to your Apache configuration file to set up the CGI binary:

- `ScriptAlias /php/ "c:/php/"`
- `AddType application/x-httpd-php .php .phtml`
- `Action application/x-httpd-php "/php/php.exe"`

Note that the second line in the list above can be found in the actual versions of `httpd.conf`, but it is commented out. Remember also to substitute the `c:/php/` for your actual path to PHP.

Varování

By using the CGI setup, your server is open to several possible attacks. Please read our CGI security section to learn how to defend yourself from attacks.

If you would like to use PHP as a module in Apache, be sure to move `php4ts.dll` to the `windows/system` (for Windows 9x/Me) or `winnt/system32` (for Windows NT/2000/XP) directory, overwriting any older file. Then you should add the following two lines to you Apache conf file:

- `LoadModule php4_module c:/php/sapi/php4apache.dll`
- `AddType application/x-httpd-php .php .phtml`

After changing the configuration file, remember to restart the server, for example, `NET STOP APACHE` followed by `NET START APACHE`, if you run Apache as a Windows Service, or use your regular shortcuts.

Poznámka: You may find after using the windows installer for Apache that you need to define the `AddModule` directive for `mod_php4.c` in the configuration file (`httpd.conf`). This is done by adding `AddModule mod_php4.c` to the `AddModule` list, near the beginning of the configuration file. This is especially important if the `ClearModuleList` directive is defined. Failure to do this may mean PHP will not be registered as an Apache module.

There are 2 ways you can use the source code highlighting feature, however their ability to work depends on your installation. If you have configured Apache to use PHP as an ISAPI module, then

by adding the following line to your configuration file you can use this feature: `AddType application/x-httpd-php-source .phps`

If you chose to configure Apache to use PHP as a CGI binary, you will need to use the `show_source()` function. To do this simply create a PHP script file and add this code: `<?php show_source ("original_php_script.php"); ?>`. Substitute `original_php_script.php` with the name of the file you wish to show the source of.

Poznámka: On Win-Apache all backslashes in a path statement such as `"c:\directory\file.ext"`, must be converted to forward slashes, as `"c:/directory/file.ext"`.

Servers-Caudium

PHP 4 can be built as a Pike module for the Caudium webserver. Note that this is not supported with PHP 3. Follow the simple instructions below to install PHP 4 for Caudium.

Příklad 2-6. Caudium Installation Instructions

1. Make sure you have Caudium installed prior to attempting to install PHP 4. For PHP 4 to work correctly, you will need Pike 7.0.268 or newer. For the sake of this example we assume that Caudium is installed in `/opt/caudium/server/`.
2. Change directory to `php-x.y.z` (where `x.y.z` is the version number).
3. `./configure --with-caudium=/opt/caudium/server`
4. `make`
5. `make install`
6. Restart Caudium if it's currently running.
7. Log into the graphical configuration interface and go to the virtual server where you want to add PHP 4 support.
8. Click Add Module and locate and then add the PHP 4 Script Support module.
9. If the documentation says that the 'PHP 4 interpreter isn't available', make sure that you restarted the server. If you did check `/opt/caudium/logs/debug/default.1` for any errors related to `<filename>PHP4.so</filename>`. Also make sure that `<filename>caudium/server/lib/[pike-version]/PHP4.so</filename>` is present.
10. Configure the PHP Script Support module if needed.

You can of course compile your Caudium module with support for the various extensions available in PHP 4. See the complete list of configure options for an exhaustive rundown.

Poznámka: When compiling PHP 4 with MySQL support you must make sure that the normal MySQL client code is used. Otherwise there might be conflicts if your Pike already has MySQL support. You do this by specifying a MySQL install directory the `--with-mysql` option.

Servers-fhttpd

To build PHP as an fhttpd module, answer "yes" to "Build as an fhttpd module?" (the `--with-fhttpd=DIR` option to configure) and specify the fhttpd source base directory. The default directory is `/usr/local/src/fhttpd`. If you are running fhttpd, building PHP as a module will give better performance, more control and remote execution capability.

Servers-IIS/PWS

This section contains notes and hints specific to IIS (Microsoft Internet Information Server). Installing PHP for PWS/IIS 3, PWS 4 or newer and IIS 4 or newer versions.

Windows and PWS/IIS 3

The recommended method for configuring these servers is to use the REG file included with the distribution (`pws-php4cgi.reg`). You may want to edit this file and make sure the extensions and PHP install directories match your configuration. Or you can follow the steps below to do it manually.

Varování

These steps involve working directly with the Windows registry. One error here can leave your system in an unstable state. We highly recommend that you back up your registry first. The PHP Development team will not be held responsible if you damage your registry.

- Run Regedit.
- Navigate to: `HKEY_LOCAL_MACHINE /System /CurrentControlSet /Services /W3Svc /Parameters /ScriptMap`.
- On the edit menu select: New->String Value.
- Type in the extension you wish to use for your php scripts. For example `.php`
- Double click on the new string value and enter the path to `php.exe` in the value data field. ex: `c:\php\php.exe`.
- Repeat these steps for each extension you wish to associate with PHP scripts.

The following steps do not affect the web server installation and only apply if you want your php scripts to be executed when they are run from the command line (ex. run `c:\myscripts\test.php`) or by double clicking on them in a directory viewer window. You may wish to skip these steps as you might prefer the PHP files to load into a text editor when you double click on them.

- Navigate to: `HKEY_CLASSES_ROOT`
- On the edit menu select: New->Key.
- Name the key to the extension you setup in the previous section. ex: `.php`

- Highlight the new key and in the right side pane, double click the "default value" and enter `phpfile`.
- Repeat the last step for each extension you set up in the previous section.
- Now create another `New->Key` under `HKEY_CLASSES_ROOT` and name it `phpfile`.
- Highlight the new key `phpfile` and in the right side pane, double click the "default value" and enter `PHP Script`.
- Right click on the `phpfile` key and select `New->Key`, name it `Shell`.
- Right click on the `Shell` key and select `New->Key`, name it `open`.
- Right click on the `open` key and select `New->Key`, name it `command`.
- Highlight the new key `command` and in the right side pane, double click the "default value" and enter the path to `php.exe`. ex: `c:\php\php.exe -q %1`. (don't forget the `%1`).
- Exit Regedit.
- If using PWS on Windows, reboot to reload the registry.

PWS and IIS 3 users now have a fully operational system. IIS 3 users can use a nifty tool (<http://www.genusa.com/iis/iiscfg.html>) from Steven Genusa to configure their script maps.

Windows and PWS 4 or newer

When installing PHP on Windows with PWS 4 or newer version, you have two options. One to set up the PHP CGI binary, the other is to use the ISAPI module DLL.

If you choose the CGI binary, do the following:

- Edit the enclosed `pws-php4cgi.reg` file (look into the SAPI dir) to reflect the location of your `php.exe`. Forward slashes should be escaped, for example:

```
[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\w3svc\parameters\ScriptMap] ".php"="c:\\php\\php.exe"
```
- In the PWS Manager, right click on a given directory you want to add PHP support to, and select Properties. Check the 'Execute' checkbox, and confirm.

If you choose the ISAPI module, do the following:

- Edit the enclosed `pws-php4isapi.reg` file (look into the SAPI dir) to reflect the location of your `php4isapi.dll`. Forward slashes should be escaped, for example:

```
[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\w3svc\parameters\ScriptMap] ".php"="c:\\php\\sapi\\php4isapi.dll"
```
- In the PWS Manager, right click on a given directory you want to add PHP support to, and select Properties. Check the 'Execute' checkbox, and confirm.

Windows NT/2000/XP and IIS 4 or newer

To install PHP on an NT/2000/XP Server running IIS 4 or newer, follow these instructions. You have two options to set up PHP, using the CGI binary (php.exe) or with the ISAPI module.

In either case, you need to start the Microsoft Management Console (may appear as 'Internet Services Manager', either in your Windows NT 4.0 Option Pack branch or the Control Panel=>Administrative Tools under Windows 2000/XP). Then right click on your Web server node (this will most probably appear as 'Default Web Server'), and select 'Properties'.

If you want to use the CGI binary, do the following:

- Under 'Home Directory', 'Virtual Directory', or 'Directory', click on the 'Configuration' button, and then enter the App Mappings tab.
- Click Add, and in the Executable box, type: `c:\php\php.exe` (assuming that you have unzipped PHP in `c:\php\`).
- In the Extension box, type the file name extension you want associated with PHP scripts. Leave 'Method exclusions' blank, and check the Script engine checkbox. You may also like to check the 'check that file exists' box - for a small performance penalty, IIS (or PWS) will check that the script file exists and sort out authentication before firing up php. This means that you will get sensible 404 style error messages instead of cgi errors complaining that php did not output any data.

You must start over from the previous step for each extension you want associated with PHP scripts. `.php` and `.phtml` are common, although `.php3` may be required for legacy applications.

- Set up the appropriate security. (This is done in Internet Service Manager), and if your NT Server uses NTFS file system, add execute rights for `IUSR_` to the directory that contains `php.exe`.

To use the ISAPI module, do the following:

- If you don't want to perform HTTP Authentication using PHP, you can (and should) skip this step. Under ISAPI Filters, add a new ISAPI filter. Use PHP as the filter name, and supply a path to the `php4isapi.dll`.
- Under 'Home Directory', click on the 'Configuration' button. Add a new entry to the Application Mappings. Use the path to the `php4isapi.dll` as the Executable, supply `.php` as the extension, leave Method exclusions blank, and check the Script engine checkbox.
- Stop IIS completely (NET STOP iisadmin)
- Start IIS again (NET START w3svc)

Servers-Netscape and iPlanet

This section contains notes and hints specific to Netscape and iPlanet installs of PHP, both for Sun Solaris and Windows versions.

You can find more information about setting up PHP for the Netscape Enterprise Server here:
<http://benoit.noss.free.fr/php/install-php4.html>

Installing PHP with Netscape on Sun Solaris

To build PHP with NES or iPlanet web servers, enter the proper install directory for the `--with-nsapi` = `DIR` option. The default directory is usually `/opt/netscape/suitespot/`. Please also read `/php-xxx-version/sapi/nsapi/nsapi-readme.txt`.

Příklad 2-7. Installation Example for Netscape Enterprise on Solaris

Instructions for Sun Solaris 2.6 with Netscape Enterprise Server 3.6
From: bhager@invacare.com

1. Install the following packages from www.sunfreeware.com or another download site:

```
flex-2_5_4a-sol26-sparc-local
gcc-2_95_2-sol26-sparc-local
gzip-1.2.4-sol26-sparc-local
perl-5_005_03-sol26-sparc-local
bison-1_25-sol26-sparc-local
make-3_76_1-sol26-sparc-local
m4-1_4-sol26-sparc-local
autoconf-2.13
automake-1.4
mysql-3.23.24-beta (if you want mysql support)
tar-1.13 (GNU tar)
```

2. Make sure your path includes the proper directories

```
PATH=./usr/local/bin:/usr/sbin:/usr/bin:/usr/ccs/bin
export PATH
```

3. `gunzip php-x.x.x.tar.gz` (if you have a .gz dist, otherwise go to 4)

4. `tar xvf php-x.x.x.tar`

5. `cd ../php-x.x.x`

6. For the following step, make sure `/opt/netscape/suitespot/` is where your netscape server is installed. Otherwise, change to correct path:

```
/configure --with-mysql=/usr/local/mysql --with-nsapi=/opt/netscape/suitespot/ -
-enable-track-vars --enable-libgcc
```

7. `make`

8. `make install`

After performing the base install and reading the appropriate readme file, you may need to perform some additional configuration steps.

Firstly you may need to add some paths to the `LD_LIBRARY_PATH` environment for Netscape to find all the shared libs. This can best be done in the start script for your Netscape server. Windows users can probably skip this step. The start script is often located in:

```
/path/to/server/https-servername/start
```

You may also need to edit the configuration files that are located

```
in:/path/to/server/https-servername/config/.
```

Příklad 2-8. Configuration Example for Netscape Enterprise

Configuration Instructions for Netscape Enterprise Server
 From: bhager@invacare.com

1. Add the following line to mime.types:
 type=magnus-internal/x-httpd-php exts=php
2. Add the following to obj.conf, shlib will vary depending on
 your OS, for unix it will be something like
 /opt/netscape/suitespot/bin/libphp4.so.

You should place the following lines after mime types init.

```
Init fn="load-modules" funcs="php4_init,php4_close,php4_execute,php4_auth_trans" shlib=shlib
Init fn=php4_init errorString="Failed to initialize PHP!"
```

```
<object name="default">
.
.
.
.#NOTE this next line should happen after all 'ObjectType' and before all 'AddLog' lines
Service fn="php4_execute" type="magnus-internal/x-httpd-php"
.
.
</Object>
```

```
<Object name="x-httpd-php">
ObjectType fn="force-type" type="magnus-internal/x-httpd-php"
Service fn=php4_execute
</Object>
```

Authentication configuration

PHP authentication cannot be used with any other authentication. ALL AUTHENTICATION IS PASSED TO YOUR PHP SCRIPT. To configure PHP Authentication for the entire server, add the following line:

```
<Object name="default">
AuthTrans fn=php4_auth_trans
.
.
.
.
</Object>
```

To use PHP Authentication on a single directory, add the following:

```
<Object ppath="d:\path\to\authenticated\dir\*">
AuthTrans fn=php4_auth_trans
</Object>
```


If you are running Netscape Enterprise 4.x, then you should use the following:

Příklad 2-9. Configuration Example for Netscape Enterprise 4.x

Place these lines after the mime types init, and everything else is similar to the example configuration above.

From: Graeme Hoose (GraemeHoose@BrightStation.com)

```
Init fn="load-modules" shlib="/path/to/server4/bin/libphp4.so" funcs="php4_init,php4_clos
Init fn="php4_init" LateInit="yes"
```

Installing PHP with Netscape on Windows

To Install PHP as CGI (for Netscape Enterprise Server, iPlanet, perhaps Fastrack), do the following:

- Copy `php4ts.dll` to your systemroot (the directory where you installed windows)
- Make a file association from the command line. Type the following two lines:

```
assoc .php=PHPScript
ftype PHPScript=c:\php\php.exe %1 %*
```

- In the Netscape Enterprise Administration Server create a dummy shellcgi directory and remove it just after (this step creates 5 important lines in `obj.conf` and allow the web server to handle shellcgi scripts).
- In the Netscape Enterprise Administration Server create a new mime type (Category: type, Content-Type: `magnus-internal/shellcgi`, File Suffix: `php`).
- Do it for each web server instance you want php to run

More details about setting up PHP as a CGI executable can be found here:

<http://benoit.noss.free.fr/php/install-php.html>

To Install PHP as NSAPI (for Netscape Enterprise Server, iPlanet, perhaps Fastrack, do the following:

- Copy `php4ts.dll` to your systemroot (the directory where you installed windows)
- Make a file association from the command line. Type the following two lines:

```
assoc .php=PHPScript
ftype PHPScript=c:\php\php.exe %1 %*
```

- In the Netscape Enterprise Administration Server create a new mime type (Category: type, Content-Type: `magnus-internal/x-httpd-php`, File Suffix: `php`).
- Stop your web service and edit `obj.conf`. At the end of the Init section, place these two lines (necessarily after mime type init!):

```
Init fn="load-modules" funcs="php4_init,php4_close,php4_execute,php4_auth_trans" shlib=
Init fn="php4_init" errorString="Failed to initialise PHP!"
```

- In The < Object name="default" > section, place this line necessarily after all 'ObjectType' and before all 'AddLog' lines:

```
Service fn="php4_execute" type="magnus-internal/x-httpd-php"
```

- At the end of the file, create a new object called x-httpd-php, by inserting these lines:

```
<Object name="x-httpd-php">
ObjectType fn="force-type" type="magnus-internal/x-httpd-php"
Service fn=php4_execute
</Object>
```

- Restart your web service and apply changes
- Do it for each web server instance you want PHP to run

More details about setting up PHP as an NSAPI filter can be found here:
<http://benoit.noss.free.fr/php/install-php4.html>

Servers-OmniHTTPd Server

This section contains notes and hints specific to OmniHTTPd.

OmniHTTPd 2.0b1 and up for Windows

You need to complete the following steps to make PHP work with OmniHTTPd. This is a CGI executable setup. SAPI is supported by OmniHTTPd, but some tests have shown that it is not so stable to use PHP as an ISAPI module.

- Step 1: Install OmniHTTPd server.
- Step 2: Right click on the blue OmniHTTPd icon in the system tray and select Properties
- Step 3: Click on Web Server Global Settings
- Step 4: On the 'External' tab, enter: virtual = .php | actual = c:\path-to-php-dir\php.exe, and use the Add button.
- Step 5: On the Mime tab, enter: virtual = wwwserver/stdcgi | actual = .php, and use the Add button.
- Step 6: Click OK

Repeat steps 2 - 6 for each extension you want to associate with PHP.

Poznámka: Some OmniHTTPd packages come with built in PHP support. You can choose at setup time to do a custom setup, and uncheck the PHP component. We recommend you to use the latest PHP binaries. Some OmniHTTPd servers come with PHP 4 beta distributions, so you should choose not to set up the built in support, but install your own. If the server is already on your machine, use the Replace button in Step 4 and 5 to set the new, correct information.

Servers-Oreilly Website Pro

This section contains notes and hints specific to Oreilly Website Pro.

Oreilly Website Pro 2.5 and up for Windows

This list describes how to set up the PHP CGI binary or the ISAPI module to work with Oreilly Website Pro on Windows.

- Edit the Server Properties and select the tab "Mapping".
- From the List select "Associations" and enter the desired extension (.php) and the path to the CGI exe (ex. c:\php\php.exe) or the ISAPI DLL file (ex. c:\php\sapi\php4isapi.dll).
- Select "Content Types" add the same extension (.php) and enter the content type. If you choose the CGI executable file, enter 'wwwserver/shellcgi', if you choose the ISAPI module, enter 'wwwserver/isapi' (both without quotes).

Servers-Xitami

This section contains notes and hints specific to Xitami.

Xitami for Windows

This list describes how to set up the PHP CGI binary to work with Xitami on Windows.

- Make sure the webserver is running, and point your browser to xitamis admin console (usually <http://127.0.0.1/admin>), and click on Configuration.
- Navigate to the Filters, and put the extension which PHP should parse (i.e. .php) into the field File extensions (.xxx).
- In Filter command or script put the path and name of your php executable i.e. c:\php\php.exe.
- Press the 'Save' icon.
- Restart the server to reflect changes.

Servers-Other web servers

PHP can be built to support a large number of web servers. Please see Server-related options for a full list of server-related configure options. The PHP CGI binaries are compatible with almost all web servers supporting the CGI standard.

Problems?

Read the FAQ

Some problems are more common than others. The most common ones are listed in the PHP FAQ, part of this manual.

Other problems

If you are still stuck, someone on the PHP installation mailing list may be able to help you. You should check out the archive first, in case someone already answered someone else who had the same problem as you. The archives are available from the support page on <http://www.php.net/>. To subscribe to the PHP installation mailing list, send an empty mail to php-install-subscribe@lists.php.net (<mailto:php-install-subscribe@lists.php.net>). The mailing list address is php-install@lists.php.net.

If you want to get help on the mailing list, please try to be precise and give the necessary details about your environment (which operating system, what PHP version, what web server, if you are running PHP as CGI or a server module, etc.), and preferably enough code to make others able to reproduce and test your problem.

Bug reports

If you think you have found a bug in PHP, please report it. The PHP developers probably don't know about it, and unless you report it, chances are it won't be fixed. You can report bugs using the bug-tracking system at <http://bugs.php.net/>. Please do not send bug reports in mailing list or personal letters. The bug system is also suitable to submit feature requests.

Read the How to report a bug (<http://bugs.php.net/how-to-report.php>) document before submitting any bug reports!

Complete list of configure options

Poznámka: These are only used at compile time. If you want to alter PHP's runtime configuration, please see the chapter on Configuration.

The following is a complete list of options supported by PHP 4 `configure` scripts (as of 4.1.0), used when compiling in Unix-like environments. Some are available in PHP 3, some in PHP 4, and some in both. This is not noted yet.

- Database
- Graphics
- Miscellaneous
- PHP Behaviour
- Server
- XML

Configure Options in PHP 4

Poznámka: These options are only used in PHP 4 as of PHP 4.1.0. Some are available in older versions of PHP 4, some even in PHP 3, some only in PHP 4.1.0. If you want to compile an older version, some options will probably not be available.

Database options

`--with-db`

Include old xDBM support (deprecated).

`--enable-dba=shared`

Build DBA as a shared module.

`--with-gdbm[=DIR]`

Include GDBM support.

`--with-ndbm[=DIR]`

Include NDBM support.

`--with-db2[=DIR]`

Include Berkeley DB2 support.

`--with-db3[=DIR]`

Include Berkeley DB3 support.

`--with-dbm[=DIR]`

Include DBM support.

`--with-cdb[=DIR]`

Include CDB support.

```
--enable-dbase
    Enable the bundled dbase library.

--with-dbplus
    Include dbplus support.

--enable-dbx
    Enable dbx.

--with-fbsql[=DIR]
    Include FrontBase support. DIR is the FrontBase base directory.

--enable-filepro
    Enable the bundled read-only filePro support.

--with-fribidi[=DIR]
    Include fribidi support (requires FriBidi >=0.1.12). DIR is the fribidi installation directory -
    default /usr/local/.

--with-informix[=DIR]
    Include Informix support. DIR is the Informix base install directory, defaults to nothing.

--with-ingres[=DIR]
    Include Ingres II support. DIR is the Ingres base directory (default /II/ingres).

--with-interbase[=DIR]
    Include InterBase support. DIR is the InterBase base install directory, defaults to /usr/interbase.

--with-mysql[=DIR]
    Include mSQL support. DIR is the mSQL base install directory, defaults to /usr/local/Hughes.

--with-mysql[=DIR]
    Include MySQL support. DIR is the MySQL base directory. If unspecified, the bundled
    MySQL library will be used.

--with-oci8[=DIR]
    Include Oracle-oci8 support. Default DIR is ORACLE_HOME.

--with-adabas[=DIR]
    Include Adabas D support. DIR is the Adabas base install directory, defaults to /usr/local.

--with-sapdb[=DIR]
    Include SAP DB support. DIR is SAP DB base install directory, defaults to /usr/local.

--with-solid[=DIR]
    Include Solid support. DIR is the Solid base install directory, defaults to /usr/local/solid.
```

`--with-ibm-db2[=DIR]`

Include IBM DB2 support. DIR is the DB2 base install directory, defaults to /home/db2inst1/sqllib.

`--with-empress[=DIR]`

Include Empress support. DIR is the Empress base install directory, defaults to \$EMPRESSPATH. From PHP4, this option only supports Empress Version 8.60 and above.

`--with-empress-bcs[=DIR]`

Include Empress Local Access support. DIR is the Empress base install directory, defaults to \$EMPRESSPATH. From PHP4, this option only supports Empress Version 8.60 and above.

`--with-birdstep[=DIR]`

Include Birdstep support. DIR is the Birdstep base install directory, defaults to /usr/local/birdstep.

`--with-custom-odbc[=DIR]`

Include a user defined ODBC support. The DIR is ODBC install base directory, which defaults to /usr/local. Make sure to define CUSTOM_ODBC_LIBS and have some odbc.h in your include dirs. E.g., you should define following for Sybase SQL Anywhere 5.5.00 on QNX, prior to run configure script: CPPFLAGS="-DODBC_QNX -DSQLANY_BUG" LDFLAGS=-lunix CUSTOM_ODBC_LIBS="-ldblib -lodbc".

`--with-iodbc[=DIR]`

Include iODBC support. DIR is the iODBC base install directory, defaults to /usr/local.

`--with-esoob[=DIR]`

Include Easysoft OOB support. DIR is the OOB base install directory, defaults to /usr/local/easysoft/oob/client.

`--with-unixODBC[=DIR]`

Include unixODBC support. DIR is the unixODBC base install directory, defaults to /usr/local.

`--with-openlink[=DIR]`

Include OpenLink ODBC support. DIR is the OpenLink base install directory, defaults to /usr/local. This is the same as iODBC.

`--with-dbmaker[=DIR]`

Include DBMaker support. DIR is the DBMaker base install directory, defaults to where the latest version of DBMaker is installed (such as /home/dbmaker/3.6).

`--with-oracle[=DIR]`

Include Oracle-oci7 support. Default DIR is ORACLE_HOME.

`--with-ovrimos[=DIR]`

Include Ovrmos SQL Server support. DIR is the Ovrmos' libsqlcli install directory.

`--with-pgsql[=DIR]`

Include PostgreSQL support. DIR is the PostgreSQL base install directory, defaults to /usr/local/pgsql. Set DIR to shared to build as a dl, or shared,DIR to build as a dl and still specify DIR.

`--with-sybase[=DIR]`

Include Sybase-DB support. DIR is the Sybase home directory, defaults to /home/sybase.

`--with-sybase-ct[=DIR]`

Include Sybase-CT support. DIR is the Sybase home directory. Defaults to /home/sybase.

`--disable-unified-odbc`

Disable unified ODBC support. Only applicable if iODBC, Adabas, Solid, Velocis or a custom ODBC interface is enabled. PHP 3 only!

Graphics options

`--with-gd[=DIR]`

Include GD support (DIR is GD's install dir). Set DIR to shared to build as a dl, or shared,DIR to build as a dl and still specify DIR.

`--enable-gd-native-ttf`

GD: Enable TrueType string function in gd.

`--with-jpeg-dir=DIR`

GD: Set the path to libjpeg install prefix.

`--with-png-dir=DIR`

GD: Set the path to libpng install prefix.

`--with-xpm-dir=DIR`

GD: Set the path to libXpm install prefix.

`--with-freetype-dir=DIR`

GD: Set the path to freetype2 install prefix.

`--with-ttf[=DIR]`

GD: Include FreeType 1.x support.

`--with-t1lib[=DIR]`

GD: Include T1lib support.

`--with-cpdf-lib[=DIR]`

Include cpdf-lib support (requires cpdf-lib >= 2). DIR is the cpdf-lib install directory, defaults to /usr.

`--with-jpeg-dir[=DIR]`

jpeg dir for cpdf-lib 2.x.

`--with-tiff-dir[=DIR]`

tiff dir for cpdfliib 2.x.

`--with-pdfliib[=DIR]`

Include PDFlib support. DIR is the pdfliib base install directory, defaults to /usr/local. Set DIR to shared to build as dl, or shared,DIR to build as dl and still specify DIR.

`--with-jpeg-dir[=DIR]`

PDFLIB: define libjpeg install directory.

`--with-png-dir[=DIR]`

PDFLIB: define libpng install directory.

`--with-tiff-dir[=DIR]`

PDFLIB: define libtiff install directory.

`--with-swf[=DIR]`

Include swf support.

`--without-gd`

Disable GD support. PHP 3 only!

`--with-imagick`

Include ImageMagick support. DIR is the install directory, and if left out, PHP will try to find it on its own. [experimental]. PHP 3 only!

`--with-ming[=DIR]`

Include ming support.

Misc options

`--enable-force-cgi-redirect`

Enable the security check for internal server redirects. You should use this if you are running the CGI version with Apache.

`--enable-discard-path`

If this is enabled, the PHP CGI binary can safely be placed outside of the web tree and people will not be able to circumvent .htaccess security.

`--with-fastcgi=SRCDIR`

Build PHP as FastCGI application.

`--enable-debug`

Compile with debugging symbols.

`--with-layout=TYPE`

Sets how installed files will be laid out. Type is one of PHP (default) or GNU.

```
--with-pear=DIR
    Install PEAR in DIR (default PREFIX/lib/php).
```

```
--without-pear
    Do not install PEAR.
```

```
--with-openssl[=DIR]
    Include OpenSSL support (requires OpenSSL >= 0.9.5).
```

```
--enable-sigchild
    Enable PHP's own SIGCHLD handler.
```

```
--disable-rpath
    Disable passing additional runtime library search paths.
```

```
--enable-libgcc
    Enable explicitly linking against libgcc.
```

```
--enable-dmalloc
    Enable dmalloc.
```

```
--enable-php-streams
    Include experimental php streams. Do not use unless you are testing the code!
```

```
--with-zlib-dir=<DIR>
    Define the location of zlib install directory.
```

```
--with-zlib[=DIR]
    Include zlib support (requires zlib >= 1.0.9). DIR is the zlib install directory.
```

```
--with-aspell[=DIR]
    Include ASPELL support.
```

```
--enable-bcmath
    Enable bc style precision math functions.
```

```
--with-bz2[=DIR]
    Include BZip2 support.
```

```
--enable-calendar
    Enable support for calendar conversion.
```

```
--with-ccvs[=DIR]
    Include CCVS support.
```

```
--with-crack[=DIR]
    Include crack support.
```

```
--enable-ctype
    Enable ctype support.

--with-curl[=DIR]
    Include CURL support.

--with-cybercash[=DIR]
    Include CyberCash support. DIR is the CyberCash MCK install directory.

--with-cybermut[=DIR]
    Include CyberMut (French Credit Mutuel telepaiement).

--with-cyrus
    Include cyrus IMAP support.

--enable-exif
    Enable exif support.

--with-fdftk[=DIR]
    Include fdftk support.

--enable-ftp
    Enable FTP support.

--with-gettext[=DIR]
    Include GNU gettext support. DIR is the gettext install directory, defaults to /usr/local.

--with-gmp
    Include gmp support.

--with-hyperwave
    Include Hyperwave support.

--with-icap[=DIR]
    Include ICAP support.

--with-iconv[=DIR]
    Include iconv support.

--with-imap[=DIR]
    Include IMAP support. DIR is the c-client install prefix.

--with-kerberos[=DIR]
    IMAP: Include Kerberos support. DIR is the Kerberos install dir.

--with-imap-ssl[=DIR]
    IMAP: Include SSL support. DIR is the OpenSSL install dir.
```

`--with-ircg-config`
 Path to the ircg-config script.

`--with-ircg`
 Include ircg support.

`--with-java[=DIR]`
 Include Java support. DIR is the base install directory for the JDK. This extension can only be built as a shared dl.

`--with-ldap[=DIR]`
 Include LDAP support. DIR is the LDAP base install directory.

`--enable-mailparse`
 Enable mailparse support.

`--enable-mbstring`
 Enable multibyte string support.

`--enable-mbstr-enc-trans`
 Enable japanese encoding translation.

`--with-mcal[=DIR]`
 Include MCAL support.

`--with-mcrypt[=DIR]`
 Include mcrypt support. DIR is the mcrypt install directory.

`--with-mhash[=DIR]`
 Include mhash support. DIR is the mhash install directory.

`--with-mnogosearch[=DIR]`
 Include mnoGoSearch support. DIR is the mnoGoSearch base install directory, defaults to /usr/local/mnogosearch.

`--with-muscat[=DIR]`
 Include muscat support.

`--with-ncurses`
 Include ncurses support.

`--enable-pcntl`
 Enable experimental pcntl support (CGI ONLY!)

`--without-pcre-regex`
 Do not include Perl Compatible Regular Expressions support. Use --with-pcre-regex=DIR to specify DIR where PCRE's include and library files are located, if not using bundled library.

```
--with-pfpro[=DIR]
    Include Verisign Payflow Pro support.

--disable-posix
    Disable POSIX-like functions.

--with-pspell[=DIR]
    Include PSpell support.

--with-qtdom
    Include QtDOM support (requires Qt >= 2.2.0).

--with-libedit[=DIR]
    Include libedit readline replacement.

--with-readline[=DIR]
    Include readline support. DIR is the readline install directory.

--with-recode[=DIR]
    Include recode support. DIR is the recode install directory.

--with-satellite[=DIR]
    Enable CORBA support via Satellite (EXPERIMENTAL) DIR is the base directory for ORBit.

--with-mm[=DIR]
    Include mm support for session storage.

--enable-trans-sid
    Enable transparent session id propagation.

--disable-session
    Disable session support.

--enable-shmop
    Enable shmop support.

--with-snmp[=DIR]
    Include SNMP support. DIR is the SNMP base install directory, defaults to searching through a
    number of common locations for the snmp install. Set DIR to shared to build as a dl, or
    shared,DIR to build as a dl and still specify DIR.

--enable-ucd-snmp-hack
    Enable UCD SNMP hack.

--enable-sockets
    Enable sockets support.

--with-regex=TYPE
    regex library type: system, apache, php.
```

```

--with-system-regex
    Use system regex library (deprecated).

--enable-sysvsem
    Enable System V semaphore support.

--enable-sysvshm
    Enable the System V shared memory support.

--with-vpopmail[=DIR]
    Include vpopmail support.

--with-tsrm-pthreads
    Use POSIX threads (default).

--enable-shared[=PKGS]
    Build shared libraries [default=yes].

--enable-static[=PKGS]
    Build static libraries [default=yes].

--enable-fast-install[=PKGS]
    Optimize for fast installation [default=yes].

--with-gnu-ld
    Assume the C compiler uses GNU ld [default=no].

--disable-libtool-lock
    Avoid locking (might break parallel builds).

--with-pic
    Try to use only PIC/non-PIC objects [default=use both].

--with-yaz[=DIR]
    Include YAZ support (ANSI/NISO Z39.50). DIR is the YAZ bin install directory.

--enable-memory-limit
    Compile with memory limit support.

--disable-url-fopen-wrapper
    Disable the URL-aware fopen wrapper that allows accessing files via HTTP or FTP.

--enable-versioning
    Export only required symbols. See INSTALL for more information.

--disable-bcmath
    Compile without bc style precision math functions. PHP 3 only!

```

`--with-imspl[=DIR]`

Include IMSP support (DIR is IMSP's include dir and libimsp.a dir). PHP 3 only!

`--with-ftp`

Include FTP support. PHP 3 only!

`--with-mck[=DIR]`

Include Cybercash MCK support. DIR is the cybercash mck build directory, defaults to /usr/src/mck-3.2.0.3-linux for help look in extra/cyberlib. PHP 3 only!

`--disable-overload`

Disable user-space object overloading support. PHP 3 only!

`--enable-yp`

Include YP support. PHP 3 only!

`--with-zip`

Include ZIP support (requires zziplib >= 0.10.6). PHP 3 only!

`--with-mod-dav=DIR`

Include DAV support through Apache's mod_dav, DIR is mod_dav's installation directory (Apache module version only!) PHP 3 only!

`--enable-debugger`

Compile with remote debugging functions. PHP 3 only!

`--enable-versioning`

Take advantage of versioning and scoping provided by Solaris 2.x and Linux. PHP 3 only!

PHP options

`--enable-maintainer-mode`

Enable make rules and dependencies not useful (and sometimes confusing) to the casual installer.

`--with-config-file-path=PATH`

Sets the path in which to look for php.ini, defaults to PREFIX/lib.

`--enable-safe-mode`

Enable safe mode by default.

`--with-exec-dir[=DIR]`

Only allow executables in DIR when in safe mode defaults to /usr/local/php/bin.

`--enable-magic-quotes`

Enable magic quotes by default.

`--disable-short-tags`

Disable the short-form `<? start` tag by default.

Server options

`--with-aolserver=DIR`

Specify path to the installed AOLserver.

`--with-apxs[=FILE]`

Build shared Apache module. FILE is the optional pathname to the Apache apxs tool; defaults to apxs.

`--with-apache[=DIR]`

Build Apache module. DIR is the top-level Apache build directory, defaults to `/usr/local/apache`.

`--with-mod_charset`

Enable transfer tables for mod_charset (Rus Apache).

`--with-apxs2[=FILE]`

Build shared Apache 2.0 module. FILE is the optional pathname to the Apache apxs tool; defaults to apxs.

`--with-fhttpd[=DIR]`

Build fhttpd module. DIR is the fhttpd sources directory, defaults to `/usr/local/src/fhttpd`.

`--with-isapi=DIR`

Build PHP as an ISAPI module for use with Zeus.

`--with-nsapi=DIR`

Specify path to the installed Netscape Server.

`--with-phttpd=DIR`

No information yet.

`--with-pi3web=DIR`

Build PHP as a module for use with Pi3Web.

`--with-roxen=DIR`

Build PHP as a Pike module. DIR is the base Roxen directory, normally `/usr/local/roxen/server`.

`--enable-roxen-zts`

Build the Roxen module using Zend Thread Safety.

`--with-servlet[=DIR]`

Include servlet support. DIR is the base install directory for the JSDK. This SAPI prereqs the java extension must be built as a shared dl.

`--with-thttpd=SRCDIR`

Build PHP as thttpd module.

`--with-tux=MODULEDIR`

Build PHP as a TUX module (Linux only).

XML options

`--with-dom[=DIR]`

Include DOM support (requires libxml >= 2.4.2). DIR is the libxml install directory, defaults to /usr.

`--disable-xml`

Disable XML support using bundled expat lib.

`--with-expat-dir=DIR`

XML: external libexpat install dir.

`--with-xmlrpc[=DIR]`

Include XMLRPC-EPI support.

`--enable-wddx`

Enable WDDX support.

Kapitola 3. Configuration

The configuration file

The configuration file (called `php3.ini` in PHP 3.0, and simply `php.ini` as of PHP 4.0) is read when PHP starts up. For the server module versions of PHP, this happens only once when the web server is started. For the CGI version, it happens on every invocation.

Příklad 3-1. `php.ini` example

```
; any text on a line after an unquoted semicolon (;) is ignored
[php] ; section markers (text within square brackets) are also ignored
; Boolean values can be set to either:
;   true, on, yes
; or false, off, no, none
register_globals = off
magic_quotes_gpc = yes

; you can enclose strings in double-quotes
include_path = ".:usr/local/lib/php"

; backslashes are treated the same as any other character
include_path = ".:c:\php\lib"
```

When using PHP as an Apache module, you can also change the configuration settings using directives in Apache configuration files and `.htaccess` files (You will need "AllowOverride Options" or "AllowOverride All" privileges)

With PHP 3.0, there are Apache directives that correspond to each configuration setting in the `php3.ini` name, except the name is prefixed by "php3_".

With PHP 4.0, there are several Apache directives that allow you to change the PHP configuration from within the Apache configuration file itself.

`php_value name value`

This sets the value of the specified variable.

`php_flag name on/off`

This is used to set a Boolean configuration option.

`php_admin_value name value`

This sets the value of the specified variable. "Admin" configuration settings can only be set from within the main Apache configuration files, and not from `.htaccess` files.

`php_admin_flag name on/off`

This is used to set a Boolean configuration option.

Příklad 3-2. Apache configuration example

```

<IfModule mod_php4.c>
    php_value include_path ".:usr/local/lib/php"
    php_flag safe_mode on
</IfModule>
<IfModule mod_php3.c>
    php3_include_path ".:usr/local/lib/php"
    php3_safe_mode on
</IfModule>

```

You can view the settings of the configuration values in the output of `phpinfo()`. You can also access the values of individual configuration settings using `get_cfg_var()`.

General Configuration Directives

allow_url_fopen boolean

This option enables the URL-aware fopen wrappers that enable accessing URL object like files. Default wrappers are provided for the access of remote files using the ftp or http protocol, some extensions like zlib may register additional wrappers.

Poznámka: This option was introduced immediately after the release of version 4.0.3. For versions up to and including 4.0.3 you can only disable this feature at compile time by using the configuration switch `--d isable-url-fopen-wrapper`.

asp_tags boolean

Enables the use of ASP-like `<% %>` tags in addition to the usual `<?php ?>` tags. This includes the variable-value printing shorthand of `<%= $value %>`. For more information, see Escaping from HTML.

Poznámka: Support for ASP-style tags was added in 3.0.4.

auto_append_file string

Specifies the name of a file that is automatically parsed after the main file. The file is included as if it was called with the `include()` function, so `include_path` is used.

The special value `none` disables auto-appending.

Poznámka: If the script is terminated with `exit()`, auto-append will *not* occur.

auto_prepend_file string

Specifies the name of a file that is automatically parsed before the main file. The file is included as if it was called with the `include()` function, so `include_path` is used.

The special value `none` disables auto-prepend.

cgi_ext string

display_errors boolean

This determines whether errors should be printed to the screen as part of the HTML output or not.

doc_root string

PHP's "root directory" on the server. Only used if non-empty. If PHP is configured with safe mode, no files outside this directory are served.

engine boolean

This directive is really only useful in the Apache module version of PHP. It is used by sites that would like to turn PHP parsing on and off on a per-directory or per-virtual server basis. By putting **engine off** in the appropriate places in the `httpd.conf` file, PHP can be enabled or disabled.

error_log string

Name of file where script errors should be logged. If the special value `syslog` is used, the errors are sent to the system logger instead. On UNIX, this means `syslog(3)` and on Windows NT it means the event log. The system logger is not supported on Windows 95.

error_reporting integer

Set the error reporting level. The parameter is an integer representing a bit field. Add the values of the error reporting levels you want.

Tabulka 3-1. Error Reporting Levels

bit value	enabled reporting
1	normal errors
2	normal warnings
4	parser errors
8	non-critical style-related warnings

The default value for this directive is 7 (normal errors, normal warnings and parser errors are shown).

html_errors boolean

Turn off HTML tags in error messages.

open_basedir string

Limit the files that can be opened by PHP to the specified directory-tree.

When a script tries to open a file with, for example, `fopen` or `gzopen`, the location of the file is checked. When the file is outside the specified directory-tree, PHP will refuse to open it. All symbolic links are resolved, so it's not possible to avoid this restriction with a symlink.

The special value `.` indicates that the directory in which the script is stored will be used as base-directory.

Under Windows, separate the directories with a semicolon. On all other systems, separate the directories with a colon. As an Apache module, `open_basedir` paths from parent directories are now automatically inherited.

The restriction specified with `open_basedir` is actually a prefix, not a directory name. This means that "`open_basedir = /dir/incl`" also allows access to `/dir/include` and `/dir/incls` if they exist. When you want to restrict access to only the specified directory, end with a slash. For example: "`open_basedir = /dir/incl/`"

Poznámka: Support for multiple directories was added in 3.0.7.

The default is to allow all files to be opened.

gpc_order string

Set the order of GET/POST/COOKIE variable parsing. The default setting of this directive is "GPC". Setting this to "GP", for example, will cause PHP to completely ignore cookies and to overwrite any GET method variables with POST-method variables of the same name.

Note, that this option is not available in PHP 4. Use `variables_order` instead.

variables_order string

Set the order of the EGPCS (Environment, GET, POST, Cookie, Server) variable parsing. The default setting of this directive is "EGPCS". Setting this to "GP", for example, will cause PHP to completely ignore environment variables, cookies and server variables, and to overwrite any GET method variables with POST-method variables of the same name.

See also `register_globals`.

ignore_user_abort string

On by default. If changed to Off scripts will be terminated as soon as they try to output something after a client has aborted their connection. `ignore_user_abort()`.

include_path string

Specifies a list of directories where the `require()`, `include()` and **`fopen_with_path()`** functions look for files. The format is like the system's PATH environment variable: a list of directories

separated with a colon in UNIX or semicolon in Windows.

Příklad 3-3. UNIX `include_path`

```
include_path=.: /home/httpd/php-lib
```

Příklad 3-4. Windows `include_path`

```
include_path=".;c:\www\phplib"
```

The default value for this directive is `.` (only the current directory).

isapi_ext string

log_errors boolean

Tells whether script error messages should be logged to the server's error log. This option is thus server-specific.

magic_quotes_gpc boolean

Sets the *magic_quotes* state for GPC (Get/Post/Cookie) operations. When *magic_quotes* are on, all `'` (single-quote), `"` (double quote), `\` (backslash) and NUL's are escaped with a backslash automatically. If *magic_quotes_sybase* is also on, a single-quote is escaped with a single-quote instead of a backslash.

magic_quotes_runtime boolean

If *magic_quotes_runtime* is enabled, most functions that return data from any sort of external source including databases and text files will have quotes escaped with a backslash. If *magic_quotes_sybase* is also on, a single-quote is escaped with a single-quote instead of a backslash.

magic_quotes_sybase boolean

If *magic_quotes_sybase* is also on, a single-quote is escaped with a single-quote instead of a backslash if *magic_quotes_gpc* or *magic_quotes_runtime* is enabled.

max_execution_time integer

This sets the maximum time in seconds a script is allowed to run before it is terminated by the parser. This helps prevent poorly written scripts from tying up the server. The default setting is 30.

The maximum execution time is not affected by system calls, the `sleep()` function, etc. Please see the `set_time_limit()` function for more details.

memory_limit integer

This sets the maximum amount of memory in bytes that a script is allowed to allocate. This helps prevent poorly written scripts for eating up all available memory on a server.

nsapi_ext string

precision integer

The number of significant digits displayed in floating point numbers.

register_argc_argv boolean

Tells PHP whether to declare the argv & argc variables (that would contain the GET information).

See also command line. Also, this directive became available in PHP 4.0.0 and was always "on" before that.

post_max_size integer

Sets max size of post data allowed. This setting also affects file upload. To upload large files, this value must be larger than upload_max_filesize.

If memory limit is enabled by configure script, memory_limit also affects file uploading. Generally speaking, memory_limit should be larger than post_max_size.

register_globals boolean

Tells whether or not to register the EGPCS (Environment, GET, POST, Cookie, Server) variables as global variables. You may want to turn this off if you don't want to clutter your scripts' global scope with user data. This makes the most sense when coupled with track_vars - in which case you can access all of the EGPCS variables through the \$_ENV, \$_GET, \$_POST, \$_COOKIE, and \$_SERVER arrays in the global scope.

Please note that you need to set AllowOverride All in your Directory block in the apache config file for this to work.

short_open_tag boolean

Tells whether the short form (<? ?>) of PHP's open tag should be allowed. If you want to use PHP in combination with XML, you have to disable this option. If disabled, you must use the long form of the open tag (<?php ?>).

sql.safe_mode boolean

track_errors boolean

If enabled, the last error message will always be present in the global variable \$php_errormsg.

track_vars boolean

If enabled, then Environment, GET, POST, Cookie, and Server variables can be found in the global associative arrays \$_ENV, \$_GET, \$_POST, \$_COOKIE, and \$_SERVER.

Note that as of PHP 4.0.3, track_vars is always turned on.

upload_tmp_dir string

The temporary directory used for storing files when doing file upload. Must be writable by whatever user PHP is running as.

upload_max_filesize integer

The maximum size of an uploaded file. The value is in bytes.

user_dir string

The base name of the directory used on a user's home directory for PHP files, for example `public_html`.

warn_plus_overloading boolean

If enabled, this option makes PHP output a warning when the plus (+) operator is used on strings. This is to make it easier to find scripts that need to be rewritten to using the string concatenator instead (.

Safe Mode Configuration Directives

safe_mode boolean

Whether to enable PHP's safe mode. Read the Security and Safe Mode chapters for more information.

safe_mode_exec_dir string

If PHP is used in safe mode, `system()` and the other functions executing system programs refuse to start programs that are not in this directory.

Debugger Configuration Directives

debugger.host string

DNS name or IP address of host used by the debugger.

debugger.port string

Port number used by the debugger.

debugger.enabled boolean

Whether the debugger is enabled.

Extension Loading Directives

enable_dl boolean

This directive is really only useful in the Apache module version of PHP. You can turn dynamic loading of PHP extensions with `dl()` on and off per virtual server or per directory.

The main reason for turning dynamic loading off is security. With dynamic loading, it's possible to ignore all the `safe_mode` and `open_basedir` restrictions.

The default is to allow dynamic loading, except when using `safe-mode`. In `safe-mode`, it's always impossible to use `dl()`.

extension_dir string

In what directory PHP should look for dynamically loadable extensions.

extension string

Which dynamically loadable extensions to load when PHP starts up.

mSQL Configuration Directives

mysql.allow_persistent boolean

Whether to allow persistent mSQL connections.

mysql.max_persistent integer

The maximum number of persistent mSQL connections per process.

mysql.max_links integer

The maximum number of mSQL connections per process, including persistent connections.

Postgres Configuration Directives

pgsql.allow_persistent boolean

Whether to allow persistent Postgres connections.

pgsql.max_persistent integer

The maximum number of persistent Postgres connections per process.

pgsql.max_links integer

The maximum number of Postgres connections per process, including persistent connections.

SESAM Configuration Directives

sesam_oml string

Name of BS2000 PLAM library containing the loadable SESAM driver modules. Required for using SESAM functions. The BS2000 PLAM library must be set `ACCESS=READ,SHARE=YES` because it must be readable by the apache server's user id.

sesam_configfile string

Name of SESAM application configuration file. Required for using SESAM functions. The BS2000 file must be readable by the apache server's user id.

The application configuration file will usually contain a configuration like (see SESAM reference manual):

```
CNF=B
NAM=K
NOTYPE
```

sesam_messagecatalog string

Name of SESAM message catalog file. In most cases, this directive is not necessary. Only if the SESAM message file is not installed in the system's BS2000 message file table, it can be set with this directive.

The message catalog must be set ACCESS=READ,SHARE=YES because it must be readable by the apache server's user id.

Sybase Configuration Directives

sybase.allow_persistent boolean

Whether to allow persistent Sybase connections.

sybase.max_persistent integer

The maximum number of persistent Sybase connections per process.

sybase.max_links integer

The maximum number of Sybase connections per process, including persistent connections.

Sybase-CT Configuration Directives

sybct.allow_persistent boolean

Whether to allow persistent Sybase-CT connections. The default is on.

sybct.max_persistent integer

The maximum number of persistent Sybase-CT connections per process. The default is -1 meaning unlimited.

sybct.max_links integer

The maximum number of Sybase-CT connections per process, including persistent connections. The default is -1 meaning unlimited.

sybct.min_server_severity integer

Server messages with severity greater than or equal to *sybct.min_server_severity* will be reported as warnings. This value can also be set from a script by calling *sybase_min_server_severity()*. The default is 10 which reports errors of information severity or greater.

sybct.min_client_severity integer

Client library messages with severity greater than or equal to *sybct.min_client_severity* will be reported as warnings. This value can also be set from a script by calling *sybase_min_client_severity()*. The default is 10 which effectively disables reporting.

sybct.login_timeout integer

The maximum time in seconds to wait for a connection attempt to succeed before returning failure. Note that if *max_execution_time* has been exceeded when a connection attempt times out, your script will be terminated before it can take action on failure. The default is one minute.

sybct.timeout integer

The maximum time in seconds to wait for a *select_db* or query operation to succeed before returning failure. Note that if *max_execution_time* has been exceeded when an operation times out, your script will be terminated before it can take action on failure. The default is no limit.

sybct.hostname string

The name of the host you claim to be connecting from, for display by *sp_who*. The default is none.

Informix Configuration Directives

ifx.allow_persistent boolean

Whether to allow persistent Informix connections.

ifx.max_persistent integer

The maximum number of persistent Informix connections per process.

ifx.max_links integer

The maximum number of Informix connections per process, including persistent connections.

ifx.default_host string

The default host to connect to when no host is specified in *ifx_connect()* or *ifx_pconnect()*.

ifx.default_user string

The default user id to use when none is specified in *ifx_connect()* or *ifx_pconnect()*.

ifx.default_password string

The default password to use when none is specified in *ifx_connect()* or *ifx_pconnect()*.

ifx.blobinfile boolean

Set to `TRUE` if you want to return blob columns in a file, `FALSE` if you want them in memory. You can override the setting at runtime with `ifx_blobinfile_mode()`.

ifx.textasvarchar boolean

Set to `TRUE` if you want to return TEXT columns as normal strings in select statements, `FALSE` if you want to use blob id parameters. You can override the setting at runtime with `ifx_textasvarchar()`.

ifx.byteasvarchar boolean

Set to `TRUE` if you want to return BYTE columns as normal strings in select queries, `FALSE` if you want to use blob id parameters. You can override the setting at runtime with `ifx_textasvarchar()`.

ifx.charasvarchar boolean

Set to `TRUE` if you want to trim trailing spaces from CHAR columns when fetching them.

ifx.nullformat boolean

Set to `TRUE` if you want to return NULL columns as the literal string "NULL", `FALSE` if you want them returned as the empty string "". You can override this setting at runtime with `ifx_nullformat()`.

BC Math Configuration Directives

bcmath.scale integer

Number of decimal digits for all bcmath functions.

Browser Capability Configuration Directives

browscap string

Name of browser capabilities file. See also `get_browser()`.

Multi-Byte String Configuration Directives

mbstring.internal_encoding string

`mbstring.internal_encoding` defines default internal character encoding.

mbstring.http_input string

`mbstring.http_input` defines default HTTP input character encoding.

mbstring.http_output string

`mbstring.http_output` defines default HTTP output character encoding.

mbstring.detect_order string

`mbstring.detect_order` defines default character encoding detection order.

mbstring.substitute_character string

`mbstring.substitute_character` defines character to substitute for invalid character codes.

Exif Configuration Directives

Exif supports automatically conversion for Unicode and JIS character encodings of user comments when module `mbstring` is available. This is done by first decoding the comment using the specified character set. The result is then encoded with another character set which should match your http output.

exif.encode_unicode string

`exif.encode_unicode` defines the character set UNICODE user comments are handled. This defaults to ISO-8859-15 which should work for most non asian countries. The setting can be empty or must be an encoding supported by `mbstring`. If it is empty the current internal encoding of `mbstring` is used.

exif.decode_unicode_motorola string

`exif.decode_unicode_motorola` defines the image internal character set for Unicode encoded user comments if image is in motorola byte order (big-endian). This setting cannot be empty but you can specify a list of encodings supported by `mbstring`. The default is UCS-2BE.

exif.decode_unicode_intel string

`exif.decode_unicode_intel` defines the image internal character set for Unicode encoded user comments if image is in intel byte order (little-endian). This setting cannot be empty but you can specify a list of encodings supported by `mbstring`. The default is UCS-2LE.

exif.encode_jis string

`exif.encode_jis` defines the character set JIS user comments are handled. This defaults to an empty value which forces the functions to use the current internal encoding of `mbstring`.

exif.decode_jis_motorola string

`exif.decode_jis_motorola` defines the image internal character set for JIS encoded user comments if image is in motorola byte order (big-endian). This setting cannot be empty but you can specify a list of encodings supported by `mbstring`. The default is JIS.

exif.decode_jis_intel string

`exif.decode_jis_intel` defines the image internal character set for JIS encoded user comments if image is in intel byte order (little-endian). This setting cannot be empty but you can specify a list of encodings supported by `mbstring`. The default is JIS.

Kapitola 4. Security

PHP is a powerful language and the interpreter, whether included in a web server as a module or executed as a separate CGI binary, is able to access files, execute commands and open network connections on the server. These properties make anything run on a web server insecure by default. PHP is designed specifically to be a more secure language for writing CGI programs than Perl or C, and with correct selection of compile-time and runtime configuration options, and proper coding practices, it can give you exactly the combination of freedom and security you need.

As there are many different ways of utilizing PHP, there are many configuration options controlling its behaviour. A large selection of options guarantees you can use PHP for a lot of purposes, but it also means there are combinations of these options and server configurations that result in an insecure setup.

The configuration flexibility of PHP is equally rivalled by the code flexibility. PHP can be used to build complete server applications, with all the power of a shell user, or it can be used for simple server-side includes with little risk in a tightly controlled environment. How you build that environment, and how secure it is, is largely up to the PHP developer.

This chapter starts with some general security advice, explains the different configuration option combinations and the situations they can be safely used, and describes different considerations in coding for different levels of security.

General considerations

A completely secure system is a virtual impossibility, so an approach often used in the security profession is one of balancing risk and usability. If every variable submitted by a user required two forms of biometric validation (such as a retinal scan and a fingerprint), you would have an extremely high level of accountability. It would also take half an hour to fill out a fairly complex form, which would tend to encourage users to find ways of bypassing the security.

The best security is often inobtrusive enough to suit the requirements without the user being prevented from accomplishing their work, or over-burdening the code author with excessive complexity. Indeed, some security attacks are merely exploits of this kind of overly built security, which tends to erode over time.

A phrase worth remembering: A system is only as good as the weakest link in a chain. If all transactions are heavily logged based on time, location, transaction type, etc. but the user is only verified based on a single cookie, the validity of tying the users to the transaction log is severely weakened.

When testing, keep in mind that you will not be able to test all possibilities for even the simplest of pages. The input you may expect will be completely unrelated to the input given by a disgruntled employee, a cracker with months of time on their hands, or a housecat walking across the keyboard. This is why it's best to look at the code from a logical perspective, to discern where unexpected data can be introduced, and then follow how it is modified, reduced, or amplified.

The Internet is filled with people trying to make a name for themselves by breaking your code, crashing your site, posting inappropriate content, and otherwise making your day interesting. It doesn't matter if you have a small or large site, you are a target by simply being online, by having a server that can be connected to. Many cracking programs do not discern by size, they simply trawl massive IP blocks looking for victims. Try not to become one.

Installed as CGI binary

Possible attacks

Using PHP as a CGI binary is an option for setups that for some reason do not wish to integrate PHP as a module into server software (like Apache), or will use PHP with different kinds of CGI wrappers to create safe chroot and setuid environments for scripts. This setup usually involves installing executable PHP binary to the web server cgi-bin directory. CERT advisory CA-96.11 (http://www.cert.org/advisories/CA-96.11.interpreters_in_cgi_bin_dir.html) recommends against placing any interpreters into cgi-bin. Even if the PHP binary can be used as a standalone interpreter, PHP is designed to prevent the attacks this setup makes possible:

- Accessing system files: `http://my.host/cgi-bin/php?/etc/passwd`

The query information in a url after the question mark (?) is passed as command line arguments to the interpreter by the CGI interface. Usually interpreters open and execute the file specified as the first argument on the command line.

When invoked as a CGI binary, PHP refuses to interpret the command line arguments.

- Accessing any web document on server: `http://my.host/cgi-bin/php/secret/doc.html`

The path information part of the url after the PHP binary name, `/secret/doc.html` is conventionally used to specify the name of the file to be opened and interpreted by the CGI program. Usually some web server configuration directives (Apache: Action) are used to redirect requests to documents like `http://my.host/secret/script.php` to the PHP interpreter. With this setup, the web server first checks the access permissions to the directory `/secret`, and after that creates the redirected request

`http://my.host/cgi-bin/php/secret/script.php`. Unfortunately, if the request is originally given in this form, no access checks are made by web server for file `/secret/script.php`, but only for the `/cgi-bin/php` file. This way any user able to access `/cgi-bin/php` is able to access any protected document on the web server.

In PHP, compile-time configuration option `--enable-force-cgi-redirect` and runtime configuration directives `doc_root` and `user_dir` can be used to prevent this attack, if the server document tree has any directories with access restrictions. See below for full the explanation of the different combinations.

Case 1: only public files served

If your server does not have any content that is not restricted by password or ip based access control, there is no need for these configuration options. If your web server does not allow you to do redirects, or the server does not have a way to communicate to the PHP binary that the request is a safely redirected request, you can specify the option `--enable-force-cgi-redirect` to the configure script. You still have to make sure your PHP scripts do not rely on one or another way of calling the script, neither by directly `http://my.host/cgi-bin/php/dir/script.php` nor by redirection `http://my.host/dir/script.php`.

Redirection can be configured in Apache by using `AddHandler` and `Action` directives (see below).

Case 2: using `--enable-force-cgi-redirect`

This compile-time option prevents anyone from calling PHP directly with a url like `http://my.host/cgi-bin/php/secret_dir/script.php`. Instead, PHP will only parse in this mode if it has gone through a web server redirect rule.

Usually the redirection in the Apache configuration is done with the following directives:

```
Action php-script /cgi-bin/php
AddHandler php-script .php
```

This option has only been tested with the Apache web server, and relies on Apache to set the non-standard CGI environment variable `REDIRECT_STATUS` on redirected requests. If your web server does not support any way of telling if the request is direct or redirected, you cannot use this option and you must use one of the other ways of running the CGI version documented here.

Case 3: setting `doc_root` or `user_dir`

To include active content, like scripts and executables, in the web server document directories is sometimes consider an insecure practice. If, because of some configuration mistake, the scripts are not executed but displayed as regular HTML documents, this may result in leakage of intellectual property or security information like passwords. Therefore many sysadmins will prefer setting up another directory structure for scripts that are accessible only through the PHP CGI, and therefore always interpreted and not displayed as such.

Also if the method for making sure the requests are not redirected, as described in the previous section, is not available, it is necessary to set up a script `doc_root` that is different from web document root.

You can set the PHP script document root by the configuration directive `doc_root` in the configuration file, or you can set the environment variable `PHP_DOCUMENT_ROOT`. If it is set, the CGI version of PHP will always construct the file name to open with this `doc_root` and the path information in the request, so you can be sure no script is executed outside this directory (except for `user_dir` below).

Another option usable here is `user_dir`. When `user_dir` is unset, only thing controlling the opened file name is `doc_root`. Opening an url like `http://my.host/~user/doc.php` does not result in opening a file under users home directory, but a file called `~user/doc.php` under `doc_root` (yes, a directory name starting with a tilde [~]).

If `user_dir` is set to for example `public_php`, a request like `http://my.host/~user/doc.php` will open a file called `doc.php` under the directory named `public_php` under the home directory of the user. If the home of the user is `/home/user`, the file executed is `/home/user/public_php/doc.php`.

`user_dir` expansion happens regardless of the `doc_root` setting, so you can control the document root and user directory access separately.

Case 4: PHP parser outside of web tree

A very secure option is to put the PHP parser binary somewhere outside of the web tree of files. In `/usr/local/bin`, for example. The only real downside to this option is that you will now have to

put a line similar to:

```
#!/usr/local/bin/php
```

as the first line of any file containing PHP tags. You will also need to make the file executable. That is, treat it exactly as you would treat any other CGI script written in Perl or sh or any other common scripting language which uses the `#!` shell-escape mechanism for launching itself.

To get PHP to handle `PATH_INFO` and `PATH_TRANSLATED` information correctly with this setup, the php parser should be compiled with the `--enable-discard-path` configure option.

Installed as an Apache module

When PHP is used as an Apache module it inherits Apache's user permissions (typically those of the "nobody" user). This has several impacts on security and authorization. For example, if you are using PHP to access a database, unless that database has built-in access control, you will have to make the database accessible to the "nobody" user. This means a malicious script could access and modify the database, even without a username and password. It's entirely possible that a web spider could stumble across a database administrator's web page, and drop all of your databases. You can protect against this with Apache authorization, or you can design your own access model using LDAP, .htaccess files, etc. and include that code as part of your PHP scripts.

Often, once security is established to the point where the PHP user (in this case, the apache user) has very little risk attached to it, it is discovered that PHP is now prevented from writing any files to user directories. Or perhaps it has been prevented from accessing or changing databases. It has equally been secured from writing good and bad files, or entering good and bad database transactions.

A frequent security mistake made at this point is to allow apache root permissions, or to escalate apache's abilities in some other way.

Escalating the Apache user's permissions to root is extremely dangerous and may compromise the entire system, so sudo'ing, chroot'ing, or otherwise running as root should not be considered by those who are not security professionals.

There are some simpler solutions. By using `open_basedir` you can control and restrict what directories are allowed to be used for PHP. You can also set up apache-only areas, to restrict all web based activity to non-user, or non-system, files.

Filesystem Security

PHP is subject to the security built into most server systems with respect to permissions on a file and directory basis. This allows you to control which files in the filesystem may be read. Care should be taken with any files which are world readable to ensure that they are safe for reading by all users who have access to that filesystem.

Since PHP was designed to allow user level access to the filesystem, it's entirely possible to write a PHP script that will allow you to read system files such as `/etc/passwd`, modify your ethernet connections, send massive printer jobs out, etc. This has some obvious implications, in that you need to ensure that the files that you read from and write to are the appropriate ones.

Consider the following script, where a user indicates that they'd like to delete a file in their home directory. This assumes a situation where a PHP web interface is regularly used for file management, so the Apache user is allowed to delete files in the user home directories.

Příklad 4-1. Poor variable checking leads to....

```
<?php
// remove a file from the user's home directory
$username = $_HTTP_POST_VARS['user_submitted_name'];
$homedir = "/home/$username";
$file_to_delete = "$userfile";
unlink ($homedir/$userfile);
echo "$file_to_delete has been deleted!";
?>
```

Since the username is postable from a user form, they can submit a username and file belonging to someone else, and delete files. In this case, you'd want to use some other form of authentication. Consider what could happen if the variables submitted were "../etc/" and "passwd". The code would then effectively read:

Příklad 4-2. ... A filesystem attack

```
<?php
// removes a file from anywhere on the hard drive that
// the PHP user has access to. If PHP has root access:
$username = "../etc/";
$homedir = "/home/../etc/";
$file_to_delete = "passwd";
unlink ("/home/../etc/passwd");
echo "/home/../etc/passwd has been deleted!";
?>
```

There are two important measures you should take to prevent these issues.

- Only allow limited permissions to the PHP web user binary.
- Check all variables which are submitted.

Here is an improved script:

Příklad 4-3. More secure file name checking

```
<?php
// removes a file from the hard drive that
// the PHP user has access to.
$username = $_HTTP_SERVER_VARS['REMOTE_USER']; // using an authentication mechanism
```

```

$homedir = "/home/$username";

$file_to_delete = basename("$userfile"); // strip paths
unlink ($homedir/$file_to_delete);

$fzp = fopen("/home/logging/filedelete.log","a"); //log the deletion
$logstring = "$username $homedir $file_to_delete";
fputs ($fzp, $logstring);
fclose($fzp);

echo "$file_to_delete has been deleted!";
?>

```

However, even this is not without its flaws. If your authentication system allowed users to create their own user logs, and a user chose the login "../etc/", the system is once again exposed. For this reason, you may prefer to write a more customized check:

Příklad 4-4. More secure file name checking

```

<?php
$username = $_HTTP_SERVER_VARS['REMOTE_USER']; // using an authentication mechanism
$homedir = "/home/$username";

if (!ereg('^[^./][^/]*$', $userfile))
    die('bad filename'); //die, do not process

if (!ereg('^[^./][^/]*$', $username))
    die('bad username'); //die, do not process
//etc...
?>

```

Depending on your operating system, there are a wide variety of files which you should be concerned about, including device entries (/dev/ or COM1), configuration files (/etc/ files and the .ini files), well known file storage areas (/home/, My Documents), etc. For this reason, it's usually easier to create a policy where you forbid everything except for what you explicitly allow.

Database Security

Nowadays, databases are cardinal components of any web based application by enabling websites to provide varying dynamic content. Since very sensitive or secret informations can be stored in such database, you should strongly consider to protect them somehow.

To retrieve or to store any information you need to connect to the database, send a legitimate query, fetch the result, and close the connection. Nowadays, the commonly used query language in this interaction is the Structured Query Language (SQL). See how an attacker can tamper with an SQL query.

As you can realize, PHP cannot protect your database by itself. The following sections aim to be an introduction into the very basics of how to access and manipulate databases within PHP scripts.

Keep in mind this simple rule: defence in depth. In the more place you take the more action to increase the protection of your database, the less probability of that an attacker succeeds, and exposes or abuse any stored secret information. Good design of the database schema and the application deals with your greatest fears.

Designing Databases

The first step is always to create the database, unless you want to use an existing third party's one. When a database is created, it is assigned to an owner, who executed the creation statement. Usually, only the owner (or a superuser) can do anything with the objects in that database, and in order to allow other users to use it, privileges must be granted.

Applications should never connect to the database as its owner or a superuser, because these users can execute any query at will, for example, modifying the schema (e.g. dropping tables) or deleting its entire content.

You may create different database users for every aspect of your application with very limited rights to database objects. The most required privileges should be granted only, and avoid that the same user can interact with the database in different use cases. This means that if intruders gain access to your database using one of these credentials, they can only effect as many changes as your application can.

You are encouraged not to implement all the business logic in the web application (i.e. your script), instead to do it in the database schema using views, triggers or rules. If the system evolves, new ports will be intended to open to the database, and you have to reimplement the logic in each separate database client. Over and above, triggers can be used to transparently and automatically handle fields, which often provides insight when debugging problems with your application or tracing back transactions.

Connecting to Database

You may want to establish the connections over SSL to encrypt client/server communications for increased security, or you can use ssh to encrypt the network connection between clients and the database server. If either of them is done, then monitoring your traffic and gaining informations in this way will be a hard work.

Encrypted Storage Model

SSL/SSH protects data travelling from the client to the server, SSL/SSH does not protect the persistent data stored in a database. SSL is an on-the-wire protocol.

Once an attacker gains access to your database directly (bypassing the webserver), the stored sensitive data may be exposed or misused, unless the information is protected by the database itself. Encrypting the data is a good way to mitigate this threat, but very few databases offer this type of data encryption.

The easiest way to work around this problem is to first create your own encryption package, and then use it from within your PHP scripts. PHP can assist you in this case with its several extensions, such as Mcrypt and Mhash, covering a wide variety of encryption algorithms. The script encrypts the data

be stored first, and decrypts it when retrieving. See the references for further examples how encryption works.

In case of truly hidden data, if its raw representation is not needed (i.e. not be displayed), hashing may be also taken into consideration. The well-known example for the hashing is storing the MD5 hash of a password in a database, instead of the password itself. See also `crypt()` and `md5()`.

Příklad 4-5. Using hashed password field

```
// storing password hash
$query = sprintf("INSERT INTO users(name,pwd) VALUES('%s','%s');",
    addslashes($username), md5($password));
$result = pg_exec($connection, $query);

// querying if user submitted the right password
$query = sprintf("SELECT 1 FROM users WHERE name='%s' AND pwd='%s';",
    addslashes($username), md5($password));
$result = pg_exec($connection, $query);

if (pg_numrows($result) > 0) {
    echo "Welcome, $username!";
}
else {
    echo "Authentication failed for $username.";
}
```

SQL Injection

Many web developers are unaware of how SQL queries can be tampered with, and assume that an SQL query is a trusted command. It means that SQL queries are able to circumvent access controls, thereby bypassing standard authentication and authorization checks, and sometimes SQL queries even may allow access to host operating system level commands.

Direct SQL Command Injection is a technique where an attacker creates or alters existing SQL commands to expose hidden data, or to override valuable ones, or even to execute dangerous system level commands on the database host. This is accomplished by the application taking user input and combining it with static parameters to build a SQL query. The following examples are based on true stories, unfortunately.

Owing to the lack of input validation and connecting to the database on behalf of a superuser or the one who can create users, the attacker may create a superuser in your database.

Příklad 4-6. Splitting the result set into pages ... and making superusers (PostgreSQL and MySQL)

```
$offset = argv[0]; // beware, no input validation!
$query = "SELECT id, name FROM products ORDER BY name LIMIT 20 OFFSET $offset;";
// with PostgreSQL
$result = pg_exec($conn, $query);
// with MySQL
$result = mysql_query($query);
```

Normal users click on the 'next', 'prev' links where the \$offset is encoded into the URL. The script expects that the incoming \$offset is decimal number. However, someone tries to break in with appending urlencode()'d form of the following to the URL

```
// in case of PostgreSQL
0;
insert into pg_shadow(username,usesysid,usesuper,usecatupd,passwd)
    select 'crack', usesysid, 't','t','crack'
    from pg_shadow where username='postgres';
--

// in case of MySQL
0;
UPDATE user SET Password=PASSWORD('crack') WHERE user='root';
FLUSH PRIVILEGES;
```

If it happened, then the script would present a superuser access to him. Note that 0; is to supply a valid offset to the original query and to terminate it.

Poznámka: It is common technique to force the SQL parser to ignore the rest of the query written by the developer with -- which is the comment sign in SQL.

A feasible way to gain passwords is to circumvent your search result pages. What the attacker needs only is to try if there is any submitted variable used in SQL statement which is not handled properly. These filters can be set commonly in a preceding form to customize WHERE, ORDER BY, LIMIT and OFFSET clauses in SELECT statements. If your database supports the UNION construct, the attacker may try to append an entire query to the original one to list passwords from an arbitrary table. Using encrypted password fields is strongly encouraged.

Příklad 4-7. Listing out articles ... and some passwords (any database server)

```
$query = "SELECT id, name, inserted, size FROM products
          WHERE size = '$size'
          ORDER BY $order LIMIT $limit, $offset;";
$result = odbc_exec($conn, $query);
```

The static part of the query can be combined with another SELECT statement which reveals all passwords:

```
,
union select '1', concat(uname||'-'||passwd) as name, '1971-01-01', '0' from usertable;
--
```


If this query (playing with the ' and --) were assigned to one of the variables used in \$query, the query beast awakened.

SQL UPDATES are also subject to attacking your database. These queries are also threatened by chopping and appending an entirely new query to it. But the attacker might fiddle with the SET clause. In this case some schema information must be possessed to manipulate the query successfully. This can be acquired by examining the form variable names, or just simply brute forcing. There are not so many naming convention for fields storing passwords or usernames.

Příklad 4-8. From resetting a password ... to gaining more privileges (any database server)

```
$query = "UPDATE usertable SET pwd='$pwd' WHERE uid='$uid';";
```

But a malicious user submits the value ' or uid like '%admin%'; -- to \$uid to change the admin's password, or simply sets \$pwd to "hehehe", admin='yes', trusted=100 " (with a trailing space) to gain more privileges. Then, the query will be twisted:

```
// $uid == ' or uid like '%admin%'; --
$query = "UPDATE usertable SET pwd='...' WHERE uid=" or uid like '%admin%'; -
-";

// $pwd == "hehehe", admin='yes', trusted=100 "
$query = "UPDATE usertable SET pwd='hehehe', admin='yes', trusted=100 WHERE ...;";
```

A frightening example how operating system level commands can be accessed on some database hosts.

Příklad 4-9. Attacking the database host's operating system (MSSQL Server)

```
$query = "SELECT * FROM products WHERE id LIKE '%$prod%'";
$result = mssql_query($query);
```

If attacker submits the value a%' exec master..xp_cmdshell 'net user test testpass /ADD' -- to \$prod, then the \$query will be:

```
$query = "SELECT * FROM products
          WHERE id LIKE 'a%'
          exec master..xp_cmdshell 'net user test testpass /ADD'-
-";
$result = mssql_query($query);
```

MSSQL Server executes the SQL statements in the batch including a command to add a new user to the local accounts database. If this application were running as `sa` and the MSSQLSERVER service is running with sufficient privileges, the attacker would now have an account with which to access this machine.

Poznámka: Some of the examples above is tied to a specific database server. This does not mean that a similar attack is impossible against other products. Your database server may be so vulnerable in other manner.

Avoiding techniques

You may plead that the attacker must possess a piece of information about the database schema in most examples. You are right, but you never know when and how it can be taken out, and if it happens, your database may be exposed. If you are using an open source, or publicly available database handling package, which may belong to a content management system or forum, the intruders easily produce a copy of a piece of your code. It may be also a security risk if it is a poorly designed one.

These attacks are mainly based on exploiting the code not being written with security in mind. Never trust on any kind of input, especially which comes from the client side, even though it comes from a select box, a hidden input field or a cookie. The first example shows that such a blameless query can cause disasters.

- Never connect to the database as a superuser or as the database owner. Use always customized users with very limited privileges.
- Check if the given input has the expected data type. PHP has a wide range of input validating functions, from the simplest ones found in Variable Functions and in Character Type Functions (e.g. `is_numeric()`, `ctype_digit()` respectively) onwards the Perl compatible Regular Expressions support.
- If the application waits for numerical input, consider to verify data with `is_numeric()`, or silently change its type using `settype()`, or use its numeric representation by `sprintf()`.

Příklad 4-10. A more secure way to compose a query for paging

```
settype($offset, 'integer');
$query = "SELECT id, name FROM products ORDER BY name LIMIT 20 OFFSET $offset;";

// please note %d in the format string, using %s would be meaningless
$query = sprintf("SELECT id, name FROM products ORDER BY name LIMIT 20 OFF-
SET %d;",
                $offset);
```

- Quote each non numeric user input which is passed to the database with `addslashes()` or `addcslashes()`. See the first example. As the examples shows, quotes burnt into the static part of the query is not enough, and can be easily hacked.

- Do not print out any database specific information, especially about the schema, by fair means or foul. See also Error Reporting and Error Handling and Logging Functions.
- You may use stored procedures and previously defined cursors to abstract data access so that users do not directly access tables or views, but this solution has another impacts.

Besides these, you benefit from logging queries either within your script or by the database itself, if it supports. Obviously, the logging is unable to prevent any harmful attempt, but it can be helpful to trace back which application has been circumvented. The log is not useful by itself, but through the information it contains. The more detail is generally better.

Error Reporting

With PHP security, there are two sides to error reporting. One is beneficial to increasing security, the other is detrimental.

A standard attack tactic involves profiling a system by feeding it improper data, and checking for the kinds, and contexts, of the errors which are returned. This allows the system cracker to probe for information about the server, to determine possible weaknesses. For example, if an attacker had gleaned information about a page based on a prior form submission, they may attempt to override variables, or modify them:

Příklad 4-11. Attacking Variables with a custom HTML page

```
<form method="post" action="attacktarget?username=badfoo&password=badfoo">
<input type="hidden" name="username" value="badfoo">
<input type="hidden" name="password" value="badfoo">
</form>
```

The PHP errors which are normally returned can be quite helpful to a developer who is trying to debug a script, indicating such things as the function or file that failed, the PHP file it failed in, and the line number which the failure occurred in. This is all information that can be exploited. It is not uncommon for a php developer to use `show_source()`, `highlight_string()`, or `highlight_file()` as a debugging measure, but in a live site, this can expose hidden variables, unchecked syntax, and other dangerous information. Especially dangerous is running code from known sources with built-in debugging handlers, or using common debugging techniques. If the attacker can determine what general technique you are using, they may try to brute-force a page, by sending various common debugging strings:

Příklad 4-12. Exploiting common debugging variables

```
<form method="post" action="attacktarget?errors=Y&showerrors=1"&debug=1">
<input type="hidden" name="errors" value="Y">
<input type="hidden" name="showerrors" value="1">
<input type="hidden" name="debug" value="1">
</form>
```

Regardless of the method of error handling, the ability to probe a system for errors leads to providing an attacker with more information.

For example, the very style of a generic PHP error indicates a system is running PHP. If the attacker was looking at an .html page, and wanted to probe for the back-end (to look for known weaknesses in the system), by feeding it the wrong data they may be able to determine that a system was built with PHP.

A function error can indicate whether a system may be running a specific database engine, or give clues as to how a web page or programmed or designed. This allows for deeper investigation into open database ports, or to look for specific bugs or weaknesses in a web page. By feeding different pieces of bad data, for example, an attacker can determine the order of authentication in a script, (from the line number errors) as well as probe for exploits that may be exploited in different locations in the script.

A filesystem or general PHP error can indicate what permissions the webserver has, as well as the structure and organization of files on the web server. Developer written error code can aggravate this problem, leading to easy exploitation of formerly "hidden" information.

There are three major solutions to this issue. The first is to scrutinize all functions, and attempt to compensate for the bulk of the errors. The second is to disable error reporting entirely on the running code. The third is to use PHP's custom error handling functions to create your own error handler. Depending on your security policy, you may find all three to be applicable to your situation.

One way of catching this issue ahead of time is to make use of PHP's own `error_reporting()`, to help you secure your code and find variable usage that may be dangerous. By testing your code, prior to deployment, with `E_ALL`, you can quickly find areas where your variables may be open to poisoning or modification in other ways. Once you are ready for deployment, by using `E_NONE`, you insulate your code from probing.

Příklad 4-13. Finding dangerous variables with E_ALL

```
<?php
if ($username) { // Not initialized or checked before usage
    $good_login = 1;
}
if ($good_login == 1) { // If above test fails, not initialized or checked before usage
    fpassthru ("/highly/sensitive/data/index.html");
}
?>
```

Using Register Globals

One feature of PHP that can be used to enhance security is configuring PHP with `register_globals = off`. By turning off the ability for any user-submitted variable to be injected into PHP code, you can

reduce the amount of variable poisoning a potential attacker may inflict. They will have to take the additional time to forge submissions, and your internal variables are effectively isolated from user submitted data.

While it does slightly increase the amount of effort required to work with PHP, it has been argued that the benefits far outweigh the effort.

Příklad 4-14. Working without `register_globals=off`

```
<?php
if ($username) { // can be forged by a user in get/post/cookies
    $good_login = 1;
}

if ($good_login == 1) { // can be forged by a user in get/post/cookies,
    fpassthru ("/highly/sensitive/data/index.html");
}
?>
```

Příklad 4-15. Working with `register_globals = off`

```
<?php
if($HTTP_COOKIE_VARS['username']){
    // can only come from a cookie, forged or otherwise
    $good_login = 1;
    fpassthru ("/highly/sensitive/data/index.html");
}
?>
```

By using this wisely, it's even possible to take preventative measures to warn when forging is being attempted. If you know ahead of time exactly where a variable should be coming from, you can check to see if submitted data is coming from an inappropriate kind of submission. While it doesn't guarantee that data has not been forged, it does require an attacker to guess the right kind of forging.

Příklad 4-16. Detecting simple variable poisoning

```
<?php
if ($HTTP_COOKIE_VARS['username'] &&
    !$HTTP_POST_VARS['username'] &&
    !$HTTP_GET_VARS['username'] ) {
    // Perform other checks to validate the user name...
    $good_login = 1;
    fpassthru ("/highly/sensitive/data/index.html");
} else {
    mail("admin@example.com", "Possible breakin attempt", $HTTP_SERVER_VARS['REMOTE_ADDR'],
        echo "Security violation, admin has been alerted.");
    exit;
}
```

```
?>
```

Of course, simply turning off `register_globals` does not mean code is secure. For every piece of data that is submitted, it should also be checked in other ways.

User Submitted Data

The greatest weakness in many PHP programs is not inherent in the language itself, but merely an issue of code not being written with security in mind. For this reason, you should always take the time to consider the implications of a given piece of code, to ascertain the possible damage if an unexpected variable is submitted to it.

Příklad 4-17. Dangerous Variable Usage

```
<?php
// remove a file from the user's home directory... or maybe
// somebody else's?
unlink ($evil_var);

// Write logging of their access... or maybe an /etc/passwd entry?
fputs ($fp, $evil_var);

// Execute something trivial.. or rm -rf *?
system ($evil_var);
exec ($evil_var);

?>
```

You should always carefully examine your code to make sure that any variables being submitted from a web browser are being properly checked, and ask yourself the following questions:

- Will this script only affect the intended files?
- Can unusual or undesirable data be acted upon?
- Can this script be used in unintended ways?
- Can this be used in conjunction with other scripts in a negative manner?
- Will any transactions be adequately logged?

By adequately asking these questions while writing the script, rather than later, you prevent an unfortunate re-write when you need to increase your security. By starting out with this mindset, you won't guarantee the security of your system, but you can help improve it.

You may also want to consider turning off `register_globals`, `magic_quotes`, or other convenience settings which may confuse you as to the validity, source, or value of a given variable. Working with PHP in `error_reporting(E_ALL)` mode can also help warn you about variables being used before they are checked or initialized (so you can prevent unusual data from being operated upon).

Hiding PHP

In general, security by obscurity is one of the weakest forms of security. But in some cases, every little bit of extra security is desirable.

A few simple techniques can help to hide PHP, possibly slowing down an attacker who is attempting to discover weaknesses in your system. By setting `expose_php = off` in your `php.ini` file, you reduce the amount of information available to them.

Another tactic is to configure web servers such as apache to parse different filetypes through PHP, either with an `.htaccess` directive, or in the apache configuration file itself. You can then use misleading file extensions:

Příklad 4-18. Hiding PHP as another language

```
# Make PHP code look like other code types
AddType application/x-httpd-php .asp .py .pl
```

Or obscure it completely:

Příklad 4-19. Using unknown types for PHP extensions

```
# Make PHP code look like unknown types
AddType application/x-httpd-php .bop .foo .133t
```

Or hide it as html code, which has a slight performance hit because all html will be parsed through the PHP engine:

Příklad 4-20. Using html types for PHP extensions

```
# Make all PHP code look like html
AddType application/x-httpd-php .htm .html
```

For this to work effectively, you must rename your PHP files with the above extensions. While it is a form of security through obscurity, it's a minor preventative measure with few drawbacks.

Keeping Current

PHP, like any other large system, is under constant scrutiny and improvement. Each new version will often include both major and minor changes to enhance and repair security flaws, configuration mishaps, and other issues that will affect the overall security and stability of your system.

Like other system-level scripting languages and programs, the best approach is to update often, and maintain awareness of the latest versions and their changes.

Část II. Reference jazyka

Kapitola 5. Základní syntaxe

Opuštění HTML

Jsou čtyři způsoby jak opustit HTML a vstoupit to "PHP módu":

Příklad 5-1. Způsoby opuštění HTML

1. `<? echo ("toto je nejjednodušší SGML zpracovatelská instrukce\n"); ?>`
2. `<?php echo("pokud chcete zpracovávat XHTML nebo XML dokumenty, používejte toto\n"); ?>`
3. `<script language="php">
 echo ("některé editory (například FrontPage) nemají zpracovatelské instrukce v lásce");
</script>`
4. `<% echo ("případně můžete používat ASP tagy"); %>
 <%= $variable; # toto je zkratka za "<?echo .." %>`

První způsob je dostupný pouze, pokud jsou povoleny krátké tagy. To se dá udělat povolením konfigurační direktivy `short_open_tag` v konfiguračním souboru PHP, nebo kompilací PHP s **configure** volbou `--enable-short-tags`.

Obecně preferovanou metodou je druhý způsob, protože umožňuje snadnou implementaci dalšího generování XHTML z PHP.

Čtvrtý způsob je dostupný, pouze pokud byly povoleny ASP tagy pomocí konfigurační direktivy `asp_tags`.

Poznámka: Podpora ASP tagů byla přidána v 3.0.4.

Případná bezprostředně následující sekvence konce řádku je součástí uzavírajícího tagu.

Oddělování instrukcí

Instrukce se oddělují stejně jako v C nebo Perlu - ukončujete každý výraz středníkem.

Uzavírající tag (`?>`) také implikuje konec výrazu, takže následující ukázky jsou ekvivalentní:

```
<?php
    echo "Toto je test";
?>

<?php echo "Toto je test" ?>
```

Komentáře

PHP podporuje komentářové notace jazyků 'C', 'C++' a Unixového shellu. Například:

```
<?php
    echo "Toto je test"; // Toto je jednořádkový komentář typu C++
    /* Toto je víceřádkový komentář
       a ještě jeden komentář */
    echo "Toto je další test";
    echo "Poslední Test"; # Toto je komentář shellového typu
?>
```

Jednořádkové typy komentářů ve skutečnosti komentují do konce řádku nebo současného bloku PHP kódu, podle toho, co se vyskytuje dříve.

```
<h1>Toto je <?php # echo "malý";?> příklad.</h1>
<p>Hlavička na předchozím řádku bude 'Toto je příklad'.
```

Měli byste si dát pozor na vnořování komentářů typu 'C++', ke kterému může dojít při zakomentování velkých bloků.

```
<?php
    /*
        echo "Toto je test"; /* Tento komentář způsobí problém */
    */
?>
```

Kapitola 6. Types

Introduction

PHP supports eight primitive types.

Four scalar types:

- boolean
- integer
- floating-point number (float)
- string

Two compound types:

- array
- object

And finally two special types:

- resource
- NULL

Poznámka: In this manual you'll often find `mixed` parameters. This pseudo-type indicates multiple possibilities for that parameter.

The type of a variable is usually not set by the programmer; rather, it is decided at runtime by PHP depending on the context in which that variable is used.

Poznámka: If you want to check out the type and value of a certain expression, use `var_dump()`. If you simply want a human-readable representation of the type for debugging, use `gettype()`. To check for a certain type, do *not* use `gettype()`, but use the `is_*` functions.

If you would like to force a variable to be converted to a certain type, you may either cast the variable or use the `settype()` function on it.

Note that a variable may behave in different manners in certain situations, depending on what type it is at the time. For more information, see the section on Type Juggling.

Booleans

This is the easiest type. A boolean expresses a truth value. It can be either `TRUE` or `FALSE`.

Poznámka: The boolean type was introduced in PHP 4.

Syntax

To specify a boolean literal, use either the keyword `TRUE` or `FALSE`. Both are case-insensitive.

```
$foo = True; // assign the value TRUE to $foo
```

Usually you use some kind of operator which returns a boolean value, and then pass it on to a control structure.

```
// == is an operator which returns a boolean
if ($action == "show_version") {
    echo "The version is 1.23";
}

// this is not necessary:
if ($show_separators == TRUE) {
    echo "<hr>\n";
}

// because you can simply type this:
if ($show_separators) {
    echo "<hr>\n";
}
```

Converting to boolean

To explicitly convert a value to boolean, use either the `(bool)` or the `(boolean)` cast. However, in most cases you do not need to use the cast, since a value will be automatically converted if an operator, function or control structure requires a boolean argument.

See also [Type Juggling](#).

When converting to boolean, the following values are considered `FALSE`:

- the boolean `FALSE`
- the integer `0` (zero)
- the float `0.0` (zero)
- the empty string, and the string `"0"`
- an array with zero elements
- an object with zero elements
- the special type `NULL` (including unset variables)

Every other value is considered `TRUE` (including any resource).

Varování

-1 is considered `TRUE`, like any other non-zero (whether negative or positive) number!

Integers

An integer is a number of the set $Z = \{ \dots, -2, -1, 0, 1, 2, \dots \}$.

See also: Arbitrary length integers and Floating point numbers

Syntax

Integers can be specified in decimal (10-based), hexadecimal (16-based) or octal (8-based) notation, optionally preceded by a sign (- or +).

If you use the octal notation, you must precede the number with a 0 (zero), to use hexadecimal notation precede the number with 0x.

Příklad 6-1. Integer literals

```
$a = 1234; # decimal number
$a = -123; # a negative number
$a = 0123; # octal number (equivalent to 83 decimal)
$a = 0x1A; # hexadecimal number (equivalent to 26 decimal)
```

The size of an integer is platform-dependent, although a maximum value of about two billion is the usual value (that's 32 bits signed). PHP does not support unsigned integers.

Integer overflow

If you specify a number beyond the bounds of the integer type, it will be interpreted as a float instead. Also, if you perform an operation that results in a number beyond the bounds of the integer type, a float will be returned instead.

```
$large_number = 2147483647;
var_dump($large_number);
// output: int(2147483647)

$large_number = 2147483648;
var_dump($large_number);
// output: float(2147483648)

// this goes also for hexadecimal specified integers:
var_dump( 0x80000000 );
```

```
// output: float(2147483648)

$million = 1000000;
$large_number = 50000 * $million;
var_dump($large_number);
// output: float(50000000000)
```

Varování

Unfortunately, there was a bug in PHP so that this does not always work correctly when there are negative numbers involved. For example: when you do `-50000 * $million`, the result will be `-429496728`. However, when both operands are positive there is no problem.

This is solved in PHP 4.1.0.

There is no integer division operator in PHP. `1/2` yields the float `0.5`.

```
var_dump( 25/7 );
// output: float(3.5714285714286)
```

Converting to integer

To explicitly convert a value to integer, use either the `(int)` or the `(integer)` cast. However, in most cases you do not need to use the cast, since a value will be automatically converted if an operator, function or control structure requires a integer argument.

See also type-juggling.

From booleans

`FALSE` will yield `0` (zero), and `TRUE` will yield `1` (one).

From floating point numbers

When converting from float to integer, the number will be rounded *towards zero*.

If the float is beyond the boundaries of integer (usually $\pm 2.15 \times 10^9 = 2^{31}$), the result is undefined, since the float hasn't got enough precision to give an exact integer result. No warning, not even a notice will be issued in this case!

Varování

Never cast an unknown fraction to integer, as this can sometimes lead to unexpected results.

```
echo (int) ( (0.1+0.7) * 10 ); // echoes 7!
```

See for more information the warning about float-precision.

From strings

See String conversion

From other types**Výstraha**

Behaviour of converting to integer is undefined for other types. Currently, the behaviour is the same as if the value was first converted to boolean. However, do *not* rely on this behaviour, as it can change without notice.

Floating point numbers

Floating point numbers (AKA "floats", "doubles" or "real numbers") can be specified using any of the following syntaxes:

```
$a = 1.234; $a = 1.2e3; $a = 7E-10;
```

The size of a float is platform-dependent, although a maximum of $\sim 1.8e308$ with a precision of roughly 14 decimal digits is a common value (that's 64 bit IEEE format).

Floating point precision

It is quite usual that simple decimal fractions like 0.1 or 0.7 cannot be converted into their internal binary counterparts without a little loss of precision. This can lead to confusing results: for example, `floor((0.1+0.7)*10)` will usually return 7 instead of the expected 8 as the result of the internal representation really being something like 7.999999999...

This is related to the fact that it is impossible to exactly express some fractions in decimal notation with a finite number of digits. For instance, $1/3$ in decimal form becomes 0.333333... .

So never trust floating number results to the last digit and never compare floating point numbers for equality. If you really need higher precision, you should use the arbitrary precision math functions or gmp functions instead.

Strings

A string is series of characters. In PHP, a character is the same as a byte, that is, there are exactly 256 different characters possible. This also implies that PHP has no native support of Unicode.

Poznámka: It is no problem for a string to become very large. There is no practical bound to the size of strings imposed by PHP, so there is no reason at all to worry about long strings.

Syntax

A string literal can be specified in three different ways.

- single quoted
- double quoted
- heredoc syntax

Single quoted

The easiest way to specify a simple string is to enclose it in single quotes (the character `'`).

To specify a literal single quote, you will need to escape it with a backslash (`\`), like in many other languages. If a backslash needs to occur before a single quote or at the end of the string, you need to double it. Note that if you try to escape any other character, the backslash too will be printed! So usually there is no need to escape the backslash itself.

Poznámka: In PHP 3, a warning will be issued at the `E_NOTICE` level when this happens.

Poznámka: Unlike the two other syntaxes, variables will *not* be expanded when they occur in single quoted strings.

```

echo 'this is a simple string';
echo 'You can also have embedded newlines in strings,
like this way.';
echo 'Arnold once said: "I\'ll be back"';
// output: ... "I'll be back"
echo 'Are you sure you want to delete C:\\*..*?';
// output: ... delete C:\\*..*?
echo 'Are you sure you want to delete C:\\*..*?';
// output: ... delete C:\\*..*?
echo 'I am trying to include at this point: \n a newline';
// output: ... this point: \n a newline

```

Double quoted

If the string is enclosed in double-quotes ("), PHP understands more escape sequences for special characters:

Tabulka 6-1. Escaped characters

sequence	meaning
\n	linefeed (LF or 0x0A (10) in ASCII)
\r	carriage return (CR or 0x0D (13) in ASCII)
\t	horizontal tab (HT or 0x09 (9) in ASCII)
\\	backslash
\\$	dollar sign
\"	double-quote
\[0-7]{1,3}	the sequence of characters matching the regular expression is a character in octal notation
\x[0-9A-Fa-f]{1,2}	the sequence of characters matching the regular expression is a character in hexadecimal notation

Again, if you try to escape any other character, the backslash will be printed too!

But the most important pre of double-quoted strings is the fact that variable names will be expanded. See string parsing for details.

Heredoc

Another way to delimit strings is by using here doc syntax ("<<<"). One should provide an identifier after <<<, then the string, and then the same identifier to close the quotation.

The closing identifier *must* begin in the first column of the line. Also, the identifier used must follow the same naming rules as any other label in PHP: it must contain only alphanumeric characters and underscores, and must start with a non-digit character or underscore.

Varování

It is very important to note that the line with the closing identifier contains no other characters, except *possibly* a semicolon (;). That means especially that the identifier *may not be indented*, and there may not be any spaces or tabs after or before the semicolon.

Probably the nastiest gotcha is that there may also not be a carriage return (`\r`) at the end of the line, only a form feed, AKA newline (`\n`). Since Microsoft Windows uses the sequence `\r\n` as a line terminator, your heredoc may not work if you write your script in a Windows editor. However, most programming editors provide a way to save your files with a UNIX line terminator.

Here doc text behaves just like a double-quoted string, without the double-quotes. This means that you do not need to escape quotes in your here docs, but you can still use the escape codes listed above. Variables are expanded, but the same care must be taken when expressing complex variables inside a here doc as with strings.

Příklad 6-2. Here doc string quoting example

```
<?php
$str = <<<EOD
Example of string
spanning multiple lines
using heredoc syntax.
EOD;

/* More complex example, with variables. */
class foo
{
    var $foo;
    var $bar;

    function foo()
    {
        $this->foo = 'Foo';
        $this->bar = array('Bar1', 'Bar2', 'Bar3');
    }
}

$foo = new foo();
$name = 'MyName';

echo <<<EOT
My name is "$name". I am printing some $foo->foo.
Now, I am printing some {$foo->bar[1]}.
This should print a capital 'A': \x41
EOT;
?>
```

Poznámka: Here doc support was added in PHP 4.

Variable parsing

When a string is specified in double quotes or with heredoc, variables are parsed within it.

There are two types of syntax, a simple one and a complex one. The simple syntax is the most common and convenient, it provides a way to parse a variable, an array value, or an object property.

The complex syntax was introduced in PHP 4, and can be recognised by the curly braces surrounding the expression.

Simple syntax

If a dollar sign (\$) is encountered, the parser will greedily take as much tokens as possible to form a valid variable name. Enclose the variable name in curly braces if you want to explicitly specify the end of the name.

```
$beer = 'Heineken';
echo "$beer's taste is great"; // works, "'" is an invalid character for varnames
echo "He drunk some $beers"; // won't work, 's' is a valid character for varnames
echo "He drunk some ${beer}s"; // works
```

Similarly, you can also have an array index or an object property parsed. With array indices, the closing square bracket (]) marks the end of the index. For object properties the same rules apply as to simple variables, though with object properties there doesn't exist a trick like the one with variables.

```
$fruits = array( 'strawberry' => 'red' , 'banana' => 'yellow' );

// note that this works differently outside string-quotes.
echo "A banana is $fruits[banana].";

echo "This square is $square->width meters broad.";

// Won't work. For a solution, see the complex syntax.
echo "This square is $square->width00 centimeters broad.";
```

For anything more complex, you should use the complex syntax.

Complex (curly) syntax

This isn't called complex because the syntax is complex, but because you can include complex expressions this way.

In fact, you can include any value that is in the namespace in strings with this syntax. You simply write the expression the same way as you would outside the string, and then include it in { and }.

Since you can't escape '{', this syntax will only be recognised when the \$ is immediately following the {. (Use "{\\$" or "{\\$" to get a literal "{\$"). Some examples to make it clear:

```
$great = 'fantastic';
echo "This is { $great}"; // won't work, outputs: This is { fantastic}
echo "This is {$great}"; // works, outputs: This is fantastic
echo "This square is {$square->width}00 centimeters broad.";
echo "This works: {$arr[4][3]}";

// This is wrong for the same reason
// as $foo[bar] is wrong outside a string.
echo "This is wrong: {$arr[foo][3]}";

echo "You should do it this way: {$arr['foo'][3]}";
echo "You can even write {$obj->values[3]->name}";
echo "This is the value of the var named $name: {${$name}}";
```

String access by character

Characters within strings may be accessed by specifying the zero-based offset of the desired character after the string in curly braces.

Poznámka: For backwards compatibility, you can still use the array-braces. However, this syntax is deprecated as of PHP 4.

Příklad 6-3. Some string examples

```
<?php
/* Assigning a string. */
$str = "This is a string";

/* Appending to it. */
$str = $str . " with some more text";

/* Another way to append, includes an escaped newline. */
$str .= " and a newline at the end.\n";

/* This string will end up being '<p>Number: 9</p>' */
$num = 9;
$str = "<p>Number: $num</p>";

/* This one will be '<p>Number: $num</p>' */
$num = 9;
$str = '<p>Number: $num</p>';
```

```

/* Get the first character of a string */
$str = 'This is a test.';
$first = $str{0};

/* Get the last character of a string. */
$str = 'This is still a test.';
$last = $str{strlen($str)-1};
?>

```

Useful functions

Strings may be concatenated using the `.` (dot) operator. Note that the `+` (addition) operator will not work for this. Please see String operators for more information.

There are a lot of useful functions for string modification.

See the string functions section for general functions, the regular expression functions for advanced find&replacing (in two tastes: Perl and POSIX extended).

There are also functions for URL-strings, and functions to encrypt/decrypt strings (mcrypt and mhash).

Finally, if you still didn't find what you're looking for, see also the character type functions.

String conversion

When a string is evaluated as a numeric value, the resulting value and type are determined as follows.

The string will evaluate as a float if it contains any of the characters `.`, `e`, or `E`. Otherwise, it will evaluate as an integer.

The value is given by the initial portion of the string. If the string starts with valid numeric data, this will be the value used. Otherwise, the value will be 0 (zero). Valid numeric data is an optional sign, followed by one or more digits (optionally containing a decimal point), followed by an optional exponent. The exponent is an `e` or `E` followed by one or more digits.

When the first expression is a string, the type of the variable will depend on the second expression.

```

$foo = 1 + "10.5";           // $foo is float (11.5)
$foo = 1 + "-1.3e3";         // $foo is float (-1299)
$foo = 1 + "bob-1.3e3";      // $foo is integer (1)
$foo = 1 + "bob3";          // $foo is integer (1)
$foo = 1 + "10 Small Pigs";  // $foo is integer (11)
$foo = 1 + "10 Little Piggies"; // $foo is integer (11)
$foo = "10.0 pigs " + 1;     // $foo is integer (11)
$foo = "10.0 pigs " + 1.0;   // $foo is float (11)

```

For more information on this conversion, see the Unix manual page for `strtod(3)`.

If you would like to test any of the examples in this section, you can cut and paste the examples and insert the following line to see for yourself what's going on:

```
echo "\$foo==\$foo; type is " . gettype ($foo) . "<br>\n";
```

Arrays

An array in PHP is actually an ordered map. A map is a type that maps *values* to *keys*. This type is optimized in several ways, so you can use it as a real array, or a list (vector), hashtable (which is an implementation of a map), dictionary, collection, stack, queue and probably more. Because you can have another PHP-array as a value, you can also quite easily simulate trees.

Explanation of those structures is beyond the scope of this manual, but you'll find at least one example for each of those structures. For more information about those structures, we refer you to external literature about this broad topic.

Syntax

Specifying with array()

An array can be created by the array() language-construct. It takes a certain number of comma-separated *key => value* pairs.

A *key* is either a nonnegative integer or a string. If a *key* is the standard representation of a non-negative integer, it will be interpreted as such (i.e. '8' will be interpreted as 8, while '08' will be interpreted as '08').

A *value* can be anything.

If you omit a *key*, the maximum of the integer-indices is taken, and the new *key* will be that maximum + 1. If no integer-indices exist yet, the *key* will be 0 (zero). If you specify a *key* that already has a *value* assigned to it, that *value* will be overwritten.

```
array( [key =>] value
      , ...
      )
// key is either string or nonnegative integer
// value can be anything
```

Creating/modifying with square-bracket syntax

You can also modify an existing array, by explicitly setting values.

This is done by assigning values to the array while specifying the key in brackets. You can also omit the key, add an empty pair of brackets ("[]") to the variable-name in that case.

```
$arr[key] = value;
$arr[] = value;
// key is either string or nonnegative integer
// value can be anything
```

If `$arr` doesn't exist yet, it will be created. So this is also an alternative way to specify an array. To change a certain value, just assign a new value to it. If you want to remove a key/value pair, you need to `unset()` it.

Useful functions

There are quite some useful function for working with arrays, see the array-functions section.

Poznámka: The `unset()` function allows unsetting keys of an array. Be aware that the array will NOT be reindexed.

```
$a = array( 1 => 'one', 2 => 'two', 3 => 'three' );
unset( $a[2] );
/* will produce an array that would have been defined as
   $a = array( 1=>'one', 3=>'three' );
   and NOT
   $a = array( 1 => 'one', 2 => 'three' );
*/
```

The `foreach` control structure exists specifically for arrays. It provides an easy way to traverse an array.

Array do's and don'ts

Why is `$foo[bar]` wrong?

You might have seen the following syntax in old scripts:

```
$foo[bar] = 'enemy';
echo $foo[bar];
// etc
```

This is wrong, but it works. Then, why is it wrong? The reason is that, as stated in the syntax section, there must be an expression between the square brackets ('[' and ']'). That means that you can write things like this:


```
echo $arr[ foo(true) ];
```

This is an example of using a function return value as the array index. PHP knows also about constants, and you may have seen the `E_*` before.

```
$error_descriptions[E_ERROR] = "A fatal error has occurred";
$error_descriptions[E_WARNING] = "PHP issued a warning";
$error_descriptions[E_NOTICE] = "This is just an informal notice";
```

Note that `E_ERROR` is also a valid identifier, just like `bar` in the first example. But the last example is in fact the same as writing:

```
$error_descriptions[1] = "A fatal error has occurred";
$error_descriptions[2] = "PHP issued a warning";
$error_descriptions[8] = "This is just an informal notice";
```

because `E_ERROR` equals 1, etc.

Then, how is it possible that `$foo[bar]` works? It works, because `bar` is due to its syntax expected to be a constant expression. However, in this case no constant with the name `bar` exists. PHP now assumes that you meant `bar` literally, as the string `"bar"`, but that you forgot to write the quotes.

So why is it bad then?

At some point in the future, the PHP team might want to add another constant or keyword, and then you get in trouble. For example, you already cannot use the words `empty` and `default` this way, since they are special keywords.

And, if these arguments don't help: this syntax is simply deprecated, and it might stop working some day.

Poznámka: When you turn `error_reporting` to `E_ALL`, you will see that PHP generates warnings whenever this construct is used. This is also valid for other deprecated 'features'. (put the line `error_reporting(E_ALL);` in your script)

Poznámka: Inside a double-quoted string, an other syntax is valid. See variable parsing in strings for more details.

Examples

The array type in PHP is very versatile, so here will be some examples to show you the full power of arrays.

```
// this
$a = array( 'color' => 'red'
           , 'taste' => 'sweet'
           , 'shape' => 'round'
           , 'name'  => 'apple'
           ,         4           // key will be 0
           );

// is completely equivalent with
$a['color'] = 'red';
$a['taste'] = 'sweet';
$a['shape'] = 'round';
$a['name']  = 'apple';
$a[]       = 4;           // key will be 0

$b[] = 'a';
$b[] = 'b';
$b[] = 'c';
// will result in the array array( 0 => 'a' , 1 => 'b' , 2 => 'c' ),
// or simply array('a', 'b', 'c')
```

Příklad 6-4. Using array()

```
// Array as (property-)map
$map = array( 'version' => 4
             , 'OS'      => 'Linux'
             , 'lang'    => 'english'
             , 'short_tags' => true
             );

// strictly numerical keys
$array = array( 7
               , 8
               , 0
               , 156
               , -10
               );

// this is the same as array( 0 => 7, 1 => 8, ...)

$switching = array(          10 // key = 0
                   , 5      => 6
                   , 3      => 7
                   , 'a'    => 4
                   ,         11 // key = 6 (maximum of integer-indices was 5)
                   , '8'    => 2 // key = 8 (integer!)
```

```

        , '02' => 77 // key = '02'
        , 0    => 12 // the value 10 will be overwritten by 12
    );

    // empty array
    $empty = array();

```

Příklad 6-5. Collection

```

$colors = array('red','blue','green','yellow');

foreach ( $colors as $color ) {
    echo "Do you like $color?\n";
}

/* output:
Do you like red?
Do you like blue?
Do you like green?
Do you like yellow?
*/

```

Note that it is currently not possible to change the values of the array directly in such a loop. A workaround is the following:

Příklad 6-6. Collection

```

foreach ($colors as $key => $color) {
    // won't work:
    //$color = strtoupper($color);

    //works:
    $colors[$key] = strtoupper($color);
}
print_r($colors);

/* output:
Array
(
    [0] => RED
    [1] => BLUE
    [2] => GREEN
    [3] => YELLOW
)
*/

```

This example creates a one-based array.

Příklad 6-7. One-based index

```
$firstquarter = array(1 => 'January', 'February', 'March');
print_r($firstquarter);

/* output:
Array
(
    [1] => 'January'
    [2] => 'February'
    [3] => 'March'
)
*/
```

Příklad 6-8. Filling real array

```
// fill an array with all items from a directory
$handle = opendir('.');
while ($file = readdir($handle))
{
    $files[] = $file;
}
closedir($handle);
```

Arrays are ordered. You can also change the order using various sorting-functions. See array-functions for more information.

Příklad 6-9. Sorting array

```
sort($files);
print_r($files);
```

Because the value of an array can be everything, it can also be another array. This way you can make recursive and multi-dimensional arrays.

Příklad 6-10. Recursive and multi-dimensional arrays

```
$fruits = array ( "fruits" => array ( "a" => "orange"
                                     , "b" => "banana"
                                     , "c" => "apple"
                                     )
                , "numbers" => array ( 1
```

```

        , 2
        , 3
        , 4
        , 5
        , 6
    )
    , "holes" => array (
        "first"
        , 5 => "second"
        , "third"
    )
);

```

Objects

Object Initialization

To initialize an object, you use the `new` statement to instantiate the object to a variable.

```

<?php
class foo
{
    function do_foo()
    {
        echo "Doing foo.";
    }
}

$bar = new foo;
$bar->do_foo();
?>

```

For a full discussion, please read the section [Classes and Objects](#).

Resource

A resource is a special variable, holding a reference to an external resource. Resources are created and used by special functions. See the appendix for a listing of all these functions and the corresponding resource types.

Poznámka: The resource type was introduced in PHP 4

Freeing resources

Due to the reference-counting system introduced with PHP4's Zend-engine, it is automatically detected when a resource is no longer referred to (just like Java). When this is the case, all resources that were in use for this resource are made free by the garbage collector. For this reason, it is rarely ever necessary to free the memory manually by using some `free_result` function.

Poznámka: Persistent database-links are special, they are *not* destroyed by the gc. See also persistent links

NULL

The special `NULL` value represents that a variable has no value. `NULL` is the only possible value of type `NULL`.

Poznámka: The null type was introduced in PHP 4

Syntax

There is only one value of type `NULL`, and that is the case-insensitive keyword `NULL`.

```
$var = NULL;
```

Type Juggling

PHP does not require (or support) explicit type definition in variable declaration; a variable's type is determined by the context in which that variable is used. That is to say, if you assign a string value to variable `var`, `var` becomes a string. If you then assign an integer value to `var`, it becomes an integer.

An example of PHP's automatic type conversion is the addition operator `'+'`. If any of the operands is a float, then all operands are evaluated as floats, and the result will be a float. Otherwise, the operands will be interpreted as integers, and the result will also be an integer. Note that this does NOT change the types of the operands themselves; the only change is in how the operands are evaluated.

```
$foo = "0"; // $foo is string (ASCII 48)

$foo += 2; // $foo is now an integer (2)
$foo = $foo + 1.3; // $foo is now a float (3.3)
$foo = 5 + "10 Little Piggies"; // $foo is integer (15)
$foo = 5 + "10 Small Pigs"; // $foo is integer (15)
```

If the last two examples above seem odd, see String conversion.

If you wish to force a variable to be evaluated as a certain type, see the section on Type casting. If you wish to change the type of a variable, see `settype()`.

If you would like to test any of the examples in this section, you can use the `var_dump()` function.

Poznámka: The behaviour of an automatic conversion to array is currently undefined.

```
$a = 1;          // $a is an integer
$a[0] = "f";     // $a becomes an array, with $a[0] holding "f"
```

While the above example may seem like it should clearly result in `$a` becoming an array, the first element of which is 'f', consider this:

```
$a = "1";        // $a is a string
$a[0] = "f";     // What about string offsets? What happens?
```

Since PHP supports indexing into strings via offsets using the same syntax as array indexing, the example above leads to a problem: should `$a` become an array with its first element being "f", or should "f" become the first character of the string `$a`?

For this reason, as of PHP 3.0.12 and PHP 4.0b3-RC4, the result of this automatic conversion is considered to be undefined. Fixes are, however, being discussed.

Type Casting

Type casting in PHP works much as it does in C: the name of the desired type is written in parentheses before the variable which is to be cast.

```
$foo = 10;       // $foo is an integer
$bar = (float) $foo; // $bar is a float
```

The casts allowed are:

- `(int)`, `(integer)` - cast to integer
- `(bool)`, `(boolean)` - cast to boolean
- `(float)`, `(double)`, `(real)` - cast to float
- `(string)` - cast to string
- `(array)` - cast to array

- (object) - cast to object

Poznámka: Instead of casting a variable to string, you can also enclose the variable in double quotes.

Note that tabs and spaces are allowed inside the parentheses, so the following are functionally equivalent:

```
$foo = (int) $bar;
$foo = ( int ) $bar;
```

It may not be obvious exactly what will happen when casting between certain types. For more info, see these sections:

- Converting to boolean
- Converting to integer

When casting or forcing a conversion from array to string, the result will be the word `Array`. When casting or forcing a conversion from object to string, the result will be the word `Object`.

When casting from a scalar or a string variable to an array, the variable will become the first element of the array:

```
$var = 'ciao';
$arr = (array) $var;
echo $arr[0]; // outputs 'ciao'
```

When casting from a scalar or a string variable to an object, the variable will become an attribute of the object; the attribute name will be `'scalar'`:

```
$var = 'ciao';
$obj = (object) $var;
echo $obj->scalar; // outputs 'ciao'
```


Kapitola 7. Proměnné

Základy

Proměnné jsou v PHP reprezentovány znakem dolaru, následovaným názvem příslušné proměnné. V názvech proměnných se rozlišuje velikost písmen.

Názvy proměnných jsou podřízeny stejným pravidlům jako jiná návěští v PHP. Platný název proměnné začíná písmenem nebo podtržítkem, následovaným libovolným počtem písmen, číslic nebo potržítek. Jako regulární výraz to lze zapsat takto: `'[a-zA-Z_\x7f-\xff][a-zA-Z0-9_\x7f-\xff]*'`

Poznámka: Pro naše účely zde budeme za písmena považovat znaky a-z, A-Z a ASCII znaky od 127 do 255 (0x7f-0xff).

```
$var = "Bob";
$Var = "Joe";
echo "$var, $Var";           // vypíše "Bob, Joe"

$4site = 'not yet';         // neplatné; začíná číslicí
$_4site = 'not yet';        // platné; začíná podtržítkem
$täyte = 'mansikka';        // platné; 'ä' je ASCII 228.
```

V PHP 3 mají proměnné vždy přiřazenu hodnotu. To znamená, že když přiřadíte výraz do proměnné, celá hodnota původního výrazu se zkopíruje do cílové proměnné. Tedy, například, po přiřazení hodnoty jedné proměnné do druhé, změna jedné z nich se na druhé neprojeví. Více informací o tomto způsobu přiřazení viz Výrazy.

PHP nabízí jiný způsob přiřazení hodnot proměnným: *přiřazení odkazu*. To znamená, že nová proměnná jednoduše odkazuje (jinými slovy, "stává se aliasem" nebo "ukazuje na") na původní proměnnou. Změny na nové proměnné se projeví na té původní a naopak. To také znamená, že se nic nekopíruje; proto je přiřazení rychlejší. Avšak toto zrychlení bude zjistitelné pouze v těsných cyklech nebo při přiřazování velkých polí či objektů.

Pro přiřazení odkazu stačí jednoduše před proměnnou, která bude přiřazována (zdrojová proměnná), předřadit ampersand (&). Například následující kus kódu vypíše dvakrát 'Jmenuji se Bob':

```
<?php
$foo = 'Bob';                // Přiřadí hodnotu 'Bob' do $foo
$bar = &$foo;                // Odkaz $foo přes $bar.
$bar = "Jmenuji se $bar";    // Změna $bar...
echo $bar;
echo $foo;                   // $foo je také změněno.
?>
```

Jednou z důležitých věcí, které je třeba si uvědomit, je to, že přes odkazy lze přiřazovat pouze pojmenované proměnné.

```

<?php
$foo = 25;
$bar = &$foo;      // Toto je platné přiřazení.
$bar = &(24 * 7);  // Neplatné; odkazuje se nepojmenovaný výraz.

function test()
{
    return 25;
}

$bar = &test();    // Neplatné.
?>

```

Předdefinované proměnné

PHP poskytuje velké množství předdefinovaných proměnných jakémukoli skriptu, který provádí. Mnoho těchto proměnných, bohužel, nemůže být plně zdokumentováno, protože závisejí na tom, na kterém serveru skript běží, na verzi a nastavení serveru a dalších faktorech. Některé z těchto proměnných nebudou dostupné, když PHP poběží z příkazové řádky. Seznam proměnných - viz sekce Předdefinované proměnné.

Varování

V PHP 4.2.0 a pozdějších se změnila implicitní sada předdefinovaných proměnných, které jsou globálně dostupné. Individuální vstupní a serverové proměnné se *implicitně* neumisťují do globálního kontextu; namísto toho jsou v následujících superglobálních polích.

Můžete však stále vynutit staré chování nastavením `register_globals` v souboru `php.ini` na 'On'.

Pro více informací a pozadí těchto změn prosím nahlédněte do PHP 4.1.0 Release Announcement (http://www.php.net/release_4_1_0.php).

Od verze 4.1.0 poskytuje PHP sadu předdefinovaných polí, obsahujících proměnné WWW serveru (pokud to jde), prostředí a uživatelského vstupu. Tato nová pole mají tu zvláštnost, že jsou automaticky globální -- tedy např. automaticky dostupné v každém kontextu. Z tohoto důvodu jsou často známa jako "autoglobální" nebo "superglobální". (V PHP neexistuje mechanismus pro uživatelskou definici superglobálních proměnných). Superglobální proměnné jsou vypsány níže; pro seznam jejich obsahů a další diskusi o předdefinovaných proměnných v PHP a jejich charakteru však musíte nahlédnout do části Předdefinované proměnné.

PHP superglobals (superglobální proměnné)

\$GLOBALS

Obsahuje odkaz na každou proměnnou, která je momentálně dostupná v globálním kontextu skriptu. Klíči tohoto pole jsou názvy globálních proměnných.

\$_SERVER

Proměnné nastavované WWW serveru nebo jinak přímo spjaté s prováděcím prostředím aktuálního skriptu. Analogické starému poli `$HTTP_SERVER_VARS` (které je stále dostupné, ale zavržené).

\$_GET

Proměnné poskytované skriptu přes HTTP GET. Analogické starému poli `$HTTP_GET_VARS` (které je stále dostupné, ale zavržené).

\$_POST

Proměnné poskytované skriptu přes HTTP POST. Analogické starému poli `$HTTP_POST_VARS` (které je stále dostupné, ale zavržené).

\$_COOKIE

Proměnné poskytované skriptu přes HTTP cookies. Analogické starému poli `$HTTP_COOKIE_VARS` (které je stále dostupné, ale zavržené).

\$_FILES

Proměnné poskytované skriptu přes HTTP post uploady souborů. Analogické uploads. Analogické starému poli `$HTTP_POST_FILES` (které je stále dostupné, ale zavržené). Více informací - viz Upload metodou POST.

\$_ENV

Proměnné poskytované skriptu z prostředí. Analogické starému poli `$HTTP_ENV_VARS` (které je stále dostupné, ale zavržené).

\$_REQUEST

Proměnné poskytované skriptu přes libovolný vstupní mechanismus a kterým proto nelze důvěřovat. Pozn.: při běhu z příkazové řádky zde *nebudou* přítomny položky `argv` a `argc`; nacházejí se v poli `$_SERVER`. Přítomnost a pořadí proměnných v tomto poli se definuje podle konfigurační direktivy `variables_order`. Toto pole nemá přímou analogii ve verzích PHP před 4.1.0.

\$_SESSION

Proměnné, které jsou momentálně registrovány v aktuální relaci skriptu. Analogické starému poli `$HTTP_SESSION_VARS` (které je stále dostupné, ale zavržené). Více informací - viz Funkce pro obsluhu sessions.

Kontext ("scope") proměnné

Kontext proměnné je oblast, ve které je definována. Většina proměnných v PHP má pouze jediný kontext. Ten zahrnuje i soubory vložené pomocí "include" nebo "require". Například:

```
$a = 1;
include "b.inc";
```

Zde bude proměnná `$a` dostupná ve vloženém skriptu `b.inc`. Avšak uvnitř uživatelsky definovaných funkcí se zakládá jejich lokální kontext. Jakákoli proměnná použitá uvnitř funkce je implicitně omezena na tento místní kontext. Například:

```
$a = 1; /* globální kontext */

function Test()
{
    echo $a; /* odkaz na proměnnou v lokálním kontextu */
}

Test();
```

Tento skript nevyprodukuje žádný výstup, protože konstrukt "echo" odkazuje na lokální verzi proměnné `$a`, a ta nemá v tomto kontextu přiřazenu žádnou hodnotu. Můžete si všimnout, že to je trochu jiné než v jazyce C, kde jsou globální funkce automaticky dostupné ve funkcích, pokud nejsou specificky zastíněny lokální definicí. To může způsobit problémy tím, že člověk může nechtěně změnit globální proměnnou. V PHP musí být globální proměnné deklarovány uvnitř funkce jako globální, pokud se v ní mají používat. Příklad:

```
$a = 1;
$b = 2;

function Sum()
{
    global $a, $b;

    $b = $a + $b;
}

Sum();
echo $b;
```

Výše uvedený skript vytiskne "3". Deklarací `$a` a `$b` ve funkci jako globálních proměnných se dosáhne toho, že při odkazování na proměnné se pracuje s jejich globální verzí. Počet globálních proměnných, se kterými lze ve funkci manipulovat, není omezen.

Druhým způsobem, jak přistupovat k proměnným z globálního kontextu, je použití speciálního pole `$GLOBALS`, definovaného v PHP. Předchozí příklad lze přepsat:

```
$a = 1;
$b = 2;

function Sum()
{
    $GLOBALS["b"] = $GLOBALS["a"] + $GLOBALS["b"];
}

Sum();
```

```
echo $b;
```

Pole `$GLOBALS` je asociativní pole s názvem globální proměnné jako klíčem a obsahem příslušné proměnné jako obsahem elementu pole.

Jinou důležitou vlastností rozlišování kontextů proměnných je možnost používání *static* proměnných. Statická proměnná existuje pouze v lokálním kontextu funkce, ale neztrácí svoji hodnotu, pokud provádění programu tento kontext opustí. Uvažujme následující příklad:

```
function Test ()
{
    $a = 0;
    echo $a;
    $a++;
}
```

Tato funkce je poněkud neužitečná, neboť při každém volání nastavuje `$a` na 0 a tiskne "0". Konstrukt `$a++`, který inkrementuje proměnnou, nemá žádný význam, protože při skončení vykonávání funkce se obsah proměnné `$a` ztrácí. Aby měla funkce skutečný význam čítače a hodnota se neztrácela, deklaruje se proměnná `$a` jako statická:

```
function Test()
{
    static $a = 0;
    echo $a;
    $a++;
}
```

Nyní se při každém volání funkce `Test()` vytiskne hodnota proměnné `$a` a inkrementuje se.

Static variables also provide one way to deal with recursive functions. A recursive function is one which calls itself. Care must be taken when writing a recursive function because it is possible to make it recurse indefinitely. You must make sure you have an adequate way of terminating the recursion. The following simple function recursively counts to 10, using the static variable `$count` to know when to stop:

```
function Test()
{
    static $count = 0;

    $count++;
    echo $count;
    if ($count < 10) {
        Test ();
    }
    $count--;
}
```

Variable variables

Sometimes it is convenient to be able to have variable variable names. That is, a variable name which can be set and used dynamically. A normal variable is set with a statement such as:

```
$a = "hello";
```

A variable variable takes the value of a variable and treats that as the name of a variable. In the above example, *hello*, can be used as the name of a variable by using two dollar signs. i.e.

```
$$a = "world";
```

At this point two variables have been defined and stored in the PHP symbol tree: `$a` with contents "hello" and `$hello` with contents "world". Therefore, this statement:

```
echo "$a ${$a}";
```

produces the exact same output as:

```
echo "$a $hello";
```

i.e. they both produce: `hello world`.

In order to use variable variables with arrays, you have to resolve an ambiguity problem. That is, if you write `$$a[1]` then the parser needs to know if you meant to use `$a[1]` as a variable, or if you wanted `$$a` as the variable and then the `[1]` index from that variable. The syntax for resolving this ambiguity is: `${$a[1]}` for the first case and `${$a}[1]` for the second.

Variables from outside PHP

HTML Forms (GET and POST)

When a form is submitted to a PHP script, any variables from that form will be automatically made available to the script by PHP. If the `track_vars` configuration option is turned on, then these

variables will be located in the associative arrays `$HTTP_POST_VARS`, `$HTTP_GET_VARS`, and/or `$HTTP_POST_FILES`, according to the source of the variable in question.

For more information on these variables, please read *Predefined variables*.

Příklad 7-1. Simple form variable

```
<form action="foo.php" method="post">
    Name: <input type="text" name="username"><br>
    <input type="submit">
</form>
```

When the above form is submitted, the value from the text input will be available in `$HTTP_POST_VARS['username']`. If the `register_globals` configuration directive is turned on, then the variable will also be available as `$username` in the global scope.

Poznámka: The `magic_quotes_gpc` configuration directive affects Get, Post and Cookie values. If turned on, value (It's "PHP!") will automatically become (It's \"PHP!\"). Escaping is needed for DB insertion. Also see `addslashes()`, `stripslashes()` and `magic_quotes_sybase`.

PHP also understands arrays in the context of form variables (see the related *faq*). You may, for example, group related variables together, or use this feature to retrieve values from a multiple select input:

Příklad 7-2. More complex form variables

```
<form action="array.php" method="post">
    Name: <input type="text" name="personal[name]"><br>
    Email: <input type="text" name="personal[email]"><br>
    Beer: <br>
    <select multiple name="beer[]">
        <option value="warthog">Warthog
        <option value="guinness">Guinness
        <option value="stuttgarter">Stuttgarter Schwabenbräu
    </select>
    <input type="submit">
</form>
```

In PHP 3, the array form variable usage is limited to single-dimensional arrays. In PHP 4, no such restriction applies.

IMAGE SUBMIT variable names

When submitting a form, it is possible to use an image instead of the standard submit button with a tag like:

```
<input type="image" src="image.gif" name="sub">
```

When the user clicks somewhere on the image, the accompanying form will be transmitted to the server with two additional variables, `sub_x` and `sub_y`. These contain the coordinates of the user click within the image. The experienced may note that the actual variable names sent by the browser contains a period rather than an underscore, but PHP converts the period to an underscore automatically.

HTTP Cookies

PHP transparently supports HTTP cookies as defined by Netscape's Spec (http://www.netscape.com/newsref/std/cookie_spec.html). Cookies are a mechanism for storing data in the remote browser and thus tracking or identifying return users. You can set cookies using the `setcookie()` function. Cookies are part of the HTTP header, so the `SetCookie` function must be called before any output is sent to the browser. This is the same restriction as for the `header()` function. Any cookies sent to you from the client will automatically be turned into a PHP variable just like GET and POST method data.

If you wish to assign multiple values to a single cookie, just add `[]` to the cookie name. For example:

```
setcookie("MyCookie[]", "Testing", time()+3600);
```

Note that a cookie will replace a previous cookie by the same name in your browser unless the path or domain is different. So, for a shopping cart application you may want to keep a counter and pass this along. i.e.

Příklad 7-3. SetCookie Example

```
$Count++;
setcookie("Count", $Count, time()+3600);
setcookie("Cart[$Count]", $item, time()+3600);
```

Environment variables

PHP automatically makes environment variables available as normal PHP variables.

```
echo $HOME; /* Shows the HOME environment variable, if set. */
```

Since information coming in via GET, POST and Cookie mechanisms also automatically create PHP variables, it is sometimes best to explicitly read a variable from the environment in order to make sure that you are getting the right version. The `getenv()` function can be used for this. You can also set an environment variable with the `putenv()` function.

Dots in incoming variable names

Typically, PHP does not alter the names of variables when they are passed into a script. However, it should be noted that the dot (period, full stop) is not a valid character in a PHP variable name. For the reason, look at it:

```
$varname.ext; /* invalid variable name */
```

Now, what the parser sees is a variable named `$varname`, followed by the string concatenation operator, followed by the barestring (i.e. unquoted string which doesn't match any known key or reserved words) `'ext'`. Obviously, this doesn't have the intended result.

For this reason, it is important to note that PHP will automatically replace any dots in incoming variable names with underscores.

Determining variable types

Because PHP determines the types of variables and converts them (generally) as needed, it is not always obvious what type a given variable is at any one time. PHP includes several functions which find out what type a variable is. They are `gettype()`, `is_array()`, `is_float()`, `is_int()`, `is_object()`, and `is_string()`.

Kapitola 8. Konstanty

PHP definuje několik konstant a poskytuje mechanismus pro definici dalších za běhu. Konstanty se hodně podobají proměnným s výjimkou dvou skutečností: konstanty se musí definovat pomocí funkce `define()`, a nemohou později nabývat jiných hodnot.

Předdefinované konstanty (dostupné vždy) jsou:

`__FILE__`

Název souboru skriptu, který je právě čten. Pokud je použita v souboru, který byl vložen pomocí `"include"` nebo `"require"`, obsahuje název vloženého souboru, nikoli rodičovského.

`__LINE__`

Číslo řádku ve skriptu, který je právě čten. Pokud je použita v souboru vloženého pomocí `"include"` nebo `"require"`, obsahuje pozici v rámci tohoto souboru.

`PHP_VERSION`

Textové vyjádření verze běžícího PHP parseru, např. `'3.0.8-dev'`.

`PHP_OS`

Název operačního systému, na kterém PHP parser běží, např. `'Linux'`.

`TRUE`

Pravdivá hodnota (logická jednička).

`FALSE`

Nepravdivá hodnota (logická nula).

`E_ERROR`

Označuje neošetřitelnou chybu jinou než `"parse error"`.

`E_WARNING`

Označuje stav, kdy PHP ví, že je něco špatně, ale bude dál pokračovat. Tyto stavy se dají ošetřit v samotném skriptu. Příkladem by byl neplatný `"regex"` (regulární výraz) ve funkci `ereg()`.

`E_PARSE`

Chyba při syntaktické analýze skriptu (chybná syntaxe). Ošetření není možné.

`E_NOTICE`

Došlo k něčemu, co by mohlo být chybou. Provádění skriptu pokračuje. Mezi příklady patří textový index pole neopatřený uvozovkami nebo práce s proměnnou, která ještě nebyla definována.

`E_ALL`

Všechny `E_*` konstanty shrnuté do jedné. Při použití s funkcí `error_reporting()` způsobí hlášení úplně všech problémů zaregistrovaných PHP.

`E_*` konstanty se typicky používají s funkcí `error_reporting()` nastavení hladiny hlášení chyb. Viz všechny tyto konstanty v Ošetření chyb.

Další konstanty můžete definovat pomocí funkce `define()`.

Všimněte si, že toto jsou konstanty, ne céčkovská makra; konstanty mohou reprezentovat pouze platná skalární data.

Příklad 8-1. Definice konstant

```
<?php
define("CONSTANT", "Hello world.");
echo CONSTANT; // vytiskne "Hello world."
?>
```

Příklad 8-2. Použití `__FILE__` a `__LINE__`

```
<?php
function report_error($file, $line, $message) {
    echo "Došlo k chybě v souboru $file na řádku $line: $message.";
}

report_error(__FILE__, __LINE__, "Něco je špatně!");
?>
```

Kapitola 9. Výrazy

Výrazy jsou nejdůležitějšími stavebními kameny PHP. V PHP je téměř vše, co napíšete, výraz. Nejjednodušší, a přece nejpřesnější definicí výrazu je "všechno, co má hodnotu".

Nezákladnějšími formami výrazů jsou konstanty a proměnné. Když napíšete "\$a = 5", přiřazujete '5' do \$a. '5' má, pochopitelně, hodnotu 5, nebo jinými slovy, '5' je výraz s hodnotou 5 (v tomto případě je '5' celočíselnou konstantou).

Po tomto přiřazení budete očekávat, že hodnota \$a bude 5, takže kdybyste napsali \$b = \$a, očekávali byste totéž, jako při napsání \$b = 5. Jinými slovy, \$a je tedy výraz s hodnotou 5. Pokud vše pracuje správně, přesně to se také stane.

O něco složitějším příkladem výrazů jsou funkce. Uvažujme např. tuto funkci:

```
function foo ()
{
    return 5;
}
```

Za předpokladu, že jste dobře seznámeni s konceptem funkcí (pokud ne, nahlédněte do kapitoly o funkcích), byste předpokládali, že napsání \$c = foo() je v zásadě totéž jako \$c = 5, a máte pravdu. Funkce jsou výrazy s hodnotou jejich návratové hodnoty. Funkce foo() vrací 5, tudíž hodnota výrazu 'foo()' je 5. Obvykle funkce nevracejí konstantní hodnotu, nýbrž něco vypočítávají.

Hodnoty v PHP samozřejmě nemusejí být pouze celá čísla, a velmi často také nejsou. PHP podporuje tři typy skalárních hodnot: celočíselné, reálné (pohyblivá řádová čárka) a řetězce (skalární hodnoty jsou hodnoty, které nejde "rozbít" na menší části, narozdíl např. od polí). PHP podporuje také dva kompozitní (neskalární) typy: pole a objekty. Každý z těchto typů hodnot může být přiřazen do proměnné nebo vrácen z funkce.

Uživatelé PHP/FI 2 by neměli pocítit změnu. Ale PHP jde ve výrazech mnohem dále, stejně jako mnoho jiných programovacích jazyků. PHP je výrazově orientovaný jazyk, ve smyslu, že téměř vše je výraz. Uvažujme příklad, kterým jsme se již zabývali, '\$a = 5'. Ihned vidíme, že jsou zde zahrnuty dvě hodnoty, celočíselná konstanta '5' a hodnota \$a, která je aktualizována na 5. Ale je pravda, že je tu ještě jedna hodnota, je to hodnota samotného přiřazení. Přiřazení jako takové ohodnocuje přiřazovanou hodnotu, v tomto případě 5. V praxi to znamená, že '\$a = 5', bez ohledu na to co dělá, je výraz s hodnotou 5. Proto je '\$b = (\$a = 5)' totéž jako '\$a = 5; \$b = 5;' (středník označuje konec výrazu). Protože přiřazení jsou parsována zprava doleva, můžete také napsat '\$b = \$a = 5'.

Jiným dobrým příkladem orientace na výrazy je pre- a post-inkrementace a dekrementace. Uživatelé PHP/FI 2 a mnoha jiných jazyků znají notaci proměnná++ a proměnná--. To jsou inkrementační a dekrementační operátory. V PHP/FI 2 nemělo '\$a++' žádnou hodnotu (není to výraz), a proto nešlo přiřadit nebo jinak použít. PHP rozšiřuje schopnosti přeměnou těchto konstrukcí ve výrazy, jako v C. V PHP, stejně jako v C, existují dva typy inkrementace - pre-inkrementace a post-inkrementace. Oba ve své podstatě inkrementují proměnnou a efekt na tuto proměnnou je totožný. Rozdíl je v hodnotě inkrementačního výrazu. Pre-inkrementace, zapsaná jako '++\$var', ohodnocuje výraz inkrementovanou hodnotou (PHP inkrementuje proměnnou dříve, než přečte její hodnotu, proto "pre-inkrementace"). Post-inkrementace, zapsaná jako '\$var++', ohodnocuje výraz původní hodnotou proměnné \$var, před inkrementací (PHP inkrementuje proměnnou po přečtení její hodnoty, proto "post-inkrement").

Velmi častým typem výrazů jsou výrazy porovnávací. Tyto výrazy se ohodnocují 0 a 1 ve významu FALSE, resp. TRUE. PHP podporuje > (větší než), >= (větší nebo rovno), == (rovná se), != (nerovná

se), < (menší než) a <= (menší nebo rovno). Tyto výrazy se nejčastěji používají v podmínkách, jako je konstrukt `if`.

Posledním příkladem výrazů, kterým se budeme zabývat, je kombinací přiřazení a operátorů. Již víte, že když chcete inkrementovat `$a` o jedničku, jednoduše napíšete `'$a++'` nebo `'++$a'`. Ale co když chcete hodnotu zvýšit o jiné číslo, např. o 3? Mohli byste napsat `'$a++'` víckrát za sebou, ale to samozřejmě není efektivní ani pohodlné. Mnohem praktičtější je napsat `'$a = $a + 3'`. Výraz `'$a + 3'` ohodnocuje hodnotu `$a` plus 3 a je přiřazen zpět do `$a`, což dává `$a` inkrementované o 3. V PHP, stejně jako v řadě jiných jazyků (jako je C), to můžete napsat kratším způsobem, který se časem stane jasnější i rychlejší k pochopení. Přičtení 3 k aktuální hodnotě `$a` lze zapsat jako `'$a += 3'`. Přesně to znamená "vezmi hodnotu `$a`, přičti k ní 3 a přiřaď zpět do `$a`". Kromě kratšího a přehlednějšího zápisu je výhodou také rychlejší provedení. Hodnota `'$a += 3'`, jako hodnota regulérního přiřazení, je přiřazovaná hodnota. Uvědomte si, že to NENÍ 3, nýbrž `$a` plus 3 (což je hodnota výrazu přiřazeného do `$a`). Takto lze použít jakýkoli binární operátor, například `'$a -= 5'` (odečti 5 od hodnoty `$a`), `'$b *= 7'` (vynásob hodnotu `$b` číslem 7) apod.

Je tu ještě jeden výraz, který se může zdát zvláštní, pokud jste ho ještě neviděli v jiných jazycích: ternární podmíněný operátor:

```
$prvni ? $druhy : $treti
```

Pokud hodnota prvního podvýrazu je `TRUE` (nenulová), je ohodnocen druhý podvýraz a je výsledkem celého podmíněného výrazu. Jinak je ohodnocen třetí podvýraz a je pak hodnotou celého výrazu.

Následující příklad by měl pomoci lépe pochopit pre- a post-inkrementaci i výrazy obecně:

```
function double($i)
{
    return $i*2;
}

$b = $a = 5;          /* přiřad' hodnotu pět do proměnných $a a $b */
$c = $a++;            /* proved' post-inkrement, přiřad' původní hodnotu $a
                        (5) do $c */
$e = $d = ++$b;        /* proved' pre-inkrement, přiřad' inkrementovanou hodnotu
                        $b (6) do $d a $e */

/* nyní jsou hodnoty proměnných $d a $e rovny 6 */

$f = double($d++);     /* přiřad' dvakrát hodnotu $d <emphasis>před</emphasis>
                        inkrementací, 2*6 = 12, do $f */
$g = double(++$e);     /* přiřad' dvakrát hodnotu $e <emphasis>po</emphasis>
                        inkrementací, 2*7 = 14 do $g */
$h = $g += 10;         /* nejdříve je $g inkrementováno o 10 má pak hodnotu 24.
                        Hodnota přiřazení (24) se přiřadí do $h a $h tím
                        získává také hodnotu 24. */
```

Na začátku kapitoly bylo řečeno, že si popíšeme různé typy konstruktů, a jak bylo slíbeno, výrazy mohou být konstrukty. V tomto případě mají konstrukty formát `'expr' ';' ,` což znamená "výraz

následovaný středníkem. V konstruktu '\$b=\$a=5;', je \$a=5 platný výraz, ale samo o sobě to není konstrukt. '\$b=\$a=5;' je i platný konstrukt.

Pozn. překladatele: Předchozím odstavci (občas i jinde) používám termín "konstrukt" pro anglické slovo "statement". Tento překlad není příliš korektní, ale v české programátorské mluvě neexistuje vhodný termín. Kdyby někdo věděl o lepším, napište mi, prosím, na luk@php.net.

Poslední věcí, která si zaslouží zmínku, je pravdivostní hodnota výrazů. V mnoha případech, hlavně podmínkách a cyklech, vás nezajímá konkrétní hodnota výrazu, nýbrž pouze to, jestli je TRUE nebo FALSE. Konstanty TRUE a FALSE (malá/velká písmena nehrají roli) představují dvě možné boolovské (pravdivostní) hodnoty. V případě potřeby je výraz automaticky převeden na typ boolean. Detailnější informace o způsobu konverze - viz sekce o typové konverzi.

PHP poskytuje plnou a silnou implementaci výrazů a úplně je zdokumentovat přesahuje rozsah tohoto manuálu. Výše uvedené příklady by vám měli naznačit, co jsou vůbec výrazy a jak konstruovat užitečné výrazy. Ve zbývajících částech manuálu budeme psát *expr* jakožto jakýkoli platný PHP výraz.

Kapitola 10. Operátory

Aritmetické operátory

Vzpomínáte si na základní aritmetiku ze školy? Tohle je úplně stejné.

Tabulka 10-1. Aritmetické operátory

Příklad	Název	Výsledek
$\$a + \b	Sčítání	Součet $\$a$ a $\$b$.
$\$a - \b	Odčítání	Rozdíl $\$a$ a $\$b$.
$\$a * \b	Násobení	Součin $\$a$ a $\$b$.
$\$a / \b	Dělení	Podíl $\$a$ a $\$b$.
$\$a \% \b	Zbytek	Zbytek po dělení $\$a$ a $\$b$.

Operátor dělení ("/") vrací celočíselnou hodnotu (výsledek celočíselného dělení) právě tehdy, když oba operandy jsou celá čísla (nebo řetězce, které se dají převést na celá čísla) a podíl je celé číslo. Pokud některý z operandů celočíselný není nebo výsledek není celé číslo, vrátí se hodnota v plovoucí řádové čárce (float).

Operátory přiřazení

Základním přiřazovacím operátorem je "=". Mohli byste si zprvu myslet, že se jedná o "rovná se". Nikoliv. Skutečně to znamená, že se levému operandu přiřadí hodnota výrazu vpravo (tj. "nastav na", "přiřad' do" atd.).

Hodnotou výrazu přiřazení je hodnota, která se přiřazuje. Tj. hodnotou " $\$a = 3$ " je číslo 3. To vám umožňuje provádět různé triky:

```
$a = ($b = 4) + 5; // $a se teď rovná 9, a $b bylo nastaveno na 4.
```

Kromě základního operátoru přiřazení existují ještě "kombinované operátory" pro všechny binární aritmetické a řetězové operátory, které umožňují použít hodnotu ve výrazu a pak hodnotu tohoto výrazu přiřadit zpět. Například:

```
$a = 3;
$a += 5; // nastaví $a na hodnotu 8, jako kdybychom řekli: $a = $a + 5;
$b = "Ahoj ";
$b .= "tam!"; // nastaví $b na "Ahoj tam!", přesně tak, jako $b = $b . "tam!";
```

Uvědomte si, že přiřazení zkopíruje hodnotu původní proměnné do nové proměnné (přiřazení hodnoty), takže změny jedné z nich se na druhé proměnné neprojeví. To může mít význam také tehdy, když potřebujete zkopírovat něco jako obrovské pole uvnitř krátkého cyklu. PHP 4 podporuje přiřazení odkazem použitím syntaxe `$var = &$othervar`; , ale v PHP 3 to provést nelze.

"Přiřazení odkazem" znamená, že obě proměnné ukazují na tatáž data a nic se nikam nekopíruje. Chcete-li se o odkazech dozvědět více, čtete prosím Vysvětlení referencí.

Bitové operátory

Bitové operátory umožňují "přehodit" konkrétní bit v celočíselné hodnotě (integer) na jedničku nebo nulu. Pokud jsou jak levý, tak pravý parametr řetězce, pracují bitové operátory na znacích v těchto řetězcích.

```
<?php
    echo 12 ^ 9; // Vypíše '5'

    echo "12" ^ "9"; // Vypíše znak Backspace (ascii 8)
                      // ('1' (ascii 49)) ^ ('9' (ascii 57)) = #8

    echo "hallo" ^ "hello"; // Vypíše ascii hodnoty #0 #4 #0 #0 #0
                          // 'a' ^ 'e' = #4

?>
```

Tabulka 10-2. Bitové operátory

Příklad	Název	Výsledek
$\$a \& \b	And (log. součin)	Nastavují se bity, kde je jednička v $\$a$ i v $\$b$.
$\$a \b	Or(log. součet)	Nastavují se bity, kde je jednička v $\$a$ nebo v $\$b$ (i v obou současně).
$\$a \wedge \b	Xor (exkluzivní log. součet)	Nastavují se bity, kde je jednička v $\$a$ nebo v $\$b$, ale ne v obou současně.
$\sim \$a$	Not (negace)	Tam, kde je nula, bude jednička, a naopak.
$\$a \ll \b	Posun vlevo	Posune bity v $\$a$ o $\$b$ kroků (míst) vlevo (každý krok znamená "násobení dvěma").
$\$a \gg \b	Posun vpravo	Posune bity v $\$a$ o $\$b$ kroků (míst) vpravo (každý krok znamená "dělení dvěma").

Operátory porovnání

Operátory porovnání, jak název napovídá, slouží k porovnání dvou hodnot.

Tabulka 10-3. Operátory porovnání

Příklad	Název	Výsledek
<code>\$a == \$b</code>	Rovnost	TRUE, právě když je \$a rovno \$b.
<code>\$a === \$b</code>	Identita	TRUE když je \$a rovno \$b a navíc téhož typu (pouze PHP 4).
<code>\$a != \$b</code>	Nerovnost	TRUE právě když \$a není rovno \$b.
<code>\$a <> \$b</code>	Nerovnost	TRUE právě když \$a není rovno \$b.
<code>\$a !== \$b</code>	Neidentita	TRUE když \$a není rovno \$b nebo nejsou téhož typu (pouze PHP 4).
<code>\$a < \$b</code>	Menší než	TRUE když je \$a ostře menší než \$b.
<code>\$a > \$b</code>	Větší než	TRUE když je \$a ostře větší než \$b.
<code>\$a <= \$b</code>	Menší nebo rovno	TRUE když je \$a menší nebo rovno \$b.
<code>\$a >= \$b</code>	Větší nebo rovno	TRUE když je \$a větší nebo rovno \$b.

Jiným podmínkovým operátorem je "?:" (ternární) operátor, který funguje stejně jako v C a mnohých jiných jazycích.

```
(expr1) ? (expr2) : (expr3);
```

Výraz je ohodnocen jako hodnota *expr2* když má *expr1* hodnotu TRUE, a *expr3* když má *expr1* hodnotu FALSE.

Operátory řízení chyb

PHP podporuje jeden operátor řízení chyb: znak at (@). Když ho předřadíte výrazu v PHP, jakékoli chybové zprávy, které se mohou generovat ve výrazu, budou ignorovány.

Pokud je zapnut `track_errors`, budou se všechny chybové zprávy generované výrazem ukládat do globální proměnné `$php_errormsg`. Tato proměnná bude přepsána při každé chybě, takže ji testujte vždy co nejdříve, pokud ji chcete používat.

```
<?php
/* Intentional file error */
$my_file = @file ('non_existent_file') or
    die ("Failed opening file: error was '$php_errormsg'");

// this works for any expression, not just functions:
```

```
$value = @$cache[$key];
// will not issue a notice if the index $key doesn't exist.

?>
```

Poznámka: Operátor @ pracuje pouze na výrazech. Platí jednoduché pravidlo: můžete-li získat hodnotu něčeho, můžete před to dát operátor @. To se týká například proměnných, funkcí, volání include() konstant a podobně. Nemůžete ho předřadit definicím funkcí nebo tříd a podmínkovým strukturám typu if nebo foreach.

Viz také error_reporting().

Varování

V současnosti předřazení operátoru řízení chyb "@" vyřadí i hlášení kritických chyb, které způsobí ukončení provádění skriptu. To mj. znamená, že pokud použijete "@" k potlačení chyb z nějaké funkce, a tato funkce není k dispozici nebo obsahuje chyby, skript zde skončí bez jakékoli indikace, co se stalo.

Prováděcí operátory

PHP podporuje jeden prováděcí operátor: obrácené apostrofy (""). Uvědomte si, že to nejsou obyčejné apostrofy! PHP se pokusí provést obsah uzavřený mezi těmito znaky jako příkaz shell; výstup je vrácen (tzn. nebude pouze vypsán na výstupů může být přiřazen proměnné).

```
$output = `ls -al`;
echo "<pre>$output</pre>";
```

Poznámka: Operátor může být vyřazen, pokud je aktivní bezpečný režim nebo je vypnuto `shell_exec()`.

Viz také `escapeshellcmd()`, `exec()`, `passthru()`, `popen()`, `shell_exec()`, a `system()`.

Inkrementační/Dekrementační operátory

PHP podporuje pre- a post inkrementační a dekrementační operátory ve stylu C.

Tabulka 10-4. Inkrementační/dekrementační operátory

Příklad	Název	Účinek
++\$a	Pre-inkrementace	Inkrementuje \$a o jedničku, potom vrátí \$a.
\$a++	Post-inkrementace	Vrátí \$a, potom inkrementuje \$a o jedničku.
--\$a	Pre-dekrementace	Dekrementuje \$a o jedničku, potom vrátí \$a.
\$a--	Post-dekrementace	Vrátí \$a, potom dekrementuje \$a o jedničku.

Zde je příklad jednoduchého skriptu:

```
<?php
echo "<h3>Postinkrementace</h3>";
$a = 5;
echo "Mělo by být 5: " . $a++ . "<br>\n";
echo "Mělo by být 6: " . $a . "<br>\n";

echo "<h3>Preinkrementace</h3>";
$a = 5;
echo "Mělo by být 6: " . ++$a . "<br>\n";
echo "Mělo by být 6: " . $a . "<br>\n";

echo "<h3>Postdekrementace</h3>";
$a = 5;
echo "Mělo by být 5: " . $a-- . "<br>\n";
echo "Mělo by být: " . $a . "<br>\n";

echo "<h3>Predekrementace</h3>";
$a = 5;
echo "Mělo by být 4: " . --$a . "<br>\n";
echo "Mělo by být 4: " . $a . "<br>\n";
?>
```

Logické operátory

Tabulka 10-5. Logické operátory

Příklad	Název	Výsledek
\$a and \$b	And	TRUE když \$a i \$b jsou TRUE.
\$a or \$b	Or	TRUE když \$a nebo \$b je TRUE.
\$a xor \$b	Xor	TRUE když \$a nebo \$b je TRUE, ale ne oba současně.

Příklad	Název	Výsledek
! \$a	Not	TRUE když \$a není TRUE.
\$a && \$b	And	TRUE když \$a i \$b jsou TRUE.
\$a \$b	Or	TRUE když \$a nebo \$b je TRUE.

Důvodem pro dvě různé varianty operátorů "and" a "or" je to, že mají jinou prioritu. (Viz Priorita operátorů.)

Priorita operátorů

Priorita operátoru specifikuje, jak "těsně" váže dva výrazy mezi sebou. Například výraz $1 + 5 * 3$, výsledkem je 16 a nikoli 18, protože operátor násobení ("*") má vyšší prioritu než operátor sčítání ("+"). K vynucení priority můžeme v případě potřeby použít závorky. Kupř. $(1 + 5) * 3$ má hodnotu 18.

Následující tabulka ukazuje přehled operátorů vzestupně seřazených podle priority.

Tabulka 10-6. Priorita operátorů

Asociativita	Operátory
levá	,
levá	or
levá	xor
levá	and
pravá	print
levá	= += -= *= /= .= %= &= = ^= ~= <=> >=>
levá	? :
levá	
levá	&&
levá	
levá	^
levá	&
bez asociativity	== != === !==
bez asociativity	< <= > >=
levá	<< >>
levá	+ - .
levá	* / %
pravá	! ~ ++ -- (int) (double) (string) (array) (object) @
pravá	[
bez asociativity	new

Řetězcové operátory

Existují dva řetězcové operátory. Jedním je operátor spojení ('.'), který vrací spojení pravého a levého argumentu. Druhým je operátor spojovacího přiřazení ('.='), jenž připojí argument na pravé straně k argumentu na straně levé. Pro více informací si laskavě přečtěte Operátory přiřazení.

```
$a = "Ahoj ";  
$b = $a . "světe!"; // nyní $b obsahuje "Ahoj světe!"  
  
$a = "Ahoj ";  
$a .= "světe!";      // nyní $a obsahuje "Ahoj světe!"
```

Kapitola 11. Řídící struktury

Jakýkoli PHP skript je složen ze série konstruktů. Konstrukt může být přiřazení, volání funkce, cyklus, podmínka, stejně jako konstrukt, který nic nedělá (prázdný konstrukt). Konstrukt obvykle končí středníkem. Navíc lze konstrukty seskupit do skupiny (bloku) uzavřené složenými závorkami. Tento blok je sám o sobě konstruktem. V této kapitole jsou popsány různé typy konstruktů.

if

Konstrukt `if` je jedním z nejdůležitějších prvků v mnoha jazycích, včetně PHP. Umožňuje podmíněné provádění kusu kódu. Struktura `if` v PHP je podobná struktuře v C:

```
if (expr)
    statement
```

Jak je popsáno v sekci o výrazech, výraz *expr* je ohodnocen svou boolovskou hodnotou. Pokud je *expr* ohodnocen jako `TRUE`, PHP provede *statement*; je-li ohodnocen jako `FALSE`, neprovede se nic. Více informací o to, jak se výrazy ohodnocují jako `FALSE` najdete v části 'Konverze na typ `boolean`'.

Následující příklad by vypsal *a* je větší než *b*, pokud *\$a* je větší než *\$b*:

```
if ($a > $b)
    print "a je větší než b";
```

Často byste chtěli, aby se podmíněně prováděl více než jeden konstrukt. Není samozřejmě nutné každý konstrukt zabalit do struktury `if`. Místo toho můžete seskupit více konstruktů do bloku. Například tento kód by zobrazil *a* je větší než *b*, pokud *\$a* je větší než *\$b* a přiřadil by hodnotu *\$a* do *\$b*:

```
if ($a > $b) {
    print "a je větší než b";
    $b = $a;
}
```

Konstrukty `if` mohou být libovolně vnořovány do jiných konstruktů `if`, což poskytuje plnou flexibilitu podmíněného provádění různých částí programu.

else

Často také můžete chtít něco provádět, pokud je jistá podmínka splněna, a něco jiného, když splněna není. To umožňuje konstrukt `else`. `else` rozšiřuje konstrukt `if` o provádění kódu v případě, že výraz v konstrukt `if` je ohodnocen jako `FALSE`. Například následující kód vypíše `a` je větší než `b`, pokud `$a` je větší než `$b`, a `a` NENÍ větší než `b` v ostatních případech:

```
if ($a > $b) {
    print "a je větší než b";
} else {
    print "a NENÍ větší než b";
}
```

Konstrukt v `else` se provádí, pouze pokud je výraz v `if` ohodnocen jako `FALSE`, a pokud by zde byly nějaké výrazy `elseif` - pouze pokud by byly také ohodnoceny jako `FALSE` (viz `elseif`).

elseif

Jak název napovídá, `elseif`, je kombinací `if` a `else`. Stejně jako `else`, rozšiřuje konstrukt `if` k provádění odlišných konstruktů v případě, že je výraz původního konstrukt `if` ohodnocen jako `FALSE`. Tedy, na rozdíl od `else`, se provádí pouze tehdy, je-li výraz v podmínce `elseif` ohodnocen jako `TRUE`. Například následující kód vypíše `a` je větší než `b`, a se rovná `b` nebo `a` je menší než `b`:

```
if ($a > $b) {
    print "a je větší než b";
} elseif ($a == $b) {
    print "a se rovná b";
} else {
    print "a je menší než b";
}
```

V rámci jednoho konstrukt `if` může být více konstruktů `elseif`. Provádí se první konstrukt `elseif` (pokud vůbec nějaký), jehož výraz je ohodnocen `TRUE`. V PHP můžete napsat i `'else if'` (dvěma slovy), chování bude naprosto totožné jako u `'elseif'` (jediným slovem). Syntaktický význam je mírně odlišný (znáte-li C, je to stejné), avšak ve výsledku dostaneme přesně totožné chování.

Konstrukt `elseif` se provádí, pouze jsou-li příslušný (bezprostředně předcházející) výraz konstrukt `if` a výrazy všech příslušných předcházejících konstruktů `elseif` ohodnoceny jako `FALSE`, a konkrétní výraz v `elseif` ohodnocen jako `TRUE`.

Alternativní syntaxe řídicích struktur

PHP nabízí alternativní syntaxi pro některé z řídicích struktur, jmenovitě `if`, `while`, `for`, `foreach`, a `switch`. V každém z těchto případů je základním formátem alternativní syntaxe záměna otvírací závorky za dvojtečku (`:`) a uzavírací závorky za `endif`, `endwhile`, `endfor`, `endforeach`, resp. `endswitch`.

```
<?php if ($a == 5): ?>
A se rovná 5
<?php endif; ?>
```

Ve výše uvedeném příkladu je HTML blok vnořen do konstruktu `if` napsaném alternativní syntaxí. Tento HTML blok by se zobrazil pouze v případě, že je `$a` rovno 5.

Alternativní syntaxi lze použít i pro `else` a `elseif`. Následující příklad ukazuje strukturu `if`, `elseif` a `else` v alternativním formátu:

```
if ($a == 5):
    print "a se rovná 5";
    print "...";
elseif ($a == 6):
    print "a se rovná 6";
    print "!!!";
else:
    print "a není ani 5, ani 6";
endif;
```

Další příklady - viz také `while`, `for`, a `if`.

while

Cykly `while` jsou nejjednodušším typem cyklů v PHP. Chovají se jako jejich protějšci v C. Základní formát konstruktu `while` je tento:

```
while (expr) statement
```

Význam konstruktu `while` je snadno pochopitelný. Říká PHP, že má provádět vnořený(é) konstrukt(y) tak dlouho, dokud je výraz ve `while` roven `TRUE`. Hodnota výrazu je testována pokaždé na začátku cyklu (v každé iteraci), takže i když se tato hodnota během provádění vnořených

konstruktů změní, provede se zbytek kódu uvnitř cyklu - v konkrétní iteraci - až do konce (každé provedení kódu uvnitř cyklu je jedna iterace). Někdy, když je výraz ve `while` ohodnocen jako `FALSE` již při vstupu do cyklu, vnořený kód se neprovede vůbec.

Podobně, jako v případě `if`, můžete i zde seskupovat konstrukty uvnitř cyklu `while` ohraničením tohoto kódu složenými závorkami nebo za použití alternativní syntaxe:

```
while (expr): statement ... endwhile;
```

Následující příklady jsou identické, oba vypíší čísla od 1 do 10:

```
/* příklad 1 */

$i = 1;
while ($i <= 10) {
    print $i++; /* vytištěná hodnota by byla rovna
                $i před inkrementací
                (post-inkrementace) */
}

/* příklad 2 */

$i = 1;
while ($i <= 10):
    print $i;
    $i++;
endwhile;
```

do..while

Cykly `do..while` jsou velmi podobné cyklům `while` kromě toho, že pravdivost výrazu se testuje na konci každé iterace namísto jejího začátku. Hlavní rozdíl oproti běžným cyklům `while` je ten, že první iterace cyklu `do..while` se provede vždy (pravdivostní výraz je testován až na konci iterace), což u cyklu `while` není zaručeno (pravdivostní výraz je testován na začátku iterace; pokud je ohodnocen jako `FALSE`, provádění cyklu hned skončí).

Toto je jediná syntaxe pro cykly `do..while`:

```
$i = 0;
do {
    print $i;
} while ($i>0);
```

Výše uvedený cyklus by se provedl právě jednou, protože po první iteraci, když se testuje pravdivostní výraz, je tento ohodnocen jako `FALSE` (\$i není větší než 0) a provádění cyklu končí.

Pokročilí programátoři v C mohou znát i odlišné použití cyklu `do...while`. Kód se uzavře do `do...while(0)` a použije se příkaz `break`. To umožňuje přerušit provádění cyklu uprostřed kódu, jak je znázorněno v tomto příkladu:

```
do {
    if ($i < 5) {
        print "i není dost velké";
        break;
    }
    $i *= $factor;
    if ($i < $minimum_limit) {
        break;
    }
    print "i je ok";

    ...zpracuj i...
} while(0);
```

Nedělejte si nic z toho, že tomu hned a beze zbytku nerozumíte. Můžete psát skripty, a to i velmi účinné skripty, i bez použití této 'finty'.

for

Cykly `for` jsou nejsložitějšími cykly v PHP. Chovají se stejně, jako jejich soukmenovci v C. Syntaxe cyklu `for` je následující:

```
for (expr1; expr2; expr3) statement
```

První výraz (*expr1*) je ohodnocen (proveden) jednou, bezpodmínečně, na začátku cyklu.

Na začátku každé iterace je ohodnocen výraz *expr2*. Pokud má hodnotu `TRUE`, cyklus pokračuje a zpracovává se kód uvnitř cyklu. Je-li naopak jeho hodnota `FALSE`, provádění cyklu končí.

Na konci každé iterace se ohodnotí (provede) výraz *expr3*.

Každý z výrazů může být prázdný. Prázdný výraz *expr2* znamená, že cyklus bude probíhat nekonečně dlouho (PHP, stejně jako C, implicitně předpokládá hodnotu `TRUE`). To nemusí být tak bez užitku, jak si můžete myslet. Často můžete totiž chtít ukončit cyklus pomocí podmíněného příkazu `break`, namísto použití pravdivostního výrazu v konstruktu cyklu `for`.

Předpokládejme následující příklady. Všechny zobrazí čísla od 1 do 10:

```

/* příklad 1 */

for ($i = 1; $i <= 10; $i++) {
    print $i;
}

/* příklad 2 */

for ($i = 1;;$i++) {
    if ($i > 10) {
        break;
    }
    print $i;
}

/* příklad 3 */

$i = 1;
for (;;) {
    if ($i > 10) {
        break;
    }
    print $i;
    $i++;
}

/* příklad 4 */

for ($i = 1; $i <= 10; print $i, $i++);

```

První příklad samozřejmě vypadá nejlépe (nebo možná i ten čtvrtý), ale můžete přijít na to, že schopnost používat prázdné výrazy v cyklech `for` nemusí být někdy úplně k zahoezení.

PHP podporuje pro cykly `for` také alternativní "dvojtečkovou syntaxi".

```
for (expr1; expr2; expr3): statement; ...; endfor;
```

Jiné jazyky mají konstrukt `foreach` k traverzování polí nebo hashů. V PHP 3 nic takového není, PHP 4 ano (viz `foreach`). V PHP 3 můžete k dosažení stejného efektu kombinovat `while` s funkcemi `list()` a `each()`. Příklady najdete v dokumentaci.

foreach

PHP 4 (ne PHP 3) zahrnuje konstrukt `foreach`, podobně jako Perl a různé další jazyky. To poskytuje snadný způsob k iteraci přes pole. Existují dvě syntaxe; ta druhá je menším, avšak užitečným rozšířením té první:

```
foreach(array_expression as $value) statement
foreach(array_expression as $key => $value) statement
```

První forma traverzuje pole dané výrazem `array_expression`. V každé iteraci je hodnota aktuálního elementu přiřazena do `$value` a vnitřní ukazatel na pole je zvýšen o jednotku (tzn. v příští iteraci budete hledět na následující element).

Druhá forma dělá totéž, kromě toho, že aktuální klíč elementu bude v každé iteraci přiřazen do proměnné `$key`.

Poznámka: Když `foreach` začne provádění první iterace, je vnitřní ukazatel automaticky nastaven na první element pole. To znamená, že před `foreach` nemusíte volat `reset()`.

Poznámka: Uvědomte si také, že `foreach` pracuje na kopii specifikovaného pole, nikoli na poli samotném, proto ukazatel na pole není modifikován tak, jako konstruktem `each()` a změny na vráceném elementu se na původním poli neprojeví.

Poznámka: `foreach` nepodporuje možnost potlačit chybová hlášení použitím '@'.

Můžete si všimnout, že následující příklady jsou funkčně totožné:

```
reset ($arr);
while (list(, $value) = each ($arr)) {
    echo "Hodnota: $value<br>\n";
}

foreach ($arr as $value) {
    echo "Hodnota: $value<br>\n";
}
```

Následující příklady jsou rovněž funkčně totožné:

```

reset ($arr);
while (list($key, $value) = each ($arr)) {
    echo "Klíč: $key; Hodnota: $value<br>\n";
}

foreach ($arr as $key => $value) {
    echo "Klíč: $key; Hodnota: $value<br>\n";
}

```

Další příklady demonstrující použití:

```

/* foreach příklad 1: pouze hodnota */

$a = array (1, 2, 3, 17);

foreach ($a as $v) {
    print "Současná hodnota \$a: $v.\n";
}

/* foreach příklad 2: hodnota (pro ilustraci je vypsán i klíč) */

$a = array (1, 2, 3, 17);

$i = 0; /* pouze pro ilustrativní účely */

foreach($a as $v) {
    print "\$a[$i] => $v.\n";
    $i++;
}

/* foreach příklad 3: klíč a hodnota */

$a = array (
    "jedna" => 1,
    "dvě" => 2,
    "tři" => 3,
    "sedmnáct" => 17
);

foreach($a as $k => $v) {
    print "\$a[$k] => $v.\n";
}

/* foreach příklad 4: vícerozměrná pole */

$a[0][0] = "a";
$a[0][1] = "b";
$a[1][0] = "y";
$a[1][1] = "z";

foreach($a as $v1) {

```

```

        foreach ($v1 as $v2) {
            print "$v2\n";
        }
    }

/* foreach příklad 5: dynamická pole */

foreach(array(1, 2, 3, 4, 5) as $v) {
    print "$v\n";
}

```

break

`break` ukončuje provádění aktuálního konstruktu `for`, `foreach` `while`, `do..while` nebo `switch`.

`break` akceptuje nepovinný číselný argument, který říká, z kolika vnořených struktur se má vyskočit.

```

$arr = array ('jedna', 'dvě', 'tři', 'čtyři', 'stop', 'pět');
while (list ($val) = each ($arr)) {
    if ($val == 'stop') {
        break; /* Tady byste mohli napsat také 'break 1;'. */
    }
    echo "$val<br>\n";
}

/* Použití nepovinného argumentu. */

$i = 0;
while (++$i) {
    switch ($i) {
        case 5:
            echo "Při 5<br>\n";
            break 1; /* Ukončuje pouze switch. */
        case 10:
            echo "Při 10; konec<br>\n";
            break 2; /* Ukončuje switch a while. */
        default:
            break;
    }
}

```

continue

`continue` se používá uvnitř cyklů k přeskočení zbytku aktuální iterace a bezprostřednímu přechodu na následující iteraci.

`continue` akceptuje nepovinný číselný argument, který říká, kolik úrovní cyklů se má naráz dokončit.

```
while (list ($key, $value) = each ($arr)) {
    if (!(($key % 2)) { // přeskoč sudé členy
        continue;
    }
    do_something_odd ($value);
}

$i = 0;
while ($i++ < 5) {
    echo "Vnější<br>\n";
    while (1) {
        echo "&nbsp;&nbsp;&nbsp;Střední<br>\n";
        while (1) {
            echo "&nbsp;&nbsp;&nbsp;Vnitřní<br>\n";
            continue 3;
        }
        echo "Toto se nikdy nevytiskne.<br>\n";
    }
    echo "Ani tohle se neprovádí.<br>\n";
}
```

switch

Konstruktor `switch` je podobná sérii konstruktů `IF`, testujících tentýž výraz. V mnoha případech můžete chtít porovnávat stejnou proměnnou (nebo výraz) s mnoha různými hodnotami a provádět různé kusy kódu v závislosti na tom, které hodnotě se rovná. To je přesně to, k čemu je `switch`.

Následující dva příklady představují dva odlišné způsoby, jak napsat totéž; jeden používá sérii podmínek `if`, zatímco druhý je založen na konstruktu `switch`:

```
if ($i == 0) {
    print "i se rovná 0";
}
if ($i == 1) {
    print "i se rovná 1";
}
if ($i == 2) {
    print "i se rovná 2";
}

switch ($i) {
```

```

case 0:
    print "i se rovná 0";
    break;
case 1:
    print "i se rovná 1";
    break;
case 2:
    print "i se rovná 2";
    break;
}

```

Je důležité pochopit, jak se konstrukt `switch` provádí, aby se zabránilo chybám. Konstrukt `switch` provádí řádek po řádku (resp. konstrukt po konstrukt). Na začátku není proveden žádný kód. Pouze tehdy, když se najde `case` s hodnotou odpovídající hodnotě výrazu u `switch`, začne PHP provádět následující konstrukty. Vykonávání kódu pokračuje, dokud se nedosáhne konce bloku `switch` nebo prvního příkazu `break`. Pokud nenapíšete na konec bloku po `case` příkaz `break`, bude PHP pokračovat v provádění dalších konstruktů (po dalším `case`). Například:

```

switch ($i) {
    case 0:
        print "i se rovná 0";
    case 1:
        print "i se rovná 1";
    case 2:
        print "i se rovná 2";
}

```

Zde, pokud se `$i` rovná 0, se budou provádět všechny příkazy `"print"`! Pokud se `$i` rovná 1, PHP provede poslední dva příkazy, a pouze rovná-li se `$i` číslu 2, obdržíte "očekávané" chování a zobrazí se pouze `"i se rovná 2"`. Takže je důležité nezapomenout na příkaz `break` (kromě případu, kdy ho chcete vynechat záměrně k dosažení určitého cíle).

V konstrukt `switch` se podmínka testuje pouze jednou a výsledek se porovnává s každou hodnotou v `case`. V případě `elseif` se podmínka pokaždé testuje znovu. Pokud je vaše podmínka komplikovanější než jednoduché porovnání a/nebo je uvnitř cyklu, `switch` může být rychlejší.

Seznam konstruktů za `case` může být také prázdný, což jednoduše předá řízení následujícímu `case`.

```

switch ($i) {
    case 0:
    case 1:
    case 2:
        print "i je menší než 3, ale nezáporné";
        break;
    case 3:
        print "i je 3";
}

```

```
}
```

Speciální case je "default". Vyhovuje všem ostatním hodnotám, které nejsou pokryty některým z ostatních case a má být vždy jako poslední. Například:

```
switch ($i) {
    case 0:
        print "i se rovná 0";
        break;
    case 1:
        print "i se rovná 1";
        break;
    case 2:
        print "i se rovná 2";
        break;
    default:
        print "i se nerovná 0, 1 ani 2";
}
```

Výraz v case může být libovolný výraz, jehož hodnota je jednoduchého typu, tj. celé nebo reálné číslo nebo řetězec. Pole ani objekty nelze použít, ledaže by odkazovaly na jednoduchý typ.

Alternativní syntaxe pro konstrukty switch je podporována. Pro víc informací viz Alternativní syntaxe řídících struktur .

```
switch ($i):
    case 0:
        print "i se rovná 0";
        break;
    case 1:
        print "i se rovná 1";
        break;
    case 2:
        print "i se rovná 2";
        break;
    default:
        print "i se nerovná 0, 1 ani 2";
endswitch;
```

declare

Konstruktor `declare` se používá k nastavení prováděcích direktiv pro blok kódu. Syntaxe `declare` je podobná syntaxi ostatních konstruktorů pro řízení toku:

```
declare (directive) statement
```

Část `directive` umožňuje nastavit chování bloku, který má být ovlivněn pomocí `declare`. V současnosti je rozpoznávána pouze jediná direktiva: `ticks`. (Pro více informací viz níže - direktiva `ticks`)

Část `statement` bloku `declare` bude provedena - jak bude provedena a jaké vedlejší efekty nastanou během provádění může záležet na direktivě nastavené v bloku `directive`.

Ticks

Tick je událost, která nastane pro každých N nízkourovňových konstruktorů provedených parserem uvnitř bloku `declare`. Hodnota N je specifikována pomocí `ticks=N` uvnitř sekce `directive` bloku `declare`.

Událost(i), která nastane při každém ticku, se specifikuje pomocí **`register_tick_function()`**. Více podrobností - viz příklad níže. Uvědomte si, že na každý tick může nastat více než jedna událost.

Příklad 11-1. Profile a section of PHP code

```
<pre>
<?php
// A function that records the time when it is called
function profile ($dump = FALSE)
{
    static $profile;

    // Return the times stored in profile, then erase it
    if ($dump) {
        $temp = $profile;
        unset ($profile);
        return ($temp);
    }

    $profile[] = microtime ();
}

// Set up a tick handler
register_tick_function("profile");

// Initialize the function before the declare block
profile ();

// Run a block of code, throw a tick every 2nd statement
declare (ticks=2) {
```

```

    for ($x = 1; $x < 50; ++$x) {
        echo similar_text (md5($x), md5($x*$x)), "<br>";
    }

// Display the data stored in the profiler
print_r (profile (TRUE));
?>
</pre>

```

The example profiles the PHP code within the 'declare' block, recording the time at which every second low-level statement in the block was executed. This information can then be used to find the slow areas within particular segments of code. This process can be performed using other methods: using ticks is more convenient and easier to implement.

Ticks are well suited for debugging, implementing simple multitasking, backgrounded I/O and many other tasks.

See also **register_tick_function()** and **unregister_tick_function()**.

return

If called from within a function, the **return()** statement immediately ends execution of the current function, and returns its argument as the value of the function call. **return()** will also end the execution of an **eval()** statement or script file.

If called from the global scope, then execution of the current script file is ended. If the current script file was **include()**ed or **require()**ed, then control is passed back to the calling file. Furthermore, if the current script file was **include()**ed, then the value given to **return()** will be returned as the value of the **include()** call. If **return()** is called from within the main script file, then script execution ends. If the current script file was named by the **auto_prepend_file** or **auto_append_file** configuration options in the configuration file, then that script file's execution is ended.

For more information, see Returning values.

Poznámka: Note that since **return()** is a language construct and not a function, the parentheses surrounding its arguments are *not* required--in fact, it is more common to leave them out than to use them, although it doesn't matter one way or the other.

require()

The **require()** statement includes and evaluates the specific file.

require() includes and evaluates a specific file. Detailed information on how this inclusion works is described in the documentation for **include()**.

require() and **include()** are identical in every way except how they handle failure. **include()** produces a Warning while **require()** results in a Fatal Error. In other words, don't hesitate to use **require()** if

you want a missing file to halt processing of the page. `include()` does not behave this way, the script will continue regardless. Be sure to have an appropriate `include_path` setting as well.

Příklad 11-2. Basic `require()` examples

```
<?php

require 'prepend.php';

require $somefile;

require ('somefile.txt');

?>
```

See the `include()` documentation for more examples.

Poznámka: Prior to PHP 4.0.2, the following applies: `require()` will always attempt to read the target file, even if the line it's on never executes. The conditional statement won't affect `require()`. However, if the line on which the `require()` occurs is not executed, neither will any of the code in the target file be executed. Similarly, looping structures do not affect the behaviour of `require()`. Although the code contained in the target file is still subject to the loop, the `require()` itself happens only once.

See also `include()`, `require_once()`, `include_once()`, `eval()`, `file()`, `readfile()`, `virtual()` and `include_path`.

`include()`

The `include()` statement includes and evaluates the specified file.

The documentation below also applies to `require()`. The two constructs are identical in every way except how they handle failure. `include()` produces a Warning while `require()` results in a Fatal Error. In other words, use `require()` if you want a missing file to halt processing of the page. `include()` does not behave this way, the script will continue regardless. Be sure to have an appropriate `include_path` setting as well.

When a file is included, the code it contains inherits the variable scope of the line on which the `include` occurs. Any variables available at that line in the calling file will be available within the called file, from that point forward.

Příklad 11-3. Basic `include()` example

```
vars.php
<?php
```

```

$color = 'green';
$fruit = 'apple';

?>

test.php
<?php

echo "A $color $fruit"; // A

include 'vars.php';

echo "A $color $fruit"; // A green apple

?>

```

If the include occurs inside a function within the calling file, then all of the code contained in the called file will behave as though it had been defined inside that function. So, it will follow the variable scope of that function.

Příklad 11-4. Including within functions

```

<?php

function foo()
{
    global $color;

        include 'vars.php';

        echo "A $color $fruit";
}

/* vars.php is in the scope of foo() so      *
 * $fruit is NOT available outside of this  *
 * scope. $color is because we declared it  *
 * as global.                               */

foo();                                     // A green apple
echo "A $color $fruit";                   // A green

?>

```

When a file is included, parsing drops out of PHP mode and into HTML mode at the beginning of the target file, and resumes again at the end. For this reason, any code inside the target file which should be executed as PHP code must be enclosed within valid PHP start and end tags.

If "URL fopen wrappers" are enabled in PHP (which they are in the default configuration), you can specify the file to be included using an URL (via HTTP) instead of a local pathname. If the target server interprets the target file as PHP code, variables may be passed to the included file using an URL request string as used with HTTP GET. This is not strictly speaking the same thing as including the file and having it inherit the parent file's variable scope; the script is actually being run on the remote server and the result is then being included into the local script.

Příklad 11-5. include() through HTTP

```
<?php

/* This example assumes that www.example.com is configured to parse .php *
 * files and not .txt files. Also, 'Works' here means that the variables *
 * $foo and $bar are available within the included file.                  */

// Won't work; file.txt wasn't handled by www.example.com as PHP
include 'http://www.example.com/file.txt?foo=1&bar=2';

// Won't work; looks for a file named 'file.php?foo=1&bar=2' on the
// local filesystem.
include 'file.php?foo=1&bar=2';

// Works.
include 'http://www.example.com/file.php?foo=1&bar=2';

$foo = 1;
$bar = 2;
include 'file.txt'; // Works.
include 'file.php'; // Works.

?>
```

See also Remote files, fopen() and file() for related information.

Because include() and require() are special language constructs, you must enclose them within a statement block if it's inside a conditional block.

Příklad 11-6. include() and conditional blocks

```
<?php

// This is WRONG and will not work as desired.
if ($condition)
    include $file;
else
    include $other;

// This is CORRECT.
if ($condition) {
    include $file;
} else {
```

```

        include $other;
    }

?>

```

Handling Returns: It is possible to execute a `return()` statement inside an included file in order to terminate processing in that file and return to the script which called it. Also, it's possible to return values from included files. You can take the value of the include call as you would a normal function.

Poznámka: In PHP 3, the return may not appear inside a block unless it's a function block, in which case the `return()` applies to that function and not the whole file.

Příklad 11-7. `include()` and the `return()` statement

```

return.php
<?php

$var = 'PHP';

return $var;

?>

noreturn.php
<?php

$var = 'PHP';

?>

testreturns.php
<?php

$foo = include 'return.php';

echo $foo; // prints 'PHP'

$bar = include 'noreturn.php';

echo $bar; // prints 1

?>

```

`$bar` is the value 1 because the include was successful. Notice the difference between the above examples. The first uses `return()` within the included file while the other does not. A few other ways

to "include" files into variables are with `fopen()`, `file()` or by using `include()` along with Output Control Functions.

See also `require()`, `require_once()`, `include_once()`, `readfile()`, `virtual()`, and `include_path`.

require_once()

The `require_once()` statement includes and evaluates the specified file during the execution of the script. This is a behavior similar to the `require()` statement, with the only difference being that if the code from a file has already been included, it will not be included again. See the documentation for `require()` for more information on how this statement works.

`require_once()` should be used in cases where the same file might be included and evaluated more than once during a particular execution of a script, and you want to be sure that it is included exactly once to avoid problems with function redefinitions, variable value reassignments, etc.

For examples on using `require_once()` and `include_once()`, look at the PEAR (<http://pear.php.net/>) code included in the latest PHP source code distributions.

Poznámka: `require_once()` was added in PHP 4.0.1pl2

See also: `require()`, `include()`, `include_once()`, `get_required_files()`, `get_included_files()`, `readfile()`, and `virtual()`.

include_once()

The `include_once()` statement includes and evaluates the specified file during the execution of the script. This is a behavior similar to the `include()` statement, with the only difference being that if the code from a file has already been included, it will not be included again. As the name suggests, it will be included just once.

`include_once()` should be used in cases where the same file might be included and evaluated more than once during a particular execution of a script, and you want to be sure that it is included exactly once to avoid problems with function redefinitions, variable value reassignments, etc.

For more examples on using `require_once()` and `include_once()`, look at the PEAR (<http://pear.php.net/>) code included in the latest PHP source code distributions.

Poznámka: `include_once()` was added in PHP 4.0.1pl2

See also `include()`, `require()`, `require_once()`, `get_required_files()`, `get_included_files()`, `readfile()`, and `virtual()`.

Kapitola 12. Funkce

Uživatelsky definované funkce

Funkce může být definována pomocí syntaxe podobné této:

```
function foo ($arg_1, $arg_2, ..., $arg_n)
{
    echo "Ukázková funkce.\n";
    return $retval;
}
```

Do funkce může být vložen jakýkoli platný PHP kód, dokonce i definice jiných funkcí a tříd.

V PHP 3 musí být funkce definovány dříve, než je na ně odkazováno. V PHP už tento požadavek neplatí.

PHP nepodporuje přetěžování funkcí, není možné ani oddefinování nebo předefinovaná dříve deklarovaných funkcí.

PHP 3 nepodporuje proměnný počet argumentů funkcí, zatímco implicitní argumenty jsou podporovány (více informací - viz Implicitní hodnoty argumentů). PHP 4 podporuje obojí: více informací - viz Seznam argumentů proměnné délky a reference funkcí `func_num_args()`, `func_get_arg()`, a `func_get_args()`.

Argumenty funkcí

Informace mohou být do funkcí předávány přes seznam argumentů, což je seznam proměnných a/nebo konstant oddělených čárkou.

PHP podporuje předávání argumentů hodnotou (implicitní), předávání odkazem, a implicitní hodnoty argumentů. Proměnná délka seznamu argumentů je podporována pouze v PHP 4 a pozdějších; viz Seznam argumentů proměnné délky a reference funkcí `func_num_args()`, `func_get_arg()`, a `func_get_args()`. Podobný efekt může být v PHP 3 dosažen předáním pole argumentů do funkce:

```
function takes_array($input)
{
    echo "$input[0] + $input[1] = ", $input[0]+$input[1];
}
```

Předávání argumentů odkazem

Implicitně jsou argumenty funkcí předávány hodnotou (takže když změníte hodnotu argumentu ve funkci, nezmění se mimo funkci). Pokud chcete umožnit funkci modifikovat své argumenty, musíte je předávat odkazem.

Pokud chcete, aby byl argument do funkce předáván vždy odkazem, můžete před název argumentu v definici funkce předřadit ampersand (&):

```
function add_some_extra(&$string)
{
    $string .= 'a něco navíc.';
}
$str = 'Toto je řetězec ';
add_some_extra($str);
echo $str;    // vypíše 'Toto je řetězec a něco navíc.'
```

Implicitní hodnoty argumentů

Funkce může ve stylu C++ definovat implicitní hodnoty pro skalární argumenty takto:

```
function makecoffee ($type = "cappucina")
{
    return "Dělám šálek $type.\n";
}
echo makecoffee ();
echo makecoffee ("espressa");
```

Výstupem výše uvedeného kódu je:

```
Dělám šálek cappucina.
Dělám šálek espresso.
```

Implicitní hodnota musí být konstantní výraz, ne (například) proměnná nebo položka třídy.

Uvědomte si, že když používáte implicitní argumenty, jakékoli implicitní hodnoty by měly být na pravé straně neimplicitního argumentu; jinak to nebude pracovat podle očekávání. Uvažujme tento kus kódu:

```
function makeyogurt ($type = "acidophilus", $flavour)
{
    return "Dělám kelímek jogurtu $type $flavour.\n";
}

echo makeyogurt ("malina");    // nebude pracovat podle očekávání
```


Výstupem uvedeného příkladu bude:

```
Warning: Missing argument 2 in call to makeyogurt() in
/usr/local/etc/httpd/htdocs/php3test/func_test.html on line 41
Dělám kelímek jogurtu malina.
```

A nyní to porovnejme s tímto:

```
function makeyogurt ($flavour, $type = "acidophilus")
{
    return "Dělám kelímek jogurtu $type $flavour.\n";
}

echo makeyogurt ("malina");    // pracuje podle očekávání
```

Příklad vytiskne:

```
Dělám kelímek jogurtu acidophilus malina.
```

Seznam argumentů proměnné délky

PHP 4 má podporu pro seznam argumentů proměnné délky v uživatelských funkcích. Je to opravdu jednoduché, použitím funkcí `func_num_args()`, `func_get_arg()`, a `func_get_args()`.

Není třeba žádná zvláštní syntaxe, seznam argumentů může být stále explicitně poskytován definicemi funkcí a bude se chovat jako normálně.

Návratové hodnoty

Hodnoty jsou vráceny pomocí nepovinné klausule `return`. Může být vrácen libovolný typ, včetně seznamů a objektů. Klausule způsobuje, že funkce okamžitě ukončí svůj běh a předá řízení zpět na řádek, odkud byla volána. Pro více informací viz `return()`.

```
function square ($num)
{
    return $num * $num;
}

echo square (4);    // vypíše '16'.
```

Z funkce nemůžete vrátet více hodnot, ale podobného výsledku může být dosaženo vrácením seznamu.

```
function small_numbers()
{
    return array (0, 1, 2);
}
list ($zero, $one, $two) = small_numbers();
```

K vrácení odkazu z funkce musíte použít referenční operátor & jak v deklaraci funkce, tak při přiřazování vrácené hodnoty do proměnné:

```
function &returns_reference()
{
    return $someref;
}

$newref =& returns_reference();
```

Pro další informace o odkazech se laskavě podívejte na Vysvětlení odkazů.

old_function

Klausule `old_function` umožňuje deklarovat funkci s identickou syntaxí jako v PHP/FI2 (kromě toho, že musíte 'function' nahradit 'old_function').

Toto je zavržená možnost a měla by být používána pouze PHP/FI2->PHP 3 konvertorem.

Varování

Funkce deklarované jako `old_function` nelze volat z interního kódu PHP. To mj. znamená, že je nemůžete používat ve funkcích jako `usort()`, `array_walk()`, a `register_shutdown_function()`. Toto omezení můžete obejít napsáním wrapperu (v normální PHP 3 formě), z něhož voláte `old_function`.

Funkce v proměnných

PHP podporuje koncept funkcí v proměnných. To znamená, že když má název proměnné připojeny závorky, PHP bude hledat funkci se stejným názvem, jako má hodnota proměnné, a pokusí se ji provést. To lze mj. použít k implementaci zpětných volání, tabulek funkcí atd.

Funkce v proměnných nebudou fungovat s jazykovými konstrukty jinými než `print()`, jako je `echo()`, `unset()`, `isset()` a `empty()`. To je jeden z velkých rozdílů mezi funkcemi PHP a jazykovými konstrukty.

Příklad 12-1. Příklad na funkce v proměnných

```
<?php
function foo()
{
    echo "V foo()<br>\n";
}

function bar($arg = "")
{
    echo "V bar(); byl argument '$arg'.<br>\n";
}

$func = 'foo';
$func();
$func = 'bar';
$func('test');
?>
```

Kapitola 13. Classes and Objects

class

A class is a collection of variables and functions working with these variables. A class is defined using the following syntax:

```
<?php
class Cart
{
    var $items; // Items in our shopping cart

    // Add $num articles of $artnr to the cart

    function add_item ($artnr, $num)
    {
        $this->items[$artnr] += $num;
    }

    // Take $num articles of $artnr out of the cart

    function remove_item ($artnr, $num)
    {
        if ($this->items[$artnr] > $num) {
            $this->items[$artnr] -= $num;
            return true;
        } else {
            return false;
        }
    }
}
?>
```

This defines a class named `Cart` that consists of an associative array of articles in the cart and two functions to add and remove items from this cart.

Výstraha

The following cautionary notes are valid for PHP 4.

The name `stdClass` is used internally by Zend and is reserved. You cannot have a class named `stdClass` in PHP.

The function names `__sleep` and `__wakeup` are magical in PHP classes. You cannot have functions with these names in any of your classes unless you want the magic functionality associated with them. See below for more information.

PHP reserves all function names starting with `__` as magical. It is recommended that you do not use function names with `__` in PHP unless you want some documented magic functionality.

Poznámka: In PHP 4, only constant initializers for `var` variables are allowed. To initialize variables with non-constant values, you need an initialization function which is called

automatically when an object is being constructed from the class. Such a function is called a constructor (see below).

```
<?php
/* None of these will work in PHP 4. */
class Cart
{
    var $todays_date = date("Y-m-d");
    var $name = $firstname;
    var $owner = 'Fred ' . 'Jones';
    var $items = array("VCR", "TV");
}

/* This is how it should be done. */
class Cart
{
    var $todays_date;
    var $name;
    var $owner;
    var $items;

    function Cart()
    {
        $this->todays_date = date("Y-m-d");
        $this->name = $GLOBALS['firstname'];
        /* etc. . . */
    }
}
```

Classes are types, that is, they are blueprints for actual variables. You have to create a variable of the desired type with the `new` operator.

```
<?php
$cart = new Cart;
$cart->add_item("10", 1);

$another_cart = new Cart;
$another_cart->add_item("0815", 3);
```

This creates the objects `$cart` and `$another_cart`, both of the class `Cart`. The function `add_item()` of the `$cart` object is being called to add 1 item of article number 10 to the `$cart`. 3 items of article number 0815 are being added to `$another_cart`.

Both, `$cart` and `$another_cart`, have functions `add_item()`, `remove_item()` and a variable `items`. These are distinct functions and variables. You can think of the objects as something similar to directories in a filesystem. In a filesystem you can have two different files `README.TXT`, as long as they are in different directories. Just like with directories where you'll have to type the full pathname in order to reach each file from the toplevel directory, you have to specify the complete name of the function you want to call: In PHP terms, the toplevel directory would be the global namespace, and the pathname separator would be `->`. Thus, the names `$cart->items` and `$another_cart->items` name two

different variables. Note that the variable is named `$cart->items`, not `$cart->$items`, that is, a variable name in PHP has only a single dollar sign.

```
// correct, single $
$cart->items = array("10" => 1);

// invalid, because $cart->$items becomes $cart->""
$cart->$items = array("10" => 1);

// correct, but may or may not be what was intended:
// $cart->$myvar becomes $cart->items
$myvar = 'items';
$cart->$myvar = array("10" => 1);
```

Within a class definition, you do not know under which name the object will be accessible in your program: at the time the `Cart` class was written, it was unknown that the object will be named `$cart` or `$another_cart` later. Thus, you cannot write `$cart->items` within the `Cart` class itself. Instead, in order to be able to access its own functions and variables from within a class, one can use the pseudo-variable `$this` which can be read as 'my own' or 'current object'. Thus, '`$this->items[$artnr] += $num`' can be read as 'add `$num` to the `$artnr` counter of my own items array' or 'add `$num` to the `$artnr` counter of the items array within the current object'.

Poznámka: There are some nice functions to handle classes and objects. You might want to take a look at the `Class/Object Functions`

extends

Often you need classes with similar variables and functions to another existing class. In fact, it is good practice to define a generic class which can be used in all your projects and adapt this class for the needs of each of your specific projects. To facilitate this, classes can be extensions of other classes. The extended or derived class has all variables and functions of the base class (this is called 'inheritance' despite the fact that nobody died) and what you add in the extended definition. It is not possible to subtract from a class, that is, to undefine any existing functions or variables. An extended class is always dependent on a single base class, that is, multiple inheritance is not supported. Classes are extended using the keyword 'extends'.

```
class Named_Cart extends Cart
{
    var $owner;

    function set_owner ($name)
    {
        $this->owner = $name;
    }
}
```

This defines a class `Named_Cart` that has all variables and functions of `Cart` plus an additional variable `$owner` and an additional function `set_owner()`. You create a named cart the usual way and can now set and get the carts owner. You can still use normal cart functions on named carts:

```
$ncart = new Named_Cart;    // Create a named cart
$ncart->set_owner("kris");  // Name that cart
print $ncart->owner;        // print the cart owners name
$ncart->add_item("10", 1);  // (inherited functionality from cart)
```

Constructors

Výstraha

In PHP 3 and PHP 4 constructors behave differently. The PHP 4 semantics are strongly preferred.

Constructors are functions in a class that are automatically called when you create a new instance of a class with `new`. In PHP 3, a function becomes a constructor when it has the same name as the class. In PHP 4, a function becomes a constructor, when it has the same name as the class it is defined in - the difference is subtle, but crucial (see below).

```
// Works in PHP 3 and PHP 4.
class Auto_Cart extends Cart
{
    function Auto_Cart()
    {
        $this->add_item ("10", 1);
    }
}
```

This defines a class `Auto_Cart` that is a `Cart` plus a constructor which initializes the cart with one item of article number "10" each time a new `Auto_Cart` is being made with "new". Constructors can take arguments and these arguments can be optional, which makes them much more useful. To be able to still use the class without parameters, all parameters to constructors should be made optional by providing default values.

```
// Works in PHP 3 and PHP 4.
class Constructor_Cart extends Cart
{
    function Constructor_Cart($item = "10", $num = 1)
    {
        $this->add_item ($item, $num);
    }
}
```



```
// Shop the same old boring stuff.

$default_cart = new Constructor_Cart;

// Shop for real...

$different_cart = new Constructor_Cart("20", 17);
```

Výstraha

In PHP 3, derived classes and constructors have a number of limitations. The following examples should be read carefully to understand these limitations.

```
class A
{
    function A()
    {
        echo "I am the constructor of A.<br>\n";
    }
}

class B extends A
{
    function C()
    {
        echo "I am a regular function.<br>\n";
    }
}

// no constructor is being called in PHP 3.
$b = new B;
```

In PHP 3, no constructor is being called in the above example. The rule in PHP 3 is: 'A constructor is a function of the same name as the class.'. The name of the class is B, and there is no function called B() in class B. Nothing happens.

This is fixed in PHP 4 by introducing another rule: If a class has no constructor, the constructor of the base class is being called, if it exists. The above example would have printed 'I am the constructor of A.
' in PHP 4.

```
class A
{
    function A()
    {
        echo "I am the constructor of A.<br>\n";
    }

    function B()
    {
```

```

        echo "I am a regular function named B in class A.<br>\n";
        echo "I am not a constructor in A.<br>\n";
    }
}

class B extends A
{
    function C()
    {
        echo "I am a regular function.<br>\n";
    }
}

// This will call B() as a constructor.
$b = new B;

```

In PHP 3, the function B() in class A will suddenly become a constructor in class B, although it was never intended to be. The rule in PHP 3 is: 'A constructor is a function of the same name as the class.'. PHP 3 does not care if the function is being defined in class B, or if it has been inherited.

This is fixed in PHP 4 by modifying the rule to: 'A constructor is a function of the same name as the class it is being defined in.'. Thus in PHP 4, the class B would have no constructor function of its own and the constructor of the base class would have been called, printing 'I am the constructor of A.
'.

Výstraha

Neither PHP 3 nor PHP 4 call constructors of the base class automatically from a constructor of a derived class. It is your responsibility to propagate the call to constructors upstream where appropriate.

Poznámka: There are no destructors in PHP 3 or PHP 4. You may use `register_shutdown_function()` instead to simulate most effects of destructors.

Destructors are functions that are called automatically when an object is destroyed, either with `unset()` or by simply going out of scope. There are no destructors in PHP.

::

Výstraha

The following is valid for PHP 4 only.

Sometimes it is useful to refer to functions and variables in base classes or to refer to functions in classes that have not yet any instances. The `::` operator is being used for this.

```

class A
{

```

```

function example()
{
    echo "I am the original function A::example().<br>\n";
}

class B extends A
{
    function example()
    {
        echo "I am the redefined function B::example().<br>\n";
        A::example();
    }
}

// there is no object of class A.
// this will print
//   I am the original function A::example().<br>
A::example();

// create an object of class B.
$b = new B;

// this will print
//   I am the redefined function B::example().<br>
//   I am the original function A::example().<br>
$b->example();

```

The above example calls the function `example()` in class A, but there is no object of class A, so that we cannot write `$a->example()` or similar. Instead we call `example()` as a 'class function', that is, as a function of the class itself, not any object of that class.

There are class functions, but there are no class variables. In fact, there is no object at all at the time of the call. Thus, a class function may not use any object variables (but it can use local and global variables), and it may not use `$this` at all.

In the above example, class B redefines the function `example()`. The original definition in class A is shadowed and no longer available, unless you are referring specifically to the implementation of `example()` in class A using the `::`-operator. Write `A::example()` to do this (in fact, you should be writing `parent::example()`, as shown in the next section).

In this context, there is a current object and it may have object variables. Thus, when used from WITHIN an object function, you may use `$this` and object variables.

parent

You may find yourself writing code that refers to variables and functions in base classes. This is particularly true if your derived class is a refinement or specialisation of code in your base class.

Instead of using the literal name of the base class in your code, you should be using the special name `parent`, which refers to the name of your base class as given in the `extends` declaration of your class. By doing this, you avoid using the name of your base class in more than one place. Should your inheritance tree change during implementation, the change is easily made by simply changing the `extends` declaration of your class.

```

class A
{
    function example()
    {
        echo "I am A::example() and provide basic functionality.<br>\n";
    }
}

class B extends A
{
    function example()
    {
        echo "I am B::example() and provide additional functionality.<br>\n";
        parent::example();
    }
}

$b = new B;

// This will call B::example(), which will in turn call A::example().
$b->example();

```

Serializing objects - objects in sessions

Poznámka: In PHP 3, objects will lose their class association throughout the process of serialization and unserialization. The resulting variable is of type object, but has no class and no methods, thus it is pretty useless (it has become just like an array with a funny syntax).

Výstraha

The following information is valid for PHP 4 only.

`serialize()` returns a string containing a byte-stream representation of any value that can be stored in PHP. `unserialize()` can use this string to recreate the original variable values. Using `serialize` to save an object will save all variables in an object. The functions in an object will not be saved, only the name of the class.

In order to be able to `unserialize()` an object, the class of that object needs to be defined. That is, if you have an object `$a` of class `A` on `page1.php` and `serialize` this, you'll get a string that refers to class `A` and contains all values of variables contained in `$a`. If you want to be able to `unserialize` this on `page2.php`, recreating `$a` of class `A`, the definition of class `A` must be present in `page2.php`. This can be done for example by storing the class definition of class `A` in an include file and including this file in both `page1.php` and `page2.php`.

```

classa.inc:
class A
{

```

```

        var $one = 1;

        function show_one()
        {
            echo $this->one;
        }
    }
}

page1.php:
    include("classa.inc");

    $a = new A;
    $s = serialize($a);
    // store $s somewhere where page2.php can find it.
    $fp = fopen("store", "w");
    fputs($fp, $s);
    fclose($fp);

page2.php:
    // this is needed for the unserialize to work properly.
    include("classa.inc");

    $s = implode("", @file("store"));
    $a = unserialize($s);

    // now use the function show_one() of the $a object.
    $a->show_one();

```

If you are using sessions and use `session_register()` to register objects, these objects are serialized automatically at the end of each PHP page, and are unserialized automatically on each of the following pages. This basically means that these objects can show up on any of your pages once they become part of your session.

It is strongly recommended that you include the class definitions of all such registered objects on all of your pages, even if you do not actually use these classes on all of your pages. If you don't and an object is being unserialized without its class definition being present, it will lose its class association and become an object of class `stdClass` without any functions available at all, that is, it will become quite useless.

So if in the example above `$a` became part of a session by running `session_register("a")`, you should include the file `classa.inc` on all of your pages, not only `page1.php` and `page2.php`.

The magic functions `__sleep` and `__wakeup`

`serialize()` checks if your class has a function with the magic name `__sleep`. If so, that function is being run prior to any serialization. It can clean up the object and is supposed to return an array with the names of all variables of that object that should be serialized.

The intended use of `__sleep` is to close any database connections that object may have, committing pending data or perform similar cleanup tasks. Also, the function is useful if you have very large objects which need not be saved completely.

Conversely, `unserialize()` checks for the presence of a function with the magic name `__wakeup`. If present, this function can reconstruct any resources that object may have.

The intended use of `__wakeup` is to reestablish any database connections that may have been lost during serialization and perform other reinitialization tasks.

References inside the constructor

Creating references within the constructor can lead to confusing results. This tutorial-like section helps you to avoid problems.

```
class Foo
{
    function Foo($name)
    {
        // create a reference inside the global array $globalref
        global $globalref;
        $globalref[] = &$this;
        // set name to passed value
        $this->setName($name);
        // and put it out
        $this->echoName();
    }

    function echoName()
    {
        echo "<br>", $this->name;
    }

    function setName($name)
    {
        $this->name = $name;
    }
}
```

Let us check out if there is a difference between `$bar1` which has been created using the copy = operator and `$bar2` which has been created using the reference =& operator...

```
$bar1 = new Foo('set in constructor');
$bar1->echoName();
$globalref[0]->echoName();

/* output:
set in constructor
set in constructor
set in constructor */

$bar2 =& new Foo('set in constructor');
$bar2->echoName();
$globalref[1]->echoName();
```

```
/* output:
set in constructor
set in constructor
set in constructor */
```

Apparently there is no difference, but in fact there is a very significant one: `$bar1` and `$globalref[0]` are NOT referenced, they are NOT the same variable. This is because "new" does not return a reference by default, instead it returns a copy.

Poznámka: There is no performance loss (since PHP 4 and up use reference counting) returning copies instead of references. On the contrary it is most often better to simply work with copies instead of references, because creating references takes some time where creating copies virtually takes no time (unless none of them is a large array or object and one of them gets changed and the other(s) one(s) subsequently, then it would be wise to use references to change them all concurrently).

To prove what is written above let us watch the code below.

```
// now we will change the name. what do you expect?
// you could expect that both $bar1 and $globalref[0] change their names...
$bar1->setName('set from outside');

// as mentioned before this is not the case.
$bar1->echoName();
$globalref[0]->echoName();

/* output:
set from outside
set in constructor */

// let us see what is different with $bar2 and $globalref[1]
$bar2->setName('set from outside');

// luckily they are not only equal, they are the same variable
// thus $bar2->name and $globalref[1]->name are the same too
$bar2->echoName();
$globalref[1]->echoName();

/* output:
set from outside
set from outside */
```

Another final example, try to understand it.

```
class A
{
    function A($i)
    {
```

```

        $this->value = $i;
        // try to figure out why we do not need a reference here
        $this->b = new B($this);
    }

    function createRef()
    {
        $this->c = new B($this);
    }

    function echoValue()
    {
        echo "<br>", "class ", get_class($this), ': ', $this->value;
    }
}

class B
{
    function B(&$a)
    {
        $this->a = &$a;
    }

    function echoValue()
    {
        echo "<br>", "class ", get_class($this), ': ', $this->a->value;
    }
}

// try to understand why using a simple copy here would yield
// in an undesired result in the *-marked line
$a =& new A(10);
$a->createRef();

$a->echoValue();
$a->b->echoValue();
$a->c->echoValue();

$a->value = 11;

$a->echoValue();
$a->b->echoValue(); // *
$a->c->echoValue();

/*
output:
class A: 10
class B: 10
class B: 10
class A: 11
class B: 11
class B: 11
*/

```


Kapitola 14. Vysvětlení referencí (odkazů)

Co jsou reference

Reference (odkazy) jsou prostředek, jak v PHP přistupovat k témuž obsahu proměnné pod různými jmény. Nejsou to ukazatele (pointery) jako v C, jsou to aliasy v tabulce symbolů. Uvědomte si, že v PHP je rozdíl mezi názvem proměnné a jejím obsahem, takže stejný obsah může mít různé názvy. Nejblíže analogií jsou názvy souborů a soubory v UNIXu - názvy proměnných jsou položky adresáře, obsahy proměnných samotné soubory. Na reference může být nazíráno jako na hardlinky v UNIXovém systému souborů.

Co reference dělají

PHP reference umožňují zajistit, aby dvě proměnné odkazovaly na tentýž obsah. Tzn. když provedete:

```
$a =& $b
```

znamená to, že `$a` a `$b` ukazují na stejnou proměnnou.

Poznámka: `$a` a `$b` jsou zde úplně ekvivalentní, tj. nikoliv že `$a` ukazuje na `$b` apod., nýbrž že `$a` a `$b` ukazují na stejné místo.

Stejná syntaxe se může použít s funkcemi, které vrací reference a s operátorem `new` (v PHP 4.0.4 a pozdějších):

```
$bar =& new fooclass();
$foo =& find_var ($bar);
```

Poznámka: Nepoužití operátoru `&` způsobí zkopírování objektu. Když ve třídě použijete `$this`, bude se pracovat s aktuální instancí třídy. Přiřazení bez `&` zkopíruje instanci (např. objektu) a `$this` bude pracovat s touto kopií, což není vždy to, co se požaduje. Většinou chcete mít jedinou instanci, s níž budete pracovat, kvůli rychlosti a alokaci paměti.

Druhou věcí, kterou reference dělají, je předávání proměnných odkazem. To se dělá vytvořením lokální proměnné ve funkci a proměnné v kontextu volajícího prostředí, kdy se odkazuje na tentýž obsah. Například:

```
function foo (&$var)
{
```

```

    $var++;
}

$a=5;
foo ($a);

```

nastaví do `$a` hodnotu 6. To proto, že ve funkci `foo` proměnná `$var` odkazuje tentýž obsah jako `$a`. Viz detailnější vysvětlení o předávání odkazem.

Třetí věcí, kterou mohou reference dělat, je vrácení přes reference.

Co reference nejsou

Jak již bylo řečeno, reference nejsou ukazatele. To znamená, že tento konstrukt nebude dělat to, co očekáváte:

```

function foo (&$var)
{
    $var =& $GLOBALS["baz"];
}
foo($bar);

```

Nastane to, že `$var` ve funkci `foo` bude přiřazena `$bar` ve volajícím kontextu, avšak poté bude přiřazena `$GLOBALS["baz"]`. Není způsob, jak přiřadit `$bar` ve volajícím kontextu něčemu jinému za použití mechanismu referencí, protože `$bar` není ve funkci `foo` dostupná (je reprezentována `$var`, ale `$var` má pouze obsah a nikoli spojení názvu s hodnotou v tabulce symbolů).

Předávání referencí (odkazem)

Můžete předávat proměnnou do funkce pomocí odkazu, takže funkce může modifikovat její argumenty. Syntaxe je následující:

```

function foo (&$var)
{
    $var++;
}

$a=5;
foo ($a);
// $a je teď 6

```

Všimněte si, že ve volání funkce není znak reference - pouze v její definici. Samotná definice funkce stačí na správné předávání argumentu odkazem.

Následující věci lze předávat referencí:

- Proměnná, např. `foo($a)`
- Konstrukt s `new`, např. `foo(new foobar())`
- Reference, vracená z funkce, např.:

```
function &bar()
{
    $a = 5;
    return $a;
}
foo(bar());
```

Viz také vysvětlení vracení přes reference.

Žádné jiné výrazy nemohou být předávány odkazem, výsledek tohoto není definován. Například, následující ukázky předávání odkazem jsou neplatné:

```
function bar() // Všimněte si chybějícího &
{
    $a = 5;
    return $a;
}
foo(bar());

foo($a = 5) // Výraz, nikoli proměnná
foo(5) // Konstanta, nikoli proměnná
```

Tyto požadavky platí pro PHP 4.0.4 a pozdější.

Vracení referencí

Vracení odkazem je užitečné, když chcete použít funkci k nalezení proměnné, která by měla být odkazu přiřazena. Při vracení referencí použijte tuto syntaxi:

```
function &find_var ($param)
{
    ...nějaký kód...
    return $found_var;
}

$foo =& find_var ($bar);
```

```
$foo->x = 2;
```

V tomto příkladu by bylo funkcí `find_var` nastaveno vlastnictví téhož objektu, nikoli jeho kopie, jak by se stalo bez použití syntaxe bez odkazů.

Poznámka: Narozdíl od předávání parametru, zde musíte `&` použít na obou místech - k indikaci, že vrátíte odkaz a nikoli kopii jako obvykle, a k indikaci přiřazení reference do `$foo` namísto běžného přiřazení (hodnoty).

Odnastavení odkazů

Když odnastavíte referenci, přerušíte vazbu mezi názvem proměnné a jejím obsahem. To neznamená, že by obsah byl zničen. Například:

```
$a = 1;
$b =& $a;
unset ($a);
```

neodnastaví `$b`, nýbrž pouze `$a`.

Znovu je dobré si připomenout analogii s UNIXovým příkazem **unlink**.

Další výskyt referencí

Mnoho syntaktických konstruktů v PHP je implementováno přes odkazový mechanismus, takže vše, co bylo řečeno výše o přiřazování referencí, platí i na tyto konstrukty. Některé konstrukty, jako předávání a vracení přes odkazy, byly již zmíněny. Ostatní konstrukty používající reference jsou:

odkazy `global`

Když deklarujete proměnnou jako **global \$var**, ve skutečnosti vytváříte odkaz na globální proměnnou. Tzn. je to totéž, jako:

```
$var =& $GLOBALS["var"];
```

To znamená, například, že odnastavení `$var` neodnastaví globální proměnnou.

\$this

V metodě objektu je `$this` vždy odkazem na volající objekt.

Část III. Vlastnosti

Kapitola 15. Zpracování chyb

V PHP existuje několik druhů chyb a varování. Jsou to:

Tabulka 15-1. Druhy chyb v PHP

Hodnota	Konstanta	Popis	Poznámka
1	E_ERROR	významné (fatální) runtimové chyby	
2	E_WARNING	runtimová varování (nevýznamné chyby)	
4	E_PARSE	kompilační syntaktické chyby	
8	E_NOTICE	runtimové zprávy (méně vážné než varování)	
16	E_CORE_ERROR	fatální chyby, které se vyskytly během startu PHP	pouze PHP 4
32	E_CORE_WARNING	varování během startu PHP	pouze PHP 4
64	E_COMPILE_ERROR	fatální kompilační chyby	pouze PHP 4
128	E_COMPILE_WARNING	kompilační varování (nevýznamné chyby)	PHP 4 only
256	E_USER_ERROR	uživatelsky generované chybové zprávy	PHP 4 only
512	E_USER_WARNING	uživatelsky generovaná varování	PHP 4 only
1024	E_USER_NOTICE	uživatelsky generované informativní zprávy	PHP 4 only
	E_ALL	všechny z uvedených, které jsou danou verzí PHP podporovány	

Výše uvedené hodnoty (ať již číselné nebo symbolické) se používají pro sestavení bitové masky, která specifikuje, které chyby se mají oznamovat. Můžete používat bitové logické operátory pro kombinaci hodnot nebo maskování určitých druhů chyb. Uvědomte si, že v souboru `php.ini` budou správně interpretovány pouze operátory '|', '~', '!', a '&', a že v `php3.ini` nelze použít žádné z těchto operátorů.

V PHP 4 je jako implicitní hodnota pro `error_reporting` nastaveno `E_ALL & ~E_NOTICE`, tzn. hlášení všech chyb a varování, které nejsou na úrovni `E_NOTICE`. V PHP 3 je implicitní (`E_ERROR | E_WARNING | E_PARSE`), což znamená totéž. Uvědomte si, že v souboru `php3.ini` nelze používat konstanty, a proto nastavení `error_reporting` musí být numerické; tedy například 7.

Iniciální nastavení může být v `ini` souboru změněno direktivou `error_reporting`, v serveru Apache v souboru `httpd.conf` direktivou `php_error_reporting` (`php3_error_reporting` v PHP 3), a konečně může být též nastaveno skriptem za použití funkce `error_reporting()`.

Varování

Pokud upgradujete kód nebo server z PHP 3 na PHP 4, měli byste ověřit tato nastavení a volání `error_reporting()` anebo potlačit hlášení nových typů chyb, zvláště `E_COMPILE_ERROR`. To může vést k vyprázdnění obsahu dokumentů bez jakékoli informace o tom, co se stalo a kde hledat problém.

Všechny PHP výrazy mohou být také volány s prefixem "@", který vypíná hlášení chyb pro tento jediný výraz. Pokud během provádění výrazu nastane chyba a volba `track_errors` je zapnutá, najdete chybovou zprávu v globální proměnné `$php_errormsg`.

Poznámka: Prefixovým operátorem řízení chyb `@` nelze potlačit chybová hlášení o syntaktických chybách.

Varování

V současnosti prefixový operátor řízení chyb v případě kritických chyb (které ukončí provádění skriptu) pouze potlačí chybové hlášení. Jinými slovy, pokud použijete `@` k potlačení chyb z jisté funkce, která není dostupná nebo byla chybně zapsána, skript zde skončí, aniž by indikoval proč.

Níže uvedený příklad ukazuje použití schopností zpracování chyb v PHP. Definujeme funkci zpracování chyb, která zaznamenává informace do souboru (v XML formátu) a v případě kritické chyby odešle e-mailovou zprávu vývojáři.

Příklad 15-1. Použití zpracování chyb ve skriptu

```
<?php
// uděláme si vlastní zpracování chyb
error_reporting(0);

// uživatelsky definovaná funkce pro zpracování chyb
function errorHandler ($errno, $errormsg, $filename, $linenum, $vars) {
    // časové razítko položky
    $dt = date("Y-m-d H:i:s (T)");

    // definuje asociativní pole pro chybový řetězec
    // ve skutečnosti mohou položky obsahovat pouze
    // hodnoty 2,8,256,512 a 1024
    $errortype = array (
        1    => "Error",
        2    => "Warning",
        4    => "Parsing Error",
        8    => "Notice",
        16   => "Core Error",
        32   => "Core Warning",
        64   => "Compile Error",
        128  => "Compile Warning",
        256  => "User Error",
        512  => "User Warning",
        1024 => "User Notice"
    );
```

```

// množina chyb, pro které bude uložen výpis proměnných
$user_errors = array(E_USER_ERROR, E_USER_WARNING, E_USER_NOTICE);

$error = "<errorentry>\n";
$error .= "\t<datetime>".$dt."</datetime>\n";
$error .= "\t<errornum>".$errno."</errornum>\n";
$error .= "\t<errortype>".$errortype[$errno."</errortype>\n";
$error .= "\t<errmsg>".$errmsg."</errmsg>\n";
$error .= "\t<scriptname>".$filename."</scriptname>\n";
$error .= "\t<scriptlinenum>".$linenum."</scriptlinenum>\n";

if (in_array($errno, $user_errors))
    $error .= "\t<vartrace>".wddx_serialize_value($vars, "Variables")."</vartrace>\n";
$error .= "</errorentry>\n\n";

// pro testování
// echo $error;

// ulož do chybového protokolu a pošli mi zprávu (pokud je to kritická chyba)
error_log($error, 3, "/usr/local/php4/error.log");
if ($errno == E_USER_ERROR)
    mail("phpdev@mydomain.com", "Critical User Error", $error);
}

function distance ($vect1, $vect2) {
    if (!is_array($vect1) || !is_array($vect2)) {
        trigger_error("Incorrect parameters, arrays expected", E_USER_ERROR);
        return NULL;
    }

    if (count($vect1) != count($vect2)) {
        trigger_error("Vectors need to be of the same size", E_USER_ERROR);
        return NULL;
    }

    for ($i=0; $i<count($vect1); $i++) {
        $c1 = $vect1[$i]; $c2 = $vect2[$i];
        $d = 0.0;
        if (!is_numeric($c1)) {
            trigger_error("Coordinate $i in vector 1 is not a number, using zero",
                E_USER_WARNING);
            $c1 = 0.0;
        }
        if (!is_numeric($c2)) {
            trigger_error("Coordinate $i in vector 2 is not a number, using zero",
                E_USER_WARNING);
            $c2 = 0.0;
        }
        $d += $c2*$c2 - $c1*$c1;
    }
    return sqrt($d);
}

$old_error_handler = set_error_handler("userErrorHandler");

// nedefinovaná konstanta, generuje varování

```

```

$t = I_AM_NOT_DEFINED;

// definuje nějaké "vektory"
$a = array(2,3,"foo");
$b = array(5.5, 4.3, -1.6);
$c = array (1,-3);

// generuje uživatelskou chybu
$t1 = distance($c,$b)."\n";

// generuje jinou uživatelskou chybu
$t2 = distance($b,"i am not an array")."\n";

// generuje hlášení
$t3 = distance($a,$b)."\n";

?>

```

Toto je pouze jednoduchý příklad, který ukazuje, jak používat Funkce pro zpracování a záznam chyb. Viz také `error_reporting()`, `error_log()`, `set_error_handler()`, `restore_error_handler()`, `trigger_error()`, `user_error()`

Kapitola 16. Tvorba a úpravy obrázků

PHP není omezeno na tvorbu pouze HTML výstupu. Může také vytvářet a upravovat obrázkové soubory různých formátů, včetně gif, png, jpg, wbmp a xpm. PHP může dokonce přímo posílat obrazové proudy do browseru. Na to budete potřebovat PHP zkompileované s GD knihovnou obrazových funkcí. GD a PHP mohou vyžadovat další knihovny v závislosti na obrazových formátech, se kterými chcete pracovat. GD přestala podporovat gif obrázky ve verzi 1.6.

Příklad 16-1. Tvorba PNG obrázků v PHP

```
<?php
    Header("Content-type: image/png");
    $string=implode($argv," ");
    $im = imageCreateFromPng("images/button1.png");
    $orange = ImageColorAllocate($im, 220, 210, 60);
    $px = (imagesx($im)-7.5*strlen($string))/2;
    ImageString($im,3,$px,9,$string,$orange);
    ImagePng($im);
    ImageDestroy($im);
?>
```

Tento příklad by se volal ze stránky pomocí tagu podobného tomuto: `` Skript `button.php` pak vezme řetězec "text", překryje jím základní obrázek, což je v tomto případě "images/button1.png" a zobrazí výsledný obrázek. Toto je vhodný způsob jak se vyhnout kreslení nového obrázku tlačítka pokaždé, když chcete změnit text tlačítka. Touto metodou se generují automaticky.

Kapitola 17. HTTP autentikace a PHP

Prostředky HTTP autentikace jsou v PHP přístupné pouze pokud PHP běží jako modul Apache, tudíž nejsou přístupné v CGI verzi. V PHP skriptu běžícím pod modulem Apache lze použít funkci `header()` k odeslání zprávy "Authentication Required" klientskému browseru, což vyvolá zobrazení dialogového okna pro vložení uživatelského jména a hesla. Jakmile uživatel zadá jméno a heslo, URL obsahující tento PHP skript se zavolá znovu s proměnnými `$PHP_AUTH_USER`, `$PHP_AUTH_PW` and `$PHP_AUTH_TYPE` obsahujícími jméno, heslo a typ autentikace. V současnosti je podporována pouze "Basic" autentikace. Více informací viz funkce `header()`.

Následující fragment kódu může posloužit jako ukázka vyžádání autentikace uživatele na stránce:

Příklad 17-1. Ukázka HTTP Autentikace

```
<?php
if(!isset($PHP_AUTH_USER)) {
    Header("WWW-Authenticate: Basic realm=\"My Realm\"");
    Header("HTTP/1.0 401 Unauthorized");
    echo "Text, který se odešle, pokud uživatel zmáčkne tlačítko Cancel\n";
    exit;
} else {
    echo "Ahoj $PHP_AUTH_USER.<P>";
    echo "Jako heslo jsi zadal $PHP_AUTH_PW.<P>";
}
?>
```

Místo protého vytištění `$PHP_AUTH_USER` a `$PHP_AUTH_PW` byste asi chtěli ověřit platnost zadaného jména a hesla. Například dotazem v databázi nebo vyhledáním uživatele v dbm souboru.

Pozor na chybové browsery Internet Explorer. Zdá se, že jsou velice vybíravé, pokud jde o pořadí hlaviček. Zdá se, že odeslání hlavičky *WWW-Authenticate* před hlavičkou *HTTP/1.0 401* zabírá.

Aby se zabránilo psaní skriptů odhalujících hesla na stránkách autentikovaných některým z tradičních externích mechanismů, `$PHP_AUTH` proměnné se nevytvorí, pokud je pro tu kterou stránku zapnuta externí autentikace. V takovém případě můžete k identifikaci externě autentikovaného uživatele použít proměnnou `$REMOTE_USER`.

Všimněte si nicméně, že výše uvedené nezabrání krádežím hesel z autentikovaných URL osobou, která ovládá neautentikovanou URL na stejném serveru.

Jak Netscape, tak Internet Explorer po přijetí response kódu 401 vyprázdní autentikační cache současného realmu. Tak můžete uživatele v podstatě "odlogovat". Někteří lidé toho využívají k "vypršení" přihlášení nebo tvorbě odhlašovacího tlačítka.

Příklad 17-2. Ukázka HTTP autentikace vyžadující nové jméno a heslo

```
<?php
function authenticate() {
    Header( "WWW-Authenticate: Basic realm=\"Test Authentication System\"");
    Header( "HTTP/1.0 401 Unauthorized");
    echo "K přístupu na tento zdroj musíte zadat platné ID a heslo\n";
    exit;
}

if(!isset($PHP_AUTH_USER) || ($SeenBefore == 1 && !strcmp($OldAuth, $PHP_AUTH_USER)) )
    authenticate();
}
```



```

else {
    echo "Welcome: $PHP_AUTH_USER<BR>";
    echo "Old: $OldAuth";
    echo "<FORM ACTION=\"\$PHP_SELF\" METHOD=POST>\n";
    echo "<INPUT TYPE=HIDDEN NAME=\"SeenBefore\" VALUE=\"1\">\n";
    echo "<INPUT TYPE=HIDDEN NAME=\"OldAuth\" VALUE=\"\$PHP_AUTH_USER\">\n";
    echo "<INPUT TYPE=Submit VALUE=\"Re Authenticate\">\n";
    echo "</FORM>\n";
}
?>

```

Podle standardu HTTP Basic authentication se toto chování nevyžaduje, takže byste na to nikdy neměli spoléhat. Pokusy s Lynxem ukázaly, že Lynx po přijetí response kódu 401 nevyprázdní autentikační údaje, takže po stisknutí back a forward se znovu ukáže požadovaný zdroj (pokud se nezměnily požadavky na údaje).

Dále si všimněte, že tato vlastnost při použití IIS serveru a CGI verze PHP díky omezením IIS nefunguje.

Kapitola 18. Cookies

PHP transparentně podporuje HTTP cookies. Cookies jsou mechanismem na ukládání dat ve vzdáleném browseru a tudíž sledování nebo identifikaci vracejících se uživatelů. Cookies můžete nastavovat pomocí funkce `setcookie()`. Cookies jsou součástí HTTP hlavičky, tudíž `setcookie()` se musí volat před odesláním výstupu do browseru. To je stejné omezení, jako má funkce `header()`.

Všechny cookies přijaté od klienta se automaticky stávají PHP proměnnou stejně jako u GET a POST dat. Pokud chcete přiřadit jednomu cookie více hodnot, přidejte `[]` na konec jména cookie. Více detailů viz funkce `setcookie()`.

Kapitola 19. Zpracování uploadu souborů

Uploading metodou POST

PHP umožňuje zpracování uploadu souborů z jakéhokoli prohlížeče vyhovujícího RFC-1867 (což zahrnuje mj. Netscape Navigator 3 a pozdější, Microsoft Internet Explorer 3 se záplatou od Microsoftu, nebo pozdější bez záplaty). Tato schopnost umožňuje lidem uploadovat textové i binární soubory. S autentizací poskytovanou PHP a s funkcemi pro manipulaci se soubory máte plnou kontrolu nad tím, kdo smí uploadovat a co se má udělat s uploadovaným souborem.

Nezapomeňte, že PHP podporuje také uploady metodou PUT tak, jak se používá v Netscape Composeru a v editoru Amaya od W3C. Pro bližší detaily viz Podpora metody PUT.

Obrazovka pro upload souboru může být tvořena speciálním formulářem, který vypadá podobně jako tento:

Příklad 19-1. Formulář pro upload souboru

```
<form enctype="multipart/form-data" action="_URL_" method="post">
<input type="hidden" name="MAX_FILE_SIZE" value="1000">
Send this file: <input name="userfile" type="file">
<input type="submit" value="Send File">
</form>
```

URL by mělo označovat PHP soubor. Skryté pole MAX_FILE_SIZE musí předcházet pole pro vložení souboru a jeho hodnota specifikuje maximální akceptovanou velikost souboru. Hodnota je v bytech.

Varování

Hodnota MAX_FILE_SIZE je z hlediska prohlížeče pouze informativní. Je snadné ji obejít. Takže nepočítejte s tím, že prohlížeč se bude chovat tak, jak si přejete. Nastavení maximální velikosti v PHP však samozřejmě nemůže být obelstěno.

Proměnné definované pro uploadované soubory se liší v závislosti na verzi a konfiguraci PHP. Pokud je aktivní volba track_vars, bude inicializováno pole \$HTTP_POST_FILES/\$_FILES. Konečně, související proměnné mohou být inicializovány jako globální, pokud je zapnuta volba register_globals. Ovšem používání globálních proměnných není doporučeno. Po úspěšném uploadu budou v cílovém skriptu definovány následující proměnné:

Poznámka: track_vars je od PHP 4.0.3 vždy zapnuto. U PHP 4.1.0 a pozdějších může být použito \$_FILES namísto \$HTTP_POST_FILES. \$_FILES je vždy globální proměnná, takže by se neměla používat specifikace global pro proměnnou \$_FILES.

\$HTTP_POST_FILES/\$_FILES obsahuje informace o uploadovaném souboru.

Obsah \$HTTP_POST_FILES je takovýto (uvědomte si, že se předpokládá použití názvu uploadovaného souboru 'userfile' tak, jako v příkladu výše):

```
$HTTP_POST_FILES['userfile']['name']
```

Originální název souboru na klientském počítači.

```
$HTTP_POST_FILES['userfile']['type']
```

MIME typ souboru, pokud prohlížeč tuto informaci poskytuje (např. "image/gif").

```
$HTTP_POST_FILES['userfile']['size']
```

Velikost uploadovaného souboru v bytech.

```
$HTTP_POST_FILES['userfile']['tmp_name']
```

Dočasný název souboru, pod nímž byl uploadovaný soubor uložen na server.

Poznámka: PHP 4.1.0 a pozdější podporují zkrácený název proměnné `$_FILES`. PHP 3 nepodporuje `$HTTP_POST_FILES`.

Obsah proměnných v situaci, kdy je proměnná `register_globals` zapnuta nastavením v souboru `php.ini` (uvědomte si, že se předpokládá použití názvu uploadovaného souboru 'userfile' tak, jako v příkladu výše):

- `$userfile` - Dočasný název souboru, pod kterým byl uploadovaný soubor uložen na server.
- `$userfile_name` - Originální název souboru nebo cesta na odesílajícím systému.
- `$userfile_size` - Velikost uploadovaného souboru v bytech.
- `$userfile_type` - MIME typ souboru, pokud prohlížeč tuto informaci poskytuje (např. "image/gif").

Uvědomte si, že proměnná "`$userfile`" ve skutečnosti představuje název pole `<input>` se specifikací `type="file"` ve formuláři. Pro výše uvedený příklad jsme zvolili název "userfile".

Poznámka: Nastavení `register_globals = On` se nedoporučuje z bezpečnostních a výkonnostních důvodů.

Soubory se implicitně ukládají do systémového adresáře pro dočasné soubory, pokud nebylo direktivou `upload_tmp_dir` v souboru `php.ini` stanoveno jinak. Systémový adresář pro dočasné soubory může být změněn nastavením proměnné prostředí `TMPDIR` v prostředí, kde PHP běží. Nastavení za použití `putenv()` z PHP skriptu nebude fungovat. Tato proměnná prostředí může být také použita k ujištění se, že všechny ostatní operace pracují s uploadovanými soubory.

Příklad 19-2. Ověřování uploadu souboru

Následující příklady jsou pro verze PHP 4 vyšší než PHP 4.0.2. (viz funkce `is_uploaded_file()` a `move_uploaded_file()`).

```
<?php
// V PHP 4.1.0 a pozdějších by mělo být použito $_FILES namísto $HTTP_POST_FILES.
if (is_uploaded_file($HTTP_POST_FILES['userfile']['tmp_name'])) {
```

```

        copy($HTTP_POST_FILES['userfile'][$tmp_name], "/place/to/put/uploaded/file");
    } else {
        echo "Possible file upload attack. Filename: " . $HTTP_POST_FILES['userfile'][$name];
    }
    /* ...or... */
    move_uploaded_file($HTTP_POST_FILES['userfile'][$tmp_name], "/place/to/put/uploaded/file");
?>

```

PHP skript, který přijímá uploadované soubory, by měl implementovat veškerou logiku pro stanovení, co by se mělo udělat s uploadovaným souborem. Můžete např. použít proměnnou `$HTTP_POST_FILES['userfile'][$size]` pro zahození souborů, které jsou příliš malé nebo velké. Mohli byste použít také proměnnou `$HTTP_POST_FILES['userfile'][$type]` pro filtraci souborů podle MIME datového typu. Bez ohledu na řešení, soubor by měl být smazán nebo přesunut jinde.

Soubor bude automaticky smazán z dočasného adresáře na konci skriptu, pokud nebyl přesunut jinde nebo přejmenován.

Častá úskalí

`MAX_FILE_SIZE` nemůže specifikovat velikost souboru větší než je ta, která byla nastavena pomocí `upload_max_filesize` v konfiguraci PHP. Implicitně jsou to 2 MB.

Pokud je zapnut limit paměti, může být potřeba větší hodnota `memory_limit`. Ujistěte se, že je hodnota `memory_limit` dostatečně velká.

Pokud je nastavená hodnota `max_execution_time` příliš malá, doba provádění skriptu ji může překročit. Ujistěte se, že je hodnota `max_execution_time` dostatečně velká.

Pokud je nastavená hodnota `post_max_size` příliš malá, nemůže být uploadován větší soubor. Ujistěte se, že je hodnota `post_max_size` dostatečně velká.

Neověřování, se kterým souborem se pracuje, může znamenat, že se uživatelé mohou dostat k citlivým informacím v jiných adresářích.

Uvědomte si prosím, že server CERN httpd odstraňuje všechno, co počíná první bílou mezerou (whitespace) v MIME hlavičce `Content-Type` obdrží od klienta. Za existence tohoto jevu nebude CERN httpd podporovat uploading souborů.

Uploading více souborů

Více souborů může být uploadováno za použití různých názvů name pro souborové pole `input`.

Je také možné uploadovat více souborů současně a nechat informace automaticky zorganizovat v polích. V takovém případě je třeba použít stejnou syntaxi v HTML formuláři jako pro vícenásobné výběry a zaškrťovací políčka (checkboxy).

Poznámka: Podpora pro upload více souborů byla přidána ve verzi 3.0.10.

Příklad 19-3. Uploading více souborů

```
<form action="file-upload.php" method="post" enctype="multipart/form-data">
  Send these files:<br>
  <input name="userfile[]" type="file"><br>
  <input name="userfile[]" type="file"><br>
  <input type="submit" value="Send files">
</form>
```

Pokud je výše uvedený formulář odeslán, pole `$HTTP_POST_FILES['userfile']`, `$HTTP_POST_FILES['userfile']['name']`, a `$HTTP_POST_FILES['userfile']['size']` budou inicializována (jak `$_FILES` v PHP 4.1.0 a pozdějším, tak `$HTTP_POST_VARS` v PHP 3. Pokud je nastavení `register_globals` aktivní globální proměnné pro uploadované soubory jsou také inicializovány). Každé z nich bude číselně indexované pole odpovídajících hodnot pro odeslané soubory.

Kupříkladu předpokládejme, že se posílají soubory s názvy `/home/test/review.html` a `/home/test/xwp.out`. V tom případě by `$HTTP_POST_FILES['userfile']['name'][0]` obsahovalo hodnotu `review.html` a `$HTTP_POST_FILES['userfile']['name'][1]` hodnotu `xwp.out`. Podobně `$HTTP_POST_FILES['userfile']['size'][0]` by obsahovalo velikost `review.html` atd.

```
$HTTP_POST_FILES['userfile']['name'][0],
$HTTP_POST_FILES['userfile']['tmp_name'][0],
$HTTP_POST_FILES['userfile']['size'][0] a
$HTTP_POST_FILES['userfile']['type'][0] budou rovněž nastaveny.
```

Podpora metody PUT

PHP poskytuje podporu pro HTTP PUT metodu používanou klienty jako Netscape Composer nebo W3C Amaya. Požadavky s metodou PUT jsou mnohem jednodušší než upload souborů a vypadají přibližně takto:

```
PUT /path/filename.html HTTP/1.1
```

Toto by normálně znamenalo, že by chtěl klient uložit obsah, který následuje za názvem `/path/filename.html`, do svého webového stromu. To samozřejmě není dobrý nápad, aby Apache nebo PHP automaticky nechal kohokoli přepsat jakékoli soubory ve stromě. Takže, pro zpracování takového požadavku je třeba nejdřív říci vašemu WWW serveru, že chcete požadavek zpracovávat konkrétním PHP skriptem. U serveru Apache se to provede direktivou *Script*. Může být umístěna kdekoli v konfiguračním souboru Apache. Častými místy jsou bloky `<Directory>` a `<Virtualhost>`. Použije se k tomu řádek podobný tomuto:

```
Skript PUT /put.php
```


Toto řekne serveru Apache, aby všechny PUT požadavky na nějaký URI vyhovující kontextu posílal skriptu put.php. To pochopitelně předpokládá, že máte povoleno PHP pro příponu .php a PHP je aktivní.

V souboru put.php byste potom mohli napsat něco jako:

```
<?php copy( $PHP_UPLOADED_FILE_NAME , $DOCUMENT_ROOT . $REQUEST_URI ) ; ?>
```

Toto by mělo zkopírovat soubor na místo požadované vzdáleným klientem. Pravděpodobně byste chtěli provést nějaká ověření a/nebo autentizace uživatele před provedením tohoto zkopírování. Jediným použitelným trikem je, že PHP uloží přenesený soubor do dočasného adresáře podobně, jako při použití metody POST. Až skript skončí, dočasný soubor bude odstraněn. Takže váš PHP skript pro zpracování PUT požadavků musí soubor zkopírovat jinam. Název souboru v dočasném umístění je uložen v proměnné \$PHP_PUT_FILENAME a požadovaný název cílového souboru v proměnné \$REQUEST_URI (může se lišit u serverů jiných než Apache). Toto cílové jméno je to jediné, co klient specifikoval. Nemusíte ho poslechnout. Mohli byste, například, kopírovat všechny uploadované soubory do speciálního uploadového adresáře.

Kapitola 20. Použití vzdálených souborů

Pokud při konfiguraci PHP aktivujete podporu "URL fopen wrapper" (standardně je zapnutá, ledaže pro configure explicitně zadáte `--disable-url-fopen-wrapper` příznak (verze do 4.0.3), nebo (u novějších verzí) nastavíte `allow_url_fopen` v `php.ini` na `off`), můžete ve voláních většiny funkcí, které očekávají jako argument název souboru (včetně `require()` a `include()`) uvést HTTP nebo FTP URL.

Poznámka: Na Windows nelze používat vzdálené soubory v `include()` a `require()` výrazech.

Můžete například otevřít soubor na vzdáleném web serveru, vyseparovat z výstupu data, která potřebujete, a tato data potom použít v dotazu na databázi, nebo je prostě začlenit do výstupu stylem odpovídajícím zbytku vaší web site.

Příklad 20-1. Získání názvu vzdálené stránky

```
<?php
$file = fopen ("http://www.php.net/", "r");
if (!$file) {
    echo "<p>Nelze otevřít vzdálený soubor.\n";
    exit;
}
while (!feof ($file)) {
    $line = fgets ($file, 1024);
    /* Toto bude fungovat pouze pokud jsou tagy a název na jedné řádce */
    if (eregi ("<title>(.*?)</title>", $line, $out)) {
        $title = $out[1];
        break;
    }
}
fclose($file);
?>
```

Pokud se připojíte jako uživatel s dostatečnými právy, a daný soubor už neexistuje, můžete data také ukládat po FTP. Pokud se chcete připojit jako jiný uživatel než 'anonymous', musíte v URL udat uživatelské jméno (a pravděpodobně i heslo), např. 'ftp://uzivatel:heslo@ftp.example.com/path/to/file'. (Pro přístup k souborům přes HTTP, které vyžadují Basic authentication, můžete použít stejnou syntaxi.)

Příklad 20-2. Uložení dat na vzdáleném serveru

```
<?php
$file = fopen ("ftp://ftp.php.net/incoming/outputfile", "w");
if (!$file) {
    echo "<p>Nelze otevřít vzdálený soubor pro zápis.\n";
    exit;
}
/* Zapišeme data. */
```

```
fputs ($file, "$HTTP_USER_AGENT\n");  
fclose ($file);  
?>
```

Poznámka: Z výše uvedeného příkladu by vás mohlo napadnout využít tuto techniku k zápisu do vzdáleného logu, ale jak už bylo zmíněno výše, pomocí URL fopen() wrapperu můžete zapisovat pouze do nového souboru. Pokud máte zájem o distribuované logování, podívejte se na syslog().

Kapitola 21. Obsluha spojení

Poznámka: Následující text platí pro verzi 3.0.7 a vyšší.

Stav spojení se v PHP interně sleduje. Jsou tři možné stavy:

- 0 - NORMAL (normální)
- 1 - ABORTED (zrušeno)
- 2 - TIMEOUT (vypršel časový limit)

Při normálním běhu PHP skriptu je aktivní stav NORMAL. Pokud se klient odpojí, nastaví se příznak ABORTED. K odpojení vzdáleného klienta typicky dochází, když uživatel zmáčkne tlačítko STOP. Pokud se dosáhne časového limitu (viz `set_time_limit()`), nastaví se stavový příznak TIMEOUT.

Můžete se rozhodnout jestli chcete, aby odpojení klienta způsobilo předčasné ukončení vašeho skriptu. Někdy je užitečné nechat skripty doběhnout do konce, přestože není vzdáleného browseru, který by přijímal výstup. Výchozí chování je nicméně takové, že při odpojení vzdáleného klienta dojde k ukončení běhu skriptu. Toto chování se dá změnit skrze konfigurační direktivu `ignore_user_abort` v `php3.ini`, odpovídající direktivu `php3_ignore_user_abort` v `.conf` souboru Apache, či funkci `ignore_user_abort()`. Pokud nedáte PHP pokyn ignorovat odpojení uživatele a ten se odpojí, váš skript se ukončí. Výjimkou je, pokud máte pomocí `register_shutdown_function()` zaregistrovanou funkci pro provedení při ukončení skriptu. V tom případě, pokud vzdálený uživatel zmáčkne tlačítko STOP, při dalším pokusu tohoto skriptu odeslat výstup PHP detekuje, že spojení bylo zrušeno, a zavolá se funkce zaregistrovaná pro provedení při ukončení skriptu. Tato funkce se zavolá také na konci běhu skriptu končícím normálně, takže pokud chcete po zrušeném spojení udělat něco jiného, můžete použít `connection_aborted()`. Tato funkce vrátí `TRUE`, pokud bylo spojení zrušeno.

Váš skript může také ukončit vestavěný čítač času. Výchozí časový limit je 30 sekund. To se dá změnit `max_execution_time` direktivou v `php3.ini` nebo odpovídající `php3_max_execution_time` direktivou v `.conf` souboru Apache, či voláním funkce `set_time_limit()`. Když čítač času doběhne, skript se ukončí, a jako ve výše uvedeném případě uživatelského odpojení, pokud je zaregistrovaná funkce pro provedení při ukončení skriptu, tato se zavolá. Uvnitř této funkce můžete zkontrolovat, jestli její zavolání způsobilo doběhnutí čítače času zavoláním funkce `connection_timeout()`. Tato funkce vrátí `TRUE`, pokud volání funkce registrované pro provedení při ukončení skriptu způsobilo doběhnutí čítače času.

Skutečností hodnou povšimnutí je, že stavy ABORTED a TIMEOUT mohou být aktivní současně. Možné je to v případě, že nařídíte PHP ignorovat odpojení uživatele. PHP i tak bude vědět, že uživatel přerušil spojení, ale skript poběží dál. Pokud potom dosáhne časového limitu, bude ukončen, a zavolá se vaše funkce pro provedení při ukončení skriptu, pokud existuje. V tomto okamžiku zjistíte, že jak `connection_timeout()`, tak `connection_aborted()` vracejí `TRUE`. Oba stavy můžete zkontrolovat jediným voláním funkce `connection_status()`. Tato funkce vrací bitové pole aktivních stavů. Takže například, pokud jsou aktivní oba tyto stavy, vrátí 3.

Kapitola 22. Persistentní databázová spojení

Trvalá spojení jsou SQL spojení, která se nezavírají na konci průběhu skriptu. Při požadavku na trvalé spojení PHP nejdříve zkontroluje, jestli už neexistuje identické spojení (které zůstalo otevřeno z dřívějšíka) - a pokud existuje, použije ho. Pokud neexistuje, PHP ho otevře. "Identické" spojení je spojení, které bylo otevřeno se stejným serverem, uživatelským jménem a heslem (pokud je zadáte).

Lidé, kteří nejsou důkladně obeznámeni se způsobem, jakým web servery fungují a distribuují zátěž mohou pokládat trvalá spojení za něco čím nejsou. Zvláště *neumožňují* otvírání "uživatelských sessions" na stejném SQL spojení, *neumožňují* efektivní tvorbu transakcí, a neumožňují spoustu dalších věcí. Dokonce, aby bylo opravdu a důkladně jasno, vám trvalá spojení nedají *žádnou* funkcionalitu, která by nebyla možná s jejich netrvalými protějšky.

Proč?

To je dáno způsobem, jakým fungují webové servery. Jsou tři způsoby, jakými váš web server může využít PHP ke generování webových stránek.

První metodou je použít PHP jako CGI "obal". V tomto režimu se vytváří a ničí jedna instance PHP interpreteru pro každý požadavek (na PHP stránku) na vašem web serveru. Protože je zničena po obslužení požadavku, všechny zdroje, které získá (jako třeba spojení s databázovým serverem) jsou při jejím zničení zavřeny. V tomto případě pokusem o použití trvalých spojení nic nezískáte - prostě nevydrží.

Druhou, a nejpobulárnější, metodou, je provozovat PHP jako modul v multiprocesním web serveru, což je množina, která v současnosti obsahuje pouze Apache. Multiprocesní web server má typicky jeden proces (rodiče), který řídí skupinu procesů (svých dětí), které dělají vlastní práci - servírují stránky. Každý požadavek, který přijde od klienta, je obslužen jedním z dětí, které právě neobsluhuje jiného klienta. To znamená, že když stejný klient vznesne další požadavek na stejný server, tento může být obslužen jiným dětským procesem než ten první. Trvalá spojení zajišťují, aby se každý dětský proces musel na váš SQL server přihlásit pouze při prvním odeslání stránky, která takové spojení využívá. Když spojení s SQL serverem vyžaduje další stránka, může použít spojení, které toto dítě otevřelo už dříve.

Poslední metodou je použít PHP jako plugin v multithreadovém web serveru. To je v současnosti pouhá teorie - PHP ještě nefunguje jako plugin v žádném multithreadovém web serveru. Pracuje se na podpoře ISAPI, WSAPI a NSAPI (na Windows), což umožní používat PHP jako plugin v multithreadových serverech jako Netscape FastTrack, Microsoft Internet Information Server (IIS), a O'Reilly's WebSite Pro. Až k tomu dojde, chování bude v podstatě stejné jako u multiprocesním modelu popsaném dříve.

Pokud trvalá spojení neposkytují žádnou přidanou funkcionalitu, k čemu jsou dobrá?

Odpověď na tuto otázku je velmi jednoduchá - efektivita. Trvalá spojení jsou dobrá, pokud má tvorba spojení s vaším SQL serverem vysokou rychlost. Reálná výše této rychlosti závisí na mnoha faktorech. Například jaký je to typ databáze, jestli sídlí na stejném počítači jako váš webserver, jak zatížený je stroj, na kterém váš SQL server běží a tak dále. Pointa je, že pokud je spojovací režim vysoký, trvalá spojení vám znatelně pomohou. Umožní dětskému procesu připojit se pouze jednou za celý jeho životní cyklus místo každého zpracování stránky, která vyžaduje spojení s SQL serverem. To znamená, že každé dítě, které otevřelo trvalé spojení, bude mít otevřené vlastní trvalé spojení se serverem. Pokud například máte 20 dětských procesů, které spustily skript, který otevřel trvalé spojení s vaším SQL serverem, máte 20 nezávislých spojení s SQL serverem, po jednom z každého dítěte.

Všimněte si nicméně, že to může mít nevýhody, pokud používáte databázi s omezeným počtem připojení, který trvalá spojení dětí překročí. Pokud má vaše databáze limit 16 současných připojení, a v rušném okamžiku se pokusí připojit 17 dětských procesů, jednomu se to nepodaří. Pokud máte ve svých skriptech chyby, které brání zavírání spojení (např. nekonečné smyčky), databáze s pouhými

32 spojeními bude brzy zaplavena. Vyhledejte si v dokumentaci vaší databáze informace o obsluze opuštěných nebo nečinných spojení.

Důležitý souhrn. Trvalá spojení byla navržena tak, aby odpovídala jedna k jedné normálním spojení. To znamená, že byste *vždy* měli být schopni nahradit trvalá spojení netrvalými beze změny fungování vašeho skriptu. *Může* to (a pravděpodobně bude) mít vliv na efektivitu tohoto skriptu, ale ne jeho chování!

Kapitola 23. Bezpečný režim

Bezpečný režim PHP je pokus o řešení bezpečnosti sdílených serverů. Je architekturně nekorektní pokoušet se řešit tento problém na úrovni PHP, ale protože řešení na úrovni webovského serveru a operačního systému nejsou příliš realistická, mnoho lidí, zvláště ISP, používá nyní bezpečný režim.

Konfigurační direktivy, které ovládají bezpečný režim:

```
safe_mode = Off
open_basedir =
safe_mode_exec_dir =
safe_mode_allowed_env_vars = PHP_
safe_mode_protected_env_vars = LD_LIBRARY_PATH
disable_functions =
```

Pokud je `safe_mode` zapnutý, PHP kontroluje, je-li vlastník běžícího skriptu vlastníkem souboru, s nímž se má manipulovat. Například:

```
-rw-rw-r-- 1 rasmus rasmus 33 Jul 1 19:20 script.php
-rw-r--r-- 1 root root 1116 May 26 18:01 /etc/passwd
```

Spuštění skriptu `script.php`

```
<?php
    readfile('/etc/passwd');
?>
```

bude mít v bezpečném režimu za výsledek tuto chybu:

```
Warning: SAFE MODE Restriction in effect. The script whose uid is 500 is not
allowed to access /etc/passwd owned by uid 0 in /docroot/script.php on line 2
```

Pokud namísto `safe_mode` nastavíte adresář `open_basedir`, potom všechny operace se soubory budou omezeny pod specifikovaný adresář. Například (příklad Apache `httpd.conf`):

```
<Directory /docroot>
    php_admin_value open_basedir /docroot
</Directory>
```

Když spustíte tentýž soubor `script.php` s tímto nastavením `open_basedir`, dostanete tento výsledek:

Warning: open_basedir restriction in effect. File is in wrong directory in /docroot/script.php on line 2

Můžete také vypnout jednotlivé funkce. Pokud přidáme toto do souboru php.ini:

```
disable_functions readfile,system
```

získáme takovýto výstup:

Warning: readfile() has been disabled for security reasons in /docroot/script.php on line 2

Funkce omezené/deaktivované v bezpečném režimu

Toto je pravděpodobně neúplný a možná nesprávný přehled funkcí omezených v bezpečném režimu.

Tabulka 23-1. Funkce omezené v bezpečném režimu

Funkce	Omezení
dbmopen()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
dbase_open()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
filepro()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
filepro_rowcount()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
filepro_retrieve()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
ifx_*	sql_safe_mode restrictions, (!= safe mode)
ingres_*	sql_safe_mode restrictions, (!= safe mode)
mysql_*	sql_safe_mode restrictions, (!= safe mode)
pg_loimport()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
posix_mkfifo()	Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript.

Funkce	Omezení
putenv()	Obeys the <code>safe_mode_protected_env_vars</code> and <code>safe_mode_allowed_env_vars</code> ini-directives. Viz také dokumentaci <code>putenv()</code>
move_uploaded_file()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
chdir()	Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript.
dl()	Tyto funkce jsou v bezpečném režimu (<code>safe-mode</code>) deaktivovány.
backtick operátor	Tyto funkce jsou v bezpečném režimu (<code>safe-mode</code>) deaktivovány.
shell_exec() (funkční ekvivalent backticks)	Tyto funkce jsou v bezpečném režimu (<code>safe-mode</code>) deaktivovány.
exec()	Můžete spouštět programy pouze uvnitř adresáře <code>safe_mode_exec_dir</code> . Z praktických důvodů není momentálně možné mít v cestě k souboru s programem komponenty . . .
system()	Můžete spouštět programy pouze uvnitř adresáře <code>safe_mode_exec_dir</code> . Z praktických důvodů není momentálně možné mít v cestě k souboru s programem komponenty . . .
passthru()	Můžete spouštět programy pouze uvnitř adresáře <code>safe_mode_exec_dir</code> . Z praktických důvodů není momentálně možné mít v cestě k souboru s programem komponenty . . .
popen()	Můžete spouštět programy pouze uvnitř adresáře <code>safe_mode_exec_dir</code> . Z praktických důvodů není momentálně možné mít v cestě k souboru s programem komponenty . . .
mkdir()	Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript.
rmdir()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
rename()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript. Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript.
unlink()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript. Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript.
copy()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript. Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript. (pro <i>source</i> a <i>target</i>)

Funkce	Omezení
chgrp()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
chown()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.
chmod()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript. Navíc nemůžete nastavovat SUID, SGID a sticky bit
touch()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript. Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript.
symlink()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript. Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript. (pozn.: testován je pouze cíl)
link()	Kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript. Kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript. (pozn.: testován je pouze cíl)
getallheaders()	V bezpečném režimu nebudou hlavičky začínající 'authorization' (bez ohledu na velikost písmen) vráceny. Varování: toto nefunguje s aol-server implementací getallheaders()!
Jakékoli funkce které používají php4/main/fopen_wrappers.c	??

Část IV. Reference funkcí

I. Funkce specifické pro Apache

apache_lookup_uri (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Provádí částečný požadavek na zadanou URI a vrací všechno info o ní

```
class apache_lookup_uri ( string filename) \linebreak
```

Tato funkce provádí částečný požadavek na URI. Jde jen tak daleko, aby získala všechny důležité informace o daném zdroji a vrací tyto informace ve třídě. Vlastnosti této třídy jsou:

```
status
the_request
status_line
method
content_type
handler
uri
filename
path_info
args
boundary
no_cache
no_local_copy
allowed
send_bodyct
bytes_sent
byterange
clength
unparsed_uri
mtime
request_time
```

Poznámka: `apache_lookup_uri()` pouze, pokud je PHP nainstalováno jako modul Apache.

apache_note (PHP 3>= 3.0.2, PHP 4 >= 4.0.0)

Získává a nastavuje poznámky požadavku u Apache.

```
string apache_note ( string note_name [, string note_value]) \linebreak
```

`apache_note()` je funkce specifická pro Apache, která získává a nastavuje hodnoty v tabulce poznámek požadavku. Při volání s jedním argumentem vrací současnou hodnotu poznámky `note_name`. Při volání se dvěma argumenty nastavuje hodnotu poznámky `note_name` na `note_value`, a vrací předchozí hodnotu poznámky `note_name`.

ascii2ebcdic (PHP 3>= 3.0.17)

Překládá řetězec z ASCII do EBCDIC

```
int ascii2ebcdic ( string ascii_str) \linebreak
```


ascii2ebcdic() je funkce specifická pro Apache dostupná pouze na operačních systémech založených na EBCDIC (OS/390, BS2000). Překládá (binárně bezpečně) řetězec v ASCII kódování *ascii_str* na jeho ekvivalentní EBCDIC reprezentaci, a vrací výsledek.

Viz také opačnou funkci `ebcdic2ascii()`

ebcdic2ascii (PHP 3 >= 3.0.17)

Překládá řetězec z EBCDIC do ASCII

int **ebcdic2ascii** (string *ebcdic_str*) \linebreak

ebcdic2ascii() je funkce specifická pro Apache dostupná pouze na operačních systémech založených na EBCDIC (OS/390, BS2000). Překládá (binárně bezpečně) řetězec v kódování EBCDIC *ascii_str* na jeho ekvivalentní ASCII reprezentaci, a vrací výsledek.

Viz také opačnou funkci `ascii2ebcdic()`

getallheaders (PHP 3, PHP 4 >= 4.0.0)

Získává všechny hlavičky HTTP požadavku

array **getallheaders** (void) \linebreak

Tato funkce vrací asociativní pole všech HTTP hlaviček v současném požadavku.

Poznámka: Hodnotu běžných CGI proměnných můžete také získat tím, že je přečtete z prostředí, což funguje, ať používáte PHP jako modu Apache nebo ne. Pokud chcete vidět seznam všech systémových proměnných definovaných tímto způsobem, použijte `phpinfo()`.

Příklad 1. `getallheaders()` Example

```
$headers = getallheaders();
while (list ($header, $value) = each ($headers)) {
    echo "$header: $value<br>\n";
}
```

Tento příklad zobrazí všechny hlavičky současného požadavku.

Poznámka: `getallheaders()` je v současnosti podporována jen když PHP běží jako modul Apache.

virtual (PHP 3, PHP 4 >= 4.0.0)

Provádí sub-požadavek Apache

int **virtual** (string filename) \linebreak

virtual() je funkce specifická pro Apache ekvivalentní s `<!--#include virtual...-->` v `mod_include`. Provádí sub-požadavek Apache. Je užitečná pro vkládání CGI skriptů nebo .shtml souborů, nebo čehokoliv jiného, co má Apache parsovat. CGI skripty musí generovat platné CGI hlavičky. To znamená, že musí přinejmenším generovat Content-type hlavičku. Pro PHP soubory musíte použít `include()` nebo `require()`; **virtual()** se nedá použít k vložení dokumentu, který je sám PHP skriptem.

II. Funkce pro práci s poli

Tyto funkce vám umožňují manipulovat a interagovat různými způsoby s poli. Pole jsou nezbytná pro ukládání a práci se sadami proměnných.

Podporována jsou jednoduchá a vícerozměrná pole; vytvářet se dají uživatelsky i jako výstup funkce. Existují databázové funkce na plnění polí výsledky databázových dotazů, a několik dalších funkcí vrací pole.

Viz také: `is_array()`, `explode()`, `implode()`, `split()` a `join()`.

array (unknown)

Vytvořit pole

array **array** ([mixed ...]) \linebreak

Vrací pole argumentů. Argumentům může být přiřazen index pomocí operátoru =>.

Poznámka: **array()** je jazykový konstrukt používaný k reprezentaci polí, nikoliv běžná funkce.

Syntaxe "index => hodnota", s čárko jako oddělovačem, definuje indexy a hodnoty. Index může být řetězec nebo číslo. Pokud se index vynechá, automaticky se generuje číselný index začínající na 0. Pokud je index integer, další generovaný index bude nejvyšší celočíselný index + 1. Pozn.: pokud jsou definovány dva identické indexy, první se přepíše posledním.

Následující ukázka demonstruje jak vytvořit dvourozměrné pole, jak určit klíče v asociativních polích, a jak přeskokovat číselné indexy v normálních polích.

Příklad 1. Ukázka array()

```
$fruits = array (
    "fruits" => array ( "a"=>"orange", "b"=>"banana", "c"=>"apple" ),
    "numbers" => array ( 1, 2, 3, 4, 5, 6 ),
    "holes"   => array ( "first", 5 => "second", "third" )
);
```

Příklad 2. Automatický index a array()

```
$array = array( 1, 1, 1, 1, 1, 8=>1, 4=>1, 19, 3=>13);
print_r($array);
```

výstup bude následující:

```
Array
(
    [0] => 1
    [1] => 1
    [2] => 1
    [3] => 13
    [4] => 1
    [8] => 1
    [9] => 19
)
```

Index 3 je definován dvakrát, a podrží si poslední hodnotu 13. Index 4 je definován po indexu 8 a další generovaný index (hodnota 19) je 9, protože nejvyšší index byl 8.

Tato ukázka vytvoří pole číselné od 1.

Příklad 3. Index začínající 1 s array()

```
$firstquarter = array(1 => 'January', 'February', 'March');
print_r($firstquarter);
```

toto bude výstup:

```
Array
(
    [1] => 'January'
    [2] => 'February'
    [3] => 'March'
)
```

Viz také: list().

array_count_values (PHP 4 >= 4.0.0)

Spočítat všechny hodnoty v poli

array **array_count_values** (array input) \linebreak

array_count_values() vrací pole používající hodnoty z *input* jako klíče a jejich četnosti v *input* jako hodnoty.

Příklad 1. Ukázka array_count_values()

```
$array = array (1, "hello", 1, "world", "hello");
array_count_values ($array); // vrací array(1=>2, "hello"=>2, "world"=>1)
```

array_diff (PHP 4)

Spočítat rozdíl polí

array **array_diff** (array array1, array array2 [, array ...]) \linebreak

array_diff() vrací pole obsahující všechny hodnoty z *array1*, které se nevyskytují v žádném z dalších argumentů. Klíče jsou zachovány.

Příklad 1. Ukázka array_diff()

```
$array1 = array ("a" => "green", "red", "blue");
$array2 = array ("b" => "green", "yellow", "red");
$result = array_diff ($array1, $array2);
```

\$result obsahuje array ("blue");

Viz také: array_intersect().

array_flip (PHP 4 >= 4.0.0)

Prohodit klíče a hodnoty pole

array **array_flip** (array trans) \linebreak

array_flip() pole s prohozenými klíči a hodnotami.

Příklad 1. Ukázka array_flip()

```
$trans = array_flip ($strans);
$original = strtr ($str, $trans);
```

array_intersect (PHP 4)

Spočítat průnik polí

array **array_intersect** (array array1, array array2 [, array ...]) \linebreak

array_intersect() vrací pole obsahující všechny hodnoty z *array1*, které se vyskytují ve všech argumentech. Klíče jsou zachovány.

Příklad 1. Ukázka array_intersect()

```
$array1 = array ("a" => "green", "red", "blue");
$array2 = array ("b" => "green", "yellow", "red");
$result = array_intersect ($array1, $array2);
```

\$result obsahuje array ("a" => "green", "red");

Viz také: array_diff().

array_keys (PHP 4 >= 4.0.0)

Vrátit všechny klíče pole

array **array_keys** (array input [, mixed search_value]) \linebreak

array_keys() vrací klíče, numerické i textové, z pole *input*.

Pokud je přítomen volitelný argument *search_value*, vrací pouze klíče této hodnoty. Jinak vrací všechny klíče z pole *input*.

Příklad 1. Ukázka array_keys()

```
$array = array (0 => 100, "color" => "red");
array_keys ($array);          // vrací array (0, "color")
```

```
$array = array ("blue", "red", "green", "blue", "blue");
array_keys ($array, "blue");  // vrací array (0, 3, 4)
```

```
$array = array ("color" => array("blue", "red", "green"), "size" => array("small", "medium"));
array_keys ($array);          // vrací array ("color", "size")
```

Poznámka: Tato funkce byla přidána v PHP 4, dále je uvedena implementace pro ty, kteří stále používají PHP 3.

Příklad 2. Implementace array_keys() pro uživatele PHP 3

```
function array_keys ($arr, $term="") {
    $t = array();
    while (list($k,$v) = each($arr)) {
        if ($term && $v != $term)
            continue;
        $t[] = $k;
    }
    return $t;
}
```

Viz také: array_values().

array_merge (PHP 4 >= 4.0.0)

Sloučit dvě nebo více polí

array **array_merge** (array array1, array array2 [, array ...]) \linebreak

array_merge() sloučí prvky dvou nebo více polí dohromady tak, že hodnoty každého pole se připojí na konec předchozího. Vrací výsledné pole.

Pokud mají vstupní pole stejný textový klíč, pozdější hodnota přepíše dřívější hodnotu. Pokud ale mají stejný číselný klíč, pozdější hodnota tu původní nepřepíše, ale připojí se k ní.

Příklad 1. Ukázka `array_merge()`

```
$array1 = array ("color" => "red", 2, 4);
$array2 = array ("a", "b", "color" => "green", "shape" => "trapezoid", 4);
array_merge ($array1, $array2);
```

Výsledné pole bude `array("color" => "green", 2, 4, "a", "b", "shape" => "trapezoid", 4)`.

Viz také: `array_merge_recursive()`.

`array_merge_recursive` (PHP 4)

Rekurzivně sloučit dvě nebo více polí

`array array_merge_recursive (array array1, array array2 [, array ...])` \linebreak

`array_merge_recursive()` sloučí prvky dvou nebo více polí tak, že hodnoty pole se připojí na konec předchozího pole. Vrací výsledné pole.

Pokud obsahují vstupní pole stejný textový klíč, hodnoty těchto klíčů se rekurzivně sloučí do pole tak, že pokud je jedna z hodnot sama pole, tato funkce ji také sloučí s odpovídající položkou z dalšího pole. Pokud ale tato pole mají stejný číselný klíč, pozdější hodnota nepřepíše tu dřívější, ale připojí se.

Příklad 1. Ukázka `array_merge_recursive()`

```
$ar1 = array ("color" => array ("favorite" => "red"), 5);
$ar2 = array (10, "color" => array ("favorite" => "green", "blue"));
$result = array_merge_recursive ($ar1, $ar2);
```

Výsledné pole bude `array ("color" => array ("favorite" => array ("red", "green"), "blue"), 5, 10)`.

Viz také: `array_merge()`.

`array_multisort` (PHP 4 >= 4.0.0)

Třídí více polí, nebo vícerozměrné pole

`bool array_multisort (array ar1 [, mixed arg [, mixed ... [, array ...]])` \linebreak

array_multisort() se dá využít k třídění několika polí najednou nebo k třídění vícerozměrného pole XXX according by one of more dimensions. Při třídění udržuje asociace klíčů.

Vstupní pole jsou manipulována jako sloupce tabulky, která se má třídit podle řádků - připomíná to funkcionality SQL klauzule ORDER BY. První pole je to, podle kterého se bude třídit. Řádky (hodnoty) v tomto poli that compare the same are sorted by the next input array, and so on.

Struktura argumentů této funkce je trochu neobvyklá, ale pružná. První argument musí být pole. Každý další argument může být buď pole nebo jeden z příznaků z následujících seznamů:

Příznaky směru třídění:

- SORT_ASC - třídit vzestupně
- SORT_DESC - třídit sestupně

Příznaky typu třídění:

- SORT_REGULAR - porovnávat položky normálně
- SORT_NUMERIC - porovnávat položky číselně
- SORT_STRING - porovnávat položky jako řetězce

Po každém poli můžete specifikovat jeden příznak každého typu. Příznaky třídění specifikované po každém poli platí pouze pro toto pole - pro další pole se resetují na defaultní SORT_ASC a SORT_REGULAR.

Při úspěchu vrací TRUE, při selhání FALSE.

Příklad 1. Třídění více polí

```
$ar1 = array ("10", 100, 100, "a");
$ar2 = array (1, 3, "2", 1);
array_multisort ($ar1, $ar2);
```

V této ukázce bude po setřídění první pole obsahovat 10, "a", 100, 100. Druhé pole bude obsahovat 1, 1, 2, "3". Položky druhého pole odpovídající identickým položkám v prvním poli (100 a 100) byly také setříděny.

Příklad 2. Třídění vícerozměrného pole

```
$ar = array (array ("10", 100, 100, "a"), array (1, 3, "2", 1));
array_multisort ($ar[0], SORT_ASC, SORT_STRING,
                 $ar[1], SORT_NUMERIC, SORT_DESC);
```

V této ukázce bude po setřídění první pole obsahovat 10, 100, 100, "a" (bylo tříděno vzestupně jako řetězce) a druhé pole bude obsahovat 1, 3, "2", 1 (tříděno jako čísla, sestupně).

array_pad (PHP 4 >= 4.0.0)

Doplnit pole hodnotou na určenou délku

array **array_pad** (array input, int pad_size, mixed pad_value) \linebreak

array_pad() vrací kopii pole *input* doplněnou na velikost *pad_size* hodnotou *pad_value*. Pokud je *pad_size* kladná, pole je doplněno zprava, pokud je negativní, zleva. Pokud je absolutní hodnota *pad_size* menší nebo rovna velikosti *input*, k doplnění nedojde.

Příklad 1. Ukázka array_pad()

```
$input = array (12, 10, 9);

$result = array_pad ($input, 5, 0);
// výsledek je array (12, 10, 9, 0, 0)

$result = array_pad ($input, -7, -1);
// výsledek je array (-1, -1, -1, -1, 12, 10, 9)

$result = array_pad ($input, 2, "noop");
// nedoplněno
```

array_pop (PHP 4 >= 4.0.0)

Odstranit prvek z konce pole

mixed **array_pop** (array array) \linebreak

array_pop() odstraní a vrátí poslední hodnotu pole *array*, čímž ho zkrátí o jeden prvek.

Příklad 1. Ukázka array_pop()

```
$stack = array ("orange", "apple", "raspberry");
$fruit = array_pop ($stack);
```

\$stack má teď pouze dva prvky: "orange" a "apple", a *\$fruit* obsahuje "raspberry".

Viz také: `array_push()`, `array_shift()` a `array_unshift()`.

array_push (PHP 4 >= 4.0.0)

Přidat jeden nebo více prvků na konec pole

int **array_push** (array array, mixed var [, mixed ...]) \linebreak

array_push() připojuje předané proměnné na konec *array*. Délka *array* se zvětšuje o počet přidaných proměnných. Účinek je stejný jako:

```
$array[] = $var;
```

opakované pro každou *var*.

Vrací nový počet prvků v poli.

Příklad 1. Ukázka array_push()

```
$stack = array (1, 2);  
array_push ($stack, "+", 3);
```

Výsledkem této ukázky by byl *\$stack* obsahující 4 prvky: 1, 2, "+" a 3.

Viz také: *array_pop()*, *array_shift()* a *array_unshift()*.

array_rand (PHP 4 >= 4.0.0)

Vybrat náhodně jeden nebo více prvků pole

mixed **array_rand** (array input [, int num_req]) \linebreak

array_rand() je poměrně užitečná, když chcete z pole vybrat náhodně jednu nebo více hodnot. Přijímá pole *input* a volitelný argument *num_req*, který určuje, kolik položek chcete. Jeho defaultní hodnota je 1.

Pokud vybíráte pouze jednu položku, **array_rand()** vrací klíč náhodné položky. Jinak vrací pole klíčů náhodně vybraných položek. Takto můžete vybírat náhodně hodnoty i klíče.

Nezapomeňte inicializovat generátor náhodných čísel pomocí *srand()*.

Příklad 1. Ukázka array_rand()

```
srand ((double) microtime() * 10000000);  
$input = array ("Neo", "Morpheus", "Trinity", "Cypher", "Tank");  
$rand_keys = array_rand ($input, 2);  
print $input[$rand_keys[0]]."\n";  
print $input[$rand_keys[1]]."\n";
```

array_reverse (PHP 4 >= 4.0.0)

Vrátit pole s prvky v opačném pořadí

array **array_reverse** (array array [, bool preserve_keys]) \linebreak

array_reverse() takes input *array* and returns a new array with the order of the elements reversed, preserving the keys if *preserve_keys* is TRUE.

Příklad 1. array_reverse() example

```
$input = array ("php", 4.0, array ("green", "red"));
$result = array_reverse ($input);
$result_keyed = array_reverse ($input, true);
```

\$result teď obsahuje array (array ("green", "red"), 4.0, "php"). Ale \$result2[0] je stále "php".

Poznámka: Druhý argument byl přidán v PHP 4.0.3.

array_shift (PHP 4 >= 4.0.0)

Odstranit prvek ze začátku pole

mixed **array_shift** (array array) \linebreak

array_shift() vrací první položku *array* a odstraní ji, čímž zkrátí *array* o jeden prvek a ostatní posune dolů.

Příklad 1. Ukázka array_shift()

```
$args = array ("-v", "-f");
$opt = array_shift ($args);
```

\$args teď má jeden prvek: "-f" a \$opt je "-v".

Viz také: array_unshift(), array_push() a array_pop().

array_slice (PHP 4 >= 4.0.0)

Vytáhnout část pole

array **array_slice** (array array, int offset [, int length]) \linebreak

array_slice() vrací sekvenci prvků *array* určených argumenty *offset* a *length*.

Pokud je *offset* kladný, tato sekvence začne *offset* položek od začátku *array*. Pokud je *offset* záporný, tato sekvence začne tolik položek od konce *array*.

Pokud je *length* kladná, tato sekvence bude obsahovat tolik prvků. Pokud je *length* záporná, tato sekvence skončí tolik prvků od konce *array*. Pokud *length* vynecháte, tato sekvence bude obsahovat všechny prvky *array* od *offset* do konce.

Příklad 1. Ukázka `array_slice()`

```
$input = array ("a", "b", "c", "d", "e");

$output = array_slice ($input, 2);           // returns "c", "d", and "e"
$output = array_slice ($input, 2, -1);       // returns "c", "d"
$output = array_slice ($input, -2, 1);       // returns "d"
$output = array_slice ($input, 0, 3);        // returns "a", "b", and "c"
```

Viz také: `array_splice()`.

`array_splice` (PHP 4 >= 4.0.0)

Odstranit část pole a nahradit ji něčím jiným

`array array_splice (array input, int offset [, int length [, array replacement]])` \linebreak

`array_splice()` odstraňuje prvky pole *input* určené argumenty *offset* a *length*, a případně je nahrazuje prvky volitelného argumentu (pole) *replacement*.

Pokud je *offset* kladný, tato odstraněná část začne *offset* položek od začátku *array*. Pokud je *offset* záporný, začne tolik položek od konce *array*.

Pokud vynecháte *length*, **`array_splice()`** odstraní všechno od *offset* do konce pole. Pokud je *length* kladná, odstraní se právě tolik prvků. Pokud je *length* záporná, konec odstraněné části bude právě tolik prvků od konce pole. Tip: k odstranění všech prvků od *offset* do konce pole při současně určeném argumentu *replacement* použijte jako *length* `count($input)`.

Pokud zadáte *replacement* pole, odstraněné prvky se nahradí prvky tohoto pole. Pokud argumenty *offset* a *length* definovány tak, že se nic neodstraní, prvky pole *replacement* se vloží na místo určené argumentem *offset*. Tip: pokud je *replacement* jen jedna hodnota, není nutno ji umístit do `array()`, ledaže chcete, aby tato položka byla opravdu pole.

Následující volání jsou ekvivalentní:

<code>array_push (\$input, \$x, \$y)</code>	<code>array_splice (\$input, count (\$input), 0,</code> <code>array (\$x, \$y))</code>
<code>array_pop (\$input)</code>	<code>array_splice (\$input, -1)</code>
<code>array_shift (\$input)</code>	<code>array_splice (\$input, 0, 1)</code>
<code>array_unshift (\$input, \$x, \$y)</code>	<code>array_splice (\$input, 0, 0, array (\$x, \$y))</code>
<code>\$a[\$x] = \$y</code>	<code>array_splice (\$input, \$x, 1, \$y)</code>

Vrací pole odstraněných prvků.

Příklad 1. Ukázky array_splice()

```

$input = array ("red", "green", "blue", "yellow");

array_splice ($input, 2);          // $input is now array ("red", "green")
array_splice ($input, 1, -1);      // $input is now array ("red", "yellow")
array_splice ($input, 1, count($input), "orange");
                                   // $input is now array ("red", "orange")
array_splice ($input, -1, 1, array("black", "maroon"));
                                   // $input is now array ("red", "green",
                                   //                       "blue", "black", "maroon")

```

Viz také: array_slice().

array_unique (PHP 4)

Odstranit z pole duplicitní hodnoty

array array_unique (array array) \linebreak

array_unique() přijímá pole *array* a vrací nové pole bez duplicitních hodnot. Klíče jsou zachovány.

Příklad 1. Ukázka array_unique()

```

$input = array ("a" => "green", "red", "b" => "green", "blue", "red");
$result = array_unique ($input);

```

\$result teď obsahuje array ("a" => "green", "red", "blue");.

array_unshift (PHP 4 >= 4.0.0)

Připojit jeden nebo více prvků na začátek pole

int array_unshift (array array, mixed var [, mixed ...]) \linebreak

array_unshift() připojí předané prvky na začátek *array*. Všechny prvky jsou přidány jako celek, čili přidané prvky si zachovávají pořadí.

vrací nový počet prvků v *array*.

Příklad 1. Ukázka array_unshift()

```

$queue = array ("p1", "p3");
array_unshift ($queue, "p4", "p5", "p6");

```

`$queue` bude mít 5 prvků: "p4", "p5", "p6", "p1" a "p3".

Viz také: `array_shift()`, `array_push()` a `array_pop()`.

array_values (PHP 4 >= 4.0.0)

Vrátit všechny hodnoty v poli

array array_values (array input) \linebreak

array_values() vrací všechny hodnoty pole *input*.

Příklad 1. Ukázka array_values()

```
$array = array ("size" => "XL", "color" => "gold");
array_values ($array);    // vrátí array ("XL", "gold")
```

Poznámka: Tato funkce byla přidána v PHP 4, následuje implementace pro ty, kdo stále používají PHP 3.

Příklad 2. Implementace array_values() pro uživatele PHP 3

```
function array_values ($arr) {
    $t = array();
    while (list($k, $v) = each ($arr)) {
        $t[] = $v;
    }
    return $t;
}
```

array_walk (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Použít uživatelskou funkci na všechny prvky pole

int array_walk (array arr, string func, mixed userdata) \linebreak

Aplikuje funkci *func* na všechny prvky pole *arr*. Funkci *func* se jako první argument předá hodnota a jako druhý klíč. Pokud je přítomen argument *userdata*, bude uživatelské funkci předán jako třetí argument.

Pokud *func* vyžaduje více než dva nebo tři argumenty (v závislosti na *userdata*), pro každé volání *func* z **array_walk()** se vygeneruje varování. Tato varování se dají potlačit přidáním znaku '@' před volání **array_walk()** nebo pomocí `error_reporting()`.

Poznámka: Pokud *func* potřebuje pracovat přímo s daným polem, první argument *func* se musí předávat odkazem. Všechny změny těchto hodnot se pak promítnou přímo v *arr*.

Poznámka: Druhý a třetí argument *func* byly přidány v PHP 4.0.

V PHP 4 je třeba volat podle potřeby `reset()`, protože **`array_walk()`** sama vstupní pole neresetuje.

Příklad 1. Ukázka `array_walk()`

```
$fruits = array ("d"=>"lemon", "a"=>"orange", "b"=>"banana", "c"=>"apple");

function test_alter (&$item1, $key, $prefix) {
    $item1 = "$prefix: $item1";
}

function test_print ($item2, $key) {
    echo "$key. $item2<br>\n";
}

array_walk ($fruits, 'test_print');
reset ($fruits);
array_walk ($fruits, 'test_alter', 'fruit');
reset ($fruits);
array_walk ($fruits, 'test_print');
```

Viz také: `each()` a `list()`.

arsort (PHP 3, PHP 4 >= 4.0.0)

Třídí pole sestupně se zachováním klíčů

void **arsort** (array array [, int sort_flags]) \linebreak

arsort() třídí pole tak, že indexy pole si zachovávají korelace s prvky, se kterými jsou asociovány. Toto je užitečné hlavně při třídění asociativních polí, kde je pořadí prvků signifikantní.

Příklad 1. Ukázka `arsort()`

```
$fruits = array ("d"=>"lemon", "a"=>"orange", "b"=>"banana", "c"=>"apple");
arsort ($fruits);
reset ($fruits);
while (list ($key, $val) = each ($fruits)) {
    echo "$key = $val\n";
}
```


Tato ukázka zobrazí:

```
fruits[a] = orange
fruits[d] = lemon
fruits[b] = banana
fruits[c] = apple
```

Ovoce bylo sestupně seříděno podle abecedy, a indexy asociované s jednotlivými prvky byly zachovány.

Chování třídění můžete upravit pomocí volitelného argumentu *sort_flags*, detaily viz `sort()`.

Viz také: `asort()`, `rsort()`, `ksort()` a `sort()`.

asort (PHP 3, PHP 4 >= 4.0.0)

Třídí pole se zachováním indexů

```
void asort ( array array [, int sort_flags]) \linebreak
```

asort() třídí pole tak, že si indexy zachovají corelace s prvky, se kterými jsou spojeny. To je užitečné hlavně při třídění asociativních polí, u kterých je pořadí prvků signifikantní.

Příklad 1. Ukázka asort()

```
$fruits = array ("d"=>"lemon", "a"=>"orange", "b"=>"banana", "c"=>"apple");
asort ($fruits);
reset ($fruits);
while (list ($key, $val) = each ($fruits)) {
    echo "$key = $val\n";
}
```

Tato ukázka zobrazí:

```
fruits[c] = apple
fruits[b] = banana
fruits[d] = lemon
fruits[a] = orange
```

Ovoce bylo seříděno podle abecedy a indexy spojené s jednotlivými prvky byly zachovány.

Chování třídění můžete upravit pomocí volitelného argumentu *sort_flags*, detaily viz `sort()`.

Viz také: `arsort()`, `rsort()`, `ksort()` a `sort()`.

compact (PHP 4 >= 4.0.0)

Vytvořit pole obsahující proměnné a jejich hodnoty

array **compact** (mixed varname [, mixed ...]) \linebreak

compact() přijímá proměnný počet argumentů. Každý argument může být buď řetězec obsahující název proměnné nebo pole názvů proměnných. Toto pole může také obsahovat pole názvů proměnných; **compact()** je rekurzivně zpracuje.

Pro každý z řetězců **compact()** vyhledá v aktivní symbolové tabulce proměnnou tohoto jména a přidá ji do výsledného pole tak, že název této proměnné se stane klíčem a obsah této proměnné hodnotou tohoto klíče. Stručně řečeno, dělá pravý opak toho, co **extract()**. Vrací pole obsahující všechny tyto proměnné.

Řetězce, které neobsahují názvy platných proměnných se přeskočí.

Příklad 1. Ukázka compact()

```
$city = "San Francisco";
$state = "CA";
$event = "SIGGRAPH";

$location_vars = array ("city", "state");

$result = compact ("event", "nothing_here", $location_vars);

$result bude array ("event" => "SIGGRAPH", "city" => "San Francisco",
"state" => "CA").
```

Viz také: **extract()**.

count (PHP 3, PHP 4 >= 4.0.0)

Spočítat prvky v proměnné

int **count** (mixed var) \linebreak

Vrací počet prvků v *var*, která je typicky pole (jelikož všechno ostatní má jeden prvek).

Vrací 1, pokud *var* není pole.

Vrací 0, pokud *var* není inicializována.

Varování

count() vrací 0 pro proměnné, které nejsou inicializovány, ale vrací také 0 pro proměnné, které obsahují prázdné pole. Pokud potřebujete zjistit, jestli dotyčná proměnná existuje, použijte **isset()**.

Příklad 1. Ukázka count()

```
$a[0] = 1;
$a[1] = 3;
$a[2] = 5;
$result = count ($a);
// $result == 3
```

Viz také: `sizeof()`, `isset()` a `is_array()`.

current (PHP 3, PHP 4 >= 4.0.0)

Vrátit současný prvek pole

mixed **current** (array array) \linebreak

Každé pole má vnitřní ukazatel na jeho "současný" prvek, který se inicializuje na první prvek vložený do tohoto pole.

current() vrací prvek, na který tento interní ukazatel právě ukazuje. Nijak tento ukazatel nemění. Pokud tento vnitřní ukazatel ukazuje za konec seznamu prvků, **current()** returns `FALSE`.

Varování

Pokud toto pole obsahuje prázdné prvky (0 nebo "", prázdný řetězec), tato funkce pro tyto prvky také vrátí `FALSE`. Je proto nemožné určit pomocí **current()**, jestli jste opravdu na konci pole. To properly traverse an array that may contain empty elements, use the `each()` function.

Viz také: `end()`, `next()`, `prev()` a `reset()`.

each (PHP 3, PHP 4 >= 4.0.0)

Vrací další klíč/hodnota pár z pole

array **each** (array array) \linebreak

Vrací současný klíč/hodnota pár z pole `array` a posune interní ukazatel pole. Tento pár se vrací jako pole čtyř prvků s klíči `0`, `1`, `key` a `value`. Prvky `0` a `key` obsahují název klíče tohoto prvku pole a `1` a `value` obsahují hodnotu.

Pokud interní ukazatel pole ukazuje za konec tohoto pole, **each()** vrací `FALSE`.

Příklad 1. Ukázky each()

```
$foo = array ("bob", "fred", "jussi", "jouni", "egon", "marliese");
$bar = each ($foo);
```

`$bar` teď obsahuje následující klíč/hodnota páry:

- 0 => 0
- 1 => 'bob'
- key => 0
- value => 'bob'

```
$foo = array ( "Robert" => "Bob", "Seppo" => "Sepi" );
$bar = each ( $foo );
```

`$bar` teď obsahuje následující klíč/hodnota páry:

- 0 => 'Robert'
- 1 => 'Bob'
- key => 'Robert'
- value => 'Bob'

each() se většinou používá s **list()** k průchodu polem, např. `$HTTP_POST_VARS`:

Příklad 2. Průchod `$HTTP_POST_VARS` pomocí `each()`

```
echo "Hodnoty odeslané metodou POST:<br>";
reset ( $HTTP_POST_VARS );
while ( list ( $key, $val ) = each ( $HTTP_POST_VARS ) ) {
    echo "$key => $val<br>";
}
```

Poté, co proběhne **each()**, se interní ukazatel pole posune na další prvek pole nebo zůstane na posledním prvku pole, pokud dojde na konec.

Viz také: **key()**, **list()**, **current()**, **reset()**, **next()** a **prev()**.

end (PHP 3, PHP 4 >= 4.0.0)

Nastavit vnitřní ukazatel pole na jeho poslední prvek

mixed end (array array) \linebreak

end() posune vnitřní ukazatel pole *array* na jeho poslední prvek a vrátí tento prvek.

Viz také: **current()**, **each()**, **end()**, **next()** a **reset()**.

extract (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Importovat proměnné z pole do symbolové tabulky

```
int extract ( array var_array [, int extract_type [, string prefix]]) \linebreak
```

Tato funkce se používá k importu proměnných z pole do aktivní symbolové tabulky. Přijímá pole *var_array*; z klíčů vytváří názvy proměnných a z hodnot hodnoty těchto proměnných. Vytváří jednu proměnnou z každého klíč/hodnota páru (s ohledem na argumenty *extract_type* a *prefix*).

Poznámka: Od PHP 4.0.5 tato funkce vrací počet extrahovaných proměnných.

extract() ověřuje, jestli všechny klíče tvoří platné názvy proměnných, a také jestli nekolidují s proměnnými existujícími v aktivní symbolové tabulce. Způsob, jakým se nakládá s neplatnými/numerickými klíči a kolizemi závisí na *extract_type*. Ten může mít jednu z následujících hodnot.

EXTR_OVERWRITE

Pokud existuje kolize, přepsat existující proměnnou.

EXTR_SKIP

Pokud existuje kolize, nepřepsat existující proměnnou.

EXTR_PREFIX_SAME

Pokud existuje kolize, předřadit před název nové proměnné *prefix*.

EXTR_PREFIX_ALL

Opatřit prefixem *prefix* všechny názvy proměnných. Od PHP 4.0.5 toto zahrnuje i číselné indexy.

EXTR_PREFIX_INVALID

Prefixem *prefix* opatřit pouze neplatné/číselné názvy proměnných. Tento příznak byl přidán v PHP 4.0.5.

Defaultní *extract_type* je EXTR_OVERWRITE.

Pozn.: *prefix* se vyžaduje pouze pokud je *extract_type* EXTR_PREFIX_SAME, EXTR_PREFIX_ALL nebo EXTR_PREFIX_INVALID. Pokud výsledný název (vč. prefixu) není platný název proměnné, nenaimportuje se do symbolové tabulky.

extract() vrací počet proměnných úspěšně naimportovaných do symbolové tabulky.

Možné využití **extract()** je import proměnných do symbolové tabulky z asociativního pole vráceného `wddx_deserialize()`.

Příklad 1. Ukázka extract()

```
<?php
```

```

/* Předpokládejme, že $var_array je pole vrácené
   z wddx_deserialize */

$size = "large";
$var_array = array ("color" => "blue",
                   "size"   => "medium",
                   "shape"  => "sphere");
extract ($var_array, EXTR_PREFIX_SAME, "wddx");

print "$color, $size, $shape, $wddx_size\n";

?>

```

Výše uvedená ukázka vytiskne:

```
blue, large, sphere, medium
```

\$size se nepřepsala, protože bylo specifikováno EXTR_PREFIX_SAME, tudíž se vytvořila proměnná \$wddx_size. Pokud by bylo zadáno EXTR_SKIP, nevytvořila by se ani \$wddx_size. EXTR_OVERWRITE by způsobilo přepsání hodnoty \$size na "medium", a EXTR_PREFIX_ALL by vytvořilo nové proměnné pojmenované \$wddx_color, \$wddx_size a \$wddx_shape.

U PHP verzí nižších než 4.0.5 musíte použít asociativní pole.

Viz také: compact().

in_array (PHP 4 >= 4.0.0)

Vrátit TRUE, pokud v poli existuje daná hodnota

bool **in_array** (mixed needle, array haystack, bool strict) \linebreak

Hledá v *haystack* *needle* a pokud ji najde, vrací TRUE, jinak FALSE.

Pokud je třetí argument *strict* TRUE, **in_array()** také kontroluje typ *needle* v *haystack*.

Příklad 1. Ukázka in_array()

```

$os = array ("Mac", "NT", "Irix", "Linux");
if (in_array ("Irix", $os)){
    print "Got Irix";
}

```

Příklad 2. Ukázka `in_array()` s argumentem *strict*

```
// Výstup bude:

1.13 found with strict check
```

key (PHP 3, PHP 4 >= 4.0.0)

Fetch a key from an associative array

mixed **key** (array array) \linebreak

key() vrací index současného prvku pole.

Viz také: `current()` a `next()`.

krsort (PHP 3 >= 3.0.13, PHP 4 >= 4.0.0)

Třídí pole sestupně podle klíčů

int **krsort** (array array [, int sort_flags]) \linebreak

Třídí pole sestupně podle klíčů se zachováním asociací indexů. To je užitečné hlavně při práci s asociativními poli.

Příklad 1. krsort() example

```
$fruits = array ("d"=>"lemon", "a"=>"orange", "b"=>"banana", "c"=>"apple");
krsort ($fruits);
reset ($fruits);
while (list ($key, $val) = each ($fruits)) {
    echo "$key -> $val\n";
}
```

Tato ukázka vytiskne:

```
fruits[d] = lemon
fruits[c] = apple
fruits[b] = banana
fruits[a] = orange
```

Vlastnosti třídění lze upravit pomocí volitelného argumentu *sort_flags*, detaily viz `sort()`.

Viz také: `asort()`, `arsort()`, `ksort()`, `sort()`, `natsort()` a `rsort()`.

ksort (PHP 3, PHP 4 >= 4.0.0)

Třídí pole podle klíčů

int ksort (array array [, int sort_flags]) \linebreak

Třídí pole podle klíčů se zachováním asociací indexů. To je užitečné hlavně při práci s asociativními poli.

Příklad 1. ksort() example

```
$fruits = array ("d"=>"lemon", "a"=>"orange", "b"=>"banana", "c"=>"apple");
ksort ($fruits);
reset ($fruits);
while (list ($key, $val) = each ($fruits)) {
    echo "$key -> $val\n";
}
```

Tato ukázka vytiskne:

```
fruits[a] = orange
fruits[b] = banana
fruits[c] = apple
fruits[d] = lemon
```

Vlastnosti třídění lze upravit pomocí volitelného argumentu *sort_flags*, detaily viz `sort()`.

Viz také: `asort()`, `arsort()`, `sort()`, `natsort()` a `rsort()`.

Poznámka: Druhý argument byl přidán v PHP 4.

list (unknown)

Přiřadit hodnoty proměnným jako kdyby byly polem

void list (mixed ...) \linebreak

Stejně jako `array()`, **list()** vlastně není funkce, ale jazykový konstrukt. Používá se k přiřazení hodnot více proměnným v jedné operaci.

Příklad 1. Ukázka list()

```

<table>
  <tr>
    <th>Employee name</th>
    <th>Salary</th>
  </tr>

  <?php

    $result = mysql ($conn, "SELECT id, name, salary FROM employees");
    while (list ($id, $name, $salary) = mysql_fetch_row ($result)) {
      print ( " <tr>\n".
        "   <td><a href=\"info.php3?id=$id\">$name</a></td>\n".
        "   <td>$salary</td>\n".
        " </tr>\n" );
    }

  ?>

</table>

```

Viz také: `each()` a `array()`.

natcasesort (PHP 4 >= 4.0.0)

Třídí pole s využitím algoritmu "přirozeného třídění" (case-insensitive)

`void natcasesort (array array) \linebreak`

Tato funkce implementuje srovnávací algoritmus který třídí alfanumerické řetězce stejným způsobem jako člověk, toto se popisuje jako "přirozené třídění".

natcasesort() je case-insensitive verze `natsort()`. Ukázka rozdílu mezi tímto algoritmem a běžným počítačovým tříděním řetězců viz `natsort()`.

Více informací viz stránka Martina Poola Natural Order String Comparison (<http://naturalordersort.org/>).

Viz také: `sort()`, `natsort()`, `strnatcmp()` and `strnatcasecmp()`.

natsort (PHP 4 >= 4.0.0)

Třídí pole s využitím algoritmu "přirozeného třídění"

`void natsort (array array) \linebreak`

Tato funkce implementuje srovnávací algoritmus který třídí alfanumerické řetězce stejným způsobem jako člověk, toto se popisuje jako "přirozené třídění". Ukázka rozdílu mezi tímto algoritmem a běžnými počítačovými algoritmy pro řazení řetězců (např. `sort()`):

Příklad 1. Ukázka natsort()

```
$array1 = $array2 = array ("img12.png", "img10.png", "img2.png", "img1.png");

sort($array1);
echo "Standardní třídění\n";
print_r($array1);

natsort($array2);
echo "\nPřirozené třídění\n";
print_r($array2);
```

Výše uvedený kód vygeneruje následující výstup:

```
Standardní třídění
Array
(
    [0] => img1.png
    [1] => img10.png
    [2] => img12.png
    [3] => img2.png
)

Přirozené třídění
Array
(
    [3] => img1.png
    [2] => img2.png
    [1] => img10.png
    [0] => img12.png
)
```

Více informací viz stránka Martina Poola Natural Order String Comparison (<http://naturalordersort.org/>).

Viz také: `natcasesort()`, `strnatcmp()` a `strnatcasecmp()`.

next (PHP 3, PHP 4 >= 4.0.0)

Posunout interní ukazatel pole

mixed **next** (array array) \linebreak

Vrací další prvek pole nebo FALSE, pokud prvky došly.

next() se chová jako `current()`, s jedním rozdílem: posouvá interní ukazatel pole o jeden prvek a vrací prvek, na který tento ukazatel ukazuje po posunu. To znamená, že vrací další prvek pole a posouvá interní ukazatel o jeden. Pokud by ukazatel po psunu ukazoval mimo pole, **next()** vrací FALSE.

Varování

Pokud toto pole obsahuje prázdné prvky, nebo prvky, jejichž index je 0, tato funkce vrátí `FALSE` i pro tyto prvky. Ke správnému průchodu polem, které může obsahovat prázdné prvky nebo prvky s indexem 0 použijte `each()`.

Viz také: `current()`, `end()`, `prev()` a `reset()`.

pos (PHP 3, PHP 4 >= 4.0.0)

Získat současný prvek pole

mixed **pos** (array array) \linebreak

Toto je alias k `current()`.

Viz také: `end()`, `next()`, `prev()` a `reset()`.

prev (PHP 3, PHP 4 >= 4.0.0)

Rewind interní ukazatel pole

mixed **prev** (array array) \linebreak

Vrací prvek pole před tím prvkem, na který ukazuje interní ukazatel pole, nebo `FALSE`, pokud prvky došly.

Varování

Pokud toto pole obsahuje prázdné prvky, tato funkce vrátí `FALSE` i pro tyto prvky. Ke správnému průchodu polem, které může obsahovat prázdné prvky použijte `each()`.

prev() se chová stejně jako `next()`, ale posouvá interní ukazatel pole o jedno místo zpátky místo dopředu.

Viz také: `current()`, `end()`, `next()` a `reset()`.

range (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Vytvořit pole obsahující rozsah integerů

array **range** (int low, int high) \linebreak

range() vrací pole integerů od *low* po *high* včetně.

Ukázka použití viz `shuffle()`.

reset (PHP 3, PHP 4 >= 4.0.0)

Nastavit interní ukazatel pole na jeho první prvek

mixed **reset** (array array) \linebreak

reset() přetočí interní ukazatel pole *array* na jeho první prvek.

reset() vrací hodnotu prvního prvku pole.

Viz také: `current()`, `each()`, `next()` a `prev()`.

rsort (PHP 3, PHP 4 >= 4.0.0)

Třídít pole sestupně

void **rsort** (array array [, int sort_flags]) \linebreak

Tato funkce sestupně třídí pole.

Příklad 1. Ukázka rsort()

```
$fruits = array ("lemon", "orange", "banana", "apple");
rsort ($fruits);
reset ($fruits);
while (list ($key, $val) = each ($fruits)) {
    echo "$key -> $val\n";
}
```

Tato ukázka zobrazí:

```
fruits[0] = orange
fruits[1] = lemon
fruits[2] = banana
fruits[3] = apple
```

Ovoce bylo setříděno podle abecedy sestupně.

Vlastnosti třídění lze upravit pomocí volitelného argumentu *sort_flags*, detaily viz `sort()`.

Viz také: `arsort()`, `asort()`, `ksort()`, `sort()` a `usort()`.

shuffle (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Zamíchat pole

void **shuffle** (array array) \linebreak

shuffle() zamíchá (náhodně změni pořadí prvků) pole. Musíte inicializovat generátor náhodných čísel pomocí `srand()`.

Příklad 1. Ukázka `shuffle()`

```
$numbers = range (1,20);
srand ((double)microtime()*1000000);
shuffle ($numbers);
while (list (, $number) = each ($numbers)) {
    echo "$number ";
}
```

Viz také: `arsort()`, `asort()`, `ksort()`, `rsort()`, `sort()` a `usort()`.

sizeof (PHP 3, PHP 4 >= 4.0.0)

Zjistit počet prvků v poli

`int sizeof (array array) \linebreak`

Vrací počet prvků v poli.

Viz také: `count()`.

sort (PHP 3, PHP 4 >= 4.0.0)

Třídí pole

`void sort (array array [, int sort_flags]) \linebreak`

sort() třídí pole. Prvky se uspořádají od nejmenšího k největšímu.

Příklad 1. Ukázka `sort()`

```
<?php

$fruits = array ("lemon", "orange", "banana", "apple");
sort ($fruits);
reset ($fruits);
while (list ($key, $val) = each ($fruits)) {
    echo "fruits[\".$key.\"] = ".$val;
}

?>
```

Tato ukázka zobrazí:

```
fruits[0] = apple
fruits[1] = banana
fruits[2] = lemon
fruits[3] = orange
```

Ovoce bylo seřazeno podle abecedy.

Vlastnosti třídění lze upravit pomocí volitelného argumentu *sort_flags*, který může nabývat těchto hodnot:

Typy třídění:

- SORT_REGULAR - normální porovnávání
- SORT_NUMERIC - numerické porovnávání
- SORT_STRING - textové porovnávání

Viz také: *arsort()*, *asort()*, *ksort()*, *natsort()*, *natcasesort()*, *rsort()*, *usort()*, *array_multisort()* a *uksort()*.

Poznámka: Druhý argument byl přidán v PHP 4.

uasort (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

Třídí pole pomocí uživatelsky definované porovnávací funkce se zachováním klíčů

```
void uasort ( array array, function cmp_function) \linebreak
```

Tato funkce třídí pole tak, že si indexy uchovávají spojením s hodnotami. To je užitečné hlavně při třídění asociativních polí, kde je důležité pořadí prvků. Srovnávací funkce je uživatelsky definována.

Poznámka: Ukázky uživatelsky definovaných porovnávacích funkcí viz *usort()* a *uksort()*.

Viz také: *usort()*, *uksort()*, *sort()*, *asort()*, *arsort()*, *ksort()* a *rsort()*.

uksort (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

Třídí pole podle klíčů pomocí uživatelsky definované porovnávací funkce

```
void uksort ( array array, function cmp_function) \linebreak
```

Tato funkce třídí pole podle klíčů pomocí uživatelsky definované porovnávací funkce. Pokud potřebujete třídí pole podle komplikovanějších kritérií, měli byste použít tuto funkci.

Příklad 1. Ukázka uksort()

```
function cmp ($a, $b) {
    if ($a == $b) return 0;
    return ($a > $b) ? -1 : 1;
}

$a = array (4 => "four", 3 => "three", 20 => "twenty", 10 => "ten");

uksort ($a, "cmp");

while (list ($key, $value) = each ($a)) {
    echo "$key: $value\n";
}
```

Tato ukázka zobrazí:

```
20: twenty
10: ten
4: four
3: three
```

Viz také: usort(), uasort(), sort(), asort(), arsort(), ksort(), natsort() a rsort().

usort (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Třídí pole podle hodnot pomocí uživatelsky definované porovnávací funkce

void usort (array array, string cmp_function) \linebreak

Tato funkce třídí pole podle hodnot pomocí uživatelsky definované porovnávací funkce. Pokud potřebujete třídí pole podle komplikovanějších kritérií, měli byste použít tuto funkci.

Porovnávací funkce musí vrace integer menší než 0, 0, a větší než 0, pokud je první argument menší než, stejný, nebo větší než druhý argument. Pokud jsou dvě porovnávané hodnoty stejné, jejich pořadí v tříděném poli je nedefinováno.

Příklad 1. Ukázka usort()

```
function cmp ($a, $b) {
    if ($a == $b) return 0;
    return ($a > $b) ? -1 : 1;
}

$a = array (3, 2, 5, 6, 1);

usort ($a, "cmp");

while (list ($key, $value) = each ($a)) {
```

```
    echo "$key: $value\n";
}
```

Tato ukázka zobrazí:

```
0: 6
1: 5
2: 3
3: 2
4: 1
```

Poznámka: V tomto jednoduchém případě by pochopitelně bylo vhodnější použít `rsort()`.

Příklad 2. Ukázka `usort()` s vícerozměrným polem

```
function cmp ($a, $b) {
    return strcmp($a["fruit"], $b["fruit"]);
}

$fruits[0]["fruit"] = "lemons";
$fruits[1]["fruit"] = "apples";
$fruits[2]["fruit"] = "grapes";

usort($fruits, "cmp");

while (list ($key, $value) = each ($fruits)) {
    echo "\$fruits[$key]: " . $value["fruit"] . "\n";
}
```

Při třídění vícerozměrného pole `$a` a `$b` obsahují reference na první index pole.

Tato ukázka zobrazí:

```
$fruits[0]: apples
$fruits[1]: grapes
$fruits[2]: lemons
```


Varování

Použitá quicksort funkce v některých C knihovnách (např. na systémech Solaris) může způsobit zhroucení PHP, pokud porovnávací funkce nevrací konsistentní hodnoty.

Viz také: `uasort()`, `uksort()`, `sort()`, `asort()`, `arsort()`, `ksort()`, `natsort()` a `rsort()`.

III. Aspell funkce

aspell() funkce umožňují ověřit hláskování slova a nabídnout možné opravy.

Poznámka: aspell funguje pouze s velmi starými (do přibližně .27.*) verzemi aspell knihovny. Tento modul, ani tyto verze aspell knihovny už nejsou podporovány. Pokud chcete v PHP použít kontrolu hláskování, použijte místo toho pspell. Využívá pspell knihovnu, a pracuje s novějšími verzemi aspellu.

Budete potřebovat aspell knihovnu dostupnou z: <http://aspell.sourceforge.net/>.

aspell_check (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Zkontrolovat slovo

boolean **aspell_check** (int dictionary_link, string word) \linebreak

aspell_check() zkontroluje hláskování slova a vrátí TRUE, pokud je hláskování správné, a FALSE, pokud není.

Příklad 1. aspell_check()

```
$aspell_link=aspell_new ("english");
if (aspell_check ($aspell_link, "testt")) {
    echo "Toto je platné hláskování";
} else {
    echo "Pardon, špatné hláskování";
}
```

aspell_check_raw (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Zkontrolovat slovo beze změny velikosti písmen nebo pokusů o ořezání

boolean **aspell_check_raw** (int dictionary_link, string word) \linebreak

aspell_check_raw() zkontroluje hláskování slova beze změn velikosti písmen nebo pokusů ho jakýmkoliv způsobem ořezat, a vrátí TRUE, pokud je hláskování správné, a FALSE, pokud není.

Příklad 1. aspell_check_raw()

```
$aspell_link=aspell_new ("english");
if (aspell_check_raw ($aspell_link, "test")) {
    echo "Toto je platné hláskování";
} else {
    echo "Pardon, špatné hláskování";
}
```

aspell_new (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Načíst nový slovník

int **aspell_new** (string master, string personal) \linebreak

aspell_new() otevře nový slovník, a vrátí identifikátor spojení na tento slovník využitelný s dalšími aspell funkcemi.

Příklad 1. aspell_new()

```
$aspell_link=aspell_new ("english");
```

aspell_suggest (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Nabídnout možné hláskování slova

array **aspell_suggest** (int dictionary_link, string word) \linebreak
aspell_suggest() vrátí pole možných hláskování daného slova.

Příklad 1. aspell_suggest()

```
$aspell_link=aspell_new ("english");

if (!aspell_check ($aspell_link, "test")) {
    $suggestions=aspell_suggest ($aspell_link, "test");

    for ($i=0; $i < count ($suggestions); $i++) {
        echo "Možné hláskování: " . $suggestions[$i] . "<br>";
    }
}
```

IV. BCMath funkce pro výpočty s libovolnou přesností

Tyto funkce jsou dostupné pouze pokud bylo PHP zkonfigurováno s `--enable-bcmath`.

bcadd (PHP 3, PHP 4 >= 4.0.0)

Sečíst dvě čísla s libovolnou přesností

string **bcadd** (string *left operand*, string *right operand* [, int *scale*]) \linebreak

Přičte *left operand* k *right operand* a vrátí součet v řetězci. Volitelný argument *scale* se používá k určení počtu desetinných míst ve výsledku.

Viz také bcsub().

bccomp (PHP 3, PHP 4 >= 4.0.0)

Porovnat dvě čísla s libovolnou přesností

int **bccomp** (string *left operand*, string *right operand* [, int *scale*]) \linebreak

Porovná *left operand* s *right operand* a vrátí výsledek jako integer. Volitelný argument *scale* se používá k určení počtu desetinných míst použitých při porovnání. Návrátová hodnota je 0, pokud jsou si oba operandy rovné. Pokud je *left operand* větší než *right operand*, návratová hodnota je +1, a pokud je *left operand* menší než *right operand*, návratová hodnota je -1.

bcdiv (PHP 3, PHP 4 >= 4.0.0)

Dělit dvě čísla s libovolnou přesností

string **bcdiv** (string *left operand*, string *right operand* [, int *scale*]) \linebreak

Vydělí argument *left operand* argumentem *right operand* a vrátí výsledek. Volitelný argument *scale* se používá k určení počtu desetinných míst ve výsledku.

Viz také bcmul().

bcmmod (PHP 3, PHP 4 >= 4.0.0)

Získat modulus čísla s libovolnou přesností

string **bcmmod** (string *left operand*, string *modulus*) \linebreak

Vrátí modulus argumentu *left operand* s použitím argumentu *modulus*.

Viz také bcdiv().

bcmul (PHP 3, PHP 4 >= 4.0.0)

Vynásobit dvě čísla s libovolnou přesností

string **bcmul** (string left operand, string right operand [, int scale]) \linebreak

Vynásobí argument *left operand* argumentem *right operand* a vrátí výsledek. Volitelný argument *scale* se používá k určení počtu desetinných míst ve výsledku.

Viz také bcdiv().

bcpow (PHP 3, PHP 4 >= 4.0.0)

Umocnit jedno číslo na jiné s libovolnou přesností

string **bcpow** (string x, string y [, int scale]) \linebreak

Umocní *x* na *y*. Volitelný argument *scale* se používá k určení počtu desetinných míst ve výsledku.

Viz také bcsqrt().

bcscale (PHP 3, PHP 4 >= 4.0.0)

Nastavit výchozí škálu pro všechny bc math funkce

string **bcscale** (int scale) \linebreak

Tato funkce nastaví výchozí škálu pro všechna následná volání bc math funkcí, která neudávají explicitně škálu přesnosti.

bcsqrt (PHP 3, PHP 4 >= 4.0.0)

Získat druhou odmocninu čísla s libovolnou přesností

string **bcsqrt** (string operand, int scale) \linebreak

Vrátí druhou odmocninu argumentu *operand*. Volitelný argument *scale* se používá k určení počtu desetinných míst ve výsledku.

Viz také bcpow().

bcsub (PHP 3, PHP 4 >= 4.0.0)

Odečíst jedno číslo od druhého s libovolnou přesností

string **bcsub** (string left operand, string right operand [, int scale]) \linebreak

Odečte argument *right operand* od argumentu *left operand* a vrátí výsledek v řetězci. Volitelný argument *scale* se používá k určení počtu desetinných míst ve výsledku.

Viz také bcadd().

V. Bzip2 Compression Functions

Úvod

The bzip2 functions are used to transparently read and write bzip2 (.bz2) compressed files.

Požadavky

This module uses the functions of the bzip2 (<http://sources.redhat.com/bzip2/>) library by Julian Seward

Instalace

Bzip2 support in PHP is not enabled by default. You will need to use the --with-bz2 configuration option when compiling PHP to enable bzip2 support. This module requires bzip2/libbzip2 version >= 1.0.x.

Konfigurace běhu

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Typy prostředků

This extension defines one resource type: a file pointer identifying the bz2-file to work on.

Předdefinované konstanty

Toto rozšíření nemá definovány žádné konstanty.

Příklady

This example opens a temporary file and writes a test string to it, then prints out the contents of the file.

Příklad 1. Small bzip2 Example

```
<?php

$filename = "/tmp/testfile.bz2";
$str = "This is a test string.\n";
```



```
// open file for writing
$bz = bzopen($filename, "w");

// write string to file
bzwrite($bz, $str);

// close file
bzclos($bz);

// open file for reading
$bz = bzopen($filename, "r");

// read 10 characters
print bzread($bz, 10);

// output until end of the file (or the next 1024 char) and close it.
print bzread($bz);

bzclos($bz);

?>
```

bzclose (PHP 4 >= 4.0.4)

Close a bzip2 file pointer

int **bzclose** (resource bz) \linebreak

Closes the bzip2 file referenced by the pointer *bz*.

Vrací TRUE při úspěchu, FALSE při selhání.

The file pointer must be valid, and must point to a file successfully opened by bzopen().

See also bzopen().

bzcompress (PHP 4 >= 4.0.4)

Compress a string into bzip2 encoded data

string **bzcompress** (string source [, int blocksize [, int workfactor]]) \linebreak

bzcompress() compresses the *source* string and returns it as bzip2 encoded data.

The optional parameter *blocksize* specifies the blocksize used during compression and should be a number from 1 to 9 with 9 giving the best compression, but using more resources to do so.

blocksize defaults to 4.

The optional parameter *workfactor* controls how the compression phase behaves when presented with worst case, highly repetitive, input data. The value can be between 0 and 250 with 0 being a special case and 30 being the default value. Regardless of the *workfactor*, the generated output is the same.

Příklad 1. bzcompress() Example

```
<?php
$str = "sample data";
$bzstr = bzcompress($str, 9);
print( $bzstr );
?>
```

See also bzdecompress().

bzdecompress (PHP 4 >= 4.0.4)

Decompresses bzip2 encoded data

string **bzdecompress** (string source [, int small]) \linebreak

bzdecompress() decompresses the *source* string containing bzip2 encoded data and returns it. If the optional parameter *small* is TRUE, an alternative decompression algorithm will be used which uses less memory (the maximum memory requirement drops to around 2300K) but works at roughly half the speed. See the bzip2 documentation (<http://sources.redhat.com/bzip2/>) for more information about this feature.

Příklad 1. bzdecompress()

```
<?php
$start_str = "This is not an honest face?";
$bzstr = bzcompress($start_str);

print( "Compressed String: " );
print( $bzstr );
print( "\n<br>\n" );

$str = bzdecompress($bzstr);
print( "Decompressed String: " );
print( $str );
print( "\n<br>\n" );
?>
```

See also bzcompress().

bzerrno (PHP 4 >= 4.0.4)

Returns a bzip2 error number

int **bzerrno** (resource bz) \linebreak

Returns the error number of any bzip2 error returned by the file pointer *bz*.

See also bzerror() and bzerrstr().

bzerror (PHP 4 >= 4.0.4)

Returns the bzip2 error number and error string in an array

array **bzerror** (resource bz) \linebreak

Returns the error number and error string, in an associative array, of any bzip2 error returned by the file pointer *bz*.

Příklad 1. bzerror() Example

```
<?php
$error = bzerror($bz);

echo $error["errno"];
echo $error["errstr"];
?>
```

See also bzerrno() and bzerrstr().

bzerrstr (PHP 4 >= 4.0.4)

Returns a bzip2 error string

string **bzerrstr** (resource bz) \linebreak

Returns the error string of any bzip2 error returned by the file pointer *bz*.

See also bzerrno() and bzerror().

bzflush (PHP 4 >= 4.0.4)

Force a write of all buffered data

int **bzflush** (resource bz) \linebreak

Forces a write of all buffered bzip2 data for the file pointer *bz*.

Vrací TRUE při úspěchu, FALSE při selhání.

See also bzread() and bzwrite().

bzopen (PHP 4 >= 4.0.4)

Open a bzip2 compressed file

resource **bzopen** (string filename, string mode) \linebreak

Opens a bzip2 (.bz2) file for reading or writing. *filename* is the name of the file to open. *mode* is similar to the fopen() function ('r' for read, 'w' for write, etc.).

If the open fails, the function returns FALSE, otherwise it returns a pointer to the newly opened file.

Příklad 1. bzopen() Example

```
<?php
$bz = bzopen("/tmp/foo.bz2", "r");
$decompressed_file = bzread($bz, filesize("/tmp/foo.bz2"));
bzclos($bz);

print( "The contents of /tmp/foo.bz2 are: " );
print( "\n<br>\n" );
print( $decompressed_file );
?>
```

See also `bzclose()`.

bzread (PHP 4 >= 4.0.4)

Binary safe bzip2 file read

string **bzread** (resource bz [, int length]) \linebreak

bzread() reads up to *length* bytes from the bzip2 file pointer referenced by *bz*. Reading stops when *length* (uncompressed) bytes have been read or EOF is reached, whichever comes first. If the optional parameter *length* is not specified, **bzread()** will read 1024 (uncompressed) bytes at a time.

Příklad 1. bzread() Example

```
<?php
$bz = bzopen("/tmp/foo.bz2", "r");
$str = bzread($bz, 2048);
print( $str );
?>
```

See also `bzwrite()` and `bzopen()`.

bzwrite (PHP 4 >= 4.0.4)

Binary safe bzip2 file write

int **bzwrite** (resource bz, string data [, int length]) \linebreak

bzwrite() writes the contents of the string *data* to the bzip2 file stream pointed to by *bz*. If the optional *length* argument is given, writing will stop after length (uncompressed) bytes have been written or the end of string is reached, whichever comes first.

Příklad 1. bzwrite() Example

```
<?php
$str = "uncompressed data";
$bz = bzopen("/tmp/foo.bz2", "w");
bzwrite($bz, $str, strlen($str));
bzclos($bz);
?>
```

See also `bzread()` and `bzopen()`.

VI. Kalendářové funkce

Kalendářové funkce jsou přístupné pouze pokud máte zkompilevanout calendar extenzi umístěnou v adresáři "dl" or "ext" ve zdrojovém kódu PHP. Před jejím použitím si prosím přečtěte README soubor.

Calendar extenze představuje sadu funkcí určených ke zjednodušení převodů mezi různými kalendáři. Prostředníkem nebo standardem, na kterém je založena je Julian Day Count. To je počet dní začínající daleko před jakýmkoli datem o které by se většina lidí zajímala (někde kolem 4000 př. n. l.). Pokud chcete převádět mezi kalendářovými systémy, musíte nejdřív převést na Julian Day Count, potom na kýžený kalendář. Julian Day Count se velmi liší od Juliánského kaledáře! Více informací o kalendářových systémech viz <http://genealogy.org/~scottlee/cal-overview.html>. Tyto instrukce obsahují výňatky z této stránky (v uvozovkách).

easter_date (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Zjistit UNIXový timestamp Velikonoční půlnoci v daném roce

```
int easter_date ( int year) \linebreak
```

Vrací UNIXový timestamp odpovídající Velikonoční půlnoci v daném roce. Default *year* je současný rok.

Varování: Tato funkce vygeneruje varování, pokud je *year* mimo rozsah UNIXových timestampů (tj. před 1970 nebo po 2037).

Příklad 1. Ukázka easter_date()

```
echo date ("M-d-Y", easter_date(1999));      /* "Apr-04-1999" */
echo date ("M-d-Y", easter_date(2000));      /* "Apr-23-2000" */
echo date ("M-d-Y", easter_date(2001));      /* "Apr-15-2001" */
```

Datum Velikonoc bylo definováno Nicaejským koncilem v r. 325 n. l. jako neděle po prvním úplňku který připadá na nebo po jarní rovnodennosti. Rovnodennost se vždy předpokládá na 21. března, takže se výpočet redukuje na určení data úplňku a data následující neděle. Zde použitý algoritmus byl poprvé použit kolem roku 532 Dionysiem Exiguem. V Juliánském kalendáři (pro léta před 1753) se na sledování fází Měsíce používal jednoduchý devatenáctiletý cyklus. V Gregoriánském kalendáři (pro léta po 1753 - navržen Claviem a Liliem a zaveden papežem Řehořem XIII v říjnu 1582, v Británii a jejích koloniích v září 1752) se přidávají dva faktory, které tento cyklus zpřesňují.

(Kód je založen na C programu od Simona Kershawa, <webmaster@ely.anglican.org>)

Výpočet Velikonoc před rokem 1970 nebo po roce 2037 viz `easter_days()`.

easter_days (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Get number of days after March 21 on which Easter falls for a given year

```
int easter_days ( int year) \linebreak
```

Vrací počet dní od 21. března do Velikonoc v daném roce. Default *year* je současný rok.

Tato funkce je využitelná místo `easter_date()` na výpočty Velikonoc pro roky které spadají mimo rozsah UNIXových timestampů (tj. před rokem 1970 a po roce 2037).

Příklad 1. Ukázka easter_date()

```
echo easter_days (1999);      /* 14, i.e. April 4  */
echo easter_days (1492);      /* 32, i.e. April 22  */
echo easter_days (1913);      /* 2, i.e. March 23  */
```

Datum Velikonoc bylo definováno Nicaejským koncilem v r. 325 n. l. jako neděle po prvním úplňku který připadá na nebo po jarní rovnodennosti. Rovnodennost se vždy předpokládá na 21. března,

takže se výpočet redukuje na určení data úplňku a data následující neděle. Zde použitý algoritmus byl poprvé použit kolem roku 532 Dionysiem Exiguem. V Juliánském kalendáři (pro léta před 1753) se na sledování fází Měsíce používal jednoduchý devatenáctiletý cyklus. V Gregoriánském kalendáři (pro léta po 1753 - navržen Claviem a Liliem a zaveden papežem Řehořem XIII v říjnu 1582, v Británii a jejích koloniích v září 1752) se přidávají dva faktory, které tento cyklus zpřesňují.

(Kód je založen na C programu od Simona Kershawa, <webmaster@ely.anglican.org>)

Viz také: `easter_date()`.

FrenchToJD (PHP 3, PHP 4 >= 4.0.0)

Převést datum z Francouzského republikánského kalendáře na Julian Day Count

`int frenchtojd (int month, int day, int year) \linebreak`

Převádí datum z Francouzského republikánského kalendáře na Julian Day Count.

Tyto rutiny konvertují pouze data v letech 1 až 14 (Gregoriánská data 22. září 1792 až 22. září 1806). To více než dostatečně pokrývá období, po které se tento kalendář používal.

GregorianToJD (PHP 3, PHP 4 >= 4.0.0)

Převést Gregoriánské datum na Julian Day Count

`int gregoriantojd (int month, int day, int year) \linebreak`

Platný rozsah Gregoriánského kalendáře je 4714 př. n. l. až 9999 n. l.

Jakkoli tento software zvládá data až do 4714 př. n. l., takové použití asi nemá smysl. Gregoriánský kalendář byl založen až 15. října 1582 (5. října 1582 podle Juliánského kalendáře). Některé země ho přijaly mnohem později, Řecko až v r. 1923. Většina evropským států před Gregoriánským kalendářem používala Juliánský.

Příklad 1. Kalendářové funkce

```
<?php
$jd = GregorianToJD (10,11,1970);
echo "$jd\n";
$gregorian = JDTToGregorian ($jd);
echo "$gregorian\n";
?>
```

JDDayOfWeek (PHP 3, PHP 4 >= 4.0.0)

Vrátit den v týdnu

mixed **jddayofweek** (int julianday, int mode) \linebreak

Vrací den v týdnu. V závislosti na módu vrací řetězec nebo integer.

Tabulka 1. Kalendářové týdenní módy

Mód	Význam
0	Vrací číslo dne jako integer (0=sunday, 1=monday, etc)
1	Vrací řetězec obsahující název dne v týdnu (anglický gregoriánský)
2	Vrací řetězec obsahující zkrácený název dne v týdnu (anglický gregoriánský)

JDMonthName (PHP 3, PHP 4 >= 4.0.0)

Vrátit název měsíce

string **jdmonthname** (int julianday, int mode) \linebreak

Vrací řetězec obsahující název měsíce. *mode* určuje, na který kalendář se má Julian Day Count konvertovat a jaký typ jména se má vrátit.

Tabulka 1. Kalendářové módy

Mód	Význam
0	Gregoriánský - zkrácený
1	Gregoriánský
2	Juliánský - zkrácený
3	Juliánský
4	idovský
5	Francouzský republikánský

JDToFrench (PHP 3, PHP 4 >= 4.0.0)

Převést Julian Day Count na Francouzský republikánský kalendář

string **jdtofrrench** (int juliandaycount) \linebreak

Převádí Julian Day Count na Francouzský republikánský kalendář.

JDTToGregorian (PHP 3, PHP 4 >= 4.0.0)

Převést Julian Day Count na Gregoriánské datum

string **jdtogregorian** (int julianday) \linebreak

Převádí Julian Day Count na řetězec obsahující Gregoriánské datum ve formátu "měsíc/den/rok".

JDTToJewish (PHP 3, PHP 4 >= 4.0.0)

Převést Julian Day Count na idovský kalendář

string **jdtojewish** (int julianday) \linebreak

Převádí Julian Day Count na idovský kalendář.

JDTToJulian (PHP 3, PHP 4 >= 4.0.0)

Převést Julian Day Count na Juliánské datum

string **jdtojulian** (int julianday) \linebreak

Převádí Julian Day Count na řetězec obsahující Juliánské datum ve formátu "měsíc/den/rok".

jdtounix (PHP 4 >= 4.0.0)

Převést Julian Day Count na UNIXový timestamp

int **jdtounix** (int jday) \linebreak

jdtounix() vrací UNIXový timestamp odpovídající Julian Day Countu danému v *jday* nebo FALSE, pokud je *jday* mimo UNIXovou epochu (Gregoriánské roky mezi 1970 a 2037, nebo-li 2440588 <= *jday* <= 2465342)

Viz také: **jdtounix()**.

Poznámka: Tato funkce byla přidána v PHP 4 RC2.

JewishToJD (PHP 3, PHP 4 >= 4.0.0)

Převést datum podle idovského kalendáře na Julian Day Count

int **jewishtojd** (int month, int day, int year) \linebreak

Platný rozsah Jakkoli tento software zvládá data až do roku 1 (3761 př. n. l.), takové použití asi nemá smysl.

idovský kalendář se používá několik tisíc let, ale zpočátku neexistoval vzorec na určení začátku měsíce. Nový měsíc začínal, když byl poprvé spatřen nový Měsíc.

JulianToJD (PHP 3, PHP 4 >= 4.0.0)

Převést Juliánské datum na Julian Day Count

int **juliantojd** (int month, int day, int year) \linebreak

Platný rozsah pro Juliánský kalendář je 4713 př. n. l. až 9999 n. l.

Jakkoli tento software zvládá data až do 4713 př. n. l., takové použití asi nemá smysl. Tento kalendář byl vytvořen v roce 46 př. n. l., ale detaily se nestabilizovaly nejméně do 8 n. l., a možná až do konce 4. století. Navíc začátek roku se lišil od kultury ke kultuře - ne všechny přijímaly leden jako první měsíc roku.

unixtojd (PHP 4 >= 4.0.0)

Převést UNIXový timestamp na Julian Day Count

int **unixtojd** ([int timestamp]) \linebreak

Vrací Julian Day Count pro UNIXový *timestamp* (sekundy od 1.1.1970), nebo pro aktuální den, pokud není dán *timestamp*.

Viz také: jdtounix().

Poznámka: Tato funkce byla přidána v PHP 4 RC2.

VII. CCVS API Funkce

Tyto funkce představují interface k CCVS API, a umožňují tak přímo pracovat s CCVS z vašich PHP skriptů. CCVS je RedHatí (<http://www.redhat.com/>) řešení "zprostředkovatele" ve zpracování kreditních karet. Umožňuje vám oslovovat přímo zpracovatele kreditních karet přes váš *nix systém a modem. Pomocí CCVS modulu pro PHP můžete zpracovávat kreditní karty přes CCVS ve vašich PHP skriptech. Následující reference tento proces přiblíží.

Pokud chcete zapnout CCVS podporu v PHP, zjistěte si nejdříve instalační adresář CCVS. Potom budete muset PHP zkonfigurovat s `--with-ccvs`. Pokud toto použijete bez udání cesty k vaší instalaci CCVS, PHP se pokusí podívat do defaultní instalační lokace CCVS (`/usr/local/ccvs`). Pokud je CCVS na nestandardním místě, spustěte configure s: `--with-ccvs=$ccvs_path`, kde `$ccvs_path` je cesta k vaší instalaci CVS. Pozn.: Podpora CCVS vyžaduje existenci `$ccvs_path/lib` a `$ccvs_path/include`, a přítomnost `cv_api.h` v adresáři `include` a `libccvs.a` v adresáři `lib`.

Dále je potřeba, aby běžel proces `ccvsd`. Navíc, PHP processy musí běžet pod stejným uživatelem, pod kterým běhá CCVS (např. pokud jste instalovali `ccvs` jako `'ccvs'`, vaše PHP procesy musí také běžet jako `'ccvs'`).

Další informace o CCVS jsou na <http://www.redhat.com/products/ccvs>.

Na této sekci dokumentace se pracuje. Prozatím RedHat udržuje mírně zastaralou, ale stále užitečnou dokumentaci na <http://www.redhat.com/products/ccvs/support/CCVS3.3docs/ProgPHP.html>.

ccvs_add (PHP 4 >= 4.0.2)

Add data to a transaction

string **ccvs_add** (string session, string invoice, string argtype, string argval) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_auth (PHP 4 >= 4.0.2)

Perform credit authorization test on a transaction

string **ccvs_auth** (string session, string invoice) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_command (PHP 4 >= 4.0.2)

Performs a command which is peculiar to a single protocol, and thus is not available in the general CCVS API

string **ccvs_command** (string session, string type, string argval) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_count (PHP 4 >= 4.0.2)

Find out how many transactions of a given type are stored in the system

int **ccvs_count** (string session, string type) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs__delete (PHP 4 >= 4.0.2)

Delete a transaction

string **ccvs_delete** (string session, string invoice) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs__done (PHP 4 >= 4.0.2)

Terminate CCVS engine and do cleanup work

string **ccvs_done** (string sess) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs__init (PHP 4 >= 4.0.2)

Initialize CCVS for use

string **ccvs_init** (string name) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_lookup (PHP 4 >= 4.0.2)

Look up an item of a particular type in the database #

string **ccvs_lookup** (string session, string invoice, int inum) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_new (PHP 4 >= 4.0.2)

Create a new, blank transaction

string **ccvs_new** (string session, string invoice) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_report (PHP 4 >= 4.0.2)

Return the status of the background communication process

string **ccvs_report** (string session, string type) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_return (PHP 4 >= 4.0.2)

Transfer funds from the merchant to the credit card holder

string **ccvs_return** (string session, string invoice) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_reverse (PHP 4 >= 4.0.2)

Perform a full reversal on an already-processed authorization

string **ccvs_reverse** (string session, string invoice) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_sale (PHP 4 >= 4.0.2)

Transfer funds from the credit card holder to the merchant

string **ccvs_sale** (string session, string invoice) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_status (PHP 4 >= 4.0.2)

Check the status of an invoice

string **ccvs_status** (string session, string invoice) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_textvalue (PHP 4 >= 4.0.2)

Get text return value for previous function call

string **ccvs_textvalue** (string session) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ccvs_void (PHP 4 >= 4.0.2)

Perform a full reversal on a completed transaction

string **ccvs_void** (string session, string invoice) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

VIII. Funkce na podporu COM ve Windows

Tyto funkce jsou dostupné pouze ve Windows verzi PHP. Byly přidány v PHP 4.

com_get (PHP 3>= 3.0.3, PHP 4 >= 4.0.5)

Získává hodnotu vlastnosti COM komponenty

mixed **com_get** (resource com_object, string property) \linebreak

Vrací hodnotu *property* COM komponenty odkazované *com_object*. Při chybě vrací FALSE.

com_invoke (PHP 3>= 3.0.3)

Volá metodu COM komponenty.

mixed **com_invoke** (resource com_object, string function_name [, mixed parametry funkce, ...]) \linebreak

com_invoke() volá metodu COM komponenty odkazované *com_object*. Pokud dojde k chybě, vrací FALSE, při úspěchu vrací návratovou hodnotu metody *function_name*.

com_load (PHP 3>= 3.0.3)

Vytvoří nový odkaz na COM komponentu

string **com_load** (string module name [, string server name]) \linebreak

com_load() vytváří novou COM komponentu a vrací odkaz na ni. Při neúspěchu vrací FALSE.

com_propget (PHP 3>= 3.0.3, PHP 4 >= 4.0.5)

Získává hodnotu vlastnosti COM komponenty

mixed **com_propget** (resource com_object, string property) \linebreak

Tato funkce je alias k *com_get()*.

com_propput (PHP 3>= 3.0.3, PHP 4 >= 4.0.5)

Přiřazuje hodnotu vlastnosti COM komponenty.

void **com_propput** (resource com_object, string property, mixed value) \linebreak

Tato funkce je alias ke *com_set()*.

com_propset (PHP 3>= 3.0.3, PHP 4 >= 4.0.5)

Přiřazuje hodnotu vlastnosti COM komponenty.

void **com_propset** (resource com_object, string property, mixed value) \linebreak

Tato funkce je alias ke com_set().

com_set (PHP 3>= 3.0.3, PHP 4 >= 4.0.5)

Přiřazuje hodnotu vlastnosti COM komponenty.

void **com_set** (resource com_object, string property, mixed value) \linebreak

Nastavuje hodnotu vlastnosti *property* COM komponent odkazované *com_object*. Vrací TRUE, pokud je *property* nastaveno. Při chybě vrací FALSE.

IX. Funkce pro práci s třídami/objekty

Úvod

About

Tyto funkce vám umožňují získávat informace o třídách a instancích. Můžete zjistit název třídy do které objekt patří nebo jeho proměnné a metody. Pomocí těchto funkcí můžete zjistit nejen příslušnost objektu k třídě, ale i jeho předka (tj. kterou třídu třída tohoto objektu rozšiřuje).

Ukázka použití

V této ukázce nejdříve definujeme základní třídu a rozšíření této třídy. Základní třída popisuje obecnou zeleninu, ať už je jedlá nebo ne a bez ohledu na její barvu. Podtřída Spenat přidává metodu na uvaření této zeleniny a další, která zjistí, jestli je vařená.

Příklad 1. classes.inc

```
<?php

// základní třída s členskými proměnnými a metodami
class Zelenina {

    var $jedla;
    var $barva;

    function Zelenina( $jedla, $barva="green" ) {
        $this->jedla = $jedla;
        $this->barva = $barva;
    }

    function je_jedla() {
        return $this->jedla;
    }

    function jaka_barva() {
        return $this->barva;
    }

} // konec tridy zelenina

// rozsiruje zakladni tridu
class Spenat extends Zelenina {

    var $varena = false;

    function Spenat() {
        $this->Zelenina( true, "zelena" );
    }

    function cook_it() {
```

```

        $this->varena = true;
    }

    function je_varena() {
        return $this->varena;
    }

} // konec tridy Spenat

?>

```

Potom z těchto tříd vytvoříme 2 objekty a vytiskneme informace o nich, vč. rodičovských tříd. Také definujeme některé pomocné funkce, především kvůli pohodlnému tisku informací.

Příklad 2. test_script.php

```

<pre>
<?php

include "classes.inc";

// pomocné funkce

function vytiskni_promenne($obj) {
    $pole = get_object_vars($obj);
    while (list($vlastnost, $hodnota) = each($pole))
        echo "\t$vlastnost = $hodnota\n";
}

function vytiskni_metody($obj) {
    $pole = get_class_methods(get_class($obj));
    foreach ($pole as $metoda)
        echo "\tfunction $metoda()\n";
}

function class_parentage($obj, $class) {
    global $$obj;
    if (is_subclass_of($$obj, $class)) {
        echo "Objekt $obj patri do tridy ".get_class($$obj);
        echo " ktera je podtridou $class\n";
    } else {
        echo "Objekt $obj nepatri do podtridy tridy $class\n";
    }
}

// instancujeme 2 objekty

$zeleninka = new Zelenina(true,"modra");
$listnaty = new Spenat();

// vytisknout informace o obou objektech
echo "zeleninka: CLASS ".get_class($zeleninka)."\n";
echo "listnaty: CLASS ".get_class($listnaty);
echo ", PARENT ".get_parent_class($listnaty)."\n";

```

```
// vytisknout vlastnosti zeleninky
echo "\nzeleninka: Vlastnosti\n";
print_vars($zeleninka);

// a metody objektu listnaty
echo "\nlistnaty: Metody\n";
print_methods($listnaty);

echo "\nRodic:\n";
class_parentage("listnaty", "Spenat");
class_parentage("listnaty", "Zelenina");
?>
</pre>

```

Je třeba poznamenat, že ve výše uvedené ukázce je objekt `$listnaty` instancí třídy `Spenat`, která je podtřídou třídy `Zelenina`, a poslední část výše uvedeného skriptu tudíž vytiskne:

```
[...]
Rodic:
Objekt listnaty nepatri do podtridy tridy Spenat
Object listnaty patri do tridy Spenat, ktera je podtridou tridy Zelenina
```


call_user_method (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Zavolat uživatelsky definovanou metodu určitého objektu

mixed **call_user_method** (string method_name, object obj [, mixed parameter [, mixed ...]]) \linebreak

Zavolá metodu *method_name* objektu *obj*. Ukázka využití je níže, kde definujeme třídu, vytvoříme objekt a použijeme **call_user_method()** k nepřímému volání její *print_info* metody.

```
<?php
class Country {
    var $NAME;
    var $TLD;

    function Country($name, $tld) {
        $this->NAME = $name;
        $this->TLD = $tld;
    }

    function print_info($prestr="") {
        echo $prestr."Country: ".$this->NAME."\n";
        echo $prestr."Top Level Domain: ".$this->TLD."\n";
    }
}

$cntry = new Country("Peru","pe");

echo "* Calling the object method directly\n";
$cntry->print_info();

echo "\n* Calling the same method indirectly\n";
call_user_method ("print_info", $cntry, "\t");
?>
```

Viz také **call_user_func()**.

class_exists (PHP 4 >= 4.0.0)

Zjistit, jestli je třída definována

bool **class_exists** (string class_name) \linebreak

Tato funkce vrátí TRUE, pokud je třída *class_name* definována, jinak FALSE.

get_class (PHP 4 >= 4.0.0)

Vrátit jméno třídy objektu

string **get_class** (object obj) \linebreak

Tato funkce vrací název třídy jíž je objekt *obj* instancí.

Viz také `get_parent_class()`, `is_subclass_of()`

get_class_methods (PHP 4 >= 4.0.0)

Vrátit pole názvů metod třídy

array **get_class_methods** (string *class_name*) \linebreak

Tato funkce vrací pole názvů metod definovaných pro třídu specifikovanou argumentem *class_name*.

Viz také `get_class_vars()`, `get_object_vars()`

get_class_vars (PHP 4 >= 4.0.0)

Vrátit pole defaultních vlastností třídy

array **get_class_vars** (string *class_name*) \linebreak

Tato funkce vrací pole defaultních vlastností třídy *class_name*.

Viz také `get_class_methods()`, `get_object_vars()`

get_declared_classes (PHP 4 >= 4.0.0)

Vrátit pole názvů definovaných tříd

array **get_declared_classes** (void) \linebreak

Tato funkce vrací pole názvů tříd definovaných v současném skriptu.

Poznámka: V PHP 4.0.1pl2 jsou na začátku pole vráceny ještě tři další třídy: `stdClass` (definovaná v `Zend/zend.c`), `OverloadedTestClass` (definovaná v `ext/standard/basic_functions.c`) a `Directory` (definovaná v `ext/standard/dir.c`).

get_object_vars (PHP 4 >= 4.0.0)

Vrátit asociativní pole vlastností objektu

array **get_object_vars** (object *obj*) \linebreak

Tato funkce vrací asociativní pole definovaných vlastností objektu *obj*. Proměnným deklarovaným v třídě jíž je *obj* instancí, kterým nebyla přiřazena hodnota, nejsou ve vráceném poli obsaženy.

Příklad 1. Použití get_object_vars()

```

<?php
class Point2D {
    var $x, $y;
    var $label;

    function Point2D($x, $y) {
        $this->x = $x;
        $this->y = $y;
    }

    function setLabel($label) {
        $this->label = $label;
    }

    function getPoint() {
        return array("x" => $this->x,
                     "y" => $this->y,
                     "label" => $this->label);
    }
}

$p1 = new Point2D(1.233, 3.445);
print_r(get_object_vars($p1));
// "$label" is declared but not defined
// Array
// (
//     [x] => 1.233
//     [y] => 3.445
// )

$p1->setLabel("point #1");
print_r(get_object_vars($p1));
// Array
// (
//     [x] => 1.233
//     [y] => 3.445
//     [label] => point #1
// )

?>

```

Viz také `get_class_methods()`, `get_class_vars()`

get_parent_class (PHP 4 >= 4.0.0)

Vrátit název rodičovské třídy objektu

string **get_parent_class** (object obj) \linebreak

Tato funkce vrací název rodičovské třídy objektu *obj*.

Viz také `get_class()`, `is_subclass_of()`

is_subclass_of (PHP 4 >= 4.0.0)

Zjistit, jestli objekt patří do podtřídy určité třídy

`bool is_subclass_of (object obj, string superclass) \linebreak`

Tato funkce vrací `TRUE`, pokud je objekt *obj* instancí třídy, která je podtřídou *superclass*, jinak `FALSE`.

Viz také `get_class()`, `get_parent_class()`

method_exists (PHP 4 >= 4.0.0)

Zjistit, jestli má třída určitou metodu

`bool method_exists (object object, string method_name) \linebreak`

Tato funkce vrací `TRUE`, pokud má *object* definovanou metodu *method_name*, jinak `FALSE`.

X. ClibPDF functions

Úvod

ClibPDF lets you create PDF documents with PHP. It is available for download from FastIO (<http://www.fastio.com/>), but requires that you purchase a license for commercial use. ClibPDF functionality and API are similar to PDFlib.

This documentation should be read alongside the ClibPDF manual since it explains the library in much greater detail.

Many functions in the native ClibPDF and the PHP module, as well as in PDFlib, have the same name. All functions except for `cpdf_open()` take the handle for the document as their first parameter.

Currently this handle is not used internally since ClibPDF does not support the creation of several PDF documents at the same time. Actually, you should not even try it, the results are unpredictable. I can't oversee what the consequences in a multi threaded environment are. According to the author of ClibPDF this will change in one of the next releases (current version when this was written is 1.10). If you need this functionality use the `pdflib` module.

A nice feature of ClibPDF (and PDFlib) is the ability to create the pdf document completely in memory without using temporary files. It also provides the ability to pass coordinates in a predefined unit length. (This feature can also be simulated by `pdf_translate()` when using the PDFlib functions.)

Another nice feature of ClibPDF is the fact that any page can be modified at any time even if a new page has been already opened. The function `cpdf_set_current_page()` allows to leave the current page and presume modifying an other page.

Most of the functions are fairly easy to use. The most difficult part is probably creating a very simple PDF document at all. The following example should help you to get started. It creates a document with one page. The page contains the text "Times-Roman" in an outlined 30pt font. The text is underlined.

Předdefinované konstanty

Tyto konstanty jsou definovány tímto rozšířením a budou k dispozici pouze tehdy, bylo-li rozšíření

zkompileováno společně s PHP nebo dynamicky zavedeno za běhu.

CPDF_PM_NONE (integer)

CPDF_PM_OUTLINES (integer)

CPDF_PM_THUMBS (integer)

CPDF_PM_FULLSCREEN (integer)

CPDF_PL_SINGLE (integer)

CPDF_PL_1COLUMN (integer)

CPDF_PL_2LCOLUMN (integer)

CPDF_PL_2RCOLUMN (integer)

Příklady

Příklad 1. Simple ClibPDF Example

```
<?php
$cpdf = cpdf_open(0);
cpdf_page_init($cpdf, 1, 0, 595, 842, 1.0);
cpdf_add_outline($cpdf, 0, 0, 0, 1, "Page 1");
cpdf_begin_text($cpdf);
cpdf_set_font($cpdf, "Times-Roman", 30, "WinAnsiEncoding");
cpdf_set_text_rendering($cpdf, 1);
cpdf_text($cpdf, "Times Roman outlined", 50, 750);
cpdf_end_text($cpdf);
cpdf_moveto($cpdf, 50, 740);
cpdf_lineto($cpdf, 330, 740);
cpdf_stroke($cpdf);
cpdf_finalize($cpdf);
Header("Content-type: application/pdf");
cpdf_output_buffer($cpdf);
cpdf_close($cpdf);
?>
```

The pdflib distribution contains a more complex example which creates a series of pages with an analog clock. Here is that example converted into PHP using the ClibPDF extension:

Příklad 2. pdfclock example from pdflib 2.0 distribution

```
<?php
$radius = 200;
$margin = 20;
$pagecount = 40;

$pdf = cpdf_open(0);
cpdf_set_creator($pdf, "pdf_clock.php3");
cpdf_set_title($pdf, "Analog Clock");

while($pagecount-- > 0) {
    cpdf_page_init($pdf, $pagecount+1, 0, 2 * ($radius + $margin), 2 * ($radius + $margin), 1.0);

    cpdf_set_page_animation($pdf, 4, 0.5, 0, 0, 0); /* wipe */

    cpdf_translate($pdf, $radius + $margin, $radius + $margin);
    cpdf_save($pdf);
    cpdf_setrgbcolor($pdf, 0.0, 0.0, 1.0);

    /* minute strokes */
    cpdf_setlinewidth($pdf, 2.0);
    for ($alpha = 0; $alpha < 360; $alpha += 6)
    {
        cpdf_rotate($pdf, 6.0);
        cpdf_moveto($pdf, $radius, 0.0);
        cpdf_lineto($pdf, $radius-$margin/3, 0.0);
        cpdf_stroke($pdf);
    }

    cpdf_restore($pdf);
    cpdf_save($pdf);

    /* 5 minute strokes */
    cpdf_setlinewidth($pdf, 3.0);
    for ($alpha = 0; $alpha < 360; $alpha += 30)
    {
        cpdf_rotate($pdf, 30.0);
        cpdf_moveto($pdf, $radius, 0.0);
        cpdf_lineto($pdf, $radius-$margin, 0.0);
        cpdf_stroke($pdf);
    }

    $ltime = getdate();

    /* draw hour hand */
    cpdf_save($pdf);
    cpdf_rotate($pdf, -((($ltime['minutes']/60.0) + $ltime['hours'] - 3.0) * 30.0);
    cpdf_moveto($pdf, -$radius/10, -$radius/20);
    cpdf_lineto($pdf, $radius/2, 0.0);
```

```

cpdf_lineto($pdf, -$radius/10, $radius/20);
cpdf_closepath($pdf);
cpdf_fill($pdf);
cpdf_restore($pdf);

/* draw minute hand */
cpdf_save($pdf);
cpdf_rotate($pdf, -(($ltime['seconds']/60.0) + $ltime['minutes'] - 15.0) * 6.0);
cpdf_moveto($pdf, -$radius/10, -$radius/20);
cpdf_lineto($pdf, $radius * 0.8, 0.0);
cpdf_lineto($pdf, -$radius/10, $radius/20);
cpdf_closepath($pdf);
cpdf_fill($pdf);
cpdf_restore($pdf);

/* draw second hand */
cpdf_setrgbcolor($pdf, 1.0, 0.0, 0.0);
cpdf_setlinewidth($pdf, 2);
cpdf_save($pdf);
cpdf_rotate($pdf, -(($ltime['seconds'] - 15.0) * 6.0));
cpdf_moveto($pdf, -$radius/5, 0.0);
cpdf_lineto($pdf, $radius, 0.0);
cpdf_stroke($pdf);
cpdf_restore($pdf);

/* draw little circle at center */
cpdf_circle($pdf, 0, 0, $radius/30);
cpdf_fill($pdf);

cpdf_restore($pdf);

cpdf_finalize_page($pdf, $pagecount+1);
}

cpdf_finalize($pdf);
Header("Content-type: application/pdf");
cpdf_output_buffer($pdf);
cpdf_close($pdf);
?>

```

Viz také

See also the PDFlib extension documentation.

cpdf_add_annotation (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Adds annotation

void **cpdf_add_annotation** (int pdf document, float llx, float lly, float urx, float ury, string title, string content [, int mode]) \linebreak

The **cpdf_add_annotation()** adds a note with the lower left corner at (*llx*, *lly*) and the upper right corner at (*urx*, *ury*).

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

cpdf_add_outline (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Adds bookmark for current page

void **cpdf_add_outline** (int pdf document, string text) \linebreak

The **cpdf_add_outline()** function adds a bookmark with text *text* that points to the current page.

Příklad 1. Adding a page outline

```
<?php
$cpdf = cpdf_open(0);
cpdf_page_init($cpdf, 1, 0, 595, 842);
cpdf_add_outline($cpdf, 0, 0, 0, 1, "Page 1");
// ...
// some drawing
// ...
cpdf_finalize($cpdf);
Header("Content-type: application/pdf");
cpdf_output_buffer($cpdf);
cpdf_close($cpdf);
?>
```

cpdf_arc (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Draws an arc

void **cpdf_arc** (int pdf document, float x-coor, float y-coor, float radius, float start, float end [, int mode]) \linebreak

The **cpdf_arc()** function draws an arc with center at point (*x-coor*, *y-coor*) and radius *radius*, starting at angle *start* and ending at angle *end*.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also `cpdf_circle()`.

cpdf_begin_text (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Starts text section

void **cpdf_begin_text** (int pdf document) \linebreak

The **cpdf_begin_text()** function starts a text section. It must be ended with `cpdf_end_text()`.

Příklad 1. Text output

```
<?php
cpdf_begin_text($pdf);
cpdf_set_font($pdf, 16, "Helvetica", "WinAnsiEncoding");
cpdf_text($pdf, 100, 100, "Some text");
cpdf_end_text($pdf)
?>
```

See also `cpdf_end_text()`.

cpdf_circle (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Draw a circle

void **cpdf_circle** (int pdf document, float x-coor, float y-coor, float radius [, int mode]) \linebreak

The **cpdf_circle()** function draws a circle with center at point (*x-coor*, *y-coor*) and radius *radius*.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also `cpdf_arc()`.

cpdf_clip (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Clips to current path

void **cpdf_clip** (int pdf document) \linebreak

The **cpdf_clip()** function clips all drawing to the current path.

cpdf_close (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Closes the pdf document

```
void cpdf_close ( int pdf document) \linebreak
```

The **cpdf_close()** function closes the pdf document. This should be the last function even after **cpdf_finalize()**, **cpdf_output_buffer()** and **cpdf_save_to_file()**.

See also **cpdf_open()**.

cpdf_closepath (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Close path

```
void cpdf_closepath ( int pdf document) \linebreak
```

The **cpdf_closepath()** function closes the current path.

cpdf_closepath_fill_stroke (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Close, fill and stroke current path

```
void cpdf_closepath_fill_stroke ( int pdf document) \linebreak
```

The **cpdf_closepath_fill_stroke()** function closes, fills the interior of the current path with the current fill color and draws current path.

See also **cpdf_closepath()**, **cpdf_stroke()**, **cpdf_fill()**, **cpdf_setgray_fill()**, **cpdf_setgray()**, **cpdf_setrgbcolor_fill()**, **cpdf_setrgbcolor()**.

cpdf_closepath_stroke (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Close path and draw line along path

```
void cpdf_closepath_stroke ( int pdf document) \linebreak
```

The **cpdf_closepath_stroke()** function is a combination of **cpdf_closepath()** and **cpdf_stroke()**. Then clears the path.

See also **cpdf_closepath()**, **cpdf_stroke()**.

cpdf_continue_text (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Output text in next line

```
void cpdf_continue_text ( int pdf document, string text) \linebreak
```

The **cpdf_continue_text()** function outputs the string in *text* in the next line.

See also `cpdf_show_xy()`, `cpdf_text()`, `cpdf_set_leading()`, `cpdf_set_text_pos()`.

cpdf_curveto (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Draws a curve

```
void cpdf_curveto ( int pdf document, float x1, float y1, float x2, float y2, float x3, float y3 [, int mode]) \linebreak
```

The **cpdf_curveto()** function draws a Bezier curve from the current point to the point (*x3*, *y3*) using (*x1*, *y1*) and (*x2*, *y2*) as control points.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also `cpdf_moveto()`, `cpdf_rmoveto()`, `cpdf_rlineto()`, `cpdf_lineto()`.

cpdf_end_text (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Ends text section

```
void cpdf_end_text ( int pdf document) \linebreak
```

The **cpdf_end_text()** function ends a text section which was started with `cpdf_begin_text()`.

Příklad 1. Text output

```
<?php
cpdf_begin_text($pdf);
cpdf_set_font($pdf, 16, "Helvetica", "WinAnsiEncoding");
cpdf_text($pdf, 100, 100, "Some text");
cpdf_end_text($pdf)
?>
```

See also `cpdf_begin_text()`.

cpdf_fill (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Fill current path

```
void cpdf_fill ( int pdf document) \linebreak
```

The **cpdf_fill()** function fills the interior of the current path with the current fill color.

See also `cpdf_closepath()`, `cpdf_stroke()`, `cpdf_setgray_fill()`, `cpdf_setgray()`, `cpdf_setrgbcolor_fill()`, `cpdf_setrgbcolor()`.

cpdf_fill_stroke (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Fill and stroke current path

```
void cpdf_fill_stroke ( int pdf document) \linebreak
```

The **cpdf_fill_stroke()** function fills the interior of the current path with the current fill color and draws current path.

See also `cpdf_closepath()`, `cpdf_stroke()`, `cpdf_fill()`, `cpdf_setgray_fill()`, `cpdf_setgray()`, `cpdf_setrgbcolor_fill()`, `cpdf_setrgbcolor()`.

cpdf_finalize (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Ends document

```
void cpdf_finalize ( int pdf document) \linebreak
```

The **cpdf_finalize()** function ends the document. You still have to call `cpdf_close()`

See also `cpdf_close()`.

cpdf_finalize_page (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Ends page

```
void cpdf_finalize_page ( int pdf document, int page number) \linebreak
```

The **cpdf_finalize_page()** function ends the page with page number *page number*.

This function is only for saving memory. A finalized page takes less memory but cannot be modified anymore.

See also `cpdf_page_init()`.

cpdf_global_set_document_limits (PHP 4 >= 4.0.0)

Sets document limits for any pdf document

```
void cpdf_global_set_document_limits ( int maxpages, int maxfonts, int maximages, int maxannotations,
int maxobjects) \linebreak
```

The **cpdf_global_set_document_limits()** function sets several document limits. This function has to be called before **cpdf_open()** to take effect. It sets the limits for any document open afterwards.

See also **cpdf_open()**.

cpdf_import_jpeg (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Opens a JPEG image

```
int cpdf_import_jpeg ( int pdf document, string file name, float x-coor, float y-coor, float angle, float width,
float height, float x-scale, float y-scale [, int mode]) \linebreak
```

The **cpdf_import_jpeg()** function opens an image stored in the file with the name *file name*. The format of the image has to be jpeg. The image is placed on the current page at position (*x-coor*, *y-coor*). The image is rotated by *angle* degrees.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also **cpdf_place_inline_image()**.

cpdf_lineto (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Draws a line

```
void cpdf_lineto ( int pdf document, float x-coor, float y-coor [, int mode]) \linebreak
```

The **cpdf_lineto()** function draws a line from the current point to the point with coordinates (*x-coor*, *y-coor*).

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also **cpdf_moveto()**, **cpdf_rmoveto()**, **cpdf_curveto()**.

cpdf_moveto (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets current point

```
void cpdf_moveto ( int pdf document, float x-coor, float y-coor [, int mode]) \linebreak
```

The **cpdf_moveto()** function set the current point to the coordinates *x-coor* and *y-coor*.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

cpdf_newpath (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Starts a new path

```
void cpdf_newpath ( int pdf document) \linebreak
```

The **cpdf_newpath()** starts a new path on the document given by the *pdf document* parameter.

cpdf_open (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Opens a new pdf document

```
int cpdf_open ( int compression [, string filename]) \linebreak
```

The **cpdf_open()** function opens a new pdf document. The first parameter turns document compression on if it is unequal to 0. The second optional parameter sets the file in which the document is written. If it is omitted the document is created in memory and can either be written into a file with the **cpdf_save_to_file()** or written to standard output with **cpdf_output_buffer()**.

Poznámka: The return value will be needed in further versions of ClibPDF as the first parameter in all other functions which are writing to the pdf document.

The ClibPDF library takes the filename "-" as a synonym for stdout. If PHP is compiled as an apache module this will not work because the way ClibPDF outputs to stdout does not work with apache. You can solve this problem by skipping the filename and using **cpdf_output_buffer()** to output the pdf document.

See also **cpdf_close()**, **cpdf_output_buffer()**.

cpdf_output_buffer (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Outputs the pdf document in memory buffer

```
void cpdf_output_buffer ( int pdf document) \linebreak
```

The **cpdf_output_buffer()** function outputs the pdf document to stdout. The document has to be created in memory which is the case if **cpdf_open()** has been called with no filename parameter.

See also **cpdf_open()**.

cpdf_page_init (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Starts new page

```
void cpdf_page_init ( int pdf document, int page number, int orientation, float height, float width [, float unit]) \linebreak
```

The **cpdf_page_init()** function starts a new page with height *height* and width *width*. The page has number *page number* and orientation *orientation*. *orientation* can be 0 for portrait and 1 for landscape. The last optional parameter *unit* sets the unit for the coordinate system. The value should be the number of postscript points per unit. Since one inch is equal to 72 points, a value of 72 would set the unit to one inch. The default is also 72.

See also **cpdf_set_current_page()**.

cpdf_place_inline_image (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Places an image on the page

```
void cpdf_place_inline_image ( int pdf document, int image, float x-coor, float y-coor, float angle, float width, float height [, int mode]) \linebreak
```

The **cpdf_place_inline_image()** function places an image created with the php image functions on the page at position (*x-coor*, *y-coor*). The image can be scaled at the same time.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also **cpdf_import_jpeg()**.

cpdf_rect (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Draw a rectangle

```
void cpdf_rect ( int pdf document, float x-coor, float y-coor, float width, float height [, int mode]) \linebreak
```

The **cpdf_rect()** function draws a rectangle with its lower left corner at point (*x-coor*, *y-coor*). This width is set to *width*. This height is set to *height*.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

cpdf_restore (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Restores formerly saved environment

```
void cpdf_restore ( int pdf document) \linebreak
```


The **cpdf_restore()** function restores the environment saved with **cpdf_save()**. It works like the postscript command **grestore**. Very useful if you want to translate or rotate an object without effecting other objects.

Příklad 1. Save/Restore

```
<?php
cpdf_save($pdf);
// do all kinds of rotations, transformations, ...
cpdf_restore($pdf)
?>
```

See also **cpdf_save()**.

cpdf_rlineto (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Draws a line

void **cpdf_rlineto** (int pdf document, float x-coor, float y-coor [, int mode]) \linebreak

The **cpdf_rlineto()** function draws a line from the current point to the relative point with coordinates (*x-coor*, *y-coor*).

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also **cpdf_moveto()**, **cpdf_rmoveto()**, **cpdf_curveto()**.

cpdf_rmoveto (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Sets current point

void **cpdf_rmoveto** (int pdf document, float x-coor, float y-coor [, int mode]) \linebreak

The **cpdf_rmoveto()** function set the current point relative to the coordinates *x-coor* and *y-coor*.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also **cpdf_moveto()**.

cpdf_rotate (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets rotation

void **cpdf_rotate** (int pdf document, float angle) \linebreak

The **cpdf_rotate()** function set the rotation in degrees to *angle*.

cpdf_rotate_text (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Sets text rotation angle

void **cpdf_rotate_text** (int pdfdoc, float angle) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cpdf_save (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Saves current environment

void **cpdf_save** (int pdf document) \linebreak

The **cpdf_save()** function saves the current environment. It works like the postscript command gsave. Very useful if you want to translate or rotate an object without effecting other objects.

See also cpdf_restore().

cpdf_save_to_file (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Writes the pdf document into a file

void **cpdf_save_to_file** (int pdf document, string filename) \linebreak

The **cpdf_save_to_file()** function outputs the pdf document into a file if it has been created in memory.

This function is not needed if the pdf document has been open by specifying a filename as a parameter of cpdf_open().

See also cpdf_output_buffer(), cpdf_open().

cpdf_scale (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets scaling

void **cpdf_scale** (int pdf document, float x-scale, float y-scale) \linebreak

The **cpdf_scale()** function set the scaling factor in both directions.

cpdf_set_action_url (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Sets hyperlink

```
void cpdf_set_action_url ( int pdfdoc, float xll, float yll, float xur, float yur, string url [, int mode]) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cpdf_set_char_spacing (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets character spacing

```
void cpdf_set_char_spacing ( int pdf document, float space) \linebreak
```

The **cpdf_set_char_spacing()** function sets the spacing between characters.

See also **cpdf_set_word_spacing()**, **cpdf_set_leading()**.

cpdf_set_creator (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets the creator field in the pdf document

```
void cpdf_set_creator ( string creator) \linebreak
```

The **cpdf_set_creator()** function sets the creator of a pdf document.

See also **cpdf_set_subject()**, **cpdf_set_title()**, **cpdf_set_keywords()**.

cpdf_set_current_page (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Sets current page

```
void cpdf_set_current_page ( int pdf document, int page number) \linebreak
```

The **cpdf_set_current_page()** function set the page on which all operations are performed. One can switch between pages until a page is finished with **cpdf_finalize_page()**.

See also **cpdf_finalize_page()**.

cpdf_set_font (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Select the current font face and size

```
void cpdf_set_font ( int pdf document, string font name, float size, string encoding) \linebreak
```

The **cpdf_set_font()** function sets the current font face, font size and encoding. Currently only the standard postscript fonts are supported.

The last parameter *encoding* can take the following values: "MacRomanEncoding", "MacExpertEncoding", "WinAnsiEncoding", and "NULL". "NULL" stands for the font's built-in encoding.

See the ClibPDF Manual for more information, especially how to support asian fonts.

cpdf_set_font_directories (PHP 4 >= 4.0.6)

Sets directories to search when using external fonts

```
void cpdf_set_font_directories ( int pdfdoc, string pfmdir, string pfmdir) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cpdf_set_font_map_file (PHP 4 >= 4.0.6)

Sets fontname to filename translation map when using external fonts

```
void cpdf_set_font_map_file ( int pdfdoc, string filename) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cpdf_set_horiz_scaling (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets horizontal scaling of text

```
void cpdf_set_horiz_scaling ( int pdf document, float scale) \linebreak
```

The **cpdf_set_horiz_scaling()** function sets the horizontal scaling to *scale* percent.

cpdf_set_keywords (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets the keywords field of the pdf document

```
void cpdf_set_keywords ( string keywords) \linebreak
```

The **cpdf_set_keywords()** function sets the keywords of a pdf document.

See also `cpdf_set_title()`, `cpdf_set_creator()`, `cpdf_set_subject()`.

cpdf_set_leading (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets distance between text lines

```
void cpdf_set_leading ( int pdf document, float distance) \linebreak
```

The **cpdf_set_leading()** function sets the distance between text lines. This will be used if text is output by `cpdf_continue_text()`.

See also `cpdf_continue_text()`.

cpdf_set_page_animation (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Sets duration between pages

```
void cpdf_set_page_animation ( int pdf document, int transition, float duration) \linebreak
```

The **cpdf_set_page_animation()** function set the transition between following pages.

The value of *transition* can be

- 0 for none,
- 1 for two lines sweeping across the screen reveal the page,
- 2 for multiple lines sweeping across the screen reveal the page,
- 3 for a box reveals the page,
- 4 for a single line sweeping across the screen reveals the page,
- 5 for the old page dissolves to reveal the page,
- 6 for the dissolve effect moves from one screen edge to another,
- 7 for the old page is simply replaced by the new page (default)

The value of *duration* is the number of seconds between page flipping.

cpdf_set_subject (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets the subject field of the pdf document

```
void cpdf_set_subject ( string subject) \linebreak
```

The **cpdf_set_subject()** function sets the subject of a pdf document.

See also **cpdf_set_title()**, **cpdf_set_creator()**, **cpdf_set_keywords()**.

cpdf_set_text_matrix (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets the text matrix

```
void cpdf_set_text_matrix ( int pdf document, array matrix) \linebreak
```

The **cpdf_set_text_matrix()** function sets a matrix which describes a transformation applied on the current text font.

cpdf_set_text_pos (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets text position

```
void cpdf_set_text_pos ( int pdf document, float x-coor, float y-coor [, int mode]) \linebreak
```

The **cpdf_set_text_pos()** function sets the position of text for the next **cpdf_show()** function call.

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

See also **cpdf_show()**, **cpdf_text()**.

cpdf_set_text_rendering (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Determines how text is rendered

```
void cpdf_set_text_rendering ( int pdf document, int mode) \linebreak
```

The **cpdf_set_text_rendering()** function determines how text is rendered.

The possible values for *mode* are 0=fill text, 1=stroke text, 2=fill and stroke text, 3=invisible, 4=fill text and add it to clipping path, 5=stroke text and add it to clipping path, 6=fill and stroke text and add it to clipping path, 7=add it to clipping path.

cpdf_set_text_rise (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets the text rise

```
void cpdf_set_text_rise ( int pdf document, float value) \linebreak
```

The **cpdf_set_text_rise()** function sets the text rising to *value* units.

cpdf_set_title (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets the title field of the pdf document

```
void cpdf_set_title ( string title) \linebreak
```

The **cpdf_set_title()** function sets the title of a pdf document.

See also `cpdf_set_subject()`, `cpdf_set_creator()`, `cpdf_set_keywords()`.

cpdf_set_viewer_preferences (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

How to show the document in the viewer

```
void cpdf_set_viewer_preferences ( int pdfdoc, array preferences) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cpdf_set_word_spacing (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets spacing between words

```
void cpdf_set_word_spacing ( int pdf document, float space) \linebreak
```

The **cpdf_set_word_spacing()** function sets the spacing between words.

See also `cpdf_set_char_spacing()`, `cpdf_set_leading()`.

cpdf_setdash (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets dash pattern

```
void cpdf_setdash ( int pdf document, float white, float black) \linebreak
```

The **cpdf_setdash()** function set the dash pattern *white* white units and *black* black units. If both are 0 a solid line is set.

cpdf_setflat (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets flatness

void **cpdf_setflat** (int pdf document, float value) \linebreak

The **cpdf_setflat()** function set the flatness to a value between 0 and 100.

cpdf_setgray (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets drawing and filling color to gray value

void **cpdf_setgray** (int pdf document, float gray value) \linebreak

The **cpdf_setgray()** function sets the current drawing and filling color to the given gray value.

See also **cpdf_setrgbcolor_stroke()**, **cpdf_setrgbcolor_fill()**.

cpdf_setgray_fill (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets filling color to gray value

void **cpdf_setgray_fill** (int pdf document, float value) \linebreak

The **cpdf_setgray_fill()** function sets the current gray value to fill a path.

See also **cpdf_setrgbcolor_fill()**.

cpdf_setgray_stroke (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets drawing color to gray value

void **cpdf_setgray_stroke** (int pdf document, float gray value) \linebreak

The **cpdf_setgray_stroke()** function sets the current drawing color to the given gray value.

See also **cpdf_setrgbcolor_stroke()**.

cpdf_setlinecap (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets linecap parameter

void **cpdf_setlinecap** (int pdf document, int value) \linebreak

The **cpdf_setlinecap()** function set the linecap parameter between a value of 0 and 2. 0 = butt end, 1 = round, 2 = projecting square.

cpdf_setlinejoin (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets linejoin parameter

void **cpdf_setlinejoin** (int pdf document, long value) \linebreak

The **cpdf_setlinejoin()** function set the linejoin parameter between a value of 0 and 2. 0 = miter, 1 = round, 2 = bevel.

cpdf_setlinewidth (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets line width

void **cpdf_setlinewidth** (int pdf document, float width) \linebreak

The **cpdf_setlinewidth()** function set the line width to *width*.

cpdf_setmiterlimit (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets miter limit

void **cpdf_setmiterlimit** (int pdf document, float value) \linebreak

The **cpdf_setmiterlimit()** function set the miter limit to a value greater or equal than 1.

cpdf_setrgbcolor (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets drawing and filling color to rgb color value

void **cpdf_setrgbcolor** (int pdf document, float red value, float green value, float blue value) \linebreak

The **cpdf_setrgbcolor()** function sets the current drawing and filling color to the given rgb color value.

See also **cpdf_setrgbcolor_stroke()**, **cpdf_setrgbcolor_fill()**.

cpdf_setrgbcolor_fill (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets filling color to rgb color value

void **cpdf_setrgbcolor_fill** (int pdf document, float red value, float green value, float blue value) \linebreak

The **cpdf_setrgbcolor_fill()** function sets the current rgb color value to fill a path.

See also **cpdf_setrgbcolor_stroke()**, **cpdf_setrgbcolor()**.

cpdf_setrgbcolor_stroke (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets drawing color to rgb color value

void **cpdf_setrgbcolor_stroke** (int pdf document, float red value, float green value, float blue value) \linebreak

The **cpdf_setrgbcolor_stroke()** function sets the current drawing color to the given rgb color value.

See also `cpdf_setrgbcolor_fill()`, `cpdf_setrgbcolor()`.

cpdf_show (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Output text at current position

void **cpdf_show** (int pdf document, string text) \linebreak

The **cpdf_show()** function outputs the string in *text* at the current position.

See also `cpdf_text()`, `cpdf_begin_text()`, `cpdf_end_text()`.

cpdf_show_xy (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Output text at position

void **cpdf_show_xy** (int pdf document, string text, float x-coor, float y-coor [, int mode]) \linebreak

The **cpdf_show_xy()** function outputs the string *text* at position with coordinates (*x-coor*, *y-coor*).

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

Poznámka: The function **cpdf_show_xy()** is identical to `cpdf_text()` without the optional parameters.

See also `cpdf_text()`.

cpdf_stringwidth (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Returns width of text in current font

float **cpdf_stringwidth** (int pdf document, string text) \linebreak

The **cpdf_stringwidth()** function returns the width of the string in *text*. It requires a font to be set before.

See also `cpdf_set_font()`.

cpdf_stroke (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Draw line along path

```
void cpdf_stroke ( int pdf document) \linebreak
```

The **cpdf_stroke()** function draws a line along current path.

See also `cpdf_closepath()`, `cpdf_closepath_stroke()`.

cpdf_text (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Output text with parameters

```
void cpdf_text ( int pdf document, string text, float x-coor, float y-coor [, int mode [, float orientation [, int alignmode]]]) \linebreak
```

The **cpdf_text()** function outputs the string *text* at position with coordinates (*x-coor*, *y-coor*).

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit. The optional parameter *orientation* is the rotation of the text in degree. The optional parameter *alignmode* determines how the text is aligned.

See the ClibPDF documentation for possible values.

See also `cpdf_show_xy()`.

cpdf_translate (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Sets origin of coordinate system

```
void cpdf_translate ( int pdf document, float x-coor, float y-coor [, int mode]) \linebreak
```

The **cpdf_translate()** function set the origin of coordinate system to the point (*x-coor*, *y-coor*).

The optional parameter *mode* determines the unit length. If it's 0 or omitted the default unit as specified for the page is used. Otherwise the coordinates are measured in postscript points disregarding the current unit.

XI. Crack functions

Úvod

These functions allow you to use the CrackLib library to test the 'strength' of a password. The 'strength' of a password is tested by that checks length, use of upper and lower case and checked against the specified CrackLib dictionary. CrackLib will also give helpful diagnostic messages that will help 'strengthen' the password.

Požadavky

More information regarding CrackLib along with the library can be found at <http://www.users.dircon.co.uk/~crypto/>.

Instalace

In order to use these functions, you must compile PHP with Crack support by using the `--with-crack[=DIR]` option.

Konfigurace běhu

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Typy prostředků

Toto rozšíření nemá definován žádný typ prostředku (resource).

Předdefinované konstanty

Toto rozšíření nemá definovány žádné konstanty.

Příklady

This example shows how to open a CrackLib dictionary, test a given password, retrieve any diagnostic messages, and close the dictionary.

Příklad 1. CrackLib example

```
<?php
```

```
// Open CrackLib Dictionary
$dictionary = crack_opendict('/usr/local/lib/pw_dict')
    or die('Unable to open CrackLib dictionary');

// Perform password check
$check = crack_check($dictionary, 'gx9A2s0x');

// Retrieve messages
$diag = crack_getlastmessage();
echo $diag; // 'strong password'

// Close dictionary
crack_closedict($dictionary);
?>
```

Poznámka: If `crack_check()` returns `TRUE`, `crack_getlastmessage()` will return 'strong password'.

crack_check (PHP 4 >= 4.0.5)

Performs an obscure check with the given password

bool **crack_check** ([resource dictionary, string password]) \linebreak

Returns TRUE if *password* is strong, or FALSE otherwise.

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

crack_check() performs an obscure check with the given *password* on the specified *dictionary* . If *dictionary* is not specified, the last opened dictionary is used.

crack_closedict (PHP 4 >= 4.0.5)

Closes an open CrackLib dictionary

bool **crack_closedict** ([resource dictionary]) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

crack_closedict() closes the specified *dictionary* identifier. If *dictionary* is not specified, the current dictionary is closed.

crack_getlastmessage (PHP 4 >= 4.0.5)

Returns the message from the last obscure check

string **crack_getlastmessage** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

crack_getlastmessage() returns the message from the last obscure check.

crack_opendict (PHP 4 >= 4.0.5)

Opens a new CrackLib dictionary

resource **crack_opendict** (string dictionary) \linebreak

Returns a dictionary resource identifier on success, or `FALSE` on failure.

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

crack_opendict() opens the specified CrackLib *dictionary* for use with `crack_check()`.

Poznámka: Only one dictionary may be open at a time.

See also: `crack_check()`, and `crack_closedict()`.

XII. Funkce pro práci s CURL, Client URL Library

PHP podporuje libcurl, knihovnu vytvořenou Danielem Stenbergem, která umožňuje spojení a komunikaci s mnoha různými typy serverů v mnoha různých typech protokolů. libcurl v současné době podporuje http, https, ftp, gopher, telnet, dict, file a ldap protokoly. libcurl také podporuje HTTPS certifikáty, HTTP POST, HTTP PUT, FTP uploady (toto umožňuje i ftp extenze PHP), HTTP formulářové uploady, proxy, cookies a user+password autentikaci.

Pokud chcete používat CURL funkce, musíte nainstalovat CURL (<http://curl.haxx.se/>). PHP vyžaduje použití CURL 7.0.2-beta nebo vyšší. S verzemi CURL staršími než 7.0.2-beta PHP nebude pracovat.

Dále musíte PHP zkompileovat s `--with-curl[=DIR]`, kde DIR je umístění adresáře obsahujícího lib a include adresáře. V "include" adresáři by měl být adresář pojmenovaný "curl", který by měl obsahovat soubory easy.h and curl.h. V adresáři "lib" by měl být soubor pojmenovaný "libcurl.a".

Tyto funkce byly přidány v PHP 4.0.2.

Pokud máte PHP zkompilevané s podporou CURL, můžete začít používat CURL funkce. Základní principem těchto funkcí je, že pomocí `curl_init()` inicializujete CURL session, potom pomocí `curl_exec()` nastavíte hodnoty přenosu a nakonec session zavřete pomocí `curl_close()`. Následuje ukázka, která využívá CURL funkce ke stažení homepage PHP do souboru:

Příklad 1. Použití CURL extenze ke stažení homepage PHP

```
<?php

$ch = curl_init ("http://www.php.net/");
$fhp = fopen ("php_homepage.txt", "w");

curl_setopt ($ch, CURLOPT_FILE, $fhp);
curl_setopt ($ch, CURLOPT_HEADER, 0);

curl_exec ($ch);
curl_close ($ch);
fclose ($fhp);
?>
```


curl_close (PHP 4 >= 4.0.2)

Zavřít CURL session

void **curl_close** (int *ch*) \linebreak

Tato funkce zavře CURL session a uvolní všechny zdroje. CURL handle, *ch*, se také smaže.

curl_exec (PHP 4 >= 4.0.2)

Provést CURL session

bool **curl_exec** (int *ch*) \linebreak

Tuto funkci byste měli zavolat po inicializaci CURL session a nastavení všech jejích parametrů. Jejím účelem je provést předdefinovanou CURL session (určenou argumentem *ch*).

curl_init (PHP 4 >= 4.0.2)

Inicializovat CURL session

int **curl_init** ([string *url*]) \linebreak

curl_init() inicializuje novou session a vrací CURL handle pro použití s funkcemi `curl_setopt()`, `curl_exec()` a `curl_close()`. Pokud je přítomen volitelný argument *url*, `CURLOPT_URL` se nastaví na hodnotu tohoto argumentu. Můžete to udělat i ručně, pomocí funkce `curl_setopt()`.

Příklad 1. Inicializace nové CURL session a stažení webové stránky

```

<?php
$ch = curl_init();

curl_setopt ($ch, CURLOPT_URL, "http://www.zend.com/");
curl_setopt ($ch, CURLOPT_HEADER, 0);

curl_exec ($ch);

curl_close ($ch);
?>

```

Viz také: `curl_close()`, `curl_setopt()`

curl_setopt (PHP 4 >= 4.0.2)

Nastavit parametr CURL transferu

bool **curl_setopt** (int *ch*, string *option*, mixed *value*) \linebreak

curl_setopt() nastavuje parametry CURL session *ch*. *option* je parametr, který chcete nastavit a *value* je hodnota, na kterou se má *option* nastavit.

Argument *value* by měl u následujících hodnot argumentu *option* obsahovat integer:

- **CURLOPT_INFILESIZE**: Tento parametr by měl u uploadů obsahovat velikost uploadovaného souboru.
- **CURLOPT_VERBOSE**: Pokud chcete, aby CURL podávala zprávy o všem co se děje, nastavte tento parametr na nenulovou hodnotu.
- **CURLOPT_HEADER**: Pokud chcete, aby výstup obsahoval hlavičky, nastavte tento parametr na nenulovou hodnotu.
- **CURLOPT_NOPROGRESS**: Pokud PHP nemá zobrazit měřidlo postupu CURL transferu, nastavte tento parametr na nenulovou hodnotu.

Poznámka: PHP tento parametr automaticky nastavuje na nenulovou hodnotu, změna je vhodná pouze pro účely ladění.

- **CURLOPT_NOBODY**: Pokud nechete, aby bylo ve výstupu zahrnuto tělo výstupu, nastavte tento parametr na nenulovou hodnotu.
- **CURLOPT_FAILONERROR**: Pokud má PHP tiše ukončit transfer po přijetí HTTP server kódu většího než 300, nastavte tento parametr na nenulovou hodnotu. Defaultní chování je ignorovat návratový kód a normálně vrátit stránku.
- **CURLOPT_UPLOAD**: Pokud chcete PHP připravit na upload, nastavte tento parametr na nenulovou hodnotu.
- **CURLOPT_POST**: Pokud chcete, aby PHP provedl běžný HTTP POST požadavek, nastavte tento parametr na nenulovou hodnotu. Jedná se o běžný application/x-www-form-urlencoded POST požadavek, který se většinou používá u HTML formulářů.
- **CURLOPT_FTPLISTONLY**: Pokud chcete, aby PHP vypsalo názvy souborů v FTP adresáři, nastavte tento parametr na nenulovou hodnotu.
- **CURLOPT_FTPAPPEND**: Pokud chcete, aby PHP místo přepsání vzdáleného souboru připojilo upload k jeho obsahu, nastavte tento parametr na nenulovou hodnotu.
- **CURLOPT_NETRC**: Pokud má PHP ve vašem ~/.netrc souboru hledat vaše uživatelské jméno a heslo pro server ke kterému se připojujete.
- **CURLOPT_FOLLOWLOCATION**: Pokud má PHP provádět přesměrování u případných "Location: " hlaviček vrácených serverem. (Pozn.: rekurzivní, PHP provede přesměrování pro všechny "Location: " hlavičky, které přijme.)
- **CURLOPT_PUT**: Pokud chcete uploadovat soubor pomocí HTTP metody PUT, nastavte tento parametr na nenulovou hodnotu. Uploadovaný soubor musí být určen parametry CURLOPT_INFILE a CURLOPT_INFILESIZE.
- **CURLOPT_MUTE**: Pokud má být PHP naprosto tiché ohledně CURL funkcí, nastavte tento parametr na nenulovou hodnotu.
- **CURLOPT_TIMEOUT**: Integer určující maximální čas ve vteřinách, který mohou CURL funkce zabrat.

- *CURLOPT_LOW_SPEED_LIMIT*: Integer určující minimální rychlost přenosu v bytech za sekundu. Pokud rychlost přenosu klesne pod tento limit po dobu *CURLOPT_LOW_SPEED_TIME* sekund, PHP ukončí transfer.
- *CURLOPT_LOW_SPEED_TIME*: Integer určující čas ve vteřinách. Pokud rychlost přenosu klesne na tuto dobu pod *CURLOPT_LOW_SPEED_LIMIT*, PHP zruší transfer.
- *CURLOPT_RESUME_FROM*: Integer určující offset v bytech, na kterém má transfer začít.
- *CURLOPT_SSLVERSION*: Integer určující, jaká verze SSL (2 nebo 3) se má použít. Defaultně se PHP pokusí určit verzi samo, ale v některých případech je nutno verzi určit manuálně.
- *CURLOPT_TIMECONDITION*: Definující chování *CURLOPT_TIMEVALUE*. Tento parametr může nabýt buď hodnoty *TIMECOND_IFMODSINCE* nebo *TIMECOND_ISUNMODSINCE*. Funguje pouze u HTTP přenosů.
- *CURLOPT_TIMEVALUE*: Integer určující počet vteřin od 1. ledna 1970. Tento čas se použije podle intervalu *CURLOPT_TIMEVALUE*, default je použití *TIMECOND_IFMODSINCE*.

Argument *value* by měl u následujících hodnot argumentu *option* obsahovat řetězec:

- *CURLOPT_URL*: Toto je URL, kterou má PHP stáhnout. Tento parametr můžete také nastavit při inicializaci CURL session pomocí funkce *curl_init()*.
- *CURLOPT_USERPWD*: Řetězec ve tvaru [username]:[password] pro použití při spojení.
- *CURLOPT_PROXYUSERPWD*: Řetězec ve tvaru [username]:[password] pro použití při spojení s HTTP proxy.
- *CURLOPT_RANGE*: Pass the specified range you want. It should be in the "X-Y" format, where X or Y may be left out. The HTTP transfers also support several intervals, seperated with commas as in X-Y,N-M.
- *CURLOPT_POSTFIELDS*: Řetězec obsahující kompletní data, která se mají odeslat v HTTP POST požadavku.
- *CURLOPT_REFERER*: Řetězec obsahující "referer" hlavičku pro použití v HTTP požadavku.
- *CURLOPT_USERAGENT*: Řetězec obsahující "user-agent" hlavičku pro použití v HTTP požadavku.
- *CURLOPT_FTPPORT*: Řetězec, na jehož základě se získá IP adresa pro FTP "POST" instrukci. POST instrukce říká serveru, aby se připojil na danou IP adresu. Tento řetězec může obsahovat IP adresu, hostname, a network interface name (under UNIX) nebo '-' (použije se defaultní IP adresa systému).
- *CURLOPT_COOKIE*: Řetězec obsahující cookie, který se má poslat v HTTP hlavičce tohoto přenosu.
- *CURLOPT_SSLCERT*: Řetězec obsahující název souboru PEM certifikátu.
- *CURLOPT_SSLCERTPASSWD*: Řetězec obsahující heslo vyžadované pro použití *CURLOPT_SSLCERT* certifikátu.
- *CURLOPT_COOKIEFILE*: Řetězec obsahující název souboru obsahujícího cookie data. Cookie soubor může být buď v Netscape formátu nebo obsahovat HTTP hlavičky.
- *CURLOPT_CUSTOMREQUEST*: Řetězec, který se má v HTTP požadavku použít místo GET nebo HEAD. Toto je užitečné při DELETE či jiných, obskurnějších HTTP požadavcích.

Poznámka: Používejte pouze v případě, že váš server tento příkaz podporuje.

Následující parametry očekávají deskriptor vrácený funkcí `fopen()`:

- `CURLOPT_FILE`: Soubor, do kterého se má umístit výstup CURL transferu. Default je `STDOUT`.
- `CURLOPT_INFILE`: Soubor, který obsahuje vstup CURL transferu.
- `CURLOPT_WRITEHEADER`: Soubor, do kterého se mají zapsat hlavičky výstupu.
- `CURLOPT_STDERR`: Soubor, do kterého se mají zapisovat chyby místo na `STDERR`.

curl_version (PHP 4 >= 4.0.2)

Vrátit verzi CURL

string **curl_version** (void) \linebreak

curl_version() vrací řetězec obsahující použitou verzi CURL.

XIII. Cybercash platební funkce

Tyto funkce jsou dostupné pouze pokud bylo PHP zkompileováno s `--with-cybercash=[DIR]`.
Tyto funkce byly přidány v PHP 4.

cybercash_base64_decode (PHP 4 >= 4.0.0)

string **cybercash_base64_decode** (string inbuff) \linebreak

cybercash_base64_encode (PHP 4 >= 4.0.0)

???

string **cybercash_base64_encode** (string inbuff) \linebreak

cybercash_decr (PHP 4 >= 4.0.0)

???

array **cybercash_decr** (string wmk, string sk, string inbuff) \linebreak

tato funkce vrací asociativní pole s elementem "errcode", a pokud je "errcode" FALSE, "outbuff" (string), "outLth" (long) a "macbuff" (string).

cybercash_encr (PHP 4 >= 4.0.0)

???

array **cybercash_encr** (string wmk, string sk, string inbuff) \linebreak

Tato funkce vrací asociativní pole s elementem "errcode", a pokud je "errcode" FALSE, "outbuff" (string), "outLth" (long) and "macbuff" (string).

XIV. Crédit Mutuel CyberMUT functions

Úvod

This extension allows you to process credit cards transactions using Crédit Mutuel CyberMUT system (http://www.creditmutuel.fr/centre_commercial/vendez_sur_internet.html).

CyberMUT is a popular Web Payment Service in France, provided by the Crédit Mutuel bank. If you are foreign in France, these functions will not be useful for you.

The use of these functions is almost identical to the original SDK functions, except for the parameters of return for `cybermut_creerformulairecm()` and `cybermut_crerreponsecm()`, which are returned directly by functions PHP, whereas they had passed in reference in the original functions.

These functions have been added in PHP 4.0.6.

Poznámka: These functions only provide a link to CyberMUT SDK. Be sure to read the CyberMUT Developers Guide for full details of the required parameters.

Instalace

These functions are only available if PHP has been compiled with the `--with-cybermut[=DIR]` option, where `DIR` is the location of `libcm-mac.a` and `cm-mac.h`. You will require the appropriate SDK for your platform, which may be sent to you after your CyberMUT's subscription (contact them via Web, or go to the nearest Crédit Mutuel).

cybermut_creerformulairecm (PHP 4 >= 4.0.5)

Generate HTML form of request for payment

string **cybermut_creerformulairecm** (string url_CM, string version, string TPE, string montant, string ref_commande, string texte_libre, string url_retour, string url_retour_ok, string url_retour_err, string langue, string code_societe, string texte_bouton) \linebreak

cybermut_creerformulairecm() is used to generate the HTML form of request for payment.

Príkklad 1. First step of payment (equiv cgi1.c)

```
<?php
// Directory where the keys are located
putenv("CMKEYDIR=/var/creditmut/cles");

// Version number
$VERSION="1.2";

$retour = cybermut_creerformulairecm(
    "https://www.creditmutuel.fr/test/telepaiement/paiement.cgi",
    $VERSION,
    "1234567890",
    "300FRF",
    $REFERENCE,
    $TEXTE_LIBRE,
    $URL_RETOUR,
    $URL_RETOUR_OK,
    $URL_RETOUR_ERR,
    "français",
    "company",
    "Paielement par carte bancaire");

echo $retour;
?>
```

See also **cybermut_testmac()** and **cybermut_creerreponsecm()**.

cybermut_creerreponsecm (PHP 4 >= 4.0.5)

Generate the acknowledgement of delivery of the confirmation of payment

string **cybermut_creerreponsecm** (string phrase) \linebreak

cybermut_creerreponsecm() returns a string containing delivery acknowledgement message.

The parameter is "OK" if the message of confirmation of the payment was correctly identified by **cybermut_testmac()**. Any other chain is regarded as an error message.

See also **cybermut_creerformulairecm()** and **cybermut_testmac()**.

cybermut_testmac (PHP 4 >= 4.0.5)

Make sure that there no was data diddling contained in the received message of confirmation

bool **cybermut_testmac** (string code_MAC, string version, string TPE, string cdate, string montant, string ref_commande, string texte_libre, string code-retour) \linebreak

cybermut_testmac() is used to make sure that there was not data diddling contained in the received message of confirmation. Pay attention to parameters *code-retour* and *texte-libre*, which cannot be evaluated as is, because of the dash. You must retrieve them by using:

```
<?php
    $code_retour=$HTTP_GET_VARS["code-retour"];
    $texte_libre=$HTTP_GET_VARS["texte-libre"];
?>
```

Příklad 1. Last step of payment (equiv cgi2.c)

```
<?php
// Make sure that Enable Track Vars is ON.
// Directory where are located the keys
putenv("CMKEYDIR=/var/creditmut/cles");

// Version number
$VERSION="1.2";

$texte_libre = $HTTP_GET_VARS["texte-libre"];
$code_retour = $HTTP_GET_VARS["code-retour"];

$mac_ok = cybermut_testmac($MAC,$VERSION,$TPE,$date,$montant,$reference,$texte_libre,$code_retour);

if ($mac_ok) {

    //
    // insert data processing here
    //
    //

    $result=cybermut_creerreponsecm("OK");
} else {
    $result=cybermut_creerreponsecm("Document Falsifie");
}

?>
```

See also **cybermut_creerformulairecm()** and **cybermut_creerreponsecm()**.

XV. Cyrus IMAP administration functions

Úvod

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

Předdefinované konstanty

Tyto konstanty jsou definovány tímto rozšířením a budou k dispozici pouze tehdy, bylo-li rozšíření zkompileováno společně s PHP nebo dynamicky zavedeno za běhu.

CYRUS_CONN_NONSYNCLITERAL (integer)

CYRUS_CONN_INITIALRESPONSE (integer)

CYRUS_CALLBACK_NUMBERED (integer)

CYRUS_CALLBACK_NOLITERAL (integer)

cyrus_authenticate (PHP 4 >= 4.1.0)

Authenticate against a Cyrus IMAP server

```
bool cyrus_authenticate ( resource connection [, string mechlist [, string service [, string user [, int minssf  
[, int maxssf]]]]) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cyrus_bind (PHP 4 >= 4.1.0)

Bind callbacks to a Cyrus IMAP connection

```
bool cyrus_bind ( resource connection, array callbacks) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cyrus_close (PHP 4 >= 4.1.0)

Close connection to a cyrus server

```
bool cyrus_close ( resource connection) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cyrus_connect (PHP 4 >= 4.1.0)

Connect to a Cyrus IMAP server

resource **cyrus_connect** ([string host [, string port [, int flags]]]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cyrus_query (PHP 4 >= 4.1.0)

Send a query to a Cyrus IMAP server

bool **cyrus_query** (resource connection, string query) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

cyrus_unbind (PHP 4 >= 4.1.0)

Unbind ...

bool **cyrus_unbind** (resource connection, string trigger_name) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

XVI. Character type functions

Úvod

The functions provided by this extension check whether a character or string falls into a certain character class according to the current locale (see also `setlocale()`).

When called with an integer argument these functions behave exactly like their C counterparts from "ctype.h".

When called with a string argument they will check every character in the string and will only return `TRUE` if every character in the string matches the requested criteria.

Passing anything else but a string or integer will return `FALSE` immediately.

Požadavky

None besides functions from the standard C library which are always available.

Instalace

Beginning with PHP 4.2.0 these functions are enabled by default. For older versions you have to configure and compile PHP with `--enable-ctype`.

Konfigurace běhu

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Typy prostředků

Toto rozšíření nemá definován žádný typ prostředku (resource).

Předdefinované konstanty

Toto rozšíření nemá definovány žádné konstanty.

ctype_alnum (PHP 4 >= 4.0.4)

Check for alphanumeric character(s)

bool **ctype_alnum** (string *text*) \linebreak

Returns `TRUE` if every character in *text* is either a letter or a digit, `FALSE` otherwise. In the standard C locale letters are just [A-Za-z]. The function is equivalent to `(ctype_alpha($text) || ctype_digit($text))`.

See also `ctype_alpha()`, `ctype_digit()`, and `setlocale()`.

ctype_alpha (PHP 4 >= 4.0.4)

Check for alphabetic character(s)

bool **ctype_alpha** (string *text*) \linebreak

Returns `TRUE` if every character in *text* is a letter from the current locale, `FALSE` otherwise. In the standard C locale letters are just [A-Za-z] and **ctype_alpha()** is equivalent to `(ctype_upper($text) || ctype_lower($text))`, but other languages have letters that are considered neither upper nor lower case.

See also `ctype_upper()`, `ctype_lower()`, and `setlocale()`.

ctype_cntrl (PHP 4 >= 4.0.4)

Check for control character(s)

bool **ctype_cntrl** (string *text*) \linebreak

Returns `TRUE` if every character in *text* has a special control function, `FALSE` otherwise. Control characters are e.g. line feed, tab, esc.

ctype_digit (PHP 4 >= 4.0.4)

Check for numeric character(s)

bool **ctype_digit** (string *text*) \linebreak

Returns `TRUE` if every character in *text* is a decimal digit, `FALSE` otherwise.

See also `ctype_alnum()` and `ctype_xdigit()`.

ctype_graph (PHP 4 >= 4.0.4)

Check for any printable character(s) except space

bool **ctype_graph** (string text) \linebreak

Returns `TRUE` if every character in *text* is printable and actually creates visible output (no white space), `FALSE` otherwise.

See also `ctype_alnum()`, `ctype_print()`, and `ctype_punct()`.

ctype_lower (PHP 4 >= 4.0.4)

Check for lowercase character(s)

bool **ctype_lower** (string text) \linebreak

Returns `TRUE` if every character in *text* is a lowercase letter in the current locale.

See also `ctype_alpha()` and `ctype_upper()`.

ctype_print (PHP 4 >= 4.0.4)

Check for printable character(s)

bool **ctype_print** (string text) \linebreak

Returns `TRUE` if every character in *text* will actually create output (including blanks). Returns `FALSE` if *text* contains control characters or characters that do not have any output or control function at all.

See also `ctype_cntrl()`, `ctype_graph()`, and `ctype_punct()`.

ctype_punct (PHP 4 >= 4.0.4)

Check for any printable character which is not whitespace or an alphanumeric character

bool **ctype_punct** (string text) \linebreak

Returns `TRUE` if every character in *text* is printable, but neither letter, digit or blank, `FALSE` otherwise.

See also `ctype_cntrl()`, `ctype_graph()`, and **`ctype_punct()`**.

ctype_space (PHP 4 >= 4.0.4)

Check for whitespace character(s)

bool **ctype_space** (string text) \linebreak

Returns `TRUE` if every character in *text* creates some sort of white space, `FALSE` otherwise.

Besides the blank character this also includes tab, vertical tab, line feed, carriage return and form feed characters.

ctype_upper (PHP 4 >= 4.0.4)

Check for uppercase character(s)

bool **ctype_upper** (string text) \linebreak

Returns `TRUE` if every character in *text* is a uppercase letter in the current locale.

See also `ctype_alpha()` and `ctype_lower()`.

ctype_xdigit (PHP 4 >= 4.0.4)

Check for character(s) representing a hexadecimal digit

bool **ctype_xdigit** (string text) \linebreak

Returns `TRUE` if every character in *text* is a hexadecimal 'digit', that is a decimal digit or a character from [`A-Fa-f`], `FALSE` otherwise.

See also `ctype_digit()`.

XVII. Database (dbm-style) abstraction layer functions

Úvod

These functions build the foundation for accessing Berkeley DB style databases.

This is a general abstraction layer for several file-based databases. As such, functionality is limited to a common subset of features supported by modern databases such as Sleepycat Software's DB2 (<http://www.sleepycat.com/>). (This is not to be confused with IBM's DB2 software, which is supported through the ODBC functions.)

Požadavky

The behaviour of various aspects depends on the implementation of the underlying database. Functions such as `dba_optimize()` and `dba_sync()` will do what they promise for one database and will do nothing for others. You have to download and install supported dba-Handlers.

Tabulka 1. List of DBA handlers

Handler	Notes
dbm	Dbm is the oldest (original) type of Berkeley DB style databases. You should avoid it, if possible. We do not support the compatibility functions built into DB2 and gdbm, because they are only compatible on the source code level, but cannot handle the original dbm format.
ndbm	Ndbm is a newer type and more flexible than dbm. It still has most of the arbitrary limits of dbm (therefore it is deprecated).
gdbm	Gdbm is the GNU database manager (ftp://ftp.gnu.org/pub/gnu/gdbm/).
db2	DB2 is Sleepycat Software's DB2 (http://www.sleepycat.com/). It is described as "a programmatic toolkit that provides high-performance built-in database support for both standalone and client/server applications."
db3	DB3 is Sleepycat Software's DB3 (http://www.sleepycat.com/).
cdb	Cdb is "a fast, reliable, lightweight package for creating and reading constant databases." It is from the author of qmail and can be found here (http://cr.yp.to/cdb.html). Since it is constant, we support only reading operations.

When invoking the `dba_open()` or `dba_popen()` functions, one of the handler names must be supplied as an argument. The actually available list of handlers is displayed by invoking `phpinfo()`.

Instalace

By using the `--enable-dba=shared` configuration option you can build a dynamic loadable modul to enable PHP for basic support of dbm-style databases. You also have to add support for at least one of the following handlers by specifying the `--with-xxxx` configure switch to your PHP configure line.

Tabulka 2. Supported DBA handlers

Handler	Configure Switch
dbm	To enable support for dbm add <code>--with-dbm[=DIR]</code> .
ndbm	To enable support for ndbm add <code>--with-ndbm[=DIR]</code> .
gdbm	To enable support for gdbm add <code>--with-gdbm[=DIR]</code> .
db2	To enable support for db2 add <code>--with-db2[=DIR]</code> .
db3	To enable support for db3 add <code>--with-db3[=DIR]</code> .
cdb	To enable support for cdb add <code>--with-cdb[=DIR]</code> .

Konfigurace běhu

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Typy prostředků

The functions `dba_open()` and `dba_popen()` return a handle to the specified database file to access

which is used by all other dba-function calls.

Předdefinované konstanty

Toto rozšíření nemá definovány žádné konstanty.

Příklady

Příklad 1. DBA example

```
<?php

$id = dba_open ("/tmp/test.db", "n", "db2");

if (!$id) {
    echo "dba_open failed\n";
    exit;
}

dba_replace ("key", "This is an example!", $id);

if (dba_exists ("key", $id)) {
    echo dba_fetch ("key", $id);
    dba_delete ("key", $id);
}

dba_close ($id);
?>
```

DBA is binary safe and does not have any arbitrary limits. However, it inherits all limits set by the underlying database implementation.

All file-based databases must provide a way of setting the file mode of a new created database, if that is possible at all. The file mode is commonly passed as the fourth argument to `dba_open()` or `dba_popen()`.

You can access all entries of a database in a linear way by using the `dba_firstkey()` and `dba_nextkey()` functions. You may not change the database while traversing it.

Příklad 2. Traversing a database

```
<?php

// ...open database...

$key = dba_firstkey ($id);
```

```
while ($key != false) {  
    if (...) {          // remember the key to perform some action later  
        $handle_later[] = $key;  
    }  
    $key = dba_nextkey ($id);  
}  
  
for ($i = 0; $i < count($handle_later); $i++)  
    dba_delete ($handle_later[$i], $id);  
  
?>
```

dba_close (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Close database

```
void dba_close ( resource handle) \linebreak
```

dba_close() closes the established database and frees all resources specified by *handle*.

handle is a database handle returned by `dba_open()`.

dba_close() does not return any value.

See also: `dba_open()` and `dba_popen()`

dba_delete (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Delete entry specified by key

```
bool dba_delete ( string key, resource handle) \linebreak
```

dba_delete() deletes the entry specified by *key* from the database specified with *handle*.

key is the key of the entry which is deleted.

handle is a database handle returned by `dba_open()`.

dba_delete() returns TRUE or FALSE, if the entry is deleted or not deleted, respectively.

See also: `dba_exists()`, `dba_fetch()`, `dba_insert()`, and `dba_replace()`.

dba_exists (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Check whether key exists

```
bool dba_exists ( string key, resource handle) \linebreak
```

dba_exists() checks whether the specified *key* exists in the database specified by *handle*.

Key is the key the check is performed for.

Handle is a database handle returned by `dba_open()`.

dba_exists() returns TRUE or FALSE, if the key is found or not found, respectively.

See also: `dba_fetch()`, `dba_delete()`, `dba_insert()`, and `dba_replace()`.

dba_fetch (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Fetch data specified by key

```
string dba_fetch ( string key, resource handle) \linebreak
```

dba_fetch() fetches the data specified by *key* from the database specified with *handle*.

Key is the key the data is specified by.

Handle is a database handle returned by `dba_open()`.

dba_fetch() returns the associated string or `FALSE`, if the key/data pair is found or not found, respectively.

See also: `dba_exists()`, `dba_delete()`, `dba_insert()`, and `dba_replace()`.

dba_firstkey (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Fetch first key

string **dba_firstkey** (resource handle) \linebreak

dba_firstkey() returns the first key of the database specified by *handle* and resets the internal key pointer. This permits a linear search through the whole database.

Handle is a database handle returned by `dba_open()`.

dba_firstkey() returns the key or `FALSE` depending on whether it succeeds or fails, respectively.

See also: `dba_nextkey()` and example 2 in the DBA examples

dba_insert (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Insert entry

bool **dba_insert** (string key, string value, resource handle) \linebreak

dba_insert() inserts the entry described with *key* and *value* into the database specified by *handle*. It fails, if an entry with the same *key* already exists.

key is the key of the entry to be inserted.

value is the value to be inserted.

handle is a database handle returned by `dba_open()`.

dba_insert() returns `TRUE` or `FALSE`, depending on whether it succeeds or fails, respectively.

See also: `dba_exists()` `dba_delete()` `dba_fetch()` `dba_replace()`

dba_nextkey (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Fetch next key

string **dba_nextkey** (resource handle) \linebreak

dba_nextkey() returns the next key of the database specified by *handle* and advances the internal key pointer.

handle is a database handle returned by `dba_open()`.

dba_nextkey() returns the key or `FALSE` depending on whether it succeeds or fails, respectively.

See also: `dba_firstkey()` and example 2 in the DBA examples

dba_open (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Open database

resource **dba_open** (string *path*, string *mode*, string *handler* [, ...]) \linebreak

dba_open() establishes a database instance for *path* with *mode* using *handler*.

path is commonly a regular path in your filesystem.

mode is "r" for read access, "w" for read/write access to an already existing database, "c" for read/write access and database creation if it doesn't currently exist, and "n" for create, truncate and read/write access.

handler is the name of the handler which shall be used for accessing *path*. It is passed all optional parameters given to **dba_open()** and can act on behalf of them.

dba_open() returns a positive handle or FALSE, in the case the open is successful or fails, respectively.

See also: dba_popen() dba_close()

dba_optimize (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Optimize database

bool **dba_optimize** (resource *handle*) \linebreak

dba_optimize() optimizes the underlying database specified by *handle*.

handle is a database handle returned by dba_open().

dba_optimize() returns TRUE or FALSE, if the optimization succeeds or fails, respectively.

See also: dba_sync()

dba_popen (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Open database persistently

resource **dba_popen** (string *path*, string *mode*, string *handler* [, ...]) \linebreak

dba_popen() establishes a persistent database instance for *path* with *mode* using *handler*.

path is commonly a regular path in your filesystem.

mode is "r" for read access, "w" for read/write access to an already existing database, "c" for read/write access and database creation if it doesn't currently exist, and "n" for create, truncate and read/write access.

handler is the name of the handler which shall be used for accessing *path*. It is passed all optional parameters given to **dba_popen()** and can act on behalf of them.

dba_popen() returns a positive handle or FALSE, in the case the open is successful or fails, respectively.

See also: dba_open() dba_close()

dba_replace (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Replace or insert entry

bool **dba_replace** (string *key*, string *value*, resource *handle*) \linebreak

dba_replace() replaces or inserts the entry described with *key* and *value* into the database specified by *handle*.

key is the key of the entry to be inserted.

value is the value to be inserted.

handle is a database handle returned by dba_open().

dba_replace() returns TRUE or FALSE, depending on whether it succeeds or fails, respectively.

See also: dba_exists(), dba_delete(), dba_fetch(), and dba_insert().

dba_sync (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Synchronize database

bool **dba_sync** (resource *handle*) \linebreak

dba_sync() synchronizes the database specified by *handle*. This will probably trigger a physical write to disk, if supported.

handle is a database handle returned by dba_open().

dba_sync() returns TRUE or FALSE, if the synchronization succeeds or fails, respectively.

See also: dba_optimize()

XVIII. Date and Time functions

Úvod

You can use this functions to handle date and time. This functions allow you to get date and time from the server where PHP is running on. You can use this functions to format the output of date and time in many different ways.

Poznámka: Please keep in mind that this functions are depending on the locale settings of your server. Especially consider daylight saving time settings and leap years.

Požadavky

Tyto funkce jsou k dispozici jako součást standardního modulu, který je vždy dostupný.

Instalace

K používání těchto funkcí není třeba žádná instalace, jsou součástí jádra PHP.

Konfigurace běhu

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Typy prostředků

Toto rozšíření nemá definován žádný typ prostředku (resource).

Předdefinované konstanty

Toto rozšíření nemá definovány žádné konstanty.

checkdate (PHP 3, PHP 4 >= 4.0.0)

Validate a gregorian date/time

bool **checkdate** (int month, int day, int year) \linebreak

Returns `TRUE` if the date given is valid; otherwise returns `FALSE`. Checks the validity of the date formed by the arguments. A date is considered valid if:

- year is between 1 and 32767 inclusive
- month is between 1 and 12 inclusive
- *Day* is within the allowed number of days for the given *month*. Leap *years* are taken into consideration.

See also `mktime()` and `strtotime()`.

date (PHP 3, PHP 4 >= 4.0.0)

Format a local time/date

string **date** (string format [, int timestamp]) \linebreak

Returns a string formatted according to the given format string using the given integer *timestamp* or the current local time if no timestamp is given.

Poznámka: The valid range of a timestamp is typically from Fri, 13 Dec 1901 20:45:54 GMT to Tue, 19 Jan 2038 03:14:07 GMT. (These are the dates that correspond to the minimum and maximum values for a 32-bit signed integer.)

To generate a timestamp from a string representation of the date, you may be able to use `strtotime()`. Additionally, some databases have functions to convert their date formats into timestamps (such as MySQL's `UNIX_TIMESTAMP` function).

The following characters are recognized in the format string:

- a - "am" or "pm"
- A - "AM" or "PM"
- B - Swatch Internet time
- d - day of the month, 2 digits with leading zeros; i.e. "01" to "31"
- D - day of the week, textual, 3 letters; i.e. "Fri"
- F - month, textual, long; i.e. "January"
- g - hour, 12-hour format without leading zeros; i.e. "1" to "12"
- G - hour, 24-hour format without leading zeros; i.e. "0" to "23"
- h - hour, 12-hour format; i.e. "01" to "12"
- H - hour, 24-hour format; i.e. "00" to "23"

- i - minutes; i.e. "00" to "59"
- I (capital i) - "1" if Daylight Savings Time, "0" otherwise.
- j - day of the month without leading zeros; i.e. "1" to "31"
- l (lowercase 'L') - day of the week, textual, long; i.e. "Friday"
- L - boolean for whether it is a leap year; i.e. "0" or "1"
- m - month; i.e. "01" to "12"
- M - month, textual, 3 letters; i.e. "Jan"
- n - month without leading zeros; i.e. "1" to "12"
- O - Difference to Greenwich time in hours; i.e. "+0200"
- r - RFC 822 formatted date; i.e. "Thu, 21 Dec 2000 16:01:07 +0200" (added in PHP 4.0.4)
- s - seconds; i.e. "00" to "59"
- S - English ordinal suffix for the day of the month, 2 characters; i.e. "th", "nd"
- t - number of days in the given month; i.e. "28" to "31"
- T - Timezone setting of this machine; i.e. "MDT"
- U - seconds since the epoch
- w - day of the week, numeric, i.e. "0" (Sunday) to "6" (Saturday)
- W - ISO-8601 week number of year, weeks starting on monday (added in PHP 4.1.0) (Saturday)
- Y - year, 4 digits; i.e. "1999"
- y - year, 2 digits; i.e. "99"
- z - day of the year; i.e. "0" to "365"
- Z - timezone offset in seconds (i.e. "-43200" to "43200"). The offset for timezones west of UTC is always negative, and for those east of UTC is always positive.

Unrecognized characters in the format string will be printed as-is. The "Z" format will always return "0" when using gmdate().

Příklad 1. date() example

```
echo date ("l dS of F Y h:i:s A");
echo "July 1, 2000 is on a " . date ("l", mktime(0,0,0,7,1,2000));
```

You can prevent a recognized character in the format string from being expanded by escaping it with a preceding backslash. If the character with a backslash is already a special sequence, you may need to also escape the backslash.

Příklad 2. Escaping characters in date()

```
echo date("l \\t\\h\\e jS"); // prints something like 'Saturday the 8th'
```

It is possible to use **date()** and **mktime()** together to find dates in the future or the past.

Příklad 3. **date()** and **mktime()** example

```
$tomorrow = mktime (0,0,0,date("m"), date("d")+1,date("Y"));
$lastmonth = mktime (0,0,0,date("m")-1,date("d"), date("Y"));
$nextyear = mktime (0,0,0,date("m"), date("d"), date("Y")+1);
```

Poznámka: This can be more reliable than simply adding or subtracting the number of seconds in a day or month to a timestamp because of daylight savings time.

Some examples of **date()** formatting. Note that you should escape any other characters, as any which currently have a special meaning will produce undesirable results, and other characters may be assigned meaning in future PHP versions. When escaping, be sure to use single quotes to prevent characters like `\n` from becoming newlines.

Příklad 4. **date()** Formatting

```
/* Today is March 10th, 2001, 5:16:18 pm */
$today = date("F j, Y, g:i a");           // March 10, 2001, 5:16 pm
$today = date("m.d.y");                   // 03.10.01
$today = date("j, n, Y");                  // 10, 3, 2001
$today = date("Ymd");                      // 20010310
$today = date('h-i-s, j-m-y, it is w Day z '); // 05-16-17, 10-03-01, 1631 1618 6 Fripm
$today = date('\i\t \i\s \t\h\e jS \d\a\y. '); // It is the 10th day.
$today = date("D M j G:i:s T Y");          // Sat Mar 10 15:16:08 MST 2001
$today = date('H:m:s \m \i\s\ \m\o\n\t\h'); // 17:03:17 m is month
$today = date("H:i:s");                    // 17:16:17
```

To format dates in other languages, you should use the **setlocale()** and **strftime()** functions.

See also **getlastmod()**, **gmdate()**, **mktime()**, **strftime()** and **time()**.

getdate (PHP 3, PHP 4 >= 4.0.0)

Get date/time information

array **getdate** ([int timestamp]) \linebreak

Returns an associative array containing the date information of the *timestamp*, or the current local time if no timestamp is given, as the following array elements:

- "seconds" - seconds
- "minutes" - minutes
- "hours" - hours
- "mday" - day of the month
- "wday" - day of the week, numeric : from 0 as Sunday up to 6 as Saturday
- "mon" - month, numeric
- "year" - year, numeric
- "yday" - day of the year, numeric; i.e. "299"
- "weekday" - day of the week, textual, full; i.e. "Friday"
- "month" - month, textual, full; i.e. "January"

Příklad 1. `getdate()` example

```
$today = getdate();
$month = $today['month'];
$mday = $today['mday'];
$year = $today['year'];
echo "$month $mday, $year";
```

gettimeofday (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Get current time

array **gettimeofday** (void) \linebreak

This is an interface to `gettimeofday(2)`. It returns an associative array containing the data returned from the system call.

- "sec" - seconds
- "usec" - microseconds
- "minuteswest" - minutes west of Greenwich
- "dsttime" - type of dst correction

gmdate (PHP 3, PHP 4 >= 4.0.0)

Format a GMT/CUT date/time

string **gmdate** (string format [, int timestamp]) \linebreak

Identical to the `date()` function except that the time returned is Greenwich Mean Time (GMT). For example, when run in Finland (GMT +0200), the first line below prints "Jan 01 1998 00:00:00", while the second prints "Dec 31 1997 22:00:00".

Příklad 1. `gmdate()` example

```
echo date ("M d Y H:i:s", mktime (0,0,0,1,1,1998));
echo gmdate ("M d Y H:i:s", mktime (0,0,0,1,1,1998));
```

See also `date()`, `mktime()`, `gmmktime()` and `strftime()`.

gmmktime (PHP 3, PHP 4 >= 4.0.0)

Get UNIX timestamp for a GMT date

```
int gmmktime ( int hour, int minute, int second, int month, int day, int year [, int is_dst]) \linebreak
```

Identical to `mktime()` except the passed parameters represents a GMT date.

gmstrftime (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Format a GMT/CUT time/date according to locale settings

```
string gmstrftime ( string format [, int timestamp]) \linebreak
```

Behaves the same as `strftime()` except that the time returned is Greenwich Mean Time (GMT). For example, when run in Eastern Standard Time (GMT -0500), the first line below prints "Dec 31 1998 20:00:00", while the second prints "Jan 01 1999 01:00:00".

Příklad 1. `gmstrftime()` example

```
setlocale ('LC_TIME', 'en_US');
echo strftime ("%b %d %Y %H:%M:%S", mktime (20,0,0,12,31,98))."\n";
echo gmstrftime ("%b %d %Y %H:%M:%S", mktime (20,0,0,12,31,98))."\n";
```

See also `strftime()`.

localtime (PHP 4 >= 4.0.0)

Get the local time

array **localtime** ([int timestamp [, bool is_associative]]) \linebreak

The **localtime()** function returns an array identical to that of the structure returned by the C function call. The first argument to **localtime()** is the timestamp, if this is not given the current time is used. The second argument to the **localtime()** is the *is_associative*, if this is set to 0 or not supplied then the array is returned as a regular, numerically indexed array. If the argument is set to 1 then **localtime()** is an associative array containing all the different elements of the structure returned by the C function call to localtime. The names of the different keys of the associative array are as follows:

- "tm_sec" - seconds
- "tm_min" - minutes
- "tm_hour" - hour
- "tm_mday" - day of the month
- "tm_mon" - month of the year, starting with 0 for January
- "tm_year" - Years since 1900
- "tm_wday" - Day of the week
- "tm_yday" - Day of the year
- "tm_isdst" - Is daylight savings time in effect

microtime (PHP 3, PHP 4 >= 4.0.0)

Return current UNIX timestamp with microseconds

string **microtime** (void) \linebreak

Returns the string "msec sec" where sec is the current time measured in the number of seconds since the Unix Epoch (0:00:00 January 1, 1970 GMT), and msec is the microseconds part. This function is only available on operating systems that support the gettimeofday() system call.

Both portions of the string are returned in units of seconds.

Příklad 1. microtime() example

```
function getmicrotime(){
    list($usec, $sec) = explode(" ",microtime());
    return ((float)$usec + (float)$sec);
}

$time_start = getmicrotime();

for ($i=0; $i < 1000; $i++){
    //do nothing, 1000 times
}

$time_end = getmicrotime();
$time = $time_end - $time_start;
```

```
echo "Did nothing in $time seconds";
```

See also `time()`.

mktime (PHP 3, PHP 4 >= 4.0.0)

Get UNIX timestamp for a date

```
int mktime ( int hour, int minute, int second, int month, int day, int year [, int is_dst]) \linebreak
```

Warning: Note the strange order of arguments, which differs from the order of arguments in a regular UNIX `mktime()` call and which does not lend itself well to leaving out parameters from right to left (see below). It is a common error to mix these values up in a script.

Returns the Unix timestamp corresponding to the arguments given. This timestamp is a long integer containing the number of seconds between the Unix Epoch (January 1 1970) and the time specified.

Arguments may be left out in order from right to left; any arguments thus omitted will be set to the current value according to the local date and time.

is_dst can be set to 1 if the time is during daylight savings time, 0 if it is not, or -1 (the default) if it is unknown whether the time is within daylight savings time or not. If it's unknown, PHP tries to figure it out itself. This can cause unexpected (but not incorrect) results.

Poznámka: *is_dst* was added in 3.0.10.

mktime() is useful for doing date arithmetic and validation, as it will automatically calculate the correct value for out-of-range input. For example, each of the following lines produces the string "Jan-01-1998".

Příklad 1. mktime() example

```
echo date ("M-d-Y", mktime (0,0,0,12,32,1997));
echo date ("M-d-Y", mktime (0,0,0,13,1,1997));
echo date ("M-d-Y", mktime (0,0,0,1,1,1998));
echo date ("M-d-Y", mktime (0,0,0,1,1,98));
```

Year may be a two or four digit value, with values between 0-69 mapping to 2000-2069 and 70-99 to 1970-1999 (on systems where `time_t` is a 32bit signed integer, as most common today, the valid range for *year* is somewhere between 1902 and 2037).

The last day of any given month can be expressed as the "0" day of the next month, not the -1 day. Both of the following examples will produce the string "The last day in Feb 2000 is: 29".

Příklad 2. Last day of next month

```
$lastday = mktime (0,0,0,3,0,2000);
echo strftime ("Last day in Feb 2000 is: %d", $lastday);

$lastday = mktime (0,0,0,4,-31,2000);
echo strftime ("Last day in Feb 2000 is: %d", $lastday);
```

Date with year, month and day equal to zero is considered illegal (otherwise it what be regarded as 30.11.1999, which would be strange behavior).

See also date() and time().

strftime (PHP 3, PHP 4 >= 4.0.0)

Format a local time/date according to locale settings

string **strftime** (string format [, int timestamp]) \linebreak

Returns a string formatted according to the given format string using the given *timestamp* or the current local time if no timestamp is given. Month and weekday names and other language dependent strings respect the current locale set with setlocale().

The following conversion specifiers are recognized in the format string:

- %a - abbreviated weekday name according to the current locale
- %A - full weekday name according to the current locale
- %b - abbreviated month name according to the current locale
- %B - full month name according to the current locale
- %c - preferred date and time representation for the current locale
- %C - century number (the year divided by 100 and truncated to an integer, range 00 to 99)
- %d - day of the month as a decimal number (range 01 to 31)
- %D - same as %m/%d/%y
- %e - day of the month as a decimal number, a single digit is preceded by a space (range ' 1' to '31')
- %g - like %G, but without the century.
- %G - The 4-digit year corresponding to the ISO week number (see %V). This has the same format and value as %Y, except that if the ISO week number belongs to the previous or next year, that year is used instead.
- %h - same as %b
- %H - hour as a decimal number using a 24-hour clock (range 00 to 23)
- %I - hour as a decimal number using a 12-hour clock (range 01 to 12)
- %j - day of the year as a decimal number (range 001 to 366)

- %m - month as a decimal number (range 01 to 12)
- %M - minute as a decimal number
- %n - newline character
- %p - either 'am' or 'pm' according to the given time value, or the corresponding strings for the current locale
- %r - time in a.m. and p.m. notation
- %R - time in 24 hour notation
- %S - second as a decimal number
- %t - tab character
- %T - current time, equal to %H:%M:%S
- %u - weekday as a decimal number [1,7], with 1 representing Monday

Varování

Sun Solaris seems to start with Sunday as 1 although ISO 9889:1999 (the current C standard) clearly specifies that it should be Monday.

- %U - week number of the current year as a decimal number, starting with the first Sunday as the first day of the first week
- %V - The ISO 8601:1988 week number of the current year as a decimal number, range 01 to 53, where week 1 is the first week that has at least 4 days in the current year, and with Monday as the first day of the week. (Use %G or %g for the year component that corresponds to the week number for the specified timestamp.)
- %W - week number of the current year as a decimal number, starting with the first Monday as the first day of the first week
- %w - day of the week as a decimal, Sunday being 0
- %x - preferred date representation for the current locale without the time
- %X - preferred time representation for the current locale without the date
- %y - year as a decimal number without a century (range 00 to 99)
- %Y - year as a decimal number including the century
- %Z - time zone or name or abbreviation
- %% - a literal '%' character

Poznámka: Not all conversion specifiers may be supported by your C library, in which case they will not be supported by PHP's **strftime()**. This means that %T and %D will not work on Windows.

Příklad 1. strftime() example

```
setlocale (LC_TIME, "C");
print (strftime ("%A in Finnish is "));
```

```

setlocale (LC_TIME, "fi_FI");
print (strftime ("%A, in French "));
setlocale (LC_TIME, "fr_FR");
print (strftime ("%A and in German "));
setlocale (LC_TIME, "de_DE");
print (strftime ("%A.\n"));

```

This example works if you have the respective locales installed in your system.

See also `setlocale()` and `mktime()` and the Open Group specification of `strftime()` (<http://www.opengroup.org/onlinepubs/7908799/xsh/strftime.html>).

strtotime (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Parse about any English textual datetime description into a UNIX timestamp

`int strtotime (string time [, int now])` \linebreak

The function expects to be given a string containing an English date format and will try to parse that format into a UNIX timestamp relative to the timestamp given in *now*, or the current time if none is supplied. Upon failure, -1 is returned.

Because `strtotime()` behaves according to GNU date syntax, have a look at the GNU manual page titled Date Input Formats (http://www.gnu.org/manual/tar-1.12/html_chapter/tar_7.html). Described there is valid syntax for the *time* parameter.

Příklad 1. strtotime() examples

```

echo strtotime ("now"), "\n";
echo strtotime ("10 September 2000"), "\n";
echo strtotime ("+1 day"), "\n";
echo strtotime ("+1 week"), "\n";
echo strtotime ("+1 week 2 days 4 hours 2 seconds"), "\n";
echo strtotime ("next Thursday"), "\n";
echo strtotime ("last Monday"), "\n";

```

Příklad 2. Checking for failure

```

$str = 'Not Good';
if (($timestamp = strtotime($str)) === -1) {
    echo "The string ($str) is bogus";
} else {
    echo "$str == ". date('l dS of F Y h:i:s A',$timestamp);
}

```

Poznámka: The valid range of a timestamp is typically from Fri, 13 Dec 1901 20:45:54 GMT to Tue, 19 Jan 2038 03:14:07 GMT. (These are the dates that correspond to the minimum and maximum values for a 32-bit signed integer.)

time (PHP 3, PHP 4 >= 4.0.0)

Return current UNIX timestamp

int **time** (void) \linebreak

Returns the current time measured in the number of seconds since the Unix Epoch (January 1 1970 00:00:00 GMT).

See also date().

XIX. dBase functions

Úvod

These functions allow you to access records stored in dBase-format (dbf) databases.

There is no support for indexes or memo fields. There is no support for locking, too. Two concurrent webserver processes modifying the same dBase file will very likely ruin your database.

dBase files are simple sequential files of fixed length records. Records are appended to the end of the file and delete records are kept until you call `dbase_pack()`.

We recommend that you do not use dBase files as your production database. Choose any real SQL server instead; MySQL or Postgres are common choices with PHP. dBase support is here to allow you to import and export data to and from your web database, because the file format is commonly understood by Windows spreadsheets and organizers.

Instalace

In order to use these functions, you must compile PHP with the `--enable-dbase` option.

Konfigurace běhu

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Typy prostředků

Toto rozšíření nemá definován žádný typ prostředku (resource).

Předdefinované konstanty

Toto rozšíření nemá definovány žádné konstanty.

dbase_add_record (PHP 3, PHP 4 >= 4.0.0)

Add a record to a dBase database

```
bool dbase_add_record ( int dbase_identifier, array record) \linebreak
```

Adds the data in the *record* to the database. If the number of items in the supplied record isn't equal to the number of fields in the database, the operation will fail and `FALSE` will be returned.

dbase_close (PHP 3, PHP 4 >= 4.0.0)

Close a dBase database

```
bool dbase_close ( int dbase_identifier) \linebreak
```

Closes the database associated with *dbase_identifier*.

dbase_create (PHP 3, PHP 4 >= 4.0.0)

Creates a dBase database

```
int dbase_create ( string filename, array fields) \linebreak
```

The *fields* parameter is an array of arrays, each array describing the format of one field in the database. Each field consists of a name, a character indicating the field type, a length, and a precision.

The types of fields available are:

L

Boolean. These do not have a length or precision.

M

Memo. (Note that these aren't supported by PHP.) These do not have a length or precision.

D

Date (stored as YYYYMMDD). These do not have a length or precision.

N

Number. These have both a length and a precision (the number of digits after the decimal point).

C

String.

If the database is successfully created, a *dbase_identifier* is returned, otherwise `FALSE` is returned.

Příklad 1. Creating a dBase database file

```
// "database" name
$dbname = "/tmp/test.dbf";

// database "definition"
$def =
    array(
        array("date",      "D"),
        array("name",      "C",  50),
        array("age",       "N",   3, 0),
        array("email",     "C", 128),
        array("ismember",  "L")
    );

// creation
if (!dbase_create($dbname, $def))
    print "<strong>Error!</strong>";
```

dbase_delete_record (PHP 3, PHP 4 >= 4.0.0)

Deletes a record from a dBase database

bool **dbase_delete_record** (int dbase_identifier, int record) \linebreak

Marks *record* to be deleted from the database. To actually remove the record from the database, you must also call `dbase_pack()`.

dbase_get_record (PHP 3, PHP 4 >= 4.0.0)

Gets a record from a dBase database

array **dbase_get_record** (int dbase_identifier, int record) \linebreak

Returns the data from *record* in an array. The array is indexed starting at 0, and includes an associative member named 'deleted' which is set to 1 if the record has been marked for deletion (see `dbase_delete_record()`).

Each field is converted to the appropriate PHP type, except:

- Dates are left as strings
- Integers that would have caused an overflow (> 32 bits) are returned as strings

dbase_get_record_with_names (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

Gets a record from a dBase database as an associative array

array **dbase_get_record_with_names** (int dbase_identifier, int record) \linebreak

Returns the data from *record* in an associative array. The array also includes an associative member named 'deleted' which is set to 1 if the record has been marked for deletion (see `dbase_delete_record()`).

Each field is converted to the appropriate PHP type, except:

- Dates are left as strings
- Integers that would have caused an overflow (> 32 bits) are returned as strings

dbase_numfields (PHP 3, PHP 4 >= 4.0.0)

Find out how many fields are in a dBase database

int **dbase_numfields** (int dbase_identifier) \linebreak

Returns the number of fields (columns) in the specified database. Field numbers are between 0 and `dbase_numfields($db)-1`, while record numbers are between 1 and `dbase_numrecords($db)`.

Příklad 1. Using dbase_numfields()

```
$rec = dbase_get_record($db, $recno);
$nf  = dbase_numfields($db);
for ($i=0; $i < $nf; $i++) {
    print $rec[$i]."<br>\n";
}
```

dbase_numrecords (PHP 3, PHP 4 >= 4.0.0)

Find out how many records are in a dBase database

int **dbase_numrecords** (int dbase_identifier) \linebreak

Returns the number of records (rows) in the specified database. Record numbers are between 1 and `dbase_numrecords($db)`, while field numbers are between 0 and `dbase_numfields($db)-1`.

dbase_open (PHP 3, PHP 4 >= 4.0.0)

Opens a dBase database

```
int dbase_open ( string filename, int flags) \linebreak
```

The flags correspond to those for the `open()` system call. (Typically 0 means read-only, 1 means write-only, and 2 means read and write.)

Returns a `dbase_identifier` for the opened database, or `FALSE` if the database couldn't be opened.

Poznámka: Pokud je zapnut bezpečný režim (safe-mode), PHP kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.

dbase_pack (PHP 3, PHP 4 >= 4.0.0)

Packs a dBase database

```
bool dbase_pack ( int dbase_identifier) \linebreak
```

Packs the specified database (permanently deleting all records marked for deletion using `dbase_delete_record()`).

dbase_replace_record (PHP 3>= 3.0.11, PHP 4 >= 4.0.0)

Replace a record in a dBase database

```
bool dbase_replace_record ( int dbase_identifier, array record, int dbase_record_number) \linebreak
```

Replaces the data associated with the record *record_number* with the data in the *record* in the database. If the number of items in the supplied record is not equal to the number of fields in the database, the operation will fail and `FALSE` will be returned.

dbase_record_number is an integer which spans from 1 to the number of records in the database (as returned by `dbase_numrecords()`).

XX. DBM Funkce

Tyto funkce vám umožňují ukládat záznamy do databází typu dbm. Tento typ databází (podporovaný Berkeley DB, GDBM, některými systémovými knihovnami, a také vestavěnou flatfile knihovnou) ukládá klíč/hodnota páry (oproti plnohodnotným relačním databázím).

Příklad 1. Ukázka DBM

```
$dbm = dbmopen ("lastseen", "w");
if (dbmexists ($dbm, $userid)) {
    $last_seen = dbmfetch ($dbm, $userid);
} else {
    dbminsert ($dbm, $userid, time());
}
do_stuff();
dbmreplace ($dbm, $userid, time());
dbmclose ($dbm);
```

dblist (PHP 3, PHP 4 >= 4.0.0)

Získat název používané DBM-kompatibilní knihovny

string **dblist** (void) \linebreak

dbmclose (PHP 3, PHP 4 >= 4.0.0)

Zavřít dbm databázi

bool **dbmclose** (int dbm_identifier) \linebreak

Odemkne a zavře určenou databázi.

dbmdelete (PHP 3, PHP 4 >= 4.0.0)

Smazat v DBM databázi hodnotu spojenou s určitým klíčem

bool **dbmdelete** (int dbm_identifier, string key) \linebreak

Vymaže z databáze hodnotu s klíčem *key*.

Pokud tento klíč v databázi neexistuje, vrací FALSE.

dbmexists (PHP 3, PHP 4 >= 4.0.0)

Zjistí, jestli pro zadaný klíč existuje v DBM databázi hodnota

bool **dbmexists** (int dbm_identifier, string key) \linebreak

Vrací TRUE, pokud existuje hodnota spojená s *key*.

dbmfetch (PHP 3, PHP 4 >= 4.0.0)

Získat z DBM databáze hodnotu spojenou s určitým klíčem

string **dbmfetch** (int dbm_identifier, string key) \linebreak

Vrací hodnotu spojenou s *key*.

dbmfirstkey (PHP 3, PHP 4 >= 4.0.0)

Získat z DBM databáze první klíč

string **dbmfirstkey** (int dbm_identifier) \linebreak

Vrací první klíč v databázi. Pozn.: Není zaručeno žádné pořadí, protože databáze může být vytvořena pomocí hash tabulky, což nezaručuje žádné řazení.

dbminsert (PHP 3, PHP 4 >= 4.0.0)

Vložit do DBM databáze hodnotu a klíč

int **dbminsert** (int dbm_identifier, string key, string value) \linebreak

Přidá do databáze hodnotu s určeným klíčem.

Vrací -1, pokud byla databáze otevřena pouze pro čtení, 0, pokud bylo vložení úspěšné, a 1, pokud už určený klíč existuje. (K nahrazení hodnoty použijte dbmreplace().)

dbmnextkey (PHP 3, PHP 4 >= 4.0.0)

Získat další klíč z DBM databáze

string **dbmnextkey** (int dbm_identifier, string key) \linebreak

Vrací klíč následující po *key*. Zavoláním dbmfirstkey() následovaným postupným voláním **dbmnextkey()** se dají získat všechny key/value páry v DBM databázi. Například:

Příklad 1. Získání všech key/value párů v DBM databázi

```
$key = dbmfirstkey ($dbm_id);
while ($key) {
    echo "$key = " . dbmfetch ($dbm_id, $key) . "\n";
    $key = dbmnextkey ($dbm_id, $key);
}
```

dbmopen (PHP 3, PHP 4 >= 4.0.0)

Otevřít DBM databázi

int **dbmopen** (string filename, string flags) \linebreak

První argument je název DBM souboru (plná cesta), který se má otevřít, druhý argument je jedno z "r" (pouze pro čtení), "n" (nový, implikuje čtení/zápis, a nejspíš smaže existující databázi stejného jména), "c" (vytvořit, implikuje čtení/zápis, a nesmaže existující databázi stejného jména) nebo "w" (čtení/zápis).

Při úspěchu vrací identifikátor, který se předává dalším DBM funkcím success, jinak FALSE.

Pokud používáte NDBM, NDBM ve skutečnosti vytváří soubory soubor.dir a soubor.pag. GDBM používá pouze jeden soubor, stejně jako interní flatfile podpora, a Berkeley DB vytváří soubor

`filename.db`. Pozn.: Vedle případného zamykání souborů vlastní DBM knihovnou provádí PHP svoje vlastní zamykání souborů. PHP nemaže `.lock` soubory, které vytváří. Používá tyto soubory jako pevné inodes, na kterých provádí zamykání souborů. Více informací o DBM souborech viz vaše Unixové man stránky, nebo si stáhněte GNU GDBM (<ftp://ftp.gnu.org/pub/gnu/gdbm/>).

dbmreplace (PHP 3, PHP 4 >= 4.0.0)

Nahradit v DBM databázi hodnotu s určitým klíčem

bool **dbmreplace** (int dbm_identifier, string key, string value) \linebreak

Nahradí v databázi hodnotu spojenou s určeným klíčem.

Pokud tento klíče v databázi neexistuje, přidá ho.

XXI. dbx functions

The dbx module is a database abstraction layer (db 'X', where 'X' is a supported database). The dbx functions allow you to access all supported databases using a single calling convention. In order to have these functions available, you must compile PHP with dbx support by using the `--enable-dbx` option and all options for the databases that will be used, e.g. for MySQL you must also specify `--with-mysql`. The dbx-functions themselves do not interface directly to the databases, but interface to the modules that are used to support these databases. To be able to use a database with the dbx-module, the module must be either linked or loaded into PHP, and the database module must be supported by the dbx-module. Currently, MySQL, PostgreSQL, Microsoft SQL Server, FrontBase, Sybase-CT and ODBC are supported, but others will follow (soon, I hope :-).

Documentation for adding additional database support to dbx can be found at <http://www.guidance.nl/php/dbx/doc/>.

dbx_close (PHP 4 >= 4.0.6)

Close an open connection/database

bool **dbx_close** (object link_identifier) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

Příklad 1. dbx_close() example

```
<?php
$link = dbx_connect(DBX_MYSQL, "localhost", "db", "username", "password")
    or die ("Could not connect");

print("Connected successfully");
dbx_close($link);
?>
```

Poznámka: Always refer to the module-specific documentation as well.

See also: dbx_connect().

dbx_compare (PHP 4 >= 4.1.0)

Compare two rows for sorting purposes

int **dbx_compare** (array row_a, array row_b, string column_key [, int flags]) \linebreak

dbx_compare() returns 0 if the row_a[\$column_key] is equal to row_b[\$column_key], and 1 or -1 if the former is greater or is smaller than the latter one, respectively, or vice versa if the *flag* is set to DBX_CMP_DESC. **dbx_compare()** is a helper function for dbx_sort() to ease the make and use of the custom sorting function.

The *flags* can be set to specify comparison direction:

- DBX_CMP_ASC - ascending order
- DBX_CMP_DESC - descending order

and the preferred comparison type:

- DBX_CMP_NATIVE - no type conversion
- DBX_CMP_TEXT - compare items as strings
- DBX_CMP_NUMBER - compare items numerically

One of the direction and one of the type constant can be combined with bitwise OR operator (|). The default value for the *flags* parameter is DBX_CMP_ASC | DBX_CMP_NATIVE.

Příklad 1. dbx_compare() example

```

<?php
function user_re_order ($a, $b) {
    $rv = dbx_compare ($a, $b, "parentid", DBX_CMP_DESC);
    if ( !$rv ) {
        $rv = dbx_compare ($a, $b, "id", DBX_CMP_NUMBER);
    }
    return $rv;
}

$link = dbx_connect (DBX_ODBC, "", "db", "username", "password")
    or die ("Could not connect");

$result = dbx_query ($link, "SELECT id, parentid, description FROM table OR-
DER BY id");
    // data in $result is now ordered by id

dbx_sort ($result, "user_re_order");
    // data in $result is now ordered by parentid (descending), then by id

dbx_close ($link);
?>

```

See also `dbx_sort()`.

dbx_connect (PHP 4 >= 4.0.6)

Open a connection/database

object **dbx_connect** (mixed module, string host, string database, string username, string password [, int persistent]) \linebreak

dbx_connect() returns an object on success, FALSE on error. If a connection has been made but the database could not be selected, the connection is closed and FALSE is returned. The *persistent* parameter can be set to DBX_PERSISTENT, if so, a persistent connection will be created.

The *module* parameter can be either a string or a constant, though the latter form is preferred. The possible values are given below, but keep in mind that they only work if the module is actually loaded.

- DBX_MYSQL or "mysql"
- DBX_ODBC or "odbc"
- DBX_PGSQL or "pgsql"
- DBX_MSSQL or "mssql"
- DBX_FBSQL or "fbsql" (available from PHP 4.1.0)
- DBX_SYBASECT or "sybase_ct" (CVS only)

The *host*, *database*, *username* and *password* parameters are expected, but not always used depending on the connect functions for the abstracted module.

The returned object has three properties:

database

It is the name of the currently selected database.

handle

It is a valid handle for the connected database, and as such it can be used in module-specific functions (if required).

```
$link = dbx_connect (DBX_MYSQL, "localhost", "db", "username", "password");
mysql_close ($link->handle); // dbx_close($link) would be better here
```

module

It is used internally by dbx only, and is actually the module number mentioned above.

Příklad 1. dbx_connect() example

```
<?php
$link = dbx_connect (DBX_ODBC, "", "db", "username", "password", DBX_PERSISTENT)
    or die ("Could not connect");

print ("Connected successfully");
dbx_close ($link);
?>
```

Poznámka: Always refer to the module-specific documentation as well.

See also: dbx_close().

dbx_error (PHP 4 >= 4.0.6)

Report the error message of the latest function call in the module (not just in the connection)

string **dbx_error** (object link_identifier) \linebreak

dbx_error() returns a string containing the error message from the last function call of the abstracted module (e.g. mysql module). If there are multiple connections in the same module, just

the last error is given. If there are connections on different modules, the latest error is returned for the module specified by the *link_identifier* parameter.

Příklad 1. dbx_error() example

```
<?php
$link    = dbx_connect(DBX_MYSQL, "localhost", "db", "username", "password")
        or die ("Could not connect");

$result = dbx_query($link, "select id from non_existing_table");
if ( $result == 0 ) {
    echo dbx_error ($link);
}
dbx_close ($link);
?>
```

Poznámka: Always refer to the module-specific documentation as well.

The error message for Microsoft SQL Server is actually the result of the `mssql_get_last_message()` function.

dbx_query (PHP 4 >= 4.0.6)

Send a query and fetch all results (if any)

object **dbx_query** (object link_identifier, string sql_statement [, long flags]) \linebreak

dbx_query() returns an object or 1 on success, and 0 on failure. The result object is returned only if the query given in *sql_statement* produces a result set.

Příklad 1. How to handle the returned value

```
<?php
$link    = dbx_connect(DBX_ODBC, "", "db", "username", "password")
        or die("Could not connect");

$result = dbx_query($link, 'SELECT id, parentid, description FROM table');

if ( is_object($result) ) {
    // ... do some stuff here, see detailed examples below ...
    // first, print out field names and types
    // then, draw a table filled with the returned field values
}
else if ( $result == 1 ) {
    echo("Query executed successfully, but no result set returned");
}
else {
    exit("Query failed");
}
```

```

}

dbx_close($link);
?>

```

The *flags* parameter is used to control the amount of information that is returned. It may be any combination of the following constants with the bitwise OR operator (`|`):

DBX_RESULT_INDEX

It is *always* set, that is, the returned object has a `data` property which is a 2 dimensional array indexed numerically. For example, in the expression `data[2][3]` 2 stands for the row (or record) number and 3 stands for the column (or field) number. The first row and column are indexed at 0.

If `DBX_RESULT_ASSOC` is also specified, the returning object contains the information related to `DBX_RESULT_INFO` too, even if it was not specified.

DBX_RESULT_INFO

It provides info about columns, such as field names and field types.

DBX_RESULT_ASSOC

It effects that the field values can be accessed with the respective column names used as keys to the returned object's `data` property.

Associated results are actually references to the numerically indexed data, so modifying `data[0][0]` causes that `data[0]['field_name_for_first_column']` is modified as well.

Note that `DBX_RESULT_INDEX` is always used, regardless of the actual value of *flags* parameter. This means that the following combinations is effective only:

- `DBX_RESULT_INDEX`
- `DBX_RESULT_INDEX | DBX_RESULT_INFO`
- `DBX_RESULT_INDEX | DBX_RESULT_INFO | DBX_RESULT_ASSOC` - this is the default, if *flags* is not specified.

The returning object has four or five properties depending on *flags*:

handle

It is a valid handle for the connected database, and as such it can be used in module specific functions (if required).

```

$result = dbx_query ($link, "SELECT id FROM table");
mysql_field_len ($result->handle, 0);

```

cols and rows

These contain the number of columns (or fields) and rows (or records) respectively.

```
$result = dbx_query ($link, 'SELECT id FROM table');
echo $result->rows; // number of records
echo $result->cols; // number of fields
```

info (optional)

It is returned only if either DBX_RESULT_INFO or DBX_RESULT_ASSOC is specified in the *flags* parameter. It is a 2 dimensional array, that has two named rows (name and type) to retrieve column information.

Příklad 2. lists each field's name and type

```
$result = dbx_query ($link, 'SELECT id FROM table',
                    DBX_RESULT_INDEX | DBX_RESULT_INFO);

for ($i = 0; $i < $result->cols; $i++ ) {
    echo $result->info['name'][$i] . "\n";
    echo $result->info['type'][$i] . "\n";
}
```

data

This property contains the actual resulting data, possibly associated with column names as well depending on *flags*. If DBX_RESULT_ASSOC is set, it is possible to use `$result->data[2]["field_name"]`.

Příklad 3. outputs the content of data property into HTML table

```
$result = dbx_query ($link, 'SELECT id, parentid, description FROM table');

echo "<table>\n";
foreach ( $result->data as $row ) {
    echo "<tr>\n";
    foreach ( $row as $field ) {
        echo "<td>$field</td>";
    }
    echo "</tr>\n";
}
echo "</table>\n";
```

Poznámka: Always refer to the module-specific documentation as well.

See also: `dbx_connect()`.

dbx_sort (PHP 4 >= 4.0.6)

Sort a result from a `dbx_query` by a custom sort function

bool **dbx_sort** (object result, string user_compare_function) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

Poznámka: It is always better to use `ORDER BY SQL` clause instead of **dbx_sort()**, if possible.

Příklad 1. dbx_sort() example

```
<?php
function user_re_order ($a, $b) {
    $rv = dbx_compare ($a, $b, "parentid", DBX_CMP_DESC);
    if ( !$rv ) {
        $rv = dbx_compare ($a, $b, "id", DBX_CMP_NUMBER);
    }
    return $rv;
}

$link = dbx_connect (DBX_ODBC, "", "db", "username", "password")
or die ("Could not connect");

$result = dbx_query ($link, "SELECT id, parentid, description FROM tbl ORDER BY id");
// data in $result is now ordered by id

dbx_sort ($result, "user_re_order");
// data in $result is now ordered by parentid (descending), then by id

dbx_close ($link);
?>
```

See also `dbx_compare()`.

XXII. DB++ Functions

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

Úvod

db++, made by the german company Concept asa (<http://www.concept-asa.de/>), is a relational database system with high performance and low memory and disk usage in mind. While providing SQL as an additional language interface it is not really a SQL database in the first place but provides its own AQL query language which is much more influenced by the relational algebra then SQL is.

Concept asa always had an interest in supporting open source languages, db++ has had Perl and Tcl call interfaces for years now and uses Tcl as its internal stored procedure language.

Požadavky

This extension relies on external client libraries so you have to have a db++ client installed on the system you want to use this extension on.

Concept asa (<http://www.concept-asa.de/>) provides db++ Demo versions (<http://www.concept-asa.de/download-eng.html>) and documentation (<http://www.concept-asa.de/downloads/doc-eng.tar.gz>) for Linux, some other UNIX versions. There is also a Windows version of db++, but this extension doesn't support it (yet).

Instalace

In order to build this extension yourself you need the db++ client libraries and header files to be installed on your system (these are included in the db++ installation archives by default). You have to run **configure** with option `--with-dbplus` to build this extension.

configure looks for the client libraries and header files under the default paths `/usr/dbplus`, `/usr/local/dbplus` and `/opt/dbplus`. If you have installed db++ in a different place you have add the installation path to the **configure** option like this:

```
--with-dbplus=/your/installation/path.
```

Konfigurace běhu

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Typy prostředků

dbplus_relation

Most db++ functions operate on or return *dbplus_relation* resources. A *dbplus_relation* is a handle to a stored relation or a relation generated as the result of a query.

Předdefinované konstanty

Tyto konstanty jsou definovány tímto rozšířením a budou k dispozici pouze tehdy, bylo-li rozšíření zkompileováno společně s PHP nebo dynamicky zavedeno za běhu.

db++ error codes

Tabulka 1. DB++ Error Codes

PHP Constant	db++ constant	meaning
DBPLUS_ERR_NOERR (integer)	ERR_NOERR	Null error condition
DBPLUS_ERR_DUPLICATE (integer)	ERR_DUPLICATE	Tried to insert a duplicate tuple
DBPLUS_ERR_EOSCAN (integer)	ERR_EOSCAN	End of scan from rget()
DBPLUS_ERR_EMPTY (integer)	ERR_EMPTY	Relation is empty (server)
DBPLUS_ERR_CLOSE (integer)	ERR_CLOSE	The server can't close
DBPLUS_ERR_WLOCKED (integer)	ERR_WLOCKED	The record is write locked
DBPLUS_ERR_LOCKED (integer)	ERR_LOCKED	Relation was already locked
DBPLUS_ERR_NOLOCK (integer)	ERR_NOLOCK	Relation cannot be locked
DBPLUS_ERR_READ (integer)	ERR_READ	Read error on relation
DBPLUS_ERR_WRITE (integer)	ERR_WRITE	Write error on relation
DBPLUS_ERR_CREATE (integer)	ERR_CREATE	Create() system call failed
DBPLUS_ERR_LSEEK (integer)	ERR_LSEEK	Lseek() system call failed

PHP Constant	db++ constant	meaning
DBPLUS_ERR_LENGTH (integer)	ERR_LENGTH	Tuple exceeds maximum length
DBPLUS_ERR_OPEN (integer)	ERR_OPEN	Open() system call failed
DBPLUS_ERR_WOPEN (integer)	ERR_WOPEN	Relation already opened for writing
DBPLUS_ERR_MAGIC (integer)	ERR_MAGIC	File is not a relation
DBPLUS_ERR_VERSION (integer)	ERR_VERSION	File is a very old relation
DBPLUS_ERR_PGSIZE (integer)	ERR_PGSIZE	Relation uses a different page size
DBPLUS_ERR_CRC (integer)	ERR_CRC	Invalid crc in the superpage
DBPLUS_ERR_PIPE (integer)	ERR_PIPE	Piped relation requires lseek()
DBPLUS_ERR_NIDX (integer)	ERR_NIDX	Too many secondary indices
DBPLUS_ERR_MALLOC (integer)	ERR_MALLOC	Malloc() call failed
DBPLUS_ERR_NUSERS (integer)	ERR_NUSERS	Error use of max users
DBPLUS_ERR_PREEEXIT (integer)	ERR_PREEEXIT	Caused by invalid usage
DBPLUS_ERR_ONTRAP (integer)	ERR_ONTRAP	Caused by a signal
DBPLUS_ERR_PREPROC (integer)	ERR_PREPROC	Error in the preprocessor
DBPLUS_ERR_DBPARSE (integer)	ERR_DBPARSE	Error in the parser
DBPLUS_ERR_DBRUNERR (integer)	ERR_DBRUNERR	Run error in db
DBPLUS_ERR_DBPREEEXIT (integer)	ERR_DBPREEEXIT	Exit condition caused by prexit() * procedure
DBPLUS_ERR_WAIT (integer)	ERR_WAIT	Wait a little (Simple only)
DBPLUS_ERR_CORRUPT_TUPLE (integer)	ERR_CORRUPT_TUPLE	A client sent a corrupt tuple
DBPLUS_ERR_WARNING0 (integer)	ERR_WARNING0	The Simple routines encountered a non fatal error which was corrected
DBPLUS_ERR_PANIC (integer)	ERR_PANIC	The server should not really die but after a disaster send ERR_PANIC to all its clients
DBPLUS_ERR_FIFO (integer)	ERR_FIFO	Can't create a fifo
DBPLUS_ERR_PERM (integer)	ERR_PERM	Permission denied
DBPLUS_ERR_TCL (integer)	ERR_TCL	TCL_error
DBPLUS_ERR_RESTRICTED (integer)	ERR_RESTRICTED	Only two users
DBPLUS_ERR_USER (integer)	ERR_USER	An error in the use of the library by an application programmer

PHP Constant	db++ constant	meaning
DBPLUS_ERR_UNKNOWN (integer)	ERR_UNKNOWN	

dbplus_add (PHP 4 >= 4.1.0)

Add a tuple to a relation

```
int dbplus_add ( resource relation, array tuple) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

This function will add a tuple to a relation. The *tuple* data is an array of attribute/value pairs to be inserted into the given *relation*. After successful execution the *tuple* array will contain the complete data of the newly created tuple, including all implicitly set domain fields like sequences.

The function will return zero (aka. DBPLUS_ERR_NOERR) on success or a db++ error code on failure. See dbplus_errcode() or the introduction to this chapter for more information on db++ error codes.

dbplus_aql (PHP 4 >= 4.1.0)

Perform AQL query

```
resource dbplus_aql ( string query [, string server [, string dbpath]]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_aql() will execute an AQL *query* on the given *server* and *dbpath*.

On success it will return a relation handle. The result data may be fetched from this relation by calling dbplus_next() and **dbplus_current()**. Other relation access functions will not work on a result relation.

Further information on the AQL A... Query Language is provided in the original db++ manual.

dbplus_chdir (PHP 4 >= 4.1.0)

Get/Set database virtual current directory

```
string dbplus_chdir ( [string newdir]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_chdir() will change the virtual current directory where relation files will be looked for by **dbplus_open()**. **dbplus_chdir()** will return the absolute path of the current directory. Calling **dbplus_chdir()** without giving any *newdir* may be used to query the current working directory.

dbplus_close (PHP 4 >= 4.1.0)

Close a relation

```
int dbplus_close ( resource relation) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Calling **dbplus_close()** will close a relation previously opened by **dbplus_open()**.

dbplus_curr (PHP 4 >= 4.1.0)

Get current tuple from relation

```
int dbplus_curr ( resource relation, array tuple) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_curr() will read the data for the current tuple for the given *relation* and will pass it back as an associative array in *tuple*.

The function will return zero (aka. DBPLUS_ERR_NOERR) on success or a db++ error code on failure. See **dbplus_errcode()** or the introduction to this chapter for more information on db++ error codes.

See also **dbplus_first()**, **dbplus_prev()**, **dbplus_next()**, and **dbplus_last()**.

dbplus_errcode (PHP 4 >= 4.1.0)

Get error string for given errorcode or last error

```
string dbplus_errcode ( int errno) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_errcode() returns a cleartext error string for the error code passed as *errno* or for the result code of the last db++ operation if no parameter is given.

dbplus_errno (PHP 4 >= 4.1.0)

Get error code for last operation

```
int dbplus_errno ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_errno() will return the error code returned by the last db++ operation.

See also dbplus_errcode().

dbplus_find (PHP 4 >= 4.1.0)

Set a constraint on a relation

```
int dbplus_find ( resource relation, array constraints, mixed tuple) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_find() will place a constraint on the given relation. Further calls to functions like dbplus_curr() or dbplus_next() will only return tuples matching the given constraints.

Constraints are triplets of strings containing of a domain name, a comparison operator and a comparison value. The *constraints* parameter array may consist of a collection of string arrays, each of which contains a domain, an operator and a value, or of a single string array containing a multiple of three elements.

The comparison operator may be one of the following strings: '==', '>', '>=', '<', '<=', '!=', '~' for a regular expression match and 'BAND' or 'BOR' for bitwise operations.

See also `dbplus_unselect()`.

dbplus_first (PHP 4 >= 4.1.0)

Get first tuple from relation

```
int dbplus_first ( resource relation, array tuple) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`dbplus_curr()` will read the data for the first tuple for the given *relation*, make it the current tuple and pass it back as an associative array in *tuple*.

The function will return zero (aka. DBPLUS_ERR_NOERR) on success or a db++ error code on failure. See `dbplus_errcode()` or the introduction to this chapter for more information on db++ error codes.

See also `dbplus_curr()`, `dbplus_prev()`, `dbplus_next()`, and `dbplus_last()`.

dbplus_flush (PHP 4 >= 4.1.0)

Flush all changes made on a relation

```
int dbplus_flush ( resource relation) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`dbplus_flush()` will write all changes applied to *relation* since the last flush to disk.

The function will return zero (aka. DBPLUS_ERR_NOERR) on success or a db++ error code on failure. See `dbplus_errcode()` or the introduction to this chapter for more information on db++ error codes.

dbplus_freealllocks (PHP 4 >= 4.1.0)

Free all locks held by this client

```
int dbplus_freealllocks ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_freealllocks() will free all tuple locks held by this client.

See also **dbplus_getlock()**, **dbplus_freelock()**, and **dbplus_freerlocks()**.

dbplus_freelock (PHP 4 >= 4.1.0)

Release write lock on tuple

```
int dbplus_freelock ( resource relation, string tname) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_freelock() will release a write lock on the given *tuple* previously obtained by **dbplus_getlock()**.

See also **dbplus_getlock()**, **dbplus_freerlocks()**, and **dbplus_freealllocks()**.

dbplus_freerlocks (PHP 4 >= 4.1.0)

Free all tuple locks on given relation

```
int dbplus_freerlocks ( resource relation) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_freerlocks() will free all tuple locks held on the given *relation*.

See also `dbplus_getlock()`, `dbplus_freelock()`, and `dbplus_freealllocks()`.

dbplus_getlock (PHP 4 >= 4.1.0)

Get a write lock on a tuple

`int dbplus_getlock (resource relation, string tname) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`dbplus_getlock()` will request a write lock on the specified *tuple*. It will return zero on success or a non-zero error code, especially `DBPLUS_ERR_WLOCKED`, on failure.

See also `dbplus_freelock()`, `dbplus_freerlocks()`, and `dbplus_freealllocks()`.

dbplus_getunique (PHP 4 >= 4.1.0)

Get a id number unique to a relation

`int dbplus_getunique (resource relation, int uniqueid) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`dbplus_getunique()` will obtain a number guaranteed to be unique for the given *relation* and will pass it back in the variable given as *uniqueid*.

The function will return zero (aka. `DBPLUS_ERR_NOERR`) on success or a db++ error code on failure. See `dbplus_errcode()` or the introduction to this chapter for more information on db++ error codes.

dbplus_info (PHP 4 >= 4.1.0)

???

`int dbplus_info (resource relation, string key, array) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Not implemented yet.

dbplus_last (PHP 4 >= 4.1.0)

Get last tuple from relation

int **dbplus_last** (resource relation, array tuple) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_curr() will read the data for the last tuple for the given *relation*, make it the current tuple and pass it back as an associative array in *tuple*.

The function will return zero (aka. DBPLUS_ERR_NOERR) on success or a db++ error code on failure. See dbplus_errcode() or the introduction to this chapter for more information on db++ error codes.

See also dbplus_first(), dbplus_curr(), dbplus_prev(), and dbplus_next().

dbplus_lockrel (unknown)

Request write lock on relation

int **dbplus_lockrel** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_lockrel() will request a write lock on the given relation. Other clients may still query the relation, but can't alter it while it is locked.

dbplus_next (PHP 4 >= 4.1.0)

Get next tuple from relation

```
int dbplus_next ( resource relation, array ) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_curr() will read the data for the next tuple for the given *relation*, will make it the current tuple and will pass it back as an associative array in *tuple*.

The function will return zero (aka. DBPLUS_ERR_NOERR) on success or a db++ error code on failure. See dbplus_errcode() or the introduction to this chapter for more information on db++ error codes.

See also dbplus_first(), dbplus_curr(), dbplus_prev(), and dbplus_last().

dbplus_open (PHP 4 >= 4.1.0)

Open relation file

```
resource dbplus_open ( string name) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

The relation file *name* will be opened. *name* can be either a file name or a relative or absolute path name. This will be mapped in any case to an absolute relation file path on a specific host machine and server.

On success a relation file resource (cursor) is returned which must be used in any subsequent commands referencing the relation. Failure leads to a zero return value, the actual error code may be asked for by calling dbplus_erno().

dbplus_prev (PHP 4 >= 4.1.0)

Get previous tuple from relation

```
int dbplus_prev ( resource relation, array tuple) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`dbplus_curr()` will read the data for the next tuple for the given *relation*, will make it the current tuple and will pass it back as an associative array in *tuple*.

The function will return zero (aka. `DBPLUS_ERR_NOERR`) on success or a db++ error code on failure. See `dbplus_errcode()` or the introduction to this chapter for more information on db++ error codes.

See also `dbplus_first()`, `dbplus_curr()`, `dbplus_next()`, and `dbplus_last()`.

dbplus_rchperm (PHP 4 >= 4.1.0)

Change relation permissions

int **dbplus_rchperm** (resource relation, int mask, string user, string group) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`dbplus_rchperm()` will change access permissions as specified by *mask*, *user* and *group*. The values for these are operating system specific.

dbplus_rcreate (PHP 4 >= 4.1.0)

Creates a new DB++ relation

resource **dbplus_rcreate** (string name, mixed domlist [, boolean overwrite]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`dbplus_rcreate()` will create a new relation named *name*. An existing relation by the same name will only be overwritten if the relation is currently not in use and *overwrite* is set to TRUE.

domlist should contain the domain specification for the new relation within an array of domain description strings. (`dbplus_rcreate()` will also accept a string with space delimited domain

description strings, but it is recommended to use an array). A domain description string consists of a domain name unique to this relation, a slash and a type specification character. See the db++ documentation, especially the dbcreate(1) manpage, for a description of available type specifiers and their meanings.

dbplus_rcrtextact (PHP 4 >= 4.1.0)

Creates an exact but empty copy of a relation including indices

resource **dbplus_rcrtextact** (string name, resource relation, boolean overwrite) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_rcrtextact() will create an exact but empty copy of the given *relation* under a new *name*. An existing relation by the same *name* will only be overwritten if *overwrite* is TRUE and no other process is currently using the relation.

dbplus_rcrtlike (PHP 4 >= 4.1.0)

Creates an empty copy of a relation with default indices

resource **dbplus_rcrtlike** (string name, resource relation, int flag) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_rcrtlike() will create an empty copy of the given *relation* under a new *name*, but with default indices. An existing relation by the same *name* will only be overwritten if *overwrite* is TRUE and no other process is currently using the relation.

dbplus_resolve (PHP 4 >= 4.1.0)

Resolve host information for relation

int **dbplus_resolve** (string relation_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_resolve() will try to resolve the given *relation_name* and find out internal server id, real hostname and the database path on this host. The function will return an array containing these values under the keys 'sid', 'host' and 'host_path' or *FALSE* on error.

See also `dbplus_tcl()`.

dbplus_restorepos (PHP 4 >= 4.1.0)

???

int **dbplus_restorepos** (resource relation, array tuple) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Not implemented yet.

dbplus_rkeys (PHP 4 >= 4.1.0)

Specify new primary key for a relation

resource **dbplus_rkeys** (resource relation, mixed domlist) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_rkeys() will replace the current primary key for *relation* with the combination of domains specified by *domlist*.

domlist may be passed as a single domain name string or as an array of domain names.

dbplus_ropen (PHP 4 >= 4.1.0)

Open relation file local

resource **dbplus_ropen** (string name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_ropen() will open the relation *file* locally for quick access without any client/server overhead. Access is read only and only **dbplus_current()** and **dbplus_next()** may be applied to the returned relation.

dbplus_rquery (PHP 4 >= 4.1.0)

Perform local (raw) AQL query

int **dbplus_rquery** (string query, string dbpath) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_rquery() performs a local (raw) AQL query using an AQL interpreter embedded into the db++ client library. **dbplus_rquery()** is faster than **dbplus_aql()** but will work on local data only.

dbplus_rrename (PHP 4 >= 4.1.0)

Rename a relation

int **dbplus_rrename** (resource relation, string name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_rrename() will change the name of *relation* to *name*.

dbplus_rsecindex (PHP 4 >= 4.1.0)

Create a new secondary index for a relation

resource **dbplus_rsecindex** (resource relation, mixed domlist, int type) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_rsecindex() will create a new secondary index for *relation* with consists of the domains specified by *domlist* and is of type *type*

domlist may be passed as a single domain name string or as an array of domain names.

dbplus_runlink (PHP 4 >= 4.1.0)

Remove relation from filesystem

int **dbplus_runlink** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_unlink() will close and remove the *relation*.

dbplus_rzap (PHP 4 >= 4.1.0)

Remove all tuples from relation

int **dbplus_rzap** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_rzap() will remove all tuples from *relation*.

dbplus_savepos (PHP 4 >= 4.1.0)

???

int **dbplus_savepos** (resource relation) \linebreak**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Not implemented yet.

dbplus_setindex (PHP 4 >= 4.1.0)

???

int **dbplus_setindex** (resource relation, string idx_name) \linebreak**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Not implemented yet.

dbplus_setindexbynumber (PHP 4 >= 4.1.0)

???

int **dbplus_setindexbynumber** (resource relation, int idx_number) \linebreak**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Not implemented yet.

dbplus_sql (PHP 4 >= 4.1.0)

Perform SQL query

resource **dbplus_sql** (string query, string server, string dbpath) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Not implemented yet.

dbplus_tcl (PHP 4 >= 4.1.0)

Execute TCL code on server side

int **dbplus_tcl** (int sid, string script) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

A db++ server will prepare a TCL interpreter for each client connection. This interpreter will enable the server to execute TCL code provided by the client as a sort of stored procedures to improve the performance of database operations by avoiding client/server data transfers and context switches.

dbplus_tcl() needs to pass the client connection id the TCL *script* code should be executed by. **dbplus_resolve()** will provide this connection id. The function will return whatever the TCL code returns or a TCL error message if the TCL code fails.

See also **dbplus_resolve()**.

dbplus_tremove (PHP 4 >= 4.1.0)

Remove tuple and return new current tuple

int **dbplus_tremove** (resource relation, array tuple [, array current]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_tremove() removes *tuple* from *relation* if it perfectly matches a tuple within the relation. *current*, if given, will contain the data of the new current tuple after calling **dbplus_tremove()**.

dbplus_undo (PHP 4 >= 4.1.0)

???

int **dbplus_undo** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Not implemented yet.

dbplus_undoprepere (PHP 4 >= 4.1.0)

???

int **dbplus_undoprepere** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Not implemented yet.

dbplus_unlockrel (PHP 4 >= 4.1.0)

Give up write lock on relation

int **dbplus_unlockrel** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_unlockrel() will release a write lock previously obtained by **dbplus_lockrel()**.

dbplus_unselect (PHP 4 >= 4.1.0)

Remove a constraint from relation

int **dbplus_unselect** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Calling **dbplus_unselect()** will remove a constraint previously set by **dbplus_find()** on *relation*.

dbplus_update (PHP 4 >= 4.1.0)

Update specified tuple in relation

int **dbplus_update** (resource relation, array old, array new) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_update() replaces the tuple given by *old* with the data from *new* if and only if *old* completely matches a tuple within *relation*.

dbplus_xlockrel (PHP 4 >= 4.1.0)

Request exclusive lock on relation

int **dbplus_xlockrel** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_xlockrel() will request an exclusive lock on *relation* preventing even read access from other clients.

See also **dbplus_xunlockrel()**.

dbplus_xunlockrel (PHP 4 >= 4.1.0)

Free exclusive lock on relation

int **dbplus_xunlockrel** (resource relation) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

dbplus_xunlockrel() will release an exclusive lock on *relation* previously obtained by **dbplus_xlockrel()**.

XXIII. Direct IO functions

Direct I/O Functions

PHP supports the direct io functions as described in the Posix Standard (Section 6) for performing I/O functions at a lower level than the C-Language stream I/O functions (fopen, fread,...).

Installation

To get these functions to work, you have to configure PHP with `--enable-dio`.

dio_close (PHP 4 >= 4.2.0)

Closes the file descriptor given by *fd*

void **dio_close** (resource *fd*) \linebreak

The function **dio_close()** closes the file descriptor *resource*.

dio_fcntl (PHP 4 >= 4.2.0)

Performs a c library fcntl on *fd*

mixed **dio_fcntl** (resource *fd*, int *cmd* [, mixed *arg*]) \linebreak

The **dio_fcntl()** function performs the operation specified by *cmd* on the file descriptor *fd*. Some commands require additional arguments *args* to be supplied.

arg is an associative array, when *cmd* is F_SETLK or F_SETLLW, with the following keys:

- "start" - offset where lock begins
- "length" - size of locked area. zero means to end of file
- "whence" - Where l_start is relative to: can be SEEK_SET, SEEK_END and SEEK_CUR
- "type" - type of lock: can be F_RDLCK (read lock), F_WRLCK (write lock) or F_UNLCK (unlock)

cmd can be one of the following operations:

- F_SETLK - Lock is set or cleared. If the lock is held by someone else **dio_fcntl()** returns -1.
- F_SETLKW - like F_SETLK, but in case the lock is held by someone else, **dio_fcntl()** waits until the lock is released.
- F_GETLK - **dio_fcntl()** returns an associative array (as described above) if someone else prevents lock. If there is no obstruction key "type" will set to F_UNLCK.
- F_DUPFD - finds the lowest numbered available file descriptor greater or equal than *arg* and returns them.

dio_open (PHP 4 >= 4.2.0)

Opens a new filename with specified permissions of flags and creation permissions of mode

resource **dio_open** (string *filename*, int *flags* [, int *mode*]) \linebreak

dio_open() opens a file and returns a new file descriptor for it, or -1 if any error occurred. If *flags* is O_CREAT, optional third parameter *mode* will set the mode of the file (creation permissions). The *flags* parameter can be one of the following options:

- `O_RDONLY` - opens the file for read access
- `O_WRONLY` - opens the file for write access
- `O_RDWR` - opens the file for both reading and writing

The *flags* parameter can also include any combination of the following flags:

- `O_CREAT` - creates the file, if it doesn't already exist
- `O_EXCL` - if both, `O_CREAT` and `O_EXCL` are set, **`dio_open()`** fails, if file already exists
- `O_TRUNC` - if file exists, and its opened for write access, file will be truncated to zero length.
- `O_APPEND` - write operations write data at the end of file
- `O_NONBLOCK` - sets non blocking mode

dio_read (PHP 4 >= 4.2.0)

Reads *n* bytes from *fd* and returns them, if *n* is not specified, reads 1k block

string **dio_read** (resource *fd* [, int *n*]) \linebreak

The function **dio_read()** reads and returns *n* bytes from file with descriptor *resource*. If *n* is not specified, **dio_read()** reads 1K sized block and returns them.

dio_seek (PHP 4 >= 4.2.0)

Seeks to *pos* on *fd* from whence

int **dio_seek** (resource *fd*, int *pos*, int *whence*) \linebreak

The function **dio_seek()** is used to change the file position of the file with descriptor *resource*. The parameter *whence* specifies how the position *pos* should be interpreted:

- `SEEK_SET` - specifies that *pos* is specified from the beginning of the file
- `SEEK_CUR` - Specifies that *pos* is a count of characters from the current file position. This count may be positive or negative
- `SEEK_END` - Specifies that *pos* is a count of characters from the end of the file. A negative count specifies a position within the current extent of the file; a positive count specifies a position past the current end. If you set the position past the current end, and actually write data, you will extend the file with zeros up to that position

dio_stat (PHP 4 >= 4.2.0)

Gets stat information about the file descriptor *fd*

array **dio_stat** (resource *fd*) \linebreak

Function **dio_stat()** returns information about the file with file descriptor *fd*. **dio_stat()** returns an associative array with the following keys:

- "device" - device
- "inode" - inode
- "mode" - mode
- "nlink" - number of hard links
- "uid" - user id
- "gid" - group id
- "device_type" - device type (if inode device)
- "size" - total size in bytes
- "blocksize" - blocksize
- "blocks" - number of blocks allocated
- "atime" - time of last access
- "mtime" - time of last modification
- "ctime" - time of last change

On error **dio_stat()** returns NULL.

dio_truncate (PHP 4 >= 4.2.0)

Truncates file descriptor *fd* to offset bytes

bool **dio_truncate** (resource *fd*, int *offset*) \linebreak

Function **dio_truncate()** causes the file referenced by *fd* to be truncated to at most *offset* bytes in size. If the file previously was larger than this size, the extra data is lost. If the file previously was shorter, it is unspecified whether the file is left unchanged or is extended. In the latter case the extended part reads as zero bytes. Returns 0 on success, otherwise -1.

dio_write (PHP 4 >= 4.2.0)

Writes data to *fd* with optional truncation at length

int **dio_write** (resource *fd*, string *data* [, int *len*]) \linebreak

The function **dio_write()** writes up to *len* bytes from *data* to file *fd*. If *len* is not specified, **dio_write()** writes all *data* to the specified file. **dio_write()** returns the number of bytes written to *fd*.

XXIV. Adresářové funkce

chdir (PHP 3, PHP 4 >= 4.0.0)

change directory

int **chdir** (string directory) \linebreak

Mění aktuální adresář PHP na *directory*. Pokud se nepodařilo změnit adresář, vrací FALSE, jinak TRUE.

dir (PHP 3, PHP 4 >= 4.0.0)

directory class

new **dir** (string directory) \linebreak

Pseudo-objektově orientovaný mechanismus pro čtení adresáře. Otevře zadaný *directory*. Po otevření adresáře jsou přístupné dvě vlastnosti. Vlastnost handle je použitelná s jinými adresářovými funkcemi jako readdir(), rewinddir() a closedir(). Hodnotou vlastnosti path je cesta k otevřenému adresáři. Dále jsou přístupné tři metody: read, rewind a close.

Příklad 1. dir() příklad

```
$d = dir("/etc");
echo "Handle: " . $d->handle . "<br>\n";
echo "Path: " . $d->path . "<br>\n";
while($entry=$d->read()) {
    echo $entry . "<br>\n";
}
$d->close();
```

closedir (PHP 3, PHP 4 >= 4.0.0)

Zavírá otevřený adresář

void **closedir** (int dir_handle) \linebreak

Zavírá proud z adresáře specifikovaný v *dir_handle*. Proud musí pocházet z funkce opendir().

getcwd (PHP 4 >= 4.0.0)

Získává aktuální pracovní adresář

string **getcwd** (void) \linebreak

Vrací aktuální pracovní adresář.

opendir (PHP 3, PHP 4 >= 4.0.0)

Otevře adresář

int **opendir** (string path) \linebreak

Vrací deskriptor adresáře použitelný v následných voláních closedir(), readdir(), a rewinddir().

readdir (PHP 3, PHP 4 >= 4.0.0)

Přečte položku z deskriptoru adresáře

string **readdir** (int dir_handle) \linebreak

Vrací název dalšího souboru v adresáři. Názvy souborů nejsou nijak tříděny.

Příklad 1. Vypiš všechny soubory v adresáři

```
// Note that !== did not exist until 4.0.0-RC2
<?php
$handle=opendir('.');
echo "Directory handle: $handle\n";
echo "Files:\n";
while (($file = readdir($handle))!==false) {
    echo "$file\n";
}
closedir($handle);
?>
```

Všimněte si, že **readdir()** vrací také . a .. položky (odkaz na sebe sama a na nadřazený adresář. Pokud je nechcete, můžete je snadno vynechat:

Příklad 2. Vypiš všechny soubory v adresáři a vynech . a ..

```
<?php
$handle=opendir('.');
while (false!==($file = readdir($handle))) {
    if ($file != "." && $file != "..") {
        echo "$file\n";
    }
}
closedir($handle);
?>
```

rewinddir (PHP 3, PHP 4 >= 4.0.0)

návrat na začátek adresáře

void **rewinddir** (int *dir_handle*) \linebreak

Vrací adresářový proud odkazovaný deskriptorem *dir_handle* na začátek adresáře.

XXV. DOM XML funkce

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

Tyto funkce jsou přístupné pouze pokud bylo PHP zkonfigurováno s volbou `--with-dom=[DIR]`, s využitím GNOME xml knihovny. Je potřeba nejméně libxml-2.0.0 (ne betaverze). Tyto funkce byly přidány v PHP 4.

Tento modul definuje následující konstanty:

Tabulka 1. XML konstanty

Konstanta	Hodnota	Popis
XML_ELEMENT_NODE	1	
XML_ATTRIBUTE_NODE	2	
XML_TEXT_NODE	3	
XML_CDATA_SECTION_NODE	4	
XML_ENTITY_REF_NODE	5	
XML_ENTITY_NODE	6	
XML_PI_NODE	7	
XML_COMMENT_NODE	8	
XML_DOCUMENT_NODE	9	
XML_DOCUMENT_TYPE_NODE	10	
XML_DOCUMENT_FRAG_NODE	11	
XML_NOTATION_NODE	12	
XML_GLOBAL_NAMESPACE	1	
XML_LOCAL_NAMESPACE	2	

Tento modul definuje několik tříd. DOM XML funkce vrací rozparsovaný strom XML dokumentu, kde každý uzel je objektem patřícím do jedné z těchto tříd.

xmlDoc (PHP 4 >= 4.0.0)

Vytvořit DOM objekt z XML dokumentu

object **xmlDoc** (string *str*) \linebreak

Tato funkce parsuje XML dokument v *str* a vrací objekt třídy "Dom document", který má vlastnosti "doc" (resource), "version" (string) and "type" (long).

xmlDocfile (PHP 4 >= 4.0.0)

Vytvořit DOM objekt z XML souboru

object **xmlDocfile** (string *filename*) \linebreak

Parsuje XML dokument v souboru pojmenovaném *filename* a vrací objekt třídy "Dom document", který má vlastnosti "doc" (resource), "version" (string).

xmltree (PHP 4 >= 4.0.0)

Vytvořit strom PHP objektů z XML dokumentu

object **xmltree** (string *str*) \linebreak

Parsuje XML dokument v *str* a vrací strom PHP objektů.

XXVI. .NET functions

dotnet_load (unknown)

Loads a DOTNET module

```
int dotnet_load ( string assembly_name [, string datatype_name [, int codepage]]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

XXVII. Error Handling and Logging Functions

These are functions dealing with error handling and logging. They allow you to define your own error handling rules, as well as modify the way the errors can be logged. This allows you to change and enhance error reporting to suit your needs.

With the logging functions, you can send messages directly to other machines, to an email (or email to pager gateway!), to system logs, etc., so you can selectively log and monitor the most important parts of your applications and websites.

The error reporting functions allow you to customize what level and kind of error feedback is given, ranging from simple notices to customized functions returned during errors.

error_log (PHP 3, PHP 4 >= 4.0.0)

send an error message somewhere

```
int error_log ( string message [, int message_type [, string destination [, string extra_headers]]]) \linebreak
```

Sends an error message to the web server's error log, a TCP port or to a file. The first parameter, *message*, is the error message that should be logged. The second parameter, *message_type* says where the message should go:

Tabulka 1. error_log() log types

0	<i>message</i> is sent to PHP's system logger, using the Operating System's system logging mechanism or a file, depending on what the error_log configuration directive is set to.
1	<i>message</i> is sent by email to the address in the <i>destination</i> parameter. This is the only message type where the fourth parameter, <i>extra_headers</i> is used. This message type uses the same internal function as mail() does.
2	<i>message</i> is sent through the PHP debugging connection. This option is only available if remote debugging has been enabled. In this case, the <i>destination</i> parameter specifies the host name or IP address and optionally, port number, of the socket receiving the debug information.
3	<i>message</i> is appended to the file <i>destination</i> .

Varování

Remote debugging via TCP/IP is a PHP 3 feature that is *not* available in PHP 4.

Příklad 1. error_log() examples

```
// Send notification through the server log if we can not
// connect to the database.
if (!Ora_Logon ($username, $password)) {
    error_log ("Oracle database not available!", 0);
}

// Notify administrator by email if we run out of FOO
if (!($foo = allocate_new_foo())) {
    error_log ("Big trouble, we're all out of FOOs!", 1,
        "operator@mydomain.com");
}
```

```
// other ways of calling error_log():
error_log ("You messed up!", 2, "127.0.0.1:7000");
error_log ("You messed up!", 2, "loghost");
error_log ("You messed up!", 3, "/var/tmp/my-errors.log");
```

error_reporting (PHP 3, PHP 4 >= 4.0.0)

set which PHP errors are reported

```
int error_reporting ( [int level]) \linebreak
```

Sets PHP's error reporting level and returns the old level. The error reporting level is either a bitmask, or named constant. Using named constants is strongly encouraged to ensure compatibility for future versions. As error levels are added, the range of integers increases, so older integer-based error levels will not always behave as expected.

Příklad 1. Error Integer changes

```
error_reporting (55); // PHP 3 equivalent to E_ALL ^ E_NOTICE

/* ...in PHP 4, '55' would mean (E_ERROR | E_WARNING | E_PARSE |
E_CORE_ERROR | E_CORE_WARNING) */

error_reporting (2039); // PHP 4 equivalent to E_ALL ^ E_NOTICE

error_reporting (E_ALL ^ E_NOTICE); // The same in both PHP 3 and 4
```

Follow the links of the constants to get their meanings:

Tabulka 1. error_reporting() bit values

value	constant
1	E_ERROR
2	E_WARNING
4	E_PARSE
8	E_NOTICE
16	E_CORE_ERROR
32	E_CORE_WARNING
64	E_COMPILE_ERROR
128	E_COMPILE_WARNING
256	E_USER_ERROR
512	E_USER_WARNING
1024	E_USER_NOTICE

value	constant
2047	E_ALL

Příklad 2. error_reporting() examples

```
// Turn off all error reporting
error_reporting(0);

// Report simple running errors
error_reporting (E_ERROR | E_WARNING | E_PARSE);

// Reporting E_NOTICE can be good too (to report uninitialized
// variables or catch variable name misspellings)
error_reporting (E_ERROR | E_WARNING | E_PARSE | E_NOTICE);

// Report all PHP errors (use bitwise 63 in PHP 3)
error_reporting (E_ALL);
```

restore_error_handler (PHP 4)

Restores the previous error handler function

void **restore_error_handler** (void) \linebreak

Used after changing the error handler function using `set_error_handler()`, to revert to the previous error handler (which could be the built-in or a user defined function)

See also `error_reporting()`, `set_error_handler()`, `trigger_error()`, `user_error()`

set_error_handler (PHP 4)

Sets a user-defined error handler function.

string **set_error_handler** (string error_handler) \linebreak

Sets a user function (*error_handler*) to handle errors in a script. Returns the previously defined error handler (if any), or `FALSE` on error. This function can be used for defining your own way of handling errors during runtime, for example in applications in which you need to do cleanup of data/files when a critical error happens, or when you need to trigger an error under certain conditions (using `trigger_error()`)

The user function needs to accept 2 parameters: the error code, and a string describing the error. From PHP 4.0.2, an additional 3 optional parameters are supplied: the filename in which the error

occurred, the line number in which the error occurred, and the context in which the error occurred (an array that points to the active symbol table at the point the error occurred).

The example below shows the handling of internal exceptions by triggering errors and handling them with a user defined function:

Příklad 1. Error handling with `set_error_handler()` and `trigger_error()`

```
<?php

// redefine the user error constants - PHP 4 only
define (FATAL,E_USER_ERROR);
define (ERROR,E_USER_WARNING);
define (WARNING,E_USER_NOTICE);

// set the error reporting level for this script
error_reporting (FATAL | ERROR | WARNING);

// error handler function
function myErrorHandler ($errno, $errstr, $errfile, $errline) {
    switch ($errno) {
        case FATAL:
            echo "<b>FATAL</b> [$errno] $errstr<br>\n";
            echo "  Fatal error in line ".$errline." of file ".$errfile;
            echo ", PHP ".PHP_VERSION." (" .PHP_OS.")<br>\n";
            echo "Aborting...<br>\n";
            exit 1;
            break;
        case ERROR:
            echo "<b>ERROR</b> [$errno] $errstr<br>\n";
            break;
        case WARNING:
            echo "<b>WARNING</b> [$errno] $errstr<br>\n";
            break;
        default:
            echo "Unkown error type: [$errno] $errstr<br>\n";
            break;
    }
}

// function to test the error handling
function scale_by_log ($vect, $scale) {
    if ( !is_numeric($scale) || $scale <= 0 )
        trigger_error("log(x) for x <= 0 is undefined, you used: scale = $scale",
            FATAL);
    if (!is_array($vect)) {
        trigger_error("Incorrect input vector, array of values expected", ERROR);
        return null;
    }
    for ($i=0; $i<count($vect); $i++) {
        if (!is_numeric($vect[$i]))
            trigger_error("Value at position $i is not a number, using 0 (zero)",
                WARNING);
        $temp[$i] = log($scale) * $vect[$i];
    }
    return $temp;
}
```

```

}

// set to the user defined error handler
$old_error_handler = set_error_handler("myErrorHandler");

// trigger some errors, first define a mixed array with a non-numeric item
echo "vector a\n";
$a = array(2,3,"foo",5.5,43.3,21.11);
print_r($a);

// now generate second array, generating a warning
echo "----\nvector b - a warning (b = log(PI) * a)\n";
$b = scale_by_log($a, M_PI);
print_r($b);

// this is trouble, we pass a string instead of an array
echo "----\nvector c - an error\n";
$c = scale_by_log("not array",2.3);
var_dump($c);

// this is a critical error, log of zero or negative number is undefined
echo "----\nvector d - fatal error\n";
$d = scale_by_log($a, -2.5);

?>

```

And when you run this sample script, the output will be

```

vector a
Array
(
    [0] => 2
    [1] => 3
    [2] => foo
    [3] => 5.5
    [4] => 43.3
    [5] => 21.11
)
----
vector b - a warning (b = log(PI) * a)
<b>WARNING</b> [1024] Value at position 2 is not a number, using 0 (zero)<br>
Array
(
    [0] => 2.2894597716988
    [1] => 3.4341896575482
    [2] => 0
    [3] => 6.2960143721717
    [4] => 49.566804057279
    [5] => 24.165247890281
)
----
vector c - an error
<b>ERROR</b> [512] Incorrect input vector, array of values expected<br>
NULL

```

```

-----
vector d - fatal error
<b>FATAL</b> [256] log(x) for x <= 0 is undefined, you used: scale = -2.5<br>
    Fatal error in line 36 of file trigger_error.php, PHP 4.0.2 (Linux)<br>
Aborting...<br>

```

It is important to remember that the standard PHP error handler is completely bypassed. `error_reporting()` settings will have no effect and your error handler will be called regardless - however you are still able to read the current value of `error_reporting` and act appropriately. Of particular note is that this value will be 0 if the statement that caused the error was prepended by the `@` error-control operator.

Also note that it is your responsibility to `die()` if necessary. If the error-handler function returns, script execution will continue with the next statement after the one that caused an error.

See also `error_reporting()`, `restore_error_handler()`, `trigger_error()`, `user_error()`

trigger_error (PHP 4)

Generates a user-level error/warning/notice message

`void trigger_error (string error_msg [, int error_type]) \linebreak`

Used to trigger a user error condition, it can be used by in conjunction with the built-in error handler, or with a user defined function that has been set as the new error handler (`set_error_handler()`). It only works with the `E_USER` family of constants, and will default to `E_USER_NOTICE`.

This function is useful when you need to generate a particular response to an exception at runtime. For example:

```

if (assert ($divisor == 0))
    trigger_error ("Cannot divide by zero", E_USER_ERROR);

```

Poznámka: See `set_error_handler()` for a more extensive example.

See also `error_reporting()`, `set_error_handler()`, `restore_error_handler()`, `user_error()`

user_error (PHP 4 >= 4.0.0)

Generates a user-level error/warning/notice message

`void user_error (string error_msg [, int error_type]) \linebreak`

This is an alias for the function `trigger_error()`.

See also `error_reporting()`, `set_error_handler()`, `restore_error_handler()`, and `trigger_error()`

XXVIII. FrontBase Functions

These functions allow you to access FrontBase database servers. In order to have these functions available, you must compile php with fbsql support by using the `--with-fbsql` option. If you use this option without specifying the path to fbsql, php will search for the fbsql client libraries in the default installation location for the platform. Users who installed FrontBase in a non standard directory should always specify the path to fbsql: `--with-fbsql=/path/to/fbsql`. This will force php to use the client libraries installed by FrontBase, avoiding any conflicts.

More information about FrontBase can be found at <http://www.frontbase.com/>.

Documentation for FrontBase can be found at <http://www.frontbase.com/cgi-bin/WebObjects/FrontBase.woa/wa/productsPage?currentPage=Documentation>.

Frontbase support has been added to PHP 4.0.6.

fbsql_affected_rows (PHP 4 >= 4.0.6)

Get number of affected rows in previous FrontBase operation

```
int fbsql_affected_rows ( [int link_identifier] ) \linebreak
```

fbsql_affected_rows() returns the number of rows affected by the last INSERT, UPDATE or DELETE query associated with *link_identifier*. If the link identifier isn't specified, the last link opened by **fbsql_connect()** is assumed.

Poznámka: If you are using transactions, you need to call **fbsql_affected_rows()** after your INSERT, UPDATE, or DELETE query, not after the commit.

If the last query was a DELETE query with no WHERE clause, all of the records will have been deleted from the table but this function will return zero.

Poznámka: When using UPDATE, FrontBase will not update columns where the new value is the same as the old value. This creates the possibility that **fbsql_affected_rows()** may not actually equal the number of rows matched, only the number of rows that were literally affected by the query.

If the last query failed, this function will return -1.

See also: **fbsql_num_rows()**.

fbsql_autocommit (PHP 4 >= 4.0.6)

Enable or disable autocommit

```
bool fbsql_autocommit ( resource link_identifier [, bool OnOff] ) \linebreak
```

fbsql_autocommit() returns the current autocommit status. if the optional OnOff parameter is given the auto commit status will be changed. With OnOff set to TRUE each statement will be committed automatically, if no errors was found. With OnOff set to FALSE the user must commit or rollback the transaction using either **fbsql_commit()** or **fbsql_rollback()**.

See also: **fbsql_commit()** and **fbsql_rollback()**

fbsql_change_user (unknown)

Change logged in user of the active connection

```
resource fbsql_change_user ( string user, string password [, string database [, int link_identifier]]) \linebreak
```

fbsql_change_user() changes the logged in user of the current active connection, or the connection given by the optional parameter *link_identifier*. If a database is specified, this will default or current database after the user has been changed. If the new user and password authorization fails, the current connected user stays active.

fbsql_close (PHP 4 >= 4.0.6)

Close FrontBase connection

boolean **fbsql_close** ([resource link_identifier]) \linebreak

Returns: TRUE on success, FALSE on error.

fbsql_close() closes the connection to the FrontBase server that's associated with the specified link identifier. If *link_identifier* isn't specified, the last opened link is used.

Using **fbsql_close()** isn't usually necessary, as non-persistent open links are automatically closed at the end of the script's execution.

Příklad 1. fbsql_close() example

```
<?php
    $link = fbsql_connect ("localhost", "_SYSTEM", "secret")
        or die ("Could not connect");
    print ("Connected successfully");
    fbsql_close ($link);
?>
```

See also: **fbsql_connect()** and **fbsql_pconnect()**.

fbsql_commit (PHP 4 >= 4.0.6)

Commits a transaction to the database

bool **fbsql_commit** ([resource link_identifier]) \linebreak

Returns: TRUE on success, FALSE on failure.

fbsql_commit() ends the current transaction by writing all inserts, updates and deletes to the disk and unlocking all row and table locks held by the transaction. This command is only needed if **autocommit** is set to false.

See also: **fbsql_autocommit()** and **fbsql_rollback()**

fbsql_connect (PHP 4 >= 4.0.6)

Open a connection to a FrontBase Server

resource **fbsql_connect** ([string hostname [, string username [, string password]]]) \linebreak

Returns a positive FrontBase link identifier on success, or an error message on failure.

fbsql_connect() establishes a connection to a FrontBase server. The following defaults are assumed for missing optional parameters: *hostname* = 'NULL', *username* = '_SYSTEM' and *password* = empty password.

If a second call is made to **fbsql_connect()** with the same arguments, no new link will be established, but instead, the link identifier of the already opened link will be returned.

The link to the server will be closed as soon as the execution of the script ends, unless it's closed earlier by explicitly calling **fbsql_close()**.

Příklad 1. **fbsql_connect()** example

```
<?php

$link = fbsql_connect ("localhost", "_SYSTEM", "secret")
    or die ("Could not connect");
print ("Connected successfully");
fbsql_close ($link);

?>
```

See also **fbsql_pconnect()** and **fbsql_close()**.

fbsql_create_blob (PHP 4 >= 4.2.0)

Create a BLOB

string **fbsql_create_blob** (string blob_data [, resource link_identifier]) \linebreak

Returns: A resource handle to the newly created blob.

fbsql_create_blob() creates a blob from blob_data. The returned resource handle can be used with insert and update commands to store the blob in the database.

Příklad 1. **fbsql_create_blob()** example

```
<?php

$link = fbsql_pconnect ("localhost", "_SYSTEM", "secret")
    or die ("Could not connect");
$filename = "blobfile.bin";
$fp = fopen($filename, "rb");
$blobdata = fread($fp, filesize($filename));
fclose($fp);

$blobHandle = fbsql_create_blob($blobdata, $link);

$sql = "INSERT INTO BLOB_TABLE (BLOB_COLUMN) VALUES ($blobHandle)";
$rs = fbsql_query($sql, $link);

?>
```

See also: **fbsql_create_clob()**, **fbsql_read_blob()**, **fbsql_read_clob()**, and **fbsql_set_lob_mode()**.

fbsql_create_clob (PHP 4 >= 4.2.0)

Create a CLOB

string **fbsql_create_clob** (string clob_data [, resource link_identifier]) \linebreak

Returns: A resource handle to the newly created CLOB.

fbsql_create_clob() creates a clob from clob_data. The returned resource handle can be used with insert and update commands to store the clob in the database.

Příklad 1. fbsql_create_clob() example

```
<?php
$link = fbsql_pconnect ("localhost", "_SYSTEM", "secret")
    or die ("Could not connect");
$filename = "clob_file.txt";
$fp = fopen($filename, "rb");
$clobdata = fread($fp, filesize($filename));
fclose($fp);

$clobHandle = fbsql_create_clob($clobdata, $link);

$sql = "INSERT INTO CLOB_TABLE (CLOB_COLUMN) VALUES ($clobHandle)";
$rs = fbsql_query($sql, $link);

?>
```

See also: [fbsql_create_blob\(\)](#), [fbsql_read_blob\(\)](#), [fbsql_read_clob\(\)](#), and [fbsql_set_lob_mode\(\)](#).

fbsql_create_db (PHP 4 >= 4.0.6)

Create a FrontBase database

bool **fbsql_create_db** (string database name [, resource link_identifier]) \linebreak

fbsql_create_db() attempts to create a new database on the server associated with the specified link identifier.

Příklad 1. fbsql_create_db() example

```
<?php
$link = fbsql_pconnect ("localhost", "_SYSTEM", "secret")
    or die ("Could not connect");
if (fbsql_create_db ("my_db")) {
    print("Database created successfully\n");
} else {
    printf("Error creating database: %s\n", fbsql_error ());
}

?>
```

See also: `fbsql_drop_db()`.

fbsql_data_seek (PHP 4 >= 4.0.6)

Move internal result pointer

bool **fbsql_data_seek** (resource result_identifier, int row_number) \linebreak

Returns: TRUE on success, FALSE on failure.

fbsql_data_seek() moves the internal row pointer of the FrontBase result associated with the specified result identifier to point to the specified row number. The next call to `fbsql_fetch_row()` would return that row.

Row_number starts at 0.

Příklad 1. fbsql_data_seek() example

```
<?php
    $link = fbsql_pconnect ("localhost", "_SYSTEM", "secret")
        or die ("Could not connect");

    fbsql_select_db ("samp_db")
        or die ("Could not select database");

    $query = "SELECT last_name, first_name FROM friends;";
    $result = fbsql_query ($query)
        or die ("Query failed");

    # fetch rows in reverse order

    for ($i = fbsql_num_rows ($result) - 1; $i >=0; $i--) {
        if (!fbsql_data_seek ($result, $i)) {
            printf ("Cannot seek to row %d\n", $i);
            continue;
        }

        if(!($row = fbsql_fetch_object ($result)))
            continue;

        printf("%s %s<BR>\n", $row->last_name, $row->first_name);
    }

    fbsql_free_result ($result);
?>
```

fbsql_database (PHP 4 >= 4.0.6)

Get or set the database name used with a connection

string **fbsql_database** (resource link_identifier [, string database]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

fbsql_database_password (PHP 4 >= 4.0.6)

Sets or retrieves the password for a FrontBase database

string **fbsql_database_password** (resource link_identifier [, string database_password]) \linebreak

Returns: The database password associated with the link identifier.

fbsql_database_password() sets and retrieves the database password used by the connection. if a database is protected by a database password, the user must call this function before calling **fbsql_select_db()**. if the second optional parameter is given the function sets the database password for the specified link identifier. If no link identifier is specified, the last opened link is assumed. If no link is open, the function will try to establish a link as if **fbsql_connect()** was called, and use it.

This function does not change the database password in the database nor can it be used to retrieve the database password for a database.

Příklad 1. fbsql_create_clob() example

```
<?php
$link = fbsql_pconnect ("localhost", "_SYSTEM", "secret")
    or die ("Could not connect");
fbsql_database_password($link, "secret db password");
fbsql_select_db($database, $link);
?>
```

See also: **fbsql_connect()**, **fbsql_pconnect()** and **fbsql_select_db()**.

fbsql_db_query (PHP 4 >= 4.0.6)

Send a FrontBase query

resource **fbsql_db_query** (string database, string query [, resource link_identifier]) \linebreak

Returns: A positive FrontBase result identifier to the query result, or FALSE on error.

fbsql_db_query() selects a database and executes a query on it. If the optional link identifier isn't specified, the function will try to find an open link to the FrontBase server and if no such link is found it'll try to create one as if **fbsql_connect()** was called with no arguments

See also **fbsql_connect()**.

fbsql_db_status (PHP 4 >= 4.1.0)

Get the status for a given database

```
int fbsql_db_status ( string database_name [, resource link_identifier]) \linebreak
```

Returns: An integer value with the current status.

fbsql_db_status() requests the current status of the database specified by *database_name*. If the *link_identifier* is omitted the default link_identifier will be used.

The return value can be one of the following constants:

- FALSE - The exec handler for the host was invalid. This error will occur when the link_identifier connects directly to a database by using a port number. FBExec can be available on the server but no connection has been made for it.
- FBSQL_UNKNOWN - The Status is unknown.
- FBSQL_STOPPED - The database is not running. Use **fbsql_start_db()** to start the database.
- FBSQL_STARTING - The database is starting.
- FBSQL_RUNNING - The database is running and can be used to perform SQL operations.
- FBSQL_STOPPING - The database is stopping.
- FBSQL_NOEXEC - FBExec is not running on the server and it is not possible to get the status of the database.

See also: **fbsql_start_db()** and **fbsql_stop_db()**.

fbsql_drop_db (PHP 4 >= 4.0.6)

Drop (delete) a FrontBase database

```
bool fbsql_drop_db ( string database_name [, resource link_identifier]) \linebreak
```

Returns: TRUE on success, FALSE on failure.

fbsql_drop_db() attempts to drop (remove) an entire database from the server associated with the specified link identifier.

fbsql_errno (PHP 4 >= 4.0.6)

Returns the numerical value of the error message from previous FrontBase operation

int **fbsql_errno** ([resource link_identifier]) \linebreak

Returns the error number from the last fbsql function, or 0 (zero) if no error occurred.

Errors coming back from the fbsql database backend don't issue warnings. Instead, use **fbsql_errno()** to retrieve the error code. Note that this function only returns the error code from the most recently executed fbsql function (not including **fbsql_error()** and **fbsql_errno()**), so if you want to use it, make sure you check the value before calling another fbsql function.

```
<?php
fbsql_connect("marliesle");
echo fbsql_errno().": ".fbsql_error()."<BR>";
fbsql_select_db("nonexistentdb");
echo fbsql_errno().": ".fbsql_error()."<BR>";
$conn = fbsql_query("SELECT * FROM nonexistenttable;");
echo fbsql_errno().": ".fbsql_error()."<BR>";
?>
```

See also: **fbsql_error()** and **fbsql_warnings()**.

fbsql_error (PHP 4 >= 4.0.6)

Returns the text of the error message from previous FrontBase operation

string **fbsql_error** ([resource link_identifier]) \linebreak

Returns the error text from the last fbsql function, or "" (the empty string) if no error occurred.

Errors coming back from the fbsql database backend don't issue warnings. Instead, use **fbsql_error()** to retrieve the error text. Note that this function only returns the error text from the most recently executed fbsql function (not including **fbsql_error()** and **fbsql_errno()**), so if you want to use it, make sure you check the value before calling another fbsql function.

```
<?php
fbsql_connect("marliesle");
echo fbsql_errno().": ".fbsql_error()."<BR>";
fbsql_select_db("nonexistentdb");
echo fbsql_errno().": ".fbsql_error()."<BR>";
$conn = fbsql_query("SELECT * FROM nonexistenttable;");
echo fbsql_errno().": ".fbsql_error()."<BR>";
?>
```


See also: `fbsql_errno()` and `fbsql_warnings()`.

fbsql_fetch_array (PHP 4 >= 4.0.6)

Fetch a result row as an associative array, a numeric array, or both

array **fbsql_fetch_array** (resource result [, int result_type]) \linebreak

Returns an array that corresponds to the fetched row, or `FALSE` if there are no more rows.

fbsql_fetch_array() is an extended version of `fbsql_fetch_row()`. In addition to storing the data in the numeric indices of the result array, it also stores the data in associative indices, using the field names as keys.

If two or more columns of the result have the same field names, the last column will take precedence. To access the other column(s) of the same name, you must the numeric index of the column or make an alias for the column.

```
select t1.f1 as foo t2.f1 as bar from t1, t2
```

An important thing to note is that using **fbsql_fetch_array()** is NOT significantly slower than using `fbsql_fetch_row()`, while it provides a significant added value.

The optional second argument *result_type* in **fbsql_fetch_array()** is a constant and can take the following values: `FBSQL_ASSOC`, `FBSQL_NUM`, and `FBSQL_BOTH`.

For further details, see also `fbsql_fetch_row()` and `fbsql_fetch_assoc()`.

Příklad 1. fbsql_fetch_array() example

```
<?php
fbsql_connect ($host, $user, $password);
$result = fbsql_db_query ("database","select user_id, fullname from table");
while ($row = fbsql_fetch_array ($result)) {
    echo "user_id: ".$row["user_id"]."<br>\n";
    echo "user_id: ".$row[0]."<br>\n";
    echo "fullname: ".$row["fullname"]."<br>\n";
    echo "fullname: ".$row[1]."<br>\n";
}
fbsql_free_result ($result);
?>
```

fbsql_fetch_assoc (PHP 4 >= 4.0.6)

Fetch a result row as an associative array

array **fbsql_fetch_assoc** (resource result) \linebreak

Returns an associative array that corresponds to the fetched row, or FALSE if there are no more rows.

fbsql_fetch_assoc() is equivalent to calling **fbsql_fetch_array()** with **FBSQL_ASSOC** for the optional second parameter. It only returns an associative array. This is the way **fbsql_fetch_array()** originally worked. If you need the numeric indices as well as the associative, use **fbsql_fetch_array()**.

If two or more columns of the result have the same field names, the last column will take precedence. To access the other column(s) of the same name, you must use **fbsql_fetch_array()** and have it return the numeric indices as well.

An important thing to note is that using **fbsql_fetch_assoc()** is NOT significantly slower than using **fbsql_fetch_row()**, while it provides a significant added value.

For further details, see also **fbsql_fetch_row()** and **fbsql_fetch_array()**.

Příklad 1. fbsql_fetch_assoc() example

```
<?php
fbsql_connect ($host, $user, $password);
$result = fbsql_db_query ("database","select * from table");
while ($row = fbsql_fetch_assoc ($result)) {
    echo $row["user_id"];
    echo $row["fullname"];
}
fbsql_free_result ($result);
?>
```

fbsql_fetch_field (PHP 4 >= 4.0.6)

Get column information from a result and return as an object

object **fbsql_fetch_field** (resource result [, int field_offset]) \linebreak

Returns an object containing field information.

fbsql_fetch_field() can be used in order to obtain information about fields in a certain query result. If the field offset isn't specified, the next field that wasn't yet retrieved by **fbsql_fetch_field()** is retrieved.

The properties of the object are:

- name - column name
- table - name of the table the column belongs to
- max_length - maximum length of the column
- not_null - 1 if the column cannot be NULL

- type - the type of the column

Příklad 1. `fbsql_fetch_field()` example

```
<?php
fbsql_connect ($host, $user, $password)
    or die ("Could not connect");
$result = fbsql_db_query ("database", "select * from table")
    or die ("Query failed");
# get column metadata
$i = 0;
while ($i < fbsql_num_fields ($result)) {
    echo "Information for column $i:<BR>\n";
    $meta = fbsql_fetch_field ($result);
    if (!$meta) {
        echo "No information available<BR>\n";
    }
    echo "<PRE>
max_length:    $meta->max_length
name:          $meta->name
not_null:      $meta->not_null
table:         $meta->table
type:          $meta->type
</PRE>";
    $i++;
}
fbsql_free_result ($result);
?>
```

See also `fbsql_field_seek()`.

fbsql_fetch_lengths (PHP 4 >= 4.0.6)

Get the length of each output in a result

array **fbsql_fetch_lengths** ([resource result]) \linebreak

Returns: An array that corresponds to the lengths of each field in the last row fetched by `fbsql_fetch_row()`, or `FALSE` on error.

fbsql_fetch_lengths() stores the lengths of each result column in the last row returned by `fbsql_fetch_row()`, `fbsql_fetch_array()` and `fbsql_fetch_object()` in an array, starting at offset 0.

See also: `fbsql_fetch_row()`.

fbsql_fetch_object (PHP 4 >= 4.0.6)

Fetch a result row as an object

object **fbsql_fetch_object** (resource result [, int result_type]) \linebreak

Returns an object with properties that correspond to the fetched row, or `FALSE` if there are no more rows.

fbsql_fetch_object() is similar to **fbsql_fetch_array()**, with one difference - an object is returned, instead of an array. Indirectly, that means that you can only access the data by the field names, and not by their offsets (numbers are illegal property names).

The optional argument *result_type* is a constant and can take the following values: `FBSQL_ASSOC`, `FBSQL_NUM`, and `FBSQL_BOTH`.

Speed-wise, the function is identical to **fbsql_fetch_array()**, and almost as quick as **fbsql_fetch_row()** (the difference is insignificant).

Příklad 1. fbsql_fetch_object() example

```
<?php
fbsql_connect ($host, $user, $password);
$result = fbsql_db_query ("database", "select * from table");
while ($row = fbsql_fetch_object ($result)) {
    echo $row->user_id;
    echo $row->fullname;
}
fbsql_free_result ($result);
?>
```

See also: **fbsql_fetch_array()** and **fbsql_fetch_row()**.

fbsql_fetch_row (PHP 4 >= 4.0.6)

Get a result row as an enumerated array

array **fbsql_fetch_row** (resource result) \linebreak

Returns: An array that corresponds to the fetched row, or `FALSE` if there are no more rows.

fbsql_fetch_row() fetches one row of data from the result associated with the specified result identifier. The row is returned as an array. Each result column is stored in an array offset, starting at offset 0.

Subsequent call to **fbsql_fetch_row()** would return the next row in the result set, or `FALSE` if there are no more rows.

See also: **fbsql_fetch_array()**, **fbsql_fetch_object()**, **fbsql_data_seek()**, **fbsql_fetch_lengths()**, and **fbsql_result()**.

fbsql_field_flags (PHP 4 >= 4.0.6)

Get the flags associated with the specified field in a result

string **fbsql_field_flags** (resource result, int field_offset) \linebreak

fbsql_field_flags() returns the field flags of the specified field. The flags are reported as a single word per flag separated by a single space, so that you can split the returned value using `explode()`.

fbsql_field_len (PHP 4 >= 4.0.6)

Returns the length of the specified field

int **fbsql_field_len** (resource result, int field_offset) \linebreak

fbsql_field_len() returns the length of the specified field.

fbsql_field_name (PHP 4 >= 4.0.6)

Get the name of the specified field in a result

string **fbsql_field_name** (resource result, int field_index) \linebreak

fbsql_field_name() returns the name of the specified field index. *result* must be a valid result identifier and *field_index* is the numerical offset of the field.

Poznámka: *field_index* starts at 0.

e.g. The index of the third field would actually be 2, the index of the fourth field would be 3 and so on.

Příklad 1. fbsql_field_name() example

```
// The users table consists of three fields:
//   user_id
//   username
//   password.

$res = fbsql_db_query("users", "select * from users", $link);

echo fbsql_field_name($res, 0) . "\n";
echo fbsql_field_name($res, 2);
```

The above example would produce the following output:

```

user_id
password

```

fbsql_field_seek (PHP 4 >= 4.0.6)

Set result pointer to a specified field offset

```
bool fbsql_field_seek ( resource result, int field_offset) \linebreak
```

Seeks to the specified field offset. If the next call to `fbsql_fetch_field()` doesn't include a field offset, the field offset specified in **fbsql_field_seek()** will be returned.

See also: `fbsql_fetch_field()`.

fbsql_field_table (PHP 4 >= 4.0.6)

Get name of the table the specified field is in

```
string fbsql_field_table ( resource result, int field_offset) \linebreak
```

Returns the name of the table that the specified field is in.

fbsql_field_type (PHP 4 >= 4.0.6)

Get the type of the specified field in a result

```
string fbsql_field_type ( resource result, int field_offset) \linebreak
```

fbsql_field_type() is similar to the `fbsql_field_name()` function. The arguments are identical, but the field type is returned instead. The field type will be one of "int", "real", "string", "blob", and others as detailed in the FrontBase documentation (<http://www.frontbase.com/cgi-bin/WebObjects/FrontBase.woa/wa/productsPage?currentPage=Documentation>).

Příklad 1. fbsql_field_type() example

```

<?php

fbsql_connect ("localhost", "_SYSTEM", "");
fbsql_select_db ("wisconsin");
$result = fbsql_query ("SELECT * FROM onek;");
$fields = fbsql_num_fields ($result);
$rows   = fbsql_num_rows ($result);
$i = 0;

```

```

$table = fbsql_field_table ($result, $i);
echo "Your '". $table. "' table has ".$fields." fields and ".$rows." records <BR>";
echo "The table has the following fields <BR>";
while ($i < $fields) {
    $type = fbsql_field_type ($result, $i);
    $name = fbsql_field_name ($result, $i);
    $len = fbsql_field_len ($result, $i);
    $flags = fbsql_field_flags ($result, $i);
    echo $type." " ".$name." " ".$len." " ".$flags."<BR>";
    $i++;
}
fbsql_close();

?>

```

fbsql_free_result (PHP 4 >= 4.0.6)

Free result memory

bool **fbsql_free_result** (int result) \linebreak

fbsql_free_result() will free all memory associated with the result identifier *result*.

fbsql_free_result() only needs to be called if you are concerned about how much memory is being used for queries that return large result sets. All associated result memory is automatically freed at the end of the script's execution.

fbsql_get_autostart_info (PHP 4 >= 4.1.0)

No description given yet

array **fbsql_get_autostart_info** ([resource link_identifier]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

fbsql_hostname (PHP 4 >= 4.0.6)

Get or set the host name used with a connection

string **fbsql_hostname** (resource link_identifier [, string host_name]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

fbsql_insert_id (PHP 4 >= 4.0.6)

Get the id generated from the previous INSERT operation

int **fbsql_insert_id** ([resource link_identifier]) \linebreak

fbsql_insert_id() returns the ID generated for an column defined as DEFAULT UNIQUE by the previous INSERT query using the given *link_identifier*. If *link_identifier* isn't specified, the last opened link is assumed.

fbsql_insert_id() returns 0 if the previous query does not generate an DEFAULT UNIQUE value. If you need to save the value for later, be sure to call **fbsql_insert_id()** immediately after the query that generates the value.

Poznámka: The value of the FrontBase SQL function `LAST_INSERT_ID()` always contains the most recently generated DEFAULT UNIQUE value, and is not reset between queries.

fbsql_list_dbs (PHP 4 >= 4.0.6)

List databases available on a FrontBase server

resource **fbsql_list_dbs** ([resource link_identifier]) \linebreak

fbsql_list_dbs() will return a result pointer containing the databases available from the current fbsql daemon. Use the **fbsql_tablename()** function to traverse this result pointer.

Příklad 1. fbsql_list_dbs() example

```
$link = fbsql_connect('localhost', 'myname', 'secret');
$db_list = fbsql_list_dbs($link);

while ($row = fbsql_fetch_object($db_list)) {
    echo $row->Database . "\n";
}
```


The above example would produce the following output:

```
database1
database2
database3
...
```

Poznámka: The above code would just as easily work with `fbsql_fetch_row()` or other similar functions.

fbsql_list_fields (PHP 4 >= 4.0.6)

List FrontBase result fields

resource **fbsql_list_fields** (string database_name, string table_name [, resource link_identifier]) \linebreak

fbsql_list_fields() retrieves information about the given tablename. Arguments are the database name and the table name. A result pointer is returned which can be used with `fbsql_field_flags()`, `fbsql_field_len()`, `fbsql_field_name()`, and `fbsql_field_type()`.

A result identifier is a positive integer. The function returns -1 if a error occurs. A string describing the error will be placed in `$phperrormsg`, and unless the function was called as `@fbsql()` then this error string will also be printed out.

Příklad 1. fbsql_list_fields() example

```
$link = fbsql_connect('localhost', 'myname', 'secret');

$fields = fbsql_list_fields("database1", "table1", $link);
$columns = fbsql_num_fields($fields);

for ($i = 0; $i < $columns; $i++) {
    echo fbsql_field_name($fields, $i) . "\n";
}
```

The above example would produce the following output:

```
field1
field2
field3
...
```

fbsql_list_tables (PHP 4 >= 4.0.6)

List tables in a FrontBase database

resource **fbsql_list_tables** (string database [, resource link_identifier]) \linebreak

fbsql_list_tables() takes a database name and returns a result pointer much like the **fbsql_db_query()** function. The **fbsql_tablename()** function should be used to extract the actual table names from the result pointer.

fbsql_next_result (PHP 4 >= 4.0.6)

Move the internal result pointer to the next result

bool **fbsql_next_result** (int result_id) \linebreak

When sending more than one SQL statement to the server or executing a stored procedure with multiple results will cause the server to return multiple result sets. This function will test for additional results available from the server. If an additional result set exists it will free the existing result set and prepare to fetch the words from the new result set. The function will return **TRUE** if an additional result set was available or **FALSE** otherwise.

Příklad 1. fbsql_next_result() example

```
<?php
$link = fbsql_connect ("localhost", "_SYSTEM", "secret");
fbsql_select_db("MyDB", $link);
$SQL = "Select * from table1; select * from table2;";
$rs = fbsql_query($SQL, $link);
do {
    while ($row = fbsql_fetch_row($rs)) {
    }
} while (fbsql_next_result($rs));
fbsql_free_result($rs);
fbsql_close ($link);
?>
```

fbsql_num_fields (PHP 4 >= 4.0.6)

Get number of fields in result

int **fbsql_num_fields** (resource result) \linebreak

fbsql_num_fields() returns the number of fields in a result set.

See also: **fbsql_db_query()**, **fbsql_query()**, **fbsql_fetch_field()**, and **fbsql_num_rows()**.

fbsql_num_rows (PHP 4 >= 4.0.6)

Get number of rows in result

int **fbsql_num_rows** (resource result) \linebreak

fbsql_num_rows() returns the number of rows in a result set. This command is only valid for SELECT statements. To retrieve the number of rows returned from a INSERT, UPDATE or DELETE query, use **fbsql_affected_rows()**.

Příklad 1. fbsql_num_rows() example

```
<?php

$link = fbsql_connect("localhost", "username", "password");
fbsql_select_db("database", $link);

$result = fbsql_query("SELECT * FROM table1;", $link);
$num_rows = fbsql_num_rows($result);

echo "$num_rows Rows\n";

?>
```

See also: **fbsql_affected_rows()**, **fbsql_connect()**, **fbsql_select_db()**, and **fbsql_query()**.

fbsql_password (PHP 4 >= 4.0.6)

Get or set the user password used with a connection

string **fbsql_password** (resource link_identifier [, string password]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

fbsql_pconnect (PHP 4 >= 4.0.6)

Open a persistent connection to a FrontBase Server

```
resource fbsql_pconnect ( [string hostname [, string username [, string password]]]) \linebreak
```

Returns: A positive FrontBase persistent link identifier on success, or `FALSE` on error.

fbsql_pconnect() establishes a connection to a FrontBase server. The following defaults are assumed for missing optional parameters: *host* = 'localhost', *username* = "_SYSTEM" and *password* = empty password.

fbsql_pconnect() acts very much like **fbsql_connect()** with two major differences.

To set Frontbase server port number, use **fbsql_select_db()**.

First, when connecting, the function would first try to find a (persistent) link that's already open with the same host, username and password. If one is found, an identifier for it will be returned instead of opening a new connection.

Second, the connection to the SQL server will not be closed when the execution of the script ends. Instead, the link will remain open for future use.

This type of links is therefore called 'persistent'.

fbsql_query (PHP 4 >= 4.0.6)

Send a FrontBase query

```
resource fbsql_query ( string query [, resource link_identifier]) \linebreak
```

fbsql_query() sends a query to the currently active database on the server that's associated with the specified link identifier. If *link_identifier* isn't specified, the last opened link is assumed. If no link is open, the function tries to establish a link as if **fbsql_connect()** was called with no arguments, and use it.

Poznámka: The query string shall always end with a semicolon.

fbsql_query() returns `TRUE` (non-zero) or `FALSE` to indicate whether or not the query succeeded. A return value of `TRUE` means that the query was legal and could be executed by the server. It does not indicate anything about the number of rows affected or returned. It is perfectly possible for a query to succeed but affect no rows or return no rows.

The following query is syntactically invalid, so **fbsql_query()** fails and returns `FALSE`:

Příklad 1. fbsql_query() example

```
<?php
$result = fbsql_query ("SELECT * WHERE 1=1")
    or die ("Invalid query");
?>
```

The following query is semantically invalid if `my_col` is not a column in the table `my_tbl`, so `fbsql_query()` fails and returns `FALSE`:

Příklad 2. `fbsql_query()` example

```
<?php
$result = fbsql_query ("SELECT my_col FROM my_tbl")
    or die ("Invalid query");
?>
```

`fbsql_query()` will also fail and return `FALSE` if you don't have permission to access the table(s) referenced by the query.

Assuming the query succeeds, you can call `fbsql_num_rows()` to find out how many rows were returned for a `SELECT` statement or `fbsql_affected_rows()` to find out how many rows were affected by a `DELETE`, `INSERT`, `REPLACE`, or `UPDATE` statement.

For `SELECT` statements, **`fbsql_query()`** returns a new result identifier that you can pass to `fbsql_result()`. When you are done with the result set, you can free the resources associated with it by calling `fbsql_free_result()`. Although, the memory will automatically be freed at the end of the script's execution.

See also: `fbsql_affected_rows()`, `fbsql_db_query()`, `fbsql_free_result()`, `fbsql_result()`, `fbsql_select_db()`, and `fbsql_connect()`.

`fbsql_read_blob` (PHP 4 >= 4.2.0)

Read a BLOB from the database

string **`fbsql_read_blob`** (string `blob_handle` [, resource `link_identifier`]) \linebreak

Returns: A string containing the BLOB specified by `blob_handle`.

`fbsql_read_blob()` reads BLOB data from the database. If a select statement contains BLOB and/or BLOB columns FrontBase will return the data directly when data is fetched. This default behavior can be changed with `fbsql_set_lob_mode()` so the fetch functions will return handles to BLOB and CLOB data. If a handle is fetched a user must call **`fbsql_read_blob()`** to get the actual BLOB data from the database.

Příklad 1. `fbsql_read_blob()` example

```
<?php
$link = fbsql_pconnect ("localhost", "_SYSTEM", "secret")
    or die ("Could not connect");
$sql = "SELECT BLOB_COLUMN FROM BLOB_TABLE;";
$rs = fbsql_query($sql, $link);
$row_data = fbsql_fetch_row($rs);
// $row_data[0] will now contain the blob data for teh first row
```

```

fbsql_free_result($rs);

$rs = fbsql_query($sql, $link);
fbsql_set_lob_mode($rs, FBSQL_LOB_HANDLE);
$row_data = fbsql_fetch_row($rs);
// $row_data[0] will now contain a handle to the BLOB data in the first row
$blob_data = fbsql_read_blob($row_data[0]);
fbsql_free_result($rs);

?>

```

See also: `fbsql_create_blob()`, **`fbsql_read_blob()`**, `fbsql_read_clob()`, and `fbsql_set_lob_mode()`.

fbsql_read_clob (PHP 4 >= 4.2.0)

Read a CLOB from the database

string **fbsql_read_clob** (string clob_handle [, resource link_identifier]) \linebreak

Returns: A string containing the CLOB specified by clob_handle.

fbsql_read_clob() reads CLOB data from the database. If a select statement contains BLOB and/or CLOB columns FrontBase will return the data directly when data is fetched. This default behavior can be changed with `fbsql_set_lob_mode()` so the fetch functions will return handles to BLOB and CLOB data. If a handle is fetched a user must call **fbsql_read_clob()** to get the actual CLOB data from the database.

Příklad 1. fbsql_read_clob() example

```

<?php
$link = fbsql_pconnect ("localhost", "_SYSTEM", "secret")
    or die ("Could not connect");
$sql = "SELECT CLOB_COLUMN FROM CLOB_TABLE;";
$rs = fbsql_query($sql, $link);
$row_data = fbsql_fetch_row($rs);
// $row_data[0] will now contain the clob data for teh first row
fbsql_free_result($rs);

$rs = fbsql_query($sql, $link);
fbsql_set_lob_mode($rs, FBSQL_LOB_HANDLE);
$row_data = fbsql_fetch_row($rs);
// $row_data[0] will now contain a handle to the CLOB data in the first row
$clob_data = fbsql_read_clob($row_data[0]);
fbsql_free_result($rs);

?>

```

See also: `fbsql_create_blob()`, `fbsql_read_blob()`, **`fbsql_read_clob()`**, and `fbsql_set_lob_mode()`.

fbsql_result (PHP 4 >= 4.0.6)

Get result data

mixed **fbsql_result** (resource result, int row [, mixed field]) \linebreak

fbsql_result() returns the contents of one cell from a FrontBase result set. The field argument can be the field's offset, or the field's name, or the field's table dot field's name (tablename.fieldname). If the column name has been aliased ('select foo as bar from...'), use the alias instead of the column name.

When working on large result sets, you should consider using one of the functions that fetch an entire row (specified below). As these functions return the contents of multiple cells in one function call, they're MUCH quicker than **fbsql_result()**. Also, note that specifying a numeric offset for the field argument is much quicker than specifying a fieldname or tablename.fieldname argument.

Calls to **fbsql_result()** should not be mixed with calls to other functions that deal with the result set.

Recommended high-performance alternatives: **fbsql_fetch_row()**, **fbsql_fetch_array()**, and **fbsql_fetch_object()**.

fbsql_rollback (PHP 4 >= 4.0.6)

Rollback a transaction to the database

bool **fbsql_rollback** ([resource link_identifier]) \linebreak

Returns: TRUE on success, FALSE on failure.

fbsql_rollback() ends the current transaction by rolling back all statements issued since last commit. This command is only needed if autocommit is set to false.

See also: **fbsql_autocommit()** and **fbsql_commit()**

fbsql_select_db (PHP 4 >= 4.0.6)

Select a FrontBase database

bool **fbsql_select_db** (string database_name [, resource link_identifier]) \linebreak

Returns: TRUE on success, FALSE on error.

fbsql_select_db() sets the current active database on the server that's associated with the specified link identifier. If no link identifier is specified, the last opened link is assumed. If no link is open, the function will try to establish a link as if **fbsql_connect()** was called, and use it.

The client contacts FBExec to obtain the port number to use for the connection to the database. If the database name is a number the system will use that as a port number and it will not ask FBExec for the port number. The FrontBase server can be started as FFrontBase -FBExec=No -port=<port number> <database name>.

Every subsequent call to **fbsql_query()** will be made on the active database.

if the database is protected with a database password, the user must call `fbsql_database_password()` before selecting the database.

See also: `fbsql_connect()`, `fbsql_pconnect()`, `fbsql_database_password()` and `fbsql_query()`.

fbsql_set_lob_mode (PHP 4 >= 4.2.0)

Set the LOB retrieve mode for a FrontBase result set

`bool fbsql_set_lob_mode (resource result, string database_name) \linebreak`

Returns: TRUE on success, FALSE on error.

fbsql_set_lob_mode() sets the mode for retrieving LOB data from the database. When BLOB and CLOB data is stored in FrontBase it can be stored direct or indirect. Direct stored LOB data will always be fetched no matter the setting of the lob mode. If the LOB data is less than 512 bytes it will always be stored directly.

- **FBSQL_LOB_DIRECT** - LOB data is retrieved directly. When data is fetched from the database with `fbsql_fetch_row()`, and other fetch functions, all CLOB and BLOB columns will be returned as ordinary columns. This is the default value on a new FrontBase result.
- **FBSQL_LOB_HANDLE** - LOB data is retrieved as handles to the data. When data is fetched from the database with **fbsql_fetch_row ()**, and other fetch functions, LOB data will be returned as a handle to the data if the data is stored indirect or the data if it is stored direct. If a handle is returned it will be a 27 byte string formatted as "@'00000000000000000000000000000000'".

See also: `fbsql_create_blob()`, `fbsql_create_clob()`, `fbsql_read_blob()`, and `fbsql_read_clob()`.

fbsql_set_transaction (PHP 4 >= 4.2.0)

Set the transaction locking and isolation

`void fbsql_set_transaction (resource link_identifier, int Locking, int Isolation) \linebreak`

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

fbsql_start_db (PHP 4 >= 4.0.6)

Start a database on local or remote server

`bool fbsql_start_db (string database_name [, resource link_identifier]) \linebreak`

Returns: TRUE on success, FALSE on failure.

fbsql_start_db()

See also: fbsql_db_status() and fbsql_stop_db().

fbsql_stop_db (PHP 4 >= 4.0.6)

Stop a database on local or remote server

bool **fbsql_stop_db** (string database_name [, resource link_identifier]) \linebreak

Returns: TRUE on success, FALSE on failure.

fbsql_stop_db()

See also: fbsql_db_status() and fbsql_start_db().

fbsql_tablename (PHP 4 >= 4.2.0)

Get table name of field

string **fbsql_tablename** (resource result, int i) \linebreak

fbsql_tablename() takes a result pointer returned by the fbsql_list_tables() function as well as an integer index and returns the name of a table. The fbsql_num_rows() function may be used to determine the number of tables in the result pointer.

Příklad 1. fbsql_tablename() example

```
<?php
fbsql_connect ("localhost", "_SYSTEM", "");
$result = fbsql_list_tables ("wisconsin");
$i = 0;
while ($i < fbsql_num_rows ($result)) {
    $tb_names[$i] = fbsql_tablename ($result, $i);
    echo $tb_names[$i] . "<BR>";
    $i++;
}
?>
```

fbsql_username (PHP 4 >= 4.0.6)

Get or set the host user used with a connection

string **fbsql_username** (resource link_identifier [, string username]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

fbsql_warnings (PHP 4 >= 4.0.6)

Enable or disable FrontBase warnings

bool **fbsql_warnings** ([bool OnOff]) \linebreak

Returns TRUE if warnings is turned on otherwise FALSE.

fbsql_warnings() enables or disables FrontBase warnings.

XXIX. filePro funkce

Tyto funkce umožňují read-only (pouze pro čtení) přístup k datům uloženým ve filePro databázích.

filePro je registrovaná obchodní značka fP Technologies, Inc. Více informací o filePro najdete na <http://www.fptech.com/>.

filepro (PHP 3, PHP 4 >= 4.0.0)

Přečíst a ověřit mapový soubor

bool **filepro** (string directory) \linebreak

Přečte a ověří mapový soubor a uloží počet sloupců a info.

Nedochází k zamykání, takže byste se měli vyhnout úpravám vaší filePro databáze, pokud může být otevřena v PHP.

filepro_fieldcount (PHP 3, PHP 4 >= 4.0.0)

Zjistit, kolik sloupců je ve filePro databázi

int **filepro_fieldcount** (void) \linebreak

Vrátí počet polí (sloupců) v otevřené filePro databázi.

Viz také filepro().

filepro_fieldname (PHP 3, PHP 4 >= 4.0.0)

Zjistit název sloupce

string **filepro_fieldname** (int field_number) \linebreak

Vrátí název sloupce odpovídajícího *field_number*.

filepro_fieldtype (PHP 3, PHP 4 >= 4.0.0)

Zjistit typ sloupce

string **filepro_fieldtype** (int field_number) \linebreak

Vrátí editační typ sloupce odpovídajícího *field_number*.

filepro_fieldwidth (PHP 3, PHP 4 >= 4.0.0)

Zjistit šířku sloupce

int **filepro_fieldwidth** (int field_number) \linebreak

Vrátí šířku sloupce odpovídajícího *field_number*.

filepro_retrieve (PHP 3, PHP 4 >= 4.0.0)

Získat data z filePro databáze

string **filepro_retrieve** (int row_number, int field_number) \linebreak

Vrátí data z určeného místa v databázi.

filepro_rowcount (PHP 3, PHP 4 >= 4.0.0)

Zjistit, kolik řádků je ve filePro databázi

int **filepro_rowcount** (void) \linebreak

Vrátí počet řádků v otevřené filePro databázi.

Viz také filepro().

XXX. Filesystemové funkce

basename (PHP 3, PHP 4 >= 4.0.0)

Vrátí část cesty obsahující název souboru

string **basename** (string path) \linebreak

Přijímá řetězec obsahující cestu na soubor, vrací název souboru.

Na Windows se jako oddělovač cesty dá použít jak lomítko (/), tak zpětné lomítko (\). V ostatních prostředích je to normální lomítko (/).

Příklad 1. Ukázka basename()

```
$path = '/home/httpd/html/index.php3' ;
$file = basename( $path ) ; // $file má hodnotu "index.php3"
```

Viz také `dirname()`

chgrp (PHP 3, PHP 4 >= 4.0.0)

Změnit skupinu souboru

int **chgrp** (string filename, mixed group) \linebreak

Pokusí se nastavit skupinu souboru *filename* na *group*. Pouze superuživatel může libovolně změnit skupinu souboru; ostatní uživatelé mohou změnit skupinu souboru na jinou skupinu, jíž jsou členy.

Při úspěchu vrací TRUE; jinak FALSE.

Viz také `chown()` a `chmod()`.

Poznámka: Tato funkce nefunguje na Windows systémech.

chmod (PHP 3, PHP 4 >= 4.0.0)

Změnit mód souboru

int **chmod** (string filename, int mode) \linebreak

Pokusí se změnit mód souboru *filename* na *mode*.

Pozn.: *mode* se nepovažuje automaticky za oktalovou hodnotu, takže řetězce (jako "g+w") nebudou správně fungovat. Pokud si chcete zajistit očekávané chování, musíte na začátek *mode* přidat nulu (0):

```
chmod ("/somedir/somefile", 755); // desítkové číslo; zřejmě nesprávně
```

```
chmod ("/somedir/somefile", "u+rw,go+rx"); // retezec; nespravny
chmod ("/somedir/somefile", 0755); // oktal; spravna hodnota modu
```

Při úspěchu vrací TRUE, jinak FALSE.

Viz také `chown()` a `chgrp()`.

Poznámka: Tato funkce nefunguje na Windows systémech

chown (PHP 3, PHP 4 >= 4.0.0)

Změní vlastníka souboru

```
int chown ( string filename, mixed user) \linebreak
```

Pokusí se změnit vlastníka souboru na *user*. Pouze superuživatel může změnit majitele souboru.

Při úspěchu vrací TRUE, jinak FALSE.

Viz také `chown()` a `chmod()`.

Poznámka: Tato funkce nefunguje na Windows systémech

clearstatcache (PHP 3, PHP 4 >= 4.0.0)

Vymaže cache stavu souborů

```
void clearstatcache ( void) \linebreak
```

Volání systémových funkcí `stat` či `lstat` má poměrně velkou režii. Tudíž se výsledek posledního volání všech stavových funkcí (viz seznam níže) ukládá pro použití při dalším takovém volání používajícím stejný název souboru. Pokud chcete vynutit novou kontrolu stavu, např. pokud je soubor kontrolován mnohokrát a může se změnit nebo zmizet, použijte tuto funkci k uvolnění výsledků posledního volání z paměti.

Tato hodnota se cachuje pouze po dobu běhu skriptu.

Ovlivněné funkce: `stat()`, `lstat()`, `file_exists()`, `is_writable()`, `is_readable()`, `is_executable()`, `is_file()`, `is_dir()`, `is_link()`, `filectime()`, `fileatime()`, `filemtime()`, `fileinode()`, `filegroup()`, `fileowner()`, `filesize()`, `filetype()`, a `fileperms()`.

copy (PHP 3, PHP 4 >= 4.0.0)

Zkopíruje soubor

int copy (string source, string dest) \linebreak

Vytvoří kopii souboru. Vrací TRUE pokud se kopírování zdařilo, jinak FALSE.

Příklad 1. Ukázka copy()

```
if (!copy($file, $file.'.bak')) {
    print ("failed to copy $file...<br>\n");
}
```

Viz také rename().

delete (unknown)

Falešná položka manuálu

void delete (string file) \linebreak

Toto je falešná položka manuálu, která by měla pomoci lidem, kteří hledají unlink() nebo unset() na špatném místě.

Viz také unlink() (mazání souborů), unset() (mazání proměnných).

dirname (PHP 3, PHP 4 >= 4.0.0)

Vrací část cesty obsahující název adresáře

string dirname (string path) \linebreak

Přijímá řetězec obsahující cestu na soubor a vrací název adresáře.

Na Windows se jako oddělovač sestry dají používat jak lomítko (/), tak zpětné lomítko (\). Na ostatních systémech je to lomítko (/).

Příklad 1. Ukázka dirname()

```
$path = "/etc/passwd";
$file = dirname ($path); // $file obsahuje "/etc"
```

Viz také basename()

diskfreespace (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Vrátí diskový prostor dostupný v adresáři

float **diskfreespace** (string directory) \linebreak

Přijímá řetězec obsahující cestu na adresář, vrací počet bytů dostupných na odpovídajícím filesystému nebo oddílu.

Příklad 1. Ukázka diskfreespace()

```
$df = diskfreespace("/"); // $df obsahuje pocet bytu
                        // dostupnych na "/"
```

fclose (PHP 3, PHP 4 >= 4.0.0)

Zavře otevřený deskriptor souboru

int **fclose** (int fp) \linebreak

Soubor, na který *fp* ukazuje, se zavře.

Vrací TRUE při úspěchu a FALSE při selhání.

Deskriptor souboru musí být platný, a musí ukazovat na soubor úspěšně otevřený pomocí fopen() nebo fsockopen().

feof (PHP 3, PHP 4 >= 4.0.0)

Test na konec souboru

int **feof** (int fp) \linebreak

Vrací TRUE, pokud je konec souboru (EOF) nebo nastala chyba, jinak FALSE.

Deskriptor souboru musí být platný a musí ukazovat na soubor úspěšně otevřený pomocí fopen(), popen(), nebo fsockopen().

fflush (PHP 4)

Zapiše obsah výstupního bufferu

int **fflush** (int fp) \linebreak

Funkce vynutí okamžitý zápis veškerých dat uložených ve výstupním bufferu do souboru odkazovaného pomocí deskriptoru *fp*. Vrací TRUE při úspěchu, jinak FALSE.

Deskriptor souboru musí být platný a musí ukazovat na soubor úspěšně otevřený pomocí fopen(), popen(), nebo fsockopen().

fgetc (PHP 3, PHP 4 >= 4.0.0)

Načte 1 znak ze souboru

string **fgetc** (int *fp*) \linebreak

Vrátí řetězec obsahující jediný znak přečtený ze souboru odkazovaného pomocí deskriptoru *fp*. Je-li konec souboru (EOF), vrátí FALSE.

Deskriptor souboru musí být platný a musí ukazovat na soubor úspěšně otevřený pomocí *fopen()*, *popen()*, nebo *fsockopen()*.

Viz také *fread()*, *fopen()*, *popen()*, *fsockopen()*, a *fgets()*.

fgetcsv (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Načte řádek ze souboru a parsuje ho na CSV hodnoty

array **fgetcsv** (int *fp*, int *length* [, string *delimiter*]) \linebreak

Podobné jako *fgets()* s výjimkou toho, že **fgetcsv()** parsuje přečtený řádek podle CSV formátu a vrátí pole obsahující získané hodnoty. Oddělovačem je čárka, pokud nespecifikujete jiný oddělovač jako nepovinný třetí parametr.

fp musí být platný deskriptor souboru úspěšně otevřeného pomocí *fopen()*, *popen()*, nebo *fsockopen()*

Délka *length* musí být větší než nejdelší řádek, vyskytující se v souboru (nepočítaje v to znak konce řádku).

fgetcsv() vrátí FALSE při chybě včetně konce souboru (EOF).

N.B. Prázdný řádek v CSV souboru bude vrácen jako pole s jediným NULL polem, aniž by to bylo vyhodnoceno jako chyba.

Příklad 1. fgetcsv() příklad - Čtení a tisk celého CVS souboru

```
$row = 1;
$fp = fopen ("test.csv","r");
while ($data = fgetcsv ($fp, 1000, ",")) {
    $num = count ($data);
    print "<p> $num fields in line $row: <br>";
    $row++;
    for ($c=0; $c<$num; $c++) {
        print $data[$c] . "<br>";
    }
}
fclose ($fp);
```

fgets (PHP 3, PHP 4 >= 4.0.0)

Přečte řádek ze souboru

string **fgets** (int fp, int length) \linebreak

Vrací řádek o délce max. *length* - 1 byte přečtený ze souboru. Čtení končí, pokud bylo přečteno *length* - 1 bytů, nastal konec řádku nebo konec souboru (podle toho, co přijde první).

Při výskytu chyby vrací FALSE.

Nejčastější úskalí:

Lidé, kteří používali 'C' sémantiku funkce fgets, by si měli uvědomit rozdíl v tom, jak je vrácen konec souboru.

Deskriptor souboru musí být platný a musí ukazovat na soubor úspěšně otevřený pomocí fopen(), popen(), nebo fsockopen().

Jednoduchý příklad:

Příklad 1. Čtení souboru řádek po řádku

```
$fd = fopen ("/tmp/inputfile.txt", "r");
while (!feof ($fd)) {
    $buffer = fgets($fd, 4096);
    echo $buffer;
}
fclose ($fd);
```

Viz také fread(), fopen(), popen(), fgetc(), fsockopen(), a socket_set_timeout().

fgetss (PHP 3, PHP 4 >= 4.0.0)

Přečte řádek ze souboru a odstraní HTML značky

string **fgetss** (int fp, int length [, string allowable_tags]) \linebreak

Identické s fgets(), ale jsou zde z přečteného textu odstraňovány HTML a PHP značky.

Jako nepovinný třetí parametr můžete specifikovat značky, které nebudou odstraňovány.

Poznámka: *allowable_tags* - přidáno v PHP 3.0.13, PHP4B3.

Viz také fgets(), fopen(), fsockopen(), popen(), a strip_tags().

file (PHP 3, PHP 4 >= 4.0.0)

Načte celý soubor do pole

array **file** (string filename [, int use_include_path]) \linebreak

Identické s `readfile()`, soubor je však vrácen v podobě pole. Každý element pole odpovídá jednomu řádku v souboru včetně znaku konce řádku.

Můžete použít nepovinný druhý parametr a nastavit ho na "1", pokud chcete hledat soubor také v `include_path`.

```
<?php
// načti WWW stránku do pole a vytiskni ji
$fcontents = file ('http://www.php.net');
while (list ($line_num, $line) = each ($fcontents)) {
    echo "<b>Line $line_num:</b> " . htmlspecialchars ($line) . "<br>\n";
}

// načti WWW stránku do řetězce
$fcontents = join ("", file ('http://www.php.net'));
?>
```

Viz také `readfile()`, `fopen()`, `fsockopen()`, a `popen()`.

file_exists (PHP 3, PHP 4 >= 4.0.0)

Zjistí, zda soubor existuje

bool **file_exists** (string filename) \linebreak

Vrací TRUE, pokud soubor specifikovaný pomocí *filename* existuje, jinak FALSE.

file_exists() nefunguje na vzdálených souborech; soubor k ověření musí být přístupný prostřednictvím filesystému serveru.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

filetime (PHP 3, PHP 4 >= 4.0.0)

Vrací čas posledního přístupu k souboru

int **filetime** (string filename) \linebreak

Vrací čas posledního přístupu k souboru, při chybě FALSE. Čas je vrácen jako Unix timestamp.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

Pozn.: *Atime* (čas posl. přístupu) souboru se obvykle mění při čtení datových bloků ze souboru. To se může značně negativně projevit na výkonu systému, pokud aplikace přistupuje k velkému počtu souborů nebo adresářů. Některé Unixové filesystémy mohou mít *atime* deaktivován za účelem zvýšení výkonu pro takové aplikace; takovým případem jsou USENET news spools. Tehdy je tato funkce bezpředmětná.

filectime (PHP 3, PHP 4 >= 4.0.0)

Vrací čas změny inodu souboru

int **filectime** (string filename) \linebreak

Vrací čas poslední změny inodu souboru, při chybě `FALSE`. Čas je vrácen jako Unix timestamp.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

Pozn.: Na většině unixových filesystemů platí, že soubor je považován za změněný, pokud jsou změněna data v Inodu, tj. přístupová práva, vlastník, skupina nebo jiná metadata jsou zapsána do Inodu. `filemtime()` (toto je to, co chcete použít, když chcete vytvořit údaj "Poslední změna" na WWW stránce) a `fileatime()`.

Pozn.: Na některých Unixech je `ctime` považován za čas vytvoření souboru. To je chyba. Na většině unixových filesystemů neexistuje žádný čas vytvoření unixových souborů.

filegroup (PHP 3, PHP 4 >= 4.0.0)

Vrací skupinu pro soubor

int **filegroup** (string filename) \linebreak

Vrací ID skupiny vlastníka souboru, při chybě `FALSE`. Skupinové ID je v číselném tvaru, použijte `posix_getgrgid()` pro získání názvu skupiny.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

Poznámka: Tato funkce nefunguje na Windows systémech

fileinode (PHP 3, PHP 4 >= 4.0.0)

Vrací inode souboru

int **fileinode** (string filename) \linebreak

Vrací inode číslo souboru, při chybě `FALSE`.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

Poznámka: Tato funkce nefunguje na Windows systémech

filemtime (PHP 3, PHP 4 >= 4.0.0)

Vrací čas změny souboru

int **filemtime** (string filename) \linebreak

Vrací čas poslední změny souboru, při chybě `FALSE`. Čas je vrácen jako Unix timestamp.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

Tato funkce vrací čas, kdy byly zapsány datové bloky, tj. čas poslední změny obsahu souboru.

Použijte funkci `date()` na výsledek této funkce k získání formátovaného tvaru data pro použití na WWW stránkách.

fileowner (PHP 3, PHP 4 >= 4.0.0)

Vrací vlastníka souboru

int **fileowner** (string filename) \linebreak

Vrací ID uživatele (UID), vlastnictvího soubor; při chybě `FALSE`. Hodnota je v číselném tvaru, použijte funkci `posix_getpwuid()` k získání uživatelského jména.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

Poznámka: Tato funkce nefunguje na Windows systémech

fileperms (PHP 3, PHP 4 >= 4.0.0)

Vrací přístupová práva k souboru

int **fileperms** (string filename) \linebreak

Vrací přístupová práva (permissions) k souboru, při chybě `FALSE`.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

filesize (PHP 3, PHP 4 >= 4.0.0)

Vrací velikost souboru

int **filesize** (string filename) \linebreak

Vrací velikost souboru, při chybě `FALSE`.

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

filetype (PHP 3, PHP 4 >= 4.0.0)

Vrací typ souboru

string **f filetype** (string filename) \linebreak

Vrací typ souboru. Možné hodnoty jsou fifo, char, dir, block, link, file a unknown.

Při chybě vrací FALSE.

Výsledek této funkce je cachován. Více informací - viz clearstatcache().

flock (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Jednotné "portable advisory" zamykání souboru

bool **flock** (int fp, int operation [, int wouldblock]) \linebreak

PHP podporuje "portable" způsob zamykání celých souborů na základě jednotného "advisory" principu (tzn. všechny přistupující programy musí používat tentýž systém zamykání, jinak to nebude fungovat).

flock() funguje na deskriptoru *fp*, který musí patřit otevřenému souboru. *operation* je jedna z následujících hodnot:

- K získání sdíleného (shared) zámku (čtení) nastavte *operation* na LOCK_SH (resp. 1 u verzí do PHP 4.0.1).
- K získání výhradního zámku (zápis) nastavte *operation* na LOCK_EX (resp. 2 u verzí do PHP 4.0.1).
- K uvolnění zámku (sdíleného nebo výhradního) nastavte *operation* na LOCK_UN (resp. 3 u verzí do PHP 4.0.1).
- Pokud nechcete, aby funkce **flock()** blokovala během zamykání, přidejte k *operation* hodnotu LOCK_NB (4 pro verze do PHP 4.0.1).

flock() umožňuje jednoduchý model čtení/zápis použitelný teoreticky na všech platformách (včetně většiny Unixů a nejspíš i Windows). Nepovinný třetí argument se nastaví na TRUE, pokud by zámek měl blokovat (EWOULDBLOCK errno podmínka).

flock() vrací TRUE při úspěchu, FALSE při chybě (např. když nelze vytvořit zámek).

Varování

Na většině operačních systémů je funkce **flock()** implementována na úrovni procesů. Při použití multithreadového serverového API (jako je ISAPI) nemůžete spoléhat na ochranu souborů proti jiným PHP skriptům běžícím v paralelních vláknech stejné instance serveru!

fopen (PHP 3, PHP 4 >= 4.0.0)

Otevře soubor nebo URL

int **fopen** (string filename, string mode [, int use_include_path]) \linebreak

Jestliže *filename* začíná "http://" (velkými nebo malými písmeny), je otevřeno spojení na příslušný server protokolem HTTP 1.0 a je vrácen deskriptor ukazující na začátek těla dokumentu. Posílá se hlavička 'Host:' pro přístup k virtuálním serverům založeným na jméně.

Nezpracovává HTTP přesměrování, je třeba vložit koncové lomítko za název adresáře.

Když *filename* začíná "ftp://" (velká či malá písmena), je otevřena FTP relace na příslušný server a vrácen deskriptor na požadovaný soubor. Pokud server nepodporuje pasivní režim FTP komunikace, selže to. Můžete přes FTP otvírat soubory pro čtení i zápis, ale ne pro obojí najednou.

Když *filename* je buď "php://stdin", "php://stdout", nebo "php://stderr", bude otevřen standardní vstup/výstup (stdio). (To platí od verze PHP 3.0.13; v dřívějších verzích se musí použít názvy jako "/dev/stdin" nebo "/dev/fd/0".)

Když *filename* začíná čímkoli jiným, bude otevřen obyčejný soubor (z filesystemu) a vrácen jeho deskriptor.

Pokud otvírání selže, funkce vrátí FALSE.

mode může být kterýkoli z těchto:

- 'r' - Otevřít pouze pro čtení; nastaví ukazatel na začátek souboru.
- 'r+' - Otevřít pro čtení a zápis; nastaví ukazatel na začátek souboru.
- 'w' - Otevřít pouze pro zápis; nastaví ukazatel na začátek souboru a zkrátí soubor na nulovou délku. Pokud soubor neexistuje, pokusí se ho vytvořit.
- 'w+' - Otevřít pro čtení a zápis; nastaví ukazatel na začátek souboru a zkrátí soubor na nulovou délku. Pokud soubor neexistuje, pokusí se ho vytvořit.
- 'a' - Otevřít pouze pro zápis; nastaví ukazatel na konec souboru, Pokud soubor neexistuje, pokusí se ho vytvořit.
- 'a+' - Otevřít pro čtení a zápis; nastaví ukazatel na konec souboru. Pokud soubor neexistuje, pokusí se ho vytvořit.

mode může obsahovat písmeno 'b'. To je užitečné pouze na systémech které rozlišují mezi binárními a textovými soubory (nikoli např. na Unixu). Pokud není zapotřebí, je ignorován.

Můžete použít nepovinný třetí parametr a nastavit ho na "1", pokud chcete hledat soubor také v include_path.

Příklad 1. fopen() příklad

```
$fp = fopen ("/home/rasmus/file.txt", "r");
$fp = fopen ("/home/rasmus/file.gif", "wb");
$fp = fopen ("http://www.php.net/", "r");
$fp = fopen ("ftp://user:password@example.com/", "w");
```

Pokud jste zaznamenali problémy se čtením a zápisem do souborů a používáte PHP jako modul do serveru, nezapomeňte zajistit, aby soubory a adresáře, které používáte, byly přístupné pro serverový proces.

Na Windows je třeba oescapovat všechna zpětná lomítka ve specifikaci cesty k souboru nebo používat obyčejná (dopředná) lomítka.

```
$fp = fopen ("c:\\data\\info.txt", "r");
```

Viz také `fclose()`, `fsockopen()`, `socket_set_timeout()`, a `popen()`.

fpasssthru (PHP 3, PHP 4 >= 4.0.0)

Vypíše všechna zbývající data v souboru

int fpasssthru (**int** *fp*) \linebreak

Čte až do dosažení konce souboru specifikovaného deskriptorem a načtené přepisuje na standardní výstup.

Pokud nastane chyba, funkce **fpasssthru()** vrátí `FALSE`.

Deskriptor souboru musí být platný a musí ukazovat na soubor úspěšně otevřený pomocí `fopen()`, `popen()`, nebo `fsockopen()`. Až funkce **fpasssthru()** ukončí čtení, zavře soubor (deskriptor *fp* tím ztrácí smysl).

Když chcete vypsát obsah souboru na standardní výstup (`stdout`), můžete použít funkci `readfile()`, která vás ušetří volání funkce `fopen()`.

Viz také `readfile()`, `fopen()`, `popen()`, a `fsockopen()`

fputs (PHP 3, PHP 4 >= 4.0.0)

Zapíše do souboru

int fputs (**int** *fp*, **string** *str* [, **int** *length*]) \linebreak

Funkce **fputs()** je alias k `fwrite()` a je s ní tedy naprosto identická. Uvědomte si, že parametr *length* je nepovinný a pokud není specifikován, zapíše se celý řetězec.

fread (PHP 3, PHP 4 >= 4.0.0)

Binárně bezpečné čtení ze souboru

string fread (**int** *fp*, **int** *length*) \linebreak

fread() přečte nejvýše *length* bytů ze souboru specifikovaného deskriptorem *fp*. Čtení končí, pokud je přečteno *length* bytů nebo je dosažen konec souboru (podle toho, co přijde dříve).

```
// načte obsah souboru do řetězce
$filename = "/usr/local/something.txt";
$fd = fopen ($filename, "r");
$contents = fread ($fd, filesize ($filename));
fclose ($fd);
```

Viz také `fwrite()`, `fopen()`, `fsockopen()`, `popen()`, `fgets()`, `fgetss()`, `fscanf()`, `file()`, a `fpasssthru()`.

fscanf (PHP 4)

Parsuje vstup ze souboru podle formátu

`mixed fscanf (int handle, string format [, string var1]) \linebreak`

Funkce **fscanf()** je podobná `sscanf()`, ale načítá ze souboru specifikovaného *handle* a interpretuje vstupní data podle specifikovaného formátu *format*. Pokud má funkce pouze dva parametry, parsované hodnoty bude vráceny jako pole. Jinak, když jsou použity nepovinné parametry, funkce vrátí určitý počet asignovaných hodnot. Nepovinné parametry musí být vloženy odkazem.

Příklad 1. fscanf() Příklad

```
$fp = fopen ("users.txt", "r");
while ($userinfo = fscanf ($fp, "%s\t%s\t%s\n")) {
    list ($name, $profession, $countrycode) = $userinfo;
    //... udelej neco s hodnotami
}
fclose($fp);
```

Příklad 2. users.txt

```
javier  argonaut      pe
hiroshi sculptor     jp
robert  slacker      us
luigi   florist       it
```

Viz také `fread()`, `fgets()`, `fgetss()`, `sscanf()`, `printf()`, a `sprintf()`.

fseek (PHP 3, PHP 4 >= 4.0.0)

Posouvá ukazatel v souboru

`int fseek (int fp, int offset [, int whence]) \linebreak`

Nastaví ukazatel pozice v souboru specifikované pomocí deskriptoru *fp*. Nová pozice, měřená počtem bytů od začátku souboru, je získána přičtením hodnoty *offset* k pozici specifikované pomocí *whence*, jehož hodnota je definována:

SEEK_SET - Nastav na pozici rovnu *offset* bytů.

SEEK_CUR - Nastav pozici na současnou plus počet bytů v *offset*.

SEEK_END - Nastav na konec souboru plus *offset* bytů.

Pokud není parametr *whence* specifikován, použije se SEEK_SET.

Při úspěchu vrátí 0, jinak -1. Pozn.: přesun za konec souboru není považován za chybu.

Nelze použít na deskriptor souboru vrácený funkcí `fopen()`, jestliže byl použit formát "http://" nebo "ftp://".

Poznámka: Argument *whence* byl přidán po verzi PHP 4.0 RC1.

Viz také `ftell()` a `rewind()`.

fstat (PHP 4 >= 4.0.0)

Vrací informace o otevřeném souboru

array **fstat** (int *fp*) \linebreak

Sbírá statistiky otevřeného souboru specifikovaném deskriptorem *fp*. Tato funkce je podobná funkci `stat()`, pracuje však s deskriptorem, nikoli názvem souboru.

Vrací pole se statistikami souboru s těmito elementy:

1. device
2. inode
3. number of links
4. user id of owner
5. group id owner
6. device type if inode device *
7. size in bytes
8. time of last access
9. time of last modification
10. time of last change
11. blocksize for filesystem I/O *
12. number of blocks allocated

* - platné pouze na systémech s podporou typu `st_blksize` -- jinde (např. na Windows) vrací -1

Výsledek této funkce je cachován. Více detailů - viz `clearstatcache()`.

ftell (PHP 3, PHP 4 >= 4.0.0)

Vrací pozici v souboru

int **ftell** (int *fp*) \linebreak

Vrací pozici v souboru odkazovaném deskriptorem *fp*; typicky offset ve streamu.

Pokud nastane chyba, vrací `FALSE`.

Deskriptor souboru musí být platný a musí ukazovat na soubor úspěšně otevřený pomocí `fopen()`, `popen()`, nebo `fsockopen()`.

Viz také `fopen()`, `popen()`, `fseek()` a `rewind()`.

ftruncate (PHP 4 >= 4.0.0)

Zkrátí soubor na danou délku

`int ftruncate (int fp, int size) \linebreak`

Vezme soubor specifikovaný pomocí *fp* a zkrátí ho na délku *size*. Vrací `TRUE` při úspěchu a `FALSE` při chybě.

fwrite (PHP 3, PHP 4 >= 4.0.0)

Binárně bezpečný zápis do souboru

`int fwrite (int fp, string string [, int length]) \linebreak`

fwrite() zapíše obsah řetězce *string* do souboru specifikovaného pomocí *fp*. Pokud je zde argument *length*, zápis skončí po zapsání *length* bytů nebo při dosažení konce řetězce *string*, podle toho, co přijde dříve.

Pozn.: pokud je dán argument *length*, volba `magic_quotes_runtime` v konfiguraci bude ignorována a nebudou odstraňována žádná lomítka z řetězce *string*.

Viz také `fread()`, `fopen()`, `fsockopen()`, `popen()`, a `fputs()`.

is_dir (PHP 3, PHP 4 >= 4.0.0)

Zjistí, zda je daný soubor adresářem

`bool is_dir (string filename) \linebreak`

Vrací `TRUE` když soubor existuje a jedná se o adresář.

Výsledek této funkce je cachován. Více detailů - viz `clearstatcache()`.

Viz také `is_file()` a `is_link()`.

is_executable (PHP 3, PHP 4 >= 4.0.0)

Zjistí, zda je soubor spustitelný

`bool is_executable (string filename) \linebreak`

Vrací `TRUE`, když soubor existuje a je spustitelný (proveditelný)

Výsledek této funkce je cachován. Více detailů - viz clearstatcache().

Viz také is_file() a is_link().

is_file (PHP 3, PHP 4 >= 4.0.0)

Zjistí, zda se jedná o obyčejný (regular) soubor

bool **is_file** (string filename) \linebreak

Vrací TRUE, když soubor existuje a jedná se o obyčejný (regular) soubor

Výsledek této funkce je cachován. Více detailů - viz clearstatcache().

Viz také is_dir() a is_link().

is_link (PHP 3, PHP 4 >= 4.0.0)

Zjistí, zda se jedná o symbolický odkaz (link)

bool **is_link** (string filename) \linebreak

Vrací TRUE, když soubor existuje a jedná se o symbolický odkaz (link).

Výsledek této funkce je cachován. Více detailů - viz clearstatcache().

Viz také is_dir() a is_file().

Poznámka: Tato funkce nefunguje na Windows systémech

is_readable (PHP 3, PHP 4 >= 4.0.0)

Zjistí, zda lze ze souboru číst

bool **is_readable** (string filename) \linebreak

Vrací TRUE, když soubor existuje a lze z něj číst.

Mějte na paměti, že PHP může přistupovat k souboru s právy, kterými disponuje WWW server (obvykle 'nobody'). Omezení bezpečného režimu (safe mode limitations) are not taken into account.

Výsledek této funkce je cachován. Více detailů - viz clearstatcache().

Viz také is_writable().

is_uploaded_file (PHP 3 >= 3.0.17, PHP 4 >= 4.0.3)

Zjistí, zda byl soubor uploadován pomocí HTTP POST

bool **is_uploaded_file** (string filename) \linebreak

Tato funkce je dostupná pouze na verzích PHP 3 od 3.0.16 a na verzích PHP 4 od 4.0.2.

Vrací TRUE, pokud soubor nazvaný `filename` byl uploadován pomocí HTTP POST. To je užitečné k ujištění se, zda se neukázněný uživatel nepokusil upravit skript tak, aby pracoval se soubory, se kterými by pracovat neměl -- například `/etc/passwd`.

Tento druh testů je zvláště důležitý, je-li možnost, že akce na uploadovaných souborech může zpřístupnit jejich obsah uživateli nebo jiným uživatelům tohoto systému.

Viz také `move_uploaded_file()`, a sekce Handling file uploads, kde je příklad jednoduchého použití.

is_writable (PHP 4 >= 4.0.0)

Zjistí, zda lze do souboru zapisovat

bool **is_writable** (string filename) \linebreak

Vrací TRUE, když soubor existuje a lze do něj zapisovat. Název souboru (argument `filename`) může být název adresáře, potom se zjišťuje, zda lze do adresáře zapisovat.

Mějte na paměti, že PHP může přistupovat k souboru s právy, kterými disponuje WWW server (obvykle 'nobody'). Omezení bezpečného režimu (safe mode limitations) are not taken into account.

Výsledek této funkce je cachován. Více detailů - viz `clearstatcache()`.

Viz také `is_readable()`.

link (PHP 3, PHP 4 >= 4.0.0)

Vytvoří hard link

int **link** (string target, string link) \linebreak

link() vytvoří hard link.

Viz také `symlink()` pro vytváření symbolických linků a `readlink()` spolu s `linkinfo()`.

Poznámka: Tato funkce nefunguje na Windows systémech

linkinfo (PHP 3, PHP 4 >= 4.0.0)

Vrací informaci o odkazu (linku)

int **linkinfo** (string path) \linebreak

linkinfo() vrací položku `st_dev` field struktury UNIX C stat získanou systémovým voláním `lstat`. Tato funkce se používá pro ověření, zda odkaz (specifikovaný pomocí `path`) opravdu existuje (používá se tatáž metoda jako je makro `S_ISLNK` definované v `stat.h`). Vrací 0, v případě chyby `FALSE`.

Viz také `symlink()`, `link()`, a `readlink()`.

Poznámka: Tato funkce nefunguje na Windows systémech

lstat (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

Zjišťuje informace o souboru nebo symbolickém odkazu

array **lstat** (string filename) \linebreak

Sbírá statistiky o souboru nebo symbolickém odkazu (linku) identifikovaném pomocí názvu *filename*. Tato funkce je identická s funkcí `stat()`, s výjimkou situace, kdy parametrem *filename* je symbolický odkaz -- tehdy jsou vráceny informace o odkazu, nikoli o souboru, na který ukazuje.

Vrací pole se statistikami souboru s těmito elementy:

1. device
2. inode
3. inode protection mode
4. number of links
5. user id of owner
6. group id owner
7. device type if inode device *
8. size in bytes
9. time of last access
10. time of last modification
11. time of last change
12. blocksize for filesystem I/O *
13. number of blocks allocated

* - platné pouze na systémech podporou typu `st_blksize` -- jinde (např. na Windows) vrátí -1

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

mkdir (PHP 3, PHP 4 >= 4.0.0)

Vytvoří adresář

int **mkdir** (string pathname, int mode) \linebreak

Pokusí se vytvořit adresář specifikovaný svým názvem.

Pozn.: Pravděpodobně chcete specifikovat mód jako oktalové číslo, potom by však mělo začínat nulou.


```
mkdir ( "/path/to/my/dir", 0700 );
```

Vrací `TRUE` při úspěchu a `FALSE` při chybě.

Viz také `rmdir()`.

move_uploaded_file (PHP 4 >= 4.0.3)

Přesune uploadovaný soubor na nové místo

```
bool move_uploaded_file ( string filename, string destination) \linebreak
```

tato funkce je dostupná pouze ve verzích PHP 3 od 3.0.16 a ve verzích PHP 4 od 4.0.2.

Tato si ověřuje, zda soubor identifikovaný názvem *filename* je platným uploadovaným souborem (prostřednictvím HTTP POST mechanismu poskytovaného PHP). Pokud je soubor platný, je přesunut/přejmenován na *destination*.

Pokud *filename* není platný uploadovaný soubor, funkce **move_uploaded_file()** nic neprovede a vrátí `FALSE`.

Pokud *filename* je platný uploadovaný soubor, ale z nějakého důvodu nemůže být přesunut, funkce **move_uploaded_file()** nic neprovede a vrátí `FALSE`. Navíc je vygenerováno varování (warning).

Tento druh testů je zvláště důležitý, je-li možnost, že akce na uploadovaných souborech může zpřístupnit jejich obsah uživateli nebo jiným uživatelům tohoto systému.

Viz také `is_uploaded_file()`, a sekce Handling file uploads, kde je příklad jednoduchého použití.

pclose (PHP 3, PHP 4 >= 4.0.0)

Zavře procesový soubor (rouru)

```
int pclose ( int fp) \linebreak
```

Zavře rouru otevřenou pomocí funkce `popen()`.

Deskriptor souboru musí být platný a musí ukazovat na rouru úspěšně otevřenou pomocí `popen()`.

Vrací návratový kód procesu, který na rouře běžel.

Viz také `popen()`.

popen (PHP 3, PHP 4 >= 4.0.0)

Otevře procesový soubor (rouru)

```
int popen ( string command, string mode) \linebreak
```

Otevře rouru do procesu spuštěného rozštěpením stávajícího procesu následným a spuštěním programu specifikovaného parametrem *command*.

Vrací deskriptor souboru identický s tím, který vrací funkce `fopen()`, je však vždy pouze jednosměrný (může být otevřen pro čtení nebo zápis, nikoli současně) a na závěr musí být zavřen pomocí `pclose()`. Tento deskriptor může být použit funkcemi `fgets()`, `fgetss()`, a `fputs()`.

Nastane-li chyba, vrací `FALSE`.

```
$fp = popen ( "/bin/ls", "r" );
```

Viz také `pclose()`.

readfile (PHP 3, PHP 4 >= 4.0.0)

Vypíše soubor

```
int readfile ( string filename [, int use_include_path] ) \linebreak
```

Přečte soubor a vypíše ho na standardní výstup.

Vrací počet bytů přečtených ze souboru. Pokud nastane chyba, vrátí `FALSE` a pokud nebyla použita notace `@readfile`, vypíše se chybové hlášení.

Když *filename* začíná "http://" (velkými nebo malými písmeny), otevře se spojení na příslušný server protokolem HTTP 1.0 a získaný dokument se vypíše na standardní výstup.

Nezpracovává HTTP přesměrování, je třeba vložit koncové lomítko za název adresáře.

Když *filename* začíná "ftp://" (velká či malá písmena), je otevřena FTP relace na příslušný server a dokument se vypíše na standardní výstup. Pokud server nepodporuje pasivní režim FTP komunikace, selže to.

Když *filename* začíná čímkoli jiným, bude otevřen obyčejný soubor (z filesystému) a jeho obsah vypsán na standardní výstup.

Můžete použít nepovinný třetí parametr a nastavit ho na "1", pokud chcete hledat soubor také v `include_path`.

Viz také `fpasssthru()`, `file()`, `fopen()`, `include()`, `require()`, a `virtual()`.

readlink (PHP 3, PHP 4 >= 4.0.0)

Vrací cíl symbolického odkazu

```
string readlink ( string path ) \linebreak
```

readlink() provádí totéž jako funkce `readlink` v C a vrací název souboru, na který symbolický odkaz (`link`) ukazuje. Při chybě vrací 0.

Viz také `symlink()`, **readlink()** a `linkinfo()`.

Poznámka: Tato funkce nefunguje na Windows systémech

realpath (PHP 4 >= 4.0.0)

Vrátí absolutní cestu v kanonickém tvaru

string **realpath** (string *path*) \linebreak

realpath() zpracuje všechny symbolické odkazy a vyhodnotí odkazy na `'./'`, `'../'` a samostatné znaky `'/'` v parametru *path* a vrátí absolutní cestu v kanonickém tvaru. Tato výsledná cesta neobsahuje symbolické odkazy a komponenty typu `'./'` or `'../'`.

Příklad 1. realpath() příklad

```
$real_path = realpath ( "../../index.php" );
```

rename (PHP 3, PHP 4 >= 4.0.0)

Přejmenuje soubor

int **rename** (string *oldname*, string *newname*) \linebreak

Pokusí se přejmenovat soubor *oldname* na *newname*.

Vrací TRUE při úspěchu a FALSE při chybě.

rewind (PHP 3, PHP 4 >= 4.0.0)

Vrátí ukazatel v souboru na začátek

int **rewind** (int *fp*) \linebreak

Nastaví pozici ukazatele v souboru specifikované deskriptorem *fp* na začátek tohoto souboru.

Nastane-li chyba, vrátí 0.

Deskriptor souboru musí být platný a musí ukazovat na soubor úspěšně otevřený pomocí `fopen()`.

Viz také `fseek()` a `ftell()`.

rmdir (PHP 3, PHP 4 >= 4.0.0)

Odstraní adresář

int **rmdir** (string dirname) \linebreak

Pokusí se odstranit adresář specifikovaný svým názvem. Adresář musí být prázdný a mít nastavena odpovídající oprávnění.

Nastane-li chyba, vrátí 0.

Viz také mkdir().

set_file_buffer (PHP 3>= 3.0.8, PHP 4)

Nastaví buffer pro soubor

int **set_file_buffer** (int fp, int buffer) \linebreak

Výstup pomocí fwrite() je implicitně bufferován do bufferu o velikosti 8 KB. To znamená, že když chtějí dva procesy zapisovat do téhož streamu (souboru), každý je vždy po 8 KB přerušen, aby ten druhý mohl zapisovat. Funkce **set_file_buffer()** nastavuje buffering pro zápis přes daný deskriptor *fp* na *buffer* bytů. Pokud je *buffer* roven 0, zápisy nejsou bufferovány. To zajišťuje, že všechny zápisy jsou dokončeny dříve, než ostatní procesy mohou do souboru zapisovat.

Funkce vrátí 0 při úspěchu nebo EOF (konec souboru) pokud požadavek nemůže být uskutečněn.

Následující příklad demonstruje, jak používat funkci **set_file_buffer()** k vytvoření nebufferovaného streamu.

Příklad 1. set_file_buffer() example

```
$fp=fopen($file, "w");
if($fp){
    set_file_buffer($fp, 0);
    fputs($fp, $output);
    fclose($fp);
}
```

Viz také fopen(), fwrite().

stat (PHP 3, PHP 4 >= 4.0.0)

Zjistí uje informace o souboru

array **stat** (string filename) \linebreak

Sbírá statistiky o souboru indentifikovaném názvem *filename*.

Vrací pole se statistikami souboru s těmito elementy:

1. device
2. inode
3. inode protection mode

4. number of links
5. user id of owner
6. group id owner
7. device type if inode device *
8. size in bytes
9. time of last access
10. time of last modification
11. time of last change
12. blocksize for filesystem I/O *
13. number of blocks allocated

* - platné pouze na systémech podporou typu `st_blksize` -- jinde (např. na Windows) vrátí -1

Výsledek této funkce je cachován. Více informací - viz `clearstatcache()`.

symlink (PHP 3, PHP 4 >= 4.0.0)

Vytvoří symbolický odkaz

`int symlink (string target, string link) \linebreak`

symlink() vytvoří symbolický odkaz (link) k existujícímu souboru *target* a nazve ho *link*.

Viz také `link()` -- vytváření hard linků, a `readlink()` společně s `linkinfo()`.

Poznámka: Tato funkce nefunguje na Windows systémech.

tempnam (PHP 3, PHP 4 >= 4.0.0)

Vytvoří soubor s unikátním názvem

`string tempnam (string dir, string prefix) \linebreak`

Ve specifikovaném adresáři vytvoří dočasný soubor s unikátním názvem. Pokud adresář neexistuje, **tempnam()** může vytvořit soubor v systémovém adresáři pro dočasné soubory.

Chování funkce **tempnam()** je závislé na platformě. Na Windows má parametr *dir* přednost před systémovou proměnnou `TMP`, na Linuxu má přednost proměnná `TMPDIR` a SVR4 vždy použije parametr *dir*, pokud tento adresář existuje. Podívejte se do dokumentace k vašemu systému na funkci `tempnam(3)`.

Vrací název nového dočasného souboru, při chybě pak řetězec `NULL`.

Příklad 1. tempnam() příklad

```
$tmpfname = tempnam ( "/tmp", "FOO" );
```

Poznámka: Chování této funkce bylo změněno ve verzi 4.0.3. The temporary file is also created to avoid a race condition where the file might appear in the filesystem between the time the string was generated and before the the script gets around to creating the file.

Viz také tmpfile().

tmpfile (PHP 3 >= 3.0.13, PHP 4 >= 4.0.0)

Vytvoří dočasný soubor

```
int tmpfile ( void) \linebreak
```

Vytvoří dočasný soubor s unikátním názvem, v módu zápisu, a vrací deskriptor tohoto souboru podobně jako fopen(). Soubor se při zavření (pomocí fclose()) nebo při ukončení skriptu automaticky smaže.

Detaily viz systémová dokumentace k funkci tmpfile(3) a soubor stdio.h.

Viz také tempnam().

touch (PHP 3, PHP 4 >= 4.0.0)

Nastavit čas změny souboru

```
int touch ( string filename [, int time]) \linebreak
```

Pokusí se nastavit čas změny souboru *filename* na *time*. Pokud *filename* není přítomen, použije se aktuální čas.

Pokud tento soubor neexistuje, vytvoří se.

Při úspěchu vrací TRUE, jinak FALSE.

Příklad 1. Ukázka touch()

```
if (touch ($FileName)) {
    print "$FileName modification time has been
        changed to todays date and time";
} else {
    print "Sorry Could Not change modification time of $FileName";
}
```

umask (PHP 3, PHP 4 >= 4.0.0)

Změní současné nastavení umask

int **umask** (int mask) \linebreak

umask() nastaví umask PHP na & 0777 a vrátí staré nastavení umask. Pokud PHP běží jako modul serveru, je staré nastavení obnoveno po ukončení každého HTTP požadavku.

umask() bez parametrů vrací současné nastavení umask.

Poznámka: Tato funkce nemusí na Windows fungovat

unlink (PHP 3, PHP 4 >= 4.0.0)

Smazat soubor

int **unlink** (string filename) \linebreak

Smaže *filename*. Podobná Unixové C funkci unlink().

Při chybě vrací 0 nebo FALSE.

Viz také rmdir() pro mazání adresářů.

Poznámka: Tato funkce nemusí na Windows fungovat

XXXI. Forms Data Format functions

Forms Data Format (FDF) is a format for handling forms within PDF documents. You should read the documentation at <http://partners.adobe.com/asn/developer/acrosdk/forms.html> for more information on what FDF is and how it is used in general.

Poznámka: If you run into problems configuring php with fdfk support, check whether the header file FdfTk.h and the library libFdfTk.so are at the right place. They should be in fdfk-dir/include and fdfk-dir/lib. This will not be the case if you just unpack the FdfTk distribution.

The general idea of FDF is similar to HTML forms. The difference is basically the format how data is transmitted to the server when the submit button is pressed (this is actually the Form Data Format) and the format of the form itself (which is the Portable Document Format, PDF). Processing the FDF data is one of the features provided by the fdf functions. But there is more. One may as well take an existing PDF form and populated the input fields with data without modifying the form itself. In such a case one would create a FDF document (fdf_create()) set the values of each input field (fdf_set_value()) and associate it with a PDF form (fdf_set_file()). Finally it has to be sent to the browser with MIME type application/vnd.fdf. The Acrobat reader plugin of your browser recognizes the MIME type, reads the associated PDF form and fills in the data from the FDF document.

If you look at an FDF-document with a text editor you will find a catalogue object with the name FDF. Such an object may contain a number of entries like Fields, F, Status etc.. The most commonly used entries are Fields which points to a list of input fields, and F which contains the filename of the PDF-document this data belongs to. Those entries are referred to in the FDF documentation as /F-Key or /Status-Key. Modifying this entries is done by functions like fdf_set_file() and fdf_set_status(). Fields are modified with fdf_set_value(), fdf_set_opt() etc..

The following examples shows just the evaluation of form data.

Příklad 1. Evaluating a FDF document

```
<?php
// Save the FDF data into a temp file
$fdffp = fopen("test.fdf", "w");
fwrite($fdffp, $HTTP_FDF_DATA, strlen($HTTP_FDF_DATA));
fclose($fdffp);

// Open temp file and evaluate data
// The pdf form contained several input text fields with the names
// volume, date, comment, publisher, preparer, and two checkboxes
// show_publisher and show_preparer.
$fdf = fdf_open("test.fdf");
$volume = fdf_get_value($fdf, "volume");
echo "The volume field has the value '<B>$volume</B>'<BR>";

$date = fdf_get_value($fdf, "date");
echo "The date field has the value '<B>$date</B>'<BR>";

$comment = fdf_get_value($fdf, "comment");
echo "The comment field has the value '<B>$comment</B>'<BR>";
```



```
if(fdf_get_value($fdf, "show_publisher") == "On") {
    $publisher = fdf_get_value($fdf, "publisher");
    echo "The publisher field has the value '<B>$publisher</B>'<BR>";
} else
    echo "Publisher shall not be shown.<BR>";

if(fdf_get_value($fdf, "show_preparer") == "On") {
    $preparer = fdf_get_value($fdf, "preparer");
    echo "The preparer field has the value '<B>$preparer</B>'<BR>";
} else
    echo "Preparer shall not be shown.<BR>";
fdf_close($fdf);
?>
```

fdf_add_template (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Adds a template into the FDF document

bool **fdf_add_template** (int fdldoc, int newpage, string filename, string template, int rename) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

fdf_close (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Close an FDF document

bool **fdf_close** (int fdf_document) \linebreak

The **fdf_close()** function closes the FDF document.

See also **fdf_open()**.

fdf_create (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Create a new FDF document

int **fdf_create** (void) \linebreak

The **fdf_create()** creates a new FDF document. This function is needed if one would like to populate input fields in a PDF document with data.

Příklad 1. Populating a PDF document

```
<?php
$outfdf = fdf_create();
fdf_set_value($outfdf, "volume", $volume, 0);

fdf_set_file($outfdf, "http://testfdf/resultlabel.pdf");
fdf_save($outfdf, "outtest.fdf");
fdf_close($outfdf);
Header("Content-type: application/vnd.fdf");
$fp = fopen("outtest.fdf", "r");
fpassthru($fp);
unlink("outtest.fdf");
?>
```

See also `fdf_close()`, `fdf_save()`, `fdf_open()`.

fdf_get_file (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Get the value of the /F key

string **fdf_get_file** (int fdf_document) \linebreak

The `fdf_get_file()` returns the value of the /F key.

See also `fdf_set_file()`.

fdf_get_status (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Get the value of the /STATUS key

string **fdf_get_status** (int fdf_document) \linebreak

The `fdf_get_status()` returns the value of the /STATUS key.

See also `fdf_set_status()`.

fdf_get_value (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Get the value of a field

string **fdf_get_value** (int fdf_document, string fieldname) \linebreak

The `fdf_get_value()` function returns the value of a field.

See also `fdf_set_value()`.

fdf_next_field_name (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Get the next field name

string **fdf_next_field_name** (int fdf_document [, string fieldname]) \linebreak

The `fdf_next_field_name()` function returns the name of the field after the field in *fieldname* or the field name of the first field if the second parameter is NULL.

See also `fdf_set_value()`, `fdf_get_value()`.

fdf_open (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Open a FDF document

int **fdf_open** (string filename) \linebreak

The **fdf_open()** function opens a file with form data. This file must contain the data as returned from a PDF form. Currently, the file has to be created 'manually' by using `fopen()` and writing the content of `HTTP_FDF_DATA` with `fwrite()` into it. A mechanism like for HTML form data where for each input field a variable is created does not exist.

Příklad 1. Accessing the form data

```
<?php
// Save the FDF data into a temp file
$fdffp = fopen("test.fdf", "w");
fwrite($fdffp, $HTTP_FDF_DATA, strlen($HTTP_FDF_DATA));
fclose($fdffp);

// Open temp file and evaluate data
$fdf = fdf_open("test.fdf");
...
fdf_close($fdf);
?>
```

See also `fdf_close()`.

fdf_save (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Save a FDF document

int **fdf_save** (string filename) \linebreak

The **fdf_save()** function saves a FDF document. The FDF Toolkit provides a way to output the document to stdout if the parameter *filename* is `''`. This does not work if PHP is used as an apache module. In such a case one will have to write to a file and use e.g. `fpassthru()` to output it.

See also `fdf_close()` and example for `fdf_create()`.

fdf_set_ap (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Set the appearance of a field

bool **fdf_set_ap** (int fdf_document, string field_name, int face, string filename, int page_number) \linebreak

The **fdf_set_ap()** function sets the appearance of a field (i.e. the value of the /AP key). The possible values of *face* are 1=FDFNormalAP, 2=FDFRolloverAP, 3=FDFDownAP.

fdf_set_encoding (PHP 4 >= 4.1.0)

Sets FDF character encoding

```
bool fdf_set_encoding ( int fdf_document, string encoding) \linebreak
```

fdf_set_encoding() sets the character encoding in FDF document *fdf_document.encoding* should be the valid encoding name. The valid encoding name in Acrobat 5.0 are "Shift-JIS", "UHC", "GBK", "BigFive".

The **fdf_set_encoding()** is available in PHP 4.1.0 or later.

fdf_set_file (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Set the value of the /F key

```
bool fdf_set_file ( int fdf_document, string filename) \linebreak
```

The **fdf_set_file()** sets the value of the /F key. The /F key is just a reference to a PDF form which is to be populated with data. In a web environment it is a URL (e.g. <http://testfdf/resultlabel.pdf>).

See also **fdf_get_file()** and example for **fdf_create()**.

fdf_set_flags (PHP 4 >= 4.0.2)

Sets a flag of a field

```
bool fdf_set_flags ( int fdf_document, string fieldname, int whichFlags, int newFlags) \linebreak
```

The **fdf_set_flags()** sets certain flags of the given field *fieldname*.

See also **fdf_set_opt()**.

fdf_set_javascript_action (PHP 4 >= 4.0.2)

Sets an javascript action of a field

```
bool fdf_set_javascript_action ( int fdf_document, string fieldname, int trigger, string script) \linebreak
```

fdf_set_javascript_action() sets a javascript action for the given field *fieldname*.

See also **fdf_set_submit_form_action()**.

fdf_set_opt (PHP 4 >= 4.0.2)

Sets an option of a field

```
bool fdf_set_opt ( int fdf_document, string fieldname, int element, string str1, string str2) \linebreak
```

The **fdf_set_opt()** sets options of the given field *fieldname*.

See also **fdf_set_flags()**.

fdf_set_status (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Set the value of the /STATUS key

```
bool fdf_set_status ( int fdf_document, string status) \linebreak
```

The **fdf_set_status()** sets the value of the /STATUS key.

See also **fdf_get_status()**.

fdf_set_submit_form_action (PHP 4 >= 4.0.2)

Sets a submit form action of a field

```
bool fdf_set_submit_form_action ( int fdf_document, string fieldname, int trigger, string script, int flags) \linebreak
```

The **fdf_set_submit_form_action()** sets a submit form action for the given field *fieldname*.

See also **fdf_set_javascript_action()**.

fdf_set_value (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Set the value of a field

```
bool fdf_set_value ( int fdf_document, string fieldname, string value, int isName) \linebreak
```

The **fdf_set_value()** function sets the value of a field. The last parameter determines if the field value is to be converted to a PDF Name (*isName* = 1) or set to a PDF String (*isName* = 0).

See also **fdf_get_value()**.

XXXII. FriBiDi functions

fribidi_log2vis (PHP 4 >= 4.0.4)

Convert a logical string to a visual one

string **fribidi_log2vis** (string str, string direction, int charset) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

XXXIII. FTP functions

The functions in this extension implement client access to file servers speaking the File Transfer Protocol FTP as defined in <http://www.faqs.org/rfcs/rfc959.html>.

Requirements

The FTP-extension has no special requirements. It's completely contained in PHP.

Installation

In order to use FTP functions with your PHP configuration, you should add the `--enable-ftp` option when installing PHP 4, and `--with-ftp` when using PHP 3.

Configuration

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Resource types

This extension uses one resource-type, which is the link-identifier of the ftp-connection.

Constants

The following constants are defined when using the FTP module: `FTP_ASCII` and `FTP_BINARY`.

Example

Příklad 1. FTP example

```
<?php
// set up basic connection
$conn_id = ftp_connect($ftp_server);

// login with username and password
$login_result = ftp_login($conn_id, $ftp_user_name, $ftp_user_pass);

// check connection
if ((!$conn_id) || (!$login_result)) {
    echo "FTP connection has failed!";
    echo "Attempted to connect to $ftp_server for user $ftp_user_name";
    die;
}
```

```
    } else {  
        echo "Connected to $ftp_server, for user $ftp_user_name";  
    }  
  
    // upload the file  
    $upload = ftp_put($conn_id, $destination_file, $source_file, FTP_BINARY);  
  
    // check upload status  
    if (!$upload) {  
        echo "FTP upload has failed!";  
    } else {  
        echo "Uploaded $source_file to $ftp_server as $destination_file";  
    }  
  
    // close the FTP stream  
    ftp_close($conn_id);  
    ?>
```

ftp_cdup (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Changes to the parent directory

bool **ftp_cdup** (resource ftp_stream) \linebreak

Changes to the parent directory.

Returns `TRUE` on success, `FALSE` on error.

ftp_chdir (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Changes directories on a FTP server

bool **ftp_chdir** (resource ftp_stream, string directory) \linebreak

Changes to the specified *directory*.

Returns `TRUE` on success, `FALSE` on error.

ftp_close (PHP 4 >= 4.2.0)

Closes an FTP connection

void **ftp_close** (resource ftp_stream) \linebreak

Poznámka: This function is only available in CVS.

ftp_close() closes *ftp_stream* and releases the resource. You can't reuse this resource but have to create a new one with `ftp_connect()`.

ftp_connect (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Opens up an FTP connection

resource **ftp_connect** (string host [, int port [, int timeout]]) \linebreak

Returns a FTP stream on success, `FALSE` on error.

ftp_connect() opens up a FTP connection to the specified *host*. The *port* parameter specifies an alternate port to connect to. If it is omitted or zero, then the default FTP port, 21, will be used.

The *timeout* parameter specifies the timeout for all subsequent network operations. If omitted, the default value is 90 seconds. The timeout can be changed and queried anytime with `ftp_set_option()` and `ftp_get_option()`.

Poznámka: This parameter is only available in CVS.

ftp_delete (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Deletes a file on the FTP server

bool **ftp_delete** (resource ftp_stream, string path) \linebreak

ftp_delete() deletes the file specified by *path* from the FTP server.

Returns TRUE on success, FALSE on error.

ftp_exec (PHP 4 >= 4.0.3)

Request execution of a program on the FTP server

bool **ftp_exec** (resource stream, string command) \linebreak

Sends a SITE EXEC *command* request to the FTP server. Returns FALSE if the request fails, returns the output of the command otherwise.

ftp_fget (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Downloads a file from the FTP server and saves to an open file

bool **ftp_fget** (resource ftp_stream, resource fp, string remote_file, int mode) \linebreak

ftp_fget() retrieves *remote_file* from the FTP server, and writes it to the given file pointer, *fp*. The transfer *mode* specified must be either FTP_ASCII or FTP_BINARY.

Returns TRUE on success, FALSE on error.

ftp_fput (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Uploads from an open file to the FTP server

bool **ftp_fput** (resource ftp_stream, string remote_file, resource fp, int mode) \linebreak

ftp_fput() uploads the data from the file pointer *fp* until end of file. The results are stored in *remote_file* on the FTP server. The transfer *mode* specified must be either FTP_ASCII or FTP_BINARY

Returns TRUE on success, FALSE on error.

ftp_get (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Downloads a file from the FTP server

bool **ftp_get** (resource ftp_stream, string local_file, string remote_file, int mode) \linebreak

ftp_get() retrieves *remote_file* from the FTP server, and saves it to *local_file* locally. The transfer *mode* specified must be either FTP_ASCII or FTP_BINARY.

Returns TRUE on success, FALSE on error.

See also ftp_fget().

ftp_get_option (PHP 4 >= 4.2.0)

Retrieves various runtime behaviours of the current FTP stream

mixed **ftp_get_option** (resource stream, int option) \linebreak

Poznámka: This function is only available in CVS.

Returns the value on success, or FALSE if the given *option* is not supported. In the latter case, a warning message is also thrown.

This function returns the value for the requested *option* from the specified *stream* . Currently, the following options are supported:

Tabulka 1. Supported runtime FTP options

FTP_TIMEOUT_SEC	Returns the current timeout used for network related operations.
-----------------	--

Příklad 1. ftp_get_option() example

```
// Get the timeout of the given FTP stream
$timeout = ftp_get_option($conn_id, FTP_TIMEOUT_SEC);
```

ftp_login (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Logs in an FTP connection

bool **ftp_login** (resource ftp_stream, string username, string password) \linebreak

Logs in the given FTP stream.

Returns `TRUE` on success, `FALSE` on error.

ftp_mdtm (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns the last modified time of the given file

int **ftp_mdtm** (resource ftp_stream, string remote_file) \linebreak

ftp_mdtm() checks the last-modified time for a file, and returns it as a UNIX timestamp. If an error occurs, or the file does not exist, -1 is returned. Note that not all servers support this feature.

Returns a UNIX timestamp on success, or -1 on error.

Poznámka: **ftp_mdtm()** does not work with directories.

ftp_mkdir (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Creates a directory

string **ftp_mkdir** (resource ftp_stream, string directory) \linebreak

Creates the specified *directory*.

Returns the newly created directory name on success, `FALSE` on error.

ftp_nlist (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns a list of files in the given directory

array **ftp_nlist** (resource ftp_stream, string directory) \linebreak

Returns an array of filenames from the specified directory on success, `FALSE` on error.

ftp_pasv (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Turns passive mode on or off

bool **ftp_pasv** (resource ftp_stream, bool pasv) \linebreak

ftp_pasv() turns on passive mode if the *pasv* parameter is `TRUE` (it turns off passive mode if *pasv* is `FALSE`.) In passive mode, data connections are initiated by the client, rather than by the server.

Returns `TRUE` on success, `FALSE` on error.

ftp_put (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Uploads a file to the FTP server

bool **ftp_put** (resource ftp_stream, string remote_file, string local_file, int mode) \linebreak

ftp_put() stores *local_file* on the FTP server, as *remote_file*. The transfer *mode* specified must be either FTP_ASCII or FTP_BINARY.

Returns TRUE on success, FALSE on error.

Příklad 1. ftp_put() example

```
$upload = ftp_put($conn_id, $destination_file, $source_file, FTP_ASCII);
```

ftp_pwd (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns the current directory name

string **ftp_pwd** (resource ftp_stream) \linebreak

Returns the current directory, or FALSE on error.

ftp_quit (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Closes an FTP connection

void **ftp_quit** (resource ftp_stream) \linebreak

ftp_quit() is an alias for ftp_close().

ftp_rawlist (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns a detailed list of files in the given directory

array **ftp_rawlist** (resource ftp_stream, string directory) \linebreak

ftp_rawlist() executes the FTP LIST command, and returns the result as an array. Each array element corresponds to one line of text. The output is not parsed in any way. The system type identifier returned by ftp_systype() can be used to determine how the results should be interpreted.

ftp_rename (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Renames a file on the FTP server

bool **ftp_rename** (resource ftp_stream, string from, string to) \linebreak

ftp_rename() renames the file or directory currently named *from* to the new name *to*, on the FTP stream *ftp_stream*.

Returns TRUE on success, FALSE on error.

ftp_rmdir (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Removes a directory

bool **ftp_rmdir** (resource ftp_stream, string directory) \linebreak

Removes the specified *directory*.

Returns TRUE on success, FALSE on error.

ftp_set_option (PHP 4 >= 4.2.0)

Set miscellaneous runtime FTP options

bool **ftp_set_option** (resource stream, int option, mixed value) \linebreak

Poznámka: This function is only available in CVS.

Returns TRUE if the option could be set; FALSE if not. A warning message will be thrown if the *option* is not supported or the passed *value* doesn't match the expected value for the given *option*.

This function controls various runtime options for the specified FTP stream. The *value* parameter depends on which *option* parameter is chosen to be altered. Currently, the following options are supported:

Tabulka 1. Supported runtime FTP options

FTP_TIMEOUT_SEC	Changes the timeout in seconds used for all network related functions. Parameter <i>value</i> has to be of type int and must be greater than 0. The default timeout is 90 seconds.
-----------------	--

Příklad 1. ftp_set_option() example


```
// Set the network timeout down to 10 seconds
ftp_set_option($conn_id, FTP_TIMEOUT_SEC, 10);
```

ftp_site (PHP 3>= 3.0.15, PHP 4 >= 4.0.0)

Sends a SITE command to the server

bool **ftp_site** (resource ftp_stream, string cmd) \linebreak

ftp_site() sends the command specified by *cmd* to the FTP server. SITE commands are not standardized, and vary from server to server. They are useful for handling such things as file permissions and group membership.

Returns TRUE on success, FALSE on error.

ftp_size (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns the size of the given file

int **ftp_size** (resource ftp_stream, string remote_file) \linebreak

ftp_size() returns the size of a file in bytes. If an error occurs, or if the file does not exist, -1 is returned. Not all servers support this feature.

Returns the file size on success, or -1 on error.

ftp_systype (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns the system type identifier of the remote FTP server

string **ftp_systype** (resource ftp_stream) \linebreak

Returns the remote system type, or FALSE on error.

XXXIV. Funkce pro práci s funkcemi

Všechny tyto funkce pokrývají různé aspekty práce s funkcemi.

call_user_func (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Zavolat uživatelskou funkci určenou prvním argumentem

mixed **call_user_func** (string function_name [, mixed parameter [, mixed ...]]) \linebreak

Zavolá uživatelsky definovanou funkci určenou argumentem *function_name*. Zvažte následující ukázkou:

```
function barber ($type) {
    print "You wanted a $type haircut, no problem";
}
call_user_func ('barber', "mushroom");
call_user_func ('barber', "shave");
```

create_function (PHP 4)

Vytvořit anonymní (lambda-style) funkci

string **create_function** (string args, string code) \linebreak

Z předaných argumentů vytvoří anonymní funkci, a vrátí unikátní název této funkce. *args* se obvykle předává jako string v jednoduchých uvozovkách, a doporučujeme to i pro *code*. Důvodem pro jednoduché uvozovky je ochrana názvů proměnných před parsováním, pokud použijete dvojité uvozovky, budete muset oescapovat názvy proměnných, např. `\$avar`.

Tuto funkci můžete (například) použít k vytvoření funkce z dat shromážděných za běhu programu:

Příklad 1. Vytvoření anonymní funkce pomocí create_function()

```
$newfunc = create_function('$a,$b','return "ln($a) + ln($b) = ".log($a * $b);');
echo "New anonymous function: $newfunc\n";
echo $newfunc(2,M_E)." \n";
// výstup
// New anonymous function: lambda_1
// ln(2) + ln(2.718281828459) = 1.6931471805599
```

Nebo třeba k vytvoření obecného handleru, který na předané argumenty aplikuje sadu operací:

Příklad 2. Vytvoření obecné zpracující funkce pomocí create_function()

```
function process($var1, $var2, $farr) {
    for ($f=0; $f < count($farr); $f++)
        echo $farr[$f]($var1,$var2)." \n";
}

// create a bunch of math functions
$f1 = 'if ($a >=0) {return "b*a^2 = ".sqrt($a);} else {return false;}';
$f2 = "return \"min(b^2+a, a^2,b) = \".min(\$a*\$a+\$b,\$b*\$b+\$a);";
$f3 = 'if ($a > 0 && $b != 0) {return "ln(a)/b = ".log($a)/$b;} else {return false;}';
```

```

$farr = array(
    create_function('$x,$y', 'return "some trig: ".(sin($x) + $x*cos($y));'),
    create_function('$x,$y', 'return "a hypotenuse: ".sqrt($x*$x + $y*$y);'),
    create_function('$a,$b', $f1),
    create_function('$a,$b', $f2),
    create_function('$a,$b', $f3)
);

echo "\nUsing the first array of anonymous functions\n";
echo "parameters: 2.3445, M_PI\n";
process(2.3445, M_PI, $farr);

// now make a bunch of string processing functions
$garr = array(
    create_function('$b,$a', 'if (strcmp($a,$b,3) == 0) return "*** \"$a\" ' .
        'and \"$b\" \n** Look the same to me! (looking at the first 3 chars)";'),
    create_function('$a,$b', 'return "CRCs: ".crc32($a)." , ".crc32($b);'),
    create_function('$a,$b', 'return "similar(a,b) = ".similar_text($a,$b,&$p). "($p%)";')
);
echo "\nUsing the second array of anonymous functions\n";
process("Twas brillling and the slithy toves", "Twas the night", $garr);

```

když spustíte výše uvedený kód, výstup bude:

```

Using the first array of anonymous functions
parameters: 2.3445, M_PI
some trig: -1.6291725057799
a hypotenuse: 3.9199852871011
b*a^2 = 4.8103313314525
min(b^2+a, a^2,b) = 8.6382729035898
ln(a/b) = 0.27122299212594

Using the second array of anonymous functions
** "Twas the night" and "Twas brillling and the slithy toves"
** Look the same to me! (looking at the first 3 chars)
CRCs: -725381282 , 1908338681
similar(a,b) = 11(45.833333333333%)

```

Ale zřejmě nejběžnějším využitím lambda-style (anonymních) funkcí je tvorba callback funkcí, např. pro použití v `array_walk()` nebo `usort()`

Příklad 3. Využití anonymních funkcí jako callback funkcí

```

$av = array("the ", "a ", "that ", "this ");
array_walk($av, create_function('&$v,$k', '$v = $v."mango";'));
print_r($av); // for PHP 3 use var_dump()
// outputs:
// Array
// (
//     [0] => the mango
//     [1] => a mango
//     [2] => that mango
//     [3] => this mango
// )

```

```
// an array of strings ordered from shorter to longer
$sv = array("small","larger","a big string","it is a string thing");
print_r($sv);
// outputs:
// Array
// (
//     [0] => small
//     [1] => larger
//     [2] => a big string
//     [3] => it is a string thing
// )

// sort it from longer to shorter
usort($sv, create_function('$a,$b','return strlen($b) - strlen($a);'));
print_r($sv);
// outputs:
// Array
// (
//     [0] => it is a string thing
//     [1] => a big string
//     [2] => larger
//     [3] => small
// )
```

func_get_arg (PHP 4 >= 4.0.0)

Vrátit položku ze seznamu argumentů

mixed **func_get_arg** (int arg_num) \linebreak

Vrací argument, který je na *arg_num*-té pozici v seznamu argumentů uživatelsky definované funkce. Argumenty funkcí se počítají od nuly. **func_get_arg()** při volání mimo definici funkce generuje varování.

Pokud je *arg_num* větší než počet skutečně předaných argumentů, vygeneruje varování a vrátí FALSE.

```
<?php
function foo() {
    $numargs = func_num_args();
    echo "Number of arguments: $numargs<br>\n";
    if ($numargs >= 2) {
        echo "Second argument is: " . func_get_arg (1) . "<br>\n";
    }
}

foo (1, 2, 3);
?>
```

func_get_arg() se dá použít ve spojení s **func_num_args()** a **func_get_args()** k tvorbě uživatelsky definovaných funkcí, které přijímají proměnný počet argumentů.

Poznámka: Tato funkce byla přidána v PHP 4.

func_get_args (PHP 4 >= 4.0.0)

Vrátit pole obsahující seznam argumentů funkce

array **func_get_args** (void) \linebreak

Vrací pole, jehož každý prvek je odpovídající položkou seznamu argumentů současné uživatelsky definované funkce. **func_get_args()** při volání mimo definici funkce generuje varování.

```
<?php
function foo() {
    $numargs = func_num_args();
    echo "Number of arguments: $numargs<br>\n";
    if ($numargs >= 2) {
        echo "Second argument is: " . func_get_arg (1) . "<br>\n";
    }
    $arg_list = func_get_args();
    for ($i = 0; $i < $numargs; $i++) {
        echo "Argument $i is: " . $arg_list[$i] . "<br>\n";
    }
}

foo (1, 2, 3);
?>
```

func_get_args() se dá použít ve spojení s **func_num_args()** a **func_get_arg()** k tvorbě uživatelsky definovaných funkcí, které přijímají proměnný počet argumentů.

Poznámka: Tato funkce byla přidána v PHP 4.

func_num_args (PHP 4 >= 4.0.0)

Vrátit počet argumentů předaných funkci

int **func_num_args** (void) \linebreak

Vrací počet argumentů předaných současné uživatelsky definované funkci. **func_num_args()** při volání mimo definici funkce generuje warning. definition.

```
<?php
function foo() {
    $numargs = func_num_args();
    echo "Number of arguments: $numargs\n";
}

foo (1, 2, 3);    // Prints 'Number of arguments: 3'
?>
```

func_num_args() se dá použít ve spojení s **func_get_arg()** a **func_get_args()** k tvorbě uživatelsky definovaných funkcí, které přijímají proměnný počet argumentů.

Poznámka: Tato funkce byla přidána v PHP 4.

function_exists (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Vrátit TRUE, pokud je daná funkce definována

bool **function_exists** (string function_name) \linebreak

Ověří přítomnost funkce *function_name* v seznamu definovaných funkcí. Pokud daná funkce existuje, vrátí TRUE, jinak FALSE.

```
if (function_exists('imap_open')) {
    echo "IMAP functions are available.<br>\n";
} else {
    echo "IMAP functions are not available.<br>\n";
}
```

Pozn.: název funkce může existovat i v případě, že je samotná funkce nepoužitelná kvůli konfiguraci nebo volbám zadaným při kompilaci.

Viz také **method_exists()**.

register_shutdown_function (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

Zaregistrovat funkci pro provedení při ukončení běhu

int **register_shutdown_function** (string func) \linebreak

Zaregistruje funkci udanou v *func* pro provedení po dokončení běhu skriptu.

Běžné problémy:

Jelikož tato funkce nemůže poslat browseru žádný výstup, nebudete ji moci debugovat pomocí příkazů jako **print()** nebo **echo()**.

XXXV. GNU Gettext

Gettext funkce implementují NLS (Native Language Support) API, která se dá použít k internacionalizaci vašich PHP aplikací. Důkladné vysvětlení těchto funkcí viz dokumentaci GNU Gettext.

bindtextdomain (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Nastavit cestu pro doménu

string **bindtextdomain** (string domain, string directory) \linebreak

Funkce **bindtextdomain()** nastaví cestu pro doménu.

dcgettext (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Změnit doménu pro jediné vyhledání

string **dcgettext** (string domain, string message, int category) \linebreak

Tato funkce vám umožní zmenit současnou doménu pro jediné vyhledání zprávy. Umožňuje také specifikovat kategorii.

dgettext (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Změnit současnou doménu

string **dgettext** (string domain, string message) \linebreak

Funkce **dgettext()** umožňuje změnit současnou doménu pro jediné vyhledání zprávy.

gettext (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Vyhledat zprávu v současné doméně

string **gettext** (string message) \linebreak

Tato funkce vrátí přeložený řetězec, pokud jej najde v překladové tabulce, nebo předaný řetězec, pokud jej nenajde. Jako alias k této funkci můžete použít podtržítko.

Příklad 1. gettext()-check

```
<?php
// Set language to German
putenv ( "LANG=de" );

// Specify location of translation tables
bindtextdomain ( "myPHPApp", "../locale" );

// Choose domain
textdomain ( "myPHPApp" );

// Print a test message
print (gettext ( "Vítejte v mé PHP Aplikaci" ));
?>
```

textdomain (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Nastavit výchozí doménu

string **textdomain** (string text_domain) \linebreak

Tato funkce nastaví doménu pro vyhledávání při volání funkce `gettext()`, obvykle pojmenovanou podle aplikace. Vrátí předchozí výchozí doménu. Při volání bez argumentů vrátí současné nastavení, aniž by jej měnila.

XXXVI. GMP functions

These functions allow you to work with arbitrary-length integers using the GNU MP library. In order to have these functions available, you must compile PHP with GMP support by using the `--with-gmp` option.

You can download the GMP library from <http://www.swox.com/gmp/>. This site also has the GMP manual available.

You will need GMP version 2 or better to use these functions. Some functions may require more recent version of the GMP library.

These functions have been added in PHP 4.0.4.

Poznámka: Most GMP functions accept GMP number arguments, defined as `resource` below. However, most of these functions will also accept numeric and string arguments, given that it is possible to convert the latter to a number. Also, if there is a faster function that can operate on integer arguments, it would be used instead of the slower function when the supplied arguments are integers. This is done transparently, so the bottom line is that you can use integers in every function that expects GMP number. See also the `gmp_init()` function.

Varování

If you want to explicitly specify a large integer, specify it as a string. If you don't do that, PHP will interpret the integer-literal first, possibly resulting in loss of precision, even before GMP comes into play.

Příklad 1. Factorial function using GMP

```
<?php
function fact ($x) {
    if ($x <= 1)
        return 1;
    else
        return gmp_mul ($x, fact ($x-1));
}

print gmp_strval (fact (1000)) . "\n";
?>
```

This will calculate factorial of 1000 (pretty big number) very fast.

gmp_abs (PHP 4 >= 4.0.4)

Absolute value

resource **gmp_abs** (resource a) \linebreak

Returns absolute value of *a*.

gmp_add (PHP 4 >= 4.0.4)

Add numbers

resource **gmp_add** (resource a, resource b) \linebreak

Add two GMP numbers. The result will be a GMP number representing the sum of the arguments.

gmp_and (PHP 4 >= 4.0.4)

Logical AND

resource **gmp_and** (resource a, resource b) \linebreak

Calculates logical AND of two GMP numbers.

gmp_clrbit (PHP 4 >= 4.0.4)

Clear bit

resource **gmp_clrbit** (resource &a, int index) \linebreak

Clears (sets to 0) bit *index* in *a*.

gmp_cmp (PHP 4 >= 4.0.4)

Compare numbers

int **gmp_cmp** (resource a, resource b) \linebreak

Returns a positive value if $a > b$, zero if $a = b$ and negative value if $a < b$.

gmp_com (PHP 4 >= 4.0.4)

Calculates one's complement of *a*

resource **gmp_com** (resource *a*) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

gmp_div (PHP 4 >= 4.0.4)

Divide numbers

resource **gmp_div** (resource *a*, resource *b*) \linebreak

This function is an alias to `gmp_div_q()`.

gmp_div_q (PHP 4 >= 4.0.4)

Divide numbers

resource **gmp_div_q** (resource *a*, resource *b* [, int *round*]) \linebreak

Divides *a* by *b* and returns the integer result. The result rounding is defined by the *round*, which can have the following values:

- `GMP_ROUND_ZERO`: The result is truncated towards 0.
- `GMP_ROUND_PLUSINF`: The result is rounded towards +infinity.
- `GMP_ROUND_MINUSINF`: The result is rounded towards -infinity.

This function can also be called as `gmp_div()`.

See also `gmp_div_r()`, `gmp_div_qr()`

gmp_div_qr (PHP 4 >= 4.0.4)

Divide numbers and get quotient and remainder

array **gmp_div_qr** (resource *n*, resource *d* [, int *round*]) \linebreak

The function divides *n* by *d* and returns array, with the first element being $\lfloor n/d \rfloor$ (the integer result of the division) and the second being $(n - \lfloor n/d \rfloor * d)$ (the remainder of the division).

See the `gmp_div_q()` function for description of the *round* argument.

Příklad 1. Division of GMP numbers

```
<?php
    $a = gmp_init ("0x41682179fbf5");
    $res = gmp_div_qr ($a, "0xDEFE75");
    printf("Result is: q - %s, r - %s",
           gmp_strval ($res[0]), gmp_strval ($res[1]));
?>
```

See also `gmp_div_q()`, `gmp_div_r()`.

gmp_div_r (PHP 4 >= 4.0.4)

Remainder of the division of numbers

resource **gmp_div_r** (resource *n*, resource *d* [, int *round*]) \linebreak

Calculates remainder of the integer division of *n* by *d*. The remainder has the sign of the *n* argument, if not zero.

See the `gmp_div_q()` function for description of the *round* argument.

See also `gmp_div_q()`, `gmp_div_qr()`

gmp_divexact (PHP 4 >= 4.0.4)

Exact division of numbers

resource **gmp_divexact** (resource *n*, resource *d*) \linebreak

Divides *n* by *d*, using fast "exact division" algorithm. This function produces correct results only when it is known in advance that *d* divides *n*.

gmp_fact (PHP 4 >= 4.0.4)

Factorial

resource **gmp_fact** (int *a*) \linebreak

Calculates factorial (*a*!) of *a*.

gmp_gcd (PHP 4 >= 4.0.4)

Calculate GCD

resource **gmp_gcd** (resource *a*, resource *b*) \linebreak

Calculate greatest common divisor of *a* and *b*. The result is always positive even if either of, or both, input operands are negative.

gmp_gcdext (PHP 4 >= 4.0.4)

Calculate GCD and multipliers

array **gmp_gcdext** (resource *a*, resource *b*) \linebreak

Calculates *g*, *s*, and *t*, such that $a*s + b*t = g = \text{gcd}(a, b)$, where *gcd* is the greatest common divisor. Returns an array with respective elements *g*, *s* and *t*.

gmp_hamdist (PHP 4 >= 4.0.4)

Hamming distance

int **gmp_hamdist** (resource *a*, resource *b*) \linebreak

Returns the hamming distance between *a* and *b*. Both operands should be non-negative.

gmp_init (PHP 4 >= 4.0.4)

Create GMP number

resource **gmp_init** (mixed *number*) \linebreak

Creates a GMP number from an integer or string. String representation can be decimal or hexadecimal. In the latter case, the string should start with 0x.

Příklad 1. Creating GMP number

```
<?php
    $a = gmp_init (123456);
    $b = gmp_init ("0xFFFFDEBACDFEDF7200");
?>
```

Poznámka: It is not necessary to call this function if you want to use integer or string in place of GMP number in GMP functions, like `gmp_add()`. Function arguments are automatically converted to GMP numbers, if such conversion is possible and needed, using the same rules as `gmp_init()`.

gmp_intval (PHP 4 >= 4.0.4)

Convert GMP number to integer

int **gmp_intval** (resource gmpnumber) \linebreak

This function allows to convert GMP number to integer.

Varování

This function returns a useful result only if the number actually fits the PHP integer (i.e., signed long type). If you want just to print the GMP number, use `gmp_strval()`.

gmp_invert (PHP 4 >= 4.0.4)

Inverse by modulo

resource **gmp_invert** (resource a, resource b) \linebreak

Computes the inverse of *a* modulo *b*. Returns `FALSE` if an inverse does not exist.

gmp_jacobi (PHP 4 >= 4.0.4)

Jacobi symbol

int **gmp_jacobi** (resource a, resource p) \linebreak

Computes Jacobi symbol (<http://www.utm.edu/research/primes/glossary/JacobiSymbol.html>) of *a* and *p*. *p* should be odd and must be positive.

gmp_legendre (PHP 4 >= 4.0.4)

Legendre symbol

int **gmp_legendre** (resource a, resource p) \linebreak

Compute the Legendre symbol
(<http://www.utm.edu/research/primes/glossary/LegendreSymbol.html>) of a and p . p should be odd and must be positive.

gmp_mod (PHP 4 >= 4.0.4)

Modulo operation

resource **gmp_mod** (resource n , resource d) \linebreak

Calculates n modulo d . The result is always non-negative, the sign of d is ignored.

gmp_mul (PHP 4 >= 4.0.4)

Multiply numbers

resource **gmp_mul** (resource a , resource b) \linebreak

Multiplies a by b and returns the result.

gmp_neg (PHP 4 >= 4.0.4)

Negate number

resource **gmp_neg** (resource a) \linebreak

Returns $-a$.

gmp_or (PHP 4 >= 4.0.4)

Logical OR

resource **gmp_or** (resource a , resource b) \linebreak

Calculates logical inclusive OR of two GMP numbers.

gmp_perfect_square (PHP 4 >= 4.0.4)

Perfect square check

bool **gmp_perfect_square** (resource a) \linebreak

Returns `TRUE` if a is a perfect square, `FALSE` otherwise.

See also: `gmp_sqrt()`, `gmp_sqrtrem()`.

gmp_popcount (PHP 4 >= 4.0.4)

Population count

```
int gmp_popcount ( resource a) \linebreak
```

Return the population count of *a*.

gmp_pow (PHP 4 >= 4.0.4)

Raise number into power

```
resource gmp_pow ( resource base, int exp) \linebreak
```

Raise *base* into power *exp*. The case of 0^0 yields 1. *exp* cannot be negative.

gmp_powm (PHP 4 >= 4.0.4)

Raise number into power with modulo

```
resource gmp_powm ( resource base, resource exp, resource mod) \linebreak
```

Calculate (*base* raised into power *exp*) modulo *mod*. If *exp* is negative, result is undefined.

gmp_prob_prime (PHP 4 >= 4.0.4)

Check if number is "probably prime"

```
int gmp_prob_prime ( resource a [, int reps]) \linebreak
```

If this function returns 0, *a* is definitely not prime. If it returns 1, then *a* is "probably" prime. If it returns 2, then *a* is surely prime. Reasonable values of *reps* vary from 5 to 10 (default being 10); a higher value lowers the probability for a non-prime to pass as a "probable" prime.

The function uses Miller-Rabin's probabilistic test.

gmp_random (PHP 4 >= 4.0.4)

Random number

```
resource gmp_random ( int limiter) \linebreak
```

Generate a random number. The number will be between *limiter* and zero in value. If *limiter* is negative, negative numbers are generated.

gmp_scan0 (PHP 4 >= 4.0.4)

Scan for 0

```
int gmp_scan0 ( resource a, int start) \linebreak
```

Scans *a*, starting with bit *start*, towards more significant bits, until the first clear bit is found.
Returns the index of the found bit.

gmp_scan1 (PHP 4 >= 4.0.4)

Scan for 1

```
int gmp_scan1 ( resource a, int start) \linebreak
```

Scans *a*, starting with bit *start*, towards more significant bits, until the first set bit is found.
Returns the index of the found bit.

gmp_setbit (PHP 4 >= 4.0.4)

Set bit

```
resource gmp_setbit ( resource &a, int index [, bool set_clear]) \linebreak
```

Sets bit *index* in *a*. *set_clear* defines if the bit is set to 0 or 1. By default the bit is set to 1.

gmp_sign (PHP 4 >= 4.0.4)

Sign of number

```
int gmp_sign ( resource a) \linebreak
```

Return sign of *a* - 1 if *a* is positive and -1 if it's negative.

gmp_sqrt (PHP 4 >= 4.0.4)

Square root

```
resource gmp_sqrt ( resource a) \linebreak
```

Calculates square root of *a*.

gmp_sqrtrm (unknown)

Square root with remainder

array **gmp_sqrtrm** (resource *a*) \linebreak

Returns array where first element is the integer square root of *a* (see also `gmp_sqrt()`), and the second is the remainder (i.e., the difference between *a* and the first element squared).

gmp_strval (PHP 4 >= 4.0.4)

Convert GMP number to string

string **gmp_strval** (resource *gmpnumber* [, int *base*]) \linebreak

Convert GMP number to string representation in base *base*. The default base is 10. Allowed values for the base are from 2 to 36.

Příklad 1. Converting a GMP number to a string

```
<?php
    $a = gmp_init("0x41682179fbf5");
    printf ("Decimal: %s, 36-based: %s", gmp_strval($a), gmp_strval($a,36));
?>
```

gmp_sub (PHP 4 >= 4.0.4)

Subtract numbers

resource **gmp_sub** (resource *a*, resource *b*) \linebreak

Subtracts *b* from *a* and returns the result.

gmp_xor (PHP 4 >= 4.0.4)

Logical XOR

resource **gmp_xor** (resource *a*, resource *b*) \linebreak

Calculates logical exclusive OR (XOR) of two GMP numbers.

XXXVII. HTTP funkce

Tyto funkce vám umožňují manipulovat výstupem posílaným zpět browseru přímo na úrovni HTTP protokolu.

header (PHP 3, PHP 4 >= 4.0.0)

Poslat HTTP hlavičku

int header (string string) \linebreak

Funkce **header()** se používá na začátku HTML souboru k odeslání HTTP hlaviček. Více informací o HTTP hlavičkách viz Specifikace HTTP 1.1 (<http://www.w3.org/Protocols/rfc2616/rfc2616>).

Poznámka: Pamatujte, že funkce **header()** musí být volána dříve než se odešle jakýkoliv normální výstup, ať už normálními HTML tagy, nebo z PHP. Velmi obvyklou chybou je načítat kód pomocí `include()` nebo `auto_prepend` a mít v tomto kódu prázdné řádky, které způsobí odeslání výstupu před voláním funkce **header()**.

Existují dva zvláštní případy volání funkce **header()**. Prvním je hlavička "Location". Ta nejenže odešle hlavičku browseru, ale navíc i vrátí Apachi stavový kód REDIRECT. Z pohledu autora skriptu by to nemělo být důležité, ale je to důležité pro lidi, kteří rozumí vnitřnostem Apache.

```
header ("Location: http://www.php.net"); /* Přesměrujeme browser
                                         na web site PHP */
exit;                                /* Pojistíme si, že se další kód nevykoná po
                                     přesměrování. */
```

Druhým zvláštním případem jsou všechny hlavičky začínající řetězcem "HTTP/" (velikost písmen nehraje roli). Například, pokud direktiva `ErrorDocument 404` vašeho Apache ukazuje na PHP skript, nebylo by od věci, kdyby skutečně generoval 404. První věcí, kterou byste v tomto skriptu měli udělat tudíž bude:

```
header ("HTTP/1.0 404 Not Found");
```

PHP skripty často generují dynamické HTML, které nesmí být cachováno uživatelským browserem, ani žádnými proxynami mezi serverem a uživatelským browserem. Mnoho proxy a klientů se dá donutit k vypnutí cachování s pomocí

```
header ("Expires: Mon, 26 Jul 1997 05:00:00 GMT"); // datum v minulosti
header ("Last-Modified: " . gmdate("D, d M Y H:i:s") . " GMT");
                                                    // vždy upraven
header ("Cache-Control: no-cache, must-revalidate"); // HTTP/1.1
header ("Pragma: no-cache"); // HTTP/1.0
```

Viz také `headers_sent()`

headers_sent (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Vrátit TRUE, pokud byly odeslány hlavičky

boolean **headers_sent** (void) \linebreak

Tato funkce vrátí TRUE, pokud už byly HTTP hlavičky odeslány, jinak FALSE.

Viz také header()

setcookie (PHP 3, PHP 4 >= 4.0.0)

Poslat cookie

int **setcookie** (string name [, string value [, int expire [, string path [, string domain [, int secure]]]]) \linebreak

setcookie() definuje cookie, který se pošle spolu s hlavičkami. Cookies se musí odeslat jako *první* ze všech HTTP hlaviček (to je omezení cookies, ne PHP). Volání této funkce musíte tudíž umístit před <html> či <head> tagy.

Všechny argumenty kromě argumentu *name* jsou nepovinné. Pokud je přítomný pouze argument *name*, u klienta se smaže cookie tohoto jména. Kterýkoliv argument můžete také nahradit prázdným řetězcem (""), čímž tento argument přeskočíte. Argumenty *expire* a *secure* jsou celočíselné a nedají se přeskočit prázdným řetězcem. Místo toho použijte nulu (0). Argument *expire* je běžné Unixové celočíselné vyjádření času, jak je vrací funkce time() či mktime(). Argument *secure* indikuje, že by se tento cookie měl přenášet pouze po zabezpečeném HTTPS spojení.

Běžné zádrhele:

- Cookies jsou přístupné až při dalším načtení stránky, na které přístupné být mají.
- Cookies se musí mazat se stejnými parametry, se kterými byly odeslány.

V PHP 3 se vícenásobná volání **setcookie()** v jednom skriptu provedou v opačném pořadí. Pokud se pokoušíte smazat jeden cookie pře odesláním jiného, měli byste umístit vložení před smazání. V PHP 4 se vícenásobná volání **setcookie()** provedou v tom pořadí, jak jsou volána.

Několik příkladů, jak posílat cookies:

Příklad 1. Ukázky odeslání cookies pomocí setcookie()

```
setcookie ("TestCookie", "Zkušební hodnota");
setcookie ("TestCookie", $value,time()+3600); /* vyprší za hodinu */
setcookie ("TestCookie", $value,time()+3600, "~/rasmus/", ".utoronto.ca", 1);
```

Následují příklady mazání cookies z předchozí ukázky:

Příklad 2. Ukázky mazání cookies pomocí setcookie()

```
setcookie ("TestCookie");
// nastaví dobu vypršení na čas před hodinou
setcookie ("TestCookie", "", time() - 3600);
setcookie ("TestCookie", "", time() - 3600, "~/rasmus/", ".utoronto.ca", 1);
```

Při mazání cookie byste se měli ujistit, že je doba vypršení v minulosti, čímž se v browseru zapne mechanismus odstranění cookie.

Všimněte si, že hodnotová část cookie se při odeslání cookie automaticky url-zakóduje, a při přijetí se automaticky dekoduje a přiřadí proměnné stejného jména, jako je jméno cookie. Pokud chcete vidět obsah našeho zkušebního cookie, použijte některý z následujících příkladů:

```
echo $TestCookie;
echo $HTTP_COOKIE_VARS["TestCookie"];
```

Cookies obsahující pole můžete také odeslat tak, že za název cookie napíšete hranaté závorky. Účinkem tohoto je odeslání tolika cookies, kolik má vaše pole prvků, ale když váš skript tyto cookies přijme, hodnoty se umístí v poli stejného jména, jako jsou vaše cookies:

```
setcookie ("cookie[three]", "cookieethree");
setcookie ("cookie[two]", "cookietwo");
setcookie ("cookie[one]", "cookieone");
if (isset ($cookie)) {
    while (list ($name, $value) = each ($cookie)) {
        echo "$name == $value<br>\n";
    }
}
```

Více informací o cookies viz specifikace cookies na http://www.netscape.com/newsref/std/cookie_spec.html.

Microsoft Internet Explorer 4 se Service Packem 1 zpracovává chybně cookies, které mají nastavený argument *path*.

Netscape Communicator 4.05 a Microsoft Internet Explorer 3.x zřejmě nezpracují cookies správně, pokud nejsou nastaveny argumenty *path* a *time*.

XXXVIII. Hyperwave functions

Introduction

Hyperwave has been developed at IICM (<http://www.iicm.edu/>) in Graz. It started with the name Hyper-G and changed to Hyperwave when it was commercialised (If I remember properly it was in 1996).

Hyperwave is not free software. The current version, 4.1, is available at www.hyperwave.com (<http://www.hyperwave.com/>). A time limited version can be ordered for free (30 days).

Hyperwave is an information system similar to a database (HIS, Hyperwave Information Server). Its focus is the storage and management of documents. A document can be any possible piece of data that may as well be stored in file. Each document is accompanied by its object record. The object record contains meta data for the document. The meta data is a list of attributes which can be extended by the user. Certain attributes are always set by the Hyperwave server, other may be modified by the user. An attribute is a name/value pair of the form name=value. The complete object record contains as many of those pairs as the user likes. The name of an attribute does not have to be unique, e.g. a title may appear several times within an object record. This makes sense if you want to specify a title in several languages. In such a case there is a convention, that each title value is preceded by the two letter language abbreviation followed by a colon, e.g. 'en:Title in English' or 'ge:Titel in deutsch'. Other attributes like a description or keywords are potential candidates. You may also replace the language abbreviation by any other string as long as it is separated by colon from the rest of the attribute value.

Each object record has native a string representation with each name/value pair separated by a newline. The Hyperwave extension also knows a second representation which is an associated array with the attribute name being the key. Multilingual attribute values itself form another associated array with the key being the language abbreviation. Actually any multiple attribute forms an associated array with the string left to the colon in the attribute value being the key. (This is not fully implemented. Only the attributes Title, Description and Keyword are treated properly yet.)

Besides the documents, all hyper links contained in a document are stored as object records as well. Hyper links which are in a document will be removed from it and stored as individual objects, when the document is inserted into the database. The object record of the link contains information about where it starts and where it ends. In order to gain the original document you will have to retrieve the plain document without the links and the list of links and reinsert them (The functions `hw_pipedocument()` and `hw_gettext()` do this for you. The advantage of separating links from the document is obvious. Once a document to which a link is pointing to changes its name, the link can easily be modified accordingly. The document containing the link is not affected at all. You may even add a link to a document without modifying the document itself.

Saying that `hw_pipedocument()` and `hw_gettext()` do the link insertion automatically is not as simple as it sounds. Inserting links implies a certain hierarchy of the documents. On a web server this is given by the file system, but Hyperwave has its own hierarchy and names do not reflect the position of an object in that hierarchy. Therefore creation of links first of all requires a mapping from the Hyperwave hierarchy and namespace into a web hierarchy respective web namespace. The fundamental difference between Hyperwave and the web is the clear distinction between names and hierarchy in Hyperwave. The name does not contain any information about the objects position in the hierarchy. In the web the name also contains the information on where the object is located in the hierarchy. This leads to two possible ways of mapping. Either the Hyperwave hierarchy and name of the Hyperwave object is reflected in the URL or the name only. To make things simple the second approach is used. Hyperwave object with name 'my_object' is mapped to 'http://host/my_object'

disregarding where it resides in the Hyperwave hierarchy. An object with name 'parent/my_object' could be the child of 'my_object' in the Hyperwave hierarchy, though in a web namespace it appears to be just the opposite and the user might get confused. This can only be prevented by selecting reasonable object names.

Having made this decision a second problem arises. How do you involve PHP? The URL `http://host/my_object` will not call any PHP script unless you tell your web server to rewrite it to e.g. `'http://host/php3_script/my_object'` and the script 'php3_script' evaluates the `$PATH_INFO` variable and retrieves the object with name 'my_object' from the Hyperwave server. There is just one little drawback which can be fixed easily. Rewriting any URL would not allow any access to other document on the web server. A PHP script for searching in the Hyperwave server would be impossible. Therefore you will need at least a second rewriting rule to exclude certain URLs like all e.g. starting with `http://host/Hyperwave`. This is basically sharing of a namespace by the web and Hyperwave server.

Based on the above mechanism links are insert into documents.

It gets more complicated if PHP is not run as a server module or CGI script but as a standalone application e.g. to dump the content of the Hyperwave server on a CD-ROM. In such a case it makes sense to retain the Hyperwave hierarchy and map in onto the file system. This conflicts with the object names if they reflect its own hierarchy (e.g. by choosing names including '/'). Therefore '/' has to be replaced by another character, e.g. '_' to be continued.

The network protocol to communicate with the Hyperwave server is called HG-CSP (`http://www.hyperwave.com/7.17-hg-prot`) (Hyper-G Client/Server Protocol). It is based on messages to initiate certain actions, e.g. get object record. In early versions of the Hyperwave Server two native clients (Harmony, Amadeus) were provided for communication with the server. Those two disappeared when Hyperwave was commercialised. As a replacement a so called wavemaster was provided. The wavemaster is like a protocol converter from HTTP to HG-CSP. The idea is to do all the administration of the database and visualisation of documents by a web interface. The wavemaster implements a set of placeholders for certain actions to customise the interface. This set of placeholders is called the PLACE Language. PLACE lacks a lot of features of a real programming language and any extension to it only enlarges the list of placeholders. This has led to the use of JavaScript which IMO does not make life easier.

Adding Hyperwave support to PHP should fill in the gap of a missing programming language for interface customisation. It implements all the messages as defined by the HG-CSP but also provides more powerful commands to e.g. retrieve complete documents.

Hyperwave has its own terminology to name certain pieces of information. This has widely been taken over and extended. Almost all functions operate on one of the following data types.

- object ID: An unique integer value for each object in the Hyperwave server. It is also one of the attributes of the object record (ObjectID). Object ids are often used as an input parameter to specify an object.
- object record: A string with attribute-value pairs of the form `attribute=value`. The pairs are separated by a carriage return from each other. An object record can easily be converted into an object array with `hw_object2array()`. Several functions return object records. The names of those functions end with `obj`.
- object array: An associated array with all attributes of an object. The key is the attribute name. If an attribute occurs more than once in an object record it will result in another indexed or associated array. Attributes which are language depended (like the title, keyword, description) will form an associated array with the key set to the language abbreviation. All other multiple

attributes will form an indexed array. PHP functions never return object arrays.

- `hw_document`: This is a complete new data type which holds the actual document, e.g. HTML, PDF etc. It is somewhat optimised for HTML documents but may be used for any format.

Several functions which return an array of object records do also return an associated array with statistical information about them. The array is the last element of the object record array. The statistical array contains the following entries:

Hidden

Number of object records with attribute `PresentationHints` set to `Hidden`.

CollectionHead

Number of object records with attribute `PresentationHints` set to `CollectionHead`.

FullCollectionHead

Number of object records with attribute `PresentationHints` set to `FullCollectionHead`.

CollectionHeadNr

Index in array of object records with attribute `PresentationHints` set to `CollectionHead`.

FullCollectionHeadNr

Index in array of object records with attribute `PresentationHints` set to `FullCollectionHead`.

Total

Total: Number of object records.

Integration with Apache

The Hyperwave extension is best used when PHP is compiled as an Apache module. In such a case the underlying Hyperwave server can be hidden from users almost completely if Apache uses its rewriting engine. The following instructions will explain this.

Since PHP with Hyperwave support built into Apache is intended to replace the native Hyperwave solution based on Wavemaster I will assume that the Apache server will only serve as a Hyperwave web interface. This is not necessary but it simplifies the configuration. The concept is quite simple. First of all you need a PHP script which evaluates the `PATH_INFO` variable and treats its value as the name of a Hyperwave object. Let's call this script '`Hyperwave`'. The URL `http://your.hostname/Hyperwave/name_of_object` would then return the Hyperwave object with the name '`name_of_object`'. Depending on the type of the object the script has to react accordingly. If it is a collection, it will probably return a list of children. If it is a document it will return the mime type and the content. A slight improvement can be achieved if the Apache rewriting engine is used. From the users point of view it would be more straight forward if the URL `http://your.hostname/name_of_object` would return the object. The rewriting rule is quite easy:

```
RewriteRule ^/(.*) /usr/local/apache/htdocs/HyperWave/$1 [L]
```

Now every URL relates to an object in the Hyperwave server. This causes a simple to solve problem. There is no way to execute a different script, e.g. for searching, than the 'Hyperwave' script. This can be fixed with another rewriting rule like the following:

```
RewriteRule ^/hw/(.*) /usr/local/apache/htdocs/hw/$1 [L]
```

This will reserve the directory `/usr/local/apache/htdocs/hw` for additional scripts and other files. Just make sure this rule is evaluated before the one above. There is just a little drawback: all Hyperwave objects whose name starts with 'hw/' will be shadowed. So, make sure you don't use such names. If you need more directories, e.g. for images just add more rules or place them all in one directory. Finally, don't forget to turn on the rewriting engine with

```
RewriteEngine on
```

My experiences have shown that you will need the following scripts:

- to return the object itself
- to allow searching
- to identify yourself
- to set your profile
- one for each additional function like to show the object attributes, to show information about users, to show the status of the server, etc.

Todo

There are still some things todo:

- The `hw_InsertDocument` has to be split into `hw_insertobject()` and **`hw_putdocument()`**.
- The names of several functions are not fixed, yet.
- Most functions require the current connection as its first parameter. This leads to a lot of typing, which is quite often not necessary if there is just one open connection. A default connection will improve this.
- Conversion from object record into object array needs to handle any multiple attribute.

hw_Array2Objrec (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

convert attributes from object array to object record

string **hw_array2objrec** (array object_array) \linebreak

Converts an *object_array* into an object record. Multiple attributes like 'Title' in different languages are treated properly.

See also hw_objrec2array().

hw_changeobject (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Changes attributes of an object (obsolete)

void **hw_changeobject** (int link, int objid, array attributes) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

hw_Children (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object ids of children

array **hw_children** (int connection, int objectID) \linebreak

Returns an array of object ids. Each id belongs to a child of the collection with ID *objectID*. The array contains all children both documents and collections.

hw_ChildrenObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object records of children

array **hw_childrenobj** (int connection, int objectID) \linebreak

Returns an array of object records. Each object record belongs to a child of the collection with ID *objectID*. The array contains all children both documents and collections.

hw_Close (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

closes the Hyperwave connection

int **hw_close** (int connection) \linebreak

Returns `FALSE` if connection is not a valid connection index, otherwise `TRUE`. Closes down the connection to a Hyperwave server with the given connection index.

hw_Connect (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

opens a connection

int **hw_connect** (string host, int port, string username, string password) \linebreak

Opens a connection to a Hyperwave server and returns a connection index on success, or `FALSE` if the connection could not be made. Each of the arguments should be a quoted string, except for the port number. The *username* and *password* arguments are optional and can be left out. In such a case no identification with the server will be done. It is similar to identify as user anonymous. This function returns a connection index that is needed by other Hyperwave functions. You can have multiple connections open at once. Keep in mind, that the password is not encrypted.

See also `hw_pconnect()`.

hw_connection_info (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Prints information about the connection to Hyperwave server

void **hw_connection_info** (int link) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

hw_Cp (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

copies objects

int **hw_cp** (int connection, array object_id_array, int destination id) \linebreak

Copies the objects with object ids as specified in the second parameter to the collection with the id *destination id*.

The value return is the number of copied objects.

See also `hw_mv()`.

hw_Deleteobject (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

deletes object

int **hw_deleteobject** (int connection, int object_to_delete) \linebreak

Deletes the object with the given object id in the second parameter. It will delete all instances of the object.

Returns `TRUE` if no error occurs otherwise `FALSE`.

See also `hw_mv()`.

hw_DocByAnchor (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object id object belonging to anchor

int **hw_docbyanchor** (int connection, int anchorID) \linebreak

Returns an th object id of the document to which *anchorID* belongs.

hw_DocByAnchorObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object record object belonging to anchor

string **hw_docbyanchorobj** (int connection, int anchorID) \linebreak

Returns an th object record of the document to which *anchorID* belongs.

hw_Document_Attributes (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object record of hw_document

string **hw_document_attributes** (int hw_document) \linebreak

Returns the object record of the document.

For backward compatibility, **hw_documentattributes()** is also accepted. This is deprecated, however.

See also `hw_document_bodytag()`, and `hw_document_size()`.

hw_Document_BodyTag (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

body tag of hw_document

string **hw_document_bodytag** (int hw_document) \linebreak

Returns the BODY tag of the document. If the document is an HTML document the BODY tag should be printed before the document.

See also `hw_document_attributes()`, and `hw_document_size()`.

For backward compatibility, `hw_documentbodytag()` is also accepted. This is deprecated, however.

hw_Document_Content (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

returns content of `hw_document`

string **hw_document_content** (int `hw_document`) \linebreak

Returns the content of the document. If the document is an HTML document the content is everything after the BODY tag. Information from the HEAD and BODY tag is in the stored in the object record.

See also `hw_document_attributes()`, `hw_document_size()`, and `hw_document_setcontent()`.

hw_Document_SetContent (PHP 4 >= 4.0.0)

sets/replaces content of `hw_document`

string **hw_document_setcontent** (int `hw_document`, string `content`) \linebreak

Sets or replaces the content of the document. If the document is an HTML document the content is everything after the BODY tag. Information from the HEAD and BODY tag is in the stored in the object record. If you provide this information in the content of the document too, the Hyperwave server will change the object record accordingly when the document is inserted. Probably not a very good idea. If this functions fails the document will retain its old content.

See also `hw_document_attributes()`, `hw_document_size()`, and `hw_document_content()`.

hw_Document_Size (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

size of `hw_document`

int **hw_document_size** (int `hw_document`) \linebreak

Returns the size in bytes of the document.

See also `hw_document_bodytag()`, and `hw_document_attributes()`.

For backward compatibility, `hw_documentsize()` is also accepted. This is deprecated, however.

hw_dummy (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Hyperwave dummy function

string **hw_dummy** (int link, int id, int msgid) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

hw_EditText (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

retrieve text document

int **hw_edittest** (int connection, int hw_document) \linebreak

Uploads the text document to the server. The object record of the document may not be modified while the document is edited. This function will only works for pure text documents. It will not open a special data connection and therefore blocks the control connection during the transfer.

See also hw_pipedocument(), hw_free_document(), hw_document_bodytag(), hw_document_size(), hw_output_document(), hw_gettext().

hw_Error (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

error number

int **hw_error** (int connection) \linebreak

Returns the last error number. If the return value is 0 no error has occurred. The error relates to the last command.

hw_ErrorMsg (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

returns error message

string **hw_errormsg** (int connection) \linebreak

Returns a string containing the last error message or 'No Error'. If FALSE is returned, this function failed. The message relates to the last command.

hw_Free_Document (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

frees hw_document

int **hw_free_document** (int hw_document) \linebreak

Frees the memory occupied by the Hyperwave document.

hw_GetAnchors (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object ids of anchors of document

array **hw_getanchors** (int connection, int objectID) \linebreak

Returns an array of object ids with anchors of the document with object ID *objectID*.

hw_GetAnchorsObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object records of anchors of document

array **hw_getanchorsobj** (int connection, int objectID) \linebreak

Returns an array of object records with anchors of the document with object ID *objectID*.

hw_GetAndLock (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

return bject record and lock object

string **hw_getandlock** (int connection, int objectID) \linebreak

Returns the object record for the object with ID *objectID*. It will also lock the object, so other users cannot access it until it is unlocked.

See also `hw_unlock()`, and `hw_getobject()`.

hw_GetChildColl (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object ids of child collections

array **hw_getchildcoll** (int connection, int objectID) \linebreak

Returns an array of object ids. Each object ID belongs to a child collection of the collection with ID *objectID*. The function will not return child documents.

See also `hw_children()`, and `hw_getchilddoccoll()`.

hw_GetChildCollObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object records of child collections

array **hw_getchildcollobj** (int connection, int objectID) \linebreak

Returns an array of object records. Each object records belongs to a child collection of the collection with ID *objectID*. The function will not return child documents.

See also `hw_childrenobj()`, and `hw_getchilddoccollobj()`.

hw_GetChildDocColl (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object ids of child documents of collection

array **hw_getchilddoccoll** (int connection, int objectID) \linebreak

Returns array of object ids for child documents of a collection.

See also `hw_children()`, and `hw_getchildcoll()`.

hw_GetChildDocCollObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object records of child documents of collection

array **hw_getchilddoccollobj** (int connection, int objectID) \linebreak

Returns an array of object records for child documents of a collection.

See also `hw_childrenobj()`, and `hw_getchildcollobj()`.

hw_GetObject (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object record

array **hw_getobject** (int connection, [int|array] objectID, string query) \linebreak

Returns the object record for the object with ID *objectID* if the second parameter is an integer. If the second parameter is an array of integer the function will return an array of object records. In such a case the last parameter is also evaluated which is a query string.

The query string has the following syntax:

<expr> ::= "(" <expr> ")" |

"!<expr> | /* NOT */

<expr> "|" <expr> | /* OR */

<expr> "&&" <expr> | /* AND */

<attribute> <operator> <value>

<attribute> ::= /* any attribute name (Title, Author, DocumentType ...) */

<operator> ::= "=" | /* equal */

"<" | /* less than (string compare) */

">" | /* greater than (string compare) */

"~" /* regular expression matching */

The query allows to further select certain objects from the list of given objects. Unlike the other query functions, this query may use not indexed attributes. How many object records are returned depends on the query and if access to the object is allowed.

See also `hw_getandlock()`, and `hw_getobjectbyquery()`.

hw_GetObjectByQuery (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

search object

array **hw_getobjectbyquery** (int connection, string query, int max_hits) \linebreak

Searches for objects on the whole server and returns an array of object ids. The maximum number of matches is limited to *max_hits*. If *max_hits* is set to -1 the maximum number of matches is unlimited.

The query will only work with indexed attributes.

See also `hw_getobjectbyqueryobj()`.

hw_GetObjectByQueryColl (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

search object in collection

array **hw_getobjectbyquerycoll** (int connection, int objectID, string query, int max_hits) \linebreak

Searches for objects in collection with ID *objectID* and returns an array of object ids. The maximum number of matches is limited to *max_hits*. If *max_hits* is set to -1 the maximum number of matches is unlimited.

The query will only work with indexed attributes.

See also `hw_getobjectbyquerycollobj()`.

hw_GetObjectByQueryCollObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

search object in collection

array **hw_getobjectbyquerycollobj** (int connection, int objectID, string query, int max_hits) \linebreak

Searches for objects in collection with ID *objectID* and returns an array of object records. The maximum number of matches is limited to *max_hits*. If *max_hits* is set to -1 the maximum number of matches is unlimited.

The query will only work with indexed attributes.

See also `hw_getobjectbyquerycoll()`.

hw_GetObjectByQueryObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

search object

array **hw_getobjectbyqueryobj** (int connection, string query, int max_hits) \linebreak

Searches for objects on the whole server and returns an array of object records. The maximum number of matches is limited to *max_hits*. If *max_hits* is set to -1 the maximum number of matches is unlimited.

The query will only work with indexed attributes.

See also `hw_getobjectbyquery()`.

hw_GetParents (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object ids of parents

array **hw_getparents** (int connection, int objectID) \linebreak

Returns an indexed array of object ids. Each object id belongs to a parent of the object with ID *objectID*.

hw_GetParentsObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

object records of parents

array **hw_getparentsobj** (int connection, int objectID) \linebreak

Returns an indexed array of object records plus an associated array with statistical information about the object records. The associated array is the last entry of the returned array. Each object record belongs to a parent of the object with ID *objectID*.

hw_getrellink (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Get link from source to dest relative to rootid

string **hw_getrellink** (int link, int rootid, int sourceid, int destid) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

hw_GetRemote (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Gets a remote document

int **hw_getremote** (int connection, int objectID) \linebreak

Returns a remote document. Remote documents in Hyperwave notation are documents retrieved from an external source. Common remote documents are for example external web pages or queries in a database. In order to be able to access external sources through remote documents Hyperwave introduces the HGI (Hyperwave Gateway Interface) which is similar to the CGI. Currently, only ftp, http-servers and some databases can be accessed by the HGI. Calling **hw_getremote()** returns the document from the external source. If you want to use this function you should be very familiar with HGIs. You should also consider to use PHP instead of Hyperwave to access external sources. Adding database support by a Hyperwave gateway should be more difficult than doing it in PHP.

See also **hw_getremotechildren()**.

hw_GetRemoteChildren (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Gets children of remote document

int **hw_getremotechildren** (int connection, string object record) \linebreak

Returns the children of a remote document. Children of a remote document are remote documents itself. This makes sense if a database query has to be narrowed and is explained in Hyperwave Programmers' Guide. If the number of children is 1 the function will return the document itself formatted by the Hyperwave Gateway Interface (HGI). If the number of children is greater than 1 it will return an array of object record with each maybe the input value for another call to **hw_getremotechildren()**. Those object records are virtual and do not exist in the Hyperwave server, therefore they do not have a valid object ID. How exactly such an object record looks like is up to the HGI. If you want to use this function you should be very familiar with HGIs. You should also consider to use PHP instead of Hyperwave to access external sources. Adding database support by a Hyperwave gateway should be more difficult than doing it in PHP.

See also **hw_getremote()**.

hw_GetSrcByDestObj (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Returns anchors pointing at object

array **hw_getsrcbydestobj** (int connection, int objectID) \linebreak

Returns the object records of all anchors pointing to the object with ID *objectID*. The object can either be a document or an anchor of type destination.

See also **hw_getanchors()**.

hw_GetText (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

retrieve text document

int **hw_gettext** (int connection, int objectID [, mixed rootID/prefix]) \linebreak

Returns the document with object ID *objectID*. If the document has anchors which can be inserted, they will be inserted already. The optional parameter *rootID/prefix* can be a string or an integer. If it is an integer it determines how links are inserted into the document. The default is 0 and will result in links that are constructed from the name of the link's destination object. This is useful for web applications. If a link points to an object with name 'internet_movie' the HTML link will be . The actual location of the source and destination object in the document hierarchy is disregarded. You will have to set up your web browser, to rewrite that URL to for example '/my_script.php3/internet_movie'. 'my_script.php3' will have to evaluate \$PATH_INFO and retrieve the document. All links will have the prefix '/my_script.php3/'. If you do not want this you can set the optional parameter *rootID/prefix* to any prefix which is used instead. In this case it has to be a string.

If *rootID/prefix* is an integer and unequal to 0 the link is constructed from all the names starting at the object with the id *rootID/prefix* separated by a slash relative to the current object. If for example the above document 'internet_movie' is located at 'a-b-c-internet_movie' with '-' being the separator between hierarchy levels on the Hyperwave server and the source document is located at 'a-b-d-source' the resulting HTML link would be: . This is useful if you want to download the whole server content onto disk and map the document hierarchy onto the file system.

This function will only work for pure text documents. It will not open a special data connection and therefore blocks the control connection during the transfer.

See also hw_pipedocument(), hw_free_document(), hw_document_bodytag(), hw_document_size(), and hw_output_document().

hw_getusername (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

name of currently logged in user

string **hw_getusername** (int connection) \linebreak

Returns the username of the connection.

hw_Identify (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

identifies as user

int **hw_identify** (string username, string password) \linebreak

Identifies as user with *username* and *password*. Identification is only valid for the current session. I do not think this function will be needed very often. In most cases it will be easier to identify with the opening of the connection.

See also hw_connect().

hw_InCollections (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

check if object ids in collections

array **hw_incollections** (int connection, array object_id_array, array collection_id_array, int return_collections) \linebreak

Checks whether a set of objects (documents or collections) specified by the *object_id_array* is part of the collections listed in *collection_id_array*. When the fourth parameter *return_collections* is 0, the subset of object ids that is part of the collections (i.e., the documents or collections that are children of one or more collections of collection ids or their subcollections, recursively) is returned as an array. When the fourth parameter is 1, however, the set of collections that have one or more objects of this subset as children are returned as an array. This option allows a client to, e.g., highlight the part of the collection hierarchy that contains the matches of a previous query, in a graphical overview.

hw_Info (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

info about connection

string **hw_info** (int connection) \linebreak

Returns information about the current connection. The returned string has the following format:
<Serverstring>, <Host>, <Port>, <Username>, <Port of Client>, <Byte swapping>

hw_InsColl (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

insert collection

int **hw_inscoll** (int connection, int objectID, array object_array) \linebreak

Inserts a new collection with attributes as in *object_array* into collection with object ID *objectID*.

hw_InsDoc (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

insert document

int **hw_insdoc** (int connection, int parentID, string object_record, string text) \linebreak

Inserts a new document with attributes as in *object_record* into collection with object ID *parentID*. This function inserts either an object record only or an object record and a pure ascii text in *text* if *text* is given. If you want to insert a general document of any kind use *hw_insertdocument()* instead.

See also *hw_insertdocument()*, and *hw_inscoll()*.

hw_insertanchors (PHP 4 >= 4.0.4)

Inserts only anchors into text

string **hw_insertanchors** (int hwdoc, array chorecs, array dest [, array urlprefixes]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

hw_InsertDocument (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

upload any document

int **hw_insertdocument** (int connection, int parent_id, int hw_document) \linebreak

Uploads a document into the collection with *parent_id*. The document has to be created before with *hw_new_document()*. Make sure that the object record of the new document contains at least the attributes: Type, DocumentType, Title and Name. Possibly you also want to set the MimeType. The functions returns the object id of the new document or *FALSE*.

See also *hw_pipedocument()*.

hw_InsertObject (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

inserts an object record

int **hw_insertobject** (int connection, string object rec, string parameter) \linebreak

Inserts an object into the server. The object can be any valid hyperwave object. See the HG-CSP documentation for a detailed information on how the parameters have to be.

Note: If you want to insert an Anchor, the attribute Position has always been set either to a start/end value or to 'invisible'. Invisible positions are needed if the annotation has no correspondig link in the annotation text.

See also *hw_pipedocument()*, *hw_insertdocument()*, *hw_insdoc()*, and *hw_inscoll()*.

hw_mapid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Maps global id on virtual local id

int **hw_mapid** (int connection, int server id, int object id) \linebreak

Maps a global object id on any hyperwave server, even those you did not connect to with `hw_connect()`, onto a virtual object id. This virtual object id can then be used as any other object id, e.g. to obtain the object record with `hw_getobject()`. The server id is the first part of the global object id (GOid) of the object which is actually the IP number as an integer.

Note: In order to use this function you will have to set the `F_DISTRIBUTED` flag, which can currently only be set at compile time in `hg_comm.c`. It is not set by default. Read the comment at the beginning of `hg_comm.c`

hw_Modifyobject (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

modifies object record

`int hw_modifyobject (int connection, int object_to_change, array remove, array add, int mode) \linebreak`

This command allows to remove, add, or modify individual attributes of an object record. The object is specified by the Object ID *object_to_change*. The first array *remove* is a list of attributes to remove. The second array *add* is a list of attributes to add. In order to modify an attribute one will have to remove the old one and add a new one. **hw_modifyobject()** will always remove the attributes before it adds attributes unless the value of the attribute to remove is not a string or array.

The last parameter determines if the modification is performed recursively. 1 means recursive modification. If some of the objects cannot be modified they will be skipped without notice. `hw_error()` may not indicate an error though some of the objects could not be modified.

The keys of both arrays are the attributes name. The value of each array element can either be an array, a string or anything else. If it is an array each attribute value is constructed by the key of each element plus a colon and the value of each element. If it is a string it is taken as the attribute value. An empty string will result in a complete removal of that attribute. If the value is neither a string nor an array but something else, e.g. an integer, no operation at all will be performed on the attribute. This is necessary if you want to add a completely new attribute not just a new value for an existing attribute. If the remove array contained an empty string for that attribute, the attribute would be tried to be removed which would fail since it doesn't exist. The following addition of a new value for that attribute would also fail. Setting the value for that attribute to e.g. 0 would not even try to remove it and the addition will work.

If you would like to change the attribute 'Name' with the current value 'books' into 'articles' you will have to create two arrays and call **hw_modifyobject()**.

Příklad 1. modifying an attribute

```
// $connect is an existing connection to the Hyperwave server
// $objid is the ID of the object to modify
$remarr = array("Name" => "books");
$addarr = array("Name" => "articles");
$hw_modifyobject($connect, $objid, $remarr, $addarr);
```

In order to delete/add a name=value pair from/to the object record just pass the remove/add array and set the last/third parameter to an empty array. If the attribute is the first one with that name to add, set attribute value in the remove array to an integer.

Příklad 2. adding a completely new attribute

```
// $connect is an existing connection to the Hyperwave server
// $objid is the ID of the object to modify
$remarr = array("Name" => 0);
$addarr = array("Name" => "articles");
$hw_modifyobject($connect, $objid, $remarr, $addarr);
```

Poznámka: Multilingual attributes, e.g. 'Title', can be modified in two ways. Either by providing the attributes value in its native form 'language':'title' or by providing an array with elements for each language as described above. The above example would then be:

Příklad 3. modifying Title attribute

```
$remarr = array("Title" => "en:Books");
$addarr = array("Title" => "en:Articles");
$hw_modifyobject($connect, $objid, $remarr, $addarr);
```

or

Příklad 4. modifying Title attribute

```
$remarr = array("Title" => array("en" => "Books"));
$addarr = array("Title" => array("en" => "Articles", "ge"=>"Artikel"));
$hw_modifyobject($connect, $objid, $remarr, $addarr);
```

This removes the english title 'Books' and adds the english title 'Articles' and the german title 'Artikel'.

Příklad 5. removing attribute

```
$remarr = array("Title" => "");
$addarr = array("Title" => "en:Articles");
$hw_modifyobject($connect, $objid, $remarr, $addarr);
```

Poznámka: This will remove all attributes with the name 'Title' and adds a new 'Title' attribute. This comes in handy if you want to remove attributes recursively.

Poznámka: If you need to delete all attributes with a certain name you will have to pass an empty string as the attribute value.

Poznámka: Only the attributes 'Title', 'Description' and 'Keyword' will properly handle the language prefix. If those attributes don't carry a language prefix, the prefix 'xx' will be assigned.

Poznámka: The 'Name' attribute is somewhat special. In some cases it cannot be completely removed. You will get an error message 'Change of base attribute' (not clear when this happens). Therefore you will always have to add a new Name first and then remove the old one.

Poznámka: You may not surround this function by calls to `hw_getandlock()` and `hw_unlock()`. `hw_modifyobject()` does this internally.

Returns `TRUE` if no error occurs otherwise `FALSE`.

hw_Mv (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

moves objects

`int hw_mv (int connection, array object id array, int source id, int destination id) \linebreak`

Moves the objects with object ids as specified in the second parameter from the collection with id *source id* to the collection with the id *destination id*. If the destination id is 0 the objects will be unlinked from the source collection. If this is the last instance of that object it will be deleted. If you want to delete all instances at once, use `hw_deleteobject()`.

The value return is the number of moved objects.

See also `hw_cp()`, and `hw_deleteobject()`.

hw_New_Document (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

create new document

`int hw_new_document (string object_record, string document_data, int document_size) \linebreak`

Returns a new Hyperwave document with document data set to *document_data* and object record set to *object_record*. The length of the *document_data* has to be passed in *document_size*. This function does not insert the document into the Hyperwave server.

See also `hw_free_document()`, `hw_document_size()`, `hw_document_bodytag()`, `hw_output_document()`, and `hw_insertdocument()`.

hw_Objrec2Array (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

convert attributes from object record to object array

array **hw_objrec2array** (string object_record [, array format]) \linebreak

Converts an *object_record* into an object array. The keys of the resulting array are the attributes names. Multi-value attributes like 'Title' in different languages form its own array. The keys of this array are the left part to the colon of the attribute value. This left part must be two characters long. Other multi-value attributes without a prefix form an indexed array. If the optional parameter is missing the attributes 'Title', 'Description' and 'Keyword' are treated as language attributes and the attributes 'Group', 'Parent' and 'HtmlAttr' as non-prefixed multi-value attributes. By passing an array holding the type for each attribute you can alter this behaviour. The array is an associated array with the attribute name as its key and the value being one of HW_ATTR_LANG or HW_ATTR_NONE

See also hw_array2objrec().

hw_Output_Document (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

prints hw_document

int **hw_output_document** (int hw_document) \linebreak

Prints the document without the BODY tag.

For backward compatibility, **hw_outputdocument()** is also accepted. This is deprecated, however.

hw_pConnect (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

make a persistent database connection

int **hw_pconnect** (string host, int port, string username, string password) \linebreak

Returns a connection index on success, or FALSE if the connection could not be made. Opens a persistent connection to a Hyperwave server. Each of the arguments should be a quoted string, except for the port number. The *username* and *password* arguments are optional and can be left out. In such a case no identification with the server will be done. It is similar to identify as user anonymous. This function returns a connection index that is needed by other Hyperwave functions. You can have multiple persistent connections open at once.

See also hw_connect().

hw_PipeDocument (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

retrieve any document

int **hw_pipedocument** (int connection, int objectID) \linebreak

Returns the Hyperwave document with object ID *objectID*. If the document has anchors which can be inserted, they will have been inserted already. The document will be transferred via a special data connection which does not block the control connection.

See also `hw_gettext()` for more on link insertion, `hw_free_document()`, `hw_document_size()`, `hw_document_bodytag()`, and `hw_output_document()`.

hw_Root (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

root object id

int **hw_root** () \linebreak

Returns the object ID of the hyperroot collection. Currently this is always 0. The child collection of the hyperroot is the root collection of the connected server.

hw_setlinkroot (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Set the id to which links are calculated

void **hw_setlinkroot** (int link, int rootid) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

hw_stat (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Returns status string

string **hw_stat** (int link) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

hw_Unlock (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

unlock object

int **hw_unlock** (int connection, int objectID) \linebreak

Unlocks a document, so other users regain access.

See also hw_getandlock().

hw_Who (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

List of currently logged in users

int **hw_who** (int connection) \linebreak

Returns an array of users currently logged into the Hyperwave server. Each entry in this array is an array itself containing the elements id, name, system, onSinceDate, onSinceTime, TotalTime and self. 'self' is 1 if this entry belongs to the user who initiated the request.

XXXIX. Hyperwave API functions

Introduction

Hyperwave has been developed at IICM (<http://www.iicm.edu/>) in Graz. It started with the name Hyper-G and changed to Hyperwave when it was commercialised (If I remember properly it was in 1996).

Hyperwave is not free software. The current version, 5.5, is available at www.hyperwave.com (<http://www.hyperwave.com/>). A time limited version can be ordered for free (30 days).

Hyperwave is an information system similar to a database (HIS, Hyperwave Information Server). Its focus is the storage and management of documents. A document can be any possible piece of data that may as well be stored in file. Each document is accompanied by its object record. The object record contains meta data for the document. The meta data is a list of attributes which can be extended by the user. Certain attributes are always set by the Hyperwave server, other may be modified by the user.

Requirements

Since 2001 there is a Hyperwave SDK available. It supports Java, JavaScript and C++. This PHP Extension is based on the C++ interface. In order to activate the hwapi support in PHP you will have to install the Hyperwave SDK first and configure PHP with `--with-hwapi=<dir>`.

Classes

The API provided by the HW_API extension is fully object oriented. It is very similar to the C++ interface of the Hyperwave SDK. It consist of the following classes.

- HW_API
- HW_API_Object
- HW_API_Attribute
- HW_API_Error
- HW_API_Content
- HW_API_Reason

Some basic classes like HW_API_String, HW_API_String_Array, etc., which exist in the Hyperwave SDK have not been implemented since PHP has powerful replacements for them.

Each class has certain method, whose names are identical to its counterparts in the Hyperwave SDK. Passing arguments to this function differs from all the other PHP Extension but is close to the C++ API of the HW SDK. Instead of passing several parameters they are all put into an associated array and passed as one parameter. The names of the keys are identical to those documented in the HW

SDK. The common parameters are listed below. If other parameters are required they will be documented if needed.

- `objectIdentifier` The name or id of an object, e.g. "rootcollection", "0x873A87680x00000002".
- `parentIdentifier` The name or id of an object which is considered to be a parent.
- `object` An instance of class `HW_API_Object`.
- `parameters` An instance of class `HW_API_Object`.
- `version` The version of an object.
- `mode` An integer value determine the way an operation is executed.
- `attributeSelector` Any array of strings, each containing a name of an attribute. This is used if you retrieve the object record and want to include certain attributes.
- `objectQuery` A query to select certain object out of a list of objects. This is used to reduce the number of objects which was delivered by a function like `hw_api->children()` or `hw_api->find()`.

Integration with Apache

The integration with Apache and possible other servers is already described in the Hyperwave Modul which has been the first extension to connect a Hyperwave Server.

hw_api_attribute (unknown)

Creates instance of class hw_api_attribute

object **attribute** ([string name [, string value]]) \linebreak

Creates a new instance of hw_api_attribute with the given name and value.

hw_api_attribute->key (unknown)

Returns key of the attribute

string **key** (void) \linebreak

Returns the name of the attribute.

See also hwapi_attribute_value().

hw_api_attribute->langdepvalue (unknown)

Returns value for a given language

string **langdepvalue** (string language) \linebreak

Returns the value in the given language of the attribute.

See also hwapi_attribute_value().

hw_api_attribute->value (unknown)

Returns value of the attribute

string **value** (void) \linebreak

Returns the value of the attribute.

See also hwapi_attribute_key(), hwapi_attribute_values().

hw_api_attribute->values (unknown)

Returns all values of the attribute

array **values** (void) \linebreak

Returns all values of the attribute as an array of strings.

See also hwapi_attribute_value().

hw_api->checkin (unknown)

Checks in an object

object **checkin** (array parameter) \linebreak

This function checks in an object or a whole hierarchy of objects. The parameters array contains the required element 'objectIdentifier' and the optional element 'version', 'comment', 'mode' and 'objectQuery'. 'version' sets the version of the object. It consists of the major and minor version separated by a period. If the version is not set, the minor version is incremented. 'mode' can be one of the following values:

HW_API_CHECKIN_NORMAL

Checks in and commits the object. The object must be a document.

HW_API_CHECKIN_RECURSIVE

If the object to check in is a collection, all children will be checked in recursively if they are documents. Trying to check in a collection would result in an error.

HW_API_CHECKIN_FORCE_VERSION_CONTROL

Checks in an object even if it is not under version control.

HW_API_CHECKIN_REVERT_IF_NOT_CHANGED

Check if the new version is different from the last version. Unless this is the case the object will be checked in.

HW_API_CHECKIN_KEEP_TIME_MODIFIED

Keeps the time modified from the most recent object.

HW_API_CHECKIN_NO_AUTO_COMMIT

The object is not automatically committed on checkin.

See also hwapi_checkout().

hw_api->checkout (unknown)

Checks out an object

object **checkout** (array parameter) \linebreak

This function checks out an object or a whole hierarchy of objects. The parameters array contains the required element 'objectIdentifier' and the optional element 'version', 'mode' and 'objectQuery'. 'mode' can be one of the following values:

HW_API_CHECKIN_NORMAL

Checks out an object. The object must be a document.

HW_API_CHECKIN_RECURSIVE

If the object to check out is a collection, all children will be checked out recursively if they are documents. Trying to check out a collection would result in an error.

See also `hwapi_checkin()`.

hw_api->children (unknown)

Returns children of an object

array **children** (array parameter) \linebreak

Retrieves the children of a collection or the attributes of a document. The children can be further filtered by specifying an object query. The parameter array contains the required elements 'objectIdentifier' and the optional elements 'attributeSelector' and 'objectQuery'.

The return value is an array of objects of type `HW_API_Object` or `HW_API_Error`.

See also `hwapi_parents()`.

hw_api->content (unknown)

Returns content of an object

object **content** (array parameter) \linebreak

This function returns the content of a document as an object of type `hw_api_content`. The parameter array contains the required elements 'objectIdentifier' and the optional element 'mode'.

The mode can be one of the constants `HW_API_CONTENT_ALLLINKS`, `HW_API_CONTENT_REACHABLELINKS` or `HW_API_CONTENT_PLAIN`.

`HW_API_CONTENT_ALLLINKS` means to insert all anchors even if the destination is not reachable. `HW_API_CONTENT_REACHABLELINKS` tells **hw_api_content()** to insert only reachable links and `HW_API_CONTENT_PLAIN` will lead to document without any links.

hw_api_content->mimetype (unknown)

Returns mimetype

string **mimetype** (void) \linebreak

Returns the mimetype of the content.

hw_api_content->read (unknown)

Read content

string **read** (string buffer, integer len) \linebreak

Reads *len* bytes from the content into the given buffer.

hw_api->copy (unknown)

Copies physically

object **copy** (array parameter) \linebreak

This function will make a physical copy including the content if it exists and returns the new object or an error object. The parameter array contains the required elements 'objectIdentifier' and 'destinationParentIdentifier'. The optional parameter is 'attributeSelector'.

See also hwapi_move(), hwapi_link().

hw_api->dbstat (unknown)

Returns statistics about database server

object **dbstat** (array parameter) \linebreak

See also hwapi_dcstat(), hwapi_hwstat(), hwapi_ftstat().

hw_api->dcstat (unknown)

Returns statistics about document cache server

object **dcstat** (array parameter) \linebreak

See also hwapi_hwstat(), hwapi_dbstat(), hwapi_ftstat().

hw_api->dstanchors (unknown)

Returns a list of all destination anchors

object **dstanchors** (array parameter) \linebreak

Retrieves all destination anchors of an object. The parameter array contains the required element 'objectIdentifier' and the optional elements 'attributeSelector' and 'objectQuery'.

See also hwapi_srcanchors().

hw_api->dstofsrcanchors (unknown)

Returns destination of a source anchor

object **dstofsrcanchors** (array parameter) \linebreak

Retrieves the destination object pointed by the specified source anchors. The destination object can either be a destination anchor or a whole document. The parameters array contains the required element 'objectIdentifier' and the optional element 'attributeSelector'.

See also hwapi_srcanchors(), hwapi_dstanchors(), hwapi_objectbyanchor().

hw_api_error->count (unknown)

Returns number of reasons

int **count** (void) \linebreak

Returns the number of error reasons.

See also hwapi_error_reason().

hw_api_error->reason (unknown)

Returns reason of error

object **reason** (void) \linebreak

Returns the first error reason.

See also hwapi_error_count().

hw_api->find (unknown)

Search for objects

array **find** (array parameter) \linebreak

This functions searches for objects either by executing a key or/and full text query. The found objects can further be filtered by an optional object query. They are sorted by their importance. The second search operation is relatively slow and its result can be limited to a certain number of hits. This allows to perform an incremental search, each returning just a subset of all found documents, starting at a given index. The parameter array contains the 'keyquery' or/and 'fulltextquery' depending on who you would like to search. Optional parameters are 'objectquery', 'scope', 'lanugages' and 'attributeselector'. In case of an incremental search the optional parameters 'startIndex', 'numberOfObjectsToGet' and 'exactMatchUnit' can be passed.

hw_api->ftstat (unknown)

Returns statistics about fulltext server

object **ftstat** (array parameter) \linebreak

See also hwapi_dcstat(), hwapi_dbstat(), hwapi_hwstat().

hwapi_hgcsp (unknown)

Returns object of class hw_api

object **hwapi_hgcsp** (string hostname [, int port]) \linebreak

Opens a connection to the Hyperwave server on host *hostname*. The protocol used is HGCSP. If you do not pass a port number, 418 is used.

See also **hwapi_hwtp**().

hw_api->hwstat (unknown)

Returns statistics about Hyperwave server

object **hwstat** (array parameter) \linebreak

See also hwapi_dcstat(), hwapi_dbstat(), hwapi_ftstat().

hw_api->identify (unknown)

Log into Hyperwave Server

object **identify** (array parameter) \linebreak

Logs into the Hyperwave Server. The parameter array must contain the elements 'username' und 'password'.

The return value will be an object of type `HW_API_Error` if identification failed or `TRUE` if it was successful.

hw_api->info (unknown)

Returns information about server configuration

object **info** (array parameter) \linebreak

See also hwapi_dcstat(), hwapi_dbstat(), hwapi_ftstat(), hwapi_hwstat().

hw_api->insert (unknown)

Inserts a new object

object **insert** (array parameter) \linebreak

Insert a new object. The object type can be user, group, document or anchor. Depending on the type other object attributes has to be set. The parameter array contains the required elements 'object' and 'content' (if the object is a document) and the optional parameters 'parameters', 'mode' and 'attributeSelector'. The 'object' must contain all attributes of the object. 'parameters' is an object as well holding further attributes like the destination (attribute key is 'Parent'). 'content' is the content of the document. 'mode' can be a combination of the following flags:

HW_API_INSERT_NORMAL

The object is inserted into the server.

HW_API_INSERT_FORCE-VERSION-CONTROL

HW_API_INSERT_AUTOMATIC-CHECKOUT

HW_API_INSERT_PLAIN

HW_API_INSERT_KEEP_TIME_MODIFIED

HW_API_INSERT_DELAY_INDEXING

See also hwapi_replace().

hw_api->insertanchor (unknown)

Inserts a new object of type anchor

object **insertanchor** (array parameter) \linebreak

This function is a shortcut for hwapi_insert(). It inserts an object of type anchor and sets some of the attributes required for an anchor. The parameter array contains the required elements 'object' and 'documentIdentifier' and the optional elements 'destinationIdentifier', 'parameter', 'hint' and 'attributeSelector'. The 'documentIdentifier' specifies the document where the anchor shall be inserted. The target of the anchor is set in 'destinationIdentifier' if it already exists. If the target does not exist the element 'hint' has to be set to the name of object which is supposed to be inserted later. Once it is inserted the anchor target is resolved automatically.

See also hwapi_insertdocument(), hwapi_insertcollection(), hwapi_insert().

hw_api->insertcollection (unknown)

Inserts a new object of type collection

object **insertcollection** (array parameter) \linebreak

This function is a shortcut for hwapi_insert(). It inserts an object of type collection and sets some of the attributes required for a collection. The parameter array contains the required elements 'object' and 'parentIdentifier' and the optional elements 'parameter' and 'attributeSelector'. See hwapi_insert() for the meaning of each element.

See also hwapi_insertdocument(), hwapi_insertanchor(), hwapi_insert().

hw_api->insertdocument (unknown)

Inserts a new object of type document

object **insertdocument** (array parameter) \linebreak

This function is a shortcut for hwapi_insert(). It inserts an object with content and sets some of the attributes required for a document. The parameter array contains the required elements 'object', 'parentIdentifier' and 'content' and the optional elements 'mode', 'parameter' and 'attributeSelector'. See hwapi_insert() for the meaning of each element.

See also hwapi_insert() hwapi_insertanchor(), hwapi_insertcollection().

hw_api->link (unknown)

Creates a link to an object

object **link** (array parameter) \linebreak

Creates a link to an object. Accessing this link is like accessing the object to links points to. The parameter array contains the required elements 'objectIdentifier' and 'destinationParentIdentifier'. 'destinationParentIdentifier' is the target collection.

The function returns true on success or an error object.

See also hwapi_copy().

hw_api->lock (unknown)

Locks an object

object **lock** (array parameter) \linebreak

Locks an object for exclusive editing by the user calling this function. The object can be only unlocked by this user or the system user. The parameter array contains the required element 'objectIdentifier' and the optional parameters 'mode' and 'objectquery'. 'mode' determines how an object is locked. HW_API_LOCK_NORMAL means, an object is locked until it is unlocked.

HW_API_LOCK_RECURSIVE is only valid for collection and locks all objects within the collection and possible subcollections. HW_API_LOCK_SESSION means, an object is locked only as long as the session is valid.

See also `hwapi_unlock()`.

hw_api->move (unknown)

Moves object between collections

object **move** (array parameter) \linebreak

See also `hw_objrec2array()`.

hw_api_content (unknown)

Create new instance of class `hw_api_content`

string **content** (string content, string mimetype) \linebreak

Creates a new content object from the string *content*. The mimetype is set to *mimetype*.

hw_api->object (unknown)

Retrieve attribute information

object **hw_api->object** (array parameter) \linebreak

This function retrieves the attribute information of an object of any version. It will not return the document content. The parameter array contains the required elements 'objectIdentifier' and the optional elements 'attributeSelector' and 'version'.

The returned object is an instance of class `HW_API_Object` on success or `HW_API_Error` if an error occurred.

This simple example retrieves an object and checks for errors.

Příklad 1. Retrieve an object

```
<?php
function handle_error($error) {
    $reason = $error->reason(0);
    echo "Type: <B>";
    switch($reason->type()) {
        case 0:
            echo "Error";
            break;
        case 1:
            echo "Warning";
```

```

        break;
    case 2:
        echo "Message";
        break;
    }
    echo "</B><BR>\n";
    echo "Description: ".$reason->description("en")."<BR>\n";
}

function list_attr($obj) {
    echo "<TABLE>\n";
    $count = $obj->count();
    for($i=0; $i<$count; $i++) {
        $attr = $obj->attribute($i);
        printf("    <TR><TD ALIGN=right bgcolor=#c0c0c0><B>%s</B></TD><TD bgcolor=#F0F0F0>%s</TD></TR>\n",
            $attr->key(), $attr->value());
    }
    echo "</TABLE>\n";
}

$hwapi = hwapi_hgcsp($g_config[HOSTNAME]);
$params = array("objectIdentifier"=>"rootcollection", "attributeSelector"=>array("Title", "Description"));
$root = $hwapi->object($params);
if(get_class($root) == "HW_API_Error") {
    handle_error($root);
    exit;
}
list_attr($root);
?>

```

See also `hwapi_content()`.

hw_api_object->assign (unknown)

Clones object

object **assign** (array parameter) \linebreak

Clones the attributes of an object.

hw_api_object->attreditable (unknown)

Checks whether an attribute is editable

bool **attreditable** (array parameter) \linebreak

hw_api_object->count (unknown)

Returns number of attributes

int **count** (array parameter) \linebreak

hw_api_object->insert (unknown)

Inserts new attribute

bool **insert** (object attribute) \linebreak

Adds an attribute to the object. Returns true on success and otherwise false.

See also hwapi_object_remove().

hw_api_object (unknown)

Creates a new instance of class hw_api_object

object **hw_api_object** (array parameter) \linebreak

See also hwapi_lock().

hw_api_object->remove (unknown)

Removes attribute

bool **remove** (string name) \linebreak

Removes the attribute with the given name. Returns true on success and otherwise false.

See also hwapi_object_insert().

hw_api_object->title (unknown)

Returns the title attribute

string **title** (array parameter) \linebreak

hw_api_object->value (unknown)

Returns value of attribute

string **value** (string name) \linebreak

Returns the value of the attribute with the given name or false if an error occurred.

hw_api->objectbyanchor (unknown)

Returns the object an anchor belongs to

object **objectbyanchor** (array parameter) \linebreak

This function retrieves an object the specified anchor belongs to. The parameter array contains the required element 'objectIdentifier' and the optional element 'attributeSelector'.

See also **hwapi_dstofsrcanchor()**, **hwapi_srcanchors()**, **hwapi_dstanchors()**.

hw_api->parents (unknown)

Returns parents of an object

array **parents** (array parameter) \linebreak

Retrieves the parents of an object. The parents can be further filtered by specifying an object query. The parameter array contains the required elements 'objectIdentifier' and the optional elements 'attributeselector' and 'objectquery'.

The return value is an array of objects of type **HW_API_Object** or **HW_API_Error**.

See also **hwapi_children()**.

hw_api_reason->description (unknown)

Returns description of reason

string **description** (void) \linebreak

Returns the description of a reason

hw_api_reason->type (unknown)

Returns type of reason

object **type** (void) \linebreak

Returns the type of a reason.

hw_api->remove (unknown)

Delete an object

object **remove** (array parameter) \linebreak

This function removes an object from the specified parent. Collections will be removed recursively. You can pass an optional object query to remove only those objects which match the query. An object will be deleted physically if it is the last instance. The parameter array contains the required elements 'objectIdentifier' and 'parentIdentifier'. If you want to remove a user or group 'parentIdentifier' can be skipped. The optional parameter 'mode' determines how the deletion is performed. In normal mode the object will not be removed physically until all instances are removed. In physical mode all instances of the object will be deleted immediately. In removelinks mode all references to and from the objects will be deleted as well. In nonrecursive the deletion is not performed recursive. Removing a collection which is not empty will cause an error.

See also hwapi_move().

hw_api->replace (unknown)

Replaces an object

object **replace** (array parameter) \linebreak

Replaces the attributes and the content of an object The parameter array contains the required elements 'objectIdentifier' and 'object' and the optional parameters 'content', 'parameters', 'mode' and 'attributeSelector'. 'objectIdentifier' contains the object to be replaced. 'object' contains the new object. 'content' contains the new content. 'parameters' contain extra information for HTML documents. HTML_Language is the letter abbreviation of the language of the title. HTML_Base sets the base attribute of the HTML document. 'mode' can be a combination of the following flags:

HW_API_REPLACE_NORMAL

The object on the server is replace with the object passed.

HW_API_REPLACE_FORCE_VERSION_CONTROL

HW_API_REPLACE_AUTOMATIC_CHECKOUT

HW_API_REPLACE_AUTOMATIC_CHECKIN

HW_API_REPLACE_PLAIN

HW_API_REPLACE_REVERT_IF_NOT_CHANGED

HW_API_REPLACE_KEEP_TIME_MODIFIED

See also `hwapi_insert()`.

hw_api->setcommittedversion (unknown)

Commits version other than last version

object **setcommittedversion** (array parameter) \linebreak

Commits a version of a document. The committed version is the one which is visible to users with read access. By default the last version is the committed version.

See also `hwapi_checkin()`, `hwapi_checkout()`, **`hwapi_revert()`**.

hw_api->srcanchors (unknown)

Returns a list of all source anchors

object **srcanchors** (array parameter) \linebreak

Retrieves all source anchors of an object. The parameter array contains the required element 'objectIdentifier' and the optional elements 'attributeSelector' and 'objectQuery'.

See also `hwapi_dstanchors()`.

hw_api->srcsofdst (unknown)

Returns source of a destination object

object **srcsofdst** (array parameter) \linebreak

Retrieves all the source anchors pointing to the specified destination. The destination object can either be a destination anchor or a whole document. The parameters array contains the required element 'objectIdentifier' and the optional element 'attributeSelector' and 'objectQuery'. The function returns an array of objects or an error.

See also **`hwapi_dstofsrcanchor()`**.

hw_api->unlock (unknown)

Unlocks a locked object

object **unlock** (array parameter) \linebreak

Unlocks a locked object. Only the user who has locked the object and the system user may unlock an object. The parameter array contains the required element 'objectIdentifier' and the optional parameters 'mode' and 'objectquery'. The meaning of 'mode' is the same as in function hwapi_lock().

Returns true on success or an object of class HW_API_Error.

See also hwapi_lock().

hw_api->user (unknown)

Returns the own user object

object **user** (array parameter) \linebreak

See also hwapi_userlist().

hw_api->userlist (unknown)

Returns a list of all logged in users

object **userlist** (array parameter) \linebreak

See also hwapi_user().

XL. ICAP funkce

Pokud chcete používat tyto funkce, musíte PHP zkompilovat s `--with-icap`. To vyžaduje nainstalovanou icap knihovnu. Stáhněte si nejnovější verzi z <http://icap.chek.com/>, zkompilujte ji a nainstalujte.

icap_close (unknown)

Zavřít ICAP stream

```
int icap_close ( int icap_stream [, int flags]) \linebreak
```

Zavře daný ICAP stream.

icap_delete_event (PHP 4 >= 4.0.0)

Delete an event from an ICAP calendar

```
string icap_delete_event ( int stream_id, int uid) \linebreak
```

icap_delete_event() maže událost *uid* z kalendáře.

Vrací TRUE.

icap_fetch_event (PHP 4 >= 4.0.0)

Získat událost z kalendářového stream

```
int icap_fetch_event ( int stream_id, int event_id [, int options]) \linebreak
```

icap_fetch_event() získá událost z kalendářového streamu určenou argumentem *event_id*.

Vrací objekt události obsahující:

- int id - ID této události.
- int public - TRUE, pokud je událost veřejná, FALSE, pokud je soukromá
- string category - kategorie této události
- string title - titul této události
- string description - popis této události
- int alarm - kolik minut před touto událostí se má odeslat alarm/připomínka
- object start - Objekt obsahující datetime záznam.
- object end - Objekt obsahující datetime záznam.

Všechny datetime záznamy tvoří objekt, který obsahuje:

- int year - rok
- int month - měsíc
- int mday - den v měsíci
- int hour - hodinu
- int min - minuty
- int sec - sekundy

icap_list_alarms (PHP 4 >= 4.0.0)

Vrátit seznam událostí, které mají v dané datum/čas puštěný alarm

int icap_list_alarms (int stream_id, array date, array time) \linebreak

Vrací pole identifikátorů událostí, které mají v dané datum/čas puštěný alarm.

icap_list_alarms() function přijímá datum v kalendářovém streamu. Vrací pole identifikátorů událostí, které mají v dané datum/čas puštěný alarm.

Všechny datetime záznamy tvoří objekt, který obsahuje:

- int year - rok
- int month - měsíc
- int mday - den v měsíci
- int hour - hodinu
- int min - minuty
- int sec - sekundy

icap_list_events (PHP 4 >= 4.0.0)

Vrátit seznam událostí mezi dvěma daty

array icap_list_events (int stream_id, int begin_date [, int end_date]) \linebreak

Vrací pole id událostí, které jsou mezi dvěma danými daty.

icap_list_events() přijímá počáteční a konečné datum kalendářového streamu. Vrací pole identifikátorů událostí, které jsou mezi těmito dvěma daty.

Všechny datetime záznamy tvoří objekt, který obsahuje:

- int year - rok
- int month - měsíc
- int mday - den v měsíci
- int hour - hodinu
- int min - minuty
- int sec - sekundy

icap_open (PHP 4 >= 4.0.0)

Otevřít ICAP spojení

stream **icap_open** (string *calendar*, string *username*, string *password*, string *options*) \linebreak

Při úspěchu vrátí ICAP stream, při chybě FALSE.

icap_open() otevře ICAP spojení s daným *calendar* zdrojem dat. Pokud je přítomen argument *options*, předá tyto *options* danému mailboxu.

icap_snooze (PHP 4 >= 4.0.0)

Zapnout alarm

string **icap_snooze** (int *stream_id*, int *uid*) \linebreak

icap_snooze() zapne alarm pro událost *uid*.

Vrací TRUE.

icap_store_event (PHP 4 >= 4.0.0)

Uložit událost do ICAP kalendáře

string **icap_store_event** (int *stream_id*, object *event*) \linebreak

icap_store_event() ukládá událost do ICAP kalendáře. Objekt události se skládá z:

- int *public* - TRUE, pokud je událost veřejná, FALSE, pokud je soukromá
- string *category* - kategorie této události
- string *title* - titul této události
- string *description* - popis této události
- int *alarm* - kolik minut před touto událostí se má odeslat alarm/připomínka
- object *start* - Objekt obsahující datetime záznam.
- object *end* - Objekt obsahující datetime záznam.

Všechny datetime záznamy tvoří objekt, který obsahuje:

- int *year* - rok
- int *month* - měsíc
- int *mday* - den v měsíci
- int *hour* - hodinu
- int *min* - minuty
- int *sec* - sekundy

Při úspěchu vrátí TRUE, při chybě FALSE.

XLI. iconv functions

This module contains an interface to the iconv library functions. To be able to use the functions defined in this module you must compile your PHP interpreter using the `--with-iconv` option. In order to do so, you must have `iconv()` function in standard C library or `libiconv` installed on your system. `libiconv` library is available from <http://www.gnu.org/software/libiconv/> (<http://www.gnu.org/software/libiconv/>).

`iconv` library function converts files between various encoded character sets. The supported character sets depend on `iconv()` implementation on your system. Note that `iconv()` function in some system is not work well as you expect. In this case, you should install `libiconv` library.

iconv (PHP 4 >= 4.0.5)

Convert string to requested character encoding

string **iconv** (string *in_charset*, string *out_charset*, string *str*) \linebreak

It converts the string *string* encoded in *in_charset* to the string encoded in *out_charset*. It returns the converted string or FALSE, if it fails.

Příklad 1. iconv() example:

```
echo iconv("ISO-8859-1", "UTF-8", "This is test.");
```

iconv_get_encoding (PHP 4 >= 4.0.5)

Get current setting for character encoding conversion

array **iconv_get_encoding** ([string *type*]) \linebreak

It returns the current settings of ob_iconv_handler() as array or FALSE in failure.

See also: iconv_set_encoding() and ob_iconv_handler().

iconv_set_encoding (PHP 4 >= 4.0.5)

Set current setting for character encoding conversion

array **iconv_set_encoding** (string *type*, string *charset*) \linebreak

It changes the value of *type* to *charset* and returns TRUE in success or FALSE in failure.

Příklad 1. iconv_set_encoding() example:

```
iconv_set_encoding("internal_encoding", "UTF-8");
iconv_set_encoding("output_encoding", "ISO-8859-1");
```

See also: iconv_get_encoding() and ob_iconv_handler().

ob_iconv_handler (PHP 4 >= 4.0.5)

Convert character encoding as output buffer handler

array **ob_iconv_handler** (string contents, int status) \linebreak

It converts the string encoded in *internal_encoding* to *output_encoding*.

internal_encoding and *output_encoding* should be defined by `iconv_set_encoding()` or in configuration file.

Příklad 1. ob_iconv_handler() example:

```
ob_start("ob_iconv_handler"); // start output buffering
```

See also: `iconv_get_encoding()` and `iconv_set_encoding()`.

XLII. Image functions

You can use the image functions in PHP to get the size of JPEG, GIF, PNG, SWF, TIFF and JPEG2000 images, and if you have the GD library (available at <http://www.boutell.com/gd/>) you will also be able to create and manipulate images.

If you have PHP compiled with `--enable-exif` you are able to work with information stored in headers of JPEG and TIFF images. These functions do not require GD library.

The format of images you are able to manipulate depend on the version of gd you install, and any other libraries gd might need to access those image formats. Versions of gd older than gd-1.6 support gif format images, and do not support png, where versions greater than gd-1.6 support png, not gif.

In order to read and write images in jpeg format, you will need to obtain and install jpeg-6b (available at <ftp://ftp.uu.net/graphics/jpeg/>), and then recompile gd to make use of jpeg-6b. You will also have to compile PHP with `--with-jpeg-dir=/path/to/jpeg-6b`.

To add support for Type 1 fonts, you can install t1lib (available at <ftp://sunsite.unc.edu/pub/Linux/libs/graphics/>), and then add `--with-t1lib[=dir]`.

exif_imagetype (PHP 4 CVS only)

Determine the type of an image

```
int|false exif_imagetype ( string filename) \linebreak
```

exif_imagetype() reads the first bytes of an image and checks its signature. When a correct signature is found a constant will be returned otherwise the return value is `FALSE`. The return value is the same value that `getimagesize()` returns in index 2 but this function is much faster.

The following constants are defined: 1 = `IMAGETYPE_GIF`, 2 = `IMAGETYPE_JPG`, 3 = `IMAGETYPE_PNG`, 4 = `IMAGETYPE_SWF`, 5 = `IMAGETYPE_PSD`, 6 = `IMAGETYPE_BMP`, 7 = `IMAGETYPE_TIFF_II` (intel byte order), 8 = `IMAGETYPE_TIFF_MM` (motorola byte order), 9 = `IMAGETYPE_JPC`, 10 = `IMAGETYPE_JP2`, 11 = `IMAGETYPE_JPX`.

This function can be used to avoid calls to other exif functions with unsupported file teypes or in conjunction with `$_SERVER['HTTP_ACCEPT']` to check whether or not the viewer is able to see a specific image in his browser.

Poznámka: This function is only available in PHP 4 compiled using `--enable-exif`.

This function does not require the GD image library.

See also `getimagesize()`.

exif_read_data (PHP 4 >= 4.2.0)

Read the EXIF headers from JPEG or TIFF

```
array exif_read_data ( string filename [, string sections [, bool arrays [, bool thumbnail]]]) \linebreak
```

The **exif_read_data()** function reads the EXIF headers from a JPEG or TIFF image file. It returns an associative array where the indexes are the header names and the values are the values associated with those headers. If no data can be returned the result is `FALSE`.

filename is the name of the file to read. This cannot be a url.

sections a comma separated lsit of sections that need to be present in file to produce a result array.

FILE	FileName, FileSize, FileDateTime, SectionsFound
COMPUTED	html, Width, Height, IsColor and some more if available.
ANY_TAG	Any information that has a Tag e.g. IFD0, EXIF, ...
IFD0	All tagged data of IFD0. In normal imagefiles this contains image size and so forth.

THUMBNAIL	A file is supposed to contain a thumbnail if it has a second IFD. All tagged information about the embedded thumbnail is stored in this section.
COMMENT	Comment headers of JPEG images.
EXIF	The EXIF section is a sub section of IFD0. It contains more detailed information about an image. Most of these entries are digital camera related.

arrays specifies whether or not each section becomes an array. The sections *FILE*, *COMPUTED* and *THUMBNAIL* allways become arrays as they may contain values whose names are conflict with other sections.

thumbnail whether or not to read the thumbnail itself and not only its tagged data.

Poznámka: Exif headers tend to be present in JPEG/TIFF images generated by digital cameras, but unfortunately each digital camera maker has a different idea of how to actually tag their images, so you can't always rely on a specific Exif header being present.

Příklad 1. `exif_read_data()` example

```
<?php
echo "test1.jpg:<br>\n";
$exif = exif_read_data ('tests/test1.jpg', 'IFD0');
echo $exif===false ? "No header data found.<br>\n" : "Image contains headers<br>";
$exif = exif_read_data ('tests/test2.jpg', 0, true);
echo "test2.jpg:<br>\n";
foreach($exif as $key=>$section) {
    foreach($section as $name=>$val) {
        echo "$key.$name: $val<br>\n";
    }
}
}??>
```

The first call fails because the image has no header information.

```
test1.jpg:
No header data found.
test2.jpg:
FILE.FileName: test2.jpg
FILE.FileDateTime: 1017666176
FILE.FileSize: 1240
FILE.FileType: 2
FILE.SectionsFound: ANY_TAG, IFD0, THUMBNAIL, COMMENT
COMPUTED.html: width="1" height="1"
COMPUTED.Height: 1
COMPUTED.Width: 1
COMPUTED.IsColor: 1
COMPUTED.ByteOrderMotorola: 1
```

```

COMPUTED.UserComment: Exif test image.
COMPUTED.UserCommentEncoding: ASCII
COMPUTED.Copyright: Photo (c) M.Boerger, Edited by M.Boerger.
COMPUTED.Copyright.Photographer: Photo (c) M.Boerger
COMPUTED.Copyright.Editor: Edited by M.Boerger.
IFD0.Copyright: Photo (c) M.Boerger
IFD0.UserComment: ASCII
THUMBNAIL.JPEGInterchangeFormat: 134
THUMBNAIL.JPEGInterchangeFormatLength: 523
COMMENT.0: Comment #1.
COMMENT.1: Comment #2.
COMMENT.2: Comment #3end

```

Poznámka: If the image contains any IFD0 data then COMPUTED contains the entry *ByteOrderMotorola* which is 0 for little-endian (intel) and 1 for big-endian (motorola) byte order. This was added in PHP 4.3.

When an Exif header contains a Copyright note this itself can contain two values. As the solution is inconsistent in the Exif 2.10 standard the COMPUTED section will return both entries *Copyright.Photographer* and *Copyright.Editor* while the IFD0 sections contains the byte array with the NULL character that splits both entries. Or just the first entry if the datatype was wrong (normal behaviour of Exif). The COMPUTED will contain also an entry *Copyright* Which is either the original copyright string or it is a comma separated list of photo and editor copyright.

Poznámka: The tag UserComment has the same problem as the Copyright tag. It can store two values first the encoding used and second the value itself. If so the IFD section only contains the encoding or a byte array. The COMPUTED section will store both in the entries *UserCommentEncoding* and *UserComment*. The entry *UserComment* is available in both cases so it should be used in preference to the value in IFD0 section.

If the user comment uses Unicode or JIS encoding and the module mbstring is available this encoding will automatically changed according to the exif ini settings. This was added in PHP 4.3.

Poznámka: Height and Width are computed the same way *getimagesize()* does so their values must not be part of any header returned. Also *html* is a height/width text string to be used inside normal HTML.

Poznámka: Starting from PHP 4.3 the function can read all embedded IFD data including arrays (returned as such). Also the size of an embedded thumbnail is returned in *THUMBNAIL* subarray and the function ***exif_read_data()*** can return thumbnails in TIFF format. Last but not least there is no longer a maximum length for returned values (not until memory limit is reached).

Poznámka: This function is only available in PHP 4 compiled using `--enable-exif`. Its functionality and behaviour has changed in PHP 4.2. Earlier versions are very unstable.

Since PHP 4.3 user comment can automatically change encoding if PHP 4 was compiled using `--enable-mbstring`.

This function does not require the GD image library.

See also `exif_thumbnail()` and `getimagesize()`.

exif_thumbnail (PHP 4 >= 4.2.0)

Retrieve the embedded thumbnail of a TIFF or JPEG image

string **exif_thumbnail** (string filename [, int &width [, int &height]]) \linebreak

exif_thumbnail() reads the embedded thumbnail of a TIFF or JPEG image. If the image contains no thumbnail `FALSE` will be returned.

Both parameters *width* and *height* are available since PHP 4.3 and return the size of the thumbnail. It is possible that **exif_thumbnail()** cannot create an image but determine its size. In this case the return value is `FALSE` but *width* and *height* are set.

Starting from version PHP 4.3 the function **exif_thumbnail()** can return thumbnails in TIFF format.

Poznámka: This function is only available in PHP 4 compiled using `--enable-exif`. Its functionality and behaviour has changed in PHP 4.2

This function does not require the GD image library.

See also `exif_read_data()`.

getimagesize (PHP 3, PHP 4 >= 4.0.0)

Get the size of an image

array **getimagesize** (string filename [, array imageinfo]) \linebreak

The **getimagesize()** function will determine the size of any GIF, JPG, PNG, SWF, PSD, TIFF or BMP image file and return the dimensions along with the file type and a height/width text string to be used inside a normal HTML `IMG` tag.

Returns an array with 4 elements. Index 0 contains the width of the image in pixels. Index 1 contains the height. Index 2 a flag indicating the type of the image. 1 = GIF, 2 = JPG, 3 = PNG, 4 = SWF, 5 = PSD, 6 = BMP, 7 = TIFF(intel byte order), 8 = TIFF(motorola byte order, 9 = JPC, 10 = JP2, 11 = JPX. Index 3 is a text string with the correct `height="yyy" width="xxx"` string that can be used directly in an `IMG` tag.

Příklad 1. getimagesize (file)

```
<?php
$size = getimagesize ("img/flag.jpg");
echo "<img src=\"img/flag.jpg\" {$size[3]}>";
?>
```

Příklad 2. getimagesize (URL)

```
<?php $size = getimagesize ("http://www.example.com/gifs/logo.gif"); ?>
```

With JPG images, two extra indexes are returned: *channel* and *bits*. *channel* will be 3 for RGB pictures, and 4 for CMYK pictures. *bits* is the number of bits for each color.

If accessing the *filename* image is impossible, or if it isn't a valid picture, **getimagesize()** will return `NULL` and generate a warning.

The optional *imageinfo* parameter allows you to extract some extended information from the image file. Currently this will return the different JPG APP markers in an associative Array. Some Programs use these APP markers to embed text information in images. A very common one is to embed IPTC <http://www.iptc.org/> information in the APP13 marker. You can use the `iptcparse()` function to parse the binary APP13 marker into something readable.

Příklad 3. getimagesize returning IPTC

```
<?php
$size = getimagesize ("testimg.jpg",&$info);
if (isset ($info["APP13"])) {
    $iptc = iptcparse ($info["APP13"]);
    var_dump ($iptc);
}
?>
```

Poznámka: TIFF support was added in PHP 4.2. JPEG2000 support will be added in PHP 4.3.

This function does not require the GD image library.

See also `exif_imagetype()`, `exif_read_data()` and `exif_thumbnail()`.

URL support was added in PHP 4.0.5

image2wbmp (PHP 4 >= 4.0.5)

Output image to browser or file

```
int image2wbmp ( resource image [, string filename [, int threshold]]) \linebreak
```

image2wbmp() creates the WBMP file in filename from the image *image*. The *image* argument is the return from `imagecreate()`.

The filename argument is optional, and if left off, the raw image stream will be output directly. By sending an `image/vnd.wap.wbmp` content-type using `header()`, you can create a PHP script that outputs WBMP images directly.

Poznámka: WBMP support is only available if PHP was compiled against GD-1.8 or later.

See also `imagewbmp()`.

imagealphablending (PHP 4 >= 4.0.6)

Set the blending mode for an image

```
int imagealphablending ( resource image, bool blendmode) \linebreak
```

imagealphablending() allows for two different modes of drawing on truecolor images. In blending mode, the alpha channel component of the color supplied to all drawing function, such as `imagepixel()` determines how much of the underlying color should be allowed to shine through. As a result, gd automatically blends the existing color at that point with the drawing color, and stores the result in the image. The resulting pixel is opaque. In non-blending mode, the drawing color is copied literally with its alpha channel information, replacing the destination pixel. Blending mode is not available when drawing on palette images. If *blendmode* is `TRUE`, then blending mode is enabled, otherwise disabled.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1

imagearc (PHP 3, PHP 4 >= 4.0.0)

Draw a partial ellipse

```
int imagearc ( resource image, int cx, int cy, int w, int h, int s, int e, int col) \linebreak
```

imagearc() draws a partial ellipse centered at *cx*, *cy* (top left is 0, 0) in the image represented by *image*. *W* and *h* specifies the ellipse's width and height respectively while the start and end points are specified in degrees indicated by the *s* and *e* arguments. 0° is located at the three-o'clock position, and the arc is drawn counter-clockwise.

See also `imageellipse()`, `imagefilledellipse()`, and `imagefilledarc()`.

imagechar (PHP 3, PHP 4 >= 4.0.0)

Draw a character horizontally

int **imagechar** (resource image, int font, int x, int y, string c, int col) \linebreak

imagechar() draws the first character of *c* in the image identified by *id* with its upper-left at *x,y* (top left is 0, 0) with the color *col*. If *font* is 1, 2, 3, 4 or 5, a built-in font is used (with higher numbers corresponding to larger fonts).

See also `imageloadfont()`.

imagecharup (PHP 3, PHP 4 >= 4.0.0)

Draw a character vertically

int **imagecharup** (resource image, int font, int x, int y, string c, int col) \linebreak

imagecharup() draws the character *c* vertically in the image identified by *image* at coordinates *x, y* (top left is 0, 0) with the color *col*. If *font* is 1, 2, 3, 4 or 5, a built-in font is used.

See also `imageloadfont()`.

imagecolorallocate (PHP 3, PHP 4 >= 4.0.0)

Allocate a color for an image

int **imagecolorallocate** (resource image, int red, int green, int blue) \linebreak

imagecolorallocate() returns a color identifier representing the color composed of the given RGB components. The *im* argument is the return from the `imagecreate()` function. *red*, *green* and *blue* are the values of the red, green and blue component of the requested color respectively. These parameters are integers between 0 and 255. **imagecolorallocate()** must be called to create each color that is to be used in the image represented by *image*.

```
$white = imagecolorallocate ($im, 255, 255, 255);
$black = imagecolorallocate ($im, 0, 0, 0);
```

Returns -1 if the allocation failed.

imagecolorat (PHP 3, PHP 4 >= 4.0.0)

Get the index of the color of a pixel

int **imagecolorat** (resource image, int x, int y) \linebreak

Returns the index of the color of the pixel at the specified location in the image specified by *image*.
See also `imagecolorset()` and `imagecolorsforindex()`.

imagecolorclosest (PHP 3, PHP 4 >= 4.0.0)

Get the index of the closest color to the specified color

int imagecolorclosest (resource image, int red, int green, int blue) \linebreak

Returns the index of the color in the palette of the image which is "closest" to the specified RGB value.

The "distance" between the desired color and each color in the palette is calculated as if the RGB values represented points in three-dimensional space.

See also `imagecolorexact()`.

imagecolorclosestalpha (PHP 4 >= 4.0.6)

Get the index of the closest color to the specified color + alpha

int imagecolorclosestalpha (resource image, int red, int green, int blue, int alpha) \linebreak

Returns the index of the color in the palette of the image which is "closest" to the specified RGB value and *alpha* level.

See also `imagecolorexactalpha()`.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1

imagecolorclosesthwb (PHP 4)

Get the index of the color which has the hue, white and blackness nearest to the given color

int imagecolorclosesthwb (resource image, int red, int green, int blue) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imagecolordeallocate (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

De-allocate a color for an image

int **imagecolordeallocate** (resource image, int color) \linebreak

The **imagecolordeallocate()** function de-allocates a color previously allocated with the **imagecolorallocate()** function.

```
$white = imagecolorallocate ($im, 255, 255, 255);
imagecolordeallocate ($im, $white);
```

imagecolorexact (PHP 3, PHP 4 >= 4.0.0)

Get the index of the specified color

int **imagecolorexact** (resource image, int red, int green, int blue) \linebreak

Returns the index of the specified color in the palette of the image.

If the color does not exist in the image's palette, -1 is returned.

See also **imagecolorclosest()**.

imagecolorexactalpha (PHP 4 >= 4.0.6)

Get the index of the specified color + alpha

int **imagecolorexactalpha** (resource image, int red, int green, int blue, int alpha) \linebreak

Returns the index of the specified color+alpha in the palette of the image.

If the color does not exist in the image's palette, -1 is returned.

See also **imagecolorclosestalpha()**.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1 or later

imagecolorresolve (PHP 3>= 3.0.2, PHP 4 >= 4.0.0)

Get the index of the specified color or its closest possible alternative

int **imagecolorresolve** (resource image, int red, int green, int blue) \linebreak

This function is guaranteed to return a color index for a requested color, either the exact color or the closest possible alternative.

See also `imagecolorclosest()`.

imagecolorresolvealpha (PHP 4 >= 4.0.6)

Get the index of the specified color + alpha or its closest possible alternative

int **imagecolorresolvealpha** (resource image, int red, int green, int blue, int alpha) \linebreak

This function is guaranteed to return a color index for a requested color, either the exact color or the closest possible alternative.

See also `imagecolorclosestalpha()`.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1

imagecolorset (PHP 3, PHP 4 >= 4.0.0)

Set the color for the specified palette index

bool **imagecolorset** (resource image, int index, int red, int green, int blue) \linebreak

This sets the specified index in the palette to the specified color. This is useful for creating flood-fill-like effects in paletted images without the overhead of performing the actual flood-fill.

See also `imagecolorat()`.

imagecolorsforindex (PHP 3, PHP 4 >= 4.0.0)

Get the colors for an index

array **imagecolorsforindex** (resource image, int index) \linebreak

This returns an associative array with red, green, and blue keys that contain the appropriate values for the specified color index.

See also `imagecolorat()` and `imagecolorexact()`.

imagecolorstotal (PHP 3, PHP 4 >= 4.0.0)

Find out the number of colors in an image's palette

int **imagecolorstotal** (resource image) \linebreak

This returns the number of colors in the specified image's palette.

See also `imagecolorat()` and `imagecolorsforindex()`.

imagecolortransparent (PHP 3, PHP 4 >= 4.0.0)

Define a color as transparent

`int imagecolortransparent (resource image [, int color])` \linebreak

imagecolortransparent() sets the transparent color in the *image* image to *color*. *image* is the image identifier returned by `imagecreate()` and *color* is a color identifier returned by `imagecolorallocate()`.

Poznámka: The transparent color is a property of the image, transparency is not a property of the color. Once you have a set a color to be the transparent color, any regions of the image in that color that were drawn previously will be transparent.

The identifier of the new (or current, if none is specified) transparent color is returned.

imagecopy (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Copy part of an image

`int imagecopy (resource dst_im, resource src_im, int dst_x, int dst_y, int src_x, int src_y, int src_w, int src_h)` \linebreak

Copy a part of *src_im* onto *dst_im* starting at the x,y coordinates *src_x*, *src_y* with a width of *src_w* and a height of *src_h*. The portion defined will be copied onto the x,y coordinates, *dst_x* and *dst_y*.

imagecopymerge (PHP 4)

Copy and merge part of an image

`int imagecopymerge (resource dst_im, resource src_im, int dst_x, int dst_y, int src_x, int src_y, int src_w, int src_h, int pct)` \linebreak

Copy a part of *src_im* onto *dst_im* starting at the x,y coordinates *src_x*, *src_y* with a width of *src_w* and a height of *src_h*. The portion defined will be copied onto the x,y coordinates, *dst_x* and *dst_y*. The two images will be merged according to *pct* which can range from 0 to 100. When *pct* = 0, no action is taken, when 100 this function behaves identically to `imagecopy()`.

Poznámka: This function was added in PHP 4.0.6

imagecopymergegray (PHP 4 >= 4.0.6)

Copy and merge part of an image with gray scale

int **imagecopymergegray** (resource *dst_im*, resource *src_im*, int *dst_x*, int *dst_y*, int *src_x*, int *src_y*, int *src_w*, int *src_h*, int *pct*) \linebreak

imagecopymergegray() copy a part of *src_im* onto *dst_im* starting at the x,y coordinates *src_x*, *src_y* with a width of *src_w* and a height of *src_h*. The portion defined will be copied onto the x,y coordinates, *dst_x* and *dst_y*. The two images will be merged according to *pct* which can range from 0 to 100. When *pct* = 0, no action is taken, when 100 this function behaves identically to **imagecopy()**.

This function is identical to **imagecopymerge()** except that when merging it preserves the hue of the source by converting the destination pixels to gray scale before the copy operation.

Poznámka: This function was added in PHP 4.0.6

imagecopyresampled (PHP 4 >= 4.0.6)

Copy and resize part of an image with resampling

int **imagecopyresampled** (resource *dst_im*, resource *src_im*, int *dstX*, int *dstY*, int *srcX*, int *srcY*, int *dstW*, int *dstH*, int *srcW*, int *srcH*) \linebreak

imagecopyresampled() copies a rectangular portion of one image to another image, smoothly interpolating pixel values so that, in particular, reducing the size of an image still retains a great deal of clarity. *Dst_im* is the destination image, *src_im* is the source image identifier. If the source and destination coordinates and width and heights differ, appropriate stretching or shrinking of the image fragment will be performed. The coordinates refer to the upper left corner. This function can be used to copy regions within the same image (if *dst_im* is the same as *src_im*) but if the regions overlap the results will be unpredictable.

See also **imagecopyresized()**.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1 or later

imagecopyresized (PHP 3, PHP 4 >= 4.0.0)

Copy and resize part of an image

int **imagecopyresized** (resource *dst_im*, resource *src_im*, int *dstX*, int *dstY*, int *srcX*, int *srcY*, int *dstW*, int *dstH*, int *srcW*, int *srcH*) \linebreak

imagecopyresized() copies a rectangular portion of one image to another image. *Dst_im* is the destination image, *src_im* is the source image identifier. If the source and destination coordinates

and width and heights differ, appropriate stretching or shrinking of the image fragment will be performed. The coordinates refer to the upper left corner. This function can be used to copy regions within the same image (if *dst_im* is the same as *src_im*) but if the regions overlap the results will be unpredictable.

See also `imagecopyresampled()`.

imagecreate (PHP 3, PHP 4 >= 4.0.0)

Create a new palette based image

resource **imagecreate** (int *x_size*, int *y_size*) \linebreak

imagecreate() returns an image identifier representing a blank image of size *x_size* by *y_size*.

Příklad 1. Creating a new GD image stream and outputting an image.

```
<?php
header ("Content-type: image/png");
$im = @imagecreate (50, 100)
    or die ("Cannot Initialize new GD image stream");
$background_color = imagecolorallocate ($im, 255, 255, 255);
$text_color = imagecolorallocate ($im, 233, 14, 91);
imagestring ($im, 1, 5, 5, "A Simple Text String", $text_color);
imagepng ($im);
?>
```

imagecreatefromgd (PHP 4 >= 4.1.0)

Create a new image from GD file or URL

resource **imagecreatefromgd** (string *filename*) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imagecreatefromgd2 (PHP 4 >= 4.1.0)

Create a new image from GD2 file or URL

resource **imagecreatefromgd2** (string filename) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imagecreatefromgd2part (PHP 4 >= 4.1.0)

Create a new image from a given part of GD2 file or URL

resource **imagecreatefromgd2part** (string filename, int srcX, int srcY, int width, int height) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imagecreatefromgif (PHP 3, PHP 4 >= 4.0.0)

Create a new image from file or URL

resource **imagecreatefromgif** (string filename) \linebreak

imagecreatefromgif() returns an image identifier representing the image obtained from the given filename.

imagecreatefromgif() returns an empty string on failure. It also outputs an error message, which unfortunately displays as a broken link in a browser. To ease debugging the following example will produce an error GIF:

Příklad 1. Example to handle an error during creation (courtesy vic@zysys.com)

```
function LoadGif ($imgname) {
    $im = @imagecreatefromgif ($imgname); /* Attempt to open */
    if (!$im) { /* See if it failed */
        $im = imagecreate (150, 30); /* Create a blank image */
        $bgc = imagecolorallocate ($im, 255, 255, 255);
        $tc = imagecolorallocate ($im, 0, 0, 0);
        imagefilledrectangle ($im, 0, 0, 150, 30, $bgc);
        /* Output an errmsg */
        imagestring ($im, 1, 5, 5, "Error loading $imgname", $tc);
    }
    return $im;
}
```

```
}
```

Poznámka: Since all GIF support was removed from the GD library in version 1.6, this function is not available if you are using that version of the GD library.

imagecreatefromjpeg (PHP 3>= 3.0.16, PHP 4 >= 4.0.0)

Create a new image from file or URL

resource **imagecreatefromjpeg** (string filename) \linebreak

imagecreatefromjpeg() returns an image identifier representing the image obtained from the given filename.

imagecreatefromjpeg() returns an empty string on failure. It also outputs an error message, which unfortunately displays as a broken link in a browser. To ease debugging the following example will produce an error JPEG:

Příklad 1. Example to handle an error during creation (courtesy vic@zysmsys.com)

```
function LoadJpeg ($imgname) {
    $im = @imagecreatefromjpeg ($imgname); /* Attempt to open */
    if (!$im) { /* See if it failed */
        $im = imagecreate (150, 30); /* Create a blank image */
        $bgc = imagecolorallocate ($im, 255, 255, 255);
        $tc = imagecolorallocate ($im, 0, 0, 0);
        imagefilledrectangle ($im, 0, 0, 150, 30, $bgc);
        /* Output an errmsg */
        imagestring ($im, 1, 5, 5, "Error loading $imgname", $tc);
    }
    return $im;
}
```

imagecreatefrompng (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Create a new image from file or URL

resource **imagecreatefrompng** (string filename) \linebreak

imagecreatefrompng() returns an image identifier representing the image obtained from the given filename.

imagecreatefrompng() returns an empty string on failure. It also outputs an error message, which unfortunately displays as a broken link in a browser. To ease debugging the following example will produce an error PNG:

Příklad 1. Example to handle an error during creation (courtesy vic@zysms.com)

```
function LoadPNG ($imgname) {
    $im = @imagecreatefrompng ($imgname); /* Attempt to open */
    if (!$im) { /* See if it failed */
        $im = imagecreate (150, 30); /* Create a blank image */
        $bgc = imagecolorallocate ($im, 255, 255, 255);
        $tc = imagecolorallocate ($im, 0, 0, 0);
        imagefilledrectangle ($im, 0, 0, 150, 30, $bgc);
        /* Output an errmsg */
        imagestring ($im, 1, 5, 5, "Error loading $imgname", $tc);
    }
    return $im;
}
```

imagecreatefromstring (PHP 4 >= 4.0.4)

Create a new image from the image stream in the string

resource **imagecreatefromstring** (string image) \linebreak

imagecreatefromstring() returns an image identifier representing the image obtained from the given string.

imagecreatefromwbmp (PHP 4)

Create a new image from file or URL

resource **imagecreatefromwbmp** (string filename) \linebreak

imagecreatefromwbmp() returns an image identifier representing the image obtained from the given filename.

imagecreatefromwbmp() returns an empty string on failure. It also outputs an error message, which unfortunately displays as a broken link in a browser. To ease debugging the following example will produce an error WBMP:

Příklad 1. Example to handle an error during creation (courtesy vic@zysms.com)

```
function LoadWBMP ($imgname) {
    $im = @imagecreatefromwbmp ($imgname); /* Attempt to open */
    if (!$im) { /* See if it failed */
```

```

    $im = imagecreate (20, 20); /* Create a blank image */
    $bgc = imagecolorallocate ($im, 255, 255, 255);
    $tc = imagecolorallocate ($im, 0, 0, 0);
    imagefilledrectangle ($im, 0, 0, 10, 10, $bgc);
    /* Output an errmsg */
    imagestring ($im, 1, 5, 5, "Error loading $imgname", $tc);
}
return $im;
}

```

Poznámka: WBMP support is only available if PHP was compiled against GD-1.8 or later.

imagecreatefromxbm (PHP 4)

Create a new image from file or URL

resource **imagecreatefromxbm** (string filename) \linebreak

imagecreatefromxbm() returns an image identifier representing the image obtained from the given filename.

imagecreatefromxpm (PHP 4)

Create a new image from file or URL

resource **imagecreatefromxpm** (string filename) \linebreak

imagecreatefromxpm() returns an image identifier representing the image obtained from the given filename.

imagecreatetruecolor (PHP 4 >= 4.0.6)

Create a new true color image

resource **imagecreatetruecolor** (int x_size, int y_size) \linebreak

imagecreatetruecolor() returns an image identifier representing a black image of size *x_size* by *y_size*.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1 or later

imagedashedline (PHP 3, PHP 4 >= 4.0.0)

Draw a dashed line

int **imagedashedline** (resource image, int x1, int y1, int x2, int y2, int col) \linebreak

This function is deprecated. Use combination of imagesetstyle() and imageline() instead.

imagedestroy (PHP 3, PHP 4 >= 4.0.0)

Destroy an image

int **imagedestroy** (resource image) \linebreak

imagedestroy() frees any memory associated with image *image*. *image* is the image identifier returned by the imagecreate() function.

imageellipse (PHP 4 >= 4.0.6)

Draw an ellipse

int **imageellipse** (resource image, int cx, int cy, int w, int h, int col) \linebreak

imageellipse() draws an ellipse centered at *cx*, *cy* (top left is 0, 0) in the image represented by *image*. *w* and *h* specifies the ellipse's width and height respectively. The color of the ellipse is specified by *color*.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.2 or later

See also imagearc().

imagefill (PHP 3, PHP 4 >= 4.0.0)

Flood fill

int **imagefill** (resource image, int x, int y, int col) \linebreak

imagefill() performs a flood fill starting at coordinate *x*, *y* (top left is 0, 0) with color *col* in the image *image*.

imagefilledarc (PHP 4 >= 4.0.6)

Draw a partial ellipse and fill it

int **imagefilledarc** (resource image, int cx, int cy, int w, int h, int s, int e, int col, int style) \linebreak

imagefilledarc() draws a partial ellipse centered at *cx*, *cy* (top left is 0, 0) in the image represented by *image*. *W* and *h* specifies the ellipse's width and height respectively while the start and end points are specified in degrees indicated by the *s* and *e* arguments. *style* is a bitwise OR of the following possibilities:

1. IMG_ARC_PIE
2. IMG_ARC_CHORD
3. IMG_ARC_NOFILL
4. IMG_ARC_EDGED

IMG_ARC_PIE and IMG_ARC_CHORD are mutually exclusive; IMG_ARC_CHORD just connects the starting and ending angles with a straight line, while IMG_ARC_PIE produces a rounded edge. IMG_ARC_NOFILL indicates that the arc or chord should be outlined, not filled. IMG_ARC_EDGED, used together with IMG_ARC_NOFILL, indicates that the beginning and ending angles should be connected to the center - this is a good way to outline (rather than fill) a 'pie slice'.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1

imagefilledellipse (PHP 4 >= 4.0.6)

Draw a filled ellipse

int **imagefilledellipse** (resource image, int cx, int cy, int w, int h, int col) \linebreak

imagefilledellipse() draws an ellipse centered at *cx*, *cy* (top left is 0, 0) in the image represented by *image*. *W* and *h* specifies the ellipse's width and height respectively. The ellipse is filled using *color*

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1 or later

See also imagefilledarc().

imagefilledpolygon (PHP 3, PHP 4 >= 4.0.0)

Draw a filled polygon

int **imagefilledpolygon** (resource image, array points, int num_points, int col) \linebreak

imagefilledpolygon() creates a filled polygon in image *image*. *points* is a PHP array containing the polygon's vertices, ie. points[0] = x0, points[1] = y0, points[2] = x1, points[3] = y1, etc. *num_points* is the total number of vertices.

imagefilledrectangle (PHP 3, PHP 4 >= 4.0.0)

Draw a filled rectangle

int **imagefilledrectangle** (resource image, int x1, int y1, int x2, int y2, int col) \linebreak

imagefilledrectangle() creates a filled rectangle of color *col* in image *image* starting at upper left coordinates *x1*, *y1* and ending at bottom right coordinates *x2*, *y2*. 0, 0 is the top left corner of the image.

imagefilltoborder (PHP 3, PHP 4 >= 4.0.0)

Flood fill to specific color

int **imagefilltoborder** (resource image, int x, int y, int border, int col) \linebreak

imagefilltoborder() performs a flood fill whose border color is defined by *border*. The starting point for the fill is *x*, *y* (top left is 0, 0) and the region is filled with color *col*.

imagefontheight (PHP 3, PHP 4 >= 4.0.0)

Get font height

int **imagefontheight** (int font) \linebreak

Returns the pixel height of a character in the specified font.

See also `imagefontwidth()` and `imageloadfont()`.

imagefontwidth (PHP 3, PHP 4 >= 4.0.0)

Get font width

int **imagefontwidth** (int font) \linebreak

Returns the pixel width of a character in font.

See also `imagefontheight()` and `imageloadfont()`.

imageftbbox (PHP 4 >= 4.1.0)

Give the bounding box of a text using fonts via freetype2

array **imageftbbox** (int size, int angle, string font_file, string text [, array extrainfo]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imagefttext (PHP 4 >= 4.1.0)

Write text to the image using fonts using FreeType 2

array **imagefttext** (resource image, int size, int angle, int x, int y, int col, string font_file, string text [, array extrainfo]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imagegammacorrect (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Apply a gamma correction to a GD image

int **imagegammacorrect** (resource image, float inputgamma, float outputgamma) \linebreak

The **imagegammacorrect()** function applies gamma correction to a gd image stream (*image*) given an input gamma, the parameter *inputgamma* and an output gamma, the parameter *outputgamma*.

imagegd (PHP 4 >= 4.1.0)

Output GD image to browser or file

int **imagegd** (resource image [, string filename]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imagegd2 (PHP 4 >= 4.1.0)

Output GD2 image to browser or file

int **imagegd2** (resource image [, string filename]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imagegif (PHP 3, PHP 4 >= 4.0.0)

Output image to browser or file

int **imagegif** (resource image [, string filename]) \linebreak

imagegif() creates the GIF file in filename from the image *image*. The *image* argument is the return from the `imagecreate()` function.

The image format will be GIF87a unless the image has been made transparent with `imagecolortransparent()`, in which case the image format will be GIF89a.

The filename argument is optional, and if left off, the raw image stream will be output directly. By sending an image/gif content-type using `header()`, you can create a PHP script that outputs GIF images directly.

Poznámka: Since all GIF support was removed from the GD library in version 1.6, this function is not available if you are using that version of the GD library.

The following code snippet allows you to write more portable PHP applications by auto-detecting the type of GD support which is available. Replace the sequence `header ("Content-type: image/gif"); imagegif ($im);` by the more flexible sequence:

```
<?php
if (function_exists("imagegif")) {
    header ("Content-type: image/gif");
    imagegif ($im);
}
elseif (function_exists("imagejpeg")) {
    header ("Content-type: image/jpeg");
    imagejpeg ($im, "", 0.5);
}
elseif (function_exists("imagepng")) {
    header ("Content-type: image/png");
    imagepng ($im);
}
elseif (function_exists("imagewbmp")) {
    header ("Content-type: image/vnd.wap.wbmp");
    imagewbmp ($im);
}
else
    die("No image support in this PHP server");
```

?>

Poznámka: As of version 3.0.18 and 4.0.2 you can use the function `imagetypes()` in place of `function_exists()` for checking the presence of the various supported image formats:

```
if (imagetypes() & IMG_GIF) {
    header ("Content-type: image/gif");
    imagegif ($im);
}
elseif (imagetypes() & IMG_JPG) {
    ... etc.
```

See also `imagepng()`, `imagewbmp()`, `imagejpeg()`, `imagetypes()`.

imageinterlace (PHP 3, PHP 4 >= 4.0.0)

Enable or disable interlace

int **imageinterlace** (resource image [, int interlace]) \linebreak

imageinterlace() turns the interlace bit on or off. If interlace is 1 the image will be interlaced, and if interlace is 0 the interlace bit is turned off.

If the interlace bit is set and the image is used as a JPEG image, the image is created as a progressive JPEG.

This function returns whether the interlace bit is set for the image.

imagejpeg (PHP 3>= 3.0.16, PHP 4 >= 4.0.0)

Output image to browser or file

int **imagejpeg** (resource image [, string filename [, int quality]]) \linebreak

imagejpeg() creates the JPEG file in filename from the image *image*. The *image* argument is the return from the `imagecreate()` function.

The filename argument is optional, and if left off, the raw image stream will be output directly. To skip the filename argument in order to provide a quality argument just use an empty string (""). By

sending an image/jpeg content-type using header(), you can create a PHP script that outputs JPEG images directly.

Poznámka: JPEG support is only available if PHP was compiled against GD-1.8 or later.

quality is optional, and ranges from 0 (worst quality, smaller file) to 100 (best quality, biggest file). The default is the default IJG quality value (about 75).

If you want to output Progressive JPEGs, you need to set interlacing on with imageinterlace().

See also imagepng(), imagegif(), imagewbmp(), imageinterlace() and imagetypes().

imageLine (PHP 3, PHP 4 >= 4.0.0)

Draw a line

int **imageLine** (resource image, int x1, int y1, int x2, int y2, int col) \linebreak

imageLine() draws a line from *x1*, *y1* to *x2*, *y2* (top left is 0, 0) in image im of color *col*.

See also imagecreate() and imagecolorallocate().

imageLoadFont (PHP 3, PHP 4 >= 4.0.0)

Load a new font

int **imageLoadFont** (string file) \linebreak

imageLoadFont() loads a user-defined bitmap font and returns an identifier for the font (that is always greater than 5, so it will not conflict with the built-in fonts).

The font file format is currently binary and architecture dependent. This means you should generate the font files on the same type of CPU as the machine you are running PHP on.

Tabulka 1. Font file format

byte position	C data type	description
byte 0-3	int	number of characters in the font
byte 4-7	int	value of first character in the font (often 32 for space)
byte 8-11	int	pixel width of each character
byte 12-15	int	pixel height of each character
byte 16-	char	array with character data, one byte per pixel in each character, for a total of (nchars*width*height) bytes.

See also `imagefontwidth()` and `imagefontheight()`.

imagepalettecopy (PHP 4)

Copy the palette from one image to another

int imagepalettecopy (resource destination, resource source) \linebreak

imagepalettecopy() copies the palette from the *source* image to the *destination* image.

imagepng (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Output a PNG image to either the browser or a file

int imagepng (resource image [, string filename]) \linebreak

The **imagepng()** outputs a GD image stream (*image*) in PNG format to standard output (usually the browser) or, if a filename is given by the *filename* it outputs the image to the file.

```
<?php
$im = imagecreatefrompng ("test.png");
imagepng ($im);
?>
```

See also `imagegif()`, `imagewbmp()`, `imagejpeg()`, `imagetypes()`.

imagepolygon (PHP 3, PHP 4 >= 4.0.0)

Draw a polygon

int imagepolygon (resource image, array points, int num_points, int col) \linebreak

imagepolygon() creates a polygon in image id. *points* is a PHP array containing the polygon's vertices, ie. `points[0] = x0`, `points[1] = y0`, `points[2] = x1`, `points[3] = y1`, etc. *num_points* is the total number of vertices.

See also `imagecreate()`.

imagepsbbox (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Give the bounding box of a text rectangle using PostScript Type1 fonts

array **imagepsbbox** (string text, int font, int size [, int space [, int tightness [, float angle]]]) \linebreak

Size is expressed in pixels.

Space allows you to change the default value of a space in a font. This amount is added to the normal value and can also be negative.

Tightness allows you to control the amount of white space between characters. This amount is added to the normal character width and can also be negative.

Angle is in degrees.

Parameters *space* and *tightness* are expressed in character space units, where 1 unit is 1/1000th of an em-square.

Parameters *space*, *tightness*, and *angle* are optional.

The bounding box is calculated using information available from character metrics, and unfortunately tends to differ slightly from the results achieved by actually rasterizing the text. If the angle is 0 degrees, you can expect the text to need 1 pixel more to every direction.

This function returns an array containing the following elements:

0	lower left x-coordinate
1	lower left y-coordinate
2	upper right x-coordinate
3	upper right y-coordinate

See also `imagepstext()`.

ImagePSCopyFont (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Make a copy of an already loaded font for further modification

int **imagepscopyfont** (int fontindex) \linebreak

Use this function if you need make further modifications to the font, for example extending/condensing, slanting it or changing it's character encoding vector, but need to keep the original along as well. Note that the font you want to copy must be one obtained using **ImagePSLoadFont()**, not a font that is itself a copied one. You can although make modifications to it before copying.

If you use this function, you *must* free the fonts obtained this way yourself and in reverse order. Otherwise your script *will* hang.

In the case everything went right, a valid font index will be returned and can be used for further purposes. Otherwise the function returns `FALSE` and prints a message describing what went wrong.

See also **ImagePSLoadFont()**.

imagepsencodefont (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Change the character encoding vector of a font

```
int imagepsencodefont ( int font_index, string encodingfile) \linebreak
```

Loads a character encoding vector from from a file and changes the fonts encoding vector to it. As a PostScript fonts default vector lacks most of the character positions above 127, you'll definitely want to change this if you use an other language than english. The exact format of this file is described in T1libs documentation. T1lib comes with two ready-to-use files, IsoLatin1.enc and IsoLatin2.enc.

If you find yourself using this function all the time, a much better way to define the encoding is to set `ps.default_encoding` in the configuration file to point to the right encoding file and all fonts you load will automatically have the right encoding.

imagepsextendfont (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Extend or condense a font

```
bool imagepsextendfont ( int font_index, float extend) \linebreak
```

Extend or condense a font (*font_index*), if the value of the *extend* parameter is less than one you will be condensing the font.

imagepsfreefont (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Free memory used by a PostScript Type 1 font

```
void imagepsfreefont ( int fontindex) \linebreak
```

See also `imagepsloadfont()`.

imagepsloadfont (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Load a PostScript Type 1 font from file

```
int imagepsloadfont ( string filename) \linebreak
```

In the case everything went right, a valid font index will be returned and can be used for further purposes. Otherwise the function returns `FALSE` and prints a message describing what went wrong, which you cannot read directly, while the output type is image.

```
<?php
header ("Content-type: image/jpeg");
$im = imagecreate (350, 45);
$black = imagecolorallocate ($im, 0, 0, 0);
$white = imagecolorallocate ($im, 255, 255, 255);
$font = imagepsloadfont ("bchbi.pfb"); // or locate your .pfb files on your machine
```

```

imagepstext ($im, "Testing... It worked!", $font, 32, $white, $black, 32, 32);
imagepsfreefont ($font);
imagejpeg ($im, "", 100); //for best quality...your mileage may vary
imagedestroy ($im);
?>

```

See also `imagepsfreefont()`.

imagepslantfont (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Slant a font

bool **imagepslantfont** (int font_index, float slant) \linebreak

Slant a font given by the *font_index* parameter with a slant of the value of the *slant* parameter.

imagepstext (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

To draw a text string over an image using PostScript Type1 fonts

array **imagepstext** (resource image, string text, int font, int size, int foreground, int background, int x, int y
[, int space [, int tightness [, float angle [, int antialias_steps]]]]) \linebreak

Size is expressed in pixels.

Foreground is the color in which the text will be painted. *Background* is the color to which the text will try to fade in with antialiasing. No pixels with the color *background* are actually painted, so the background image does not need to be of solid color.

The coordinates given by *x*, *y* will define the origin (or reference point) of the first character (roughly the lower-left corner of the character). This is different from the `imagestring()`, where *x*, *y* define the upper-right corner of the first character. Refer to PostScript documentation about fonts and their measuring system if you have trouble understanding how this works.

Space allows you to change the default value of a space in a font. This amount is added to the normal value and can also be negative.

Tightness allows you to control the amount of white space between characters. This amount is added to the normal character width and can also be negative.

Angle is in degrees.

Antialias_steps allows you to control the number of colours used for antialiasing text. Allowed values are 4 and 16. The higher value is recommended for text sizes lower than 20, where the effect in text quality is quite visible. With bigger sizes, use 4. It's less computationally intensive.

Parameters *space* and *tightness* are expressed in character space units, where 1 unit is 1/1000th of an em-square.

Parameters *space*, *tightness*, *angle* and *antialias* are optional.

This function returns an array containing the following elements:

0	lower left x-coordinate
1	lower left y-coordinate
2	upper right x-coordinate
3	upper right y-coordinate

See also `imagepsbbox()`.

imagerectangle (PHP 3, PHP 4 >= 4.0.0)

Draw a rectangle

int **imagerectangle** (resource image, int x1, int y1, int x2, int y2, int col) \linebreak

imagerectangle() creates a rectangle of color `col` in image *image* starting at upper left coordinate `x1`, `y1` and ending at bottom right coordinate `x2`, `y2`. 0, 0 is the top left corner of the image.

imagesetbrush (PHP 4 >= 4.0.6)

Set the brush image for line drawing

int **imagesetbrush** (resource image, resource brush) \linebreak

imagesetbrush() sets the brush image to be used by all line drawing functions (such as `imageline()` and `imagepolygon()`) when drawing with the special colors `IMG_COLOR_BRUSHED` or `IMG_COLOR_STYLED BRUSHED`.

Poznámka: You need not take special action when you are finished with a brush, but if you destroy the brush image, you must not use the `IMG_COLOR_BRUSHED` or `IMG_COLOR_STYLED BRUSHED` colors until you have set a new brush image!

Poznámka: This function was added in PHP 4.0.6

imagesetpixel (PHP 3, PHP 4 >= 4.0.0)

Set a single pixel

int **imagesetpixel** (resource image, int x, int y, int col) \linebreak

imagesetpixel() draws a pixel at `x`, `y` (top left is 0, 0) in image *image* of color `col`.

See also `imagecreate()` and `imagecolorallocate()`.

void **imagesetthickness** (resource image, int thickness) \linebreak

imagesetthickness() sets the thickness of the lines drawn when drawing rectangles, polygons, ellipses etc. etc. to *thickness* pixels.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1 or later

imagesttile (PHP 4 >= 4.0.6)

Set the tile image for filling

int **imagesttile** (resource image, resource tile) \linebreak

imagesttile() sets the tile image to be used by all region filling functions (such as `imagefill()` and `imagefilledpolygon()`) when filling with the special color `IMG_COLOR_TILED`.

A tile is an image used to fill an area with a repeated pattern. *Any* GD image can be used as a tile, and by setting the transparent color index of the tile image with `imagecolortransparent()`, a tile allows certain parts of the underlying area to shine through can be created.

Poznámka: You need not take special action when you are finished with a tile, but if you destroy the tile image, you must not use the `IMG_COLOR_TILED` color until you have set a new tile image!

Poznámka: This function was added in PHP 4.0.6

imagestring (PHP 3, PHP 4 >= 4.0.0)

Draw a string horizontally

int **imagestring** (resource image, int font, int x, int y, string s, int col) \linebreak

imagestring() draws the string *s* in the image identified by *image* at coordinates *x*, *y* (top left is 0, 0) in color *col*. If font is 1, 2, 3, 4 or 5, a built-in font is used.

See also `imageloadfont()`.

imagestringup (PHP 3, PHP 4 >= 4.0.0)

Draw a string vertically

int **imagestringup** (resource image, int font, int x, int y, string s, int col) \linebreak

imagestringup() draws the string *s* vertically in the image identified by *image* at coordinates *x*, *y* (top left is 0, 0) in color *col*. If font is 1, 2, 3, 4 or 5, a built-in font is used.

See also `imageloadfont()`.

imagesx (PHP 3, PHP 4 >= 4.0.0)

Get image width

int **imagesx** (resource image) \linebreak

imagesx() returns the width of the image identified by *image*.

See also `imagecreate()` and `imagesy()`.

imagesy (PHP 3, PHP 4 >= 4.0.0)

Get image height

int **imagesy** (resource image) \linebreak

imagesy() returns the height of the image identified by *image*.

See also `imagecreate()` and `imagesx()`.

imagetruecolortopalette (PHP 4 >= 4.0.6)

Convert a true color image to a palette image

void **imagetruecolortopalette** (resource image, bool dither, int ncolors) \linebreak

imagetruecolortopalette() converts a truecolor image to a palette image. The code for this function was originally drawn from the Independent JPEG Group library code, which is excellent. The code has been modified to preserve as much alpha channel information as possible in the resulting palette, in addition to preserving colors as well as possible. This does not work as well as might be hoped. It is usually best to simply produce a truecolor output image instead, which guarantees the highest output quality.

dither indicates if the image should be dithered - if it is `TRUE` then dithering will be used which will result in a more speckled image but with better color approximation.

ncolors sets the maximum number of colors that should be retained in the palette.

Poznámka: This function was added in PHP 4.0.6 and requires GD 2.0.1 or later

imagettfbbox (PHP 3>= 3.0.1, PHP 4 >= 4.0.0)

Give the bounding box of a text using TrueType fonts

array **imagettfbbox** (int size, int angle, string fontfile, string text) \linebreak

This function calculates and returns the bounding box in pixels for a TrueType text.

text

The string to be measured.

size

The font size in pixels.

fontfile

The name of the TrueType font file. (Can also be an URL.) Depending on which version of the GD library that PHP is using, it may attempt to search for files that do not begin with a leading '/' by appending '.ttf' to the filename and searching along a library-defined font path.

angle

Angle in degrees in which *text* will be measured.

imagettfbbox() returns an array with 8 elements representing four points making the bounding box of the text:

0	lower left corner, X position
1	lower left corner, Y position
2	lower right corner, X position
3	lower right corner, Y position
4	upper right corner, X position
5	upper right corner, Y position
6	upper left corner, X position
7	upper left corner, Y position

The points are relative to the *text* regardless of the angle, so "upper left" means in the top left-hand corner seeing the text horizontally.

This function requires both the GD library and the FreeType library.

See also `imagettftext()`.

imagettftext (PHP 3, PHP 4 >= 4.0.0)

Write text to the image using TrueType fonts

array **imagettftext** (resource image, int size, int angle, int x, int y, int col, string fontfile, string text) \linebreak

imagettftext() draws the string *text* in the image identified by *image*, starting at coordinates *x*, *y* (top left is 0, 0), at an angle of *angle* in color *col*, using the TrueType font file identified by *fontfile*. Depending on which version of the GD library that PHP is using, when *fontfile* does not begin with a leading '/', '.ttf' will be appended to the filename and the the library will attempt to search for that filename along a library-defined font path.

The coordinates given by *x*, *y* will define the basepoint of the first character (roughly the lower-left corner of the character). This is different from the `imagestring()`, where *x*, *y* define the upper-right corner of the first character.

Angle is in degrees, with 0 degrees being left-to-right reading text (3 o'clock direction), and higher values representing a counter-clockwise rotation. (i.e., a value of 90 would result in bottom-to-top reading text).

Fontfile is the path to the TrueType font you wish to use.

Text is the text string which may include UTF-8 character sequences (of the form: `{`) to access characters in a font beyond the first 255.

Col is the color index. Using the negative of a color index has the effect of turning off antialiasing.

imagettftext() returns an array with 8 elements representing four points making the bounding box of the text. The order of the points is lower left, lower right, upper right, upper left. The points are relative to the text regardless of the angle, so "upper left" means in the top left-hand corner when you see the text horizontally.

This example script will produce a black GIF 400x30 pixels, with the words "Testing..." in white in the font Arial.

Příklad 1. imagettftext

```
<?php
header ("Content-type: image/gif");
$im = imagecreate (400, 30);
$black = imagecolorallocate ($im, 0, 0, 0);
$white = imagecolorallocate ($im, 255, 255, 255);
imagettftext ($im, 20, 0, 10, 20, $white, "/path/arial.ttf", "Testing...Omega: &#937;");
imagegif ($im);
imagedestroy ($im);
?>
```

This function requires both the GD library and the FreeType (<http://www.freetype.org/>) library.

See also `imagettfbbox()`.

imagetypes (PHP 3 CVS only, PHP 4 >= 4.0.2)

Return the image types supported by this PHP build

int imagetypes (void) \linebreak

This function returns a bit-field corresponding to the image formats supported by the version of GD linked into PHP. The following bits are returned, `IMG_GIF` | `IMG_JPG` | `IMG_PNG` | `IMG_WBMP`. To check for PNG support, for example, do this:

Příklad 1. imagetypes

```
<?php
if (imagetypes() & IMG_PNG) {
    echo "PNG Support is enabled";
}
?>
```

imagewbmp (PHP 3>= 3.0.15, PHP 4)

Output image to browser or file

int **imagewbmp** (resource image [, string filename [, int foreground]]) \linebreak

imagewbmp() creates the WBMP file in filename from the image *image*. The *image* argument is the return from the *imagecreate()* function.

The filename argument is optional, and if left off, the raw image stream will be output directly. By sending an image/vnd.wap.wbmp content-type using *header()*, you can create a PHP script that outputs WBMP images directly.

Poznámka: WBMP support is only available if PHP was compiled against GD-1.8 or later.

Using the optional *foreground* parameter, you can set the foreground color. Use an identifier obtained from *imagecolorallocate()*. The default foreground color is black.

See also *image2wbmp()*, *imagepng()*, *imagegif()*, *imagejpeg()*, *imagetypes()*.

iptcembed (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Embed binary IPTC data into a JPEG image

array **iptcembed** (string iptcdata, string jpeg_file_name [, int spool]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

jpeg2wbmp (PHP 4 >= 4.0.5)

Convert JPEG image file to WBMP image file

```
int jpeg2wbmp ( string jpegname, string wbmpname, int d_height, int d_width, int threshold) \linebreak
```

Converts the *jpegname* JPEG file to WBMP format, and saves it as *wbmpname*. With the *d_height* and *d_width* you specify the height and width of the destination image.

Poznámka: WBMP support is only available if PHP was compiled against GD-1.8 or later.

See also `png2wbmp()`.

png2wbmp (PHP 4 >= 4.0.5)

Convert PNG image file to WBMP image file

```
int png2wbmp ( string pngname, string wbmpname, int d_height, int d_width, int threshold) \linebreak
```

Converts the *pngname* PNG file to WBMP format, and saves it as *wbmpname*. With the *d_height* and *d_width* you specify the height and width of the destination image.

Poznámka: WBMP support is only available if PHP was compiled against GD-1.8 or later.

See also `jpeg2wbmp()`.

read_exif_data (PHP 4)

Reads header information stored in TIFF and JPEG images

```
array exif_read_data ( string filename, string sections, bool arrays, bool thumbnail) \linebreak
```

Poznámka: The `read_exif_data()` function is an alias for `exif_read_data()`.

See also `exif_thumbnail()`.

XLIII. IMAP, POP3 and NNTP functions

To get these functions to work, you have to compile PHP with `--with-imap`. That requires the `c-client` library to be installed. Grab the latest version from <ftp://ftp.cac.washington.edu/imap/> and compile it.

Then copy `c-client/c-client.a` to `/usr/local/lib/libc-client.a` or some other directory on your link path and copy `c-client/*.h` to `/usr/local/include` or some other directory in your include path.

Poznámka: Depending how the `c-client` was configured, you might also need to add `--with-imap-ssl=/path/to/openssl/` and/or `--with-kerberos` into the PHP configure line.

Note that these functions are not limited to the IMAP protocol, despite their name. The underlying `c-client` library also supports NNTP, POP3 and local mailbox access methods.

This document can't go into detail on all the topics touched by the provided functions. Further information is provided by the documentation of the `c-client` library source (`docs/internal.txt`) and the following RFC documents:

- RFC2821 (<http://www.faqs.org/rfcs/rfc2821.html>): Simple Mail Transfer Protocol (SMTP).
- RFC2822 (<http://www.faqs.org/rfcs/rfc2822.html>): Standard for ARPA internet text messages.
- RFC2060 (<http://www.faqs.org/rfcs/rfc2060.html>): Internet Message Access Protocol (IMAP) Version 4rev1.
- RFC1939 (<http://www.faqs.org/rfcs/rfc1939.html>): Post Office Protocol Version 3 (POP3).
- RFC977 (<http://www.faqs.org/rfcs/rfc977.html>): Network News Transfer Protocol (NNTP).
- RFC2076 (<http://www.faqs.org/rfcs/rfc2076.html>): Common Internet Message Headers.
- RFC2045 (<http://www.faqs.org/rfcs/rfc2045.html>) , RFC2046 (<http://www.faqs.org/rfcs/rfc2046.html>) , RFC2047 (<http://www.faqs.org/rfcs/rfc2047.html>) , RFC2048 (<http://www.faqs.org/rfcs/rfc2048.html>) & RFC2049 (<http://www.faqs.org/rfcs/rfc2049.html>): Multipurpose Internet Mail Extensions (MIME).

A detailed overview is also available in the books *Programming Internet Email* (<http://www.oreilly.com/catalog/progintemail/noframes.html>) by David Wood and *Managing IMAP* (<http://www.oreilly.com/catalog/mimap/noframes.html>) by Dianna Mullet & Kevin Mullet.

imap_8bit (PHP 3, PHP 4 >= 4.0.0)

Convert an 8bit string to a quoted-printable string

string **imap_8bit** (string string) \linebreak

Convert an 8bit string to a quoted-printable string (according to RFC2045 (<http://www.faqs.org/rfcs/rfc2045.html>), section 6.7).

Returns a quoted-printable string.

See also `imap_qprint()`.

imap_alerts (PHP 3 >= 3.0.12, PHP 4 >= 4.0.0)

This function returns all IMAP alert messages (if any) that have occurred during this page request or since the alert stack was reset

array **imap_alerts** (void) \linebreak

This function returns an array of all of the IMAP alert messages generated since the last **imap_alerts()** call, or the beginning of the page. When **imap_alerts()** is called, the alert stack is subsequently cleared. The IMAP specification requires that these messages be passed to the user.

imap_append (PHP 3, PHP 4 >= 4.0.0)

Append a string message to a specified mailbox

int **imap_append** (int imap_stream, string mbox, string message [, string flags]) \linebreak

Returns `TRUE` on success, `FALSE` on error.

imap_append() appends a string message to the specified mailbox *mbox*. If the optional *flags* is specified, writes the *flags* to that mailbox also.

When talking to the Cyrus IMAP server, you must use `"\r\n"` as your end-of-line terminator instead of `"\n"` or the operation will fail.

Příklad 1. imap_append() example

```
$stream = imap_open("{your.imap.host}INBOX.Drafts", "username", "password");

$check = imap_check($stream);
print "Msg Count before append: ". $check->Nmsgs."\n";

imap_append($stream, "{your.imap.host}INBOX.Drafts"
    , "From: me@my.host\r\n"
    . "To: you@your.host\r\n"
    . "Subject: test\r\n"
    . "\r\n"
    . "this is a test message, please ignore\r\n"
```

```

    );

    $check = imap_check($stream);
    print "Msg Count after append : ". $check->Nmsgs."\n";

    imap_close($stream);

```

imap_base64 (PHP 3, PHP 4 >= 4.0.0)

Decode BASE64 encoded text

string **imap_base64** (string text) \linebreak

imap_base64() function decodes BASE-64 encoded text (see RFC2045 (<http://www.faqs.org/rfcs/rfc2045.html>), Section 6.8). The decoded message is returned as a string.

See also `imap_binary()`.

imap_binary (PHP 3 >= 3.0.2, PHP 4 >= 4.0.0)

Convert an 8bit string to a base64 string

string **imap_binary** (string string) \linebreak

Convert an 8bit string to a base64 string (according to RFC2045 (<http://www.faqs.org/rfcs/rfc2045.html>), Section 6.8).

Returns a base64 string.

See also `imap_base64()`.

imap_body (PHP 3, PHP 4 >= 4.0.0)

Read the message body

string **imap_body** (int imap_stream, int msg_number [, int flags]) \linebreak

imap_body() returns the body of the message, numbered *msg_number* in the current mailbox. The optional *flags* are a bit mask with one or more of the following:

- FT_UID - The *msgno* is a UID
- FT_PEEK - Do not set the \Seen flag if not already set
- FT_INTERNAL - The return string is in internal format, will not canonicalize to CRLF.

imap_body() will only return a verbatim copy of the message body. To extract single parts of a multipart MIME-encoded message you have to use **imap_fetchstructure()** to analyze its structure and **imap_fetchbody()** to extract a copy of a single body component.

imap_bodysttruct (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Read the structure of a specified body section of a specific message

object **imap_bodysttruct** (int stream_id, int msg_no, int section) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imap_check (PHP 3, PHP 4 >= 4.0.0)

Check current mailbox

object **imap_check** (int imap_stream) \linebreak

Returns information about the current mailbox. Returns `FALSE` on failure.

The **imap_check()** function checks the current mailbox status on the server and returns the information in an object with following properties:

- Date - last change of mailbox contents
- Driver - protocol used to access this mailbox: POP3, IMAP, NNTP
- Mailbox - the mailbox name
- Nmsgs - number of messages in the mailbox
- Recent - number of recent messages in the mailbox

imap_clearflag_full (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Clears flags on messages

string **imap_clearflag_full** (int stream, string sequence, string flag, string options) \linebreak

This function causes a store to delete the specified flag to the flags set for the messages in the specified sequence. The flags which you can unset are "\\Seen", "\\Answered", "\\Flagged", "\\Deleted", "\\Draft", and "\\Recent" (as defined by RFC2060).

The options are a bit mask with one or more of the following:

ST_UID The sequence argument contains UIDs instead of
sequence numbers

imap_close (PHP 3, PHP 4 >= 4.0.0)

Close an IMAP stream

```
int imap_close ( int imap_stream [, int flags]) \linebreak
```

Close the imap stream. Takes an optional *flag* **CL_EXPUNGE**, which will silently expunge the mailbox before closing, removing all messages marked for deletion.

imap_createmailbox (PHP 3, PHP 4 >= 4.0.0)

Create a new mailbox

```
int imap_createmailbox ( int imap_stream, string mbox) \linebreak
```

imap_createmailbox() creates a new mailbox specified by *mbox*. Names containing international characters should be encoded by `imap_utf7_encode()`

Returns **TRUE** on success and **FALSE** on error.

See also `imap_renamemailbox()`, `imap_deletemailbox()` and `imap_open()` for the format of *mbox* names.

Příklad 1. imap_createmailbox() example

```
$mbox = imap_open("{your.imap.host}", "username", "password", OP_HALFOPEN)
    or die("can't connect: ".imap_last_error());

$name1 = "phpnewbox";
$name2 = imap_utf7_encode("phpnew&ouml;x");

$newname = $name1;

echo "Newname will be '$name1'<br>\n";

# we will now create a new mailbox "phptestbox" in your inbox folder,
# check its status after creation and finally remove it to restore
# your inbox to its initial state
if(@imap_createmailbox($mbox,imap_utf7_encode("{your.imap.host}INBOX.$newname")) {
    $status = @imap_status($mbox,"{your.imap.host}INBOX.$newname", SA_ALL);
    if($status) {
        print("your new mailbox '$name1' has the following status:<br>\n");
        print("Messages:    ". $status->messages    )."<br>\n";
```

```

print("Recent:      ". $status->recent      )."<br>\n";
print("Unseen:      ". $status->unseen      )."<br>\n";
print("UIDnext:     ". $status->uidnext     )."<br>\n";
print("UIDvalidity:". $status->uidvalidity)."<br>\n";

if(imap_renamemailbox($mbox,"{your.imap.host}INBOX.$newname","{your.imap.host}INBOX.$name1") {
    echo "renamed new mailbox from '$name1' to '$name2'<br>\n";
    $newname=$name2;
} else {
    print "imap_renamemailbox on new mailbox failed: ".imap_last_error()."<br>\n";
}
} else {
    print "imap_status on new mailbox failed: ".imap_last_error()."<br>\n";
}
}
if(@imap_deletemailbox($mbox,"{your.imap.host}INBOX.$newname")) {
    print "new mailbox removed to restore initial state<br>\n";
} else {
    print "imap_deletemailbox on new mailbox failed: ".implode("<br>\n",imap_errors())."<br>\n";
}

} else {
    print "could not create new mailbox: ".implode("<br>\n",imap_errors())."<br>\n";
}

imap_close($mbox);

```

imap_delete (PHP 3, PHP 4 >= 4.0.0)

Mark a message for deletion from current mailbox

int **imap_delete** (int imap_stream, int msg_number [, int flags]) \linebreak

Returns TRUE.

imap_delete() marks messages listed in *msg_number* for deletion. The optional *flags* parameter only has a single option, *FT_UID*, which tells the function to treat the *msg_number* argument as a *UID*. Messages marked for deletion will stay in the mailbox until either *imap_expunge()* is called or *imap_close()* is called with the optional parameter *CL_EXPUNGE*.

Poznámka: POP3 mailboxes do not have their message flags saved between connections, so *imap_expunge()* must be called during the same connection in order for messages marked for deletion to actually be purged.

Příklad 1. imap_delete() Beispiel

```

$mbx = imap_open ("{your.imap.host}INBOX", "username", "password")
    or die ("can't connect: " . imap_last_error());

$check = imap_mailboxmsginfo ($mbx);
print "Messages before delete: " . $check->Nmsgs . "<br>\n" ;
imap_delete ($mbx, 1);
$check = imap_mailboxmsginfo ($mbx);
print "Messages after delete: " . $check->Nmsgs . "<br>\n" ;
imap_expunge ($mbx);
$check = imap_mailboxmsginfo ($mbx);
print "Messages after expunge: " . $check->Nmsgs . "<br>\n" ;
imap_close ($mbx);

```

imap_deletemailbox (PHP 3, PHP 4 >= 4.0.0)

Delete a mailbox

int **imap_deletemailbox** (int imap_stream, string mbox) \linebreak

imap_deletemailbox() deletes the specified mailbox (see `imap_open()` for the format of *mbox* names).

Returns `TRUE` on success and `FALSE` on error.

See also `imap_createmailbox()`, `imap_renamemailbox()`, and `imap_open()` for the format of *mbox*.

imap_errors (PHP 3 >= 3.0.12, PHP 4 >= 4.0.0)

This function returns all of the IMAP errors (if any) that have occurred during this page request or since the error stack was reset.

array **imap_errors** (void) \linebreak

This function returns an array of all of the IMAP error messages generated since the last **imap_errors()** call, or the beginning of the page. When **imap_errors()** is called, the error stack is subsequently cleared.

imap_expunge (PHP 3, PHP 4 >= 4.0.0)

Delete all messages marked for deletion

int **imap_expunge** (int imap_stream) \linebreak

imap_expunge() deletes all the messages marked for deletion by `imap_delete()`, `imap_mail_move()`, or `imap_setflag_full()`.

Returns `TRUE`.

imap_fetch_overview (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Read an overview of the information in the headers of the given message

array **imap_fetch_overview** (int *imap_stream*, string *sequence* [, int *flags*]) \linebreak

This function fetches mail headers for the given *sequence* and returns an overview of their contents. *sequence* will contain a sequence of message indices or UIDs, if *flags* contains `FT_UID`. The returned value is an array of objects describing one message header each:

- `subject` - the messages subject
- `from` - who sent it
- `date` - when was it sent
- `message_id` - Message-ID
- `references` - is a reference to this message id
- `size` - size in bytes
- `uid` - UID the message has in the mailbox
- `msgno` - message sequence number in the mailbox
- `recent` - this message is flagged as recent
- `flagged` - this message is flagged
- `answered` - this message is flagged as answered
- `deleted` - this message is flagged for deletion
- `seen` - this message is flagged as already read
- `draft` - this message is flagged as being a draft

Příklad 1. imap_fetch_overview() example

```
$mbox = imap_open("{your.imap.host:143}", "username", "password")
    or die("can't connect: ".imap_last_error());

$overview = imap_fetch_overview($mbox, "2,4:6", 0);

if(is_array($overview)) {
    reset($overview);
    while( list($key,$val) = each($overview)) {
        print    $val->msgno
        . " - " . $val->date
        . " - " . $val->subject
        . "\n";
    }
}
```

```

}

imap_close($mbox);

```

imap_fetchbody (PHP 3, PHP 4 >= 4.0.0)

Fetch a particular section of the body of the message

string **imap_fetchbody** (int imap_stream, int msg_number, string part_number [, flags flags]) \linebreak

This function causes a fetch of a particular section of the body of the specified messages as a text string and returns that text string. The section specification is a string of integers delimited by period which index into a body part list as per the IMAP4 specification. Body parts are not decoded by this function.

The options for **imap_fetchbody()** is a bitmask with one or more of the following:

- FT_UID - The *msg_number* is a UID
- FT_PEEK - Do not set the \Seen flag if not already set
- FT_INTERNAL - The return string is in "internal" format, without any attempt to canonicalize CRLF.

See also: `imap_fetchstructure()`.

imap_fetchheader (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Returns header for a message

string **imap_fetchheader** (int imap_stream, int msgno, int flags) \linebreak

This function causes a fetch of the complete, unfiltered RFC2822 (<http://www.faqs.org/rfcs/rfc2822.html>) format header of the specified message as a text string and returns that text string.

The options are:

FT_UID The msgno argument is a UID

FT_INTERNAL The return string is in "internal" format,
without any attempt to canonicalize to CRLF
newlines

FT_PREFETCHTEXT The RFC822.TEXT should be pre-fetched at the
same time. This avoids an extra RTT on an
IMAP connection if a full message text is
desired (e.g. in a "save to local file"
operation)

imap_fetchstructure (PHP 3, PHP 4 >= 4.0.0)

Read the structure of a particular message

object **imap_fetchstructure** (int imap_stream, int msg_number [, int flags]) \linebreak

This function fetches all the structured information for a given message. The optional *flags* parameter only has a single option, *FT_UID*, which tells the function to treat the *msg_number* argument as a *UID*. The returned object includes the envelope, internal date, size, flags and body structure along with a similar object for each mime attachment. The structure of the returned objects is as follows:

Tabulka 1. Returned Objects for imap_fetchstructure()

type	Primary body type
encoding	Body transfer encoding
ifsubtype	TRUE if there is a subtype string
subtype	MIME subtype
ifdescription	TRUE if there is a description string
description	Content description string
ifid	TRUE if there is an identification string
id	Identification string
lines	Number of lines
bytes	Number of bytes
ifdisposition	TRUE if there is a disposition string
disposition	Disposition string
ifdparameters	TRUE if the dparameters array exists
dparameters	An array of objects where each object has an "attribute" and a "value" property corresponding to the parameters on the Content-disposition MIMEheader.
ifparameters	TRUE if the parameters array exists
parameters	An array of objects where each object has an "attribute" and a "value" property.
parts	An array of objects identical in structure to the top-level object, each of which corresponds to a MIME body part.

Tabulka 2. Primary body type

0	text
1	multipart
2	message
3	application
4	audio
5	image
6	video
7	other

Tabulka 3. Transfer encodings

0	7BIT
1	8BIT
2	BINARY
3	BASE64
4	QUOTED-PRINTABLE
5	OTHER

See also: `imap_fetchbody()`.

imap_get_quota (PHP 4 >= 4.0.5)

Retrieve the quota level settings, and usage statics per mailbox

array **imap_get_quota** (int *imap_stream*, string *quota_root*) \linebreak

Returns an array with integer values limit and usage for the given mailbox. The value of limit represents the total amount of space allowed for this mailbox. The usage value represents the mailboxes current level of capacity. Will return `FALSE` in the case of failure.

This function is currently only available to users of the c-client2000 library.

imap_stream should be the value returned from an `imap_status()` call. This stream is required to be opened as the mail admin user for the quota function to work. *quota_root* should normally be in the form of `user.name` where name is the mailbox you wish to retrieve information about.

Příklad 1. `imap_get_quota()` example

```
$mbox = imap_open("{your.imap.host}", "mailadmin", "password", OP_HALFOPEN)
    or die("can't connect: ".imap_last_error());

$quota_value = imap_get_quota($mbox, "user.kalowsky");
if(is_array($quota_value)) {
```



```

        print "Usage level is: " . $quota_value['usage'];
        print "Limit level is: " . $quota_value['limit'];
    }

    imap_close($mbox);

```

See also `imap_open()`, `imap_set_quota()`.

imap_getmailboxes (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Read the list of mailboxes, returning detailed information on each one

array **imap_getmailboxes** (int `imap_stream`, string `ref`, string `pattern`) \linebreak

Returns an array of objects containing mailbox information. Each object has the attributes *name*, specifying the full name of the mailbox; *delimiter*, which is the hierarchy delimiter for the part of the hierarchy this mailbox is in; and *attributes*. *Attributes* is a bitmask that can be tested against:

- LATT_NOINFERIORS - This mailbox has no "children" (there are no mailboxes below this one).
- LATT_NOSELECT - This is only a container, not a mailbox - you cannot open it.
- LATT_MARKED - This mailbox is marked. Only used by UW-IMAPD.
- LATT_UNMARKED - This mailbox is not marked. Only used by UW-IMAPD.

Mailbox names containing international Characters outside the printable ASCII range will be encoded and may be decoded by `imap_utf7_decode()`.

ref should normally be just the server specification as described in `imap_open()`, and *pattern* specifies where in the mailbox hierarchy to start searching. If you want all mailboxes, pass '*' for *pattern*.

There are two special characters you can pass as part of the *pattern*: '%' and '%*'. '%' means to return all mailboxes. If you pass *pattern* as '%*', you will get a list of the entire mailbox hierarchy. '%' means to return the current level only. '%' as the *pattern* parameter will return only the top level mailboxes; '~/' on UW-IMAPD will return every mailbox in the ~/mail directory, but none in subfolders of that directory.

Příklad 1. imap_getmailboxes() example

```

$mbox = imap_open("{your.imap.host}", "username", "password", OP_HALFOPEN)
        or die("can't connect: ".imap_last_error());

$list = imap_getmailboxes($mbox, "{your.imap.host}", "%*");
if (is_array($list)) {
    reset($list);
    while (list($key, $val) = each($list))
    {

```

```

        print "($key) ";
        print imap_utf7_decode($val->name).", ";
        print "'".$val->delimiter."' , ";
        print $val->attributes."<br>\n";
    }
} else
    print "imap_getmailboxes failed: ".imap_last_error()."\n";

imap_close($mbox);

```

See also `imap_getsubscribed()`.

imap_getsubscribed (PHP 3 >= 3.0.12, PHP 4 >= 4.0.0)

List all the subscribed mailboxes

array **imap_getsubscribed** (int imap_stream, string ref, string pattern) \linebreak

This function is identical to `imap_getmailboxes()`, except that it only returns mailboxes that the user is subscribed to.

imap_header (PHP 3, PHP 4 >= 4.0.0)

Read the header of the message

object **imap_header** (int imap_stream, int msg_number [, int fromlength [, int subjectlength [, string defaulthost]]) \linebreak

This is an alias to `imap_headerinfo()` and is identical to this in any way.

imap_headerinfo (PHP 3, PHP 4 >= 4.0.0)

Read the header of the message

object **imap_headerinfo** (int imap_stream, int msg_number [, int fromlength [, int subjectlength [, string defaulthost]]) \linebreak

This function returns an object of various header elements.

remail, date, Date, subject, Subject, in_reply_to, message_id,
newsgroups, followup_to, references

message flags:

Recent - 'R' if recent and seen,

```

    'N' if recent and not seen,
    ' ' if not recent
Unseen - 'U' if not seen AND not recent,
    ' ' if seen OR not seen and recent
Answered - 'A' if answered,
    ' ' if unanswered
Deleted - 'D' if deleted,
    ' ' if not deleted
Draft - 'X' if draft,
    ' ' if not draft
Flagged - 'F' if flagged,
    ' ' if not flagged

```

NOTE that the Recent/Unseen behavior is a little odd. If you want to know if a message is Unseen, you must check for

```
Unseen == 'U' || Recent == 'N'
```

toaddress (full to: line, up to 1024 characters)

to[] (returns an array of objects from the To line, containing):

```

personal
adl
mailbox
host

```

fromaddress (full from: line, up to 1024 characters)

from[] (returns an array of objects from the From line, containing):

```

personal
adl
mailbox
host

```

ccaddress (full cc: line, up to 1024 characters)

cc[] (returns an array of objects from the Cc line, containing):

```

personal
adl
mailbox
host

```

bccaddress (full bcc line, up to 1024 characters)

bcc[] (returns an array of objects from the Bcc line, containing):

```

personal
adl
mailbox
host

```

reply_toaddress (full reply_to: line, up to 1024 characters)

reply_to[] (returns an array of objects from the Reply_to line, containing):

```

personal

```

adl
mailbox
host

senderaddress (full sender: line, up to 1024 characters)
sender[] (returns an array of objects from the sender line, containing):
personal
adl
mailbox
host

return_path (full return-path: line, up to 1024 characters)
return_path[] (returns an array of objects from the return_path line, containing):
personal
adl
mailbox
host

update (mail message date in unix time)

fetchfrom (from line formatted to fit *fromlength* characters)

fetchsubject (subject line formatted to fit *subjectlength* characters)

imap_headers (PHP 3, PHP 4 >= 4.0.0)

Returns headers for all messages in a mailbox

array **imap_headers** (int imap_stream) \linebreak

Returns an array of string formatted with header info. One element per mail message.

imap_last_error (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

This function returns the last IMAP error (if any) that occurred during this page request

string **imap_last_error** (void) \linebreak

This function returns the full text of the last IMAP error message that occurred on the current page. The error stack is untouched; calling **imap_last_error()** subsequently, with no intervening errors, will return the same error.

imap_listmailbox (PHP 3, PHP 4 >= 4.0.0)

Read the list of mailboxes

array **imap_listmailbox** (int imap_stream, string ref, string pattern) \linebreak

Returns an array containing the names of the mailboxes. See `imap_getmailboxes()` for a description of *ref* and *pattern*.

Příklad 1. imap_listmailbox() example

```
$mbox = imap_open("{your.imap.host}", "username", "password", OP_HALFOPEN)
    or die("can't connect: ".imap_last_error());

$list = imap_listmailbox($mbox, "{your.imap.host}", "*");
if(is_array($list)) {
    reset($list);
    while (list($key, $val) = each($list))
        print imap_utf7_decode($val). "<br>\n";
} else
    print "imap_listmailbox failed: ".imap_last_error(). "\n";

imap_close($mbox);
```

imap_listsubscribed (PHP 3, PHP 4 >= 4.0.0)

List all the subscribed mailboxes

array **imap_listsubscribed** (int imap_stream, string ref, string pattern) \linebreak

Returns an array of all the mailboxes that you have subscribed. This is almost identical to `imap_listmailbox()`, but will only return mailboxes the user you logged in as has subscribed.

imap_mail (PHP 3 >= 3.0.14, PHP 4 >= 4.0.0)

Send an email message

string **imap_mail** (string to, string subject, string message [, string additional_headers [, string cc [, string bcc [, string rpath]]]]) \linebreak

This function allows sending of emails with correct handling of Cc and Bcc receivers. The parameters to, cc and bcc are all strings and are all parsed as rfc822 address lists. The receivers specified in bcc will get the mail, but are excluded from the headers. Use the rpath parameter to specify return path. This is useful when using php as a mail client for multiple users.

imap_mail_compose (PHP 3 >= 3.0.5, PHP 4 >= 4.0.0)

Create a MIME message based on given envelope and body sections

string **imap_mail_compose** (array envelope, array body) \linebreak

Příklad 1. imap_mail_compose() example

```
<?php

$envelope["from"]="musone@afterfive.com";
$envelope["to"]="musone@darkstar";
$envelope["cc"]="musone@edgeglobal.com";

$part1["type"]=TYPEMULTIPART;
$part1["subtype"]="mixed";

$filename="/tmp/imap.c.gz";
$fp=fopen($filename,"r");
$contents=fread($fp,filesize($filename));
fclose($fp);

$part2["type"]=TYPEAPPLICATION;
$part2["encoding"]=ENCBINARAY;
$part2["subtype"]="octet-stream";
$part2["description"]=basename($filename);
$part2["contents.data"]=$contents;

$part3["type"]=TYPETEXT;
$part3["subtype"]="plain";
$part3["description"]="description3";
$part3["contents.data"]="contents.data3\n\n\n\t";

$body[1]=$part1;
$body[2]=$part2;
$body[3]=$part3;

echo nl2br(imap_mail_compose($envelope,$body));

?>
```

imap_mail_copy (PHP 3, PHP 4 >= 4.0.0)

Copy specified messages to a mailbox

int **imap_mail_copy** (int imap_stream, string msglist, string mbox [, int flags]) \linebreak

Returns TRUE on success and FALSE on error.

Copies mail messages specified by *msglist* to specified mailbox. *msglist* is a range not just message numbers (as described in RFC2060 (<http://www.faqs.org/rfcs/rfc2060.html>)).

Flags is a bitmask of one or more of

- CP_UID - the sequence numbers contain UIDS
- CP_MOVE - Delete the messages from the current mailbox after copying

imap_mail_move (PHP 3, PHP 4 >= 4.0.0)

Move specified messages to a mailbox

int **imap_mail_move** (int imap_stream, string msglist, string mbox [, int flags]) \linebreak

Moves mail messages specified by *msglist* to specified mailbox. *msglist* is a range not just message numbers (as described in RFC2060 (<http://www.faqs.org/rfcs/rfc2060.html>)).

Flags is a bitmask and may contain the single option

- CP_UID - the sequence numbers contain UIDS

Returns TRUE on success and FALSE on error.

imap_mailboxmsginfo (PHP 3 >= 3.0.2, PHP 4 >= 4.0.0)

Get information about the current mailbox

object **imap_mailboxmsginfo** (int imap_stream) \linebreak

Returns information about the current mailbox. Returns FALSE on failure.

The **imap_mailboxmsginfo()** function checks the current mailbox status on the server. It is similar to **imap_status()**, but will additionally sum up the size of all messages in the mailbox, which will take some additional time to execute. It returns the information in an object with following properties.

Tabulka 1. Mailbox properties

Date	date of last change
Driver	driver
Mailbox	name of the mailbox
Nmsgs	number of messages
Recent	number of recent messages
Unread	number of unread messages
Deleted	number of deleted messages
Size	mailbox size

Příklad 1. imap_mailboxmsginfo() example

```

<?php

$mbx = imap_open("{your.imap.host}INBOX","username", "password")
    or die("can't connect: ".imap_last_error());

$check = imap_mailboxmsginfo($mbx);

if($check) {
    print "Date: "      . $check->Date      . "<br>\n" ;
    print "Driver: "    . $check->Driver    . "<br>\n" ;
    print "Mailbox: "   . $check->Mailbox   . "<br>\n" ;
    print "Messages: " . $check->Nmsgs     . "<br>\n" ;
    print "Recent: "    . $check->Recent    . "<br>\n" ;
    print "Unread: "    . $check->Unread    . "<br>\n" ;
    print "Deleted: "   . $check->Deleted   . "<br>\n" ;
    print "Size: "      . $check->Size      . "<br>\n" ;
} else {
    print "imap_check() failed: ".imap_last_error(). "<br>\n";
}

imap_close($mbx);

?>

```

imap_mime_header_decode (PHP 3 >= 3.0.17, PHP 4 >= 4.0.0)

Decode MIME header elements

array **imap_mime_header_decode** (string text) \linebreak

imap_mime_header_decode() function decodes MIME message header extensions that are non ASCII text (see RFC2047 (<http://www.faqs.org/rfcs/rfc2047.html>)) The decoded elements are returned in an array of objects, where each object has two properties, "charset" & "text". If the element hasn't been encoded, and in other words is in plain US-ASCII, the "charset" property of that element is set to "default".

Příklad 1. imap_mime_header_decode() example

```

$text="=?ISO-8859-1?Q?Keld_J=F8rn_Simonsen?= <keld@dkuug.dk>";

$elements=imap_mime_header_decode($text);
for($i=0;$i<count($elements);$i++) {
    echo "Charset: {$elements[$i]->charset}\n";
}

```



```

        echo "Text: {$elements[$i]->text}\n\n";
    }

```

In the above example we would have two elements, whereas the first element had previously been encoded with ISO-8859-1, and the second element would be plain US-ASCII.

imap_msgno (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

This function returns the message sequence number for the given UID

```
int imap_msgno ( int imap_stream, int uid) \linebreak
```

This function returns the message sequence number for the given UID. It is the inverse of `imap_uid()`.

imap_num_msg (PHP 3, PHP 4 >= 4.0.0)

Gives the number of messages in the current mailbox

```
int imap_num_msg ( int imap_stream) \linebreak
```

Return the number of messages in the current mailbox.

See also: `imap_num_recent()` and `imap_status()`.

imap_num_recent (PHP 3, PHP 4 >= 4.0.0)

Gives the number of recent messages in current mailbox

```
int imap_num_recent ( int imap_stream) \linebreak
```

Returns the number of recent messages in the current mailbox.

See also: `imap_num_msg()` and `imap_status()`.

imap_open (PHP 3, PHP 4 >= 4.0.0)

Open an IMAP stream to a mailbox

```
int imap_open ( string mailbox, string username, string password [, int flags]) \linebreak
```

Returns an IMAP stream on success and `FALSE` on error. This function can also be used to open streams to POP3 and NNTP servers, but some functions and features are only available on IMAP servers.

A mailbox name consists of a server part and a mailbox path on this server. The special name INBOX stands for the current users personal mailbox. The server part, which is enclosed in '{' and '}', consists of the servers name or ip address, an optional port (prefixed by ':'), and an optional protocol specification (prefixed by '/'). The server part is mandatory in all mailbox parameters. Mailbox names that contain international characters besides those in the printable ASCII space have to be encoded with `imap_utf7_encode()`.

The options are a bit mask with one or more of the following:

- `OP_READONLY` - Open mailbox read-only
- `OP_ANONYMOUS` - Dont use or update a `.newsrc` for news (NNTP only)
- `OP_HALFOPEN` - For IMAP and NNTP names, open a connection but dont open a mailbox
- `CL_EXPUNGE` - Expunge mailbox automatically upon mailbox close

To connect to an IMAP server running on port 143 on the local machine, do the following:

```
$mbox = imap_open ("{localhost:143}INBOX", "user_id", "password");
```

To connect to a POP3 server on port 110 on the local server, use:

```
$mbox = imap_open ("{localhost:110/pop3}INBOX", "user_id", "password");
```

To connect to an SSL IMAP or POP3 server, add `/ssl` after the protocol specification:

```
$mbox = imap_open ("{localhost:993/imap/ssl}INBOX", "user_id", "password");
```

To connect to an SSL IMAP or POP3 server with a self-signed certificate, add `/ssl/novalidate-cert` after the protocol specification:

```
$mbox = imap_open ("{localhost:995/pop3/ssl/novalidate-cert}", "user_id", "password");
```

To connect to an NNTP server on port 119 on the local server, use:

```
$nntp = imap_open ("{localhost:119/nntp}comp.test", "", "");
```

To connect to a remote server replace "localhost" with the name or the IP address of the server you want to connect to.

Příklad 1. `imap_open()` example

```
$mbox = imap_open ("{your.imap.host:143}", "username", "password");

echo "<p><h1>Mailboxes</h1>\n";
$folders = imap_listmailbox ($mbox, "{your.imap.host:143}", "*");

if ($folders == false) {
    echo "Call failed<br>\n";
} else {
    while (list ($key, $val) = each ($folders)) {
        echo $val."<br>\n";
    }
}

echo "<p><h1>Headers in INBOX</h1>\n";
$headers = imap_headers ($mbox);

if ($headers == false) {
    echo "Call failed<br>\n";
} else {
    while (list ($key,$val) = each ($headers)) {
        echo $val."<br>\n";
    }
}

imap_close($mbox);
```

imap_ping (PHP 3, PHP 4 >= 4.0.0)

Check if the IMAP stream is still active

int **imap_ping** (int imap_stream) \linebreak

Returns `TRUE` if the stream is still alive, `FALSE` otherwise.

imap_ping() function pings the stream to see it is still active. It may discover new mail; this is the preferred method for a periodic "new mail check" as well as a "keep alive" for servers which have inactivity timeout. (As PHP scripts do not tend to run that long, i can hardly imagine that this function will be usefull to anyone.)

imap_popen (PHP 3 >= 3.0.12, PHP 4 >= 4.0.0)

Open a persistent IMAP stream to a mailbox

int **imap_popen** (string mailbox, string user, string password [, int options]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imap_qprint (PHP 3, PHP 4 >= 4.0.0)

Convert a quoted-printable string to an 8 bit string

string **imap_qprint** (string string) \linebreak

Convert a quoted-printable string to an 8 bit string (according to RFC2045 (<http://www.faqs.org/rfcs/rfc2045.html>), section 6.7).

Returns an 8 bit (binary) string.

See also `imap_8bit()`.

imap_renamemailbox (PHP 3, PHP 4 >= 4.0.0)

Rename an old mailbox to new mailbox

int **imap_renamemailbox** (int imap_stream, string old_mbox, string new_mbox) \linebreak

This function renames an old mailbox to new mailbox (see `imap_open()` for the format of *mbx* names).

Returns `TRUE` on success and `FALSE` on error.

See also `imap_createmailbox()`, `imap_deletemailbox()`, and `imap_open()` for the format of *mbx*.

imap_reopen (PHP 3, PHP 4 >= 4.0.0)

Reopen IMAP stream to new mailbox

int **imap_reopen** (int imap_stream, string mailbox [, string flags]) \linebreak

This function reopens the specified stream to a new mailbox on an IMAP or NNTP server.

The options are a bit mask with one or more of the following:

- OP_READONLY - Open mailbox read-only
- OP_ANONYMOUS - Dont use or update a .newsrc for news (NNTP only)
- OP_HALFOPEN - For IMAP and NNTP names, open a connection but dont open a mailbox.
- CL_EXPUNGE - Expunge mailbox automatically upon mailbox close (see also imap_delete() and imap_expunge())

Returns TRUE on success and FALSE on error.

imap_rfc822_parse_adrlist (PHP 3 >= 3.0.2, PHP 4 >= 4.0.0)

Parses an address string

array **imap_rfc822_parse_adrlist** (string address, string default_host) \linebreak

This function parses the address string as defined in RFC2822

(<http://www.faqs.org/rfcs/rfc2822.html>) and for each address, returns an array of objects. The objects properties are:

- mailbox - the mailbox name (username)
- host - the host name
- personal - the personal name
- adl - at domain source route

Příklad 1. imap_rfc822_parse_adrlist() example

```
$address_string = "Hartmut Holzgraefe <hartmut@cvs.php.net>, postmaster@somedomain.net, " .
$address_array = imap_rfc822_parse_adrlist($address_string, "somedomain.net");
if(! is_array($address_array)) die("somethings wrong\n");

reset($address_array);
while(list($key,$val)=each($address_array)){
    print "mailbox : ".$val->mailbox."<br>\n";
    print "host      : ".$val->host."<br>\n";
    print "personal: ".$val->personal."<br>\n";
    print "adl       : ".$val->adl."<p>\n";
}
```

imap_rfc822_parse_headers (PHP 4 >= 4.0.0)

Parse mail headers from a string

object **imap_rfc822_parse_headers** (string headers [, string defaulthost]) \linebreak

This function returns an object of various header elements, similar to `imap_header()`, except without the flags and other elements that come from the IMAP server.

imap_rfc822_write_address (PHP 3 >= 3.0.2, PHP 4 >= 4.0.0)

Returns a properly formatted email address given the mailbox, host, and personal info.

string **imap_rfc822_write_address** (string mailbox, string host, string personal) \linebreak

Returns a properly formatted email address as defined in RFC2822 (<http://www.faqs.org/rfcs/rfc2822.html>) given the mailbox, host, and personal info.

Příklad 1. `imap_rfc822_write_address()` example

```
print imap_rfc822_write_address("hartmut", "cvs.php.net", "Hartmut Holzgraefe")."\n";
```

imap_scanmailbox (PHP 3, PHP 4 >= 4.0.0)

Read the list of mailboxes, takes a string to search for in the text of the mailbox

array **imap_scanmailbox** (int imap_stream, string ref, string pattern, string content) \linebreak

Returns an array containing the names of the mailboxes that have *content* in the text of the mailbox. This function is similar to `imap_listmailbox()`, but it will additionally check for the presence of the string *content* inside the mailbox data. See `imap_getmailboxes()` for a description of *ref* and *pattern*.

imap_search (PHP 3 >= 3.0.12, PHP 4 >= 4.0.0)

This function returns an array of messages matching the given search criteria

array **imap_search** (int imap_stream, string criteria, int flags) \linebreak

This function performs a search on the mailbox currently opened in the given imap stream. *criteria* is a string, delimited by spaces, in which the following keywords are allowed. Any multi-word arguments (eg. FROM "joey smith") must be quoted.

- ALL - return all messages matching the rest of the criteria
- ANSWERED - match messages with the `\\ANSWERED` flag set
- BCC "string" - match messages with "string" in the Bcc: field
- BEFORE "date" - match messages with Date: before "date"
- BODY "string" - match messages with "string" in the body of the message
- CC "string" - match messages with "string" in the Cc: field
- DELETED - match deleted messages
- FLAGGED - match messages with the `\\FLAGGED` (sometimes referred to as Important or Urgent) flag set
- FROM "string" - match messages with "string" in the From: field
- KEYWORD "string" - match messages with "string" as a keyword
- NEW - match new messages
- OLD - match old messages
- ON "date" - match messages with Date: matching "date"
- RECENT - match messages with the `\\RECENT` flag set
- SEEN - match messages that have been read (the `\\SEEN` flag is set)
- SINCE "date" - match messages with Date: after "date"
- SUBJECT "string" - match messages with "string" in the Subject:
- TEXT "string" - match messages with text "string"
- TO "string" - match messages with "string" in the To:
- UNANSWERED - match messages that have not been answered
- UNDELETED - match messages that are not deleted
- UNFLAGGED - match messages that are not flagged
- UNKEYWORD "string" - match messages that do not have the keyword "string"
- UNSEEN - match messages which have not been read yet

For example, to match all unanswered messages sent by Mom, you'd use: "UNANSWERED FROM mom". Searches appear to be case insensitive. This list of criteria is from a reading of the UW c-client source code and may be uncomplete or inaccurate (see also RFC2060, section 6.4.4).

Valid values for flags are `SE_UID`, which causes the returned array to contain UIDs instead of messages sequence numbers.

imap_set_quota (PHP 4 >= 4.0.5)

Sets a quota for a given mailbox

int **imap_set_quota** (int imap_stream, string quota_root, int quota_limit) \linebreak

Sets an upper limit quota on a per mailbox basis. This function requires the *imap_stream* to have been opened as the mail administrator account. It will not work if opened as any other user.

This function is currently only available to users of the c-client2000 library.

imap_stream is the stream pointer returned from a `imap_open()` call. This stream must be opened as the mail administrator, otherwise this function will fail. *quota_root* is the mailbox to have a quota set. This should follow the IMAP standard format for a mailbox, 'user.name'. *quota_limit* is the maximum size (in KB) for the *quota_root*.

Returns TRUE on success and FALSE on error.

Příklad 1. `imap_set_quota()` example

```
$mbox = imap_open ("{your.imap.host:143}", "mailadmin", "password");

if(!imap_set_quota($mbox, "user.kalowsky", 3000)) {
    print "Error in setting quota\n";
    return;
}

imap_close($mbox);
```

See also `imap_open()`, `imap_set_quota()`.

imap__setacl (PHP 4 >= 4.1.0)

Sets the ACL for a giving mailbox

int **imap__setacl** (int stream_id, string mailbox, string id, string rights) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imap_setflag_full (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Sets flags on messages

string **imap_setflag_full** (int stream, string sequence, string flag, string options) \linebreak

This function causes a store to add the specified flag to the flags set for the messages in the specified sequence.

The flags which you can set are "\\Seen", "\\Answered", "\\Flagged", "\\Deleted", "\\Draft", and "\\Recent" (as defined by RFC2060).

The options are a bit mask with one or more of the following:

ST_UID The sequence argument contains UIDs instead of sequence numbers

Příklad 1. `imap_setflag_full()` example

```
$mbox = imap_open("{your.imap.host:143}", "username", "password")
    or die("can't connect: ".imap_last_error());

$status = imap_setflag_full($mbox, "2,5", "\\Seen \\Flagged");

print gettype($status)."\n";
print $status."\n";

imap_close($mbox);
```

imap_sort (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Sort an array of message headers

array **imap_sort** (int stream, int criteria, int reverse, int options) \linebreak

Returns an array of message numbers sorted by the given parameters.

Reverse is 1 for reverse-sorting.

Criteria can be one (and only one) of the following:

SORTDATE	message Date
SORTARRIVAL	arrival date
SORTFROM	mailbox in first From address
SORTSUBJECT	message Subject
SORTTO	mailbox in first To address
SORTCC	mailbox in first cc address
SORTSIZE	size of message in octets

The flags are a bitmask of one or more of the following:

SE_UID	Return UIDs instead of sequence numbers
SE_NOPREFETCH	Don't prefetch searched messages.

imap_status (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

This function returns status information on a mailbox other than the current one

object **imap_status** (int imap_stream, string mailbox, int options) \linebreak

This function returns an object containing status information. Valid flags are:

- SA_MESSAGES - set status->messages to the number of messages in the mailbox
- SA_RECENT - set status->recent to the number of recent messages in the mailbox
- SA_UNSEEN - set status->unseen to the number of unseen (new) messages in the mailbox
- SA_UIDNEXT - set status->uidnext to the next uid to be used in the mailbox
- SA_UIDVALIDITY - set status->uidvalidity to a constant that changes when uids for the mailbox may no longer be valid
- SA_ALL - set all of the above

status->flags is also set, which contains a bitmask which can be checked against any of the above constants.

Příklad 1. imap_status() example

```
$mbox = imap_open("{your.imap.host}", "username", "password", OP_HALFOPEN)
        or die("can't connect: ".imap_last_error());

$status = imap_status($mbox, "{your.imap.host}INBOX", SA_ALL);
if($status) {
    print("Messages:      ". $status->messages      ). "<br>\n";
    print("Recent:       ". $status->recent         ). "<br>\n";
    print("Unseen:       ". $status->unseen          ). "<br>\n";
    print("UIDnext:      ". $status->uidnext         ). "<br>\n";
    print("UIDvalidity: ". $status->uidvalidity      ). "<br>\n";
} else
    print "imap_status failed: ".imap_last_error(). "\n";

imap_close($mbox);
```

imap_subscribe (PHP 3, PHP 4 >= 4.0.0)

Subscribe to a mailbox

int **imap_subscribe** (int imap_stream, string mbox) \linebreak

Subscribe to a new mailbox.

Returns `TRUE` on success and `FALSE` on error.

imap_thread (PHP 4 >= 4.1.0)

Return threaded by REFERENCES tree

int **imap_thread** (int stream_id [, int flags]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

imap_uid (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

This function returns the UID for the given message sequence number

int **imap_uid** (int imap_stream, int msgno) \linebreak

This function returns the UID for the given message sequence number. An UID is an unique identifier that will not change over time while a message sequence number may change whenever the content of the mailbox changes. This function is the inverse of `imap_msgno()`.

Poznámka: This is not supported by POP3 mailboxes.

imap_undelete (PHP 3, PHP 4 >= 4.0.0)

Unmark the message which is marked deleted

int **imap_undelete** (int imap_stream, int msg_number) \linebreak

This function removes the deletion flag for a specified message, which is set by `imap_delete()` or `imap_mail_move()`.

Returns `TRUE` on success and `FALSE` on error.

imap_unsubscribe (PHP 3, PHP 4 >= 4.0.0)

Unsubscribe from a mailbox

int **imap_unsubscribe** (int imap_stream, string mbox) \linebreak

Unsubscribe from a specified mailbox.

Returns `TRUE` on success and `FALSE` on error.

imap_utf7_decode (PHP 3>= 3.0.15, PHP 4 >= 4.0.0)

Decodes a modified UTF-7 encoded string.

string **imap_utf7_decode** (string text) \linebreak

Decodes modified UTF-7 *text* into 8bit data.

Returns the decoded 8bit data, or `FALSE` if the input string was not valid modified UTF-7. This function is needed to decode mailbox names that contain international characters outside of the printable ASCII range. The modified UTF-7 encoding is defined in RFC 2060 (<http://www.faqs.org/rfcs/rfc2060.html>), section 5.1.3 (original UTF-7 was defined in RFC1642 (<http://www.faqs.org/rfcs/rfc1642.html>)).

imap_utf7_encode (PHP 3>= 3.0.15, PHP 4 >= 4.0.0)

Converts 8bit data to modified UTF-7 text.

string **imap_utf7_encode** (string data) \linebreak

Converts 8bit *data* to modified UTF-7 text. This is needed to encode mailbox names that contain international characters outside of the printable ASCII range. The modified UTF-7 encoding is defined in RFC 2060 (<http://www.faqs.org/rfcs/rfc2060.html>), section 5.1.3 (original UTF-7 was defined in RFC1642 (<http://www.faqs.org/rfcs/rfc1642.html>)).

Returns the modified UTF-7 text.

imap_utf8 (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Converts text to UTF8

string **imap_utf8** (string text) \linebreak

Converts the given *text* to UTF8 (as defined in RFC2044 (<http://www.faqs.org/rfcs/rfc2044.html>)).

XLIV. Informix functions

The Informix driver for Informix (IDS) 7.x, SE 7.x, Universal Server (IUS) 9.x and IDS 2000 is implemented in "ifx.ec" and "php3_ifx.h" in the informix extension directory. IDS 7.x support is fairly complete, with full support for BYTE and TEXT columns. IUS 9.x support is partly finished: the new data types are there, but SLOB and CLOB support is still under construction.

Configuration notes: You need a version of ESQL/C to compile the PHP Informix driver. ESQL/C versions from 7.2x on should be OK. ESQL/C is now part of the Informix Client SDK.

Make sure that the "INFORMIXDIR" variable has been set, and that \$INFORMIXDIR/bin is in your PATH before you run the "configure" script.

The configure script will autodetect the libraries and include directories, if you run "configure --with_informix=yes". You can override this detection by specifying "IFX_LIBDIR", "IFX_LIBS" and "IFX_INCDIR" in the environment. The configure script will also try to detect your Informix server version. It will set the "HAVE_IFX_IUS" conditional compilation variable if your Informix version >= 9.00.

Runtime considerations: Make sure that the Informix environment variables INFORMIXDIR and INFORMIXSERVER are available to the PHP ifx driver, and that the INFORMIX bin directory is in the PATH. Check this by running a script that contains a call to phpinfo() before you start testing. The phpinfo() output should list these environment variables. This is TRUE for both CGI php and Apache mod_php. You may have to set these environment variables in your Apache startup script.

The Informix shared libraries should also be available to the loader (check LD_LIBRARY_PATH or ld.so.conf/ldconfig).

Some notes on the use of BLOBs (TEXT and BYTE columns): BLOBs are normally addressed by BLOB identifiers. Select queries return a "blob id" for every BYTE and TEXT column. You can get at the contents with "string_var = ifx_get_blob(\$blob_id);" if you choose to get the BLOBs in memory (with : "ifx_blobinfile(0);"). If you prefer to receive the content of BLOB columns in a file, use "ifx_blobinfile(1);", and "ifx_get_blob(\$blob_id);" will get you the filename. Use normal file I/O to get at the blob contents.

For insert/update queries you must create these "blob id's" yourself with "ifx_create_blob();". You then plug the blob id's into an array, and replace the blob columns with a question mark (?) in the query string. For updates/inserts, you are responsible for setting the blob contents with ifx_update_blob().

The behaviour of BLOB columns can be altered by configuration variables that also can be set at runtime :

configuration variable : ifx.textasvarchar

configuration variable : ifx.byteasvarchar

runtime functions :

ifx_textasvarchar(0) : use blob id's for select queries with TEXT columns

ifx_byteasvarchar(0) : use blob id's for select queries with BYTE columns

ifx_textasvarchar(1) : return TEXT columns as if they were VARCHAR columns, so that you don't need to use blob id's for select queries.

ifx_byteasvarchar(1) : return BYTE columns as if they were VARCHAR columns, so that you

don't need to use blob id's for select queries.

configuration variable : ifx.blobinfile

runtime function :

ifx_blobinfile_mode(0) : return BYTE columns in memory, the blob id lets you get at the contents.

ifx_blobinfile_mode(1) : return BYTE columns in a file, the blob id lets you get at the file name.

If you set ifx_text/byteasvarchar to 1, you can use TEXT and BYTE columns in select queries just like normal (but rather long) VARCHAR fields. Since all strings are "counted" in PHP, this remains "binary safe". It is up to you to handle this correctly. The returned data can contain anything, you are responsible for the contents.

If you set ifx_blobinfile to 1, use the file name returned by ifx_get_blob(..) to get at the blob contents. Note that in this case YOU ARE RESPONSIBLE FOR DELETING THE TEMPORARY FILES CREATED BY INFORMIX when fetching the row. Every new row fetched will create new temporary files for every BYTE column.

The location of the temporary files can be influenced by the environment variable "blobdir", default is "." (the current directory). Something like : putenv(blobdir=tmpblob"); will ease the cleaning up of temp files accidentally left behind (their names all start with "blb").

Automatically trimming "char" (SQLCHAR and SQLNCHAR) data: This can be set with the configuration variable

ifx.charasvarchar : if set to 1 trailing spaces will be automatically trimmed, to save you some "chopping".

NULL values: The configuration variable ifx.nullformat (and the runtime function ifx_nullformat()) when set to TRUE will return NULL columns as the string "NULL", when set to FALSE they return the empty string. This allows you to discriminate between NULL columns and empty columns.

ifx_affected_rows (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Get number of rows affected by a query

int ifx_affected_rows (int *result_id*) \linebreak

result_id is a valid result id returned by ifx_query() or ifx_prepare().

Returns the number of rows affected by a query associated with *result_id*.

For inserts, updates and deletes the number is the real number (sqlerrd[2]) of affected rows. For selects it is an estimate (sqlerrd[0]). Don't rely on it. The database server can never return the actual number of rows that will be returned by a SELECT because it has not even begun fetching them at this stage (just after the "PREPARE" when the optimizer has determined the query plan).

Useful after ifx_prepare() to limit queries to reasonable result sets.

See also: ifx_num_rows()

Příklad 1. Informix affected rows

```
$rid = ifx_prepare ("select * from emp
                  where name like " . $name, $connid);
if (! $rid) {
    ... error ...
}
$rowcount = ifx_affected_rows ($rid);
if ($rowcount > 1000) {
    printf ("Too many rows in result set (%d)\n<br>", $rowcount);
    die ("Please restrict your query<br>\n");
}
```

ifx_blobinfile_mode (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Set the default blob mode for all select queries

void ifx_blobinfile_mode (int *mode*) \linebreak

Set the default blob mode for all select queries. Mode "0" means save Byte-Blobs in memory, and mode "1" means save Byte-Blobs in a file.

ifx_byteasvarchar (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Set the default byte mode

void ifx_byteasvarchar (int *mode*) \linebreak

Sets the default byte mode for all select-queries. Mode "0" will return a blob id, and mode "1" will return a varchar with text content.

ifx_close (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Close Informix connection

```
int ifx_close ( [int link_identifier] ) \linebreak
```

Returns: always TRUE.

ifx_close() closes the link to an Informix database that's associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed.

Note that this isn't usually necessary, as non-persistent open links are automatically closed at the end of the script's execution.

ifx_close() will not close persistent links generated by **ifx_pconnect()**.

See also: **ifx_connect()**, and **ifx_pconnect()**.

Příklad 1. Closing a Informix connection

```
$conn_id = ifx_connect ("mydb@ol_srv", "itsme", "mypassword");
... some queries and stuff ...
ifx_close($conn_id);
```

ifx_connect (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Open Informix server connection

```
int ifx_connect ( [string database [, string userid [, string password]]] ) \linebreak
```

Returns a connection identifier on success, or FALSE on error.

ifx_connect() establishes a connection to an Informix server. All of the arguments are optional, and if they're missing, defaults are taken from values supplied in configuration file (**ifx.default_host** for the host (Informix libraries will use **INFORMIXSERVER** environment value if not defined), **ifx.default_user** for user, **ifx.default_password** for the password (none if not defined).

In case a second call is made to **ifx_connect()** with the same arguments, no new link will be established, but instead, the link identifier of the already opened link will be returned.

The link to the server will be closed as soon as the execution of the script ends, unless it's closed earlier by explicitly calling **ifx_close()**.

See also **ifx_pconnect()**, and **ifx_close()**.

Příklad 1. Connect to a Informix database

```
$conn_id = ifx_connect ("mydb@ol_srv1", "imyself", "mypassword");
```


ifx_copy_blob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Duplicates the given blob object

```
int ifx_copy_blob ( int bid) \linebreak
```

Duplicates the given blob object. *bid* is the ID of the blob object.

Returns `FALSE` on error otherwise the new blob object-id.

ifx_create_blob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Creates an blob object

```
int ifx_create_blob ( int type, int mode, string param) \linebreak
```

Creates an blob object.

type: 1 = TEXT, 0 = BYTE

mode: 0 = blob-object holds the content in memory, 1 = blob-object holds the content in file.

param: if mode = 0: pointer to the content, if mode = 1: pointer to the filestring.

Return `FALSE` on error, otherwise the new blob object-id.

ifx_create_char (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Creates an char object

```
int ifx_create_char ( string param) \linebreak
```

Creates an char object. *param* should be the char content.

ifx_do (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Execute a previously prepared SQL-statement

```
int ifx_do ( int result_id) \linebreak
```

Returns `TRUE` on success, `FALSE` on error.

Executes a previously prepared query or opens a cursor for it.

Does NOT free *result_id* on error.

Also sets the real number of `ifx_affected_rows()` for non-select statements for retrieval by `ifx_affected_rows()`

See also: `ifx_prepare()`. There is a example.

ifx_error (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Returns error code of last Informix call

string **ifx_error** (void) \linebreak

The Informix error codes (SQLSTATE & SQLCODE) formatted as follows :

x [SQLSTATE = aa bbb SQLCODE=cccc]

where x = space : no error

E : error

N : no more data

W : warning

? : undefined

If the "x" character is anything other than space, SQLSTATE and SQLCODE describe the error in more detail.

See the Informix manual for the description of SQLSTATE and SQLCODE

Returns in a string one character describing the general results of a statement and both SQLSTATE and SQLCODE associated with the most recent SQL statement executed. The format of the string is "(char) [SQLSTATE=(two digits) (three digits) SQLCODE=(one digit)]". The first character can be ' ' (space) (success), 'w' (the statement caused some warning), 'E' (an error happened when executing the statement) or 'N' (the statement didn't return any data).

See also: `ifx_errormsg()`

ifx_errormsg (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Returns error message of last Informix call

string **ifx_errormsg** ([int errorcode]) \linebreak

Returns the Informix error message associated with the most recent Informix error, or, when the optional "*errorcode*" param is present, the error message corresponding to "*errorcode*".

See also: `ifx_error()`

```
printf("%s\n<br>", ifx_errormsg(-201));
```

ifx_fetch_row (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Get row as enumerated array

array **ifx_fetch_row** (int result_id [, mixed position]) \linebreak

Returns an associative array that corresponds to the fetched row, or FALSE if there are no more rows.

Blob columns are returned as integer blob id values for use in ifx_get_blob() unless you have used ifx_textasvarchar(1) or ifx_byteasvarchar(1), in which case blobs are returned as string values.

Returns FALSE on error

result_id is a valid resultid returned by ifx_query() or ifx_prepare() (select type queries only!).

position is an optional parameter for a "fetch" operation on "scroll" cursors: "NEXT", "PREVIOUS", "CURRENT", "FIRST", "LAST" or a number. If you specify a number, an "absolute" row fetch is executed. This parameter is optional, and only valid for SCROLL cursors.

ifx_fetch_row() fetches one row of data from the result associated with the specified result identifier. The row is returned as an array. Each result column is stored in an array offset, starting at offset 0, with the column name as key.

Subsequent calls to **ifx_fetch_row()** would return the next row in the result set, or FALSE if there are no more rows.

Příklad 1. Informix fetch rows

```
$rid = ifx_prepare ("select * from emp where name like " . $name,
                  $connid, IFX_SCROLL);

if (! $rid) {
    ... error ...
}
$rowcount = ifx_affected_rows($rid);
if ($rowcount > 1000) {
    printf ("Too many rows in result set (%d)\n<br>", $rowcount);
    die ("Please restrict your query<br>\n");
}
if (! ifx_do ($rid)) {
    ... error ...
}
$row = ifx_fetch_row ($rid, "NEXT");
while (is_array($row)) {
    for(reset($row); $fieldname=key($row); next($row)) {
        $fieldvalue = $row[$fieldname];
        printf ("%s = %s,", $fieldname, $fieldvalue);
    }
    printf("\n<br>");
    $row = ifx_fetch_row ($rid, "NEXT");
}
ifx_free_result ($rid);
```

ifx_fieldproperties (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

List of SQL fieldproperties

array **ifx_fieldproperties** (int result_id) \linebreak

Returns an associative array with fieldnames as key and the SQL fieldproperties as data for a query with *result_id*. Returns FALSE on error.

Returns the Informix SQL fieldproperties of every field in the query as an associative array.

Properties are encoded as: "SQLTYPE;length;precision;scale;ISNULLABLE" where SQLTYPE = the Informix type like "SQLVCHAR" etc. and ISNULLABLE = "Y" or "N".

Příklad 1. Informix SQL fieldproperties

```
$properties = ifx_fieldproperties ($resultid);
if (! isset($properties)) {
    ... error ...
}
for ($i = 0; $i < count($properties); $i++) {
    $fname = key ($properties);
    printf ("%s:\t type = %s\n", $fname, $properties[$fname]);
    next ($properties);
}
```

ifx_fielddtypes (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

List of Informix SQL fields

array **ifx_fielddtypes** (int result_id) \linebreak

Returns an associative array with fieldnames as key and the SQL fieldtypes as data for query with *result_id*. Returns FALSE on error.

Příklad 1. Fieldnames and SQL fieldtypes

```
$types = ifx_fielddtypes ($resultid);
if (! isset ($types)) {
    ... error ...
}
for ($i = 0; $i < count($types); $i++) {
    $fname = key($types);
    printf ("%s :\t type = %s\n", $fname, $types[$fname]);
    next($types);
}
```

ifx_free_blob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Deletes the blob object

```
int ifx_free_blob ( int bid) \linebreak
```

Deletes the blobobject for the given blob object-id *bid*. Returns FALSE on error otherwise TRUE.

ifx_free_char (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Deletes the char object

```
int ifx_free_char ( int bid) \linebreak
```

Deletes the charobject for the given char object-id *bid*. Returns FALSE on error otherwise TRUE.

ifx_free_result (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Releases resources for the query

```
int ifx_free_result ( int result_id) \linebreak
```

Releases resources for the query associated with *result_id*. Returns FALSE on error.

ifx_get_blob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Return the content of a blob object

```
int ifx_get_blob ( int bid) \linebreak
```

Returns the content of the blob object for the given blob object-id *bid*.

ifx_get_char (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Return the content of the char object

```
int ifx_get_char ( int bid) \linebreak
```

Returns the content of the char object for the given char object-id *bid*.

ifx_getsqlca (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Get the contents of sqlca.sqlerrd[0..5] after a query

array **ifx_getsqlca** (int result_id) \linebreak

result_id is a valid result id returned by ifx_query() or ifx_prepare().

Returns a pseudo-row (associative array) with sqlca.sqlerrd[0] ... sqlca.sqlerrd[5] after the query associated with *result_id*.

For inserts, updates and deletes the values returned are those as set by the server after executing the query. This gives access to the number of affected rows and the serial insert value. For SELECTs the values are those saved after the PREPARE statement. This gives access to the *estimated* number of affected rows. The use of this function saves the overhead of executing a "select dbinfo('sqlca.sqlerrdx')" query, as it retrieves the values that were saved by the ifx driver at the appropriate moment.

Příklad 1. Retrieve Informix sqlca.sqlerrd[x] values

```
/* assume the first column of 'sometable' is a serial */
$qid = ifx_query("insert into sometable
                values (0, '2nd column', 'another column') ", $connid);
if (! $qid) {
    ... error ...
}
$sqlca = ifx_getsqlca ($qid);
$serial_value = $sqlca["sqlerrd1"];
echo "The serial value of the inserted row is : " . $serial_value<br>\n";
```

ifx_htmltbl_result (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Formats all rows of a query into a HTML table

int **ifx_htmltbl_result** (int result_id [, string html_table_options]) \linebreak

Returns the number of rows fetched or FALSE on error.

Formats all rows of the *result_id* query into a html table. The optional second argument is a string of <table> tag options

Příklad 1. Informix results as HTML table

```
$rid = ifx_prepare ("select * from emp where name like " . $name,
                  $connid, IFX_SCROLL);
if (! $rid) {
    ... error ...
}
$rowcount = ifx_affected_rows ($rid);
if ($rowcount > 1000) {
    printf ("Too many rows in result set (%d)\n<br>", $rowcount);
    die ("Please restrict your query<br>\n");
}
if (! ifx_do($rid) {
    ... error ...
}
```

```

}

ifx_htmltbl_result ($rid, "border=\"2\"");

ifx_free_result($rid);

```

ifx_nullformat (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Sets the default return value on a fetch row

```
void ifx_nullformat ( int mode) \linebreak
```

Sets the default return value of a NULL-value on a fetch row. Mode "0" returns "", and mode "1" returns "NULL".

ifx_num_fields (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Returns the number of columns in the query

```
int ifx_num_fields ( int result_id) \linebreak
```

Returns the number of columns in query for *result_id* or FALSE on error

After preparing or executing a query, this call gives you the number of columns in the query.

ifx_num_rows (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Count the rows already fetched from a query

```
int ifx_num_rows ( int result_id) \linebreak
```

Gives the number of rows fetched so far for a query with *result_id* after a ifx_query() or ifx_do() query.

ifx_pconnect (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Open persistent Informix connection

```
int ifx_pconnect ( [string database [, string userid [, string password]]]) \linebreak
```

Returns: A positive Informix persistent link identifier on success, or FALSE on error

ifx_pconnect() acts very much like ifx_connect() with two major differences.

This function behaves exactly like ifx_connect() when PHP is not running as an Apache module.

First, when connecting, the function would first try to find a (persistent) link that's already open with

the same host, username and password. If one is found, an identifier for it will be returned instead of opening a new connection.

Second, the connection to the SQL server will not be closed when the execution of the script ends. Instead, the link will remain open for future use (`ifx_close()` will not close links established by `ifx_pconnect()`).

This type of links is therefore called 'persistent'.

See also: `ifx_connect()`.

ifx_prepare (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Prepare an SQL-statement for execution

```
int ifx_prepare ( string query, int conn_id [, int cursor_def, mixed blobidarray]) \linebreak
```

Returns an integer *result_id* for use by `ifx_do()`. Sets *affected_rows* for retrieval by the `ifx_affected_rows()` function.

Prepares *query* on connection *conn_id*. For "select-type" queries a cursor is declared and opened. The optional *cursor_type* parameter allows you to make this a "scroll" and/or "hold" cursor. It's a bitmask and can be either `IFX_SCROLL`, `IFX_HOLD`, or both or'ed together.

For either query type the estimated number of affected rows is saved for retrieval by `ifx_affected_rows()`.

If you have BLOB (BYTE or TEXT) columns in the query, you can add a *blobidarray* parameter containing the corresponding "blob ids", and you should replace those columns with a "?" in the query text.

If the contents of the TEXT (or BYTE) column allow it, you can also use "`ifx_textasvarchar(1)`" and "`ifx_byteasvarchar(1)`". This allows you to treat TEXT (or BYTE) columns just as if they were ordinary (but long) VARCHAR columns for select queries, and you don't need to bother with blob id's.

With `ifx_textasvarchar(0)` or `ifx_byteasvarchar(0)` (the default situation), select queries will return BLOB columns as blob id's (integer value). You can get the value of the blob as a string or file with the blob functions (see below).

See also: `ifx_do()`.

ifx_query (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Send Informix query

```
int ifx_query ( string query [, int link_identifier [, int cursor_type [, mixed blobidarray]]]) \linebreak
```

Returns: A positive Informix result identifier on success, or `FALSE` on error.

A "result_id" resource used by other functions to retrieve the query results. Sets "affected_rows" for retrieval by the `ifx_affected_rows()` function.

ifx_query() sends a query to the currently active database on the server that's associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed. If no link is open, the function tries to establish a link as if **ifx_connect()** was called, and use it.

Executes *query* on connection *conn_id*. For "select-type" queries a cursor is declared and opened. The optional *cursor_type* parameter allows you to make this a "scroll" and/or "hold" cursor. It's a bitmask and can be either **IFX_SCROLL**, **IFX_HOLD**, or both or'ed together. Non-select queries are "execute immediate". **IFX_SCROLL** and **IFX_HOLD** are symbolic constants and as such shouldn't be between quotes. If you omit this parameter the cursor is a normal sequential cursor.

For either query type the number of (estimated or real) affected rows is saved for retrieval by **ifx_affected_rows()**.

If you have BLOB (BYTE or TEXT) columns in an update query, you can add a *blobidarray* parameter containing the corresponding "blob ids", and you should replace those columns with a "?" in the query text.

If the contents of the TEXT (or BYTE) column allow it, you can also use "ifx_textasvarchar(1)" and "ifx_byteasvarchar(1)". This allows you to treat TEXT (or BYTE) columns just as if they were ordinary (but long) VARCHAR columns for select queries, and you don't need to bother with blob id's.

With **ifx_textasvarchar(0)** or **ifx_byteasvarchar(0)** (the default situation), select queries will return BLOB columns as blob id's (integer value). You can get the value of the blob as a string or file with the blob functions (see below).

See also: **ifx_connect()**.

Příklad 1. Show all rows of the "orders" table as a html table

```
ifx_textasvarchar(1);          // use "text mode" for blobs
$res_id = ifx_query("select * from orders", $conn_id);
if (! $res_id) {
    printf("Can't select orders : %s\n<br>%s<br>\n", ifx_error());
    ifx_errormsg();
    die;
}
ifx_htmltbl_result($res_id, "border=\"1\"");
ifx_free_result($res_id);
```

Příklad 2. Insert some values into the "catalog" table

```
                                // create blob id's for a byte and text column
$textid = ifx_create_blob(0, 0, "Text column in memory");
$byteid = ifx_create_blob(1, 0, "Byte column in memory");
                                // store blob id's in a blobid array
$blobidarray[] = $textid;
$blobidarray[] = $byteid;
                                // launch query
$query = "insert into catalog (stock_num, manu_code, " .
        "cat_descr,cat_picture) values(1,'HRO',?,?)";
$res_id = ifx_query($query, $conn_id, $blobidarray);
```

```

if (! $res_id) {
    ... error ...
}

// free result id
ifx_free_result($res_id);

```

ifx_textasvarchar (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Set the default text mode

```
void ifx_textasvarchar ( int mode) \linebreak
```

Sets the default text mode for all select-queries. Mode "0" will return a blob id, and mode "1" will return a varchar with text content.

ifx_update_blob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Updates the content of the blob object

```
ifx_update_blob ( int bid, string content) \linebreak
```

Updates the content of the blob object for the given blob object *bid*. *content* is a string with new data. Returns `FALSE` on error otherwise `TRUE`.

ifx_update_char (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Updates the content of the char object

```
int ifx_update_char ( int bid, string content) \linebreak
```

Updates the content of the char object for the given char object *bid*. *content* is a string with new data. Returns `FALSE` on error otherwise `TRUE`.

ifxus_close_slob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Deletes the slob object

```
int ifxus_close_slob ( int bid) \linebreak
```

Deletes the slob object on the given slob object-id *bid*. Return `FALSE` on error otherwise `TRUE`.

ifxus_create_slob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Creates an slob object and opens it

```
int ifxus_create_slob ( int mode) \linebreak
```

Creates an slob object and opens it. Modes: 1 = LO_RDONLY, 2 = LO_WRONLY, 4 = LO_APPEND, 8 = LO_RDWR, 16 = LO_BUFFER, 32 = LO_NOBUFFER -> or-mask. You can also use constants named IFX_LO_RDONLY, IFX_LO_WRONLY etc. Return FALSE on error otherwise the new slob object-id.

ifxus_free_slob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Deletes the slob object

```
int ifxus_free_slob ( int bid) \linebreak
```

Deletes the slob object. *bid* is the Id of the slob object. Returns FALSE on error otherwise TRUE.

ifxus_open_slob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Opens an slob object

```
int ifxus_open_slob ( long bid, int mode) \linebreak
```

Opens an slob object. *bid* should be an existing slob id. Modes: 1 = LO_RDONLY, 2 = LO_WRONLY, 4 = LO_APPEND, 8 = LO_RDWR, 16 = LO_BUFFER, 32 = LO_NOBUFFER -> or-mask. Returns FALSE on error otherwise the new slob object-id.

ifxus_read_slob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Reads nbytes of the slob object

```
int ifxus_read_slob ( long bid, long nbytes) \linebreak
```

Reads nbytes of the slob object. *bid* is a existing slob id and *nbytes* is the number of bytes read. Return FALSE on error otherwise the string.

ifxus_seek_slob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Sets the current file or seek position

```
int ifxus_seek_slob ( long bid, int mode, long offset) \linebreak
```

Sets the current file or seek position of an open slob object. *bid* should be an existing slob id.
 Modes: 0 = LO_SEEK_SET, 1 = LO_SEEK_CUR, 2 = LO_SEEK_END and *offset* is an byte offset. Return `FALSE` on error otherwise the seek position.

ifxus_tell_slob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Returns the current file or seek position

int **ifxus_tell_slob** (long bid) \linebreak

Returns the current file or seek position of an open slob object *bid* should be an existing slob id.
 Return `FALSE` on error otherwise the seek position.

ifxus_write_slob (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Writes a string into the slob object

int **ifxus_write_slob** (long bid, string content) \linebreak

Writes a string into the slob object. *bid* is a existing slob id and *content* the content to write.
 Return `FALSE` on error otherwise bytes written.

XLV. InterBase functions

InterBase is a popular database put out by Borland/Inprise. More information about InterBase is available at <http://www.interbase.com/>. Oh, by the way, InterBase just joined the open source movement!

Poznámka: Full support for InterBase 6 was added in PHP 4.0.

This database uses a single quote (') character for escaping, a behavior similar to the Sybase database, add to your `php.ini` the following directive:

```
magic_quotes_sybase = On
```

ibase_blob_add (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Add data into created blob

```
int ibase_blob_add ( int blob_id, string data) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_blob_cancel (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Cancel creating blob

```
int ibase_blob_cancel ( int blob_id) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_blob_close (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Close blob

```
int ibase_blob_close ( int blob_id) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_blob_create (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Create blob for adding data

```
int ibase_blob_create ( [int link_idenfier]) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_blob_echo (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Output blob contents to browser

```
int ibase_blob_echo ( string blob_id_str) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_blob_get (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Get len bytes data from open blob

```
string ibase_blob_get ( int blob_id, int len) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_blob_import (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Create blob, copy file in it, and close it

```
string ibase_blob_import ( [int link_identifier, int file_id]) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_blob_info (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Return blob length and other useful info

object **ibase_blob_info** (string blob_id_str) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_blob_open (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Open blob for retrieving data parts

int **ibase_blob_open** (string blob_id) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ibase_close (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Close a connection to an InterBase database

int **ibase_close** ([int connection_id]) \linebreak

Closes the link to an InterBase database that's associated with a connection id returned from `ibase_connect()`. If the connection id is omitted, the last opened link is assumed. Default transaction on link is committed, other transactions are rolled back.

ibase_commit (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Commit a transaction

int **ibase_commit** ([int link_identifier, int trans_number]) \linebreak

Commits transaction *trans_number* which was created with *ibase_trans()*.

ibase_connect (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Open a connection to an InterBase database

```
int ibase_connect ( string database [, string username [, string password [, string charset [, int buffers [, int dialect [, string role]]]]]) \linebreak
```

Establishes a connection to an InterBase server. The *database* argument has to be a valid path to database file on the server it resides on. If the server is not local, it must be prefixed with either 'hostname:' (TCP/IP), '//hostname/' (NetBEUI) or 'hostname@' (IPX/SPX), depending on the connection protocol used. *username* and *password* can also be specified with PHP configuration directives *ibase.default_user* and *ibase.default_password*. *charset* is the default character set for a database. *buffers* is the number of database buffers to allocate for the server-side cache. If 0 or omitted, server chooses its own default. *dialect* selects the default SQL dialect for any statement executed within a connection, and it defaults to the highest one supported by client libraries.

In case a second call is made to **ibase_connect()** with the same arguments, no new link will be established, but instead, the link identifier of the already opened link will be returned. The link to the server will be closed as soon as the execution of the script ends, unless it's closed earlier by explicitly calling *ibase_close()*.

Příklad 1. ibase_connect() example

```
<?php
    $dbh = ibase_connect($host, $username, $password);
    $stmt = 'SELECT * FROM tblname';
    $sth = ibase_query($dbh, $stmt);
    while ($row = ibase_fetch_object($sth)) {
        echo $row->email, "\n";
    }
    ibase_free_result($sth);
    ibase_close($dbh);
?>
```

Poznámka: *buffers* was added in PHP 4.0RC2.

Poznámka: *dialect* was added in PHP 4.0RC2. It is functional only with InterBase 6 and versions higher than that.

Poznámka: *role* was added in PHP 4.0RC2. It is functional only with InterBase 5 and versions higher than that.

See also `ibase_pconnect()`.

ibase_errmsg (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Returns error messages

string **ibase_errmsg** (void) \linebreak

Returns a string containing an error message.

ibase_execute (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Execute a previously prepared query

int **ibase_execute** (int query [, int bind_args]) \linebreak

Execute a query prepared by `ibase_prepare()`. This is a lot more effective than using `ibase_query()` if you are repeating a same kind of query several times with only some parameters changing.

```
<?php
    $updates = array(
        1 => 'Eric',
        5 => 'Filip',
        7 => 'Larry'
    );

    $query = ibase_prepare("UPDATE FOO SET BAR = ? WHERE BAZ = ?");

    while (list($baz, $bar) = each($updates)) {
        ibase_execute($query, $bar, $baz);
    }
?>
```

ibase_fetch_object (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Get an object from a InterBase database

object **ibase_fetch_object** (int result_id) \linebreak

Fetches a row as a pseudo-object from a *result_id* obtained either by `ibase_query()` or `ibase_execute()`.

```
<php
    $dbh = ibase_connect ($host, $username, $password);
```

```

$stmt = 'SELECT * FROM tblname';
$sth = ibase_query ($dbh, $stmt);
while ($row = ibase_fetch_object ($sth)) {
    print $row->email . "\n";
}
ibase_close ($dbh);
?>

```

Subsequent call to **ibase_fetch_object()** would return the next row in the result set, or FALSE if there are no more rows.

See also **ibase_fetch_row()**.

ibase_fetch_row (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Fetch a row from an InterBase database

array **ibase_fetch_row** (int result_identifier) \linebreak

Returns an array that corresponds to the fetched row, or FALSE if there are no more rows.

ibase_fetch_row() fetches one row of data from the result associated with the specified *result_identifier*. The row is returned as an array. Each result column is stored in an array offset, starting at offset 0.

Subsequent call to **ibase_fetch_row()** would return the next row in the result set, or FALSE if there are no more rows.

ibase_field_info (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Get information about a field

array **ibase_field_info** (int result, int field number) \linebreak

Returns an array with information about a field after a select query has been run. The array is in the form of name, alias, relation, length, type.

```

$rs=ibase_query("SELECT * FROM tablename");
$coln = ibase_num_fields($rs);
for ($i=0; $i < $coln; $i++) {
    $col_info = ibase_field_info($rs, $i);
    echo "name: ".$col_info['name']."\n";
    echo "alias: ".$col_info['alias']."\n";
    echo "relation: ".$col_info['relation']."\n";
    echo "length: ".$col_info['length']."\n";
    echo "type: ".$col_info['type']."\n";
}

```

ibase_free_query (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Free memory allocated by a prepared query

```
int ibase_free_query ( int query) \linebreak
```

Free a query prepared by `ibase_prepare()`.

ibase_free_result (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Free a result set

```
int ibase_free_result ( int result_identifier) \linebreak
```

Free's a result set the has been created by `ibase_query()`.

ibase_num_fields (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Get the number of fields in a result set

```
int ibase_num_fields ( int result_id) \linebreak
```

Returns an integer containing the number of fields in a result set.

```
<?php
$dbh = ibase_connect ($host, $username, $password);
$stmt = 'SELECT * FROM tblname';
$sth = ibase_query ($dbh, $stmt);

if (ibase_num_fields($sth) > 0) {
while ($row = ibase_fetch_object ($sth)) {
print $row->email . "\n";
}
} else {
die ("No Results were found for your query");
}

ibase_close ($dbh);
?>
```

See also: `ibase_field_info()`.

ibase_pconnect (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Creates an persistent connection to an InterBase database

```
int ibase_pconnect ( string database [, string username [, string password [, string charset [, int buffers [, int dialect [, string role]]]]]] ) \linebreak
```

ibase_pconnect() acts very much like **ibase_connect()** with two major differences. First, when connecting, the function will first try to find a (persistent) link that's already opened with the same parameters. If one is found, an identifier for it will be returned instead of opening a new connection. Second, the connection to the InterBase server will not be closed when the execution of the script ends. Instead, the link will remain open for future use (**ibase_close()** will not close links established by **ibase_pconnect()**). This type of link is therefore called 'persistent'.

Poznámka: *buffers* was added in PHP4-RC2.

Poznámka: *dialect* was added in PHP4-RC2. It is functional only with InterBase 6 and versions higher than that.

Poznámka: *role* was added in PHP4-RC2. It is functional only with InterBase 5 and versions higher than that.

See also **ibase_connect()** for the meaning of parameters passed to this function. They are exactly the same.

ibase_prepare (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Prepare a query for later binding of parameter placeholders and execution

```
int ibase_prepare ( [int link_identifier, string query] ) \linebreak
```

Prepare a query for later binding of parameter placeholders and execution (via **ibase_execute()**).

ibase_query (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Execute a query on an InterBase database

```
int ibase_query ( [int link_identifier, string query [, int bind_args]] ) \linebreak
```

Performs a query on an InterBase database. If the query is not successful, returns **FALSE**. If it is successful and there are resulting rows (such as with a **SELECT** query), returns a result identifier. If the query was successful and there were no results, returns **TRUE**. Returns **FALSE** if the query fails.

See also **ibase_errmsg()**, **ibase_fetch_row()**, **ibase_fetch_object()**, and **ibase_free_result()**.

ibase_rollback (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Rolls back a transaction

```
int ibase_rollback ( [int link_identifier, int trans_number] ) \linebreak
```

Rolls back transaction *trans_number* which was created with *ibase_trans()*.

ibase_timefmt (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets the format of timestamp, date and time type columns returned from queries

```
int ibase_timefmt ( string format [, int columntype] ) \linebreak
```

Sets the format of timestamp, date or time type columns returned from queries. Internally, the columns are formatted by *c*-function *strftime()*, so refer to it's documentation regarding to the format of the string. *columntype* is one of the constants *IBASE_TIMESTAMP*, *IBASE_DATE* and *IBASE_TIME*. If omitted, defaults to *IBASE_TIMESTAMP* for backwards compatibility.

```
<?php
// InterBase 6 TIME-type columns will be returned in
// the form '05 hours 37 minutes'.
ibase_timefmt("%H hours %M minutes", IBASE_TIME);
?>
```

You can also set defaults for these formats with PHP configuration directives *ibase.timestampformat*, *ibase.dateformat* and *ibase.timeformat*.

Poznámka: *columntype* was added in PHP 4.0. It has any meaning only with InterBase version 6 and higher.

Poznámka: A backwards incompatible change happened in PHP 4.0 when PHP configuration directive *ibase.timeformat* was renamed to *ibase.timestampformat* and directives *ibase.dateformat* and *ibase.timeformat* were added, so that the names would match better their functionality.

ibase_trans (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Begin a transaction

```
int ibase_trans ( [int trans_args [, int link_identifier]] ) \linebreak
```

Begins a transaction.

XLVI. Ingres II functions

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

These functions allow you to access Ingres II database servers.

In order to have these functions available, you must compile php with Ingres support by using the `--with-ingres` option. You need the Open API library and header files included with Ingres II. If the `II_SYSTEM` environment variable isn't correctly set you may have to use `--with-ingres=DIR` to specify your Ingres installation directory.

When using this extension with Apache, if Apache does not start and complains with "PHP Fatal error: Unable to start ingres_ii module in Unknown on line 0" then make sure the environment variable `II_SYSTEM` is correctly set. Adding "export `II_SYSTEM=/home/ingres/II`" in the script that starts Apache, just before launching httpd, should be fine.

Poznámka: If you already used PHP extensions to access other database servers, note that Ingres doesn't allow concurrent queries and/or transaction over one connection, thus you won't find any result or transaction handle in this extension. The result of a query must be treated before sending another query, and a transaction must be committed or rolled back before opening another transaction (which is automatically done when sending the first query).

ingres_autocommit (PHP 4 >= 4.0.2)

Switch autocommit on or off

```
bool ingres_autocommit ( [resource link] ) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_autocommit() is called before opening a transaction (before the first call to **ingres_query()** or just after a call to **ingres_rollback()** or **ingres_autocommit()** to switch the "autocommit" mode of the server on or off (when the script begins the autocommit mode is off).

When the autocommit mode is on, every query is automatically committed by the server, as if **ingres_commit()** was called after every call to **ingres_query()**.

See also **ingres_query()**, **ingres_rollback()**, and **ingres_commit()**.

ingres_close (PHP 4 >= 4.0.2)

Close an Ingres II database connection

```
bool ingres_close ( [resource link] ) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Returns TRUE on success, or FALSE on failure.

ingres_close() closes the connection to the Ingres server that's associated with the specified link. If the *link* parameter isn't specified, the last opened link is used.

ingres_close() isn't usually necessary, as it won't close persistent connections and all non-persistent connections are automatically closed at the end of the script.

See also **ingres_connect()** and **ingres_pconnect()**.

ingres_commit (PHP 4 >= 4.0.2)

Commit a transaction

```
bool ingres_commit ( [resource link] ) \linebreak
```


Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_commit() commits the currently open transaction, making all changes made to the database permanent.

This closes the transaction. A new one can be open by sending a query with **ingres_query()**.

You can also have the server commit automatically after every query by calling **ingres_autocommit()** before opening the transaction.

See also **ingres_query()**, **ingres_rollback()**, and **ingres_autocommit()**.

ingres_connect (PHP 4 >= 4.0.2)

Open a connection to an Ingres II database

resource **ingres_connect** ([string database [, string username [, string password]]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Returns a Ingres II link resource on success, or **FALSE** on failure.

ingres_connect() opens a connection with the Ingres database designated by *database*, which follows the syntax `[node_id::]dbname[/svr_class]`.

If some parameters are missing, **ingres_connect()** uses the values in `php.ini` for `ingres.default_database`, `ingres.default_user`, and `ingres.default_password`.

The connection is closed when the script ends or when **ingres_close()** is called on this link.

All the other ingres functions use the last opened link as a default, so you need to store the returned value only if you use more than one link at a time.

Příklad 1. ingres_connect() example

```
<?php
$link = ingres_connect ("mydb", "user", "pass")
    or die ("Could not connect");
print ("Connected successfully");
ingres_close ($link);
?>
```

Příklad 2. ingres_connect() example using default link

```
<?php
    ingres_connect ("mydb", "user", "pass")
        or die ("Could not connect");
    print ("Connected successfully");
    ingres_close ();
?>
```

See also `ingres_pconnect()` and `ingres_close()`.

ingres_fetch_array (PHP 4 >= 4.0.2)

Fetch a row of result into an array

array **ingres_fetch_array** ([int result_type [, resource link]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_fetch_array() Returns an array that corresponds to the fetched row, or `FALSE` if there are no more rows.

This function is an extended version of `ingres_fetch_row()`. In addition to storing the data in the numeric indices of the result array, it also stores the data in associative indices, using the field names as keys.

If two or more columns of the result have the same field names, the last column will take precedence. To access the other column(s) of the same name, you must use the numeric index of the column or make an alias for the column.

```
ingres_query(select t1.f1 as foo t2.f1 as bar from t1, t2);
$result = ingres_fetch_array();
$foo = $result["foo"];
$bar = $result["bar"];
```

result_type can be `INGRES_NUM` for enumerated array, `INGRES_ASSOC` for associative array, or `INGRES_BOTH` (default).

Speed-wise, the function is identical to `ingres_fetch_object()`, and almost as quick as `ingres_fetch_row()` (the difference is insignificant).

Příklad 1. ingres_fetch_array() example

```
<?php
ingres_connect ($database, $user, $password);

ingres_query ("select * from table");
while ($row = ingres_fetch_array()) {
    echo $row["user_id"]; # using associative array
    echo $row["fullname"];
    echo $row[1];         # using enumerated array
    echo $row[2];
}
?>
```

See also `ingres_query()`, `ingres_num_fields()`, `ingres_field_name()`, `ingres_fetch_object()`, and `ingres_fetch_row()`.

ingres_fetch_object (PHP 4 >= 4.0.2)

Fetch a row of result into an object.

object **ingres_fetch_object** ([int result_type [, resource link]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_fetch_object() Returns an object that corresponds to the fetched row, or `FALSE` if there are no more rows.

This function is similar to `ingres_fetch_array()`, with one difference - an object is returned, instead of an array. Indirectly, that means that you can only access the data by the field names, and not by their offsets (numbers are illegal property names).

The optional argument *result_type* is a constant and can take the following values: `INGRES_ASSOC`, `INGRES_NUM`, and `INGRES_BOTH`.

Speed-wise, the function is identical to `ingres_fetch_array()`, and almost as quick as `ingres_fetch_row()` (the difference is insignificant).

Příklad 1. ingres_fetch_object() example

```
<?php
ingres_connect ($database, $user, $password);
ingres_query ("select * from table");
```

```

while ($row = ingres_fetch_object()) {
    echo $row->user_id;
    echo $row->fullname;
}
?>

```

See also `ingres_query()`, `ingres_num_fields()`, `ingres_field_name()`, `ingres_fetch_array()`, and `ingres_fetch_row()`.

ingres_fetch_row (PHP 4 >= 4.0.2)

Fetch a row of result into an enumerated array

array **ingres_fetch_row** ([resource link]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_fetch_row() returns an array that corresponds to the fetched row, or `FALSE` if there are no more rows. Each result column is stored in an array offset, starting at offset 1.

Subsequent call to **ingres_fetch_row()** would return the next row in the result set, or `FALSE` if there are no more rows.

Příklad 1. ingres_fetch_row() example

```

<?php
ingres_connect ($database, $user, $password);

ingres_query ("select * from table");
while ($row = ingres_fetch_row()) {
    echo $row[1];
    echo $row[2];
}
?>

```

See also `ingres_num_fields()`, `ingres_query()`, `ingres_fetch_array()`, and `ingres_fetch_object()`.

ingres_field_length (PHP 4 >= 4.0.2)

Get the length of a field

```
int ingres_field_length ( int index [, resource link]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_field_length() returns the length of a field. This is the number of bytes used by the server to store the field. For detailed information, see the Ingres/OpenAPI User Guide - Appendix C.

index is the number of the field and must be between 1 and the value given by **ingres_num_fields()**.

See also **ingres_query()**, **ingres_fetch_array()**, **ingres_fetch_object()**, and **ingres_fetch_row()**.

ingres_field_name (PHP 4 >= 4.0.2)

Get the name of a field in a query result.

```
string ingres_field_name ( int index [, resource link]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_field_name() returns the name of a field in a query result, or **FALSE** on failure.

index is the number of the field and must be between 1 and the value given by **ingres_num_fields()**.

See also **ingres_query()**, **ingres_fetch_array()**, **ingres_fetch_object()** and **ingres_fetch_row()**.

ingres_field_nullable (PHP 4 >= 4.0.2)

Test if a field is nullable

```
bool ingres_field_nullable ( int index [, resource link]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_field_nullable() returns `TRUE` if the field can be set to the `NULL` value and `FALSE` if it can't.

index is the number of the field and must be between 1 and the value given by `ingres_num_fields()`.

See also `ingres_query()`, `ingres_fetch_array()`, `ingres_fetch_object()`, and `ingres_fetch_row()`.

ingres_field_precision (PHP 4 >= 4.0.2)

Get the precision of a field

```
int ingres_field_precision ( int index [, resource link]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_field_precision() returns the precision of a field. This value is used only for decimal, float and money SQL data types. For detailed information, see the Ingres/OpenAPI User Guide - Appendix C.

index is the number of the field and must be between 1 and the value given by `ingres_num_fields()`.

See also `ingres_query()`, `ingres_fetch_array()`, `ingres_fetch_object()`, and `ingres_fetch_row()`.

ingres_field_scale (PHP 4 >= 4.0.2)

Get the scale of a field

```
int ingres_field_scale ( int index [, resource link]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_field_scale() returns the scale of a field. This value is used only for the decimal SQL data type. For detailed information, see the Ingres/OpenAPI User Guide - Appendix C.

index is the number of the field and must be between 1 and the value given by `ingres_num_fields()`.

See also `ingres_query()`, `ingres_fetch_array()`, `ingres_fetch_object()`, and `ingres_fetch_row()`.

ingres_field_type (PHP 4 >= 4.0.2)

Get the type of a field in a query result

```
string ingres_field_type ( int index [, resource link]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_field_type() returns the type of a field in a query result, or `FALSE` on failure. Examples of types returned are "IIAPI_BYTE_TYPE", "IIAPI_CHA_TYPE", "IIAPI_DTE_TYPE", "IIAPI_FLT_TYPE", "IIAPI_INT_TYPE", "IIAPI_VCH_TYPE". Some of these types can map to more than one SQL type depending on the length of the field (see **ingres_field_length()**). For example "IIAPI_FLT_TYPE" can be a float4 or a float8. For detailed information, see the Ingres/OpenAPI User Guide - Appendix C.

index is the number of the field and must be between 1 and the value given by **ingres_num_fields()**.

See also **ingres_query()**, **ingres_fetch_array()**, **ingres_fetch_object()**, and **ingres_fetch_row()**.

ingres_num_fields (PHP 4 >= 4.0.2)

Get the number of fields returned by the last query

```
int ingres_num_fields ( [resource link]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_num_fields() returns the number of fields in the results returned by the Ingres server after a call to **ingres_query()**

See also **ingres_query()**, **ingres_fetch_array()**, **ingres_fetch_object()**, and **ingres_fetch_row()**.

ingres_num_rows (PHP 4 >= 4.0.2)

Get the number of rows affected or returned by the last query

```
int ingres_num_rows ( [resource link]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

For delete, insert or update queries, **ingres_num_rows()** returns the number of rows affected by the query. For other queries, **ingres_num_rows()** returns the number of rows in the query's result.

Poznámka: This function is mainly meant to get the number of rows modified in the database. If this function is called before using **ingres_fetch_array()**, **ingres_fetch_object()** or **ingres_fetch_row()** the server will delete the result's data and the script won't be able to get them.

You should instead retrieve the result's data using one of these fetch functions in a loop until it returns **FALSE**, indicating that no more results are available.

See also **ingres_query()**, **ingres_fetch_array()**, **ingres_fetch_object()**, and **ingres_fetch_row()**.

ingres_pconnect (PHP 4 >= 4.0.2)

Open a persistent connection to an Ingres II database

resource **ingres_pconnect** ([string database [, string username [, string password]]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Returns a Ingres II link resource on success, or **FALSE** on failure.

See **ingres_connect()** for parameters details and examples. There are only 2 differences between **ingres_pconnect()** and **ingres_connect()** : First, when connecting, the function will first try to find a (persistent) link that's already opened with the same parameters. If one is found, an identifier for it will be returned instead of opening a new connection. Second, the connection to the Ingres server will not be closed when the execution of the script ends. Instead, the link will remain open for future use (**ingres_close()** will not close links established by **ingres_pconnect()**). This type of link is therefore called 'persistent'.

See also **ingres_connect()** and **ingres_close()**.

ingres_query (PHP 4 >= 4.0.2)

Send a SQL query to Ingres II

bool **ingres_query** (string query [, resource link]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Returns TRUE on success, or FALSE on failure.

ingres_query() sends the given *query* to the Ingres server. This query must be a valid SQL query (see the Ingres SQL reference guide)

The query becomes part of the currently open transaction. If there is no open transaction, **ingres_query()** opens a new transaction. To close the transaction, you can either call **ingres_commit()** to commit the changes made to the database or **ingres_rollback()** to cancel these changes. When the script ends, any open transaction is rolled back (by calling **ingres_rollback()**). You can also use **ingres_autocommit()** before opening a new transaction to have every SQL query immediatly committed.

Some types of SQL queries can't be sent with this function:

- close (see **ingres_close()**)
- commit (see **ingres_commit()**)
- connect (see **ingres_connect()**)
- disconnect (see **ingres_close()**)
- get dbevent
- prepare to commit
- rollback (see **ingres_rollback()**)
- savepoint
- set autocommit (see **ingres_autocommit()**)
- all cursor related queries are unsupported

Příklad 1. **ingres_query()** example

```
<?php
ingres_connect ($database, $user, $password);

ingres_query ("select * from table");
while ($row = ingres_fetch_row()) {
    echo $row[1];
    echo $row[2];
}
?>
```

See also `ingres_fetch_array()`, `ingres_fetch_object()`, `ingres_fetch_row()`, `ingres_commit()`, `ingres_rollback()`, and `ingres_autocommit()`.

ingres_rollback (PHP 4 >= 4.0.2)

Roll back a transaction

bool **ingres_rollback** ([resource link]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ingres_rollback() rolls back the currently open transaction, actually canceling all changes made to the database during the transaction.

This closes the transaction. A new one can be open by sending a query with `ingres_query()`.

See also `ingres_query()`, `ingres_commit()`, and `ingres_autocommit()`.

XLVII. IRC Gateway Functions

What is ircg?

With ircg you can build powerful, fast and scalable webchat solutions in conjunction with dedicated or public IRC servers.

Platforms

IRCG runs under

- AIX
- FreeBSD
- HP-UX
- Irix
- Linux
- Solaris
- Tru64

Requirements

To install and use IRCG you need the following software:

1. IRCG-Library (<http://www.schumann.cx/ircg/>) from Sascha Schumann.
2. SGI Static Threads Library (<http://sourceforge.net/projects/state-threads/>)
3. tthttpd (<http://www.acme.com/software/tthttpd/>) webserver

Installation

A detailed installation instruction can be found here (<http://lxr.php.net/source/php4/ext/ircg/README.txt>).

ircg_channel_mode (PHP 4 >= 4.0.5)

Set channel mode flags for user

boolean **ircg_channel_mode** (resource connection, string channel, string mode_spec, string nick) \linebreak

Set channel mode flags for *channel* on server connected to by *connection*. Mode flags are passed in *mode_spec* and are applied to the user specified by *nick*.

Mode flags are set or cleared by specifying a mode character and prepending it with a plus or minus character respectively. E.g. operator mode is granted by '+o' and revoked by '-o' passed as *mode_spec*.

ircg_disconnect (PHP 4 >= 4.0.4)

Close connection to server

boolean **ircg_disconnect** (resource connection, string reason) \linebreak

ircg_disconnect() will close a *connection* to a server previously established with *ircg_pconnect()*.

See also: *ircg_pconnect()*.

ircg_fetch_error_msg (PHP 4 >= 4.1.0)

Returns the error from previous ircg operation

array **ircg_fetch_error_msg** (resource connection) \linebreak

ircg_fetch_error_msg() returns the error from the last called ircg function.

Poznámka: Errorcode is stored in first array element, errortext in second.

Příklad 1. ircg_fetch_error_msg() example

```
if (!ircg_join ($id, "#php")) {
    $error = ircg_fetch_error_msg($id);
    print ("Can't join channel #php. Errorcode:
           $error[0] Description: $error[1]");
}
```

ircg_get_username (PHP 4 >= 4.1.0)

Get username for connection

string **ircg_get_username** (int connection) \linebreak

Function **ircg_get_username()** returns the username for specified connection *connection*.
Returns `FALSE` if *connection* died or is not valid.

ircg_html_encode (PHP 4 >= 4.0.5)

Encodes HTML preserving output

boolean **ircg_html_encode** (string html_string) \linebreak

Encodes a HTML string *html_string* for output. This feature could be usable, e.g. if someone wants to discuss about an html problem.

ircg_ignore_add (PHP 4 >= 4.0.5)

Add a user to your ignore list on a server

boolean **ircg_ignore_add** (resource connection, string nick) \linebreak

This function will add user *nick* to your ignore list on the server connected to by *connection*.
By doing so you will suppress all messages from this user from being send to you.

See also: `ircg_ignore_del()`.

ircg_ignore_del (PHP 4 >= 4.0.5)

Remove a user from your ignore list on a server

boolean **ircg_ignore_del** (resource connection, string nick) \linebreak

This function remove user *nick* from your ignore list on the server connected to by *connection*.

See also: `ircg_ignore_add()`.

ircg_is_conn_alive (PHP 4 >= 4.0.5)

Check connection status

boolean **ircg_is_conn_alive** (resource connection) \linebreak

ircg_is_conn_alive() returns `TRUE` if *connection* is still alive and working or `FALSE` if the server no longer talks to us.

ircg_join (PHP 4 >= 4.0.4)

Join a channel on a connected server

boolean **ircg_join** (resource connection, string channel) \linebreak

Join the channel *channel* on the server connected to by *connection*.

ircg_kick (PHP 4 >= 4.0.5)

Kick a user out of a channel on server

boolean **ircg_kick** (resource connection, string channel, string nick, string reason) \linebreak

Kick user *nick* from *channel* on server connected to by *connection*. *reason* should give a short message describing why this action was performed.

ircg_lookup_format_messages (PHP 4 >= 4.0.5)

Select a set of format strings for display of IRC messages

boolean **ircg_lookup_format_messages** (string name) \linebreak

Select the set of format strings to use for display of IRC messages and events. Sets may be registered with `ircg_register_format_messages()`, a default set named `ircg` is always available.

See also: `ircg_register_format_messages()`

ircg_msg (PHP 4 >= 4.0.4)

Send message to channel or user on server

boolean **ircg_msg** (resource connection, string recipient, string message [, boolean suppress]) \linebreak

ircg_msg() will send the message to a channel or user on the server connected to by *connection*. A *recipient* starting with # or & will send the *message* to a channel, anything else will be interpreted as a username.

Setting the optional parameter *suppress* to a TRUE value will suppress output of your message to your own *connection*.

ircg_nick (PHP 4 >= 4.0.5)

Change nickname on server

boolean **ircg_nick** (resource connection, string nick) \linebreak

Change your nickname on the given *connection* to the one given in *nick* if possible.

Will return `TRUE` on success and `FALSE` on failure.

ircg_nickname_escape (PHP 4 >= 4.0.6)

Encode special characters in nickname to be IRC-compliant

string **ircg_nickname_escape** (string *nick*) \linebreak

Function **ircg_nickname_escape()** returns a decoded nickname specified by *nick* wich is IRC-compliant.

See also: `ircg_nickname_unescape()`

ircg_nickname_unescape (PHP 4 >= 4.0.6)

Decodes encoded nickname

string **ircg_nickname_unescape** (string *nick*) \linebreak

Function **ircg_nickname_unescape()** returns a decoded nickname, which is specified in *nick*.

See also: `ircg_nickname_escape()`

ircg_notice (PHP 4 >= 4.0.5)

Send a notice to a user on server

boolean **ircg_notice** (resource *connection*, string , string *message*) \linebreak

This function will send the *message* text to the user *nick* on the server connected to by *connection*. Query your IRC documentation of choice for the exact difference between a MSG and a NOTICE.

ircg_part (PHP 4 >= 4.0.4)

Leave a channel on server

boolean **ircg_part** (resource *connection*, string *channel*) \linebreak

Leave the channel *channel* on the server connected to by *connection*.

ircg_pconnect (PHP 4 >= 4.0.4)

Connect to an IRC server

resource **ircg_pconnect** (string *username* [, string *server_ip* [, int *server_port* [, string *msg_format* [, array *ctcp_messages* [, array *user_settings*]]]]]) \linebreak

ircg_pconnect() will try to establish a connection to an IRC server and return a connection resource handle for further use.

The only mandatory parameter is *username*, this will set your initial nickname on the server. *server_ip* and *server_port* are optional and default to 127.0.0.1 and 6667.

Poznámka: For now parameter *server_ip* will not do any hostname lookups and will only accept IP addresses in numerical form.

Currently **ircg_pconnect()** always returns a valid handle, even if the connection failed.

You can customize the output of IRC messages and events by selection a format string set previously created with `ircg_register_format_messages()` by specifying the sets name in *msg_format*.

ctcp_messages

user_settings

See also: `ircg_disconnect()`, `ircg_is_conn_alive()`, `ircg_register_format_messages()`.

ircg_register_format_messages (PHP 4 >= 4.0.5)

Register a set of format strings for display of IRC messages

boolean **ircg_register_format_messages** (string *name*, array *messages*) \linebreak

With **ircg_register_format_messages()** you can customize the way your IRC output looks like. You can even register different format string sets and switch between them on the fly with `ircg_lookup_format_messages()`.

- Plain channel message
- Private message received
- Private message sent
- Some user leaves channel
- Some user enters channel
- Some user was kicked from the channel
- Topic has been changed
- Error
- Fatal error
- Join list end(?)

- Self part(?)
- Some user changes his nick
- Some user quits his connection
- Mass join begin
- Mass join element
- Mass join end
- Whois user
- Whois server
- Whois idle
- Whois channel
- Whois end
- Voice status change on user
- Operator status change on user
- Banlist
- Banlist end
- %f - from
- %t - to
- %c - channel
- %r - plain message
- %m - encoded message
- %j - js encoded message
- 1 - mod encode
- 2 - nickname decode

See also: `ircg_lookup_format_messages()`.

ircg_set_current (PHP 4 >= 4.0.4)

Set current connection for output

boolean **ircg_set_current** (resource connection) \linebreak

Select the current connection for output in this execution context. Every output sent from the server connected to by *connection* will be copied to standard output while using default formatting or a format string set specified by `ircg_register_format_messages()` and selected by `ircg_lookup_format_messages()`.

See also: `ircg_register_format_messages()` and `ircg_lookup_format_messages()`.

ircg_set_file (PHP 4 >= 4.2.0)

Set logfile for connection

bool **ircg_set_file** (int connection, string path) \linebreak

Function **ircg_set_file()** specifies a logfile *path* in which all output from connection *connection* will be logged. Returns TRUE on success, otherwise FALSE.

ircg_set_on_die (PHP 4 >= 4.2.0)

Set hostaction to be execute when connection dies

bool **ircg_set_on_die** (int connection, string host, int port, string data) \linebreak

In case of the termination of connection *connection* IRCG will connect to *host* at *port* (Note: host must be an IPv4 address, IRCG does not resolve host-names due to blocking issues), send *data* to the new host connection and will wait until the remote part closes connection. This can be used to trigger a php script for example.

ircg_topic (PHP 4 >= 4.0.5)

Set topic for channel on server

boolean **ircg_topic** (resource connection, string channel, string new_topic) \linebreak

Change the topic for channel *channel* on the server connected to by *connection* to *new_topic*.

ircg_whois (PHP 4 >= 4.0.5)

Query user information for nick on server

boolean **ircg_whois** (resource connection, string nick) \linebreak

Sends a query to the connected server *connection* to send information for the specified user *nick*.

XLVIII. Java

There are two possible ways to bridge PHP and Java: you can either integrate PHP into a Java Servlet environment, which is the more stable and efficient solution, or integrate Java support into PHP. The former is provided by a SAPI module that interfaces with the Servlet server, the latter by the Java extension.

PHP 4 ext/java provides a simple and effective means for creating and invoking methods on Java objects from PHP. The JVM is created using JNI, and everything runs in-process. Build instructions for ext/java can be found in `php4/ext/java/README`.

Příklad 1. Java Example

```
<?php
// get instance of Java class java.lang.System in PHP
$system = new Java('java.lang.System');

// demonstrate property access
print 'Java version=' . $system->getProperty('java.version') . ' <br>';
print 'Java vendor=' . $system->getProperty('java.vendor') . ' <br>';
print 'OS=' . $system->getProperty('os.name') . ' ' .
      $system->getProperty('os.version') . ' on ' .
      $system->getProperty('os.arch') . ' <br>';

// java.util.Date example
$formatter = new Java('java.text.SimpleDateFormat',
                      "EEEE, MMMM dd, yyyy 'at' h:mm:ss a zzzz");

print $formatter->format(new Java('java.util.Date'));
?>
```

Příklad 2. AWT Example

```
<?php
// This example is only intended to be run as a CGI.

$frame = new Java('java.awt.Frame', 'PHP');
$button = new Java('java.awt.Button', 'Hello Java World!');

$frame->add('North', $button);
$frame->validate();
$frame->pack();
$frame->visible = True;

$thread = new Java('java.lang.Thread');
$thread->sleep(10000);

$frame->dispose();
?>
```

Notes:

- `new Java()` will create an instance of a class if a suitable constructor is available. If no parameters are passed and the default constructor is useful as it provides access to classes like `java.lang.System` which expose most of their functionality through static methods.
- Accessing a member of an instance will first look for bean properties then public fields. In other words, `print $date.time` will first attempt to be resolved as `$date.getTime()`, then as `$date.time`.
- Both static and instance members can be accessed on an object with the same syntax. Furthermore, if the java object is of type `java.lang.Class`, then static members of the class (fields and methods) can be accessed.
- Exceptions raised result in PHP warnings, and `NULL` results. The warnings may be eliminated by prefixing the method call with an "@" sign. The following APIs may be used to retrieve and reset the last error:
 - `java_last_exception_get()`
 - `java_last_exception_clear()`
- Overload resolution is in general a hard problem given the differences in types between the two languages. The PHP Java extension employs a simple, but fairly effective, metric for determining which overload is the best match.

Additionally, method names in PHP are not case sensitive, potentially increasing the number of overloads to select from.

Once a method is selected, the parameters are coerced if necessary, possibly with a loss of data (example: double precision floating point numbers will be converted to boolean).

- In the tradition of PHP, arrays and hashtables may pretty much be used interchangeably. Note that hashtables in PHP may only be indexed by integers or strings; and that arrays of primitive types in Java can not be sparse. Also note that these constructs are passed by value, so may be expensive in terms of memory and time.

`sapi/servlet` builds upon the mechanism defined by `ext/java` to enable the entire PHP processor to be run as a servlet. The primary advantage of this from a PHP perspective is that web servers which support servlets typically take great care in pooling and reusing JVMs. Build instructions for the Servlet SAPI module can be found in `php4/sapi/README`. Notes:

- While this code is intended to be able to run on any servlet engine, it has only been tested on Apache's Jakarta/tomcat to date. Bug reports, success stories and/or patches required to get this code to run on other engines would be appreciated.
- PHP has a habit of changing the working directory. `sapi/servlet` will eventually change it back, but while PHP is running the servlet engine may not be able to load any classes from the `CLASSPATH` which are specified using a relative directory syntax, or find the work directory used for administration and JSP compilation tasks.

java_last_exception_clear (PHP 4 >= 4.0.2)

Clear last Java exception

```
void java_last_exception_clear ( void) \linebreak
```

java_last_exception_get (PHP 4 >= 4.0.2)

Get last Java exception

```
exception java_last_exception_get ( void) \linebreak
```

The following example demonstrates the usage of Java's exception handler from within PHP:

Příklad 1. Java exception handler

```
<?php
    $stack = new Java('java.util.Stack');
    $stack->push(1);

    // This should succeed
    $result = $stack->pop();
    $ex = java_last_exception_get();
    if (!$ex) print "$result\n";

    // This should fail (error suppressed by @)
    $result = @$stack->pop();
    $ex = java_last_exception_get();
    if ($ex) print $ex->toString();

    // Clear last exception
    java_last_exception_clear();
?>
```

XLIX. LDAP functions

Introduction to LDAP

LDAP is the Lightweight Directory Access Protocol, and is a protocol used to access "Directory Servers". The Directory is a special kind of database that holds information in a tree structure.

The concept is similar to your hard disk directory structure, except that in this context, the root directory is "The world" and the first level subdirectories are "countries". Lower levels of the directory structure contain entries for companies, organisations or places, while yet lower still we find directory entries for people, and perhaps equipment or documents.

To refer to a file in a subdirectory on your hard disk, you might use something like

```
/usr/local/myapp/docs
```

The forwards slash marks each division in the reference, and the sequence is read from left to right.

The equivalent to the fully qualified file reference in LDAP is the "distinguished name", referred to simply as "dn". An example dn might be.

```
cn=John Smith,ou=Accounts,o=My Company,c=US
```

The comma marks each division in the reference, and the sequence is read from right to left. You would read this dn as ..

```
country = US
organization = My Company
organizationalUnit = Accounts
commonName = John Smith
```

In the same way as there are no hard rules about how you organise the directory structure of a hard disk, a directory server manager can set up any structure that is meaningful for the purpose. However, there are some conventions that are used. The message is that you can not write code to access a directory server unless you know something about its structure, any more than you can use a database without some knowledge of what is available.

Complete code example

Retrieve information for all entries where the surname starts with "S" from a directory server, displaying an extract with name and email address.

Příklad 1. LDAP search example

```
<?php
// basic sequence with LDAP is connect, bind, search, interpret search
// result, close connection
```

```

echo "<h3>LDAP query test</h3>";
echo "Connecting ...";
$ds=ldap_connect("localhost"); // must be a valid LDAP server!
echo "connect result is ".$ds."<p>";

if ($ds) {
    echo "Binding ...";
    $r=ldap_bind($ds); // this is an "anonymous" bind, typically
                      // read-only access
    echo "Bind result is ".$r."<p>";

    echo "Searching for (sn=S*) ...";
    // Search surname entry
    $sr=ldap_search($ds,"o=My Company, c=US", "sn=S*");
    echo "Search result is ".$sr."<p>";

    echo "Number of entires returned is ".ldap_count_entries($ds,$sr)."<p>";

    echo "Getting entries ...<p>";
    $info = ldap_get_entries($ds, $sr);
    echo "Data for ".$info["count"]." items returned:<p>";

    for ($i=0; $i<$info["count"]; $i++) {
        echo "dn is: ". $info[$i]["dn"] ."<br>";
        echo "first cn entry is: ". $info[$i]["cn"][0] ."<br>";
        echo "first email entry is: ". $info[$i]["mail"][0] ."<p>";
    }

    echo "Closing connection";
    ldap_close($ds);
} else {
    echo "<h4>Unable to connect to LDAP server</h4>";
}
?>

```

Using the PHP LDAP calls

You will need to get and compile LDAP client libraries from either the University of Michigan ldap-3.3 package or the Netscape Directory SDK 3.0. You will also need to recompile PHP with LDAP support enabled before PHP's LDAP calls will work.

Before you can use the LDAP calls you will need to know ..

- The name or address of the directory server you will use
- The "base dn" of the server (the part of the world directory that is held on this server, which could be "o=My Company,c=US")
- Whether you need a password to access the server (many servers will provide read access for an

"anonymous bind" but require a password for anything else)

The typical sequence of LDAP calls you will make in an application will follow this pattern:

```
ldap_connect() // establish connection to server
|
ldap_bind()    // anonymous or authenticated "login"
|
do something like search or update the directory
and display the results
|
ldap_close()   // "logout"
```

More Information

Lots of information about LDAP can be found at

- Netscape (<http://developer.netscape.com/tech/directory/>)
- University of Michigan (<http://www.umich.edu/~dirsvcs/ldap/index.html>)
- OpenLDAP Project (<http://www.openldap.org/>)
- LDAP World (<http://www.innosoft.com/ldapworld>)

The Netscape SDK contains a helpful Programmer's Guide in .html format.

ldap_8859_to_t61 (PHP 4 >= 4.0.2)

Translate 8859 characters to t61 characters

string **ldap_8859_to_t61** (string value) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_add (PHP 3, PHP 4 >= 4.0.0)

Add entries to LDAP directory

bool **ldap_add** (resource link_identifier, string dn, array entry) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

The **ldap_add()** function is used to add entries in the LDAP directory. The DN of the entry to be added is specified by *dn*. Array *entry* specifies the information about the entry. The values in the entries are indexed by individual attributes. In case of multiple values for an attribute, they are indexed using integers starting with 0.

```
entry["attribute1"] = value
entry["attribute2"][0] = value1
entry["attribute2"][1] = value2
```

Příklad 1. Complete example with authenticated bind

```
<?php
$ds=ldap_connect("localhost"); // assuming the LDAP server is on this host

if ($ds) {
    // bind with appropriate dn to give update access
    $r=ldap_bind($ds,"cn=root, o=My Company, c=US", "secret");

    // prepare data
    $info["cn"]="John Jones";
    $info["sn"]="Jones";
    $info["mail"]="jonj@here.and.now";
    $info["objectclass"]="person";

    // add data to directory
    $r=ldap_add($ds, "cn=John Jones, o=My Company, c=US", $info);

    ldap_close($ds);
} else {
    echo "Unable to connect to LDAP server";
```

```
}
?>
```

ldap_bind (PHP 3, PHP 4 >= 4.0.0)

Bind to LDAP directory

```
bool ldap_bind ( resource link_identifier [, string bind_rdn [, string bind_password]]) \linebreak
```

Binds to the LDAP directory with specified RDN and password. Vrací TRUE při úspěchu, FALSE při selhání.

ldap_bind() does a bind operation on the directory. *bind_rdn* and *bind_password* are optional. If not specified, anonymous bind is attempted.

ldap_close (PHP 3, PHP 4 >= 4.0.0)

Close link to LDAP server

```
bool ldap_close ( resource link_identifier) \linebreak
```

Vrací TRUE při úspěchu, FALSE při selhání.

ldap_close() closes the link to the LDAP server that's associated with the specified *link_identifier*.

This call is internally identical to **ldap_unbind()**. The LDAP API uses the call **ldap_unbind()**, so perhaps you should use this in preference to **ldap_close()**.

Poznámka: This function is an alias of **ldap_unbind()**.

ldap_compare (PHP 4 >= 4.0.2)

Compare value of attribute found in entry specified with DN

```
bool ldap_compare ( resource link_identifier, string dn, string attribute, string value) \linebreak
```

Returns TRUE if *value* matches otherwise returns FALSE. Returns -1 on error.

ldap_compare() is used to compare *value* of *attribute* to value of same attribute in LDAP directory entry specified with *dn*.

The following example demonstrates how to check whether or not given password matches the one defined in DN specified entry.

Příklad 1. Complete example of password check

```

<?php

$ds=ldap_connect("localhost"); // assuming the LDAP server is on this host

if ($ds) {

    // bind
    if(ldap_bind($ds)) {

        // prepare data
        $dn = "cn=Matti Meikku, ou=My Unit, o=My Company, c=FI";
        $value = "secretpassword";
        $attr = "password";

        // compare value
        $r=ldap_compare($ds, $dn, $attr, $value);

        if ($r === -1) {
            echo "Error: ".ldap_error($ds);
        } elseif ($r === TRUE) {
            echo "Password correct.";
        } elseif ($r === FALSE) {
            echo "Wrong guess! Password incorrect.";
        }

    } else {
        echo "Unable to bind to LDAP server.";
    }

    ldap_close($ds);

} else {
    echo "Unable to connect to LDAP server.";
}
?>

```

Varování

ldap_compare() can NOT be used to compare BINARY values!

Poznámka: This function was added in 4.0.2.

ldap_connect (PHP 3, PHP 4 >= 4.0.0)

Connect to an LDAP server

resource **ldap_connect** ([string hostname [, int port]]) \linebreak

Returns a positive LDAP link identifier on success, or `FALSE` on error.

ldap_connect() establishes a connection to a LDAP server on a specified *hostname* and *port*. Both the arguments are optional. If no arguments are specified then the link identifier of the already opened link will be returned. If only *hostname* is specified, then the port defaults to 389.

If you are using OpenLDAP 2.x.x you can specify a URL instead of the hostname. To use LDAP with SSL, compile OpenLDAP 2.x.x with SSL support, configure PHP with SSL, and use `ldaps://hostname/` as host parameter. The port parameter is not used when using URLs.

Poznámka: URL and SSL support were added in 4.0.4.

ldap_count_entries (PHP 3, PHP 4 >= 4.0.0)

Count the number of entries in a search

int **ldap_count_entries** (resource link_identifier, resource result_identifier) \linebreak

Returns number of entries in the result or `FALSE` on error.

ldap_count_entries() returns the number of entries stored in the result of previous search operations. *result_identifier* identifies the internal ldap result.

ldap_delete (PHP 3, PHP 4 >= 4.0.0)

Delete an entry from a directory

bool **ldap_delete** (resource link_identifier, string dn) \linebreak

Vrací `TRUE` při úspěchu, `FALSE` při selhání.

ldap_delete() function delete a particular entry in LDAP directory specified by *dn*.

ldap_dn2ufn (PHP 3, PHP 4 >= 4.0.0)

Convert DN to User Friendly Naming format

string **ldap_dn2ufn** (string dn) \linebreak

ldap_dn2ufn() function is used to turn a DN, specified by *dn*, into a more user-friendly form, stripping off type names.

ldap_err2str (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Convert LDAP error number into string error message

string **ldap_err2str** (int *errno*) \linebreak

Returns string error message.

This function returns the string error message explaining the error number *errno*. While LDAP *errno* numbers are standardized, different libraries return different or even localized textual error messages. Never check for a specific error message text, but always use an error number to check.

See also `ldap_errno()` and `ldap_error()`.

Příklad 1. Enumerating all LDAP error messages

```
<?php
    for($i=0; $i<100; $i++) {
        printf("Error $i: %s<br>\n", ldap_err2str($i));
    }
?>
```

ldap_errno (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Return the LDAP error number of the last LDAP command

int **ldap_errno** (resource *link_identifier*) \linebreak

Return the LDAP error number of the last LDAP command for this link.

This function returns the standardized error number returned by the last LDAP command for the given *link_identifier*. This number can be converted into a textual error message using `ldap_err2str()`.

Unless you lower your warning level in your `php.ini` sufficiently or prefix your LDAP commands with @ (at) characters to suppress warning output, the errors generated will also show up in your HTML output.

Příklad 1. Generating and catching an error

```
<?php
// This example contains an error, which we will catch.
$lid = ldap_connect("localhost");
$bind = ldap_bind($lid);
// syntax error in filter expression (errno 87),
// must be "objectclass=*" to work.
$res = @ldap_search($lid, "o=Myorg, c=DE", "objectclass");
if (!$res) {
    printf("LDAP-Errno: %s<br>\n", ldap_errno($lid));
    printf("LDAP-Error: %s<br>\n", ldap_error($lid));
}
```

```

        die("Argh!<br>\n");
    }
    $info = ldap_get_entries($ld, $res);
    printf("%d matching entries.<br>\n", $info["count"]);
?>

```

See also `ldap_err2str()` and `ldap_error()`.

ldap_error (PHP 3 >= 3.0.12, PHP 4 >= 4.0.0)

Return the LDAP error message of the last LDAP command

string **ldap_error** (resource link_identifier) \linebreak

Returns string error message.

This function returns the string error message explaining the error generated by the last LDAP command for the given *link_identifier*. While LDAP errno numbers are standardized, different libraries return different or even localized textual error messages. Never check for a specific error message text, but always use an error number to check.

Unless you lower your warning level in your `php.ini` sufficiently or prefix your LDAP commands with @ (at) characters to suppress warning output, the errors generated will also show up in your HTML output.

See also `ldap_err2str()` and `ldap_errno()`.

ldap_explode_dn (PHP 3, PHP 4 >= 4.0.0)

Splits DN into its component parts

array **ldap_explode_dn** (string dn, int with_attr) \linebreak

ldap_explode_dn() function is used to split the DN returned by `ldap_get_dn()` and breaks it up into its component parts. Each part is known as Relative Distinguished Name, or RDN.

ldap_explode_dn() returns an array of all those components. *with_attr* is used to request if the RDNs are returned with only values or their attributes as well. To get RDNs with the attributes (i.e. in attribute=value format) set *with_attr* to 0 and to get only values set it to 1.

ldap_first_attribute (PHP 3, PHP 4 >= 4.0.0)

Return first attribute

string **ldap_first_attribute** (resource link_identifier, resource result_entry_identifier, int ber_identifier) \linebreak

Returns the first attribute in the entry on success and `FALSE` on error.

Similar to reading entries, attributes are also read one by one from a particular entry.

ldap_first_attribute() returns the first attribute in the entry pointed by the *result_entry_identifier*. Remaining attributes are retrieved by calling **ldap_next_attribute()** successively. *ber_identifier* is the identifier to internal memory location pointer. It is passed by reference. The same *ber_identifier* is passed to the **ldap_next_attribute()** function, which modifies that pointer.

See also **ldap_get_attributes()**

ldap_first_entry (PHP 3, PHP 4 >= 4.0.0)

Return first result id

resource **ldap_first_entry** (resource link_identifier, resource result_identifier) \linebreak

Returns the result entry identifier for the first entry on success and **FALSE** on error.

Entries in the LDAP result are read sequentially using the **ldap_first_entry()** and **ldap_next_entry()** functions. **ldap_first_entry()** returns the entry identifier for first entry in the result. This entry identifier is then supplied to **ldap_next_entry()** routine to get successive entries from the result.

See also **ldap_get_entries()**.

ldap_first_reference (PHP 4 >= 4.0.5)

Return first reference

resource **ldap_first_reference** (resource link, resource result) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_free_result (PHP 3, PHP 4 >= 4.0.0)

Free result memory

bool **ldap_free_result** (resource result_identifier) \linebreak

Vrací **TRUE** při úspěchu, **FALSE** při selhání.

ldap_free_result() frees up the memory allocated internally to store the result and pointed by the *result_identifier*. All result memory will be automatically freed when the script terminates.

Typically all the memory allocated for the ldap result gets freed at the end of the script. In case the script is making successive searches which return large result sets, **ldap_free_result()** could be called to keep the runtime memory usage by the script low.

ldap_get_attributes (PHP 3, PHP 4 >= 4.0.0)

Get attributes from a search result entry

array **ldap_get_attributes** (resource link_identifier, resource result_entry_identifier) \linebreak

Returns a complete entry information in a multi-dimensional array on success and FALSE on error.

ldap_get_attributes() function is used to simplify reading the attributes and values from an entry in the search result. The return value is a multi-dimensional array of attributes and values.

Having located a specific entry in the directory, you can find out what information is held for that entry by using this call. You would use this call for an application which "browses" directory entries and/or where you do not know the structure of the directory entries. In many applications you will be searching for a specific attribute such as an email address or a surname, and won't care what other data is held.

return_value["count"] = number of attributes in the entry

return_value[0] = first attribute

return_value[n] = nth attribute

return_value["attribute"]["count"] = number of values for attribute

return_value["attribute"][0] = first value of the attribute

return_value["attribute"][i] = (i+1)th value of the attribute

Příklad 1. Show the list of attributes held for a particular directory entry

```
// $ds is the link identifier for the directory

// $sr is a valid search result from a prior call to
// one of the ldap directory search calls

$entry = ldap_first_entry($ds, $sr);

$attrs = ldap_get_attributes($ds, $entry);

echo $attrs["count"]." attributes held for this entry:<p>";

for ($i=0; $i<$attrs["count"]; $i++)
    echo $attrs[$i]."<br>";
```

See also `ldap_first_attribute()` and `ldap_next_attribute()`

ldap_get_dn (PHP 3, PHP 4 >= 4.0.0)

Get the DN of a result entry

string **ldap_get_dn** (resource link_identifier, resource result_entry_identifier) \linebreak

Returns the DN of the result entry and FALSE on error.

ldap_get_dn() function is used to find out the DN of an entry in the result.

ldap_get_entries (PHP 3, PHP 4 >= 4.0.0)

Get all result entries

array **ldap_get_entries** (resource link_identifier, resource result_identifier) \linebreak

Returns a complete result information in a multi-dimensional array on success and FALSE on error.

ldap_get_entries() function is used to simplify reading multiple entries from the result, specified with *result_identifier*, and then reading the attributes and multiple values. The entire information is returned by one function call in a multi-dimensional array. The structure of the array is as follows.

The attribute index is converted to lowercase. (Attributes are case-insensitive for directory servers, but not when used as array indices.)

return_value["count"] = number of entries in the result

return_value[0] : refers to the details of first entry

return_value[i]["dn"] = DN of the ith entry in the result

return_value[i]["count"] = number of attributes in ith entry

return_value[i][j] = jth attribute in the ith entry in the result

return_value[i]["attribute"]["count"] = number of values for
attribute in ith entry

return_value[i]["attribute"][j] = jth value of attribute in ith entry

See also `ldap_first_entry()` and `ldap_next_entry()`

ldap_get_option (PHP 4 >= 4.0.4)

Get the current value for given option

bool **ldap_get_option** (resource link_identifier, int option, mixed retval) \linebreak

Sets *retval* to the value of the specified option. Vrací TRUE při úspěchu, FALSE při selhání.

The parameter *option* can be one of: LDAP_OPT_DEREF, LDAP_OPT_SIZELIMIT, LDAP_OPT_TIMELIMIT, LDAP_OPT_PROTOCOL_VERSION,

LDAP_OPT_ERROR_NUMBER, LDAP_OPT_REFERRALS, LDAP_OPT_RESTART,
LDAP_OPT_HOST_NAME, LDAP_OPT_ERROR_STRING, LDAP_OPT_MATCHED_DN.

These are described in draft-ietf-ldapext-ldap-c-api-xx.txt

(<http://www.openldap.org/devel/cvsweb.cgi/~checkout~/doc/drafts/draft-ietf-ldapext-ldap-c-api-xx.txt>)

Poznámka: This function is only available when using OpenLDAP 2.x.x OR Netscape Directory SDK x.x, and was added in PHP 4.0.4

Příklad 1. Check protocol version

```
// $ds is a valid link identifier for a directory server
if (ldap_get_option($ds, LDAP_OPT_PROTOCOL_VERSION, $version))
    echo "Using protocol version $version";
else
    echo "Unable to determine protocol version";
```

See also `ldap_set_option()`.

ldap_get_values (PHP 3, PHP 4 >= 4.0.0)

Get all values from a result entry

array **ldap_get_values** (resource link_identifier, resource result_entry_identifier, string attribute) \linebreak

Returns an array of values for the attribute on success and FALSE on error.

ldap_get_values() function is used to read all the values of the attribute in the entry in the result. entry is specified by the *result_entry_identifier*. The number of values can be found by indexing "count" in the resultant array. Individual values are accessed by integer index in the array. The first index is 0.

This call needs a *result_entry_identifier*, so needs to be preceded by one of the ldap search calls and one of the calls to get an individual entry.

You application will either be hard coded to look for certain attributes (such as "surname" or "mail") or you will have to use the `ldap_get_attributes()` call to work out what attributes exist for a given entry.

LDAP allows more than one entry for an attribute, so it can, for example, store a number of email addresses for one person's directory entry all labeled with the attribute "mail"

```
return_value["count"] = number of values for attribute
return_value[0] = first value of attribute
return_value[i] = ith value of attribute
```

Příklad 1. List all values of the "mail" attribute for a directory entry

```
// $ds is a valid link identifier for a directory server

// $sr is a valid search result from a prior call to
//     one of the ldap directory search calls

// $entry is a valid entry identifier from a prior call to
//     one of the calls that returns a directory entry

$values = ldap_get_values($ds, $entry, "mail");

echo $values["count"]." email addresses for this entry.<p>";

for ($i=0; $i < $values["count"]; $i++)
    echo $values[$i]."<br>";
```

ldap_get_values_len (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Get all binary values from a result entry

array **ldap_get_values_len** (resource link_identifier, resource result_entry_identifier, string attribute) \linebreak

Returns an array of values for the attribute on success and FALSE on error.

ldap_get_values_len() function is used to read all the values of the attribute in the entry in the result. entry is specified by the *result_entry_identifier*. The number of values can be found by indexing "count" in the resultant array. Individual values are accessed by integer index in the array. The first index is 0.

This function is used exactly like `ldap_get_values()` except that it handles binary data and not string data.

Poznámka: This function was added in 4.0.

ldap_list (PHP 3, PHP 4 >= 4.0.0)

Single-level search

resource **ldap_list** (resource link_identifier, string base_dn, string filter [, array attributes [, int attrsonly [, int sizelimit [, int timelimit [, int deref]]]]) \linebreak

Returns a search result identifier or FALSE on error.

ldap_list() performs the search for a specified *filter* on the directory with the scope LDAP_SCOPE_ONELEVEL.

LDAP_SCOPE_ONELEVEL means that the search should only return information that is at the level immediately below the *base_dn* given in the call. (Equivalent to typing "ls" and getting a list of files and folders in the current working directory.)

This call takes 5 optional parameters. See `ldap_search()` notes.

Poznámka: These optional parameters were added in 4.0.2: *attrsonly*, *sizelimit*, *timelimit*, *deref*.

Příklad 1. Produce a list of all organizational units of an organization

```
// $ds is a valid link identifier for a directory server

$basedn = "o=My Company, c=US";
$justthese = array("ou");

$sr=ldap_list($ds, $basedn, "ou=", $justthese);

$info = ldap_get_entries($ds, $sr);

for ($i=0; $i<$info["count"]; $i++)
    echo $info[$i]["ou"][0] ;
```

Poznámka: From 4.0.5 on it's also possible to do parallel searches. See `ldap_search()` for details.

ldap_mod_add (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Add attribute values to current attributes

bool **ldap_mod_add** (resource link_identifier, string dn, array entry) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

This function adds attribute(s) to the specified *dn*. It performs the modification at the attribute level as opposed to the object level. Object-level additions are done by the `ldap_add()` function.

ldap_mod_del (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Delete attribute values from current attributes

bool **ldap_mod_del** (resource link_identifier, string dn, array entry) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

This function removes attribute(s) from the specified *dn*. It performs the modification at the attribute level as opposed to the object level. Object-level deletions are done by the `ldap_delete()` function.

ldap_mod_replace (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Replace attribute values with new ones

bool **ldap_mod_replace** (resource link_identifier, string dn, array entry) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

This function replaces attribute(s) from the specified *dn*. It performs the modification at the attribute level as opposed to the object level. Object-level modifications are done by the `ldap_modify()` function.

ldap_modify (PHP 3, PHP 4 >= 4.0.0)

Modify an LDAP entry

bool **ldap_modify** (resource link_identifier, string dn, array entry) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

ldap_modify() function is used to modify the existing entries in the LDAP directory. The structure of the entry is same as in `ldap_add()`.

ldap_next_attribute (PHP 3, PHP 4 >= 4.0.0)

Get the next attribute in result

string **ldap_next_attribute** (resource link_identifier, resource result_entry_identifier, resource ber_identifier) \linebreak

Returns the next attribute in an entry on success and FALSE on error.

ldap_next_attribute() is called to retrieve the attributes in an entry. The internal state of the pointer is maintained by the *ber_identifier*. It is passed by reference to the function. The first call to **ldap_next_attribute()** is made with the *result_entry_identifier* returned from `ldap_first_attribute()`.

See also `ldap_get_attributes()`

ldap_next_entry (PHP 3, PHP 4 >= 4.0.0)

Get next result entry

resource **ldap_next_entry** (resource link_identifier, resource result_entry_identifier) \linebreak

Returns entry identifier for the next entry in the result whose entries are being read starting with `ldap_first_entry()`. If there are no more entries in the result then it returns `FALSE`.

ldap_next_entry() function is used to retrieve the entries stored in the result. Successive calls to the **ldap_next_entry()** return entries one by one till there are no more entries. The first call to **ldap_next_entry()** is made after the call to `ldap_first_entry()` with the *result_entry_identifier* as returned from the `ldap_first_entry()`.

See also `ldap_get_entries()`

ldap_next_reference (PHP 4 >= 4.0.5)

Get next reference

resource **ldap_next_reference** (resource link, resource entry) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_parse_reference (PHP 4 >= 4.0.5)

Extract information from reference entry

bool **ldap_parse_reference** (resource link, resource entry, array referrals) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_parse_result (PHP 4 >= 4.0.5)

Extract information from result

bool **ldap_parse_result** (resource link, resource result, int errcode, string matcheddn, string errmsg, array referrals) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_read (PHP 3, PHP 4 >= 4.0.0)

Read an entry

resource **ldap_read** (resource link_identifier, string base_dn, string filter [, array attributes [, int attrsonly [, int sizelimit [, int timelimit [, int deref]]]]) \linebreak

Returns a search result identifier or FALSE on error.

ldap_read() performs the search for a specified *filter* on the directory with the scope LDAP_SCOPE_BASE. So it is equivalent to reading an entry from the directory.

An empty filter is not allowed. If you want to retrieve absolutely all information for this entry, use a filter of "objectClass=*". If you know which entry types are used on the directory server, you might use an appropriate filter such as "objectClass=inetOrgPerson".

This call takes 5 optional parameters. See ldap_search() notes.

Poznámka: These optional parameters were added in 4.0.2: *attrsonly*, *sizelimit*, *timelimit*, *deref*.

From 4.0.5 on it's also possible to do parallel searches. See ldap_search() for details.

ldap_rename (PHP 4 >= 4.0.5)

Modify the name of an entry

bool **ldap_rename** (resource link_identifier, string dn, string newrdn, string newparent, bool deleteoldrdn) \linebreak

The entry specified by *dn* is renamed/moved. The new RDN is specified by *newrdn* and the new parent/superior entry is specified by *newparent*. If the parameter *deleteoldrdn* is TRUE the old RDN value(s) is removed, else the old RDN value(s) is retained as non-distinguished values of the entry. Vrací TRUE při úspěchu, FALSE při selhání.

Poznámka: This function currently only works with LDAPv3. You may have to use ldap_set_option() prior to binding to use LDAPv3. This function is only available when using OpenLDAP 2.x.x OR Netscape Directory SDK x.x, and was added in PHP 4.0.5.

ldap_search (PHP 3, PHP 4 >= 4.0.0)

Search LDAP tree

resource **ldap_search** (resource link_identifier, string base_dn, string filter [, array attributes [, int attrsonly [, int sizelimit [, int timelimit [, int deref]]]]) \linebreak

Returns a search result identifier or FALSE on error.

ldap_search() performs the search for a specified filter on the directory with the scope of LDAP_SCOPE_SUBTREE. This is equivalent to searching the entire directory. *base_dn* specifies the base DN for the directory.

There is a optional fourth parameter, that can be added to restrict the attributes and values returned by the server to just those required. This is much more efficient than the default action (which is to return all attributes and their associated values). The use of the fourth parameter should therefore be considered good practice.

The fourth parameter is a standard PHP string array of the required attributes, eg array("mail","sn","cn") Note that the "dn" is always returned irrespective of which attributes types are requested.

Note too that some directory server hosts will be configured to return no more than a preset number of entries. If this occurs, the server will indicate that it has only returned a partial results set. This occurs also if the sixth parameter *sizelimit* has been used to limit the count of fetched entries.

The fifth parameter *attrsonly* should be set to 1 if only attribute types are wanted. If set to 0 both attributes types and attribute values are fetched which is the default behaviour.

With the sixth parameter *sizelimit* it is possible to limit the count of entries fetched. Setting this to 0 means no limit. NOTE: This parameter can NOT override server-side preset sizelimit. You can set it lower though.

The seventh parameter *timelimit* sets the number of seconds how long is spend on the search. Setting this to 0 means no limit. NOTE: This parameter can NOT override server-side preset timelimit. You can set it lower though.

The eighth parameter *deref* specifies how aliases should be handled during the search. It can be one of the following:

- LDAP_DEREF_NEVER - (default) aliases are never dereferenced.
- LDAP_DEREF_SEARCHING - aliases should be dereferenced during the search but not when locating the base object of the search.
- LDAP_DEREF_FINDING - aliases should be dereferenced when locating the base object but not during the search.
- LDAP_DEREF_ALWAYS - aliases should be dereferenced always.

Poznámka: These optional parameters were added in 4.0.2: *attrsonly*, *sizelimit*, *timelimit*, *deref*.

The search filter can be simple or advanced, using boolean operators in the format described in the LDAP doumentation (see the Netscape Directory SDK

(<http://developer.netscape.com/docs/manuals/directory/41/ag/find.htm>) for full information on filters).

The example below retrieves the organizational unit, surname, given name and email address for all people in "My Company" where the surname or given name contains the substring \$person. This example uses a boolean filter to tell the server to look for information in more than one attribute.

Příklad 1. LDAP search

```
// $ds is a valid link identifier for a directory server

// $person is all or part of a person's name, eg "Jo"

$dn = "o=My Company, c=US";
$filter="(|(sn=$person*)(givenname=$person*))";
$justthese = array( "ou", "sn", "givenname", "mail");

$sr=ldap_search($ds, $dn, $filter, $justthese);

$info = ldap_get_entries($ds, $sr);

print $info["count"]." entries returned<p>";
```

From 4.0.5 on it's also possible to do parallel searches. To do this you use an array of link identifiers, rather than a single identifier, as the first argument. If you don't want the same base DN and the same filter for all the searches, you can also use an array of base DN's and/or an array of filters. Those arrays must be of the same size as the link identifier array since the first entries of the arrays are used for one search, the second entries are used for another, and so on. When doing parallel searches an array of search result identifiers is returned, except in case of error, then the entry corresponding to the search will be FALSE. This is very much like the value normally returned, except that a result identifier is always returned when a search was made. There are some rare cases where the normal search returns FALSE while the parallel search returns an identifier.

ldap_set_option (PHP 4 >= 4.0.4)

Set the value of the given option

bool **ldap_set_option** (resource link_identifier, int option, mixed newval) \linebreak

Sets the value of the specified option to be *newval*. Vrací TRUE při úspěchu, FALSE při selhání. on error.

The parameter *option* can be one of: LDAP_OPT_DEREF, LDAP_OPT_SIZELIMIT, LDAP_OPT_TIMELIMIT, LDAP_OPT_PROTOCOL_VERSION, LDAP_OPT_ERROR_NUMBER, LDAP_OPT_REFERRALS, LDAP_OPT_RESTART, LDAP_OPT_HOST_NAME, LDAP_OPT_ERROR_STRING, LDAP_OPT_MATCHED_DN, LDAP_OPT_SERVER_CONTROLS, LDAP_OPT_CLIENT_CONTROLS. Here's a brief description, see draft-ietf-ldapext-ldap-c-api-xx.txt

(<http://www.openldap.org/devel/cvsweb.cgi/~checkout~/doc/drafts/draft-ietf-ldapext-ldap-c-api-xx.txt>) for details.

The options `LDAP_OPT_DEREF`, `LDAP_OPT_SIZELIMIT`, `LDAP_OPT_TIMELIMIT`, `LDAP_OPT_PROTOCOL_VERSION` and `LDAP_OPT_ERROR_NUMBER` have integer value, `LDAP_OPT_REFERRALS` and `LDAP_OPT_RESTART` have boolean value, and the options `LDAP_OPT_HOST_NAME`, `LDAP_OPT_ERROR_STRING` and `LDAP_OPT_MATCHED_DN` have string value. The first example illustrates their use. The options `LDAP_OPT_SERVER_CONTROLS` and `LDAP_OPT_CLIENT_CONTROLS` require a list of controls, this means that the value must be an array of controls. A control consists of an *oid* identifying the control, an optional *value*, and an optional flag for *criticality*. In PHP a control is given by an array containing an element with the key *oid* and string value, and two optional elements. The optional elements are key *value* with string value and key *iscritical* with boolean value. *iscritical* defaults to `FALSE` if not supplied. See also the second example below.

Poznámka: This function is only available when using OpenLDAP 2.x.x OR Netscape Directory SDK x.x, and was added in PHP 4.0.4.

Příklad 1. Set protocol version

```
// $ds is a valid link identifier for a directory server
if (ldap_set_option($ds, LDAP_OPT_PROTOCOL_VERSION, 3))
    echo "Using LDAPv3";
else
    echo "Failed to set protocol version to 3";
```

Příklad 2. Set server controls

```
// $ds is a valid link identifier for a directory server
// control with no value
$ctrl1 = array("oid" => "1.2.752.58.10.1", "iscritical" => TRUE);
// iscritical defaults to FALSE
$ctrl2 = array("oid" => "1.2.752.58.1.10", "value" => "magic");
// try to set both controls
if (!ldap_set_option($ds, LDAP_OPT_SERVER_CONTROLS, array($ctrl1, $ctrl2)))
    echo "Failed to set server controls";
```

See also `ldap_get_option()`.

ldap_set_rebind_proc (PHP 4 >= 4.2.0)

Set a callback function to do re-binds on referral chasing.

bool **ldap_set_rebind_proc** (resource link, string callback) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_sort (PHP 4 >= 4.2.0)

Sort LDAP result entries

bool **ldap_sort** (resource link, resource result, string sortfilter) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_start_tls (PHP 4 >= 4.2.0)

Start TLS

bool **ldap_start_tls** (resource link) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_t61_to_8859 (PHP 4 >= 4.0.2)

Translate t61 characters to 8859 characters

string **ldap_t61_to_8859** (string value) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ldap_unbind (PHP 3, PHP 4 >= 4.0.0)

Unbind from LDAP directory

bool **ldap_unbind** (resource link_identifier) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

ldap_unbind() function unbinds from the LDAP directory.

L. Mailové funkce

Funkce `mail()` umožňuje odesílat maily.

ezmlm_hash (PHP 3 >= 3.0.17, PHP 4 >= 4.0.2)

Počítá hash hodnotu potřebnou pro EZMLM

`int ezmlm_hash (string addr) \linebreak`

ezmlm_hash() Počítá hash hodnotu, která je potřeba pro uchovávání EZMLM mailing listů v MySQL databázi.

Příklad 1. Výpočet hashe a přihlášení uživatele

```
$user = "kris@koehtopp.de";
$hash = ezmlm_hash ($user);
$query = sprintf ("INSERT INTO sample VALUES (%s, '%s')", $hash, $user);
$db->query($query); // použito databázové rozhraní PHPLIB
```

mail (PHP 3, PHP 4 >= 4.0.0)

send mail

`bool mail (string to, string subject, string message [, string additional_headers]) \linebreak`

mail() automaticky odmailuje vzkaz specifikovaný v *message* příjemci specifikovanému v *to*. Přidáním čárky mezi adresami v *to* můžete specifikovat více příjemců.

Příklad 1. Odeslání mailu.

```
mail("rasmus@lerdorf.on.ca", "Můj předmět", "Řádek 1\nŘádek 2\nŘádek 3");
```

Pokud je předán čtvrtý argument, jeho hodnota se vloží na konec hlaviček. Toto se obvykle používá k přidání extra hlaviček. Vícenásobné hlavičky se oddělují zařádkováním.

Příklad 2. Odeslání mailu s extra hlavičkami.

```
mail("nobody@aol.com", "předmět", $message,
     "From: webmaster@$SERVER_NAME\nReply-To: webmaster@$SERVER_NAME\nX-Mailer: PHP/" . PHP_VERSION);
```

K vytvoření komplexních emailů můžete také použít poměrně jednoduché techniky pro tvorbu řetězců.

Příklad 3. Odeslání komplexního emailu

```
/* recipients */
$recipient .= "Mary <mary@u.college.edu>" . ", " ; //všimněte si čárky
$recipient .= "Kelly <kelly@u.college.edu>" . ", " ;
```

```

$recipient .= "ronabop@php.net";

/* subject */
$subject = "Birthday Reminders for August";

/* message */
$message .= "Následující email obsahuje formátovanou ASCII tabulku\n";
$message .= "Day \t\tMonth \t\tYear\n";
$message .= "3rd \t\tAug \t\t1970\n";
$message .= "17rd\t\tAug \t\t1973\n";

/* můžete přidat signaturu */
$message .= "--\r\n"; //oddělovač signatury
$message .= "Birthday reminder copylefted by public domain";

/* dodatečné hlavičky pro chyby, From, cc, bcc, atd */

$headers .= "From: Birthday Reminder <birthday@php.net>\n";
$headers .= "X-Sender: <birthday@php.net>\n";
$headers .= "X-Mailer: PHP\n"; // mailový klient
$headers .= "X-Priority: 1\n"; // Urgentní vzkaz!
$headers .= "Return-Path: <birthday@php.net>\n"; // Návratová cesta pro chyby

/* Pokud chcete poslat HTML email, odkomentujte následující řádek */
// $headers .= "Content-Type: text/html; charset=iso-8859-1\n"; // Mime typ

$headers .= "cc:birthdayarchive@php.net\n"; // CC
$headers .= "bcc:birthdaycheck@php.net, birthdaygifts@php.net\n"; // BCC

/* a teď to odešleme */
mail($recipient, $subject, $message, $headers);

```

LI. mailparse functions

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

mailparse_determine_best_xfer_encoding (4.1.0 - 4.2.0 only)

Figures out the best way of encoding the content read from the file pointer fp, which must be seek-able

```
int mailparse_determine_best_xfer_encoding ( resource fp) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_create (4.1.0 - 4.2.0 only)

Returns a handle that can be used to parse a message

```
int mailparse_msg_create ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_extract_part (4.1.0 - 4.2.0 only)

Extracts/decodes a message section. If callbackfunc is not specified, the contents will be sent to "stdout"

void **mailparse_msg_extract_part** (resource rfc2045, string msgbody [, string callbackfunc]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_extract_part_file (4.1.0 - 4.2.0 only)

Extracts/decodes a message section, decoding the transfer encoding

string **mailparse_msg_extract_part_file** (resource rfc2045, string filename [, string callbackfunc]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_free (4.1.0 - 4.2.0 only)

Frees a handle allocated by mailparse_msg_crea

void **mailparse_msg_free** (resource rfc2045buf) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_get_part (4.1.0 - 4.2.0 only)

Returns a handle on a given section in a mimemessage

int **mailparse_msg_get_part** (resource rfc2045, string mimesection) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_get_part_data (4.1.0 - 4.2.0 only)

Returns an associative array of info about the message

array **mailparse_msg_get_part_data** (resource rfc2045) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_get_structure (4.1.0 - 4.2.0 only)

Returns an array of mime section names in the supplied message

array **mailparse_msg_get_structure** (resource rfc2045) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_parse (4.1.0 - 4.2.0 only)

Incrementally parse data into buffer

void **mailparse_msg_parse** (resource rfc2045buf, string data) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_msg_parse_file (4.1.0 - 4.2.0 only)

Parse file and return a resource representing the structure

resource **mailparse_msg_parse_file** (string filename) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_rfc822_parse_addresses (4.1.0 - 4.2.0 only)

Parse addresses and returns a hash containing that data

array **mailparse_rfc822_parse_addresses** (string addresses) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_stream_encode (4.1.0 - 4.2.0 only)

Streams data from source file pointer, apply encoding and write to destfp

bool **mailparse_stream_encode** (resource sourcefp, resource destfp, string encoding) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mailparse_uudecode_all (PHP 4 4.2.0 only)

Scans the data from fp and extract each embedded uuencoded file. Returns an array listing filename information

array **mailparse_uudecode_all** (resource fp) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

LII. Mathematical Functions

Introduction

These math functions will only handle values within the range of the integer and float types on your computer. (this corresponds currently to the C types long resp. double) If you need to handle bigger numbers, take a look at the arbitrary precision math functions.

Math constants

The following values are defined as constants in PHP by the math extension:

Tabulka 1. Math constants

Constant	Value	Description
M_PI	3.14159265358979323846	Pi
M_E	2.7182818284590452354	e
M_LOG2E	1.4426950408889634074	$\log_2 e$
M_LOG10E	0.43429448190325182765	$\log_{10} e$
M_LN2	0.69314718055994530942	$\log_e 2$
M_LN10	2.30258509299404568402	$\log_e 10$
M_PI_2	1.57079632679489661923	$\pi/2$
M_PI_4	0.78539816339744830962	$\pi/4$
M_1_PI	0.31830988618379067154	$1/\pi$
M_2_PI	0.63661977236758134308	$2/\pi$
M_SQRTPI	1.77245385090551602729	$\sqrt{\pi}$ [4.0.2]
M_2_SQRTPI	1.12837916709551257390	$2/\sqrt{\pi}$
M_SQRT2	1.41421356237309504880	$\sqrt{2}$
M_SQRT3	1.73205080756887729352	$\sqrt{3}$ [4.0.2]
M_SQRT1_2	0.70710678118654752440	$1/\sqrt{2}$
M_LNPI	1.14472988584940017414	$\log_e(\pi)$ [4.0.2]
M_EULER	0.57721566490153286061	Euler constant [4.0.2]

Only M_PI is available in PHP versions up to and including PHP 4.0.0. All other constants are available starting with PHP 4.0.0. Constants labeled [4.0.2] were added in PHP 4.0.2.

abs (PHP 3, PHP 4 >= 4.0.0)

Absolute value

mixed **abs** (mixed number) \linebreak

Returns the absolute value of number. If the argument number is of type float, the return type is also float, otherwise it is integer (as float usually has a bigger value range than integer).

Příklad 1. abs() example

```
$abs = abs(-4.2); // $abs = 4.2; (double/float)
$abs2 = abs(5);   // $abs2 = 5; (integer)
$abs3 = abs(-5);  // $abs3 = 5; (integer)
```

acos (PHP 3, PHP 4 >= 4.0.0)

Arc cosine

float **acos** (float arg) \linebreak

Returns the arc cosine of *arg* in radians.

See also acosh(), asin() and atan().

acosh (PHP 4 >= 4.1.0)

Inverse hyperbolic cosine

float **acosh** (float arg) \linebreak

Returns the inverse hyperbolic cosine of *arg*, i.e. the value whose hyperbolic cosine is *arg*.

Poznámka: Tato funkce není implementována na platformách Windows.

See also acos(), asin() and atan().

asin (PHP 3, PHP 4 >= 4.0.0)

Arc sine

float **asin** (float arg) \linebreak

Returns the arc sine of arg in radians.

See also `asinh()`, `acos()` and `atan()`.

asinh (PHP 4 >= 4.1.0)

Inverse hyperbolic sine

`float asinh (float arg)` \linebreak

Returns the inverse hyperbolic sine of *arg*, i.e. the value whose hyperbolic sine is *arg*.

Poznámka: Tato funkce není implementována na platformách Windows.

See also `asin()`, `acos()` and `atan()`.

atan (PHP 3, PHP 4 >= 4.0.0)

Arc tangent

`float atan (float arg)` \linebreak

Returns the arc tangent of *arg* in radians.

See also `atanh()`, `asin()` and `acos()`.

atan2 (PHP 3 >= 3.0.5, PHP 4 >= 4.0.0)

arc tangent of two variables

`float atan2 (float y, float x)` \linebreak

This function calculates the arc tangent of the two variables *x* and *y*. It is similar to calculating the arc tangent of *y* / *x*, except that the signs of both arguments are used to determine the quadrant of the result.

The function returns the result in radians, which is between -PI and PI (inclusive).

See also `acos()` and `atan()`.

atanh (PHP 4 >= 4.1.0)

Inverse hyperbolic tangent

`float atanh (float arg)` \linebreak

Returns the inverse hyperbolic tangent of *arg*, i.e. the value whose hyperbolic tangent is *arg*.

Poznámka: Tato funkce není implementována na platformách Windows.

See also atan(), asin() and acos().

base_convert (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Convert a number between arbitrary bases

string **base_convert** (string number, int frombase, int tobase) \linebreak

Returns a string containing *number* represented in base *tobase*. The base in which *number* is given is specified in *frombase*. Both *frombase* and *tobase* have to be between 2 and 36, inclusive. Digits in numbers with a base higher than 10 will be represented with the letters a-z, with a meaning 10, b meaning 11 and z meaning 35.

Příklad 1. base_convert()

```
$binary = base_convert ($hexadecimal, 16, 2);
```

bindec (PHP 3, PHP 4 >= 4.0.0)

Binary to decimal

int **bindec** (string binary_string) \linebreak

Returns the decimal equivalent of the binary number represented by the *binary_string* argument.

bindec() converts a binary number to an integer. The largest number that can be converted is 31 bits of 1's or 2147483647 in decimal.

See also the decbin() function.

ceil (PHP 3, PHP 4 >= 4.0.0)

Round fractions up

float **ceil** (float value) \linebreak

Returns the next highest integer value by rounding up *value* if necessary. The return value of **ceil()** is still of type float as the value range of float is usually bigger than that of int.

Příklad 1. ceil() examples

```
$five = ceil(4.3);    // $five = 5.0;
$ten = ceil(9.999);  // $ten = 10.0;
```

See also floor() and round().

cos (PHP 3, PHP 4 >= 4.0.0)

Cosine

float **cos** (float arg) \linebreak

Returns the cosine of arg in radians.

See also sin() and tan().

cosh (PHP 4 >= 4.1.0)

Hyperbolic cosine

float **cosh** (float arg) \linebreak

Returns the hyperbolic cosine of *arg*, defined as $(\exp(\text{arg}) + \exp(-\text{arg})) / 2$.

See also cos(), acosh(), sin() and tan().

decbin (PHP 3, PHP 4 >= 4.0.0)

Decimal to binary

string **decbin** (int number) \linebreak

Returns a string containing a binary representation of the given number argument. The largest number that can be converted is 4294967295 in decimal resulting to a string of 32 1's.

See also the bindec() function.

dechex (PHP 3, PHP 4 >= 4.0.0)

Decimal to hexadecimal

string **dechex** (int number) \linebreak

Returns a string containing a hexadecimal representation of the given number argument. The largest number that can be converted is 2147483647 in decimal resulting to "7fffffff".

See also `hexdec()`.

decoct (PHP 3, PHP 4 >= 4.0.0)

Decimal to octal

string **decoct** (int number) \linebreak

Returns a string containing an octal representation of the given number argument. The largest number that can be converted is 2147483647 in decimal resulting to "17777777777".

See also `octdec()`.

deg2rad (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Converts the number in degrees to the radian equivalent

float **deg2rad** (float number) \linebreak

This function converts *number* from degrees to the radian equivalent.

See also `rad2deg()`.

exp (PHP 3, PHP 4 >= 4.0.0)

e to the power of ...

float **exp** (float arg) \linebreak

Returns e raised to the power of *arg*.

See also `pow()`.

expm1 (PHP 4 >= 4.1.0)

Returns `exp(number) - 1`, computed in a way that accurate even when the value of number is close to zero

float **expm1** (float number) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

floor (PHP 3, PHP 4 >= 4.0.0)

Round fractions down

float **floor** (float value) \linebreak

Returns the next lowest integer value by rounding down *value* if necessary. The return value of **floor()** is still of type float because the value range of float is usually bigger than that of int.

Příklad 1. floor() examples

```
$four = floor(4.3);    // $four = 4.0;
$nine = floor(9.999); // $nine = 9.0;
```

See also ceil() and round().

getrandmax (PHP 3, PHP 4 >= 4.0.0)

Show largest possible random value

int **getrandmax** (void) \linebreak

Returns the maximum value that can be returned by a call to rand().

See also rand(), srand(), mt_rand(), mt_srand(), and mt_getrandmax().

hexdec (PHP 3, PHP 4 >= 4.0.0)

Hexadecimal to decimal

int **hexdec** (string hex_string) \linebreak

Returns the decimal equivalent of the hexadecimal number represented by the *hex_string* argument. **hexdec()** converts a hexadecimal string to a decimal number. The largest number that can be converted is 7fffffff or 2147483647 in decimal.

hexdec() will replace of any non-hexadecimal characters it encounters by 0. This way, all left zeros are ignored, but right zeros will be valued.

Příklad 1. hexdec() example

```
var_dump(hexdec("See"));
var_dump(hexdec("ee"));
// both prints "int(238)"

var_dump(hexdec("that"));
var_dump(hexdec("a0"));
// both prints int(160)
```

See also `dechex()`.

hypot (PHP 4 >= 4.1.0)

Returns `sqrt(num1*num1 + num2*num2)`

float **hypot** (float num1, float num2) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

is_finite (PHP 4 >= 4.2.0)

bool **is_finite** (float val) \linebreak

Returns `TRUE` if `val` is a legal finite number within the allowed range for a PHP float on this platform.

is_infinite (PHP 4 >= 4.2.0)

bool **is_infinite** (float *val*) \linebreak

Returns `TRUE` if *val* is infinite (positive or negative), like the result of `log(0)` or any value too big to fit into a float on this platform.

is_nan (PHP 4 >= 4.2.0)

bool **is_nan** (float *val*) \linebreak

Returns `TRUE` if *val* is 'not a number', like the result of `acos(1.01)`.

lcg_value (PHP 4 >= 4.0.0)

Combined linear congruential generator

float **lcg_value** (void) \linebreak

lcg_value() returns a pseudo random number in the range of (0, 1). The function combines two CGs with periods of $2^{31} - 85$ and $2^{31} - 249$. The period of this function is equal to the product of both primes.

log (PHP 3, PHP 4 >= 4.0.0)

Natural logarithm

float **log** (float *arg*) \linebreak

Returns the natural logarithm of *arg*.

log10 (PHP 3, PHP 4 >= 4.0.0)

Base-10 logarithm

float **log10** (float *arg*) \linebreak

Returns the base-10 logarithm of *arg*.

log1p (PHP 4 >= 4.1.0)

Returns $\log(1 + \text{number})$, computed in a way that accurate even when the value of number is close to zero

float **log1p** (float number) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

max (PHP 3, PHP 4 >= 4.0.0)

Find highest value

mixed **max** (mixed arg1, mixed arg2, mixed argn) \linebreak

max() returns the numerically highest of the parameter values.

If the first parameter is an array, **max()** returns the highest value in that array. If the first parameter is an integer, string or float, you need at least two parameters and **max()** returns the biggest of these values. You can compare an unlimited number of values.

If one or more of the values is a float, all the values will be treated as floats, and a float is returned. If none of the values is a float, all of them will be treated as integers, and an integer is returned.

min (PHP 3, PHP 4 >= 4.0.0)

Find lowest value

number **min** (number arg1, number arg2 [, ...]) \linebreak number **min** (array numbers) \linebreak

min() returns the numerically lowest of the parameter values.

In the first variant, you need at least two parameters and **min()** returns the lowest of these values. You can compare an unlimited number of values.

In the second variant, **min()** returns the lowest value in *numbers*.

If one or more of the values is a float, all the values will be treated as floats, and a float is returned. If none of the values is a float, all of them will be treated as integers, and an integer is returned.

mt_getrandmax (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Show largest possible random value

```
int mt_getrandmax ( void) \linebreak
```

Returns the maximum value that can be returned by a call to `mt_rand()`.

See also `mt_rand()`, `mt_srand()`, `rand()`, `srand()`, and `getrandmax()`.

mt_rand (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Generate a better random value

```
int mt_rand ( [int min, int max]) \linebreak
```

Many random number generators of older libcs have dubious or unknown characteristics and are slow. By default, PHP uses the libc random number generator with the `rand()` function. **mt_rand()** function is a drop-in replacement for this. It uses a random number generator with known characteristics, the Mersenne Twister, which will produce random numbers that should be suitable for seeding some kinds of cryptography (see the home pages for details) and is four times faster than what the average libc provides. The Homepage of the Mersenne Twister can be found at <http://www.math.keio.ac.jp/~matumoto/emt.html>, and an optimized version of the MT source is available from <http://www.scp.syr.edu/~marc/hawk/twister.html> (<http://www.scp.syr.edu/~marc/hawk/twister.html>).

If called without the optional *min*, *max* arguments **mt_rand()** returns a pseudo-random value between 0 and `RAND_MAX`. If you want a random number between 5 and 15 (inclusive), for example, use `mt_rand (5 , 15)`.

Remember to seed the random number generator before use with `mt_srand()`.

Poznámka: In versions before 3.0.7 the meaning of *max* was *range*. To get the same results in these versions the short example should be `mt_rand (5 , 11)` to get a random number between 5 and 15.

See also `mt_srand()`, `mt_getrandmax()`, `srand()`, `rand()` and `getrandmax()`.

mt_srand (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Seed the better random number generator

```
void mt_srand ( int seed) \linebreak
```

Seeds the random number generator with *seed*.

```
// seed with microseconds
function make_seed() {
    list($usec, $sec) = explode(' ', microtime());
    return (float) $sec + ((float) $usec * 100000);
}
mt_srand(make_seed());
$randval = mt_rand();
```

See also `mt_rand()`, `mt_getrandmax()`, `srand()`, `rand()`, and `getrandmax()`.

number_format (PHP 3, PHP 4 >= 4.0.0)

Format a number with grouped thousands

string **number_format** (float *number* [, int *decimals* [, string *dec_point* [, string *thousands_sep*]]]) \linebreak

number_format() returns a formatted version of *number*. This function accepts either one, two or four parameters (not three):

If only one parameter is given, *Number* will be formatted without decimals, but with a comma (",") between every group of thousands.

If two parameters are given, *number* will be formatted with *decimals* decimals with a dot (".") in front, and a comma (",") between every group of thousands.

If all four parameters are given, *number* will be formatted with *decimals* decimals, *dec_point* instead of a dot (".") before the decimals and *thousands_sep* instead of a comma (",") between every group of thousands.

Poznámka: Only the first character of *thousands_sep* is used. For example, if you use `foo` as *thousands_sep* on the number 1000, **number_format()** will return `1f000`.

Příklad 1. number_format() Example

For instance, French notation usually use two decimals, comma (',') as decimal separator, and space (' ') as thousand separator. This is achieved with this line :

```
<?php

$number = 1234.56;

// english notation (default)
$english_format_number = number_format($number);
// 1,234.56

// French notation
$nombre_format_francais = number_format($number, 2, ',', ' ');
```

```
// 1 234,56

$number = 1234.5678;

// english notation without thousands separator
$english_format_number = number_format($number, 2, '.', '');
// 1234.56

?>
```

Poznámka: See also: `sprintf()`, `printf()` and `sscanf()`.

octdec (PHP 3, PHP 4 >= 4.0.0)

Octal to decimal

int **octdec** (string *octal_string*) \linebreak

Returns the decimal equivalent of the octal number represented by the *octal_string* argument. The largest number that can be converted is 1777777777 or 2147483647 in decimal.

See also `decoct()`.

pi (PHP 3, PHP 4 >= 4.0.0)

Get value of pi

float **pi** (void) \linebreak

Returns an approximation of pi. The returned float has a precision based on the precision directive in `php.ini`, which defaults to 14. Also, you can use the `M_PI` constant which yields identical results to **pi()**.

```
echo pi(); // 3.1415926535898
echo M_PI; // 3.1415926535898
```

pow (PHP 3, PHP 4 >= 4.0.0)

Exponential expression

number **pow** (number base, number exp) \linebreak

Returns *base* raised to the power of *exp*. If possible, this function will return an integer.

If the power cannot be computed, a warning will be issued, and **pow()** will return `FALSE`.

Příklad 1. Some examples of pow()

```
<?php

var_dump( pow(2,8) ); // int(256)
echo pow(-1,20); // 1
echo pow(0, 0); // 1

echo pow(-1, 5.5); // error

?>
```

Varování

In PHP 4.0.6 and earlier **pow()** always returned a float, and did not issue warnings.

See also `exp()` and `sqrt()`.

rad2deg (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Converts the radian number to the equivalent number in degrees

float **rad2deg** (float number) \linebreak

This function converts *number* from radian to degrees.

See also `deg2rad()`.

rand (PHP 3, PHP 4 >= 4.0.0)

Generate a random value

int **rand** ([int min, int max]) \linebreak

If called without the optional *min*, *max* arguments **rand()** returns a pseudo-random value between 0 and `RAND_MAX`. If you want a random number between 5 and 15 (inclusive), for example, use `rand (5, 15)`.

Remember to seed the random number generator before use with `srand()`.

Poznámka: In versions before 3.0.7 the meaning of *max* was *range*. To get the same results in these versions the short example should be `rand (5, 11)` to get a random number between 5 and 15.

See also `srand()`, `getrandmax()`, `mt_rand()`, `mt_srand()`, and `mt_getrandmax()`.

round (PHP 3, PHP 4 >= 4.0.0)

Rounds a float

float **round** (float *val* [, int *precision*]) \linebreak

Returns the rounded value of *val* to specified *precision* (number of digits after the decimal point). *precision* can also be negative or zero (default).

Výstraha

PHP doesn't handle strings like "12,300.2" correctly by default. See converting from strings.

```
$foo = round(3.4); // $foo == 3.0
$foo = round(3.5); // $foo == 4.0
$foo = round(3.6); // $foo == 4.0
$foo = round(3.6, 0); // equivalent with above

$foo = round(1.95583, 2); // $foo == 1.96

$foo = round(1241757, -3); // $foo == 1242000
```

Poznámka: The *precision* parameter is only available in PHP 4.

See also `ceil()` and `floor()`.

sin (PHP 3, PHP 4 >= 4.0.0)

Sine

float **sin** (float *arg*) \linebreak

Returns the sine of *arg* in radians.

See also `cos()` and `tan()`.

sinh (PHP 4 >= 4.1.0)

Hyperbolic sine

float **sinh** (float *arg*) \linebreak

Returns the hyperbolic sine of *arg*, defined as $(\exp(\textit{arg}) - \exp(-\textit{arg})) / 2$.

See also `sin()`, `asinh()`, `cos()` and `tan()`.

sqrt (PHP 3, PHP 4 >= 4.0.0)

Square root

float **sqrt** (float *arg*) \linebreak

Returns the square root of *arg*.

See also `pow()`.

srand (PHP 3, PHP 4 >= 4.0.0)

Seed the random number generator

void **srand** (int *seed*) \linebreak

Seeds the random number generator with *seed*.

```
// seed with microseconds
function make_seed() {
    list($usec, $sec) = explode(' ', microtime());
    return (float) $sec + ((float) $usec * 100000);
}
srand(make_seed());
$randval = rand();
```

See also `rand()`, `getrandmax()`, `mt_rand()`, `mt_srand()`, and `mt_getrandmax()`.

tan (PHP 3, PHP 4 >= 4.0.0)

Tangent

float **tan** (float *arg*) \linebreak

Returns the tangent of *arg* in radians.

See also `sin()` and `cos()`.

tanh (PHP 4 >= 4.1.0)

Hyperbolic tangent

float **tanh** (float *arg*) \linebreak

Returns the hyperbolic tangent of *arg*, defined as $\sinh(\textit{arg}) / \cosh(\textit{arg})$.

See also `tan()`, `atanh()`, `sin()` and `cos()`.

LIII. Multi-Byte String Functions

Introduction

There are many languages in which all characters can be expressed by single byte. Multi-byte character codes are used to express many characters for many languages. `mbstring` is developed to handle Japanese characters. However, many `mbstring` functions are able to handle character encoding other than Japanese.

A multi-byte character encoding represents single character with consecutive bytes. Some character encoding has shift(escape) sequences to start/end multi-byte character strings. Therefore, a multi-byte character string may be destroyed when it is divided and/or counted unless multi-byte character encoding safe method is used. This module provides multi-byte character safe string functions and other utility functions such as conversion functions.

Since PHP is basically designed for ISO-8859-1, some multi-byte character encoding does not work well with PHP. Therefore, it is important to set `mbstring.internal_encoding` to a character encoding that works with PHP.

PHP4 Character Encoding Requirements

- Per byte encoding
- Single byte characters in range of 00h-7fh which is compatible with ASCII
- Multi-byte characters without 00h-7fh

These are examples of internal character encoding that works with PHP and does NOT work with PHP.

Character encodings work with PHP:
ISO-8859-*, EUC-JP, UTF-8

Character encodings do NOT work with PHP:
JIS, SJIS

Character encoding, that does not work with PHP, may be converted with `mbstring`'s HTTP input/output conversion feature/function.

Poznámka: SJIS should not be used for internal encoding unless the reader is familiar with parser/compiler, character encoding and character encoding issues.

Poznámka: If you use database with PHP, it is recommended that you use the same character encoding for both database and `internal_encoding` for ease of use and better performance.

If you are using PostgreSQL, it supports character encoding that is different from backend

character encoding. See the PostgreSQL manual for details.

How to Enable mbstring

`mbstring` is an extended module. You must enable module with `configure` script. Refer to the Install section for details.

The following configure options are related to `mbstring` module.

- `--enable-mbstring` : Enable `mbstring` functions. This option is required to use `mbstring` functions.
- `--enable-mbstr-enc-trans` : Enable HTTP input character encoding conversion using `mbstring` conversion engine. If this feature is enabled, HTTP input character encoding may be converted to `mbstring.internal_encoding` automatically.

HTTP Input and Output

HTTP input/output character encoding conversion may convert binary data also. Users are supposed to control character encoding conversion if binary data is used for HTTP input/output.

If `enctype` for HTML form is set to `multipart/form-data`, `mbstring` does not convert character encoding in POST data. If it is the case, strings are needed to be converted to internal character encoding.

- HTTP Input

There is no way to control HTTP input character conversion from PHP script. To disable HTTP input character conversion, it has to be done in `php.ini`.

Příklad 1. Disable HTTP input conversion in `php.ini`

```
;; Disable HTTP Input conversion
mbstring.http_input = pass
```

When using PHP as an Apache module, it is possible to override PHP ini setting per Virtual Host in `httpd.conf` or per directory with `.htaccess`. Refer to the Configuration section and Apache Manual for details.

- HTTP Output

There are several ways to enable output character encoding conversion. One is using `php.ini`, another is using `ob_start()` with `mb_output_handler()` as `ob_start` callback function.

Poznámka: For PHP3-i18n users, `mbstring`'s output conversion differs from PHP3-i18n.

Character encoding is converted using output buffer.

Příklad 2. php.ini setting example

```
// Enable output character encoding conversion for all PHP pages

// Enable Output Buffering
output_buffering    = On

// Set mb_output_handler to enable output conversion
output_handler      = mb_output_handler
```

Příklad 3. Script example

```
<?php

// Enable output character encoding conversion only for this page

// Set HTTP output character encoding to SJIS
mb_http_output('SJIS');

// Start buffering and specify "mb_output_handler" as
// callback function
ob_start('mb_output_handler');

?>
```

Supported Character Encoding

Currently, the following character encoding is supported by `mbstring` module. Character encoding may be specified for `mbstring` functions' encoding parameter.

The following character encoding is supported in this PHP extension :

UCS-4, UCS-4BE, UCS-4LE, UCS-2, UCS-2BE, UCS-2LE, UTF-32, UTF-32BE, UTF-32LE, UCS-2LE, UTF-16, UTF-16BE, UTF-16LE, UTF-8, UTF-7, ASCII, EUC-JP, SJIS, eucJP-win, SJIS-win, ISO-2022-JP, JIS, ISO-8859-1, ISO-8859-2, ISO-8859-3, ISO-8859-4, ISO-8859-5, ISO-8859-6, ISO-8859-7, ISO-8859-8, ISO-8859-9, ISO-8859-10,

ISO-8859-13, ISO-8859-14, ISO-8859-15, byte2be, byte2le, byte4be, byte4le, BASE64, 7bit, 8bit and UTF7-IMAP.

php.ini entry, which accepts encoding name, accepts "auto" and "pass" also. mbstring functions, which accepts encoding name, and accepts "auto".

If "pass" is set, no character encoding conversion is performed.

If "auto" is set, it is expanded to "ASCII,JIS,UTF-8,EUC-JP,SJIS".

See also mb_detect_order()

Poznámka: "Supported character encoding" does not mean that it works as internal character code.

php.ini settings

- mbstring.internal_encoding defines default internal character encoding.
- mbstring.http_input defines default HTTP input character encoding.
- mbstring.http_output defines default HTTP output character encoding.
- mbstring.detect_order defines default character code detection order. See also mb_detect_order().
- mbstring.substitute_character defines character to substitute for invalid character encoding.

Web Browsers are supposed to use the same character encoding when submitting form. However, browsers may not use the same character encoding. See mb_http_input() to detect character encoding used by browsers.

If enctype is set to multipart/form-data in HTML forms, mbstring does not convert character encoding in POST data. The user must convert them in the script, if conversion is needed.

Although, browsers are smart enough to detect character encoding in HTML. charset is better to be set in HTTP header. Change default_charset according to character encoding.

Příklad 4. php.ini setting example

```
// Set default internal encoding
// Note: Make sure to use character encoding works with PHP
mbstring.internal_encoding = UTF-8 ; Set internal encoding to UTF-8

// Set default HTTP input character encoding
// Note: Script cannot change http_input setting.
mbstring.http_input       = pass    ; No conversion.
mbstring.http_input       = auto    ; Set HTTP input to auto
                                ; "auto" is expanded to "ASCII,JIS,UTF-8,EUC-
JP,SJIS"
mbstring.http_input       = SJIS    ; Set HTTP2 input to SJIS
mbstring.http_input       = UTF-8,SJIS,EUC-JP ; Specify order
```

```

;; Set default HTTP output character encoding
mbstring.http_output      = pass      ; No conversion
mbstring.http_output      = UTF-8     ; Set HTTP output encoding to UTF-8

;; Set default character encoding detection order
mbstring.detect_order     = auto      ; Set detect order to auto
mbstring.detect_order     = ASCII,JIS,UTF-8,SJIS,EUC-JP ; Specify order

;; Set default substitute character
mbstring.substitute_character = 12307 ; Specify Unicode value
mbstring.substitute_character = none   ; Do not print character
mbstring.substitute_character = long   ; Long Example: U+3000,JIS+7E7E

```

Příklad 5. php.ini setting for EUC-JP users

```

;; Disable Output Buffering
output_buffering      = Off

;; Set HTTP header charset
default_charset       = EUC-JP

;; Set HTTP input encoding conversion to auto
mbstring.http_input   = auto

;; Convert HTTP output to EUC-JP
mbstring.http_output  = EUC-JP

;; Set internal encoding to EUC-JP
mbstring.internal_encoding = EUC-JP

;; Do not print invalid characters
mbstring.substitute_character = none

```

Příklad 6. php.ini setting for SJIS users

```

;; Enable Output Buffering
output_buffering      = On

;; Set mb_output_handler to enable output conversion
output_handler        = mb_output_handler

;; Set HTTP header charset
default_charset       = Shift_JIS

;; Set http input encoding conversion to auto

```

```

mbstring.http_input  = auto

;; Convert to SJIS
mbstring.http_output = SJIS

;; Set internal encoding to EUC-JP
mbstring.internal_encoding = EUC-JP

;; Do not print invalid characters
mbstring.substitute_character = none

```

Overload of PHP string functions by mbstring functions with multibyte support

Because almost PHP application written for language using single-byte character encoding, there are some difficulties for multibyte string handling including Japanese. Almost PHP string functions such as `substr()` do not support multibyte string.

Multibyte extension (mbstring) has some PHP string functions with multibyte support (ex. `substr()` supports `mb_substr()`).

Multibyte extension (mbstring) also supports 'function overloading' to add multibyte string functionality without code modification. Using function overloading, some PHP string functions will be overloaded multibyte string functions. For example, `mb_substr()` is called instead of `substr()` if function overloading is enabled. Function overload makes easy to port application supporting only single-byte encoding for multibyte application.

`mbstring.func_overload` in `php.ini` should be set some positive value to use function overloading. The value should specify the category of overloading functions, should be set 1 to enable mail function overloading, 2 to enable string functions, 4 to regular expression functions. For example, if it is set for 7, mail, strings, regex functions should be overloaded. The list of overloaded functions are shown in below.

Tabulka 1. Functions to be overloaded

value of <code>mbstring.func_overload</code>	original function	overloaded function
1	<code>mail()</code>	<code>mb_send_mail()</code>
2	<code>strlen()</code>	<code>mb_strlen()</code>
2	<code>strpos()</code>	<code>mb_strpos()</code>
2	<code>strrpos()</code>	<code>mb_strrpos()</code>
2	<code>substr()</code>	<code>mb_substr()</code>
4	<code>ereg()</code>	<code>mb_ereg()</code>
4	<code>eregi()</code>	<code>mb_eregi()</code>
4	<code>ereg_replace()</code>	<code>mb_ereg_replace()</code>
4	<code>eregi_replace()</code>	<code>mb_eregi_replace()</code>
4	<code>split()</code>	<code>mb_split()</code>

Basics for Japanese multi-byte character

Most Japanese characters need more than 1 byte per character. In addition, several character encoding schemas are used under a Japanese environment. There are EUC-JP, Shift_JIS(SJIS) and ISO-2022-JP(JIS) character encoding. As Unicode becomes popular, UTF-8 is used also. To develop Web applications for a Japanese environment, it is important to use the character set for the task in hand, whether HTTP input/output, RDBMS and E-mail.

- Storage for a character can be up to six bytes
- A multi-byte character is usually twice of the width compared to single-byte characters. Wider characters are called "zen-kaku" - meaning full width, narrower characters are called "han-kaku" - meaning half width. "zen-kaku" characters are usually fixed width.
- Some character encoding defines shift(escape) sequence for entering/exiting multi-byte character strings.
- ISO-2022-JP must be used for SMTP/NNTP.
- "i-mode" web site is supposed to use SJIS.

References

Multi-byte character encoding and its related issues are very complex. It is impossible to cover in sufficient detail here. Please refer to the following URLs and other resources for further readings.

- Unicode/UTF/UCS/etc
<http://www.unicode.org/>
- Japanese/Korean/Chinese character information
<ftp://ftp.ora.com/pub/examples/nutshell/ujip/doc/cjk.inf>

mb_convert_encoding (PHP 4 >= 4.0.6)

Convert character encoding

string **mb_convert_encoding** (string *str*, string *to-encoding* [, mixed *from-encoding*]) \linebreak

mb_convert_encoding() converts character encoding of string *str* from *from-encoding* to *to-encoding*.

str : String to be converted.

from-encoding is specified by character code name before conversion. it can be array or string - comma separated enumerated list. If it is not specified, the internal encoding will be used.

Příklad 1. mb_convert_encoding() example

```
/* Convert internal character encoding to SJIS */
$str = mb_convert_encoding($str, "SJIS");

/* Convert EUC-JP to UTF-7 */
$str = mb_convert_encoding($str, "UTF-7", "EUC-JP");

/* Auto detect encoding from JIS, eucjp-win, sjis-win, then convert str to UCS-2LE */
$str = mb_convert_encoding($str, "UCS-2LE", "JIS, eucjp-win, sjis-win");

/* "auto" is expanded to "ASCII,JIS,UTF-8,EUC-JP,SJIS" */
$str = mb_convert_encoding($str, "EUC-JP", "auto");
```

See also: mb_detect_order().

mb_convert_kana (PHP 4 >= 4.0.6)

Convert "kana" one from another ("zen-kaku" ,"han-kaku" and more)

string **mb_convert_kana** (string *str*, string *option* [, mixed *encoding*]) \linebreak

mb_convert_kana() performs "han-kaku" - "zen-kaku" conversion for string *str*. It returns converted string. This function is only useful for Japanese.

option is conversion option. Default value is "KV".

encoding is character encoding. If it is omitted, internal character encoding is used.

Applicable Conversion Options

```
option : Specify with conversion of following options. Default "KV"
"r" : Convert "zen-kaku" alphabets to "han-kaku"
"R" : Convert "han-kaku" alphabets to "zen-kaku"
```



```

"n" : Convert "zen-kaku" numbers to "han-kaku"
"N" : Convert "han-kaku" numbers to "zen-kaku"
"a" : Convert "zen-kaku" alphabets and numbers to "han-kaku"
"A" : Convert "zen-kaku" alphabets and numbers to "han-kaku"
(Characters included in "a", "A" options are
U+0021 - U+007E excluding U+0022, U+0027, U+005C, U+007E)
"s" : Convert "zen-kaku" space to "han-kaku" (U+3000 -> U+0020)
"S" : Convert "han-kaku" space to "zen-kaku" (U+0020 -> U+3000)
"k" : Convert "zen-kaku kata-kana" to "han-kaku kata-kana"
"K" : Convert "han-kaku kata-kana" to "zen-kaku kata-kana"
"h" : Convert "zen-kaku hira-gana" to "han-kaku kata-kana"
"H" : Convert "han-kaku kata-kana" to "zen-kaku hira-gana"
"c" : Convert "zen-kaku kata-kana" to "zen-kaku hira-gana"
"C" : Convert "zen-kaku hira-gana" to "zen-kaku kata-kana"
"V" : Collapse voiced sound notation and convert them into a character. Use with "K", "H"

```

Příklad 1. mb_convert_kana() example

```

/* Convert all "kana" to "zen-kaku" "kata-kana" */
$str = mb_convert_kana($str, "KVC");

/* Convert "han-kaku" "kata-kana" to "zen-kaku" "kata-kana"
and "zen-kaku" alpha-numeric to "han-kaku" */
$str = mb_convert_kana($str, "KVa");

```

mb_convert_variables (PHP 4 >= 4.0.6)

Convert character code in variable(s)

string **mb_convert_variables** (string to-encoding, mixed from-encoding, mixed vars) \linebreak

mb_convert_variables() convert character encoding of variables *vars* in encoding *from-encoding* to encoding *to-encoding*. It returns character encoding before conversion for success, FALSE for failure.

mb_convert_variables() join strings in Array or Object to detect encoding, since encoding detection tends to fail for short strings. Therefore, it is impossible to mix encoding in single array or object.

It *from-encoding* is specified by array or comma separated string, it tries to detect encoding from *from-coding*. When *encoding* is omitted, *detect_order* is used.

vars (3rd and larger) is reference to variable to be converted. String, Array and Object are accepted. **mb_convert_variables()** assumes all parameters have the same encoding.

Příklad 1. mb_convert_variables() example

```

/* Convert variables $post1, $post2 to internal encoding */
$interenc = mb_internal_encoding();
$inputenc = mb_convert_variables($interenc, "ASCII,UTF-8,SJIS-win", $post1, $post2);

```

mb_decode_mimeheader (PHP 4 >= 4.0.6)

Decode string in MIME header field

string **mb_decode_mimeheader** (string *str*) \linebreak

mb_decode_mimeheader() decodes encoded-word string *str* in MIME header.

It returns decoded string in internal character encoding.

See also mb_encode_mimeheader().

mb_decode_numericentity (PHP 4 >= 4.0.6)

Decode HTML numeric string reference to character

string **mb_decode_numericentity** (string *str*, array *convmap* [, string *encoding*]) \linebreak

Convert numeric string reference of string *str* in specified block to character. It returns converted string.

array is array to specifies code area to convert.

encoding is character encoding. If it is omitted, internal character encoding is used.

Příklad 1. convmap example

```

$convmap = array (
    int start_code1, int end_code1, int offset1, int mask1,
    int start_code2, int end_code2, int offset2, int mask2,
    .....
    int start_codeN, int end_codeN, int offsetN, int maskN );
// Specify Unicode value for start_codeN and end_codeN
// Add offsetN to value and take bit-wise 'AND' with maskN,
// then convert value to numeric string reference.

```

See also: mb_encode_numericentity().

mb_detect_encoding (PHP 4 >= 4.0.6)

Detect character encoding

string **mb_detect_encoding** (string *str* [, mixed *encoding-list*]) \linebreak

mb_detect_encoding() detects character encoding in string *str*. It returns detected character encoding.

encoding-list is list of character encoding. Encoding order may be specified by array or comma separated list string.

If *encoding_list* is omitted, *detect_order* is used.

Příklad 1. mb_detect_encoding() example

```
/* Detect character encoding with current detect_order */
echo mb_detect_encoding($str);

/* "auto" is expanded to "ASCII,JIS,UTF-8,EUC-JP,SJIS" */
echo mb_detect_encoding($str, "auto");

/* Specify encoding_list character encoding by comma separated list */
echo mb_detect_encoding($str, "JIS, eucjp-win, sjis-win");

/* Use array to specify encoding_list */
$array[] = "ASCII";
$array[] = "JIS";
$array[] = "EUC-JP";
echo mb_detect_encoding($str, $array);
```

See also: `mb_detect_order()`.

mb_detect_order (PHP 4 >= 4.0.6)

Set/Get character encoding detection order

array **mb_detect_order** ([mixed *encoding-list*]) \linebreak

mb_detect_order() sets automatic character encoding detection order to *encoding-list*. It returns TRUE for success, FALSE for failure.

encoding-list is array or comma separated list of character encoding. ("auto" is expanded to "ASCII, JIS, UTF-8, EUC-JP, SJIS")

If *encoding-list* is omitted, it returns current character encoding detection order as array.

This setting affects `mb_detect_encoding()` and `mb_send_mail()`.

Poznámka: `mbstring` currently implements following encoding detection filters. If there is a invalid byte sequence for following encoding, encoding detection will fail.

Poznámka: UTF-8, UTF-7, ASCII, EUC-JP, SJIS, eucJP-win, SJIS-win, JIS, ISO-2022-JP

For ISO-8859-*, mbstring always detects as ISO-8859-*.

For UTF-16, UTF-32, UCS2 and UCS4, encoding detection will fail always.

Příklad 1. Useless detect order example

```
; Always detect as ISO-8859-1
detect_order = ISO-8859-1, UTF-8

; Always detect as UTF-8, since ASCII/UTF-7 values are
; valid for UTF-8
detect_order = UTF-8, ASCII, UTF-7
```

Příklad 2. mb_detect_order() examples

```
/* Set detection order by enumerated list */
mb_detect_order("eucjp-win,sjis-win,UTF-8");

/* Set detection order by array */
$array[] = "ASCII";
$array[] = "JIS";
$array[] = "EUC-JP";
mb_detect_order($array);

/* Display current detection order */
echo implode(", ", mb_detect_order());
```

See also mb_internal_encoding(), mb_http_input(), mb_http_output() mb_send_mail().

mb_encode_mimeheader (PHP 4 >= 4.0.6)

Encode string for MIME header

string **mb_encode_mimeheader** (string *str* [, string *charset* [, string *transfer-encoding* [, string *linefeed*]]])
 \linebreak

mb_encode_mimeheader() converts string *str* to encoded-word for header field. It returns converted string in ASCII encoding.

charset is character encoding name. Default is ISO-2022-JP.

transfer-encoding is transfer encoding. It should be one of "B" (Base64) or "Q" (Quoted-Printable). Default is "B".

linefeed is end of line marker. Default is "\r\n" (CRLF).

Příklad 1. `mb_convert_kana()` example

```
$name = ""; // kanji
$mbox = "kru";
$doma = "gtinn.mon";
$addr = mb_encode_mimeheader($name, "UTF-7", "Q") . " <" . $mbox . "@" . $doma . ">";
echo $addr;
```

See also `mb_decode_mimeheader()`.

`mb_encode_numericentity` (PHP 4 >= 4.0.6)

Encode character to HTML numeric string reference

string **`mb_encode_numericentity`** (string *str*, array *convmap* [, string *encoding*]) \linebreak

`mb_encode_numericentity()` converts specified character codes in string *str* from HTML numeric character reference to character code. It returns converted string.

array is array specifies code area to convert.

encoding is character encoding.

Příklad 1. *convmap* example

```
$convmap = array (
    int start_code1, int end_code1, int offset1, int mask1,
    int start_code2, int end_code2, int offset2, int mask2,
    .....
    int start_codeN, int end_codeN, int offsetN, int maskN );
// Specify Unicode value for start_codeN and end_codeN
// Add offsetN to value and take bit-wise 'AND' with maskN, then
// it converts value to numeric string reference.
```

Příklad 2. `mb_encode_numericentity()` example

```
/* Convert Left side of ISO-8859-1 to HTML numeric character reference */
$convmap = array(0x80, 0xff, 0, 0xff);
```

```

$str = mb_encode_numericentity($str, $convmap, "ISO-8859-1");

/* Convert user defined SJIS-win code in block 95-104 to numeric
   string reference */
$convmap = array(
    0xe000, 0xe03e, 0x1040, 0xffff,
    0xe03f, 0xe0bb, 0x1041, 0xffff,
    0xe0bc, 0xe0fa, 0x1084, 0xffff,
    0xe0fb, 0xe177, 0x1085, 0xffff,
    0xe178, 0xe1b6, 0x10c8, 0xffff,
    0xe1b7, 0xe233, 0x10c9, 0xffff,
    0xe234, 0xe272, 0x110c, 0xffff,
    0xe273, 0xe2ef, 0x110d, 0xffff,
    0xe2f0, 0xe32e, 0x1150, 0xffff,
    0xe32f, 0xe3ab, 0x1151, 0xffff );
$str = mb_encode_numericentity($str, $convmap, "sjis-win");

```

See also: `mb_decode_numericentity()`.

mb_ereg (PHP 4 >= 4.2.0)

Regular expression match with multibyte support

int **mb_ereg** (string pattern, string string [, array regs]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg() executes the regular expression match with multibyte support, and returns 1 if matches are found. If the optional third parameter was specified, the function returns the byte length of matched part, and the array *regs* will contain the substring of matched string. The function returns 1 if it matches with the empty string. If no match is found or an error happens, `FALSE` will be returned.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_i()`

mb_ereg_match (PHP 4 >= 4.2.0)

Regular expression match for multibyte string

bool **mb_ereg_match** (string pattern, string string [, string option]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_match() returns `TRUE` if *string* matches regular expression *pattern*, `FALSE` if not.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg()`.

mb_ereg_replace (PHP 4 >= 4.2.0)

Replace regular expression with multibyte support

string **mb_ereg_replace** (string pattern, string replacement, string string [, array option]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_replace() scans *string* for matches to *pattern*, then replaces the matched text with *replacement* and returns the result string or `FALSE` on error. Multibyte character can be used in *pattern*.

Matching condition can be set by *option* parameter. If `i` is specified for this parameter, the case will be ignored. If `x` is specified, white space will be ignored. If `m` is specified, match will be executed in multiline mode and line break will be included in `'.'`. If `p` is specified, match will be executed in POSIX mode, line break will be considered as normal character. If `e` is specified, *replacement* string will be evaluated as PHP expression.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_eregi_replace()`.

mb_ereg_search (PHP 4 >= 4.2.0)

Multibyte regular expression match for predefined multibyte string

bool **mb_ereg_search** ([string pattern [, string option]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_search() returns `TRUE` if the multibyte string matches with the regular expression, `FALSE` for otherwise. The string for matching is set by `mb_ereg_search_init()`. If *pattern* is not specified, the previous one is used.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_search_init()`.

mb_ereg_search_getpos (PHP 4 >= 4.2.0)

Returns start point for next regular expression match

array **mb_ereg_search_getpos** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_search_getpos() returns the point to start regular expression match for `mb_ereg_search()`, `mb_ereg_search_pos()`, `mb_ereg_search_regs()`. The position is represented by bytes from the head of string.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_search_setpos()`.

mb_ereg_search_getregs (PHP 4 >= 4.2.0)

Retrieve the result from the last multibyte regular expression match

array **mb_ereg_search_getregs** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_search_getregs() returns an array including the sub-string of matched part by last `mb_ereg_search()`, `mb_ereg_search_pos()`, `mb_ereg_search_regs()`. If there are some matches, the first element will have the matched sub-string, the second element will have the first part grouped with brackets, the third element will have the second part grouped with brackets, and so on. It returns `FALSE` on error;

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_search_init()`.

mb_ereg_search_init (PHP 4 >= 4.2.0)

Setup string and regular expression for multibyte regular expression match

array **mb_ereg_search_init** (string string [, string pattern [, string option]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_search_init() sets *string* and *pattern* for multibyte regular expression. These values are used for `mb_ereg_search()`, `mb_ereg_search_pos()`, `mb_ereg_search_regs()`. It returns `TRUE` for success, `FALSE` for error.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_search_regs()`.

mb_ereg_search_pos (PHP 4 >= 4.2.0)

Return position and length of matched part of multibyte regular expression for predefined multibyte string

array **mb_ereg_search_pos** ([string pattern [, string option]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_search_pos() returns an array including position of matched part for multibyte regular expression. The first element of the array will be the beginning of matched part, the second element will be length (bytes) of matched part. It returns `FALSE` on error.

The string for match is specified by `mb_ereg_search_init()`. If it is not specified, the previous one will be used.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_search_init()`.

mb_ereg_search_regs (PHP 4 >= 4.2.0)

Returns the matched part of multibyte regular expression

array **mb_ereg_search_regs** ([string pattern [, string option]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_search_regs() executes the multibyte regular expression match, and if there are some matched part, it returns an array including substring of matched part as first element, the first

grouped part with brackets as second element, the second grouped part as third element, and so on. It returns `FALSE` on error.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_search_init()`.

mb_ereg_search_setpos (PHP 4 >= 4.2.0)

Set start point of next regular expression match

array **mb_ereg_search_setpos** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_ereg_search_setpos() sets the starting point of match for `mb_ereg_search()`.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_search_init()`.

mb_eregi (PHP 4 >= 4.2.0)

Regular expression match ignoring case with multibyte support

int **mb_eregi** (string pattern, string string [, array regs]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_eregi() executes the regular expression match with multibyte support, and returns 1 if matches are found. This function ignore case. If the optional third parameter was specified, the function

returns the byte length of matched part, and the array *regs* will contain the substring of matched string. The function returns 1 if it matches with the empty string. If no match is found or an error happens, `FALSE` will be returned.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg()`.

mb_eregi_replace (PHP 4 >= 4.2.0)

Replace regular expression with multibyte support ignoring case

string **mb_eregi_replace** (string pattern, string replace, string string) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`mb_ereg_replace()` scans *string* for matches to *pattern*, then replaces the matched text with *replacement* and returns the result string or `FALSE` on error. Multibyte character can be used in *pattern*. The case will be ignored.

The internal encoding or the character encoding specified in `mb_regex_encoding()` will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: `mb_regex_encoding()`, `mb_ereg_replace()`.

mb_get_info (PHP 4 >= 4.2.0)

Get internal settings of mbstring

string **mb_get_info** ([string type]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_get_info() returns internal setting parameter of mbstring.

If *type* isn't specified or is specified to "all", an array having the elements "internal_encoding", "http_output", "http_input", "func_overload" will be returned.

If *type* is specified for "http_output", "http_input", "internal_encoding", "func_overload", the specified setting parameter will be returned.

See also mb_internal_encoding(), mb_http_output().

mb_http_input (PHP 4 >= 4.0.6)

Detect HTTP input character encoding

string **mb_http_input** ([string type]) \linebreak

mb_http_input() returns result of HTTP input character encoding detection.

type: Input string specifies input type. "G" for GET, "P" for POST, "C" for COOKIE. If type is omitted, it returns last input type processed.

Return Value: Character encoding name. If **mb_http_input()** does not process specified HTTP input, it returns *FALSE*.

See also mb_internal_encoding(), mb_http_output(), mb_detect_order().

mb_http_output (PHP 4 >= 4.0.6)

Set/Get HTTP output character encoding

string **mb_http_output** ([string encoding]) \linebreak

If *encoding* is set, **mb_http_output()** sets HTTP output character encoding to *encoding*.

Output after this function is converted to *encoding*. **mb_http_output()** returns *TRUE* for success and *FALSE* for failure.

If *encoding* is omitted, **mb_http_output()** returns current HTTP output character encoding.

See also mb_internal_encoding(), mb_http_input(), mb_detect_order().

mb_internal_encoding (PHP 4 >= 4.0.6)

Set/Get internal character encoding

string **mb_internal_encoding** ([string encoding]) \linebreak

mb_internal_encoding() sets internal character encoding to *encoding* If parameter is omitted, it returns current internal encoding.

encoding is used for HTTP input character encoding conversion, HTTP output character encoding conversion and default character encoding for string functions defined by mbstring module.

encoding: Character encoding name

Return Value: If *encoding* is set, **mb_internal_encoding()** returns TRUE for success, otherwise returns FALSE. If *encoding* is omitted, it returns current character encoding name.

Příklad 1. **mb_internal_encoding()** example

```
/* Set internal character encoding to UTF-8 */
mb_internal_encoding( "UTF-8" );

/* Display current internal character encoding */
echo mb_internal_encoding();
```

See also **mb_http_input()**, **mb_http_output()**, **mb_detect_order()**.

mb_language (PHP 4 >= 4.0.6)

Set/Get current language

string **mb_language** ([string language]) \linebreak

mb_language() sets language. If *language* is omitted, it returns current language as string.

language setting is used for encoding e-mail messages. Valid languages are "Japanese", "ja", "English", "en" and "uni" (UTF-8). **mb_send_mail()** uses this setting to encode e-mail.

Language and its setting is ISO-2022-JP/Base64 for Japanese, UTF-8/Base64 for uni, ISO-8859-1/quoted printable for English.

Return Value: If *language* is set and *language* is valid, it returns TRUE. Otherwise, it returns FALSE. When *language* is omitted, it returns language name as string. If no language is set previously, it returns FALSE.

See also **mb_send_mail()**.

mb_output_handler (PHP 4 >= 4.0.6)

Callback function converts character encoding in output buffer

string **mb_output_handler** (string contents, int status) \linebreak

mb_output_handler() is ob_start() callback function. **mb_output_handler()** converts characters in output buffer from internal character encoding to HTTP output character encoding.

4.1.0 or later version, this handler adds charset HTTP header when following conditions are met:

- Does not set Content-Type by header()
- Default MIME type begins with text/
- http_output setting is other than pass

contents : Output buffer contents

status : Output buffer status

Return Value: String converted

Příklad 1. `mb_output_handler()` example

```
mb_http_output( "UTF-8" );
ob_start( "mb_output_handler" );
```

Poznámka: If you want to output some binary data such as image from PHP script, you must set output encoding to "pass" using `mb_http_output()`.

See also `ob_start()`.

`mb_parse_str` (PHP 4 >= 4.0.6)

Parse GET/POST/COOKIE data and set global variable

boolean **mb_parse_str** (string *encoded_string* [, array *result*]) \linebreak

mb_parse_str() parses GET/POST/COOKIE data and sets global variables. Since PHP does not provide raw POST/COOKIE data, it can only be used for GET data for now. It parses URL encoded data, detects encoding, converts coding to internal encoding and sets values to *result* array or global variables.

encoded_string: URL encoded data.

result: Array contains decoded and character encoding converted values.

Return Value: It returns `TRUE` for success or `FALSE` for failure.

See also `mb_detect_order()`, `mb_internal_encoding()`.

`mb_preferred_mime_name` (PHP 4 >= 4.0.6)

Get MIME charset string

string **mb_preferred_mime_name** (string *encoding*) \linebreak

mb_preferred_mime_name() returns MIME charset string for character encoding *encoding*. It returns charset string.

Příklad 1. mb_preferred_mime_string() example

```
$outputenc = "sjis-win";
mb_http_output($outputenc);
ob_start("mb_output_handler");
header("Content-Type: text/html; charset=" . mb_preferred_mime_name($outputenc));
```

mb_regex_encoding (PHP 4 >= 4.2.0)

Returns current encoding for multibyte regex as string

string **mb_regex_encoding** ([string encoding]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_regex_encoding() returns the character encoding used by multibyte regex functions.

If the optional parameter *encoding* is specified, it is set to the character encoding for multibyte regex. The default value is the internal character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: mb_internal_encoding(), mb_ereg()

mb_send_mail (PHP 4 >= 4.0.6)

Send encoded mail.

boolean **mb_send_mail** (string to, string subject, string message [, string additional_headers [, string additional_parameter]]) \linebreak

mb_send_mail() sends email. Headers and message are converted and encoded according to mb_language() setting. **mb_send_mail()** is wrapper function of mail(). See mail() for details.

to is mail addresses send to. Multiple recipients can be specified by putting a comma between each address in to. This parameter is not automatically encoded.

subject is subject of mail.

message is mail message.

additional_headers is inserted at the end of the header. This is typically used to add extra headers. Multiple extra headers are separated with a newline ("\n").

additional_parameter is a MTA command line parameter. It is useful when setting the correct Return-Path header when using sendmail.

Vrací TRUE při úspěchu, FALSE při selhání.

See also mail(), mb_encode_mimeheader(), and mb_language().

mb_split (PHP 4 >= 4.2.0)

Split multibyte string using regular expression

array **mb_split** (string pattern, string string [, int limit]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

mb_split() split multibyte *string* using regular expression *pattern* and returns the result as an array.

If optional parameter *limit* is specified, it will be split in *limit* elements as maximum.

The internal encoding or the character encoding specified in mb_regex_encoding() will be used as character encoding.

Poznámka: This function is supported in PHP 4.2.0 or higher.

See also: mb_regex_encoding(), mb_ereg().

mb_strcut (PHP 4 >= 4.0.6)

Get part of string

string **mb_strcut** (string str, int start [, int length [, string encoding]]) \linebreak

mb_strcut() returns the portion of *str* specified by the *start* and *length* parameters.

mb_strcut() performs equivalent operation as mb_substr() with different method. If *start* position is multi-byte character's second byte or larger, it starts from first byte of multi-byte character.

It subtracts string from *str* that is shorter than *length* AND character that is not part of multi-byte string or not being middle of shift sequence.

encoding is character encoding. If it is not set, internal character encoding is used.

See also mb_substr(), mb_internal_encoding().

mb_strimwidth (PHP 4 >= 4.0.6)

Get truncated string with specified width

string **mb_strimwidth** (string *str*, int *start*, int *width*, string *trimmarker* [, string *encoding*]) \linebreak

mb_strimwidth() truncates string *str* to specified *width*. It returns truncated string.

If *trimmarker* is set, *trimmarker* is appended to return value.

start is start position offset. Number of characters from the beginning of string. (First character is 0)

trimmarker is string that is added to the end of string when string is truncated.

encoding is character encoding. If it is omitted, internal encoding is used.

Příklad 1. mb_strimwidth() example

```
$str = mb_strimwidth($str, 0, 40, "...>");
```

See also: mb_strwidth(), mb_internal_encoding().

mb_strlen (PHP 4 >= 4.0.6)

Get string length

string **mb_strlen** (string *str* [, string *encoding*]) \linebreak

mb_strlen() returns number of characters in string *str* having character encoding *encoding*. A multi-byte character is counted as 1.

encoding is character encoding for *str*. If *encoding* is omitted, internal character encoding is used.

See also mb_internal_encoding(), strlen().

mb_strpos (PHP 4 >= 4.0.6)

Find position of first occurrence of string in a string

int **mb_strpos** (string *haystack*, string *needle* [, int *offset* [, string *encoding*]]) \linebreak

mb_strpos() returns the numeric position of the first occurrence of *needle* in the *haystack* string. If *needle* is not found, it returns FALSE.

mb_strpos() performs multi-byte safe strpos() operation based on number of characters. *needle* position is counted from the beginning of the *haystack*. First character's position is 0. Second character position is 1, and so on.

If *encoding* is omitted, internal character encoding is used. `mb_strrpos()` accepts *string* for *needle* where `strrpos()` accepts only character.

offset is search offset. If it is not specified, 0 is used.

encoding is character encoding name. If it is omitted, internal character encoding is used.

See also `mb_strpos()`, `mb_internal_encoding()`, `strpos()`

mb_strrpos (PHP 4 >= 4.0.6)

Find position of last occurrence of a string in a string

int **mb_strrpos** (string haystack, string needle [, string encoding]) \linebreak

mb_strrpos() returns the numeric position of the last occurrence of *needle* in the *haystack* string. If *needle* is not found, it returns FALSE.

mb_strrpos() performs multi-byte safe `strrpos()` operation based on number of characters. *needle* position is counted from the beginning of *haystack*. First character's position is 0. Second character position is 1.

If *encoding* is omitted, internal encoding is assumed. **mb_strrpos()** accepts *string* for *needle* where `strrpos()` accepts only character.

encoding is character encoding. If it is not specified, internal character encoding is used.

See also `mb_strpos()`, `mb_internal_encoding()`, `strrpos()`.

mb_strwidth (PHP 4 >= 4.0.6)

Return width of string

int **mb_strwidth** (string str [, string encoding]) \linebreak

mb_strwidth() returns width of string *str*.

Multi-byte character usually twice of width compare to single byte character.

Character width

U+0000 - U+0019	0
U+0020 - U+1FFF	1
U+2000 - U+FF60	2
U+FF61 - U+FF9F	1
U+FFA0 -	2

encoding is character encoding. If it is omitted, internal encoding is used.

See also: `mb_strimwidth()`, `mb_internal_encoding()`.

mb_substitute_character (PHP 4 >= 4.0.6)

Set/Get substitution character

mixed **mb_substitute_character** ([mixed substrchar]) \linebreak

mb_substitute_character() specifies substitution character when input character encoding is invalid or character code is not exist in output character encoding. Invalid characters may be substituted NULL(no output), string or integer value (Unicode character code value).

This setting affects `mb_detect_encoding()` and `mb_send_mail()`.

substchar : Specify Unicode value as integer or specify as string as follows

- "none" : no output
- "long" : Output character code value (Example: U+3000,JIS+7E7E)

Return Value: If *substchar* is set, it returns TRUE for success, otherwise returns FALSE. If *substchar* is not set, it returns Unicode value or "none"/"long".

Příklad 1. mb_substitute_character() example

```
/* Set with Unicode U+3013 (GETA MARK) */
mb_substitute_character(0x3013);

/* Set hex format */
mb_substitute_character("long");

/* Display current setting */
echo mb_substitute_character();
```

mb_substr (PHP 4 >= 4.0.6)

Get part of string

string **mb_substr** (string str, int start [, int length [, string encoding]]) \linebreak

mb_substr() returns the portion of *str* specified by the *start* and *length* parameters.

mb_substr() performs multi-byte safe substr() operation based on number of characters. Position is counted from the beginning of *str*. First character's position is 0. Second character position is 1, and so on.

If *encoding* is omitted, internal encoding is assumed.

encoding is character encoding. If it is omitted, internal character encoding is used.

See also `mb_strcut()`, `mb_internal_encoding()`.

LIV. MCAL functions

MCAL stands for Modular Calendar Access Library.

Libmcal is a C library for accessing calendars. It's written to be very modular, with pluggable drivers. MCAL is the calendar equivalent of the IMAP module for mailboxes.

With mcal support, a calendar stream can be opened much like the mailbox stream with the IMAP support. Calendars can be local file stores, remote ICAP servers, or other formats that are supported by the mcal library.

Calendar events can be pulled up, queried, and stored. There is also support for calendar triggers (alarms) and recurring events.

With libmcal, central calendar servers can be accessed, removing the need for any specific database or local file programming.

To get these functions to work, you have to compile PHP with `--with-mcal`. That requires the mcal

library to be installed. Grab the latest version from <http://mc.al.chek.com/> and compile and install it.

The following constants are defined when using the MCAL module. For weekdays :

- MCAL_SUNDAY
- MCAL_MONDAY
- MCAL_TUESDAY
- MCAL_WEDNESDAY
- MCAL_THURSDAY
- MCAL_FRIDAY
- MCAL_SATURDAY

For recurrence :

- MCAL_RECUR_NONE
- MCAL_RECUR_DAILY
- MCAL_RECUR_WEEKLY
- MCAL_RECUR_MONTHLY_MDAY
- MCAL_RECUR_MONTHLY_WDAY
- MCAL_RECUR_YEARLY

For months :

- MCAL_JANUARY
- MCAL_FEBRUARY
- MCAL_MARCH
- MCAL_APRIL
- MCAL_MAY
- MCAL_JUNE
- MCAL_JULY
- MCAL_AUGUST
- MCAL_SEPTEMBER
- MCAL_OCTOBER
- MCAL_NOVEMBER
- MCAL_DECEMBER

Most of the functions use an internal event structure that is unique for each stream. This alleviates the need to pass around large objects between functions. There are convenience functions for setting, initializing, and retrieving the event structure values.

mcalf_append_event (PHP 4 >= 4.0.0)

Store a new event into an MCAL calendar

int **mcalf_append_event** (int mcal_stream) \linebreak

mcalf_append_event() Stores the global event into an MCAL calendar for the given stream.

Returns the id of the newly inserted event.

mcalf_close (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Close an MCAL stream

int **mcalf_close** (int mcal_stream, int flags) \linebreak

Closes the given mcal stream.

mcalf_create_calendar (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Create a new MCAL calendar

string **mcalf_create_calendar** (int stream, string calendar) \linebreak

Creates a new calendar named *calendar*.

mcalf_date_compare (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Compares two dates

int **mcalf_date_compare** (int a_year, int a_month, int a_day, int b_year, int b_month, int b_day) \linebreak

mcalf_date_compare() Compares the two given dates, returns <0, 0, >0 if a<b, a==b, a>b respectively.

mcalf_date_valid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns TRUE if the given year, month, day is a valid date

int **mcalf_date_valid** (int year, int month, int day) \linebreak

mcalf_date_valid() Returns TRUE if the given year, month and day is a valid date, FALSE if not.

mcalday_of_week (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns the day of the week of the given date

```
int mcalday_of_week ( int year, int month, int day) \linebreak
```

mcalday_of_week() returns the day of the week of the given date. Possible return values range from 0 for Sunday through 6 for Saturday.

mcalday_of_year (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns the day of the year of the given date

```
int mcalday_of_year ( int year, int month, int day) \linebreak
```

mcalday_of_year() returns the day of the year of the given date.

mcaldays_in_month (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns the number of days in the given month

```
int mcaldays_in_month ( int month, int leap year) \linebreak
```

mcaldays_in_month() Returns the number of days in the given month, taking into account if the given year is a leap year or not.

mcaldel_calendar (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Delete an MCAL calendar

```
string mcaldel_calendar ( int stream, string calendar) \linebreak
```

Deletes the calendar named *calendar*.

mcaldel_event (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Delete an event from an MCAL calendar

```
int mcaldel_event ( int mcald_stream [, int event_id]) \linebreak
```

mcaldel_event() deletes the calendar event specified by the event_id.

Returns TRUE.

mcald_event_add_attribute (PHP 3>= 3.0.15, PHP 4 >= 4.0.0)

Adds an attribute and a value to the streams global event structure

void **mcald_event_add_attribute** (int stream, string attribute, string value) \linebreak

mcald_event_add_attribute() adds an attribute to the stream's global event structure with the value given by "value".

mcald_event_init (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Initializes a streams global event structure

int **mcald_event_init** (int stream) \linebreak

mcald_event_init() initializes a streams global event structure. this effectively sets all elements of the structure to 0, or the default settings.

Returns TRUE.

mcald_event_set_alarm (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the alarm of the streams global event structure

int **mcald_event_set_alarm** (int stream, int alarm) \linebreak

mcald_event_set_alarm() sets the streams global event structure's alarm to the given minutes before the event.

Returns TRUE.

mcald_event_set_category (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the category of the streams global event structure

int **mcald_event_set_category** (int stream, string category) \linebreak

mcald_event_set_category() sets the streams global event structure's category to the given string.

Returns TRUE.

mcald_event_set_class (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the class of the streams global event structure

int **mcald_event_set_class** (int stream, int class) \linebreak

mcald_event_set_class() sets the streams global event structure's class to the given value. The class is either 1 for public, or 0 for private.

Returns TRUE.

mcald_event_set_description (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the description of the streams global event structure

int **mcald_event_set_description** (int stream, string description) \linebreak

mcald_event_set_description() sets the streams global event structure's description to the given string.

Returns TRUE.

mcald_event_set_end (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the end date and time of the streams global event structure

int **mcald_event_set_end** (int stream, int year, int month [, int day [, int hour [, int min [, int sec]]]]) \linebreak

mcald_event_set_end() sets the streams global event structure's end date and time to the given values.

Returns TRUE.

mcald_event_set_recur_daily (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the recurrence of the streams global event structure

int **mcald_event_set_recur_daily** (int stream, int year, int month, int day, int interval) \linebreak

mcald_event_set_recur_daily() sets the streams global event structure's recurrence to the given value to be reoccurring on a daily basis, ending at the given date.

mcald_event_set_recur_monthly_mday (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the recurrence of the streams global event structure

int **mcald_event_set_recur_monthly_mday** (int stream, int year, int month, int day, int interval) \linebreak

mcald_event_set_recur_monthly_mday() sets the streams global event structure's recurrence to the given value to be reoccurring on a monthly by month day basis, ending at the given date.

mcald_event_set_recur_monthly_wday (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the recurrence of the streams global event structure

```
int mcald_event_set_recur_monthly_wday ( int stream, int year, int month, int day, int interval) \linebreak
```

mcald_event_set_recur_monthly_wday() sets the streams global event structure's recurrence to the given value to be reoccurring on a monthly by week basis, ending at the given date.

mcald_event_set_recur_none (PHP 3>= 3.0.15, PHP 4 >= 4.0.0)

Sets the recurrence of the streams global event structure

```
int mcald_event_set_recur_none ( int stream) \linebreak
```

mcald_event_set_recur_none() sets the streams global event structure to not recur (event->recur_type is set to MCAL_RECUR_NONE).

mcald_event_set_recur_weekly (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the recurrence of the streams global event structure

```
int mcald_event_set_recur_weekly ( int stream, int year, int month, int day, int interval, int weekdays) \linebreak
```

mcald_event_set_recur_weekly() sets the streams global event structure's recurrence to the given value to be reoccurring on a weekly basis, ending at the given date.

mcald_event_set_recur_yearly (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the recurrence of the streams global event structure

```
int mcald_event_set_recur_yearly ( int stream, int year, int month, int day, int interval) \linebreak
```

mcald_event_set_recur_yearly() sets the streams global event structure's recurrence to the given value to be reoccurring on a yearly basis, ending at the given date.

mcald_event_set_start (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the start date and time of the streams global event structure

```
int mcald_event_set_start ( int stream, int year, int month [, int day [, int hour [, int min [, int sec]]]]) \linebreak
```

mcald_event_set_start() sets the streams global event structure's start date and time to the given values.

Returns TRUE.

mcald_event_set_title (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Sets the title of the streams global event structure

int **mcald_event_set_title** (int stream, string title) \linebreak

mcald_event_set_title() sets the streams global event structure's title to the given string.

Returns TRUE.

mcald_expunge (unknown)

Deletes all events marked for being expunged.

int **mcald_expunge** (int stream) \linebreak

mcald_expunge() Deletes all events which have been previously marked for deletion.

mcald_fetch_current_stream_event (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns an object containing the current streams event structure

object **mcald_fetch_current_stream_event** (int stream) \linebreak

mcald_fetch_current_stream_event() returns the current stream's event structure as an object containing:

- int id - ID of that event.
- int public - TRUE if the event if public, FALSE if it is private.
- string category - Category string of the event.
- string title - Title string of the event.
- string description - Description string of the event.
- int alarm - number of minutes before the event to send an alarm/reminder.
- object start - Object containing a datetime entry.
- object end - Object containing a datetime entry.
- int recur_type - recurrence type
- int recur_interval - recurrence interval
- datetime recur_enddate - recurrence end date
- int recur_data - recurrence data

All datetime entries consist of an object that contains:

- int year - year

- int month - month
- int mday - day of month
- int hour - hour
- int min - minutes
- int sec - seconds
- int alarm - minutes before event to send an alarm

mcal_fetch_event (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Fetches an event from the calendar stream

object **mcal_fetch_event** (int mcald_stream, int event_id [, int options]) \linebreak

mcal_fetch_event() fetches an event from the calendar stream specified by *id*.

Returns an event object consisting of:

- int id - ID of that event.
- int public - TRUE if the event is public, FALSE if it is private.
- string category - Category string of the event.
- string title - Title string of the event.
- string description - Description string of the event.
- int alarm - number of minutes before the event to send an alarm/reminder.
- object start - Object containing a datetime entry.
- object end - Object containing a datetime entry.
- int recur_type - recurrence type
- int recur_interval - recurrence interval
- datetime recur_enddate - recurrence end date
- int recur_data - recurrence data

All datetime entries consist of an object that contains:

- int year - year
- int month - month
- int mday - day of month
- int hour - hour
- int min - minutes
- int sec - seconds
- int alarm - minutes before event to send an alarm

The possible values for recur_type are:

- 0 - Indicates that this event does not recur
- 1 - This event recurs daily
- 2 - This event recurs on a weekly basis
- 3 - This event recurs monthly on a specific day of the month (e.g. the 10th of the month)
- 4 - This event recurs monthly on a sequenced day of the week (e.g. the 3rd Saturday)
- 5 - This event recurs on an annual basis

mcalf_is_leap_year (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns if the given year is a leap year or not

`int mcal_is_leap_year (int year)` \linebreak

`mcalf_is_leap_year()` returns 1 if the given year is a leap year, 0 if not.

mcalf_list_alarms (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Return a list of events that has an alarm triggered at the given datetime

`array mcal_list_alarms (int mcal_stream [, int begin_year [, int begin_month [, int begin_day [, int end_year [, int end_month [, int end_day]]]]]])` \linebreak

Returns an array of event ID's that has an alarm going off between the start and end dates, or if just a stream is given, uses the start and end dates in the global event structure.

`mcalf_list_events()` function takes in an optional beginning date and an end date for a calendar stream. An array of event id's that are between the given dates or the internal event dates are returned.

mcalf_list_events (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Return a list of IDs for a date or a range of dates.

`array mcal_list_events (int mcal_stream, object begin_date [, object end_date])` \linebreak

Returns an array of ID's that are between the start and end dates, or if just a stream is given, uses the start and end dates in the global event structure.

`mcalf_list_events()` function takes in an beginning date and an optional end date for a calendar stream. An array of event id's that are between the given dates or the internal event dates are returned.

mcalf_next_recurrence (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns the next recurrence of the event

int **mcalf_next_recurrence** (int stream, int weekstart, array next) \linebreak

mcalf_next_recurrence() returns an object filled with the next date the event occurs, on or after the supplied date. Returns empty date field if event does not occur or something is invalid. Uses weekstart to determine what day is considered the beginning of the week.

mcalf_open (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Opens up an MCAL connection

int **mcalf_open** (string calendar, string username, string password [, int options]) \linebreak

Returns an MCAL stream on success, FALSE on error.

mcalf_open() opens up an MCAL connection to the specified *calendar* store. If the optional *options* is specified, passes the *options* to that mailbox also. The streams internal event structure is also initialized upon connection.

mcalf_popen (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Opens up a persistent MCAL connection

int **mcalf_popen** (string calendar, string username, string password [, int options]) \linebreak

Returns an MCAL stream on success, FALSE on error.

mcalf_popen() opens up an MCAL connection to the specified *calendar* store. If the optional *options* is specified, passes the *options* to that mailbox also. The streams internal event structure is also initialized upon connection.

mcalf_rename_calendar (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Rename an MCAL calendar

string **mcalf_rename_calendar** (int stream, string old_name, string new_name) \linebreak

Renames the calendar *old_name* to *new_name*.

mcalf_reopen (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Reopens an MCAL connection

int **mcalf_reopen** (string calendar [, int options]) \linebreak

Reopens an MCAL stream to a new calendar.

mcalf_reopen() reopens an MCAL connection to the specified *calendar* store. If the optional *options* is specified, passes the *options* to that mailbox also.

mcald_snooze (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Turn off an alarm for an event

int **mcald_snooze** (int id) \linebreak

mcald_snooze() turns off an alarm for a calendar event specified by the id.

Returns TRUE.

mcald_store_event (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Modify an existing event in an MCAL calendar

int **mcald_store_event** (int mcald_stream) \linebreak

mcald_store_event() Stores the modifications to the current global event for the given stream.

Returns the event id of the modified event on success and FALSE on error.

mcald_time_valid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Returns TRUE if the given year, month, day is a valid time

int **mcald_time_valid** (int hour, int minutes, int seconds) \linebreak

mcald_time_valid() Returns TRUE if the given hour, minutes and seconds is a valid time, FALSE if not.

mcald_week_of_year (PHP 4 >= 4.0.0)

Returns the week number of the given date

int **mcald_week_of_year** (int day, int month, int year) \linebreak

LV. Mcrypt Encryption Functions

This is an interface to the mcrypt library, which supports a wide variety of block algorithms such as DES, TripleDES, Blowfish (default), 3-WAY, SAFER-SK64, SAFER-SK128, TWOFISH, TEA, RC2 and GOST in CBC, OFB, CFB and ECB cipher modes. Additionally, it supports RC6 and IDEA which are considered "non-free".

Mcrypt can be used to encrypt and decrypt using the above mentioned ciphers. If you linked against libmcrypt-2.2.x, the four important mcrypt commands (mcrypt_cfb(), mcrypt_cbc(), mcrypt_ecb(), and mcrypt_ofb()) can operate in both modes which are named MCRYPT_ENCRYPT and MCRYPT_DECRYPT, respectively.

Příklad 1. Encrypt an input value with TripleDES under 2.2.x in ECB mode

```
<?php
$key = "this is a very secret key";
$input = "Let us meet at 9 o'clock at the secret place.";

$encrypted_data = mcrypt_ecb (MCRYPT_3DES, $key, $input, MCRYPT_ENCRYPT);
?>
```

This example will give you the encrypted data as a string in \$encrypted_data.

If you linked against libmcrypt 2.4.x, these functions are still available, but it is recommended that you use the advanced functions.

Příklad 2. Encrypt an input value with TripleDES under 2.4.x in ECB mode

```
<?php
$key = "this is a very secret key";
$input = "Let us meet at 9 o'clock at the secret place.";

$td = mcrypt_module_open (MCRYPT_TripleDES, "", MCRYPT_MODE_ECB, "");
$iv = mcrypt_create_iv (mcrypt_enc_get_iv_size ($td), MCRYPT_RAND);
mcrypt_generic_init ($td, $key, $iv);
$encrypted_data = mcrypt_generic ($td, $input);
mcrypt_generic_end ($td);
?>
```

This example will give you the encrypted data as a string in \$encrypted_data.

Requirements

These functions work using mcrypt (<http://mcrypt.hellug.gr/>).

If you linked against libmcrypt 2.4.x, the following additional block algorithms are supported:

CAST, LOKI97, RIJNDAEL, SAFERPLUS, SERPENT and the following stream ciphers: ENIGMA

(crypt), PANAMA, RC4 and WAKE. With libmccrypt 2.4.x another cipher mode is also available; nOFB.

Installation

To use it, download libmccrypt-x.x.tar.gz from here (<http://mccrypt.hellug.gr/>) and follow the included installation instructions. You need to compile PHP with the `--with-mccrypt` parameter to enable this extension. Make sure you compile libmccrypt with the option `--disable-posix-threads`.

Runtime Configuration

Resource types

Toto rozšíření nemá definován žádný typ prostředku (resource).

Predefined constants

Mccrypt can operate in four block cipher modes (CBC, OFB, CFB, and ECB). If linked against libmccrypt-2.4.x mccrypt can also operate in the block cipher mode nOFB and in STREAM mode. Below you find a list with all supported encryption modes together with the constants that are defines for the encryption mode. For a more complete reference and discussion see Applied Cryptography by Schneier (ISBN 0-471-11709-9).

- `MCRYPT_MODE_ECB` (electronic codebook) is suitable for random data, such as encrypting other keys. Since data there is short and random, the disadvantages of ECB have a favorable negative effect.
- `MCRYPT_MODE_CBC` (cipher block chaining) is especially suitable for encrypting files where the security is increased over ECB significantly.
- `MCRYPT_MODE_CFB` (cipher feedback) is the best mode for encrypting byte streams where single bytes must be encrypted.
- `MCRYPT_MODE_OFB` (output feedback, in 8bit) is comparable to CFB, but can be used in applications where error propagation cannot be tolerated. It's insecure (because it operates in 8bit mode) so it is not recommended to use it.
- `MCRYPT_MODE_NOFB` (output feedback, in nbit) is comparable to OFB, but more secure because it operates on the block size of the algorithm.
- `MCRYPT_MODE_STREAM` is an extra mode to include some stream algorithms like WAKE or RC4.

Here is a list of ciphers which are currently supported by the mccrypt extension. For a complete list of supported ciphers, see the defines at the end of `mccrypt.h`. The general rule with the mccrypt-2.2.x API is that you can access the cipher from PHP with `MCRYPT_ciphername`. With the mccrypt-2.4.x

API these constants also work, but it is possible to specify the name of the cipher as a string with a

call to `mccrypt_module_open()`.

- `MCCRYPT_3DES`
- `MCCRYPT_ARCFOUR_IV` (libmccrypt 2.4.x only)
- `MCCRYPT_ARCFOUR` (libmccrypt 2.4.x only)
- `MCCRYPT_BLOWFISH`
- `MCCRYPT_CAST_128`
- `MCCRYPT_CAST_256`
- `MCCRYPT_CRYPT`
- `MCCRYPT_DES`
- `MCCRYPT_DES_COMPAT` (libmccrypt 2.2.x only)
- `MCCRYPT_ENIGMA` (libmccrypt 2.4.x only, alias for `MCCRYPT_CRYPT`)
- `MCCRYPT_GOST`
- `MCCRYPT_IDEA` (non-free)
- `MCCRYPT_LOKI97` (libmccrypt 2.4.x only)
- `MCCRYPT_MARS` (libmccrypt 2.4.x only, non-free)
- `MCCRYPT_PANAMA` (libmccrypt 2.4.x only)
- `MCCRYPT_RIJNDAEL_128` (libmccrypt 2.4.x only)
- `MCCRYPT_RIJNDAEL_192` (libmccrypt 2.4.x only)
- `MCCRYPT_RIJNDAEL_256` (libmccrypt 2.4.x only)
- `MCCRYPT_RC2`
- `MCCRYPT_RC4` (libmccrypt 2.2.x only)
- `MCCRYPT_RC6` (libmccrypt 2.4.x only)
- `MCCRYPT_RC6_128` (libmccrypt 2.2.x only)
- `MCCRYPT_RC6_192` (libmccrypt 2.2.x only)
- `MCCRYPT_RC6_256` (libmccrypt 2.2.x only)
- `MCCRYPT_SAFER64`
- `MCCRYPT_SAFER128`
- `MCCRYPT_SAFERPLUS` (libmccrypt 2.4.x only)
- `MCCRYPT_SERPENT`(libmccrypt 2.4.x only)
- `MCCRYPT_SERPENT_128` (libmccrypt 2.2.x only)
- `MCCRYPT_SERPENT_192` (libmccrypt 2.2.x only)
- `MCCRYPT_SERPENT_256` (libmccrypt 2.2.x only)
- `MCCRYPT_SKIPJACK` (libmccrypt 2.4.x only)
- `MCCRYPT_TEAN` (libmccrypt 2.2.x only)
- `MCCRYPT_THREEWAY`
- `MCCRYPT_TRIPLEDES` (libmccrypt 2.4.x only)
- `MCCRYPT_TWOFISH` (for older mccrypt 2.x versions, or mccrypt 2.4.x)
- `MCCRYPT_TWOFISH128` (`TWOFISHxxx` are available in newer 2.x versions, but not in the 2.4.x

versions)

- MCRYPT_TWOFISH192
- MCRYPT_TWOFISH256
- MCRYPT_WAKE (libmcrypt 2.4.x only)
- MCRYPT_XTEA (libmcrypt 2.4.x only)

You must (in CFB and OFB mode) or can (in CBC mode) supply an initialization vector (IV) to the respective cipher function. The IV must be unique and must be the same when decrypting/encrypting. With data which is stored encrypted, you can take the output of a function of the index under which the data is stored (e.g. the MD5 key of the filename). Alternatively, you can transmit the IV together with the encrypted data (see chapter 9.3 of Applied Cryptography by Schneier (ISBN 0-471-11709-9) for a discussion of this topic).

mccrypt_cbc (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Encrypt/decrypt data in CBC mode

```
string mccrypt_cbc ( int cipher, string key, string data, int mode [, string iv]) \linebreak
string mccrypt_cbc ( string cipher, string key, string data, int mode [, string iv]) \linebreak
```

The first prototype is when linked against libmccrypt 2.2.x, the second when linked against libmccrypt 2.4.x.

mccrypt_cbc() encrypts or decrypts (depending on *mode*) the *data* with *cipher* and *key* in CBC cipher mode and returns the resulting string.

Cipher is one of the MCRYPT_ciphernam constants.

Key is the key supplied to the algorithm. It must be kept secret.

Data is the data which shall be encrypted/decrypted.

Mode is MCRYPT_ENCRYPT or MCRYPT_DECRYPT.

IV is the optional initialization vector.

See also: mccrypt_cfb(), mccrypt_ecb(), and mccrypt_ofb().

mccrypt_cfb (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Encrypt/decrypt data in CFB mode

```
string mccrypt_cfb ( int cipher, string key, string data, int mode, string iv) \linebreak
string mccrypt_cfb ( string cipher, string key, string data, int mode [, string iv]) \linebreak
```

The first prototype is when linked against libmccrypt 2.2.x, the second when linked against libmccrypt 2.4.x.

mccrypt_cfb() encrypts or decrypts (depending on *mode*) the *data* with *cipher* and *key* in CFB cipher mode and returns the resulting string.

Cipher is one of the MCRYPT_ciphernam constants.

Key is the key supplied to the algorithm. It must be kept secret.

Data is the data which shall be encrypted/decrypted.

Mode is MCRYPT_ENCRYPT or MCRYPT_DECRYPT.

IV is the initialization vector.

See also: mccrypt_cbc(), mccrypt_ecb(), and mccrypt_ofb().

mccrypt_create_iv (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Create an initialization vector (IV) from a random source

```
string mccrypt_create_iv ( int size, int source) \linebreak
```

mccrypt_create_iv() is used to create an IV.

mcrypt_create_iv() takes two arguments, *size* determines the size of the IV, *source* specifies the source of the IV.

The source can be MCRYPT_RAND (system random number generator), MCRYPT_DEV_RANDOM (read data from /dev/random) and MCRYPT_DEV_URANDOM (read data from /dev/urandom). If you use MCRYPT_RAND, make sure to call `srand()` before to initialize the random number generator.

Příklad 1. `mcrypt_create_iv()` example

```
<?php
$cipher = MCRYPT_TripleDES;
$block_size = mcrypt_get_block_size ($cipher);
$iv = mcrypt_create_iv ($block_size, MCRYPT_DEV_RANDOM);
?>
```

The IV is only meant to give an alternative seed to the encryption routines. This IV does not need to be secret at all, though it can be desirable. You even can send it along with your ciphertext without losing security.

More information can be found at ???, ??? and in chapter 9.3 of Applied Cryptography by Schneier (ISBN 0-471-11709-9) for a discussion of this topic.

mcrypt_decrypt (PHP 4 >= 4.0.2)

Decrypts crypttext with given parameters

string **mcrypt_decrypt** (string cipher, string key, string data, string mode [, string iv]) \linebreak

mcrypt_decrypt() decrypts the data and returns the unencrypted data.

Cipher is one of the MCRYPT_ciphertype constants of the name of the algorithm as string.

Key is the key with which the data is encrypted. If it's smaller than the required keysize, it is padded with '\0'.

Data is the data that will be decrypted with the given cipher and mode. If the size of the data is not `n * blocksize`, the data will be padded with '\0'.

Mode is one of the MCRYPT_MODE_modename constants of one of "ecb", "cbc", "cfb", "ofb", "nofb" or "stream".

The *IV* parameter is used for the initialisation in CBC, CFB, OFB modes, and in some algorithms in STREAM mode. If you do not supply an IV, while it is needed for an algorithm, the function issues a warning and uses an IV with all bytes set to '\0'.

mcrypt_ecb (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Encrypt/decrypt data in ECB mode

```
string mcrypt_ecb ( int cipher, string key, string data, int mode) \linebreak
string mcrypt_ecb ( string cipher, string key, string data, int mode [, string iv]) \linebreak
```

The first prototype is when linked against libmcrypt 2.2.x, the second when linked against libmcrypt 2.4.x.

mcrypt_ecb() encrypts or decrypts (depending on *mode*) the *data* with *cipher* and *key* in ECB cipher mode and returns the resulting string.

Cipher is one of the MCRYPT_ciphernam constants.

Key is the key supplied to the algorithm. It must be kept secret.

Data is the data which shall be encrypted/decrypted.

Mode is MCRYPT_ENCRYPT or MCRYPT_DECRYPT.

See also: `mcrypt_cbc()`, `mcrypt_cfb()`, and `mcrypt_ofb()`.

mcrypt_enc_get_algorithms_name (PHP 4 >= 4.0.2)

Returns the name of the opened algorithm

```
string mcrypt_enc_get_algorithms_name ( resource td) \linebreak
```

This function returns the name of the algorithm.

mcrypt_enc_get_block_size (PHP 4 >= 4.0.2)

Returns the blocksize of the opened algorithm

```
int mcrypt_enc_get_block_size ( resource td) \linebreak
```

This function returns the block size of the algorithm specified by the encryption descriptor *td* in bytes.

mcrypt_enc_get_iv_size (PHP 4 >= 4.0.2)

Returns the size of the IV of the opened algorithm

```
int mcrypt_enc_get_iv_size ( resource td) \linebreak
```

This function returns the size of the iv of the algorithm specified by the encryption descriptor in bytes. If it returns '0' then the IV is ignored in the algorithm. An IV is used in cbc, cfb and ofb modes, and in some algorithms in stream mode.

mdecrypt_enc_get_key_size (PHP 4 >= 4.0.2)

Returns the maximum supported keysize of the opened mode

int **mdecrypt_enc_get_key_size** (resource td) \linebreak

This function returns the maximum supported key size of the algorithm specified by the encryption descriptor td in bytes.

mdecrypt_enc_get_modes_name (PHP 4 >= 4.0.2)

Returns the name of the opened mode

string **mdecrypt_enc_get_modes_name** (resource td) \linebreak

This function returns the name of the mode.

mdecrypt_enc_get_supported_key_sizes (PHP 4 >= 4.0.2)

Returns an array with the supported key sizes of the opened algorithm

array **mdecrypt_enc_get_supported_key_sizes** (resource td) \linebreak

Returns an array with the key sizes supported by the algorithm specified by the encryption descriptor. If it returns an empty array then all key sizes between 1 and mdecrypt_enc_get_key_size() are supported by the algorithm.

mdecrypt_enc_is_block_algorithm (PHP 4 >= 4.0.2)

Checks whether the algorithm of the opened mode is a block algorithm

int **mdecrypt_enc_is_block_algorithm** (resource td) \linebreak

This function returns 1 if the algorithm is a block algorithm, or 0 if it is a stream algorithm.

mdecrypt_enc_is_block_algorithm_mode (PHP 4 >= 4.0.2)

Checks whether the encryption of the opened mode works on blocks

int **mdecrypt_enc_is_block_algorithm_mode** (resource td) \linebreak

This function returns 1 if the mode is for use with block algorithms, otherwise it returns 0. (eg. 0 for stream, and 1 for cbc, cfb, ofb).

mcrypt_enc_is_block_mode (PHP 4 >= 4.0.2)

Checks whether the opened mode outputs blocks

```
int mcrypt_enc_is_block_mode ( resource td) \linebreak
```

This function returns 1 if the mode outputs blocks of bytes or 0 if it outputs bytes. (eg. 1 for cbc and ecb, and 0 for cfb and stream).

mcrypt_enc_self_test (PHP 4 >= 4.0.2)

This function runs a self test on the opened module

```
int mcrypt_enc_self_test ( resource td) \linebreak
```

This function runs the self test on the algorithm specified by the descriptor td. If the self test succeeds it returns zero. In case of an error, it returns 1.

mcrypt_encrypt (PHP 4 >= 4.0.2)

Encrypts plaintext with given parameters

```
string mcrypt_encrypt ( string cipher, string key, string data, string mode [, string iv]) \linebreak
```

mcrypt_encrypt() encrypts the data and returns the encrypted data.

Cipher is one of the MCRYPT_cipername constants of the name of the algorithm as string.

Key is the key with which the data will be encrypted. If it's smaller than the required keysize, it is padded with '\0'. It is better not to use ASCII strings for keys. It is recommended to use the mhash functions to create a key from a string.

Data is the data that will be encrypted with the given cipher and mode. If the size of the data is not $n * \text{blocksize}$, the data will be padded with '\0'. The returned crypttext can be larger than the size of the data that is given by *data*.

Mode is one of the MCRYPT_MODE_modename constants of one of "ecb", "cbc", "cfb", "ofb", "nofb" or "stream".

The *IV* parameter is used for the initialisation in CBC, CFB, OFB modes, and in some algorithms in STREAM mode. If you do not supply an IV, while it is needed for an algorithm, the function issues a warning and uses an IV with all bytes set to '\0'.

Příklad 1. mcrypt_encrypt() Example

```
<?php
$iv = mcrypt_create_iv (mcrypt_get_iv_size (MCRYPT_RIJNDAEL_256, MCRYPT_MODE_ECB), MCRYPT_RAND);
$key = "This is a very secret key";
$text = "Meet me at 11 o'clock behind the monument.";
echo strlen ($text)."\n";
```

```
$crypttext = mcrypt_encrypt (MCRYPT_RIJNDAEL_256, $key, $text, MCRYPT_MODE_ECB, $iv);
echo strlen ($crypttext)."\n";
?>
```

The above example will print out:

```
42
64
```

mcrypt_generic (PHP 4 >= 4.0.2)

This function encrypts data

string **mcrypt_generic** (resource td, string data) \linebreak

This function encrypts data. The data is padded with "\0" to make sure the length of the data is n * blocksize. This function returns the encrypted data. Note that the length of the returned string can in fact be longer then the input, due to the padding of the data.

mcrypt_generic_deinit (PHP 4 >= 4.1.1)

This function terminates encrypt specified by the descriptor td

bool **mcrypt_generic_deinit** (resource td) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mcrypt_generic_end (PHP 4 >= 4.0.2)

This function terminates encryption

bool **mcrypt_generic_end** (resource td) \linebreak

This function terminates encryption specified by the encryption descriptor (td). Actually it clears all buffers, and closes all the modules used. Returns FALSE on error, or TRUE on succes.

mccrypt_generic_init (PHP 4 >= 4.0.2)

This function initializes all buffers needed for encryption

```
int mccrypt_generic_init ( resource td, string key, string iv) \linebreak
```

The maximum length of the key should be the one obtained by calling `mccrypt_enc_get_key_size()` and every value smaller than this is legal. The IV should normally have the size of the algorithms block size, but you must obtain the size by calling `mccrypt_enc_get_iv_size()`. IV is ignored in ECB. IV MUST exist in CFB, CBC, STREAM, nOFB and OFB modes. It needs to be random and unique (but not secret). The same IV must be used for encryption/decryption. If you do not want to use it you should set it to zeros, but this is not recommended. The function returns a negative value on error.

You need to call this function before every `mccrypt_generic()` or `mdecrypt_generic()`.

mccrypt_get_block_size (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Get the block size of the specified cipher

```
int mccrypt_get_block_size ( int cipher) \linebreak int mccrypt_get_block_size ( string cipher, string mod-  
ule) \linebreak
```

The first prototype is when linked against libmccrypt 2.2.x, the second when linked against libmccrypt 2.4.x.

`mccrypt_get_block_size()` is used to get the size of a block of the specified *cipher*.

`mccrypt_get_block_size()` takes one or two arguments, the *cipher* and *module*, and returns the size in bytes.

See also: `mccrypt_get_key_size()`.

mccrypt_get_cipher_name (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Get the name of the specified cipher

```
string mccrypt_get_cipher_name ( int cipher) \linebreak string mccrypt_get_cipher_name ( string cipher)  
\linebreak
```

`mccrypt_get_cipher_name()` is used to get the name of the specified cipher.

`mccrypt_get_cipher_name()` takes the cipher number as an argument (libmccrypt 2.2.x) or takes the cipher name as an argument (libmccrypt 2.4.x) and returns the name of the cipher or FALSE, if the cipher does not exist.

Příklad 1. mccrypt_get_cipher_name() Example

```
<?php  
$cipher = MCRYPT_TripleDES;  
  
print mccrypt_get_cipher_name ($cipher);
```

```
?>
```

The above example will produce:

```
3DES
```

mccrypt_get_iv_size (PHP 4 >= 4.0.2)

Returns the size of the IV belonging to a specific cipher/mode combination

```
int mccrypt_get_iv_size ( string cipher, string mode) \linebreak
int mccrypt_get_iv_size ( resource td) \linebreak
```

The first prototype is when linked against libmccrypt 2.2.x, the second when linked against libmccrypt 2.4.x.

mccrypt_get_iv_size() returns the size of the Initialisation Vector (IV) in bytes. On error the function returns `FALSE`. If the IV is ignored in the specified cipher/mode combination zero is returned.

Cipher is one of the `MCRYPT_ciphernam` constants of the name of the algorithm as string.

Mode is one of the `MCRYPT_MODE_modename` constants of one of "ecb", "cbc", "cfb", "ofb", "nofb" or "stream".

Td is the algorithm specified.

mccrypt_get_key_size (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Get the key size of the specified cipher

```
int mccrypt_get_key_size ( int cipher) \linebreak
int mccrypt_get_key_size ( string cipher, string module) \linebreak
```

The first prototype is when linked against libmccrypt 2.2.x, the second when linked against libmccrypt 2.4.x.

mccrypt_get_key_size() is used to get the size of a key of the specified *cipher*.

mccrypt_get_key_size() takes one or two arguments, the *cipher* and *module*, and returns the size in bytes.

See also: `mccrypt_get_block_size()`.

mccrypt_list_algorithms (PHP 4 >= 4.0.2)

Get an array of all supported ciphers

array **mccrypt_list_algorithms** ([string lib_dir]) \linebreak

mccrypt_list_algorithms() is used to get an array of all supported algorithms in the

lib_dir. **mccrypt_list_algorithms()** takes as optional parameter a directory which specifies the directory where all algorithms are located. If not specifies, the value of the `mccrypt.algorithms_dir` `php.ini` directive is used.

Příklad 1. mccrypt_list_algorithms() Example

```
<?php
$algorithms = mccrypt_list_algorithms ( "/usr/local/lib/libmccrypt" );

foreach ( $algorithms as $cipher ) {
    echo $cipher . "/n";
}
?>
```

The above example will produce a list with all supported algorithms in the `"/usr/local/lib/libmccrypt"` directory.

mccrypt_list_modes (PHP 4 >= 4.0.2)

Get an array of all supported modes

array **mccrypt_list_modes** ([string lib_dir]) \linebreak

mccrypt_list_modes() is used to get an array of all supported modes in the *lib_dir*.

mccrypt_list_modes() takes as optional parameter a directory which specifies the directory where all modes are located. If not specifies, the value of the `mccrypt.modes_dir` `php.ini` directive is used.

Příklad 1. mccrypt_list_modes() Example

```
<?php
$modes = mccrypt_list_modes ( );

foreach ( $modes as $mode ) {
    echo "$mode <br/>";
}
?>
```

The above example will produce a list with all supported algorithms in the default mode directory. If it is not set with the ini directive `mccrypt.modes_dir`, the default directory of `mccrypt` is used (which is `/usr/local/lib/libmccrypt`).

mccrypt_module_close (PHP 4 >= 4.0.2)

Free the descriptor `td`

```
bool mccrypt_module_close ( resource td ) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mccrypt_module_get_algo_block_size (PHP 4 >= 4.0.2)

Returns the blocksize of the specified algorithm

```
int mccrypt_module_get_algo_block_size ( string algorithm [, string lib_dir] ) \linebreak
```

This function returns the block size of the algorithm specified in bytes. The optional *lib_dir* parameter can contain the location where the mode module is on the system.

mccrypt_module_get_algo_key_size (PHP 4 >= 4.0.2)

Returns the maximum supported keysize of the opened mode

```
int mccrypt_module_get_algo_key_size ( string algorithm [, string lib_dir] ) \linebreak
```

This function returns the maximum supported key size of the algorithm specified in bytes. The optional *lib_dir* parameter can contain the location where the mode module is on the system.

mccrypt_module_get_supported_key_sizes (PHP 4 >= 4.0.2)

Returns an array with the supported key sizes of the opened algorithm

```
array mccrypt_module_get_supported_key_sizes ( string algorithm [, string lib_dir] ) \linebreak
```

Returns an array with the key sizes supported by the specified algorithm. If it returns an empty array then all key sizes between 1 and `mcrypt_module_get_algo_key_size()` are supported by the algorithm. The optional *lib_dir* parameter can contain the location where the mode module is on the system.

mcrypt_module_is_block_algorithm (PHP 4 >= 4.0.2)

This function checks whether the specified algorithm is a block algorithm

bool `mcrypt_module_is_block_algorithm` (string algorithm [, string lib_dir]) \linebreak

This function returns `TRUE` if the specified algorithm is a block algorithm, or `FALSE` if it is a stream algorithm. The optional *lib_dir* parameter can contain the location where the algorithm module is on the system.

mcrypt_module_is_block_algorithm_mode (PHP 4 >= 4.0.2)

This function returns if the the specified module is a block algorithm or not

bool `mcrypt_module_is_block_algorithm_mode` (string mode [, string lib_dir]) \linebreak

This function returns `TRUE` if the mode is for use with block algorithms, otherwise it returns 0. (eg. 0 for stream, and 1 for cbc, cfb, ofb). The optional *lib_dir* parameter can contain the location where the mode module is on the system.

mcrypt_module_is_block_mode (PHP 4 >= 4.0.2)

This function returns if the the specified mode outputs blocks or not

bool `mcrypt_module_is_block_mode` (string mode [, string lib_dir]) \linebreak

This function returns `TRUE` if the mode outputs blocks of bytes or `FALSE` if it outputs just bytes. (eg. 1 for cbc and ecb, and 0 for cfb and stream). The optional *lib_dir* parameter can contain the location where the mode module is on the system.

mcrypt_module_open (PHP 4 >= 4.0.2)

This function opens the module of the algorithm and the mode to be used

resource `mcrypt_module_open` (string algorithm, string algorithm_directory, string mode, string mode_directory) \linebreak

This function opens the module of the algorithm and the mode to be used. The name of the algorithm is specified in *algorithm*, eg "twofish" or is one of the `MCRYPT_ciphname` constants. The library is closed by calling `mcrypt_module_close()`, but there is no need to call that function if `mcrypt_generic_end()` is called. Normally it returns an encryption descriptor, or `FALSE` on error.

The *algorithm_directory* and *mode_directory* are used to locate the encryption modules. When you supply a directory name, it is used. When you set one of these to the empty string (""), the value set by the *mccrypt.algorithms_dir* or *mccrypt.modes_dir* ini-directive is used. When these are not set, the default directory are used that are compiled in into libmccrypt (usually /usr/local/lib/libmccrypt).

Příklad 1. mccrypt_module_open() Example

```
<?php
$td = mccrypt_module_open (MCRYPT_DES, "", MCRYPT_MODE_ECB, "/usr/lib/mccrypt-
modes" );
?>
```

The above example will try to open the DES cipher from the default directory and the ECB mode from the directory /usr/lib/mccrypt-modes.

mccrypt_module_self_test (PHP 4 >= 4.0.2)

This function runs a self test on the specified module

```
bool mccrypt_module_self_test ( string algorithm [, string lib_dir]) \linebreak
```

This function runs the self test on the algorithm specified. The optional *lib_dir* parameter can contain the location of where the algorithm module is on the system.

The function returns TRUE if the self test succeeds, or FALSE when it fails.

mccrypt_ofb (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Encrypt/decrypt data in OFB mode

```
string mccrypt_ofb ( int cipher, string key, string data, int mode, string iv) \linebreak string mccrypt_ofb (
string cipher, string key, string data, int mode [, string iv]) \linebreak
```

The first prototype is when linked against libmccrypt 2.2.x, the second when linked against libmccrypt 2.4.x.

mccrypt_ofb() encrypts or decrypts (depending on *mode*) the *data* with *cipher* and *key* in OFB cipher mode and returns the resulting string.

Cipher is one of the MCRYPT_ciphernam constants.

Key is the key supplied to the algorithm. It must be kept secret.

Data is the data which shall be encrypted/decrypted.

Mode is MCRYPT_ENCRYPT or MCRYPT_DECRYPT.

IV is the initialization vector.

See also: `mdecrypt_cbc()`, `mdecrypt_cfb()`, and `mdecrypt_ecb()`.

mdecrypt_generic (PHP 4 >= 4.0.2)

This function decrypts data

string **mdecrypt_generic** (resource *td*, string *data*) \linebreak

This function decrypts data. Note that the length of the returned string can in fact be longer than the unencrypted string, due to the padding of the data.

Příklad 1. mdecrypt_generic() Example

```
<?php
$iv_size = mdecrypt_enc_get_iv_size ($td);
$iv = @mdecrypt_create_iv ($iv_size, MCRYPT_RAND);

if (@mdecrypt_generic_init ($td, $key, $iv) != -1)
{
    $c_t = mdecrypt_generic ($td, $plain_text);
    @mdecrypt_generic_init ($td, $key, $iv);
    $p_t = mdecrypt_generic ($td, $c_t);
}
if (strcmp ($p_t, $plain_text, strlen($plain_text)) == 0)
    echo "ok";
else
    echo "error";
?>
```

The above example shows how to check if the data before the encryption is the same as the data after the decryption.

LVI. Mhash funkce

Tyto funkce jsou určeny pro práci s mhash (<http://mhash.sourceforge.net/>).

Toto je interface ke knihvně mhash. mhash podporuje širokou škálu hash algoritmů jako např. MD5, SHA1, GOST a mnoho jiných.

Pokud chcete tyto funkce používat, stáhněte si mhash distribuci z its web site (<http://mhash.sourceforge.net/>) a postupujte podle přiložených instrukcí k instalaci. K aktivaci tohoto modulu budete muset zkompilevat PHP s volbou `--with-mhash`

Mhash se dá použít k vytváření kontrolních součtů, message digests, message authentication codes, and more.

Příklad 1. Compute the MD5 digest and hmac and print it out as hex

```
<?php
$input = "what do ya want for nothing?";
$hash = mhash (MHASH_MD5, $input);
print "The hash is ".bin2hex ($hash)."\n<br>";
$hash = mhash (MHASH_MD5, $input, "Jefe");
print "The hmac is ".bin2hex ($hash)."\n<br>";
?>
```

This will produce:

```
The hash is d03cb659cbf9192dcd066272249f8412
The hmac is 750c783e6ab0b503eaa86e310a5db738
```

Kompletní seznam podporovaných hashů viz dokumentaci mhash. Obecným pravidlem je, že hash algoritmus je dostupný z PHP pomocí MHASH_NAZEVMHASHE. Například TIGER se v PHP používá pomocí konstanty MHASH_TIGER.

Zde je seznam hashů podporovaných mhashem v současné době. Pokud zde není některý hash jmenován, ale v dokumentaci mhash je uveden jako podporovaný, můžete bezpečně předpokládat, že je tato dokumentace zastaralá.

- MHASH_MD5
- MHASH_SHA1
- MHASH_HAVAL256
- MHASH_HAVAL192
- MHASH_HAVAL160
- MHASH_HAVAL128
- MHASH_RIPEMD160
- MHASH_GOST
- MHASH_TIGER
- MHASH_CRC32
- MHASH_CRC32B

mhash (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Spočítat hash

string **mhash** (int hash, string data, string [key]) \linebreak

mhash() aplikuje hash funkci určenou argumentem *hash* na *data* a vrací výsledný hash (také nazývaný digest). Pokud je předán *key*, vrací výsledný HMAC. HMAC is keyed hashing for message authentication, or simply a message digest that depends on the specified key. Not all algorithms supported in mhash can be used in HMAC mode. In case of an error returns **FALSE**.

mhash_count (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Získat nejvyšší dostupné hash id

int **mhash_count** (void) \linebreak

mhash_count() vrací nejvyšší dostupné hash id. Hashe jsou číslovány od 0 po toto hash id.

Příklad 1. Traversing all hashes

```
<?php

$nr = mhash_count();

for ($i = 0; $i <= $nr; $i++) {
    echo sprintf ("The blocksize of %s is %d\n",
        mhash_get_hash_name ($i),
        mhash_get_block_size ($i));
}
?>
```

mhash_get_block_size (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Získat velikost bloku určeného hashe

int **mhash_get_block_size** (int hash) \linebreak

mhash_get_block_size() se používá ke zjištění velikosti bloku argumentu *hash*.

mhash_get_block_size() přijímá jeden argument, *hash* a vrací velikost v bytech nebo **FALSE**, pokud *hash* neexistuje.

mhash_get_hash_name (PHP 3 >= 3.0.9, PHP 4 >= 4.0.0)

Získat název zadaného hashe

string **mhash_get_hash_name** (int hash) \linebreak

mhash_get_hash_name() se používá ke zjištění názvu zadaného hashe.

mhash_get_hash_name() přijímá id hashe jako argument a vrací název tohoto hashe nebo `FALSE`, pokud tento hash neexistuje.

Příklad 1. Ukázka mhash_get_hash_name()

```
<?php
$hash = MHASH_MD5;

print mhash_get_hash_name ($hash);
?>
```

Výše uvedená ukázka vytiskne:

MD5

mhash_keygen_s2k (PHP 4 >= 4.0.4)

Vygenerovat klíč

string **mhash_keygen_s2k** (int hash, string password, string salt, int bytes) \linebreak

mhash_keygen_s2k() generuje klíč, který je *bytes* dlouhý, z předaného hesla. Toto je Salted S2K algoritmus specifikovaný v OpenPGP dokumentu (RFC 2440). Tento algoritmus použije k vytvoření klíče *hash* algoritmus. *salt* musí být pro každý generovaný klíč jiný a dostatečně náhodný, aby vytvořil různé klíče. Salt musí být při kontrole klíčů znám, tudíž je dobrý nápad ho připojit ke klíči. Salt má pevnou délku 8 bytů a pokud dodáte méně bytů, bude doplněn nulami. Pamatujte, že uživatelsky určená hesla nejsou vhodná k použití jako klíče, protože uživatelé obvykle volí klíče, které mohou napsat na klávesnici. Tato hesla využívají pouze 6 až 7 bytů na znak (nebo méně). Je velmi vhodné na uživateli určené klíče použít nějakou transformaci (jako je tato funkce).

LVII. Microsoft SQL Server functions

The MSSQL extension is available on Win32 systems only. You can use the Sybase extension to connect to MSSQL databases from other platforms.

These functions allow you to access MS SQL Server database. The extension requires the MS SQL Client Tools to be installed on the system where PHP is installed. The Client Tools can be installed from the MS SQL Server CD or by copying ntwdlib.dll from \winnt\system32 on the server to \winnt\system32 on the PHP box. Copying ntwdlib.dll will only provide access. Configuration of the client will require installation of all the tools.

The MSSQL extension is enabled by adding `extension=php_mssql.dll` to `php.ini`.

mssql_bind (PHP 4 >= 4.1.0)

Adds a parameter to a stored procedure or a remote stored procedure

`int mssql_bind (int stmt, string param_name, mixed var, int type [, int is_output [, int is_null [, int maxlen]])`
\\linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mssql_close (PHP 3, PHP 4 >= 4.0.0)

Close MS SQL Server connection

`int mssql_close ([int link_identifier])` \\linebreak

Returns: TRUE on success, FALSE on error.

mssql_close() closes the link to a MS SQL Server database that's associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed.

Note that this isn't usually necessary, as non-persistent open links are automatically closed at the end of the script's execution.

mssql_close() will not close persistent links generated by **mssql_pconnect()**.

See also: **mssql_connect()**, **mssql_pconnect()**.

mssql_connect (PHP 3, PHP 4 >= 4.0.0)

Open MS SQL server connection

`int mssql_connect ([string servername [, string username [, string password]])` \\linebreak

Returns: A positive MS SQL link identifier on success, or FALSE on error.

mssql_connect() establishes a connection to a MS SQL server. The servername argument has to be a valid servername that is defined in the 'interfaces' file.

In case a second call is made to **mssql_connect()** with the same arguments, no new link will be established, but instead, the link identifier of the already opened link will be returned.

The link to the server will be closed as soon as the execution of the script ends, unless it's closed earlier by explicitly calling **mssql_close()**.

See also **mssql_pconnect()**, **mssql_close()**.

mssql_data_seek (PHP 3, PHP 4 >= 4.0.0)

Move internal row pointer

```
int mssql_data_seek ( int result_identifier, int row_number) \linebreak
```

Returns: TRUE on success, FALSE on failure.

mssql_data_seek() moves the internal row pointer of the MS SQL result associated with the specified result identifier to point to the specified row number. The next call to **mssql_fetch_row()** would return that row.

See also: **mssql_data_seek()**.

mssql_execute (PHP 4 >= 4.1.0)

Executes a stored procedure on a MS-SQL server database

```
int mssql_execute ( int stmt) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mssql_fetch_array (PHP 3, PHP 4 >= 4.0.0)

Fetch row as array

```
int mssql_fetch_array ( int result) \linebreak
```

Returns: An array that corresponds to the fetched row, or FALSE if there are no more rows.

mssql_fetch_array() is an extended version of **mssql_fetch_row()**. In addition to storing the data in the numeric indices of the result array, it also stores the data in associative indices, using the field names as keys.

An important thing to note is that using **mssql_fetch_array()** is NOT significantly slower than using **mssql_fetch_row()**, while it provides a significant added value.

For further details, also see **mssql_fetch_row()**.

mssql_fetch_assoc (PHP 4 >= 4.2.0)

Returns an associative array of the current row in the result set specified by result_id

```
array mssql_fetch_assoc ( int result_id [, int result_type]) \linebreak
```


Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mssql_fetch_batch (PHP 4 >= 4.0.4)

Returns the next batch of records

int **mssql_fetch_batch** (string result_index) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mssql_fetch_field (PHP 3, PHP 4 >= 4.0.0)

Get field information

object **mssql_fetch_field** (int result [, int field_offset]) \linebreak

Returns an object containing field information.

mssql_fetch_field() can be used in order to obtain information about fields in a certain query result. If the field offset isn't specified, the next field that wasn't yet retrieved by **mssql_fetch_field()** is retrieved.

The properties of the object are:

- name - column name. if the column is a result of a function, this property is set to computed#N, where #N is a serial number.
- column_source - the table from which the column was taken
- max_length - maximum length of the column
- numeric - 1 if the column is numeric

See also **mssql_field_seek()**.

mssql_fetch_object (PHP 3, PHP 4 >= 4.0.0)

Fetch row as object

`int mssql_fetch_object (int result) \linebreak`

Returns: An object with properties that correspond to the fetched row, or `FALSE` if there are no more rows.

mssql_fetch_object() is similar to **mssql_fetch_array()**, with one difference - an object is returned, instead of an array. Indirectly, that means that you can only access the data by the field names, and not by their offsets (numbers are illegal property names).

Speed-wise, the function is identical to **mssql_fetch_array()**, and almost as quick as **mssql_fetch_row()** (the difference is insignificant).

See also: **mssql_fetch_array()** and **mssql_fetch_row()**.

mssql_fetch_row (PHP 3, PHP 4 >= 4.0.0)

Get row as enumerated array

`array mssql_fetch_row (int result) \linebreak`

Returns: An array that corresponds to the fetched row, or `FALSE` if there are no more rows.

mssql_fetch_row() fetches one row of data from the result associated with the specified result identifier. The row is returned as an array. Each result column is stored in an array offset, starting at offset 0.

Subsequent call to **mssql_fetch_rows()** would return the next row in the result set, or `FALSE` if there are no more rows.

See also: **mssql_fetch_array()**, **mssql_fetch_object()**, **mssql_data_seek()**, **mssql_fetch_lengths()**, and **mssql_result()**.

mssql_field_length (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Get the length of a field

`int mssql_field_length (int result [, int offset]) \linebreak`

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mssql_field_name (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Get the name of a field

`int mssql_field_name (int result [, int offset]) \linebreak`

mssql_field_seek (PHP 3, PHP 4 >= 4.0.0)

Set field offset

```
int mssql_field_seek ( int result, int field_offset) \linebreak
```

Seeks to the specified field offset. If the next call to `mssql_fetch_field()` won't include a field offset, this field would be returned.

See also: `mssql_fetch_field()`.

mssql_field_type (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Get the type of a field

```
string mssql_field_type ( int result [, int offset]) \linebreak
```

mssql_free_result (PHP 3, PHP 4 >= 4.0.0)

Free result memory

```
int mssql_free_result ( int result) \linebreak
```

mssql_free_result() only needs to be called if you are worried about using too much memory while your script is running. All result memory will automatically be freed when the script ends. You may call **mssql_free_result()** with the result identifier as an argument and the associated result memory will be freed.

mssql_get_last_message (PHP 3, PHP 4 >= 4.0.0)

Returns the last message from server (over min_message_severity?)

```
string mssql_get_last_message ( void) \linebreak
```

mssql_guid_string (PHP 4 >= 4.1.0)

Converts a 16 byte binary GUID to a string

```
string mssql_guid_string ( string binary [, int short_format]) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mssql_init (PHP 4 >= 4.1.0)

Initializes a stored procedure or a remote stored procedure

```
int mssql_init ( string sp_name [, int conn_id]) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mssql_min_error_severity (PHP 3, PHP 4 >= 4.0.0)

Sets the lower error severity

```
void mssql_min_error_severity ( int severity) \linebreak
```

mssql_min_message_severity (PHP 3, PHP 4 >= 4.0.0)

Sets the lower message severity

```
void mssql_min_message_severity ( int severity) \linebreak
```

mssql_next_result (PHP 4 >= 4.0.5)

Move the internal result pointer to the next result

```
bool mssql_next_result ( int result_id) \linebreak
```

When sending more than one SQL statement to the server or executing a stored procedure with multiple results, it will cause the server to return multiple result sets. This function will test for additional results available from the server. If an additional result set exists it will free the existing result set and prepare to fetch the rows from the new result set. The function will return TRUE if an additional result set was available or FALSE otherwise.

Příklad 1. mssql_next_result() example

```
<?php
$link = mssql_connect ("localhost", "userid", "secret");
mssql_select_db("MyDB", $link);
```

```

$SQL = "Select * from table1 select * from table2";
$rs = mssql_query($SQL, $link);
do {
    while ($row = mssql_fetch_row($rs)) {
    }
} while (mssql_next_result($rs));
mssql_free_result($rs);
mssql_close ($link);
?>

```

mssql_num_fields (PHP 3, PHP 4 >= 4.0.0)

Get number of fields in result

```
int mssql_num_fields ( int result) \linebreak
```

mssql_num_fields() returns the number of fields in a result set.

See also: **mssql_db_query()**, **mssql_query()**, **mssql_fetch_field()**, and **mssql_num_rows()**.

mssql_num_rows (PHP 3, PHP 4 >= 4.0.0)

Get number of rows in result

```
int mssql_num_rows ( string result) \linebreak
```

mssql_num_rows() returns the number of rows in a result set.

See also: **mssql_db_query()**, **mssql_query()**, and **mssql_fetch_row()**.

mssql_pconnect (PHP 3, PHP 4 >= 4.0.0)

Open persistent MS SQL connection

```
int mssql_pconnect ( [string servername [, string username [, string password]]]) \linebreak
```

Returns: A positive MS SQL persistent link identifier on success, or **FALSE** on error.

mssql_pconnect() acts very much like **mssql_connect()** with two major differences.

First, when connecting, the function would first try to find a (persistent) link that's already open with the same host, username and password. If one is found, an identifier for it will be returned instead of opening a new connection.

Second, the connection to the SQL server will not be closed when the execution of the script ends. Instead, the link will remain open for future use (**mssql_close()** will not close links established by **mssql_pconnect()**).

This type of links is therefore called 'persistent'.

mssql_query (PHP 3, PHP 4 >= 4.0.0)

Send MS SQL query

```
int mssql_query ( string query [, int link_identifier]) \linebreak
```

Returns: A positive MS SQL result identifier on success, or `FALSE` on error.

mssql_query() sends a query to the currently active database on the server that's associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed. If no link is open, the function tries to establish a link as if **mssql_connect()** was called, and use it.

See also: **mssql_db_query()**, **mssql_select_db()**, and **mssql_connect()**.

mssql_result (PHP 3, PHP 4 >= 4.0.0)

Get result data

```
int mssql_result ( int result, int i, mixed field) \linebreak
```

mssql_result() returns the contents of one cell from a MS SQL result set. The field argument can be the field's offset, the field's name or the field's table dot field's name (tablename.fieldname). If the column name has been aliased ('select foo as bar from...'), it uses the alias instead of the column name.

When working on large result sets, you should consider using one of the functions that fetch an entire row (specified below). As these functions return the contents of multiple cells in one function call, they're MUCH quicker than **mssql_result()**. Also, note that specifying a numeric offset for the field argument is much quicker than specifying a fieldname or tablename.fieldname argument.

Recommended high-performance alternatives: **mssql_fetch_row()**, **mssql_fetch_array()**, and **mssql_fetch_object()**.

mssql_rows_affected (PHP 4 >= 4.0.4)

Returns the number of records affected by the query

```
int mssql_rows_affected ( int conn_id) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

mssql_select_db (PHP 3, PHP 4 >= 4.0.0)

Select MS SQL database

```
int mssql_select_db ( string database_name [, int link_identifier]) \linebreak
```

Returns: TRUE on success, FALSE on error

mssql_select_db() sets the current active database on the server that's associated with the specified link identifier. If no link identifier is specified, the last opened link is assumed. If no link is open, the function will try to establish a link as if **mssql_connect()** was called, and use it.

Every subsequent call to **mssql_query()** will be made on the active database.

See also: **mssql_connect()**, **mssql_pconnect()**, and **mssql_query()**

LVIII. Ming functions for Flash

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

Introduction

Ming is an open-source (LGPL) library which allows you to create SWF ("Flash") format movies. Ming supports almost all of Flash 4's features, including: shapes, gradients, bitmaps (pngs and jpegs), morphs ("shape tweens"), text, buttons, actions, sprites ("movie clips"), streaming mp3, and color transforms--the only thing that's missing is sound events.

Ming is not an acronym.

Note that all values specifying length, distance, size, etc. are in "twips", twenty units per pixel. That's pretty much arbitrary, though, since the player scales the movie to whatever pixel size is specified in the embed/object tag, or the entire frame if not embedded.

Ming offers a number of advantages over the existing PHP/libswf module. You can use Ming anywhere you can compile the code, whereas libswf is closed-source and only available for a few platforms, Windows not one of them. Ming provides some insulation from the mundane details of the SWF file format, wrapping the movie elements in PHP objects. Also, Ming is still being maintained; if there's a feature that you want to see, just let us know ming@opaque.net (mailto:ming@opaque.net).

Ming was added in PHP 4.0.5.

Installation

To use Ming with PHP, you first need to build and install the Ming library. Source code and installation instructions are available at the Ming home page : <http://www.opaque.net/ming/> along with examples, a small tutorial, and the latest news.

Download the ming archive. Unpack the archive. Go in the Ming directory. make. make install.

This will build `libming.so` and install it into `/usr/lib/`, and copy `ming.h` into `/usr/include/`. Edit the `PREFIX=` line in the `Makefile` to change the installation directory.

built into php (unix)

```
mkdir <phpdir>/ext/ming
cp php_ext/* <phpdir>/ext/ming
cd <phpdir>
./buildconf
./configure --with-ming <other config options>
```


Build and install php as usual, Restart web server if necessary

built into php (unix)

download `php_ming.so.gz`, uncompress it and copy it to your php modules directory. (you can find your php module directory by running **`php-config --extension-dir`**). Now either just add `extension=php_ming.so` to your `php.ini` file, or put `dl('php_ming.so');` at the head of all of your Ming scripts.

How to use Ming

Ming introduces 13 new objects in PHP, all with matching methods and attributes. To use them, you need to know about objects.

- `swfmovie()`.
- `swfshape()`.
- `swfdisplayitem()`.
- `swfgradient()`.
- `swfbitmap()`.
- `swffill()`.
- `swfmorph()`.
- `swftext()`.
- `swffont()`.
- `swftextfield()`.
- `swfsprite()`.
- `swfbutton()`.
- `swfaction()`.

ming_setcubicthreshold (PHP 4 >= 4.0.5)

Set cubic threshold (?)

void **ming_setcubicthreshold** (int threshold) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ming_setscale (PHP 4 >= 4.0.5)

Set scale (?)

void **ming_setscale** (int scale) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

ming_useswfversion (PHP 4 >= 4.2.0)

Use SWF version (?)

void **ming_useswfversion** (int version) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

SWFAction (PHP 4 >= 4.0.5)

Creates a new Action.

new **swfaction** (string script) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfaction() creates a new Action, and compiles the given script into an SWFAction object.

The script syntax is based on the C language, but with a lot taken out- the SWF bytecode machine is just too simpleminded to do a lot of things we might like. For instance, we can't implement function calls without a tremendous amount of hackery because the jump bytecode has a hardcoded offset value. No pushing your calling address to the stack and returning- every function would have to know exactly where to return to.

So what's left? The compiler recognises the following tokens:

- break
- for
- continue
- if
- else
- do
- while

There is no typed data; all values in the SWF action machine are stored as strings. The following functions can be used in expressions:

time()

Returns the number of milliseconds (?) elapsed since the movie started.

random(seed)

Returns a pseudo-random number in the range 0-seed.

length(expr)

Returns the length of the given expression.

int(number)

Returns the given number rounded down to the nearest integer.

concat(expr, expr)

Returns the concatenation of the given expressions.

ord(expr)

Returns the ASCII code for the given character

chr(num)

Returns the character for the given ASCII code

`substr(string, location, length)`

Returns the substring of length `length` at location `location` of the given string `string`.

Additionally, the following commands may be used:

`duplicateClip(clip, name, depth)`

Duplicate the named movie clip (aka sprite). The new movie clip has name `name` and is at depth `depth`.

`removeClip(expr)`

Removes the named movie clip.

`trace(expr)`

Write the given expression to the trace log. Doubtful that the browser plugin does anything with this.

`startDrag(target, lock, [left, top, right, bottom])`

Start dragging the movie clip `target`. The `lock` argument indicates whether to lock the mouse (?)- use 0 (`FALSE`) or 1 (`TRUE`). Optional parameters define a bounding area for the dragging.

`stopDrag()`

Stop dragging my heart around. And this movie clip, too.

`callFrame(expr)`

Call the named frame as a function.

`getURL(url, target, [method])`

Load the given URL into the named `target`. The `target` argument corresponds to HTML document targets (such as `"_top"` or `"_blank"`). The optional `method` argument can be `POST` or `GET` if you want to submit variables back to the server.

`loadMovie(url, target)`

Load the given URL into the named `target`. The `target` argument can be a frame name (I think), or one of the magical values `"_level0"` (replaces current movie) or `"_level1"` (loads new movie on top of current movie).

`nextFrame()`

Go to the next frame.

`prevFrame()`

Go to the last (or, rather, previous) frame.

`play()`

Start playing the movie.

`stop()`

Stop playing the movie.

`toggleQuality()`

Toggle between high and low quality.

`stopSounds()`

Stop playing all sounds.

`gotoFrame(num)`

Go to frame number num. Frame numbers start at 0.

`gotoFrame(name)`

Go to the frame named name. Which does a lot of good, since I haven't added frame labels yet.

`setTarget(expr)`

Sets the context for action. Or so they say- I really have no idea what this does.

And there's one weird extra thing. The expression `frameLoaded(num)` can be used in if statements and while loops to check if the given frame number has been loaded yet. Well, it's supposed to, anyway, but I've never tested it and I seriously doubt it actually works. You can just use `/:framesLoaded` instead.

Movie clips (all together now- aka sprites) have properties. You can read all of them (or can you?), you can set some of them, and here they are:

- `x`
- `y`
- `xScale`
- `yScale`
- `currentFrame` - (read-only)
- `totalFrames` - (read-only)
- `alpha` - transparency level
- `visible` - 1=on, 0=off (?)
- `width` - (read-only)
- `height` - (read-only)
- `rotation`
- `target` - (read-only) (???)
- `framesLoaded` - (read-only)
- `name`
- `dropTarget` - (read-only) (???)
- `url` - (read-only) (???)
- `highQuality` - 1=high, 0=low (?)
- `focusRect` - (???)
- `soundBufTime` - (???)

So, setting a sprite's x position is as simple as `/box.x = 100;`. Why the slash in front of the box, though? That's how flash keeps track of the sprites in the movie, just like a unix filesystem- here it

shows that box is at the top level. If the sprite named box had another sprite named biff inside of it, you'd set its x position with `/box/biff.x = 100;`. At least, I think so; correct me if I'm wrong here.

This simple example will move the red square across the window.

Příklad 1. swfaction() example

```
<?php
$s = new SWFShape();
$f = $s->addFill(0xff, 0, 0);
$s->setRightFill($f);

$s->movePenTo(-500,-500);
$s->drawLineTo(500,-500);
$s->drawLineTo(500,500);
$s->drawLineTo(-500,500);
$s->drawLineTo(-500,-500);

$p = new SWFSprite();
$i = $p->add($s);
$i->setDepth(1);
$p->nextFrame();

for($n=0; $n<5; ++$n)
{
    $i->rotate(-15);
    $p->nextFrame();
}

$m = new SWFMovie();
$m->setBackground(0xff, 0xff, 0xff);
$m->setDimension(6000,4000);

$i = $m->add($p);
$i->setDepth(1);
$i->moveTo(-500,2000);
$i->setName("box");

$m->add(new SWFAction("/box.x += 3;"));
$m->nextFrame();
$m->add(new SWFAction("gotoFrame(0); play();"));
$m->nextFrame();

header('Content-type: application/x-shockwave-flash');
$m->output();
?>
```

This simple example tracks down your mouse on the screen.

Příklad 2. swfaction() example

```

<?php

$m = new SWFMovie();
$m->setRate(36.0);
$m->setDimension(1200, 800);
$m->setBackground(0, 0, 0);

/* mouse tracking sprite - empty, but follows mouse so we can
   get its x and y coordinates */

$i = $m->add(new SWFSprite());
$i->setName('mouse');

$m->add(new SWFAction("
    startDrag('/mouse', 1); /* '1' means lock sprite to the mouse */
"));

/* might as well turn off antialiasing, since these are just squares. */

$m->add(new SWFAction("
    this.quality = 0;
"));

/* morphing box */
$r = new SWFMorph();
$s = $r->getShape1();

/* Note this is backwards from normal shapes. No idea why. */
$s->setLeftFill($s->addFill(0xff, 0xff, 0xff));
$s->movePenTo(-40, -40);
$s->drawLine(80, 0);
$s->drawLine(0, 80);
$s->drawLine(-80, 0);
$s->drawLine(0, -80);

$s = $r->getShape2();

$s->setLeftFill($s->addFill(0x00, 0x00, 0x00));
$s->movePenTo(-1, -1);
$s->drawLine(2, 0);
$s->drawLine(0, 2);
$s->drawLine(-2, 0);
$s->drawLine(0, -2);

/* sprite container for morphing box -
   this is just a timeline w/ the box morphing */

$box = new SWFSprite();
$box->add(new SWFAction("
    stop();
"));
$i = $box->add($r);

for($n=0; $n<=20; ++$n)

```

```

{
    $i->setRatio($n/20);
    $box->nextFrame();
}

/* this container sprite allows us to use the same action code many times */

$cell = new SWFSprite();
$i = $cell->add($box);
$i->setName('box');

$cell->add(new SWFAction("

    setTarget('box');

    /* ...x means the x coordinate of the parent, i.e. (...).x */
    dx = (/mouse.x + random(6)-3 - ...x)/5;
    dy = (/mouse.y + random(6)-3 - ...y)/5;
    gotoFrame(int(dx*dx + dy*dy));

"));

$cell->nextFrame();
$cell->add(new SWFAction("

    gotoFrame(0);
    play();

"));

$cell->nextFrame();

/* finally, add a bunch of the cells to the movie */

for($x=0; $x<12; ++$x)
{
    for($y=0; $y<8; ++$y)
    {
        $i = $m->add($cell);
        $i->moveTo(100*$x+50, 100*$y+50);
    }
}

$m->nextFrame();

$m->add(new SWFAction("

    gotoFrame(1);
    play();

"));

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```


Same as above, but with nice colored balls...

Příklad 3. swfaction() example

```
<?php

$m = new SWFMovie();
$m->setDimension(11000, 8000);
$m->setBackground(0x00, 0x00, 0x00);

$m->add(new SWFAction("

this.quality = 0;
/frames.visible = 0;
startDrag('/mouse', 1);

"));

// mouse tracking sprite
$t = new SWFSprite();
$i = $m->add($t);
$i->setName('mouse');

$g = new SWFGradient();
$g->addEntry(0, 0xff, 0xff, 0xff, 0xff);
$g->addEntry(0.1, 0xff, 0xff, 0xff, 0xff);
$g->addEntry(0.5, 0xff, 0xff, 0xff, 0x5f);
$g->addEntry(1.0, 0xff, 0xff, 0xff, 0);

// gradient shape thing
$s = new SWFShape();
$f = $s->addFill($g, SWFFILL_RADIAL_GRADIENT);
$f->scaleTo(0.03);
$s->setRightFill($f);
$s->movePenTo(-600, -600);
$s->drawLine(1200, 0);
$s->drawLine(0, 1200);
$s->drawLine(-1200, 0);
$s->drawLine(0, -1200);

// need to make this a sprite so we can multColor it
$p = new SWFSprite();
$p->add($s);
$p->nextFrame();

// put the shape in here, each frame a different color
$q = new SWFSprite();
$q->add(new SWFAction("gotoFrame(random(7)+1); stop();"));
$i = $q->add($p);

$i->multColor(1.0, 1.0, 1.0);
$q->nextFrame();
$i->multColor(1.0, 0.5, 0.5);
$q->nextFrame();
```

```

$i->multColor(1.0, 0.75, 0.5);
$q->nextFrame();
$i->multColor(1.0, 1.0, 0.5);
$q->nextFrame();
$i->multColor(0.5, 1.0, 0.5);
$q->nextFrame();
$i->multColor(0.5, 0.5, 1.0);
$q->nextFrame();
$i->multColor(1.0, 0.5, 1.0);
$q->nextFrame();

// finally, this one contains the action code
$p = new SWFSprite();
$i = $p->add($q);
$i->setName('frames');
$p->add(new SWFAction("

dx = (:mousex-/:lastx)/3 + random(10)-5;
dy = (:mousey-/:lasty)/3;
x = /:mousex;
y = /:mousey;
alpha = 100;

"));
$p->nextFrame();

$p->add(new SWFAction("

this.x = x;
this.y = y;
this.alpha = alpha;
x += dx;
y += dy;
dy += 3;
alpha -= 8;

"));
$p->nextFrame();

$p->add(new SWFAction("prevFrame(); play();"));
$p->nextFrame();

$i = $m->add($p);
$i->setName('frames');
$m->nextFrame();

$m->add(new SWFAction("

lastx = mousex;
lasty = mousey;
mousex = /mouse.x;
mousey = /mouse.y;

++num;

if(num == 11)
    num = 1;

```

```

removeClip('char' & num);
duplicateClip(/frames, 'char' & num, num);

    ));

$m->nextFrame();
$m->add(new SWFAction("prevFrame(); play();"));

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

This simple example will handles keyboard actions. (You'll probably have to click in the window to give it focus. And you'll probably have to leave your mouse in the frame, too. If you know how to give buttons focus programatically, feel free to share, won't you?)

Příklad 4. swfaction() example

```

<?php

/* sprite has one letter per frame */

$p = new SWFSprite();
$p->add(new SWFAction("stop();"));

$chars = "abcdefghijklmnopqrstuvwxyz".
         "ABCDEFGHIJKLMNOPQRSTUVWXYZ".
         "1234567890!@#$$%^&/*()_+~=/[]{}|;:,.<>`~";

$f = new SWFFont("_sans");

for($n=0; $nremove($i);
    $t = new SWFTextField();
    $t->setFont($f);
    $t->setHeight(240);
    $t->setBounds(600,240);
    $t->align(SWFTEXTFIELD_ALIGN_CENTER);
    $t->addString($c);
    $i = $p->add($t);
    $p->labelFrame($c);
    $p->nextFrame();
}

/* hit region for button - the entire frame */

$s = new SWFShape();
$s->setFillStyle0($s->addSolidFill(0, 0, 0, 0));
$s->drawLine(600, 0);
$s->drawLine(0, 400);
$s->drawLine(-600, 0);
$s->drawLine(0, -400);

```

```

/* button checks for pressed key, sends sprite to the right frame */

$b = new SWFButton();
$b->addShape($s, SWFBUTTON_HIT);

for($n=0; $naddAction(new SWFAction("

setTarget('/char');
gotoFrame('$c');

    "), SWFBUTTON_KEYPRESS($c));
}

$m = new SWFMovie();
$m->setDimension(600,400);
$i = $m->add($p);
$i->setName('char');
$i->moveTo(0,80);

$m->add($b);

header('Content-type: application/x-shockwave-flash');
$m->output();

?>

```

SWFBitmap (PHP 4 >= 4.0.5)

Loads Bitmap object

```
new swfbitmap ( string filename [, int alphafilename]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbitmap() creates a new SWFBitmap object from the Jpeg or DBL file named *filename*. *alphafilename* indicates a MSK file to be used as an alpha mask for a Jpeg image.

Poznámka: We can only deal with baseline (frame 0) jpegs, no baseline optimized or progressive scan jpegs!

SWFBitmap has the following methods : **swfbitmap->getwidth()** and **swfbitmap->getheight()**.

You can't import png images directly, though- have to use the png2dbl utility to make a dbl ("define bits lossless") file from the png. The reason for this is that I don't want a dependency on the png library in ming- autoconf should solve this, but that's not set up yet.

Příklad 1. Import PNG files

```
<?php
    $s = new SWFShape();
    $f = $s->addFill(new SWFBitmap("png.dbl"));
    $s->setRightFill($f);

    $s->drawLine(32, 0);
    $s->drawLine(0, 32);
    $s->drawLine(-32, 0);
    $s->drawLine(0, -32);

    $m = new SWFMovie();
    $m->setDimension(32, 32);
    $m->add($s);

    header('Content-type: application/x-shockwave-flash');
    $m->output();
?>
```

And you can put an alpha mask on a jpeg fill.

Příklad 2. swfbitmap() example

```
<?php

    $s = new SWFShape();

    // .msk file generated with "gif2mask" utility
    $f = $s->addFill(new SWFBitmap("alphafill.jpg", "alphafill.msk"));
    $s->setRightFill($f);

    $s->drawLine(640, 0);
    $s->drawLine(0, 480);
    $s->drawLine(-640, 0);
    $s->drawLine(0, -480);

    $c = new SWFShape();
    $c->setRightFill($c->addFill(0x99, 0x99, 0x99));
    $c->drawLine(40, 0);
    $c->drawLine(0, 40);
    $c->drawLine(-40, 0);
    $c->drawLine(0, -40);

    $m = new SWFMovie();
    $m->setDimension(640, 480);
    $m->setBackground(0xcc, 0xcc, 0xcc);
```

```
// draw checkerboard background
for($y=0; $y<480; $y+=40)
{
    for($x=0; $x<640; $x+=80)
    {
        $i = $m->add($c);
        $i->moveTo($x, $y);
    }

    $y+=40;

    for($x=40; $x<640; $x+=80)
    {
        $i = $m->add($c);
        $i->moveTo($x, $y);
    }
}

$m->add($s);

header('Content-type: application/x-shockwave-flash');
$m->output();
?>
```

SWFBitmap->getHeight (unknown)

Returns the bitmap's height.

```
int swfbitmap->getHeight ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbitmap->getHeight() returns the bitmap's height in pixels.

See also **swfbitmap->getWidth()**.

SWFBitmap->getWidth (unknown)

Returns the bitmap's width.

```
int swfbitmap->getWidth ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbitmap->getwidth() returns the bitmap's width in pixels.

See also **swfbitmap->getheight()**.

SWFbutton (PHP 4 >= 4.0.5)

Creates a new Button.

new **swfbutton** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbutton() creates a new Button. Roll over it, click it, see it call action code. Swank.

SWFButton has the following methods : **swfbutton->addshape()**, **swfbutton->setup()**, **swfbutton->setover()** **swfbutton->setdown()**, **swfbutton->sethit()** **swfbutton->setaction()** and **swfbutton->addaction()**.

This simple example will show your usual interactions with buttons : rollover, rollon, mouseup, mousedown, noaction.

Příklad 1. swfbutton() example

```
<?php

$f = new SWFFont("_serif");

$p = new SWFSprite();

function label($string)
{
    global $f;

    $t = new SWFTextField();
    $t->setFont($f);
    $t->addString($string);
    $t->setHeight(200);
    $t->setBounds(3200,200);
    return $t;
}

function addLabel($string)
```

```

{
    global $p;

    $i = $p->add(label($string));
    $p->nextFrame();
    $p->remove($i);
}

$p->add(new SWFAction("stop();"));
addLabel("NO ACTION");
addLabel("SWFBUTTON_MOUSEUP");
addLabel("SWFBUTTON_MOUSEDOWN");
addLabel("SWFBUTTON_MOUSEOVER");
addLabel("SWFBUTTON_MOUSEOUT");
addLabel("SWFBUTTON_MOUSEUPOUTSIDE");
addLabel("SWFBUTTON_DRAGOVER");
addLabel("SWFBUTTON_DRAGOUT");

function rect($r, $g, $b)
{
    $s = new SWFShape();
    $s->setRightFill($s->addFill($r, $g, $b));
    $s->drawLine(600,0);
    $s->drawLine(0,600);
    $s->drawLine(-600,0);
    $s->drawLine(0,-600);

    return $s;
}

$b = new SWFButton();
$b->addShape(rect(0xff, 0, 0), SWFBUTTON_UP | SWFBUTTON_HIT);
$b->addShape(rect(0, 0xff, 0), SWFBUTTON_OVER);
$b->addShape(rect(0, 0, 0xff), SWFBUTTON_DOWN);

$b->addAction(new SWFAction("setTarget('/label'); gotoFrame(1);"),
    SWFBUTTON_MOUSEUP);

$b->addAction(new SWFAction("setTarget('/label'); gotoFrame(2);"),
    SWFBUTTON_MOUSEDOWN);

$b->addAction(new SWFAction("setTarget('/label'); gotoFrame(3);"),
    SWFBUTTON_MOUSEOVER);

$b->addAction(new SWFAction("setTarget('/label'); gotoFrame(4);"),
    SWFBUTTON_MOUSEOUT);

$b->addAction(new SWFAction("setTarget('/label'); gotoFrame(5);"),
    SWFBUTTON_MOUSEUPOUTSIDE);

$b->addAction(new SWFAction("setTarget('/label'); gotoFrame(6);"),
    SWFBUTTON_DRAGOVER);

$b->addAction(new SWFAction("setTarget('/label'); gotoFrame(7);"),
    SWFBUTTON_DRAGOUT);

$m = new SWFMovie();

```



```

$m->setDimension(4000,3000);

$i = $m->add($p);
$i->setName("label");
$i->moveTo(400,1900);

$i = $m->add($b);
$i->moveTo(400,900);

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

This simple example will enables you to drag draw a big red button on the windows. No drag-and-drop, just moving around.

Příklad 2. swfbutton->addaction() example

```

<?php

$s = new SWFShape();
$s->setRightFill($s->addFill(0xff, 0, 0));
$s->drawLine(1000,0);
$s->drawLine(0,1000);
$s->drawLine(-1000,0);
$s->drawLine(0,-1000);

$b = new SWFButton();
$b->addShape($s, SWFBUTTON_HIT | SWFBUTTON_UP | SWFBUTTON_DOWN | SWFBUTTON_OVER);

$b->addAction(new SWFAction("startDrag('/test', 0);"), // '0' means don't lock to mouse
    SWFBUTTON_MOUSEDOWN);

$b->addAction(new SWFAction("stopDrag();"),
    SWFBUTTON_MOUSEUP | SWFBUTTON_MOUSEUPOUTSIDE);

$p = new SWFSprite();
$p->add($b);
$p->nextFrame();

$m = new SWFMovie();
$i = $m->add($p);
$i->setName('test');
$i->moveTo(1000,1000);

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

swfbutton_keypress (PHP 4 >= 4.0.5)

Returns the action flag for keyPress(char)

```
int swfbutton_keypress ( string str) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

SWFbutton->addAction (unknown)

Adds an action

```
void swfbutton->addaction ( ressource action, int flags) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbutton->addaction() adds the action *action* to this button for the given conditions. The following *flags* are valid: SWFBUTTON_MOUSEOVER, SWFBUTTON_MOUSEOUT, SWFBUTTON_MOUSEUP, SWFBUTTON_MOUSEUPOUTSIDE, SWFBUTTON_MOUSEDOWN, SWFBUTTON_DRAGOUT and SWFBUTTON_DRAGOVER.

See also **swfbutton->addshape()** and **SWFAction()**.

SWFbutton->addShape (unknown)

Adds a shape to a button

```
void swfbutton->addshape ( ressource shape, int flags) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbutton->addshape() adds the shape *shape* to this button. The following *flags*' values are valid: SWFBUTTON_UP, SWFBUTTON_OVER, SWFBUTTON_DOWN or SWFBUTTON_HIT.

SWFBUTTON_HIT isn't ever displayed, it defines the hit region for the button. That is, everywhere the hit shape would be drawn is considered a "touchable" part of the button.

SWFbutton->setAction (unknown)

Sets the action

void **swfbutton->setaction** (resource action) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbutton->setaction() sets the action to be performed when the button is clicked. Alias for `addAction(shape, SWFBUTTON_MOUSEUP)`. *action* is a `swfaction()`.

See also **swfbutton->addshape()** and **SWFAction()**.

SWFbutton->setdown (unknown)

Alias for `addShape(shape, SWFBUTTON_DOWN)`

void **swfbutton->setdown** (resource shape) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbutton->setdown() alias for `addShape(shape, SWFBUTTON_DOWN)`.

See also **swfbutton->addshape()** and **SWFAction()**.

SWFbutton->setHit (unknown)

Alias for `addShape(shape, SWFBUTTON_HIT)`

void **swfbutton->sethit** (resource shape) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbutton->sethit() alias for addShape(shape, SWFBUTTON_HIT).

See also **swfbutton->addshape()** and **SWFAction()**.

SWFbutton->setOver (unknown)

Alias for addShape(shape, SWFBUTTON_OVER)

void **swfbutton->setover** (resource shape) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbutton->setover() alias for addShape(shape, SWFBUTTON_OVER).

See also **swfbutton->addshape()** and **SWFAction()**.

SWFbutton->setUp (unknown)

Alias for addShape(shape, SWFBUTTON_UP)

void **swfbutton->setup** (resource shape) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfbutton->setup() alias for addShape(shape, SWFBUTTON_UP).

See also **swfbutton->addshape()** and **SWFAction()**.

SWFDisplayItem (unknown)

Creates a new displayitem object.

new **swfdisplayitem** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem() creates a new swfdisplayitem object.

Here's where all the animation takes place. After you define a shape, a text object, a sprite, or a button, you add it to the movie, then use the returned handle to move, rotate, scale, or skew the thing.

SWFDisplayItem has the following methods : **swfdisplayitem->move()**, **swfdisplayitem->moveto()**, **swfdisplayitem->scaleteto()**, **swfdisplayitem->scale()**, **swfdisplayitem->rotate()**, **swfdisplayitem->rotateto()**, **swfdisplayitem->skewxto()**, **swfdisplayitem->skewx()**, **swfdisplayitem->skewyto()** **swfdisplayitem->skewyto()**, **swfdisplayitem->setdepth()** **swfdisplayitem->remove()**, **swfdisplayitem->setname()** **swfdisplayitem->setratio()**, **swfdisplayitem->addcolor()** and **swfdisplayitem->multicolor()**.

SWFDisplayItem->addColor (unknown)

Adds the given color to this item's color transform.

void **swfdisplayitem->addcolor** ([int red [, int green [, int blue [, int a]]]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->addcolor() adds the color to this item's color transform. The color is given in its RGB form.

The object may be a swfshape(), a swfbutton(), a swftext() or a swfsprite() object. It must have been added using the **swfmovie->add()**.

SWFDisplayItem->move (unknown)

Moves object in relative coordinates.

void **swfdisplayitem->move** (int dx, int dy) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->move() moves the current object by (dx,dy) from its current position.

The object may be a `swfshape()`, a `swfbutton()`, a `swftext()` or a `swfsprite()` object. It must have been added using the **swfmovie->add()**.

See also **swfdisplayitem->moveto()**.

SWFDisplayItem->moveTo (unknown)

Moves object in global coordinates.

`void swfdisplayitem->moveto (int x, int y) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->moveto() moves the current object to (x,y) in global coordinates.

The object may be a `swfshape()`, a `swfbutton()`, a `swftext()` or a `swfsprite()` object. It must have been added using the **swfmovie->add()**.

See also **swfdisplayitem->move()**.

SWFDisplayItem->multColor (unknown)

Multiplies the item's color transform.

`void swfdisplayitem->multicolor ([int red [, int green [, int blue [, int a]]]]) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->multicolor() multiplies the item's color transform by the given values.

The object may be a `swfshape()`, a `swfbutton()`, a `swftext()` or a `swfsprite()` object. It must have been added using the **swfmovie->add()**.

This simple example will modify your picture's atmosphere to Halloween (use a landscape or bright picture).

Příklad 1. `swfdisplayitem->multicolor()` example

```
<?php

$b = new SWFBitmap("backyard.jpg");
// note use your own picture :-
$s = new SWFShape();
$s->setRightFill($s->addFill($b));
$s->drawLine($b->getWidth(), 0);
$s->drawLine(0, $b->getHeight());
$s->drawLine(-$b->getWidth(), 0);
$s->drawLine(0, -$b->getHeight());

$m = new SWFMovie();
$m->setDimension($b->getWidth(), $b->getHeight());

$i = $m->add($s);

for($n=0; $n<=20; ++$n)
{
    $i->multColor(1.0-$n/10, 1.0, 1.0);
    $i->addColor(0xff*$n/20, 0, 0);
    $m->nextFrame();
}

header('Content-type: application/x-shockwave-flash');
$m->output();
?>
```

SWFDisplayItem->remove (unknown)

Removes the object from the movie

void **swfdisplayitem->remove** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->remove() removes this object from the movie's display list.

The object may be a `swfshape()`, a `swfbutton()`, a `swftext()` or a `swfsprite()` object. It must have been added using the **swfmovie->add()**.

See also **swfmovie->add()**.

SWFDisplayItem->Rotate (unknown)

Rotates in relative coordinates.

void **swfdisplayitem->rotate** (float *ddegrees*) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->rotate() rotates the current object by *ddegrees* degrees from its current rotation.

The object may be a **swfshape()**, a **swfbutton()**, a **swftext()** or a **swfsprite()** object. It must have been added using the **swfmovie->add()**.

See also **swfdisplayitem->rotateto()**.

SWFDisplayItem->rotateTo (unknown)

Rotates the object in global coordinates.

void **swfdisplayitem->rotateto** (float *degrees*) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->rotateto() set the current object rotation to *degrees* degrees in global coordinates.

The object may be a **swfshape()**, a **swfbutton()**, a **swftext()** or a **swfsprite()** object. It must have been added using the **swfmovie->add()**.

This example bring three rotating string from the background to the foreground. Pretty nice.

Příklad 1. swfdisplayitem->rotateto() example

```
<?php
    $thetext = "ming!";

    $f = new SWFFont("Bauhaus 93.fdb");
```



```

$m = new SWFMovie();
$m->setRate(24.0);
$m->setDimension(2400, 1600);
$m->setBackground(0xff, 0xff, 0xff);

// functions with huge numbers of arbitrary
// arguments are always a good idea! Really!

function text($r, $g, $b, $a, $rot, $x, $y, $scale, $string)
{
    global $f, $m;

    $t = new SWFText();
    $t->setFont($f);
    $t->setColor($r, $g, $b, $a);
    $t->setHeight(960);
    $t->moveTo(-($f->getWidth($string))/2, $f->getAscent()/2);
    $t->addString($string);

    // we can add properties just like a normal php var,
    // as long as the names aren't already used.
    // e.g., we can't set $i->scale, because that's a function

    $i = $m->add($t);
    $i->x = $x;
    $i->y = $y;
    $i->rot = $rot;
    $i->s = $scale;
    $i->rotateTo($rot);
    $i->scale($scale, $scale);

    // but the changes are local to the function, so we have to
    // return the changed object. kinda weird..

    return $i;
}

function step($i)
{
    $oldrot = $i->rot;
    $i->rot = 19*$i->rot/20;
    $i->x = (19*$i->x + 1200)/20;
    $i->y = (19*$i->y + 800)/20;
    $i->s = (19*$i->s + 1.0)/20;

    $i->rotateTo($i->rot);
    $i->scaleTo($i->s, $i->s);
    $i->moveTo($i->x, $i->y);

    return $i;
}

// see? it sure paid off in legibility:

$i1 = text(0xff, 0x33, 0x33, 0xff, 900, 1200, 800, 0.03, $thetext);
$i2 = text(0x00, 0x33, 0xff, 0x7f, -560, 1200, 800, 0.04, $thetext);
$i3 = text(0xff, 0xff, 0xff, 0x9f, 180, 1200, 800, 0.001, $thetext);

```

```

for($i=1; $i<=100; ++$i)
{
    $i1 = step($i1);
    $i2 = step($i2);
    $i3 = step($i3);

    $m->nextFrame();
}

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

See also `swfdisplayitem->rotate()`.

SWFDisplayItem->scale (unknown)

Scales the object in relative coordinates.

`void swfdisplayitem->scale (int dx, int dy) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`swfdisplayitem->scale()` scales the current object by (dx, dy) from its current size.

The object may be a `swfshape()`, a `swfbutton()`, a `swftext()` or a `swfsprite()` object. It must have been added using the `swfmovie->add()`.

See also `swfdisplayitem->scaletto()`.

SWFDisplayItem->scaletTo (unknown)

Scales the object in global coordinates.

`void swfdisplayitem->scaletto (int x, int y) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->scalet() scales the current object to (x,y) in global coordinates.

The object may be a swfshape(), a swfbutton(), a swftext() or a swfsprite() object. It must have been added using the **swfmovie->add()**.

See also **swfdisplayitem->scale()**.

SWFDisplayItem->setDepth (unknown)

Sets z-order

void **swfdisplayitem->setdepth** (float depth) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->rotate() sets the object's z-order to *depth*. Depth defaults to the order in which instances are created (by add'ing a shape/text to a movie)- newer ones are on top of older ones. If two objects are given the same depth, only the later-defined one can be moved.

The object may be a swfshape(), a swfbutton(), a swftext() or a swfsprite() object. It must have been added using the **swfmovie->add()**.

SWFDisplayItem->setName (unknown)

Sets the object's name

void **swfdisplayitem->setname** (string name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->setname() sets the object's name to *name*, for targeting with action script. Only useful on sprites.

The object may be a swfshape(), a swfbutton(), a swftext() or a swfsprite() object. It must have been added using the **swfmovie->add()**.

SWFDisplayItem->setRatio (unknown)

Sets the object's ratio.

```
void swfdisplayitem->setratio ( float ratio) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->setratio() sets the object's ratio to *ratio*. Obviously only useful for morphs.

The object may be a swfshape(), a swfbutton(), a swftext() or a swfsprite() object. It must have been added using the **swfmovie->add()**.

This simple example will morph nicely three concentric circles.

Příklad 1. swfdisplayitem->setname() example

```
<?php
```

```
$p = new SWFMorph();

$g = new SWFGradient();
$g->addEntry(0.0, 0, 0, 0);
$g->addEntry(0.16, 0xff, 0xff, 0xff);
$g->addEntry(0.32, 0, 0, 0);
$g->addEntry(0.48, 0xff, 0xff, 0xff);
$g->addEntry(0.64, 0, 0, 0);
$g->addEntry(0.80, 0xff, 0xff, 0xff);
$g->addEntry(1.00, 0, 0, 0);

$s = $p->getShape1();
$f = $s->addFill($g, SWFFILL_RADIAL_GRADIENT);
$f->scaleTo(0.05);
$s->setLeftFill($f);
$s->movePenTo(-160, -120);
$s->drawLine(320, 0);
$s->drawLine(0, 240);
$s->drawLine(-320, 0);
$s->drawLine(0, -240);

$g = new SWFGradient();
$g->addEntry(0.0, 0, 0, 0);
$g->addEntry(0.16, 0xff, 0, 0);
$g->addEntry(0.32, 0, 0, 0);
$g->addEntry(0.48, 0, 0xff, 0);
$g->addEntry(0.64, 0, 0, 0);
$g->addEntry(0.80, 0, 0, 0xff);
$g->addEntry(1.00, 0, 0, 0);

$s = $p->getShape2();
```

```

$f = $s->addFill($g, SWFFILL_RADIAL_GRADIENT);
$f->scaleTo(0.05);
$f->skewXTo(1.0);
$s->setLeftFill($f);
$s->movePenTo(-160, -120);
$s->drawLine(320, 0);
$s->drawLine(0, 240);
$s->drawLine(-320, 0);
$s->drawLine(0, -240);

$m = new SWFMovie();
$m->setDimension(320, 240);
$i = $m->add($p);
$i->moveTo(160, 120);

for($n=0; $n<=1.001; $n+=0.01)
{
    $i->setRatio($n);
    $m->nextFrame();
}

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

SWFDisplayItem->skewX (unknown)

Sets the X-skew.

void **swfdisplayitem->skewx** (float *ddegrees*) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->skewx() adds *ddegrees* to current x-skew.

The object may be a **swfshape()**, a **swfbutton()**, a **swftext()** or a **swfsprite()** object. It must have been added using the **swfmovie->add()**.

See also **swfdisplayitem->skewx()**, **swfdisplayitem->skewy()** and **swfdisplayitem->skewyto()**.

SWFDisplayItem->skewXTo (unknown)

Sets the X-skew.

void **swfdisplayitem->skewxto** (float degrees) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->skewxto() sets the x-skew to *degrees*. For *degrees* is 1.0, it means a 45-degree forward slant. More is more forward, less is more backward.

The object may be a **swfshape()**, a **swfbutton()**, a **swftext()** or a **swfsprite()** object. It must have been added using the **swfmovie->add()**.

See also **swfdisplayitem->skewx()**, **swfdisplayitem->skewy()** and **swfdisplayitem->skewyto()**.

SWFDisplayItem->skewY (unknown)

Sets the Y-skew.

void **swfdisplayitem->skewy** (float ddegrees) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->skewy() adds *ddegrees* to current y-skew.

The object may be a **swfshape()**, a **swfbutton()**, a **swftext()** or a **swfsprite()** object. It must have been added using the **swfmovie->add()**.

See also **swfdisplayitem->skewyto()**, **swfdisplayitem->skewx()** and **swfdisplayitem->skewxto()**.

SWFDisplayItem->skewYTo (unknown)

Sets the Y-skew.

void **swfdisplayitem->skewyto** (float degrees) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfdisplayitem->skewyto() sets the y-skew to *degrees*. For *degrees* is 1.0, it means a 45-degree forward slant. More is more upward, less is more downward.

The object may be a **swfshape()**, a **swfbutton()**, a **swftext()** or a **swfsprite()** object. It must have been added using the **swfmovie->add()**.

See also **swfdisplayitem->skewy()**, **swfdisplayitem->skewx()** and **swfdisplayitem->skewxto()**.

SWFFill (PHP 4 >= 4.0.5)

Loads SWFFill object

The **swffill()** object allows you to transform (scale, skew, rotate) bitmap and gradient fills. **swffill()** objects are created by the **swfshape->addfill()** methods.

SWFFill has the following methods : **swffill->moveto()** and **swffill->scaleteto()**, **swffill->rotateto()**, **swffill->skewxto()** and **swffill->skewyto()**.

SWFFill->moveTo (unknown)

Moves fill origin

void **swffill->moveto** (int x, int y) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swffill->moveto() moves fill's origin to (x,y) in global coordinates.

SWFFill->rotateTo (unknown)

Sets fill's rotation

void **swffill->rotateto** (float degrees) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swffill->rotateto() sets fill's rotation to *degrees* degrees.

SWFFill->scaleTo (unknown)

Sets fill's scale

void **swffill->scaletto** (int x, int y) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swffill->scaletto() sets fill's scale to *x* in the x-direction, *y* in the y-direction.

SWFFill->skewXTo (unknown)

Sets fill x-skew

void **swffill->skewxto** (float x) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swffill->skewxto() sets fill x-skew to *x*. For *x* is 1.0, it is a 45-degree forward slant. More is more forward, less is more backward.

SWFFill->skewYTo (unknown)

Sets fill y-skew

void **swffill->skewyto** (float y) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swffill->skewyto() sets fill y-skew to y . For y is 1.0, it is a 45-degree upward slant. More is more upward, less is more downward.

SWFFont (PHP 4 >= 4.0.5)

Loads a font definition

new **swffont** (string filename) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

If *filename* is the name of an FDB file (i.e., it ends in ".fdb"), load the font definition found in said file. Otherwise, create a browser-defined font reference.

FDB ("font definition block") is a very simple wrapper for the SWF DefineFont2 block which contains a full description of a font. One may create FDB files from SWT Generator template files with the included makefdb utility- look in the util directory off the main ming distribution directory.

Browser-defined fonts don't contain any information about the font other than its name. It is assumed that the font definition will be provided by the movie player. The fonts `_serif`, `_sans`, and `_typewriter` should always be available. For example:

```
<?php
$f = newSWFFont ( "_sans" );
?>
```

will give you the standard sans-serif font, probably the same as what you'd get with `` in HTML.

swffont() returns a reference to the font definition, for use in the **SWFText->setFont()** and the **SWFTextField->setFont()** methods.

SWFFont has the following methods : **swffont->getwidth()**.

swffont->getwidth (unknown)

Returns the string's width

```
int swffont->getwidth ( string string) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swffont->getwidth() returns the string *string*'s width, using font's default scaling. You'll probably want to use the **SWFText()** version of this method which uses the text object's scale.

SWFGradient (PHP 4 >= 4.0.5)

Creates a gradient object

```
new swfgradient ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfgradient() creates a new SWFGradient object.

After you've added the entries to your gradient, you can use the gradient in a shape fill with the **swfshape->addfill()** method.

SWFGradient has the following methods : **swfgradient->addentry()**.

This simple example will draw a big black-to-white gradient as background, and a redish disc in its center.

Příklad 1. swfgradient() example

```
<?php
```

```
$m = new SWFMovie();
$m->setDimension(320, 240);

$s = new SWFShape();

// first gradient- black to white
$g = new SWFGradient();
$g->addEntry(0.0, 0, 0, 0);
$g->addEntry(1.0, 0xff, 0xff, 0xff);
```

```

$f = $s->addFill($g, SWFFILL_LINEAR_GRADIENT);
$f->scaleTo(0.01);
$f->moveTo(160, 120);
$s->setRightFill($f);
$s->drawLine(320, 0);
$s->drawLine(0, 240);
$s->drawLine(-320, 0);
$s->drawLine(0, -240);

$m->add($s);

$s = new SWFShape();

// second gradient- radial gradient from red to transparent
$g = new SWFGradient();
$g->addEntry(0.0, 0xff, 0, 0, 0xff);
$g->addEntry(1.0, 0xff, 0, 0, 0);

$f = $s->addFill($g, SWFFILL_RADIAL_GRADIENT);
$f->scaleTo(0.005);
$f->moveTo(160, 120);
$s->setRightFill($f);
$s->drawLine(320, 0);
$s->drawLine(0, 240);
$s->drawLine(-320, 0);
$s->drawLine(0, -240);

$m->add($s);

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

SWFGradient->addEntry (unknown)

Adds an entry to the gradient list.

void **swfgradient->addentry** (float ratio, int red, int green, int blue [, int a]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfgradient->addentry() adds an entry to the gradient list. *ratio* is a number between 0 and 1 indicating where in the gradient this color appears. Thou shalt add entries in order of increasing ratio.

red, green, blue is a color (RGB mode). Last parameter *a* is optional.

SWFMorph (PHP 4 >= 4.0.5)

Creates a new SWFMorph object.

new **swfmorph** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmorph() creates a new SWFMorph object.

Also called a "shape tween". This thing lets you make those tacky twisting things that make your computer choke. Oh, joy!

The methods here are sort of weird. It would make more sense to just have newSWFMorph(shape1, shape2);, but as things are now, shape2 needs to know that it's the second part of a morph. (This, because it starts writing its output as soon as it gets drawing commands- if it kept its own description of its shapes and wrote on completion this and some other things would be much easier.)

SWFMorph has the following methods : **swfmorph->getshape1()** and **swfmorph->getshape1()**.

This simple example will morph a big red square into a smaller blue black-bordered square.

Příklad 1. swfmorph() example

```
<?php
    $p = new SWFMorph();

    $s = $p->getShape1();
    $s->setLine(0,0,0,0);

    /* Note that this is backwards from normal shapes (left instead of right).
       I have no idea why, but this seems to work.. */

    $s->setLeftFill($s->addFill(0xff, 0, 0));
    $s->movePenTo(-1000,-1000);
    $s->drawLine(2000,0);
    $s->drawLine(0,2000);
    $s->drawLine(-2000,0);
    $s->drawLine(0,-2000);

    $s = $p->getShape2();
    $s->setLine(60,0,0,0);
    $s->setLeftFill($s->addFill(0, 0, 0xff));
    $s->movePenTo(0,-1000);
    $s->drawLine(1000,1000);
    $s->drawLine(-1000,1000);
    $s->drawLine(-1000,-1000);
```

```

$s->drawLine(1000,-1000);

$m = new SWFMovie();
$m->setDimension(3000,2000);
$m->setBackground(0xff, 0xff, 0xff);

$i = $m->add($p);
$i->moveTo(1500,1000);

for($r=0.0; $r<=1.0; $r+=0.1)
{
    $i->setRatio($r);
    $m->nextFrame();
}

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

SWFMorph->getshape1 (unknown)

Gets a handle to the starting shape

mixed **swfmorph->getshape1** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmorph->getshape1() gets a handle to the morph's starting shape. **swfmorph->getshape1()** returns an swfshape() object.

SWFMorph->getshape2 (unknown)

Gets a handle to the ending shape

mixed **swfmorph->getshape2** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmorph->getshape2() gets a handle to the morph's ending shape. **swfmorph->getshape2()** returns an swfshape() object.

SWFMovie (PHP 4 >= 4.0.5)

Creates a new movie object, representing an SWF version 4 movie.

new **swfmovie** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie() creates a new movie object, representing an SWF version 4 movie.

SWFMovie has the following methods : **swfmovie->output()**, **swfmovie->save()**, **swfmovie->add()**, **swfmovie->remove()**, **swfmovie->nextframe()**, **swfmovie->setbackground()**, **swfmovie->setrate()**, **swfmovie->setdimension()**, **swfmovie->setframes()** and **swfmovie->streammp3()**.

See examples in : **swfdisplayitem->rotateto()**, **swfshape->setline()**, **swfshape->addfill()**... Any example will use this object.

SWFMovie->add (unknown)

Adds any type of data to a movie.

void **swfmovie->add** (ressource instance) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->add() adds *instance* to the current movie. *instance* is any type of data : Shapes, text, fonts, etc. must all be add'ed to the movie to make this work.

For displayable types (shape, text, button, sprite), this returns an **SWFDisplayItem()**, a handle to the object in a display list. Thus, you can add the same shape to a movie multiple times and get separate handles back for each separate instance.

See also all other objects (adding this later), and **swfmovie->remove()**

See examples in : **swfdisplayitem->rotateto()** and **swfshape->addfill()**.

SWFMovie->nextframe (unknown)

Moves to the next frame of the animation.

void **swfmovie->nextframe** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->setframes() moves to the next frame of the animation.

SWFMovie->output (unknown)

Dumps your lovingly prepared movie out.

void **swfmovie->output** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->output() dumps your lovingly prepared movie out. In PHP, preceding this with the command

```
<?php
header('Content-type: application/x-shockwave-flash');
?>
```

convinces the browser to display this as a flash movie.

See also **swfmovie->save()**.

See examples in : **swfmovie->streammp3()**, **swfdisplayitem->rotateto()**, **swfaction()**... Any example will use this method.

SWFMovie->remove (unknown)

Removes the object instance from the display list.

```
void swfmovie->remove ( resource instance) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->remove() removes the object instance *instance* from the display list.

See also **swfmovie->add()**.

SWFMovie->save (unknown)

Saves your movie in a file.

```
void swfmovie->save ( string filename) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->save() saves your movie to the file named *filename*.

See also **output()**.

SWFMovie->setbackground (unknown)

Sets the background color.

```
void swfmovie->setbackground ( int red, int green, int blue) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->setbackground() sets the background color. Why is there no rgba version? Think about it. (Actually, that's not such a dumb question after all- you might want to let the html background

show through. There's a way to do that, but it only works on IE4. Search the <http://www.macromedia.com/> site for details.)

SWFMovie->setdimension (unknown)

Sets the movie's width and height.

```
void swfmovie->setdimension ( int width, int height) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->setdimension() sets the movie's width to *width* and height to *height*.

SWFMovie->setframes (unknown)

Sets the total number of frames in the animation.

```
void swfmovie->setframes ( string numberofframes) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->setframes() sets the total number of frames in the animation to *numberofframes*.

SWFMovie->setrate (unknown)

Sets the animation's frame rate.

```
void swfmovie->setrate ( int rate) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->setrate() sets the frame rate to *rate*, in frame per seconds. Animation will slow down if the player can't render frames fast enough- unless there's a streaming sound, in which case display frames are sacrificed to keep sound from skipping.

SWFMovie->streammp3 (unknown)

Streams a MP3 file.

```
void swfmovie->streammp3 ( string mp3FileName) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfmovie->streammp3() streams the mp3 file *mp3FileName*. Not very robust in dealing with oddities (can skip over an initial ID3 tag, but that's about it). Like **SWFShape->addJpegFill()**, this isn't a stable function- we'll probably need to make a separate SWFSound object to contain sound types.

Note that the movie isn't smart enough to put enough frames in to contain the entire mp3 stream- you'll have to add (length of song * frames per second) frames to get the entire stream in.

Yes, now you can use ming to put that rock and roll devil worship music into your SWF files. Just don't tell the RIAA.

Příklad 1. swfmovie->streammp3() example

```
<?php
$m = new SWFMovie();
$m->setRate(12.0);
$m->streamMp3("distortobass.mp3");
// use your own MP3

// 11.85 seconds at 12.0 fps = 142 frames
$m->setFrames(142);

header('Content-type: application/x-shockwave-flash');
$m->output();
?>
```

SWFShape (PHP 4 >= 4.0.5)

Creates a new shape object.

new **swfshape** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape() creates a new shape object.

SWFShape has the following methods : **swfshape->setline()**, **swfshape->addfill()**, **swfshape->setleftfill()**, **swfshape->setrightfill()**, **swfshape->moverpentto()**, **swfshape->moverpen()**, **swfshape->drawlineto()**, **swfshape->drawline()**, **swfshape->drawcurveto()** and **swfshape->drawcurve()**.

This simple example will draw a big red elliptic quadrant.

Příklad 1. swfshape() example

```
<?php
    $s = new SWFShape();
    $s->setLine(40, 0x7f, 0, 0);
    $s->setRightFill($s->addFill(0xff, 0, 0));
    $s->movePenTo(200, 200);
    $s->drawLineTo(6200, 200);
    $s->drawLineTo(6200, 4600);
    $s->drawCurveTo(200, 4600, 200, 200);

    $m = new SWFMovie();
    $m->setDimension(6400, 4800);
    $m->setRate(12.0);
    $m->add($s);
    $m->nextFrame();

    header('Content-type: application/x-shockwave-flash');
    $m->output();
?>
```

SWFShape->addFill (unknown)

Adds a solid fill to the shape.

void **swfshape->addfill** (int red, int green, int blue [, int a]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

void **swfshape->addfill** (SWFBitmap bitmap [, int flags]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

void **swfshape->addfill** (SWFGradient gradient [, int flags]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape->addfill() adds a solid fill to the shape's list of fill styles. **swfshape->addfill()** accepts three different types of arguments.

red, *green*, *blue* is a color (RGB mode). Last parameter *a* is optional.

The *bitmap* argument is an `swfbitmap()` object. The *flags* argument can be one of the following values : `SWFFILL_CLIPPED_BITMAP` or `SWFFILL_TILED_BITMAP`. Default is `SWFFILL_TILED_BITMAP`. I think.

The *gradient* argument is an `swfgradient()` object. The *flags* argument can be one of the following values : `SWFFILL_RADIAL_GRADIENT` or `SWFFILL_LINEAR_GRADIENT`. Default is `SWFFILL_LINEAR_GRADIENT`. I'm sure about this one. Really.

swfshape->addfill() returns an `swffill()` object for use with the **swfshape->setleftfill()** and **swfshape->setrightfill()** functions described below.

See also **swfshape->setleftfill()** and **swfshape->setrightfill()**.

This simple example will draw a frame on a bitmap. Ah, here's another buglet in the flash player- it doesn't seem to care about the second shape's bitmap's transformation in a morph. According to spec, the bitmap should stretch along with the shape in this example..

Příklad 1. swfshape->addfill() example

```
<?php
```

```
$p = new SWFMorph();

$b = new SWFBitmap("alphafill1.jpg");
// use your own bitmap
```

```

$width = $b->getWidth();
$height = $b->getHeight();

$s = $p->getShape1();
$f = $s->addFill($b, SWFFILL_TILED_BITMAP);
$f->moveTo(-$width/2, -$height/4);
$f->scaleTo(1.0, 0.5);
$s->setLeftFill($f);
$s->movePenTo(-$width/2, -$height/4);
$s->drawLine($width, 0);
$s->drawLine(0, $height/2);
$s->drawLine(-$width, 0);
$s->drawLine(0, -$height/2);

$s = $p->getShape2();
$f = $s->addFill($b, SWFFILL_TILED_BITMAP);

// these two have no effect!
$f->moveTo(-$width/4, -$height/2);
$f->scaleTo(0.5, 1.0);

$s->setLeftFill($f);
$s->movePenTo(-$width/4, -$height/2);
$s->drawLine($width/2, 0);
$s->drawLine(0, $height);
$s->drawLine(-$width/2, 0);
$s->drawLine(0, -$height);

$m = new SWFMovie();
$m->setDimension($width, $height);
$i = $m->add($p);
$i->moveTo($width/2, $height/2);

for($n=0; $n<1.001; $n+=0.03)
{
    $i->setRatio($n);
    $m->nextFrame();
}

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

SWFShape->drawCurve (unknown)

Draws a curve (relative).

void swfshape->drawcurve (int controldx, int controldy, int anchordx, int anchordy) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape->drawcurve() draws a quadratic curve (using the current line style, set by **swfshape->setline()**) from the current pen position to the relative position (*anchorx, anchory*) using relative control point (*controlx, controly*). That is, head towards the control point, then smoothly turn to the anchor point.

See also **swfshape->drawlineto()**, **swfshape->drawline()**, **swfshape->movepento()** and **swfshape->movepen()**.

SWFShape->drawCurveTo (unknown)

Draws a curve.

```
void swfshape->drawcurveto ( int controlx, int controly, int anchorx, int anchory) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape->drawcurveto() draws a quadratic curve (using the current line style, set by **swfshape->setline()**) from the current pen position to (*anchorx, anchory*) using (*controlx, controly*) as a control point. That is, head towards the control point, then smoothly turn to the anchor point.

See also **swfshape->drawlineto()**, **swfshape->drawline()**, **swfshape->movepento()** and **swfshape->movepen()**.

SWFShape->drawLine (unknown)

Draws a line (relative).

```
void swfshape->drawline ( int dx, int dy) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape->drawline() draws a line (using the current line style set by **swfshape->setline()**) from the current pen position to displacement (dx, dy).

See also **swfshape->movepento()**, **swfshape->drawcurveto()**, **swfshape->movepen()** and **swfshape->drawlineto()**.

SWFShape->drawLineTo (unknown)

Draws a line.

```
void swfshape->drawlineto ( int x, int y) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape->setrightfill() draws a line (using the current line style, set by **swfshape->setline()**) from the current pen position to point (x, y) in the shape's coordinate space.

See also **swfshape->movepento()**, **swfshape->drawcurveto()**, **swfshape->movepen()** and **swfshape->drawline()**.

SWFShape->movePen (unknown)

Moves the shape's pen (relative).

```
void swfshape->movepen ( int dx, int dy) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape->setrightfill() move the shape's pen from coordinates (current x,current y) to (current x + dx , current y + dy) in the shape's coordinate space.

See also **swfshape->movepento()**, **swfshape->drawcurveto()**, **swfshape->drawlineto()** and **swfshape->drawline()**.

SWFShape->movePenTo (unknown)

Moves the shape's pen.

```
void swfshape->movepento ( int x, int y) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape->setrightfill() move the shape's pen to (x,y) in the shape's coordinate space.

See also **swfshape->movepen()**, **swfshape->drawcurveto()**, **swfshape->drawlineto()** and **swfshape->drawline()**.

SWFShape->setLeftFill (unknown)

Sets left rasterizing color.

```
void swfshape->setleftfill ( swfgradient fill) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

```
void swfshape->setleftfill ( int red, int green, int blue [, int a]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

What this nonsense is about is, every edge segment borders at most two fills. When rasterizing the object, it's pretty handy to know what those fills are ahead of time, so the swf format requires these to be specified.

swfshape->setleftfill() sets the fill on the left side of the edge- that is, on the interior if you're defining the outline of the shape in a counter-clockwise fashion. The fill object is an SWFFill object returned from one of the addFill functions above.

This seems to be reversed when you're defining a shape in a morph, though. If your browser crashes, just try setting the fill on the other side.

Shortcut for **swfshape->setleftfill(\$s->addfill(\$r, \$g, \$b [, \$a]))**;

See also **swfshape->setrightfill()**.

SWFShape->setLine (unknown)

Sets the shape's line style.

```
void swfshape->setline ( int width [, int red [, int green [, int blue [, int a]]]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfshape->setline() sets the shape's line style. *width* is the line's width. If *width* is 0, the line's style is removed (then, all other arguments are ignored). If *width* > 0, then line's color is set to *red*, *green*, *blue*. Last parameter *a* is optional.

swfshape->setline() accepts 1, 4 or 5 arguments (not 3 or 2).

You must declare all line styles before you use them (see example).

This simple example will draw a big "!#%*@", in funny colors and gracious style.

Příklad 1. swfshape->setline() example

```
<?php
    $s = new SWFShape();
    $f1 = $s->addFill(0xff, 0, 0);
    $f2 = $s->addFill(0xff, 0x7f, 0);
    $f3 = $s->addFill(0xff, 0xff, 0);
    $f4 = $s->addFill(0, 0xff, 0);
    $f5 = $s->addFill(0, 0, 0xff);

    // bug: have to declare all line styles before you use them
    $s->setLine(40, 0x7f, 0, 0);
    $s->setLine(40, 0x7f, 0x3f, 0);
    $s->setLine(40, 0x7f, 0x7f, 0);
    $s->setLine(40, 0, 0x7f, 0);
    $s->setLine(40, 0, 0, 0x7f);

    $f = new SWFFont('Techno.fdb');

    $s->setRightFill($f1);
    $s->setLine(40, 0x7f, 0, 0);
    $s->drawGlyph($f, '!');
    $s->movePen($f->getWidth('!'), 0);

    $s->setRightFill($f2);
    $s->setLine(40, 0x7f, 0x3f, 0);
    $s->drawGlyph($f, '#');
    $s->movePen($f->getWidth('#'), 0);

    $s->setRightFill($f3);
    $s->setLine(40, 0x7f, 0x7f, 0);
    $s->drawGlyph($f, '%');
    $s->movePen($f->getWidth('%'), 0);
```

```

$s->setRightFill($f4);
$s->setLine(40, 0, 0x7f, 0);
$s->drawGlyph($f, '*');
$s->movePen($f->getWidth('*'), 0);

$s->setRightFill($f5);
$s->setLine(40, 0, 0, 0x7f);
$s->drawGlyph($f, '@');

$m = new SWFMovie();
$m->setDimension(3000,2000);
$m->setRate(12.0);
$i = $m->add($s);
$i->moveTo(1500-$f->getWidth("!%*@")/2, 1000+$f->getAscent()/2);

header('Content-type: application/x-shockwave-flash');
$m->output();
?>

```

SWFShape->setRightFill (unknown)

Sets right rasterizing color.

void **swfshape->setrightfill** (swfgradient fill) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

void **swfshape->setrightfill** (int red, int green, int blue [, int a]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

See also **swfshape->setleftfill**().

Shortcut for **swfshape->setrightfill**(\$s->addfill(\$r, \$g, \$b [, \$a]));.

SWFSprite (PHP 4 >= 4.0.5)

Creates a movie clip (a sprite)

new **swfsprite** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfsprite() are also known as a "movie clip", this allows one to create objects which are animated in their own timelines. Hence, the sprite has most of the same methods as the movie.

swfsprite() has the following methods : **swfsprite->add()**, **swfsprite->remove()**, **swfsprite->nextframe()** and **swfsprite->setframes()**.

This simple example will spin gracefully a big red square.

Příklad 1. swfsprite() example

```
<?php
    $s = new SWFShape();
    $s->setRightFill($s->addFill(0xff, 0, 0));
    $s->movePenTo(-500,-500);
    $s->drawLineTo(500,-500);
    $s->drawLineTo(500,500);
    $s->drawLineTo(-500,500);
    $s->drawLineTo(-500,-500);

    $p = new SWFSprite();
    $i = $p->add($s);
    $p->nextFrame();
    $i->rotate(15);
    $p->nextFrame();
    $i->rotate(15);
    $p->nextFrame();
    $i->rotate(15);
    $p->nextFrame();
    $i->rotate(15);
    $p->nextFrame();
    $i->rotate(15);
    $p->nextFrame();

    $m = new SWFMovie();
    $i = $m->add($p);
    $i->moveTo(1500,1000);
    $i->setName("blah");

    $m->setBackground(0xff, 0xff, 0xff);
    $m->setDimension(3000,2000);

    header('Content-type: application/x-shockwave-flash');
```

```
$m->output();
?>
```

SWFSprite->add (unknown)

Adds an object to a sprite

```
void swfsprite->add ( resource object) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfsprite->add() adds a swfshape(), a swfbutton(), a swftext(), a swfaction() or a swfsprite() object.

For displayable types (swfshape(), swfbutton(), swftext(), swfaction() or swfsprite()), this returns a handle to the object in a display list.

SWFSprite->nextframe (unknown)

Moves to the next frame of the animation.

```
void swfsprite->nextframe ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfsprite->setframes() moves to the next frame of the animation.

SWFSprite->remove (unknown)

Removes an object to a sprite

```
void swfsprite->remove ( ressource object) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfsprite->remove() remove a swfshape(), a swfbutton(), a swftext(), a swfaction() or a swfsprite() object from the sprite.

SWFSprite->setframes (unknown)

Sets the total number of frames in the animation.

void **swfsprite->setframes** (int numberofframes) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swfsprite->setframes() sets the total number of frames in the animation to *numberofframes*.

SWFText (PHP 4 >= 4.0.5)

Creates a new SWFText object.

new **swftext** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftext() creates a new SWFText object, fresh for manipulating.

SWFText has the following methods : **swftext->setfont()**, **swftext->setheight()**, **swftext->setspacing()**, **swftext->setcolor()**, **swftext->moveto()**, **swftext->addstring()** and **swftext->getwidth()**.

This simple example will draw a big yellow "PHP generates Flash with Ming" text, on white background.

Příklad 1. swftext() example

```

<?php
    $f = new SWFFont("Techno.fdb");
    $t = new SWFText();
    $t->setFont($f);
    $t->moveTo(200, 2400);
    $t->setColor(0xff, 0xff, 0);
    $t->setHeight(1200);
    $t->addString("PHP generates Flash with Ming!!");

    $m = new SWFMovie();
    $m->setDimension(5400, 3600);

    $m->add($t);

    header('Content-type: application/x-shockwave-flash');
    $m->output();
?>

```

SWFText->addString (unknown)

Draws a string

void **swftext->addstring** (string string) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftext->addstring() draws the string *string* at the current pen (cursor) location. Pen is at the baseline of the text; i.e., ascending text is in the -y direction.

SWFText->getWidth (unknown)

Computes string's width

void **swftext->addstring** (string string) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftext->addstring() returns the rendered width of the *string* string at the text object's current font, scale, and spacing settings.

SWFText->moveTo (unknown)

Moves the pen

void **swftext->moveto** (int x, int y) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftext->moveto() moves the pen (or cursor, if that makes more sense) to (*x,y*) in text object's coordinate space. If either is zero, though, value in that dimension stays the same. Annoying, should be fixed.

SWFText->setColor (unknown)

Sets the current font color

void **swftext->setcolor** (int red, int green, int blue [, int a]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftext->setspacing() changes the current text color. Default is black. I think. Color is represented using the RGB system.

SWFText->setFont (unknown)

Sets the current font

```
void swftext->setfont ( string font) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftext->setfont() sets the current font to *font*.

SWFText->setHeight (unknown)

Sets the current font height

```
void swftext->setheight ( int height) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftext->setheight() sets the current font height to *height*. Default is 240.

SWFText->setSpacing (unknown)

Sets the current font spacing

```
void swftext->setspacing ( float spacing) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftext->setspacing() sets the current font spacing to *spacing*. Default is 1.0. 0 is all of the letters written at the same point. This doesn't really work that well because it inflates the advance across the letter, doesn't add the same amount of spacing between the letters. I should try and explain that better, proly. Or just fix the damn thing to do constant spacing. This was really just a way to figure out how letter advances work, anyway.. So yah.

SWFTextField (PHP 4 >= 4.0.5)

Creates a text field object

```
new swftextfield ( [int flags]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftextfield() creates a new text field object. Text Fields are less flexible than swftext() objects- they can't be rotated, scaled non-proportionally, or skewed, but they can be used as form entries, and they can use browser-defined fonts.

The optional flags change the text field's behavior. It has the following possible values :

- SWFTEXTFIELD_NOEDIT indicates that the field shouldn't be user-editable
- SWFTEXTFIELD_PASSWORD obscures the data entry
- SWFTEXTFIELD_DRAWBOX draws the outline of the textfield
- SWFTEXTFIELD_MULTILINE allows multiple lines
- SWFTEXTFIELD_WORDWRAP allows text to wrap
- SWFTEXTFIELD_NOSELECT makes the field non-selectable

Flags are combined with the bitwise OR operation. For example,

```
<?php
$t = newSWFTextField(SWFTEXTFIELD_PASSWORD | SWFTEXTFIELD_NOEDIT);
?>
```

creates a totally useless non-editable password field.

SWFTextField has the following methods : **swftextfield->setfont()**, **swftextfield->setbounds()**, **swftextfield->align()**, **swftextfield->setheight()**, **swftextfield->setleftmargin()**, **swftextfield->setrightmargin()**, **swftextfield->setmargins()**, **swftextfield->setindentation()**, **swftextfield->setlinespacing()**, **swftextfield->setcolor()**, **swftextfield->setname()** and **swftextfield->addstring()**.

SWFTextField->addstring (unknown)

Concatenates the given string to the text field

```
void swftextfield->addstring ( string string) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`swftextfield->setname()` concatenates the string *string* to the text field.

SWFTextField->align (unknown)

Sets the text field alignment

`void swftextfield->align (int alignment) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`swftextfield->align()` sets the text field alignment to *alignment*. Valid values for *alignment* are : SWFTEXTFIELD_ALIGN_LEFT, SWFTEXTFIELD_ALIGN_RIGHT, SWFTEXTFIELD_ALIGN_CENTER and SWFTEXTFIELD_ALIGN_JUSTIFY.

SWFTextField->setbounds (unknown)

Sets the text field width and height

`void swftextfield->setbounds (int width, int height) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`swftextfield->setbounds()` sets the text field width to *width* and height to *height*. If you don't set the bounds yourself, Ming makes a poor guess at what the bounds are.

SWFTextField->setcolor (unknown)

Sets the color of the text field.

```
void swftextfield->setcolor ( int red, int green, int blue [, int a]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftextfield->setcolor() sets the color of the text field. Default is fully opaque black. Color is represented using RGB system.

SWFTextField->setFont (unknown)

Sets the text field font

```
void swftextfield->setfont ( string font) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftextfield->setfont() sets the text field font to the [browser-defined?] *font* font.

SWFTextField->setHeight (unknown)

Sets the font height of this text field font.

```
void swftextfield->setheight ( int height) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftextfield->setheight() sets the font height of this text field font to the given height *height*. Default is 240.

SWFTextField->setindentation (unknown)

Sets the indentation of the first line.

```
void swftextfield->setindentation ( int width) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`swftextfield->setindentation()` sets the indentation of the first line in the text field, to *width*.

SWFTextField->setLeftMargin (unknown)

Sets the left margin width of the text field.

```
void swftextfield->setleftmargin ( int width) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`swftextfield->setleftmargin()` sets the left margin width of the text field to *width*. Default is 0.

SWFTextField->setLineSpacing (unknown)

Sets the line spacing of the text field.

```
void swftextfield->setlinespacing ( int height) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`swftextfield->setlinespacing()` sets the line spacing of the text field to the height of *height*. Default is 40.

SWFTextField->setMargins (unknown)

Sets the margins width of the text field.

```
void swftextfield->setmargins ( int left, int right) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftextfield->setmargins() set both margins at once, for the man on the go.

SWFTextField->setname (unknown)

Sets the variable name

```
void swftextfield->setname ( string name) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftextfield->setname() sets the variable name of this text field to *name*, for form posting and action scripting purposes.

SWFTextField->setrightMargin (unknown)

Sets the right margin width of the text field.

```
void swftextfield->setrightmargin ( int width) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

swftextfield->setrightmargin() sets the right margin width of the text field to *width*. Default is 0.

LIX. Smíšené funkce

Tyto funkce byly umístěny zde, protože nespádají do žádné jiné kategorie.

connection_aborted (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Vrací TRUE, pokud se klient odpojil

int connection_aborted (void) \linebreak

Vrátí TRUE, pokud se klient odpojil. Úplné vysvětlení viz popis v Obsluha spojení v kapitole Vlastnosti.

connection_status (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Vrací bitové pole stavu spojení

int connection_status (void) \linebreak

Vrací bitové pole stavu spojení. Úplné vysvětlení viz popis v Obsluha spojení v kapitole Vlastnosti.

connection_timeout (PHP 3 >= 3.0.7, 4.0.0 - 4.0.4 only)

Return TRUE if script timed out

int connection_timeout (void) \linebreak

Returns TRUE if script timed out. Úplné vysvětlení viz popis v Obsluha spojení v kapitole Vlastnosti.

define (PHP 3, PHP 4 >= 4.0.0)

Definuje pojmenovanou konstantu.

int define (string name, mixed value [, int case_insensitive]) \linebreak

Definuje pojmenovanou konstantu, která je podobná proměnné s výjimkou toho, že:

- Konstanty nemají znak dolaru ('\$') před jménem;
- Konstanty jsou dostupné odkudkoliv bez ohledu na pravidla rozsahu platnosti proměnných;
- Konstanty se nedají předefinovat a rušit; a
- Konstanty se mohou nabývat pouze skalárních hodnot.

Název konstanty je dán argumentem *name*; hodnota je dána argumentem *value*.

Dále je dostupný volitelný třetí argument *case_insensitive*. Pokud má hodnotu 1, konstanta bude definována case-insensitive. Výchozí chování je case-sensitive; tj. CONSTANT and Constant reprezentují různé hodnoty.

Příklad 1. Definování konstant

```
<?php
define ("CONSTANT", "Hello world.");
echo CONSTANT; // výstup je "Hello world."
?>
```

define() vrací TRUE při úspěchu a FALSE pokud dojde k chybě.

Viz také defined() a sekci Konstanty.

defined (PHP 3, PHP 4 >= 4.0.0)

Zkontroluje, jestli existuje daná pojmenovaná konstanta

int **defined** (string name) \linebreak

Vrací TRUE, pokud byla definována pojmenovaná konstanta daná argumentem *name*, jinak FALSE.

Příklad 1. Kontrola konstant

```
<?php
if (defined("CONSTANT")){ // název konstanty by měl být v uvozovkách
    echo CONSTANT; //
}
?>
```

Viz také define() a sekci Konstanty.

die (unknown)

Vytiskne vzkaz a ukončí současný skript

void **die** (string message) \linebreak

Tento jazykový konstrukt vytiskne vzkaz a ukončí parsování skriptu. Nemá návratovou hodnotu.

Příklad 1. die example

```
<?php
$filename = '/path/to/data-file';
$file = fopen ($filename, 'r')
    or die("nepodařilo se otevřít soubor ($filename)");
?>
```


Viz také `exit()`.

eval (unknown)

Vyhodnotí řetězec jako PHP kód

mixed **eval** (string *code_str*) \linebreak

eval() vyhodnotí řetězec předaný v *code_str* jako PHP kód. Kromě jiného se dá využít na ukládání kódu v textovém sloupci databáze pro pozdější vykonání.

Při používání **eval()** byste měli mít na paměti několik faktorů. Pamatujte si, že předávaný řetězec musí být platný PHP kód, včetně věcí jako ukončování výrazů středníkem, aby parser nezemřel na řádku po **eval()**, a řádné escapování v *code_str*.

Také pamatujte, že hodnoty přiřazené proměnným v **eval()** těmto proměnným zůstanou i v hlavním skriptu.

Výraz `return` okamžitě ukončí vyhodnocování předaného řetězce. V PHP 4 můžete použít `return` k vrácení hodnoty, která se stane výsledkem **eval()** funkce, zatímco v PHP 3 byl **eval()** typu `void` nic nevracel.

Příklad 1. eval() příklad - jednoduché spojení textů

```
<?php
$string = 'cup';
$name = 'coffee';
$str = 'This is a $string with my $name in it.<br>';
echo $str;
eval ("\$str = \"\$str\";");
echo $str;
?>
```

Výše uvedený příklad ukáže:

```
This is a $string with my $name in it.
This is a cup with my coffee in it.
```

exit (unknown)

Ukončí současný skript

void **exit** (void) \linebreak

Tento jazykový konstrukt ukončí parsování skriptu. Nevrací žádnou hodnotu.

Viz také `die()`.

get_browser (PHP 3, PHP 4 >= 4.0.0)

Určuje schopnosti uživatelského browseru

object **get_browser** ([string *user_agent*]) \linebreak

get_browser() se pokusí určit schopnosti uživatelského browseru. Toho je dosaženo vyhledáním informací o browseru v souboru `browscap.ini`. Standardně se použije `$HTTP_USER_AGENT`; nicméně, můžete to změnit (tj. vyhledat informace o jiném browseru) předáním volitelného argumentu *user_agent*.

Informace se vrací jako objekt, který obsahuje různé datové elementy, které reprezentují například hlavní a vedlejší číslo verze a ID řetězec; TRUE/false hodnoty vlastností jako podpora rámců, JavaScript a cookies, atd.

Jakkoli `browscap.ini` obsahuje informace o mnoha browserech, aktuálnost databáze závisí na uživatelských updatech. Formát souboru je poměrně snadno pochopitelný.

Následující příklad ukazuje, jak by se daly vypsát všechny informace získané o uživatelském browseru.

Příklad 1. get_browser() příklad

```
<?php
function list_array ($array) {
    while (list ($key, $value) = each ($array)) {
        $str .= "<b>$key:</b> $value<br>\n";
    }
    return $str;
}
echo "$HTTP_USER_AGENT<hr>\n";
$browser = get_browser();
echo list_array ((array) $browser);
?>
```

Výstup z výše uvedeného skriptu by vypadal asi takto:

```
Mozilla/4.5 [en] (X11; U; Linux 2.2.9 i586)<hr>
<b>browser_name_pattern:</b> Mozilla/4\..*<br>
<b>parent:</b> Netscape 4.0<br>
<b>platform:</b> Unknown<br>
<b>majorver:</b> 4<br>
<b>minorver:</b> 5<br>
<b>browser:</b> Netscape<br>
<b>version:</b> 4<br>
<b>frames:</b> 1<br>
<b>tables:</b> 1<br>
<b>cookies:</b> 1<br>
<b>backgroundsounds:</b> <br>
<b>vbscript:</b> <br>
<b>javascript:</b> 1<br>
<b>javaapplets:</b> 1<br>
<b>activexcontrols:</b> <br>
<b>beta:</b> <br>
<b>crawler:</b> <br>
```

```
<b>authenticcodeupdate:</b> <br>
<b>msn:</b> <br>
```

Aby to fungovalo, browscap direktiva ve vašem konfiguračním souboru musí ukazovat na platné umístění browscap.ini souboru.

Pro další informace (včetně lokací na kterých můžete získat browscap.ini soubor) viz PHP FAQ na <http://www.php.net/FAQ.php>.

highlight_file (PHP 4 >= 4.0.0)

Zvýrazní syntaxi souboru

boolean **highlight_file** (string filename) \linebreak

Funkce **highlight_file()** vytiskne barevně zvýrazněnou syntaxi kódu obsaženého ve *filename* s použitím barev definovaných ve zvýrazňovači syntaxe zabudovaném v PHP. Vrací TRUE při úspěchu, jinak FALSE (PHP 4).

Příklad 1. Tvorba URL zvýrazňující syntaxi

K vytvoření URL, která zvýrazní syntaxi jakéhokoliv skriptu, který jí předáte využijeme "ForceType" direktivu Apache k vytvoření hezkého vzorce URL, and pomocí funkce **highlight_file()** vypíšeme hezky vypadající výpis kódu.

Do svého httpd.conf přidejte následující:

```
<Location /source>
    ForceType application/x-httpd-php
</Location>
```

A potom vytvořte soubor pojmenovaný "source", a umístěte ho do svého web root adresáře.

```
<HTML>
<HEAD>
<TITLE>Zobrazení zdroje</TITLE>
</HEAD>
<BODY BGCOLOR="white">
<?php
    $script = getenv ("PATH_TRANSLATED");
    if (!$script) {
        echo "<BR><B>CHYBA: Je potřeba název skriptu!</B><BR>";
    } else {
        if (ereg ("\\.php|\\.inc)$", $script)) {
            echo "<H1>Zdroj souboru: $PATH_INFO</H1>\n<HR>\n";
            highlight_file($script);
        } else {
            echo "<H1>CHYBA: Povoleny jsou pouze soubory s příponou .php nebo .inc!</H1>";
        }
    }
}
```

```

        echo "<HR>Zpracováno: ".date("Y/M/d H:i:s",time());
    ?>
</BODY>
</HTML>

```

Potom můžete použít URL jako je ta níže k zobrazení obarvené verze skriptu umístěné v "/path/to/script.php" na vašem webu.

```
http://your.server.com/source/path/to/script.php
```

Viz také `highlight_string()`, `show_source()`.

highlight_string (PHP 4 >= 4.0.0)

Zvýraznění syntaxe řetězce

```
void highlight_string ( string str) \linebreak
```

Funkce **highlight_string()** vytiskne barevně zvýrazněnou verzi *str* s použitím barev definovaných ve zvýrazňovači syntaxe zabudovaném v PHP. Vrací TRUE při úspěchu, jinak FALSE (PHP 4).

Viz také `highlight_file()`, `show_source()`.

ignore_user_abort (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Nastavuje, jestli má ukončení spojení klientem přerušit vykonávání skriptu

```
int ignore_user_abort ( [int setting]) \linebreak
```

Tato funkce nastavuje, jestli má odpojení klienta způsobit ukončení skriptu. Vrací předchozí nastavení, a při zavolání bez argumentu současné nastavení nemění, pouze ho vrací. Úplné vysvětlení viz popis v sekci Obsluha spojení v kapitole Vlastnosti

iptcparse (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Parsuje binární IPTC <http://www.iptc.org/> blok do jednotlivých tagů.

```
array iptcparse ( string iptcblock) \linebreak
```

Tato funkce parsuje binární IPTC blok do jeho jednotlivých tagů. Vrací pole, které používá tagmarker jako index, a jeho hodnotu jako hodnotu. Vrací FALSE při chybě, nebo pokud nenajde žádná IPTC data. Příklad viz `GetImageSize()`.

leak (PHP 3, PHP 4 >= 4.0.0)

Nenávratně alokuje paměť

`void leak (int bytes) \linebreak`

leak() nenávratně alokuje specifikované množství paměti.

Tato funkce je užitečná při ladění správce paměti, který automaticky čistí "vyteklu" (leaked) paměť při dokončení každého požadavku.

pack (PHP 3, PHP 4 >= 4.0.0)

Sbalí data do binárního řetězce.

`string pack (string format [, mixed args]) \linebreak`

Sbalí předané argumenty do binárního řetězce podle argumentu *format*. Vrací binární řetězec obsahující předaná data.

Nápad na tuto funkci byl převzat z Perlu, a všechny formátovací kódy fungují stejně jako tam, nicméně, některé formátovací kódy chybí, jako například Perlovský formátovací kód "u". Formátovací řetězec sestává z formátovacích kódů následovaných volitelným opakovacím argumentem. Opakovací argument může být buď celočíselná hodnota, nebo * pro opakování do konce vstupních dat. U a, A, h, H počet opakování určuje, kolik znaků se vezme z jednoho datového argumentu, u @ je to absolutní pozice, kde se mají umístit další data, u všeho ostatního počet opakování určuje, kolik datových argumentů se spotřebuje a sbalí do výsledného binárního řetězce. V současnosti jsou implementovány

- a řetězec doplněný NUL hodnotami
- A řetězec doplněný SPACE hodnotami
- h Hex řetězec, spodní slabika první
- H Hex řetězec, horní slabika první
- c signed char
- C unsigned char
- s signed short (vždy 16 bitů, machine byte order)
- S unsigned short (vždy 16 bitů, machine byte order)
- n unsigned short (vždy 16 bitů, big endian byte order)
- v unsigned short (vždy 16 bitů, little endian byte order)
- i signed integer (velikost a pořadí bytů závislá na systému)
- I unsigned integer (velikost a pořadí bytů závislá na systému)
- l signed long (vždy 32 bitů, machine byte order)
- L unsigned long (vždy 32 bitů, machine byte order)
- N unsigned long (vždy 32 bitů, big endian byte order)
- V unsigned long (vždy 32 bitů, little endian byte order)

- f float (velikost a reprezentace závislá na systému)
- d double (velikost a reprezentace závislá na systému)
- x NUL byte
- X Back up one byte
- @ NUL-fill to absolute position

Příklad 1. pack() formátovací řetězec

```
$binarydata = pack ("nvc*", 0x1234, 0x5678, 65, 66);
```

Výsledný binární řetězec bude 6 bytů dlouhý, a bude obsahovat bytovou sekvenci 0x12, 0x34, 0x78, 0x56, 0x41, 0x42.

Všimněte si, že rozdíl mezi hodnotami se znaménkem a bez znaménka ovlivňuje pouze funkci `unpack()`, zatímco funkce **pack()** dává stejný výsledek pro formátovací kódy se znaménkem i bez znaménka.

Dále si všimněte, že PHP interně ukládá celočíselné hodnoty jako hodnoty se znaménkem o velikosti závislé na systému. Pokud zadáte hodnotu bez znaménka, která bude příliš velká, než aby se dala takto uložit, převede se na double, což často vytváří nežádoucí výsledky.

show_source (PHP 4 >= 4.0.0)

Zvýrazní syntaxi souboru

boolean **show_source** (string filename) \linebreak

Funkce **show_source()** vytiskne barevně zvýrazněnou syntaxi kódu obsaženého ve *filename* s použitím barev definovaných ve zvýrazňovači syntaxe zabudovaném v PHP. Vrací TRUE při úspěchu, jinak FALSE (PHP 4).

Poznámka: Tato funkce je alias funkce `highlight_file()`

Viz také `highlight_string()`, `highlight_file()`.

sleep (PHP 3, PHP 4 >= 4.0.0)

Odloží provedení

void **sleep** (int seconds) \linebreak

Funkce `sleep` odkládá provedení programu o počet sekund předaný v argumentu *seconds*.

Viz také `usleep()`.

uniqid (PHP 3, PHP 4 >= 4.0.0)

Generuje unikátní id

`int uniqid (string prefix [, boolean lcg])` \linebreak

uniqid() vrací unikátní identifikátor založený na současném čase v mikrosekundách, opatřený prefixem. Prefix může být užitečný například pokud generujete identifikátory na několika serverech současně, které by mohly vygenerovat identifikátor ve stejnou mikrosekundu. *Prefix* může být až 114 znaků dlouhý.

Pokud je volitelný argument *lcg* `TRUE`, **uniqid()** přidá dodatečnou "kombinovanou LCG" entropii na konec své návratové hodnoty, což by mělo učinit výsledky ještě unikátnějšími.

Pokud je *prefix* prázdný, vrácený řetězec bude 13 znaků dlouhý. Pokud je *lcg* `TRUE`, bude dlouhý 23 znaků.

Poznámka: *lcg* argument je přístupný pouze v PHP 4 and PHP 3.0.13 a vyšších.

Pokud potřebujete unikátní identifikátor nebo symbol, a zamýšlíte předat tento symbol uživateli po síti (např. session cookies), doporučujeme použít něco jako

```
$token = md5 (uniqid ("")); // no random portion
$better_token = md5 (uniqid (rand())); // better, difficult to guess
```

Toto vytvoří 32znakový identifikátor (128bitové hexa číslo), které se extrémně těžko předpovídá.

unpack (PHP 3, PHP 4 >= 4.0.0)

Rozbalí data z binárního řetězce

`array unpack (string format, string data)` \linebreak

unpack() rozbalí data z binárního řetězce do pole podle *format*. Vrací pole obsahující rozbalené prvky binárního řetězce.

unpack() funguje trochu jinak než v Perlu, jelikož rozbalená data jsou uložena v asociativním poli. Toho dosáhnete tak, že vyjmenujete různé formátovací kódy a oddělíte je lomítkem /.

Příklad 1. unpack() format string

```
$array = unpack ("c2chars/nint", $binarydata);
```

Výsledné pole obsahuje položky "chars1", "chars2" and "int".

Vysvětlení formátovacích kódů viz také: `pack()`

Všimněte si, že PHP interně ukládá celočíselné hodnoty se znaménkem. Pokud rozbalíte velkou celočíselnou hodnotu bez znaménka a ta má stejnou velikost jako hodnoty interně ukládané PHP, výsledkem bude negativní číslo, i když bylo zadáno rozbalování bez znaménka.

usleep (PHP 3, PHP 4 >= 4.0.0)

Odloží provedení v mikrosekundách

void **usleep** (int micro_seconds) \linebreak

Funkce **usleep()** odloží provedení skriptu o daný počet *micro_seconds*.

Viz také sleep().

Poznámka: Tato funkce nefunguje na Windows systémech.

LX. mnoGoSearch Functions

These functions allow you to access mnoGoSearch (former UdmSearch) free search engine. In order to have these functions available, you must compile php with mnogosearch support by using the `--with-mnogosearch` option. If you use this option without specifying the path to mnogosearch, php will look for mnogosearch under `/usr/local/mnogosearch` path by default. If you installed mnogosearch at other path you should specify it: `--with-mnogosearch=DIR`.

mnoGoSearch is a full-featured search engine software for intranet and internet servers, distributed under the GNU license. mnoGoSearch has number of unique features, which makes it appropriate for a wide range of application from search within your site to a specialized search system such as cooking recipes or newspaper search, ftp archive search, news articles search, etc. It offers full-text indexing and searching for HTML, PDF, and text documents. mnoGoSearch consists of two parts. The first is an indexing mechanism (indexer). The purpose of indexer is to walk through HTTP, FTP, NEWS servers or local files, recursively grabbing all the documents and storing meta-data about that documents in a SQL database in a smart and effective manner. After every document is referenced by its corresponding URL, meta-data collected by indexer is used later in a search process. The search is performed via Web interface. C CGI, PHP and Perl search front ends are included.

Poznámka: php contains built-in mysql access library, which can be used to access mysql. It is known that mnoGoSearch is not compatible with this built-in library and can work only with generic mysql libraries. Thus, if you use mnoGoSearch with mysql, during php configuration you have to indicate directory of mysql installation, that was used during mnoGoSearch configuration, i.e. for example: `--with-mnogosearch --with-mysql=/usr`.

You need at least 3.1.10 version of mnoGoSearch installed to use these functions.

More information about mnoGoSearch can be found at <http://www.mnogosearch.ru/>.

udm_add_search_limit (PHP 4 >= 4.0.5)

Add various search limits

```
int udm_add_search_limit ( int agent, int var, string val) \linebreak
```

udm_add_search_limit() returns TRUE on success, FALSE on error. Adds search restrictions.

agent - a link to Agent, received after call to `udm_alloc_agent()`.

var - defines parameter, indicating limit.

val - defines value of the current parameter.

Possible *var* values:

- **UDM_LIMIT_URL** - defines document URL limitations to limit search through subsection of database. It supports SQL % and _ LIKE wildcards, where % matches any number of characters, even zero characters, and _ matches exactly one character. E.g. `http://my.domain.__/catalog` may stand for `http://my.domain.ru/catalog` and `http://my.domain.ua/catalog`.
- **UDM_LIMIT_TAG** - defines site TAG limitations. In `indexer-conf` you can assign specific TAGs to various sites and parts of a site. Tags in mnoGoSearch 3.1.x are lines, that may contain metasymbols % and _. Metasymbols allow searching among groups of tags. E.g. there are links with tags ABCD and ABCE, and search restriction is by `ABC_` - the search will be made among both of the tags.
- **UDM_LIMIT_LANG** - defines document language limitations.
- **UDM_LIMIT_CAT** - defines document category limitations. Categories are similar to tag feature, but nested. So you can have one category inside another and so on. You have to use two characters for each level. Use a hex number going from 0-F or a 36 base number going from 0-Z. Therefore a top-level category like 'Auto' would be 01. If it has a subcategory like 'Ford', then it would be 01 (the parent category) and then 'Ford' which we will give 01. Put those together and you get 0101. If 'Auto' had another subcategory named 'VW', then it's id would be 01 because it belongs to the 'Ford' category and then 02 because it's the next category. So it's id would be 0102. If VW had a sub category called 'Engine' then it's id would start at 01 again and it would get the 'VW' id 02 and 'Auto' id of 01, making it 010201. If you want to search for sites under that category then you pass it `cat=010201` in the url.
- **UDM_LIMIT_DATE** - defines limitation by date document was modified.

Format of parameter value: a string with first character < or >, then with no space - date in unixtime format, for example:

```
Udm_Add_Search_Limit($udm,UDM_LIMIT_DATE,"<908012006");
```

If > character is used, then search will be restricted to those documents having modification date greater than entered. If <, then smaller.

udm_alloc_agent (PHP 4 >= 4.0.5)

Allocate mnoGoSearch session

```
int udm_alloc_agent ( string dbaddr [, string dbmode]) \linebreak
```

udm_alloc_agent() returns mnogosearch agent identifier on success, `FALSE` on error. This function creates a session with database parameters.

dbaddr - URL-style database description. Options (type, host, database name, port, user and password) to connect to SQL database. Do not matter for built-in text files support. Format: DBAddr DBType:[//[DBUser[:DBPass]@]DBHost[:DBPort]]/DBName/ Currently supported DBType values are: mysql, pgsql, msql, solid, mssql, oracle, ibase. Actually, it does not matter for native libraries support. But ODBC users should specify one of supported values. If your database type is not supported, you may use "unknown" instead.

dbmode - You may select SQL database mode of words storage. When "single" is specified, all words are stored in the same table. If "multi" is selected, words will be located in different tables depending of their lengths. "multi" mode is usually faster but requires more tables in database. If "crc" mode is selected, mnoGoSearch will store 32 bit integer word IDs calculated by CRC32 algorithm instead of words. This mode requires less disk space and it is faster comparing with "single" and "multi" modes. "crc-multi" uses the same storage structure with the "crc" mode, but also stores words in different tables depending on words lengths like "multi" mode. Format: DBMode single/multi/crc/crc-multi

Poznámka: *dbaddr* and *dbmode* must match those used during indexing.

Poznámka: In fact this function does not open connection to database and thus does not check entered login and password. Actual connection to database and login/password verification is done by `udm_find()`.

udm_api_version (PHP 4 >= 4.0.5)

Get mnoGoSearch API version.

`int udm_api_version (void) \linebreak`

udm_api_version() returns mnoGoSearch API version number. E.g. if mnoGoSearch 3.1.10 API is used, this function will return 30110.

This function allows user to identify which API functions are available, e.g. `udm_get_doc_count()` function is only available in mnoGoSearch 3.1.11 or later.

Example:

```
if (udm_api_version() >= 30111) {
    print "Total number of urls in database: ".udm_get_doc_count($udm). "<br>\n";
}
```

udm_cat_list (PHP 4 >= 4.0.6)

Get all the categories on the same level with the current one.

array **udm_cat_list** (int agent, string category) \linebreak

udm_cat_list() returns array listing all categories of the same level as current category in the categories tree.

The function can be useful for developing categories tree browser.

Returns array with the following format:

The array consists of pairs. Elements with even index numbers contain category paths, odd elements contain corresponding category names.

```
$array[0] will contain '020300'
$array[1] will contain 'Audi'
$array[2] will contain '020301'
$array[3] will contain 'BMW'
$array[4] will contain '020302'
$array[5] will contain 'Opel'
...
etc.
```

Following is an example of displaying links of the current level in format:

```
Audi
BMW
Opel
...
```

```
<?php
$cat_list_arr = udm_cat_list($udm_agent,$cat);
$cat_list = "";
for ($i=0; $i<count($cat_list_arr); $i+=2) {
    $path = $cat_list_arr[$i];
    $name = $cat_list_arr[$i+1];
    $cat_list .= "<a href=\"".$PHP_SELF?cat=$path\">$name</a><br>";
}
?>
```

udm_cat_path (PHP 4 >= 4.0.6)

Get the path to the current category.

array **udm_cat_path** (int agent, string category) \linebreak

udm_cat_path() returns array describing path in the categories tree from the tree root to the current category.

agent - agent link identifier.

category - current category - the one to get path to.

Returns array with the following format:

The array consists of pairs. Elements with even index numbers contain category paths, odd elements contain corresponding category names.

For example, the call `$array=udm_cat_path($agent, '02031D');` may return the following array:

```
$array[0] will contain ''
$array[1] will contain 'Root'
$array[2] will contain '02'
$array[3] will contain 'Sport'
$array[4] will contain '0203'
$array[5] will contain 'Auto'
$array[6] will contain '02031D'
$array[7] will contain 'Ferrari'
```

Příklad 1. Specifying path to the current category in the following format: '> Root > Sport > Auto > Ferrari'

```
<?php
$cat_path_arr = udm_cat_path($udm_agent,$cat);
$cat_path = "";
for ($i=0; $i<count($cat_path_arr); $i+=2) {
    $path = $cat_path_arr[$i];
    $name = $cat_path_arr[$i+1];
    $cat_path .= " > <a href=\"\$PHP_SELF?cat=$path\">$name</a> ";
}
?>
```

udm_check_charset (PHP 4 >= 4.2.0)

Check if the given charset is known to mnogosearch

int **udm_check_charset** (int agent, string charset) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

udm_check_stored (PHP 4 >= 4.2.0)

Check connection to stored

int **udm_check_stored** (int agent, int link, string doc_id) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

udm_clear_search_limits (PHP 4 >= 4.0.5)

Clear all mnoGoSearch search restrictions

int **udm_clear_search_limits** (int agent) \linebreak

udm_clear_search_limits() resets defined search limitations and returns TRUE.

udm_close_stored (PHP 4 >= 4.2.0)

Close connection to stored

int **udm_close_stored** (int agent, int link) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

udm_crc32 (PHP 4 >= 4.2.0)

Return CRC32 checksum of gived string

int **udm_crc32** (int agent, string str) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

udm_errno (PHP 4 >= 4.0.5)

Get mnoGoSearch error number

int **udm_errno** (int agent) \linebreak

udm_errno() returns mnoGoSearch error number, zero if no error.

agent - link to agent identifier, received after call to `udm_alloc_agent()`.

Receiving numeric agent error code.

udm_error (PHP 4 >= 4.0.5)

Get mnoGoSearch error message

string **udm_error** (int agent) \linebreak

udm_error() returns mnoGoSearch error message, empty string if no error.

agent - link to agent identifier, received after call to `udm_alloc_agent()`.

Receiving agent error message.

udm_find (PHP 4 >= 4.0.5)

Perform search

int **udm_find** (int agent, string query) \linebreak

udm_find() returns result link identifier on success, `FALSE` on error.

The search itself. The first argument - session, the next one - query itself. To find something just type words you want to find and press SUBMIT button. For example, "mysql odbc". You should not use quotes " in query, they are written here only to divide a query from other text. mnoGoSearch will find all documents that contain word "mysql" and/or word "odbc". Best documents having bigger weights will be displayed first. If you use search mode ALL, search will return documents that

contain both (or more) words you entered. In case you use mode ANY, the search will return list of documents that contain any of the words you entered. If you want more advanced results you may use query language. You should select "bool" match mode in the search from.

mnoGoSearch understands the following boolean operators:

& - logical AND. For example, "mysql & odbc". mnoGoSearch will find any URLs that contain both "mysql" and "odbc".

| - logical OR. For example "mysql|odbc". mnoGoSearch will find any URLs, that contain word "mysql" or word "odbc".

~ - logical NOT. For example "mysql & ~odbc". mnoGoSearch will find URLs that contain word "mysql" and do not contain word "odbc" at the same time. Note that ~ just excludes given word from results. Query "~odbc" will find nothing!

() - group command to compose more complex queries. For example "(mysql | msql) & ~postgres". Query language is simple and powerful at the same time. Just consider query as usual boolean expression.

udm_free_agent (PHP 4 >= 4.0.5)

Free mnoGoSearch session

```
int udm_free_agent ( int agent) \linebreak
```

udm_free_agent() returns TRUE on success, FALSE on error.

agent - link to agent identifier, received ' after call to udm_alloc_agent().

Freeing up memory allocated for agent session.

udm_free_ispell_data (PHP 4 >= 4.0.5)

Free memory allocated for ispell data

```
int udm_free_ispell_data ( int agent) \linebreak
```

udm_free_ispell_data() always returns TRUE.

agent - agent link identifier, received after call to udm_alloc_agent().

Poznámka: This function is supported beginning from version 3.1.12 of mnoGoSearch and it does not do anything in previous versions.

udm_free_res (PHP 4 >= 4.0.5)

Free mnoGoSearch result

```
int udm_free_res ( int res) \linebreak
```


udm_free_res() returns TRUE on success, FALSE on error.

res - a link to result identifier, received after call to `udm_find()`.

Freeing up memory allocated for results.

udm_get_doc_count (PHP 4 >= 4.0.5)

Get total number of documents in database.

int **udm_get_doc_count** (int agent) \linebreak

udm_get_doc_count() returns number of documents in database.

agent - link to agent identifier, received after call to `udm_alloc_agent()`.

Poznámka: This function is supported only in mnoGoSearch 3.1.11 or later.

udm_get_res_field (PHP 4 >= 4.0.5)

Fetch mnoGoSearch result field

string **udm_get_res_field** (int res, int row, int field) \linebreak

udm_get_res_field() returns result field value on success, FALSE on error.

res - a link to result identifier, received after call to `udm_find()`.

row - the number of the link on the current page. May have values from 0 to

`UDM_PARAM_NUM_ROWS-1`.

field - field identifier, may have the following values:

- UDM_FIELD_URL - document URL field
- UDM_FIELD_CONTENT - document Content-type field (for example, text/html).
- UDM_FIELD_CATEGORY - document category field. Use `udm_cat_path()` to get full path to current category from the categories tree root. (This parameter is available only in PHP 4.0.6 or later).
- UDM_FIELD_TITLE - document title field.
- UDM_FIELD_KEYWORDS - document keywords field (from META KEYWORDS tag).
- UDM_FIELD_DESC - document description field (from META DESCRIPTION tag).
- UDM_FIELD_TEXT - document body text (the first couple of lines to give an idea of what the document is about).
- UDM_FIELD_SIZE - document size.
- UDM_FIELD_URLID - unique URL ID of the link.
- UDM_FIELD_RATING - page rating (as calculated by mnoGoSearch).
- UDM_FIELD_MODIFIED - last-modified field in unixtime format.

- UDM_FIELD_ORDER - the number of the current document in set of found documents.
- UDM_FIELD_CRC - document CRC.

udm_get_res_param (PHP 4 >= 4.0.5)

Get mnoGoSearch result parameters

string **udm_get_res_param** (int res, int param) \linebreak

udm_get_res_param() returns result parameter value on success, `FALSE` on error.

res - a link to result identifier, received after call to `udm_find()`.

param - parameter identifier, may have the following values:

- UDM_PARAM_NUM_ROWS - number of received found links on the current page. It is equal to UDM_PARAM_PAGE_SIZE for all search pages, on the last page - the rest of links.
- UDM_PARAM_FOUND - total number of results matching the query.
- UDM_PARAM_WORDINFO - information on the words found. E.g. search for "a good book" will return "a: stopword, good:5637, book: 120"
- UDM_PARAM_SEARCHTIME - search time in seconds.
- UDM_PARAM_FIRST_DOC - the number of the first document displayed on current page.
- UDM_PARAM_LAST_DOC - the number of the last document displayed on current page.

udm_load_ispell_data (PHP 4 >= 4.0.5)

Load ispell data

int **udm_load_ispell_data** (int agent, int var, string val1, string val2, int flag) \linebreak

udm_load_ispell_data() loads ispell data. Returns `TRUE` on success, `FALSE` on error.

agent - agent link identifier, received after call to `udm_alloc_agent()`.

var - parameter, indicating the source for ispell data. May have the following values:

After using this function to free memory allocated for ispell data, please use `udm_free_ispell_data()`, even if you use UDM_ISPELL_TYPE_SERVER mode.

The fastest mode is UDM_ISPELL_TYPE_SERVER. UDM_ISPELL_TYPE_TEXT is slower and UDM_ISPELL_TYPE_DB is the slowest. The above pattern is `TRUE` for mnoGoSearch 3.1.10 - 3.1.11. It is planned to speed up DB mode in future versions and it is going to be faster than TEXT mode.

- UDM_ISPELL_TYPE_DB - indicates that ispell data should be loaded from SQL. In this case, parameters *val1* and *val2* are ignored and should be left blank. *flag* should be equal to 1.

Poznámka: *flag* indicates that after loading ispell data from defined source it could be sorted (it is necessary for correct functioning of ispell). In case of loading ispell data from files there may be several calls to **udm_load_ispell_data()**, and there is no sense to sort data

after every call, but only after the last one. Since in db mode all the data is loaded by one call, this parameter should have the value 1. In this mode in case of error, e.g. if ispell tables are absent, the function will return `FALSE` and code and error message will be accessible through `udm_error()` and `udm_errno()`.

Example:

```
if (! udm_load_ispell_data($udm,UDM_ISPELL_TYPE_DB,"",1)) {
    printf("Error #d: '%s'\n", udm_errno($udm), udm_error($udm));
    exit;
}
```

- `UDM_ISPELL_TYPE_AFFIX` - indicates that ispell data should be loaded from file and initiates loading affixes file. In this case *val1* defines double letter language code for which affixes are loaded, and *val2* - file path. Please note, that if a relative path entered, the module looks for the file not in `UDM_CONF_DIR`, but in relation to current path, i.e. to the path where the script is executed. In case of error in this mode, e.g. if file is absent, the function will return `FALSE`, and an error message will be displayed. Error message text cannot be accessed through `udm_error()` and `udm_errno()`, since those functions can only return messages associated with SQL. Please, see *flag* parameter description in `UDM_ISPELL_TYPE_DB`.

Example:

```
if ((! udm_load_ispell_data($udm,UDM_ISPELL_TYPE_AFFIX,'en','/opt/ispell/en.aff',0)
    (! udm_load_ispell_data($udm,UDM_ISPELL_TYPE_AFFIX,'ru','/opt/ispell/ru.aff',0)
    (! udm_load_ispell_data($udm,UDM_ISPELL_TYPE_SPELL,'en','/opt/ispell/en.dict',0)
    (! udm_load_ispell_data($udm,UDM_ISPELL_TYPE_SPELL,'ru','/opt/ispell/ru.dict',0)
    exit;
}
```

Poznámka: *flag* is equal to 1 only in the last call.

- `UDM_ISPELL_TYPE_SPELL` - indicates that ispell data should be loaded from file and initiates loading of ispell dictionary file. In this case *val1* defines double letter language code for which affixes are loaded, and *val2* - file path. Please note, that if a relative path entered, the module looks for the file not in `UDM_CONF_DIR`, but in relation to current path, i.e. to the path where the script is executed. In case of error in this mode, e.g. if file is absent, the function will return `FALSE`, and an error message will be displayed. Error message text cannot be accessed through `udm_error()` and `udm_errno()`, since those functions can only return messages associated with SQL. Please, see *flag* parameter description in `UDM_ISPELL_TYPE_DB`.

```
if ((! Udm_Load_Ispell_Data($udm,UDM_ISPELL_TYPE_AFFIX,'en','/opt/ispell/en.aff',0
```

```

        (! Udm_Load_Ispell_Data($udm,UDM_ISPELL_TYPE_AFFIX,'ru','/opt/ispell/ru.aff',0)
        (! Udm_Load_Ispell_Data($udm,UDM_ISPELL_TYPE_SPELL,'en','/opt/ispell/en.dict',0)
        (! Udm_Load_Ispell_Data($udm,UDM_ISPELL_TYPE_SPELL,'ru','/opt/ispell/ru.dict',1)
    exit;
}

```

Poznámka: *flag* is equal to 1 only in the last call.

- UDM_ISPELL_TYPE_SERVER - enables spell server support. *val1* parameter indicates address of the host running spell server. *val2* ' is not used yet, but in future releases it is going to indicate number of port used by spell server. *flag* parameter in this case is not needed since ispell data is stored on spellserver already sorted.

Spelld server reads spell-data from a separate configuration file (/usr/local/mnogosearch/etc/spelld.conf by default), sorts it and stores in memory. With clients server communicates in two ways: to indexer all the data is transferred (so that indexer starts faster), from search.cgi server receives word to normalize and then passes over to client (search.cgi) list of normalized word forms. This allows fastest, compared to db and text modes processing of search queries (by omitting loading and sorting all the spell data).

udm_load_ispell_data() function in UDM_ISPELL_TYPE_SERVER mode does not actually load ispell data, but only defines server address. In fact, server is automatically used by **udm_find()** function when performing search. In case of errors, e.g. if spellserver is not running or invalid host indicated, there are no messages returned and ispell conversion does not work.

Poznámka: This function is available in mnoGoSearch 3.1.12 or later.

Example:

```

if (!udm_load_ispell_data($udm,UDM_ISPELL_TYPE_SERVER,"",1)) {
    printf("Error loading ispell data from server<br>\n");
    exit;
}

```

udm_open_stored (PHP 4 >= 4.2.0)

Open connection to stored

int **udm_open_stored** (int agent, string storedaddr) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

udm_set_agent_param (PHP 4 >= 4.0.5)

Set mnoGoSearch agent session parameters

int **udm_set_agent_param** (int agent, int var, string val) \linebreak

udm_set_agent_param() returns TRUE on success, FALSE on error. Defines mnoGoSearch session parameters.

The following parameters and their values are available:

- UDM_PARAM_PAGE_NUM - used to choose search results page number (results are returned by pages beginning from 0, with UDM_PARAM_PAGE_SIZE results per page).
- UDM_PARAM_PAGE_SIZE - number of search results displayed on one page.
- UDM_PARAM_SEARCH_MODE - search mode. The following values available:
UDM_MODE_ALL - search for all words; UDM_MODE_ANY - search for any word;
UDM_MODE_PHRASE - phrase search; UDM_MODE_BOOL - boolean search. See udm_find() for details on boolean search.
- UDM_PARAM_CACHE_MODE - turns on or off search result cache mode. When enabled, the search engine will store search results to disk. In case a similar search is performed later, the engine will take results from the cache for faster performance. Available values:
UDM_CACHE_ENABLED, UDM_CACHE_DISABLED.
- UDM_PARAM_TRACK_MODE - turns on or off trackquery mode. Since version 3.1.2 mnoGoSearch has a query tracking support. Note that tracking is implemented in SQL version only and not available in built-in database. To use tracking, you have to create tables for tracking support. For MySQL, use create/mysql/track.txt. When doing a search, front-end uses those tables to store query words, a number of found documents and current UNIX timestamp in seconds. Available values: UDM_TRACK_ENABLED, UDM_TRACK_DISABLED.
- UDM_PARAM_PHRASE_MODE - defines whether index database using phrases ("phrase" parameter in indexer.conf). Possible values: UDM_PHRASE_ENABLED and UDM_PHRASE_DISABLED. Please note, that if phrase search is enabled (UDM_PHRASE_ENABLED), it is still possible to do search in any mode (ANY, ALL, BOOL or PHRASE). In 3.1.10 version of mnoGoSearch phrase search is supported only in sql and built-in database modes, while beginning with 3.1.11 phrases are supported in cachemode as well.

Examples of phrase search:

"Arizona desert" - This query returns all indexed documents that contain "Arizona desert" as a phrase. Notice that you need to put double quotes around the phrase

- UDM_PARAM_CHARSET - defines local charset. Available values: set of charsets supported by mnoGoSearch, e.g. koi8-r, cp1251, ...

- UDM_PARAM_STOPFILE - Defines name and path to stopwords file. (There is a small difference with mnoGoSearch - while in mnoGoSearch if relative path or no path entered, it looks for this file in relation to UDM_CONF_DIR, the module looks for the file in relation to current path, i.e. to the path where the php script is executed.)
- UDM_PARAM_STOPTABLE - Load stop words from the given SQL table. You may use several StopwordTable commands. This command has no effect when compiled without SQL database support.
- UDM_PARAM_WEIGHT_FACTOR - represents weight factors for specific document parts. Currently body, title, keywords, description, url are supported. To activate this feature please use degrees of 2 in *Weight commands of the indexer.conf. Let's imagine that we have these weights:

```
URLWeight 1
BodyWeight 2
TitleWeight 4
KeywordWeight 8
DescWeight 16
```

As far as indexer uses bit OR operation for word weights when some word presents several time in the same document, it is possible at search time to detect word appearance in different document parts. Word which appears only in the body will have 00000010 aragate weight (in binary notation). Word used in all document parts will have 00011111 aggregate weight.

This parameter's value is a string of hex digits ABCDE. Each digit is a factor for corresponding bit in word weight. For the given above weights configuration:

```
E is a factor for weight 1 (URL Weight bit)
D is a factor for weight 2 (BodyWeight bit)
C is a factor for weight 4 (TitleWeight bit)
B is a factor for weight 8 (KeywordWeight bit)
A is a factor for weight 16 (DescWeight bit)
```

Examples:

UDM_PARAM_WEIGHT_FACTOR=00001 will search through URLs only.

UDM_PARAM_WEIGHT_FACTOR=00100 will search through Titles only.

UDM_PARAM_WEIGHT_FACTOR=11100 will search through Title,Keywords,Description but not through URL and Body.

UDM_PARAM_WEIGHT_FACTOR=F9421 will search through:

```
Description with factor 15 (F hex)
Keywords with factor 9
Title with factor 4
Body with factor 2
URL with factor 1
```

If UDM_PARAM_WEIGHT_FACTOR variable is ommited, original weight value is taken to sort results. For a given above weight configuration it means that document description has a most big weight 16.

- UDM_PARAM_WORD_MATCH - word match. You may use this parameter to choose word match type. This feature works only in "single" and "multi" modes using SQL based and built-in

database. It does not work in cachemode and other modes since they use word CRC and do not support substring search. Available values:

UDM_MATCH_BEGIN - word beginning match;

UDM_MATCH_END - word ending match;

UDM_MATCH_WORD - whole word match;

UDM_MATCH_SUBSTR - word substring match.

- UDM_PARAM_MIN_WORD_LEN - defines minimal word length. Any word shorter this limit is considered to be a stopword. Please note that this parameter value is inclusive, i.e. if UDM_PARAM_MIN_WORD_LEN=3, a word 3 characters long will not be considered a stopword, while a word 2 characters long will be. Default value is 1.
- UDM_PARAM_ISPELL_PREFIXES - Possible values: UDM_PREFIXES_ENABLED and UDM_PREFIXES_DISABLED, that respectively enable or disable using prefixes. E.g. if a word "tested" is in search query, also words like "test", "testing", etc. Only suffixes are supported by default. Prefixes usually change word meanings, for example if somebody is searching for the word "tested" one hardly wants "untested" to be found. Prefixes support may also be found useful for site's spelling checking purposes. In order to enable ispell, you have to load ispell data with `udm_load_ispell_data()`.
- UDM_PARAM_CROSS_WORDS - enables or disables crosswords support. Possible values: UDM_CROSS_WORDS_ENABLED and UDM_CROSS_WORDS_DISABLED.

The crosswords feature allows to assign words between `` and `` also to a document this link leads to. It works in SQL database mode and is not supported in built-in database and Cachemode.

Poznámka: Crosswords are supported only in mnoGoSearch 3.1.11 or later.

- UDM_PARAM_VARDIR - specifies a custom path to directory where indexer stores data when using built-in database and in cache mode. By default `/var` directory of mnoGoSearch installation is used. Can have only string values. The parameter is available in PHP 4.1.0 or later.
- UDM_PARAM_VARDIR - specifies a custom path to directory where indexer stores data when using built-in database and in cache mode. By default `/var` directory of mnoGoSearch installation is used. Can have only string values. The parameter is available in PHP 4.1.0 or later.

LXI. mSQL functions

These functions allow you to access mSQL database servers. In order to have these functions available, you must compile php with msql support by using the `--with-msql[=dir]` option. The default location is `/usr/local/Hughes`.

More information about mSQL can be found at <http://www.hughes.com.au/>.

mysql (PHP 3, PHP 4 >= 4.0.0)

Send mSQL query

```
int mysql ( string database, string query, int link_identifier) \linebreak
```

Returns a positive mSQL query identifier to the query result, or `FALSE` on error.

mysql() selects a database and executes a query on it. If the optional link identifier isn't specified, the function will try to find an open link to the mSQL server and if no such link is found it'll try to create one as if `mysql_connect()` was called with no arguments (see `mysql_connect()`).

mysql_affected_rows (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Returns number of affected rows

```
int mysql_affected_rows ( int query_identifier) \linebreak
```

Returns number of affected ("touched") rows by a specific query (i.e. the number of rows returned by a `SELECT`, the number of rows modified by an update, or the number of rows removed by a delete).

See also: `mysql_query()`.

mysql_close (PHP 3, PHP 4 >= 4.0.0)

Close mSQL connection

```
int mysql_close ( int link_identifier) \linebreak
```

Returns `TRUE` on success, `FALSE` on error.

mysql_close() closes the link to a mSQL database that's associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed.

Note that this isn't usually necessary, as non-persistent open links are automatically closed at the end of the script's execution.

mysql_close() will not close persistent links generated by `mysql_pconnect()`.

See also: `mysql_connect()` and `mysql_pconnect()`.

mysql_connect (PHP 3, PHP 4 >= 4.0.0)

Open mSQL connection

```
int mysql_connect ( [string hostname [, string server [, string username [, string password]]]]) \linebreak
```

Returns a positive mSQL link identifier on success, or `FALSE` on error.

mysql_connect() establishes a connection to a mSQL server. The *server* parameter can also include a port number. eg. "hostname:port". It defaults to 'localhost'.

In case a second call is made to **mysql_connect()** with the same arguments, no new link will be established, but instead, the link identifier of the already opened link will be returned.

The link to the server will be closed as soon as the execution of the script ends, unless it's closed earlier by explicitly calling **mysql_close()**.

See also **mysql_pconnect()**, **mysql_close()**.

mysql_create_db (PHP 3, PHP 4 >= 4.0.0)

Create mSQL database

```
int mysql_create_db ( string database name [, int link_identifier] ) \linebreak
```

mysql_create_db() attempts to create a new database on the server associated with the specified link identifier.

See also: **mysql_drop_db()**.

mysql_createdb (PHP 3, PHP 4 >= 4.0.0)

Create mSQL database

```
int mysql_createdb ( string database name [, int link_identifier] ) \linebreak
```

Identical to **mysql_create_db()**.

mysql_data_seek (PHP 3, PHP 4 >= 4.0.0)

Move internal row pointer

```
int mysql_data_seek ( int query_identifier, int row_number ) \linebreak
```

Vrací TRUE při úspěchu, FALSE při selhání.

mysql_data_seek() moves the internal row pointer of the mSQL result associated with the specified query identifier to pointer to the specified row number. The next call to **mysql_fetch_row()** would return that row.

See also: **mysql_fetch_row()**.

mysql_dbname (PHP 3, PHP 4 >= 4.0.0)

Get current mSQL database name

```
string mysql_dbname ( int query_identifier, int i ) \linebreak
```

mysql_dbname() returns the database name stored in position *i* of the result pointer returned from the **mysql_listdbs()** function. The **mysql_numrows()** function can be used to determine how many database names are available.

mysql_drop_db (PHP 3, PHP 4 >= 4.0.0)

Drop (delete) mSQL database

```
int mysql_drop_db ( string database_name, int link_identifier) \linebreak
```

Vrací **TRUE** při úspěchu, **FALSE** při selhání.

mysql_drop_db() attempts to drop (remove) an entire database from the server associated with the specified link identifier.

See also: **mysql_create_db()**.

mysql_dropdb (PHP 3, PHP 4 >= 4.0.0)

Drop (delete) mSQL database

See **mysql_drop_db()**.

mysql_error (PHP 3, PHP 4 >= 4.0.0)

Returns error message of last mysql call

```
string mysql_error ( [int link_identifier]) \linebreak
```

Errors coming back from the mSQL database backend no longer issue warnings. Instead, use these functions to retrieve the error string.

mysql_fetch_array (PHP 3, PHP 4 >= 4.0.0)

Fetch row as array

```
int mysql_fetch_array ( int query_identifier [, int result_type]) \linebreak
```

Returns an array that corresponds to the fetched row, or **FALSE** if there are no more rows.

mysql_fetch_array() is an extended version of **mysql_fetch_row()**. In addition to storing the data in the numeric indices of the result array, it also stores the data in associative indices, using the field names as keys.

The second optional argument *result_type* in **mysql_fetch_array()** is a constant and can take the following values: **MYSQL_ASSOC**, **MYSQL_NUM**, and **MYSQL_BOTH**.

Be careful if you are retrieving results from a query that may return a record that contains only one field that has a value of 0 (or an empty string, or `NULL`).

An important thing to note is that using **`mysql_fetch_array()`** is NOT significantly slower than using **`mysql_fetch_row()`**, while it provides a significant added value.

For further details, also see **`mysql_fetch_row()`**.

`mysql_fetch_field` (PHP 3, PHP 4 >= 4.0.0)

Get field information

object **`mysql_fetch_field`** (int query_identifier, int field_offset) \linebreak

Returns an object containing field information

`mysql_fetch_field()` can be used in order to obtain information about fields in a certain query result. If the field offset isn't specified, the next field that wasn't yet retrieved by **`mysql_fetch_field()`** is retrieved.

The properties of the object are:

- `name` - column name
- `table` - name of the table the column belongs to
- `not_null` - 1 if the column cannot be `NULL`
- `primary_key` - 1 if the column is a primary key
- `unique` - 1 if the column is a unique key
- `type` - the type of the column

See also **`mysql_field_seek()`**.

`mysql_fetch_object` (PHP 3, PHP 4 >= 4.0.0)

Fetch row as object

int **`mysql_fetch_object`** (int query_identifier [, int result_type]) \linebreak

Returns an object with properties that correspond to the fetched row, or `FALSE` if there are no more rows.

`mysql_fetch_object()` is similar to **`mysql_fetch_array()`**, with one difference - an object is returned, instead of an array. Indirectly, that means that you can only access the data by the field names, and not by their offsets (numbers are illegal property names).

The optional second argument *result_type* in **`mysql_fetch_array()`** is a constant and can take the following values: `MYSQL_ASSOC`, `MYSQL_NUM`, and `MYSQL_BOTH`.

Speed-wise, the function is identical to **`mysql_fetch_array()`**, and almost as quick as **`mysql_fetch_row()`** (the difference is insignificant).

See also: **`mysql_fetch_array()`** and **`mysql_fetch_row()`**.

mysql_fetch_row (PHP 3, PHP 4 >= 4.0.0)

Get row as enumerated array

```
array mysql_fetch_row ( int query_identifier) \linebreak
```

Returns an array that corresponds to the fetched row, or `FALSE` if there are no more rows.

mysql_fetch_row() fetches one row of data from the result associated with the specified query identifier. The row is returned as an array. Each result column is stored in an array offset, starting at offset 0.

Subsequent call to **mysql_fetch_row()** would return the next row in the result set, or `FALSE` if there are no more rows.

See also: `mysql_fetch_array()`, `mysql_fetch_object()`, `mysql_data_seek()`, and `mysql_result()`.

mysql_field_seek (PHP 3, PHP 4 >= 4.0.0)

Set field offset

```
int mysql_field_seek ( int query_identifier, int field_offset) \linebreak
```

Seeks to the specified field offset. If the next call to `mysql_fetch_field()` won't include a field offset, this field would be returned.

See also: `mysql_fetch_field()`.

mysql_fieldflags (PHP 3, PHP 4 >= 4.0.0)

Get field flags

```
string mysql_fieldflags ( int query_identifier, int i) \linebreak
```

mysql_fieldflags() returns the field flags of the specified field. Currently this is either, "not NULL", "primary key", a combination of the two or "" (an empty string).

mysql_fieldlen (PHP 3, PHP 4 >= 4.0.0)

Get field length

```
int mysql_fieldlen ( int query_identifier, int i) \linebreak
```

mysql_fieldlen() returns the length of the specified field.

mysql_fieldname (PHP 3, PHP 4 >= 4.0.0)

Get field name

string **mysql_fieldname** (int query_identifier, int field) \linebreak

mysql_fieldname() returns the name of the specified field. *query_identifier* is the query identifier, and *field* is the field index. `mysql_fieldname($result, 2);` will return the name of the second field in the result associated with the result identifier.

mysql_fieldtable (PHP 3, PHP 4 >= 4.0.0)

Get table name for field

int **mysql_fieldtable** (int query_identifier, int field) \linebreak

Returns the name of the table *field* was fetched from.

mysql_fieldtype (PHP 3, PHP 4 >= 4.0.0)

Get field type

string **mysql_fieldtype** (int query_identifier, int i) \linebreak

mysql_fieldtype() is similar to the `mysql_fieldname()` function. The arguments are identical, but the field type is returned. This will be one of "int", "char" or "real".

mysql_free_result (PHP 3, PHP 4 >= 4.0.0)

Free result memory

int **mysql_free_result** (int query_identifier) \linebreak

mysql_free_result() frees the memory associated with *query_identifier*. When PHP completes a request, this memory is freed automatically, so you only need to call this function when you want to make sure you don't use too much memory while the script is running.

mysql_freeresult (PHP 3, PHP 4 >= 4.0.0)

Free result memory

See `mysql_free_result()`

mysql_list_dbs (PHP 3, PHP 4 >= 4.0.0)

List mSQL databases on server

int **mysql_list_dbs** (void) \linebreak

mysql_list_dbs() will return a result pointer containing the databases available from the current msql daemon. Use the **mysql_dbname()** function to traverse this result pointer.

mysql_list_fields (PHP 3, PHP 4 >= 4.0.0)

List result fields

int **mysql_list_fields** (string database, string tablename) \linebreak

mysql_list_fields() retrieves information about the given tablename. Arguments are the database name and the table name. A result pointer is returned which can be used with **mysql_fieldflags()**, **mysql_fieldlen()**, **mysql_fieldname()**, and **mysql_fieldtype()**. A query identifier is a positive integer. The function returns -1 if a error occurs. A string describing the error will be placed in `$phperrormsg`, and unless the function was called as `@mysql_list_fields()` then this error string will also be printed out.

See also **mysql_error()**.

mysql_list_tables (PHP 3, PHP 4 >= 4.0.0)

List tables in an mSQL database

int **mysql_list_tables** (string database) \linebreak

mysql_list_tables() takes a database name and result pointer much like the **mysql()** function. The **mysql_tablename()** function should be used to extract the actual table names from the result pointer.

mysql_listdbs (PHP 3, PHP 4 >= 4.0.0)

List mSQL databases on server

See **mysql_list_dbs()**.

mysql_listfields (PHP 3, PHP 4 >= 4.0.0)

List result fields

See **mysql_list_fields()**.

mysql_listtables (PHP 3, PHP 4 >= 4.0.0)

List tables in an mSQL database

See `mysql_list_tables()`.

mysql_num_fields (PHP 3, PHP 4 >= 4.0.0)

Get number of fields in result

int **mysql_num_fields** (int query_identifier) \linebreak

mysql_num_fields() returns the number of fields in a result set.

See also: `mysql()`, `mysql_query()`, `mysql_fetch_field()`, and `mysql_num_rows()`.

mysql_num_rows (PHP 3, PHP 4 >= 4.0.0)

Get number of rows in result

int **mysql_num_rows** (int query_identifier) \linebreak

mysql_num_rows() returns the number of rows in a result set.

See also: `mysql()`, `mysql_query()`, and `mysql_fetch_row()`.

mysql_numfields (PHP 3, PHP 4 >= 4.0.0)

Get number of fields in result

int **mysql_numfields** (int query_identifier) \linebreak

Identical to `mysql_num_fields()`.

mysql_numrows (PHP 3, PHP 4 >= 4.0.0)

Get number of rows in result

int **mysql_numrows** (void) \linebreak

Identical to `mysql_num_rows()`.

mysql_pconnect (PHP 3, PHP 4 >= 4.0.0)

Open persistent mSQL connection

```
int mysql_pconnect ( [string server [, string username [, string password]]]) \linebreak
```

Returns a positive mSQL persistent link identifier on success, or `FALSE` on error.

mysql_pconnect() acts very much like **mysql_connect()** with two major differences.

First, when connecting, the function would first try to find a (persistent) link that's already open with the same host. If one is found, an identifier for it will be returned instead of opening a new connection.

Second, the connection to the SQL server will not be closed when the execution of the script ends. Instead, the link will remain open for future use (**mysql_close()** will not close links established by **mysql_pconnect()**).

This type of links is therefore called 'persistent'.

mysql_query (PHP 3, PHP 4 >= 4.0.0)

Send mSQL query

```
int mysql_query ( string query, int link_identifier) \linebreak
```

mysql_query() sends a query to the currently active database on the server that's associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed. If no link is open, the function tries to establish a link as if **mysql_connect()** was called, and use it.

Returns a positive mSQL query identifier on success, or `FALSE` on error.

Příklad 1. mysql_query()

```
<?php
$link = mysql_connect("dbserver")
    or die("unable to connect to mysql server: ".mysql_error());
mysql_select_db("db", $link)
    or die("unable to select database 'db': ".mysql_error());

$result = mysql_query("SELECT * FROM table WHERE id=1", $link);
if (!$result) {
    die("query failed: ".mysql_error());
}

while ($row = mysql_fetch_array($result)) {
    echo $row["id"];
}
?>
```

See also: **mysql()**, **mysql_select_db()**, and **mysql_connect()**.

mysql_regcase (PHP 3, PHP 4 >= 4.0.0)

Make regular expression for case insensitive match

See sql_regcase().

mysql_result (PHP 3, PHP 4 >= 4.0.0)

Get result data

```
int mysql_result ( int query_identifier, int i, mixed field) \linebreak
```

Returns the contents of the cell at the row and offset in the specified mSQL result set.

mysql_result() returns the contents of one cell from a mSQL result set. The field argument can be the field's offset, or the field's name, or the field's table dot field's name (fieldname.tablename). If the column name has been aliased ('select foo as bar from ...'), use the alias instead of the column name.

When working on large result sets, you should consider using one of the functions that fetch an entire row (specified below). As these functions return the contents of multiple cells in one function call, they're MUCH quicker than **mysql_result()**. Also, note that specifying a numeric offset for the field argument is much quicker than specifying a fieldname or tablename.fieldname argument.

Recommended high-performance alternatives: **mysql_fetch_row()**, **mysql_fetch_array()**, and **mysql_fetch_object()**.

mysql_select_db (PHP 3, PHP 4 >= 4.0.0)

Select mSQL database

```
int mysql_select_db ( string database_name, int link_identifier) \linebreak
```

Returns **TRUE** on success, **FALSE** on error.

mysql_select_db() sets the current active database on the server that's associated with the specified link identifier. If no link identifier is specified, the last opened link is assumed. If no link is open, the function will try to establish a link as if **mysql_connect()** was called, and use it.

Every subsequent call to **mysql_query()** will be made on the active database.

See also: **mysql_connect()**, **mysql_pconnect()**, and **mysql_query()**.

mysql_selectdb (PHP 3, PHP 4 >= 4.0.0)

Select mSQL database

See mysql_select_db().

mysql_tablename (PHP 3, PHP 4 >= 4.0.0)

Get table name of field

string **mysql_tablename** (int query_identifier, int field) \linebreak

mysql_tablename() takes a result pointer returned by the `mysql_list_tables()` function as well as an integer index and returns the name of a table. The `mysql_numrows()` function may be used to determine the number of tables in the result pointer.

Příklad 1. mysql_tablename() example

```
<?php
mysql_connect ("localhost");
$result = mysql_list_tables ("wisconsin");
$i = 0;
while ($i < mysql_numrows ($result)) {
    $tb_names[$i] = mysql_tablename ($result, $i);
    echo $tb_names[$i] . "<BR>";
    $i++;
}
?>
```

LXII. MySQL Funkce

Tyto funkce zprostředkovávají přístup na MySQL databázový server. Mají-li být tyto funkce dostupné, musí být PHP zkompileováno s podporou MySQL parametrem `--with-mysql`. Pokud použijete tento parametr bez zadané cesty k MySQL, PHP použije vestavěné MySQL klient knihovny. Uživatelé, kteří spouští další aplikace používající MySQL (např.: spuštěné PHP3 a PHP4 jako vzájemné moduly v apache či auth-mysql) by měli vždy zadat cestu k MySQL: `--with-mysql=/cesta/k/mysql`. PHP tak použije klientské knihovny instalované MySQL, čímž se vyvarujete možných konfliktů.

Více informací o MySQL naleznete na <http://www.mysql.com/>.

Dokumentace k MySQL je na <http://www.mysql.com/documentation/>.

Chování funkcí MySQL je ovlivněno nastavením v globálním konfiguračním souboru.

Tabulka 1. Konfigurace MySQL Volby

Jméno	Výchozí	Změnitelné
mysql.allow_persistent	"On"	PHP_INI_SYSTEM
mysql.max_persistent	"-1"	PHP_INI_SYSTEM
mysql.max_links	"-1"	PHP_INI_SYSTEM
mysql.default_port	NULL	PHP_INI_ALL
mysql.default_socket	NULL	PHP_INI_ALL
mysql.default_host	NULL	PHP_INI_ALL
mysql.default_user	NULL	PHP_INI_ALL

Podrobný popis a definice konstant `PHP_INI_*` naleznete v `ini_set()`.

Toto je jednoduchý ukázkový příklad jak se připojit, provést dotaz, zobrazit výsledné řádky a odpojit se z MySQL databáze.

Příklad 1. MySQL extension overview example

```
<?php
// Připojení, výběr databáze
$link = mysql_connect("mysql_host", "mysql_login", "mysql_heslo")
    or die("Nelze se připojit");
print "Connected successfully";
mysql_select_db("moje_databaze")
    or die("Nelze vybrat databázi");

// Příprava SQL dotazu
$query = "SELECT * FROM moje_tabulka";
$result = mysql_query($query)
    or die("Dotaz nelze provést");

// Zobrazení výsledku v HTML
print "<table>\n";
while ($line = mysql_fetch_array($result, MYSQL_ASSOC)) {
    print "\t<tr>\n";
    foreach ($line as $col_value) {
        print "\t\t<td>$col_value</td>\n";
    }
}
```

```
        print "\t</tr>\n";  
    }  
    print "</table>\n";  
  
    // Odpojení z MySQL databáze  
    mysql_close($link);  
?>
```

mysql_affected_rows (PHP 3, PHP 4 >= 4.0.0)

Vrátí počet ovlivněných (změněných) záznamů v MySQL po posledním dotazu

```
int mysql_affected_rows ( [resource spojeni] ) \linebreak
```

mysql_affected_rows() vrátí počet záznamů ovlivněných posledním použitím dotazu INSERT, UPDATE nebo DELETE, kterému odpovídá *spojení*. Není-li identifikátor spojení uveden, použije se poslední spojení otevřené pomocí mysql_connect().

Poznámka: Používáte-li transakce, je nutné **mysql_affected_rows()** volat až po dotazu INSERT, UPDATE nebo DELETE, nikoli hned po potvrzení transakce.

Byl-li poslední dotaz DELETE bez části WHERE, budou smázány všechny záznamy z tabulky, ale tato funkce vrátí nulu.

Poznámka: Při použití UPDATE, MySQL neuloží sloupce, ve kterých je nová hodnota shodná s původní. Toto může způsobit, že **mysql_affected_rows()** nemusí vždy přesně souhlasit se skutečným počtem ovlivněných řádků.

mysql_affected_rows() nelze použít s dotazy SELECT, ale jen s takovými, které mění záznamy. K zjištění počtu řádků vrácených dotazem SELECT použijte funkci mysql_num_rows().

Je-li poslední dotaz chybný, funkce vrátí -1.

Viz. také: mysql_num_rows().

mysql_change_user (PHP 3 >= 3.0.13)

Změní přihlášeného uživatele v současném spojení

```
int mysql_change_user ( string uzivatel, string heslo [, string databaze [, resource spojeni]] ) \linebreak
```

mysql_change_user() změní přihlášeného uživatele současného aktivního spojení nebo spojení definované nepovinným parametrem *spojení*. Je-li uveden parameter *databaze* nastaví se tato databáze jako výchozí, v opačném případě zůstane aktivní současná databáze definovaná ve změněném spojení.

Poznámka: Tato funkce byla přidána v PHP 3.0.13 a vyžaduje použití MySQL 3.23.3 nebo vyšší.

mysql_close (PHP 3, PHP 4 >= 4.0.0)

Ukončí (zavře) MySQL spojení

```
bool mysql_close ( [resource spojeni] ) \linebreak
```

Vrací TRUE při úspěchu, FALSE při selhání.

mysql_close() uzavře spojení s MySQL serverem, které je asociováno se určitým identifikátorem spojení. Pokud *spojení* není zadán uzavře poslední otevřené spojení.

Použití **mysql_close()** není obvykle nutné, protože nepersistentní (netrvalá) otevřená spojení jsou zavřena automaticky po zpracování skriptu. Dále viz. freeing resources.

Poznámka: **mysql_close()** neuzavře persistentní spojení otevřené pomocí **mysql_pconnect()**.

Příklad 1. Příklad k MySQL close

```
<?php
$link = mysql_connect("kraemer", "marliesle", "tajne")
    or exit("Nelze se připojit");
print ("Spojení navázáno");
mysql_close($link);
?>
```

Viz. také: **mysql_connect()**, a **mysql_pconnect()**.

mysql_connect (PHP 3, PHP 4 >= 4.0.0)

Vytvoří spojení s MySQL Serverem

resource **mysql_connect** ([string server [, string uživ_jmeno [, string heslo]]]) \linebreak

Je-li spojení úspěšné vrátí identifikátor spojení v opačném případě ???

mysql_connect() vytvoří spojení s MySQL serverem. Nejsou-li zádány nepovinné parametry, použijí se následující hodnoty: *server* = 'localhost:3306', *uživ_jmeno* = jméno uživatele, pod kterým běží právě spuštěný skript a *heslo* = bez hesla.

Parametr *server* může obsahovat číslo portu ve tvaru "hostname:port" nebo cestu k socketu ve tvaru ":/cesta/k/socketu" pro localhost.

Poznámka: Podpora pro "port" byla přidána v PHP 3.0B4.

Podpora pro ":/cesta/k/socketu" byla přidána v PHP 3.0.10.

Chybovou hlášku lze potlačit přidáním '@' před jméno funkce.

Bude-li funkce **mysql_connect()** zavolána podruhé se stejnými parametry, nebude vytvořeno nové spojení, ale použije se stávající se stejným identifikátorem spojení.

Spojení se serverem bude ukončeno automaticky po skončení běhu skriptu nebude-li dříve zavolána funkce **mysql_close()**.

Příklad 1. MySQL příklad spojení

```
<?php
    $link = mysql_connect("localhost", "uziv_jmeno", "tajne")
        or die("Nelze se připojit");
    print ("Spojení navázáno");
    mysql_close($link);
?>
```

Viz. také `mysql_pconnect()` a `mysql_close()`.

mysql_create_db (PHP 3, PHP 4 >= 4.0.0)

Vytvoří MySQL databázi

bool **mysql_create_db** (string jméno databáze [, resource spojeni]) \linebreak

mysql_create_db() vytvoří na serveru identifikovaném parametrem spojeni novou databázi.

Vrací TRUE při úspěchu, FALSE při selhání.

Příklad 1. MySQL příklad vytvoření nové databáze

```
<?php
    $link = mysql_pconnect("kron", "jutta", "geheim")
        or exit("Nelze se připojit");
    if (mysql_create_db("moje_db")) {
        print ("Databáze byla vytvořena\n");
    } else {
        printf ("Chyba při vytváření databáze: %s\n", mysql_error ());
    }
?>
```

Kvůli zpětné kompatibilitě je možné použít i **mysql_createdb()**. Není to však doporučeno.

Viz. také: `mysql_drop_db()`.

mysql_data_seek (PHP 3, PHP 4 >= 4.0.0)

Přesune ukazatel na aktuální záznam

bool **mysql_data_seek** (zdroj result_idenfier, int row_number) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

mysql_data_seek() přesune interní ukazatel výsledku MySQL na záznam specifikovaný číslem záznamu. Následné volání funkce `mysql_fetch_row()` načte požadovaný záznam.

Není-li zadáno *cislo_zaznamu* začíná se od 0.

Příklad 1. MySQL příklad přesunutí ukazatele

```
<?php
$link = mysql_pconnect("kron", "jutta", "geheim")
    or die("Nelze se připojit");

mysql_select_db("samp_db")
    or exit("Nelze vybrat databázi");

$query = "SELECT last_name, first_name FROM friends";
$result = mysql_query($query)
    or die("Chyba dotazu");

// načtení záznamů v obráceném pořadí

for ($i = mysql_num_rows($result) - 1; $i >= 0; $i--) {
    if (!mysql_data_seek($result, $i)) {
        echo "Nelze nalézt záznam $i\n";
        continue;
    }

    if (!($row = mysql_fetch_object($result)))
        continue;

    echo "$row->last_name $row->first_name<br />\n";
}

mysql_free_result($result);
?>
```

mysql_db_name (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Vrátí seznam všech databází

string **mysql_db_name** (resource výsledek, int záznam [, mixed field]) \linebreak

První parametr funkce **mysql_db_name()** obsahuje identifikátor volání **mysql_list_dbs()**. Parametr *záznam* určuje pořadí databáze ve výsledku.

Nastane-li chyba vrací **FALSE**. Použitím **mysql_errno()** a **mysql_error()** zjistíte chybovou hlášku.

Příklad 1. mysql_db_name() příklad

```
<?php
error_reporting(E_ALL);

mysql_connect('dbhost', 'uziv_jmeno', 'heslo');
$db_list = mysql_list_dbs();
```

```

$i = 0;
$cnt = mysql_num_rows($db_list);
while ($i < $cnt) {
    echo mysql_db_name($db_list, $i) . "\n";
    $i++;
}
?>

```

Kvůli zpětné kompatibilitě lze použít i **mysql_dbname()**. Není to však doporučeno.

mysql_db_query (PHP 3, PHP 4 >= 4.0.0)

Provede MySQL dotaz

resource **mysql_db_query** (string databáze, string dotaz [, resource spojeni]) \linebreak

Vrátí identifikátor výsledku dotazu do určené databáze nebo **FALSE** nastane-li chyba

mysql_db_query() provede dotaz v databázi specifikované parametrem *database*. Není-li identifikátor databáze uveden, funkce se pokusí nalézt již otevřené spojení s MySQL serverem. Pokud není žádné aktivní spojení nalezeno, pokusí se vytvořit nové spojení s výchozími hodnotami funkce **mysql_connect()**

Viz. také **mysql_connect()** and **mysql_query()**.

Poznámka: Tato funkce není od verze PHP 4.0.6 podporována. Místo této funkce použijte **mysql_select_db()** a **mysql_query()**.

mysql_drop_db (PHP 3, PHP 4 >= 4.0.0)

Vymaže (odstraní) MySQL databázi

bool **mysql_drop_db** (string database_name [, resource spojeni]) \linebreak

Vrací **TRUE** při úspěchu, **FALSE** při selhání.

mysql_drop_db() odstraní ze serveru databázi uvedeného jména pod specifikovaným identifikátorem spojení.

Kvůli zpětné kompatibilitě se můžete setkat i s **mysql_dropdb()**. Nedoporučujeme však používat. Tento zápis nemusí být v příštích verzích PHP podporován.

Viz. také: **mysql_create_db()**.

mysql_errno (PHP 3, PHP 4 >= 4.0.0)

Vrátí číselnou hodnotu chybové hlášky předchozího MySQL příkazu.

int mysql_errno ([resource spojeni]) \linebreak

Vrátí číselnou hodnotu chybové hlášky vyvolané poslední MySQL funkcí nebo 0 (nulu), pokud nenastala žádná chyba.

Chyby vrácené MySQL již nezpůsobují upozorňující chybové hlášení (warning). Potřebujete-li zjistit číselný kód chyby, použijte **mysql_errno()**, případně **mysql_error()** k zjištění textu chyby. Pamatujte, že tato funkce vrací chybový kód pouze naposledy vykonané MySQL funkce (netýká se **mysql_error()** a **mysql_errno()**), pokud ji tedy budete používat, musíte kontrolovat hodnotu ještě před voláním další MySQL funkce.

```
<?php
mysql_connect("marliesle");
echo mysql_errno().": ".mysql_error()."<BR>";
mysql_select_db("neexistujicidb");
echo mysql_errno().": ".mysql_error()."<BR>";
$conn = mysql_query("SELECT * FROM neexistujicitabulka");
echo mysql_errno().": ".mysql_error()."<BR>";
?>
```

Viz. také: **mysql_error()**

mysql_error (PHP 3, PHP 4 >= 4.0.0)

Vrátí text chybové zprávy předchozího MySQL příkazu.

string mysql_error ([resource spojeni]) \linebreak

Vrátí text chybové zprávy posledního MySQL příkazu nebo " (prázdný řetězec) pokud žádná chyba nenastala.

Chyby vrácené MySQL již nezpůsobují upozorňující chybové hlášení (warning). Potřebujete-li zjistit text chyby, použijte **mysql_error()**, případně **mysql_errno()** k zjištění číselného kódu chyby. Pamatujte, že tato funkce vrací chybový kód pouze naposledy vykonané MySQL funkce (netýká se **mysql_error()** a **mysql_errno()**), pokud ji tedy budete používat, musíte kontrolovat hodnotu ještě před voláním další MySQL funkce.

```
<?php
mysql_connect("marliesle");
echo mysql_errno().": ".mysql_error()."<BR>";
mysql_select_db("neexistujicidb");
echo mysql_errno().": ".mysql_error()."<BR>";
$conn = mysql_query("SELECT * FROM neexistujicitab");
echo mysql_errno().": ".mysql_error()."<BR>";
?>
```

Viz. také: `mysql_erro()`

mysql_escape_string (PHP 4 >= 4.0.3)

Upraví řetězec pro použití v `mysql_query`.

string **mysql_escape_string** (string *neupraveny_retezec*) \linebreak

Tato funkce upraví *neupraveny_retezec* pro snadné použití v `mysql_query()`. Před funkční znaky jako " (uvozovky) či ' (apostrofy) jsou doplněna zpětná lomítka, konce řádků jsou nahrazeny značkou \n.

Poznámka: `mysql_escape_string()` nepřidává zpětná lomítka před znaky % a _.

mysql_fetch_array (PHP 3, PHP 4 >= 4.0.0)

Načte výsledný řádek do asociativního, číselného pole nebo obojího.

array **mysql_fetch_array** (resource výsledek [, int *result_type*]) \linebreak

Funkce vrací pole hodnot načteného řádku nebo FALSE, není-li žádný další řádek.

mysql_fetch_array() je rozšířenou verzí `mysql_fetch_row()`. Navíc zde jsou data uložena v poli nejen pod číselnými klíči, ale také pod asociativními textovými klíči jmenujícími se podle názvu sloupce sql tabulky.

Pokud dva nebo více sloupců mají stejný název, bude dostupná hodnota pouze toho posledního. Chcete-li přistupovat i k hodnotám ostatních sloupců, musíte k nim v sql dotazu vytvořit aliasy. Název klíče sloupce, k němuž je vytvořen alias, je vždy jméno aliasu a proto není možné použít originální jméno sloupce v sql tabulce (viz. 'sloupec' v následujícím příkladu).

```
select prvni_tab.sloupec as prvni_sloupec druha_tab.sloupec as druhy_sloupec
from prvni_tab, druha_tab
```

Důležité ovšem je, že použití **mysql_fetch_array()** *není nijak významně* pomalejší než použití `mysql_fetch_row()`, pokud je její použití přidanou hodnotou.

Nepovinný druhý parametr *result_type* v **mysql_fetch_array()** je konstanta, která může nabývat následujících hodnot: MYSQL_ASSOC, MYSQL_NUM, a MYSQL_BOTH. Tato vlastnost byla přidána v PHP 3.0.7. Výchozí hodnota je MYSQL_BOTH.

Použitím `MYSQL_BOTH` získáte pole s asociativními i číselnými klíči. Použitím `MYSQL_ASSOC` získáte pole pouze s asociativními klíči (stejně funguje `mysql_fetch_assoc()`) a použitím `MYSQL_NUM`, pole obsahovat pouze číselné klíče (tak funguje `mysql_fetch_row()`).

Pro další detaily viz. také `mysql_fetch_row()` a `mysql_fetch_assoc()`.

Příklad 1. `mysql_fetch_array()` příklad

```
<?php
mysql_connect($host, $user, $password);
mysql_select_db("databaze");
$result = mysql_query("select uziv_id, celejmeno from tabulka");
while ($row = mysql_fetch_array($result)) {
    echo "user_id: " . $row["uziv_id"] . "<br>\n";
    echo "user_id: " . $row[0] . "<br>\n";
    echo "fullname: " . $row["celejmeno"] . "<br>\n";
    echo "fullname: " . $row[1] . "<br>\n";
}
mysql_free_result($result);
?>
```

`mysql_fetch_assoc` (PHP 4 >= 4.0.3)

Načte výsledný řádek do asociativního pole

array **mysql_fetch_assoc** (resource výsledek) \linebreak

Funkce vrátí asociativní pole hodnot načteného řádku nebo `FALSE`, není-li žádný další řádek.

mysql_fetch_assoc() je ekvivalentem k `mysql_fetch_array()` s nepovinným druhým parametrem `MYSQL_ASSOC`, což vrátí pouze asociativní pole. Pokud potřebujete používat číselné indexy spolu s asociativními, použijte `mysql_fetch_array()`.

Pokud dva nebo více sloupců mají stejný název, bude dostupná hodnota pouze toho posledního. Chcete-li přistupovat i k hodnotám ostatních sloupců, musíte k nim v sql dotazu vytvořit aliasy. Název klíče sloupce, k němuž je vytvořen alias, je vždy jméno aliasu a proto není možné použít originální jméno sloupce v sql tabulce. Podívejte se na vysvětlení použití aliasů v příkladu u `mysql_fetch_array()`.

Důležité ovšem je, že použití **mysql_fetch_assoc()** *není nijak významně* pomalejší než použití `mysql_fetch_row()`, pokud je její použití přidanou hodnotou.

Pro další detaily viz. také `mysql_fetch_row()` a `mysql_fetch_array()`.

Příklad 1. `mysql_fetch_assoc()`

```
<?php
mysql_connect($host, $user, $password);
mysql_select_db($databaze);
$query = "select * from tabulka";
$result = mysql_query($query);
```

```

while ($row = mysql_fetch_assoc($result)) {
    echo $row["uziv_id"];
    echo $row["celejmeno"];
}
mysql_free_result($result);
?>

```

mysql_fetch_field (PHP 3, PHP 4 >= 4.0.0)

Načte informace o sloupci z výsledku do proměnné objektu

object **mysql_fetch_field** (resource výsledek [, int field_offset]) \linebreak

Vrátí objekt obsahující informace o sloupci z výsledku.

mysql_fetch_field() může použít v případě, že potřebujete získat informace o sloupci z určitého výsledku. Není-li specifikován název sloupce, funkce načte informace o prvním následujícím ještě nenačteném sloupci.

Vlastnosti objektu jsou:

- name - název sloupce
- table - název tabulky, v níž se tento sloupec nachází
- max_length - maximální délka sloupce ve znacích
- not_null - 1 pokud sloupec nemůže být NULL
- primary_key - 1 pokud je sloupec primární klíč
- unique_key - 1 pokud je sloupec unikátní klíč
- multiple_key - 1 pokud je sloupec neunikátní klíč
- numeric - 1 pokud je sloupec číslo
- blob - 1 pokud je sloupec BLOB
- type - typ sloupce
- unsigned - 1 pokud je sloupec bez znaménka
- zerofill - 1 pokud je sloupec doplněn nulami na svou velikost

Příklad 1. mysql_fetch_field()

```

<?php
mysql_connect('localhost:3306', $user, $password)
    or die ("Nelze se připojit");
mysql_select_db("databaze");
$result = mysql_query("select * from tabulka")
    or die("Chyba dotazu");
# vrátí informace o sloupci
$i = 0;

```

```

while ($i < mysql_num_fields($result)) {
    echo "Informace pro sloupec $i:<BR>\n";
    $meta = mysql_fetch_field($result);
    if (!$meta) {
        echo "Nejsou dostupné žádné informace<BR>\n";
    }
    echo "<PRE>
blob:          $meta->blob
max_length:    $meta->max_length
multiple_key:  $meta->multiple_key
name:          $meta->name
not_null:      $meta->not_null
numeric:       $meta->numeric
primary_key:   $meta->primary_key
table:         $meta->table
type:          $meta->type
unique_key:    $meta->unique_key
unsigned:      $meta->unsigned
zerofill:      $meta->zerofill
</PRE>";
    $i++;
}
mysql_free_result($result);
?>

```

Viz. také `mysql_field_seek()`.

mysql_fetch_lengths (PHP 3, PHP 4 >= 4.0.0)

Zjistí délku všech položek aktuálního výstupu

array **mysql_fetch_lengths** (resource výsledek) \linebreak

Vrátí pole obsahující délku každého sloupce v posledně načteném záznamu pomocí `mysql_fetch_row()`, nebo `FALSE` dojde-li k chybě.

mysql_fetch_lengths() obahuje délky hodnot všech vrácených sloupců posledního načteného záznamu pomocí `mysql_fetch_row()`, `mysql_fetch_array()`, a `mysql_fetch_object()` v poli, začínajícího klíčem 0.

Viz. také: `mysql_fetch_row()`.

mysql_fetch_object (PHP 3, PHP 4 >= 4.0.0)

Načte výsledný řádek do proměnné objektu

object **mysql_fetch_object** (resource výsledek [, int result_type]) \linebreak

Vrátí objekt, jehož proměnné obsahují hodnoty načteného záznamu nebo `FALSE` není-li žádný další záznam.

mysql_fetch_object() je obdobou **mysql_fetch_array()**, s jedním rozdílem - narozdíl od pole, je vrácen objekt. Což znamená, že k hodnotám výsledku lze přistupovat pouze přes názvy sloupců a nikoli přes jejich číselné klíče (název vlastnosti nemůže být číslo).

Nepovinný parametr *result_type* je konstanta, která může nabývat následujících hodnot: **MYSQL_ASSOC**, **MYSQL_NUM**, a **MYSQL_BOTH**. Výsvětlení těchto konstant naleznete v **mysql_fetch_array()**.

Rychlostně je tato funkce identická s **mysql_fetch_array()**, a téměř tak rychlá jako **mysql_fetch_row()** (rozdíl je nevýznamný).

Příklad 1. **mysql_fetch_object()** příklad

```
<?php
mysql_connect("hostname", "user", "password");
mysql_select_db($db);
$result = mysql_query("select * from tabulka");
while ($row = mysql_fetch_object($result)) {
    echo $row->uziv_id;
    echo $row->celejmeno;
}
mysql_free_result($result);
?>
```

Viz. také: **mysql_fetch_array()** a **mysql_fetch_row()**.

mysql_fetch_row (PHP 3, PHP 4 >= 4.0.0)

Načte výsledný řádek do pole

array **mysql_fetch_row** (resource výsledek) \linebreak

Funkce vrací číselné pole hodnot načteného řádku nebo **FALSE**, není-li žádný další řádek.

mysql_fetch_row() načte jeden záznam výsledku do pole s číselnými klíči. Každá hodnota sloupce je samostatná hodnota pole; klíče jsou číslovány od 0.

Další volání **mysql_fetch_row()** vrátí následující záznam výsledku, nebo **FALSE** není-li žádný další záznam.

Viz. také: **mysql_fetch_array()**, **mysql_fetch_object()**, **mysql_data_seek()**, **mysql_fetch_lengths()**, a **mysql_result()**.

mysql_field_flags (PHP 3, PHP 4 >= 4.0.0)

Načte doplňující informace o položce

string **mysql_field_flags** (resource výsledek, int field_offset) \linebreak

mysql_field_flags() returns the field flags of the specified field. The flags are reported as a single word per flag separated by a single space, so that you can split the returned value using `explode()`.

The following flags are reported, if your version of MySQL is current enough to support them: "not_null", "primary_key", "unique_key", "multiple_key", "blob", "unsigned", "zerofill", "binary", "enum", "auto_increment", "timestamp".

For downward compatibility **mysql_fieldflags()** can also be used. This is deprecated, however.

mysql_field_len (PHP 3, PHP 4 >= 4.0.0)

Vrátí délku položky

```
int mysql_field_len ( resource výsledek, int field_offset ) \linebreak
```

mysql_field_len() returns the length of the specified field.

For downward compatibility **mysql_fieldlen()** can also be used. This is deprecated, however.

mysql_field_name (PHP 3, PHP 4 >= 4.0.0)

Načte název položky

```
string mysql_field_name ( resource výsledek, int field_index ) \linebreak
```

mysql_field_name() returns the name of the specified field index. *výsledek* must be a valid result identifier and *field_index* is the numerical offset of the field.

Poznámka: *field_index* starts at 0.

e.g. The index of the third field would actually be 2, the index of the fourth field would be 3 and so on.

Příklad 1. mysql_field_name() example

```
// The users table consists of three fields:
//   user_id
//   username
//   password.
$link = mysql_connect('localhost', $user, "secret");
mysql_select_db($dbname, $link)
    or die("Could not set $dbname");
$res = mysql_query("select * from users", $link);

echo mysql_field_name($res, 0) . "\n";
echo mysql_field_name($res, 2);
```

The above example would produce the following output:

```
user_id
password
```

For downwards compatibility **mysql_fieldname()** can also be used. This is deprecated, however.

mysql_field_seek (PHP 3, PHP 4 >= 4.0.0)

Nastaví ukazatel na zadaný záznam

```
int mysql_field_seek ( resource výsledek, int field_offset) \linebreak
```

Seeks to the specified field offset. If the next call to **mysql_fetch_field()** doesn't include a field offset, the field offset specified in **mysql_field_seek()** will be returned.

Viz. také: **mysql_fetch_field()**.

mysql_field_table (PHP 3, PHP 4 >= 4.0.0)

Zjistí jméno tabulky, z níž je zadaná položka

```
string mysql_field_table ( resource výsledek, int field_offset) \linebreak
```

Returns the name of the table that the specified field is in.

For downward compatibility **mysql_fieldtable()** can also be used. This is deprecated, however.

mysql_field_type (PHP 3, PHP 4 >= 4.0.0)

Zjistí typ položky výsledku

```
string mysql_field_type ( resource výsledek, int field_offset) \linebreak
```

mysql_field_type() is similar to the **mysql_field_name()** function. The arguments are identical, but the field type is returned instead. The field type will be one of "int", "real", "string", "blob", and others as detailed in the MySQL documentation (<http://www.mysql.com/documentation/>).

Příklad 1. MySQL field types

```
<?php

mysql_connect( "localhost:3306" );
mysql_select_db( "wisconsin" );
$result = mysql_query( "SELECT * FROM onek" );
```

```

$fields = mysql_num_fields($result);
$rows   = mysql_num_rows($result);
$i = 0;
$table = mysql_field_table($result, $i);
echo "Your '". $table. "' table has ".$fields." fields and ".$rows." records
<BR>";
echo "The table has the following fields <BR>";
while ($i < $fields) {
    $type = mysql_field_type($result, $i);
    $name = mysql_field_name($result, $i);
    $len  = mysql_field_len($result, $i);
    $flags = mysql_field_flags($result, $i);
    echo $type." " ".$name." " ".$len." " ".$flags."<BR>";
    $i++;
}
mysql_close();

?>

```

For downward compatibility **mysql_fieldtype()** can also be used. This is deprecated, however.

mysql_free_result (PHP 3, PHP 4 >= 4.0.0)

Uvolní výsledek z paměti

bool **mysql_free_result** (resource výsledek) \linebreak

mysql_free_result() will free all memory associated with the result identifier *výsledek*.

mysql_free_result() only needs to be called if you are concerned about how much memory is being used for queries that return large result sets. All associated result memory is automatically freed at the end of the script's execution.

Vrací TRUE při úspěchu, FALSE při selhání.

For downward compatibility **mysql_freeresult()** can also be used. This is deprecated, however.

mysql_get_client_info (PHP 4 >= 4.0.5)

Načte MySQL klient info

string **mysql_get_client_info** (void) \linebreak

mysql_get_client_info() returns a string that represents the client library version.

mysql_get_client_info() was added in PHP 4.0.5.

mysql_get_host_info (PHP 4 >= 4.0.5)

Načte MySQL host info

```
string mysql_get_host_info ( [resource spojeni] ) \linebreak
```

mysql_get_host_info() returns a string describing the type of connection in use for the connection *spojeni*, including the server host name. If *spojeni* is omitted, the last opened connection will be used.

mysql_get_host_info() was added in PHP 4.0.5.

mysql_get_proto_info (PHP 4 >= 4.0.5)

Načte MySQL protokol info

```
int mysql_get_proto_info ( [resource spojeni] ) \linebreak
```

mysql_get_proto_info() returns the protocol version used by connection *spojeni*. If *spojeni* is omitted, the last opened connection will be used.

mysql_get_proto_info() was added in PHP 4.0.5.

mysql_get_server_info (PHP 4 >= 4.0.5)

Načte MySQL server info

```
int mysql_get_server_info ( [resource spojeni] ) \linebreak
```

mysql_get_server_info() returns the server version used by connection *spojeni*. If *spojeni* is omitted, the last opened connection will be used.

mysql_get_server_info() was added in PHP 4.0.5.

mysql_insert_id (PHP 3, PHP 4 >= 4.0.0)

Vrátí hodnotu id posledního příkazu INSERT

```
int mysql_insert_id ( [resource spojeni] ) \linebreak
```

mysql_insert_id() returns the ID generated for an AUTO_INCREMENT column by the previous INSERT query using the given *spojeni*. If *spojeni* isn't specified, the last opened link is assumed.

mysql_insert_id() returns 0 if the previous query does not generate an AUTO_INCREMENT value. If you need to save the value for later, be sure to call **mysql_insert_id()** immediately after the query that generates the value.

Poznámka: The value of the MySQL SQL function `LAST_INSERT_ID()` always contains the most recently generated AUTO_INCREMENT value, and is not reset between queries.

Varování

mysql_insert_id() converts the return type of the native MySQL C API function `mysql_insert_id()` to a type of `long` (named `int` in PHP). If your `AUTO_INCREMENT` column has a column type of `BIGINT`, the value returned by **mysql_insert_id()** will be incorrect. Instead, use the internal MySQL SQL function `LAST_INSERT_ID()` in an SQL query.

mysql_list_dbs (PHP 3, PHP 4 >= 4.0.0)

Načte všechny databáze dostupné na MySQL serveru

resource **mysql_list_dbs** ([resource spojení]) \linebreak

mysql_list_dbs() will return a result pointer containing the databases available from the current mysql daemon. Use the `mysql_tablename()` function to traverse this result pointer, or any function for result tables.

Příklad 1. mysql_list_dbs() example

```
<?php
$link = mysql_connect('localhost', 'myname', 'secret');
$db_list = mysql_list_dbs($link);

while ($row = mysql_fetch_object($db_list)) {
    echo $row->Database . "\n";
}
?>
```

The above example would produce the following output:

```
database1
database2
database3
...
```

Poznámka: The above code would just as easily work with `mysql_fetch_row()` or other similar functions.

For downward compatibility **mysql_listdbs()** can also be used. This is deprecated however.

Viz. také `mysql_db_name()`.

mysql_list_fields (PHP 3, PHP 4 >= 4.0.0)

Načte výsledek s obsahem položky

resource **mysql_list_fields** (string jmeno_database, string table_name [, resource spojeni]) \linebreak

mysql_list_fields() retrieves information about the given tablename. Arguments are the database name and the table name. A result pointer is returned which can be used with `mysql_field_flags()`, `mysql_field_len()`, `mysql_field_name()`, and `mysql_field_type()`.

Příklad 1. mysql_list_fields() example

```
<?php
$link = mysql_connect('localhost', 'myname', 'secret');

$fields = mysql_list_fields("database1", "table1", $link);
$num_columns = mysql_num_fields($fields);

for ($i = 0; $i < $num_columns; $i++) {
    echo mysql_field_name($fields, $i) . "\n";
}
```

The above example would produce the following output:

```
field1
field2
field3
...
```

For downward compatibility **mysql_listfields()** can also be used. This is deprecated however.

mysql_list_tables (PHP 3, PHP 4 >= 4.0.0)

Načte všechny tabulky v MySQL databázi

resource **mysql_list_tables** (string database [, resource spojeni]) \linebreak

mysql_list_tables() takes a database name and returns a result pointer much like the `mysql_db_query()` function. You can use the `mysql_tablename()` function to extract the actual table names from the result pointer, or any other result table function.

For downward compatibility **mysql_listtables()** can also be used. This is deprecated however.

mysql_num_fields (PHP 3, PHP 4 >= 4.0.0)

Vrátí počet položek ve výsledku

```
int mysql_num_fields ( resource výsledek ) \linebreak
```

mysql_num_fields() returns the number of fields in a result set.

Viz. také: `mysql_db_query()`, `mysql_query()`, `mysql_fetch_field()`, `mysql_num_rows()`.

For downward compatibility **mysql_numfields()** can also be used. This is deprecated however.

mysql_num_rows (PHP 3, PHP 4 >= 4.0.0)

Vrátí počet záznamů ve výsledku

```
int mysql_num_rows ( resource výsledek ) \linebreak
```

mysql_num_rows() returns the number of rows in a result set. This command is only valid for SELECT statements. To retrieve the number of rows affected by a INSERT, UPDATE or DELETE query, use `mysql_affected_rows()`.

Příklad 1. mysql_num_rows() example

```
<?php

$link = mysql_connect("localhost", "username", "password");
mysql_select_db("database", $link);

$result = mysql_query("SELECT * FROM table1", $link);
$num_rows = mysql_num_rows($result);

echo "$num_rows Rows\n";

?>
```

Viz. také: `mysql_affected_rows()`, `mysql_connect()`, `mysql_select_db()`, and `mysql_query()`.

For downward compatibility **mysql_numrows()** can also be used. This is deprecated however.

mysql_pconnect (PHP 3, PHP 4 >= 4.0.0)

Otevře persistentní spojení s MySQL serverem

```
resource mysql_pconnect ( [string server [, string username [, string password]]]) \linebreak
```

Returns a positive MySQL persistent link identifier on success, or FALSE on error.

mysql_pconnect() establishes a connection to a MySQL server. The following defaults are assumed for missing optional parameters: *server* = 'localhost:3306', *username* = name of the user that owns the server process and *password* = empty password.

The *server* parameter can also include a port number. eg. "hostname:port" or a path to a socket eg. ":/path/to/socket" for the localhost.

Poznámka: Support for "port" was added in 3.0B4.

Support for the ":/path/to/socket" was added in 3.0.10.

mysql_pconnect() acts very much like **mysql_connect()** with two major differences.

First, when connecting, the function would first try to find a (persistent) link that's already open with the same host, username and password. If one is found, an identifier for it will be returned instead of opening a new connection.

Second, the connection to the SQL server will not be closed when the execution of the script ends. Instead, the link will remain open for future use (**mysql_close()** will not close links established by **mysql_pconnect()**).

This type of link is therefore called 'persistent'.

Poznámka: Note, that these kind of links only work if you are using a module version of PHP. See the Persistent Database Connections section for more information.

Varování

Using persistent connections can require a bit of tuning of your Apache and MySQL configurations to ensure that you do not exceed the number of connections allowed by MySQL.

mysql_query (PHP 3, PHP 4 >= 4.0.0)

Pošle MySQL dotaz

resource **mysql_query** (string query [, resource spojeni]) \linebreak

mysql_query() sends a query to the currently active database on the server that's associated with the specified link identifier. If *spojeni* isn't specified, the last opened link is assumed. If no link is open, the function tries to establish a link as if **mysql_connect()** was called with no arguments, and use it.

Poznámka: The query string should not end with a semicolon.

Only for SELECT statements **mysql_query()** returns a resource identifier or **FALSE** if the query was not executed correctly. For other type of SQL statements, **mysql_query()** returns **TRUE** on success and **FALSE** on error. A non-**FALSE** return value means that the query was legal and could be executed

by the server. It does not indicate anything about the number of rows affected or returned. It is perfectly possible for a query to succeed but affect no rows or return no rows.

The following query is syntactically invalid, so **mysql_query()** fails and returns **FALSE**:

Příklad 1. **mysql_query()**

```
<php
$result = mysql_query("SELECT * WHERE 1=1")
    or die("Invalid query");
?>
```

The following query is semantically invalid if **my_col** is not a column in the table **my_tbl**, so **mysql_query()** fails and returns **FALSE**:

Příklad 2. **mysql_query()**

```
<?php
$result = mysql_query("SELECT my_col FROM my_tbl")
    or exit ("Invalid query");
?>
```

mysql_query() will also fail and return **FALSE** if you don't have permission to access the table(s) referenced by the query.

Assuming the query succeeds, you can call **mysql_num_rows()** to find out how many rows were returned for a **SELECT** statement or **mysql_affected_rows()** to find out how many rows were affected by a **DELETE**, **INSERT**, **REPLACE**, or **UPDATE** statement.

Only for **SELECT** statements, **mysql_query()** returns a new result identifier that you can pass to **mysql_fetch_array()** and other functions dealing with result tables. When you are done with the result set, you can free the resources associated with it by calling **mysql_free_result()**. Although, the memory will automatically be freed at the end of the script's execution.

Viz. také: **mysql_num_rows()**, **mysql_affected_rows()**, **mysql_unbuffered_query()**, **mysql_free_result()**, **mysql_fetch_array()**, **mysql_fetch_row()**, **mysql_fetch_assoc()**, **mysql_result()**, **mysql_select_db()**, and **mysql_connect()**.

mysql_result (PHP 3, PHP 4 >= 4.0.0)

Načte výslednou hodnotu jedné položky

mixed **mysql_result** (resource výsledek, int záznam [, mixed field]) \linebreak

mysql_result() returns the contents of one cell from a MySQL result set. The field argument can be the field's offset, or the field's name, or the field's table dot field name (tablename.fieldname). If the column name has been aliased ('select foo as bar from...'), use the alias instead of the column name.

When working on large result sets, you should consider using one of the functions that fetch an entire row (specified below). As these functions return the contents of multiple cells in one function call, they're MUCH quicker than **mysql_result()**. Also, note that specifying a numeric offset for the field argument is much quicker than specifying a fieldname or tablename.fieldname argument.

Calls to **mysql_result()** should not be mixed with calls to other functions that deal with the result set.

Recommended high-performance alternatives: **mysql_fetch_row()**, **mysql_fetch_array()**, and **mysql_fetch_object()**.

mysql_select_db (PHP 3, PHP 4 >= 4.0.0)

Vybere MySQL databázi

bool **mysql_select_db** (string jmeno_databaze [, resource spojeni]) \linebreak

Vrací TRUE při úspěchu, FALSE při selhání.

mysql_select_db() sets the current active database on the server that's associated with the specified link identifier. If no link identifier is specified, the last opened link is assumed. If no link is open, the function will try to establish a link as if **mysql_connect()** was called without arguments, and use it.

Every subsequent call to **mysql_query()** will be made on the active database.

Viz. také: **mysql_connect()**, **mysql_pconnect()**, and **mysql_query()**.

For downward compatibility **mysql_selectdb()** can also be used. This is deprecated however.

mysql_tablename (PHP 3, PHP 4 >= 4.0.0)

Načte jméno tabulky

string **mysql_tablename** (resource výsledek, int i) \linebreak

mysql_tablename() takes a result pointer returned by the **mysql_list_tables()** function as well as an integer index and returns the name of a table. The **mysql_num_rows()** function may be used to determine the number of tables in the result pointer.

Příklad 1. mysql_tablename() Example

```
<?php
mysql_connect("host");
$result = mysql_list_tables("wisconsin");
for ($i = 0; $i < mysql_num_rows($result); $i++) {
    $tb_names[$i] = mysql_tablename($result, $i);
    echo $tb_names[$i] . "<BR>";
}
?>
```

mysql_unbuffered_query (PHP 4 >= 4.0.6)

Pošle SQL dotaz MySQL bez vykonání a načtení výsledných záznamů

resource **mysql_unbuffered_query** (string query [, resource spojeni]) \linebreak

mysql_unbuffered_query() sends a SQL query *query* to MySQL, without fetching and buffering the result rows automatically, as **mysql_query()** does. On the one hand, this saves a considerable amount of memory with SQL queries that produce large result sets. On the other hand, you can start working on the result set immediately after the first row has been retrieved: you don't have to wait until the complete SQL query has been performed. When using multiple DB-connects, you have to specify the optional parameter *spojeni*.

Poznámka: The benefits of **mysql_unbuffered_query()** come at a cost: You cannot use **mysql_num_rows()** on a result set returned from **mysql_unbuffered_query()**. You also have to fetch all result rows from an unbuffered SQL query, before you can send a new SQL query to MySQL.

Viz. také: **mysql_query()**.

LXIII. Mohawk Software session handler functions

msession is an interface to a high speed session daemon which can run either locally or remotely. It is designed to provide consistent session management for a PHP web farm.

The session server software can be found at <http://www.mohawksoft.com/phoenix/>.

msession_connect (PHP 4 >= 4.2.0)

Connect to msession server

bool **msession_connect** (string host, string port) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_count (PHP 4 >= 4.2.0)

Get session count

int **msession_count** (void) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_create (PHP 4 >= 4.2.0)

Create a session

bool **msession_create** (string session) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_destroy (PHP 4 >= 4.2.0)

Destroy a session

bool **msession_destroy** (string name) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_disconnect (PHP 4 >= 4.2.0)

Close connection to msession server

void **msession_disconnect** (void) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_find (PHP 4 >= 4.2.0)

Find value

array **msession_find** (string name, string value) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_get (PHP 4 >= 4.2.0)

Get value from session

string **msession_get** (string session, string name, string value) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_get_array (PHP 4 >= 4.2.0)

Get array of ... ?

array **msession_get_array** (string session) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_getdata (unknown)

Get data ... ?

string **msession_getdata** (string session) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_inc (PHP 4 >= 4.2.0)

Increment value in session

string **msession_inc** (string session, string name) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_list (PHP 4 >= 4.2.0)

List ... ?

array **msession_list** (void) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_listvar (PHP 4 >= 4.2.0)

List sessions with variable

array **msession_listvar** (string name) \linebreak

Returns an associative array of value, session for all sessions with a variable named *name*.

Used for searching sessions with common attributes.

msession_lock (PHP 4 >= 4.2.0)

Lock a session

int **msession_lock** (string name) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_plugin (PHP 4 >= 4.2.0)

Call an escape function within the msession personality plugin

string **msession_plugin** (string session, string val [, string param]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_randstr (PHP 4 >= 4.2.0)

Get random string

string **msession_randstr** (int param) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_set (PHP 4 >= 4.2.0)

Set value in session

bool **msession_set** (string session, string name, string value) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_set_array (PHP 4 >= 4.2.0)

Set array of ...

bool **msession_set_array** (string session, array tuples) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_setdata (unknown)

Set data ... ?

bool **msession_setdata** (string session, string value) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_timeout (PHP 4 >= 4.2.0)

Set/get session timeout

int **msession_timeout** (string session [, int param]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_uniq (PHP 4 >= 4.2.0)

Get uniq id

string **msession_uniq** (int param) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

msession_unlock (PHP 4 >= 4.2.0)

Unlock a session

int **msession_unlock** (string session, int key) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

LXIV. muscat functions

muscat_close (4.0.5 - 4.2.0 only)

Shuts down the muscat session and releases any memory back to php. [Not back to the system, note!]

```
int muscat_close ( resource muscat_handle) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

muscat_get (4.0.5 - 4.2.0 only)

Gets a line back from the core muscat api. Returns a literal FALSE when there is no more to get (as opposed to ""). Use === FALSE or !== FALSE to check for this

```
string muscat_get ( resource muscat_handle) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

muscat_give (4.0.5 - 4.2.0 only)

Sends string to the core muscat api

int **muscat_give** (resource muscat_handle, string string) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

muscat_setup (4.0.5 - 4.2.0 only)

Creates a new muscat session and returns the handle. Size is the ammount of memory in bytes to allocate for muscat muscat_dir is the muscat installation dir e.g. "/usr/local/empower", it defaults to the compile time muscat directory

resource **muscat_setup** (int size [, string muscat_dir]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

muscat_setup_net (4.0.5 - 4.2.0 only)

Creates a new muscat session and returns the handle. muscat_host is the hostname to connect to port is the port number to connect to - actually takes exactly the same args as fsockopen

resource **muscat_setup_net** (string muscat_host, int port) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

LXV. Network Functions

checkdnsrr (PHP 3, PHP 4 >= 4.0.0)

Check DNS records corresponding to a given Internet host name or IP address

int **checkdnsrr** (string host [, string type]) \linebreak

Searches DNS for records of type *type* corresponding to *host*. Returns TRUE if any records are found; returns FALSE if no records were found or if an error occurred.

type may be any one of: A, MX, NS, SOA, PTR, CNAME, or ANY. The default is MX.

Host may either be the IP address in dotted-quad notation or the host name.

Poznámka: Tato funkce není implementována na platformách Windows.

See also getmxrr(), gethostbyaddr(), gethostbyname(), gethostbyname1(), and the named(8) manual page.

closelog (PHP 3, PHP 4 >= 4.0.0)

Close connection to system logger

int **closelog** (void) \linebreak

closelog() closes the descriptor being used to write to the system logger. The use of **closelog()** is optional.

See also define_syslog_variables(), syslog() and openlog().

debugger__off (PHP 3)

Disable internal PHP debugger

int **debugger__off** (void) \linebreak

Disables the internal PHP debugger. The debugger is still under development.

debugger_on (PHP 3)

Enable internal PHP debugger

int **debugger_on** (string address) \linebreak

Enables the internal PHP debugger, connecting it to *address*. The debugger is still under development.

define_syslog_variables (PHP 3, PHP 4 >= 4.0.0)

Initializes all syslog related constants

```
void define_syslog_variables ( void) \linebreak
```

Initializes all constants used in the syslog functions.

See also `openlog()`, `syslog()` and `closelog()`.

fsockopen (PHP 3, PHP 4 >= 4.0.0)

Open Internet or Unix domain socket connection

```
int fsockopen ( string hostname, int port [, int errno [, string errstr [, float timeout]]]) \linebreak
```

Initiates a stream connection in the Internet (AF_INET, using TCP or UDP) or Unix (AF_UNIX) domain. For the Internet domain, it will open a TCP socket connection to *hostname* on port *port*. *hostname* may in this case be either a fully qualified domain name or an IP address. For UDP connections, you need to explicitly specify the protocol by prefixing *hostname* with 'udp://'. For the Unix domain, *hostname* will be used as the path to the socket, *port* must be set to 0 in this case. The optional *timeout* can be used to set a timeout in seconds for the connect system call.

As of PHP 4.3.0, if you have compiled in OpenSSL support, you may prefix the *hostname* with either 'ssl://' or 'tls://' to use an SSL or TLS client connection over TCP/IP to connect to the remote host.

fsockopen() returns a file pointer which may be used together with the other file functions (such as `fgets()`, `fgetss()`, `fputs()`, `fclose()`, and `feof()`).

If the call fails, it will return `FALSE` and if the optional *errno* and *errstr* arguments are present they will be set to indicate the actual system level error that occurred in the system-level `connect()` call. If the value returned in *errno* is 0 and the function returned `FALSE`, it is an indication that the error occurred before the `connect()` call. This is most likely due to a problem initializing the socket. Note that the *errno* and *errstr* arguments will always be passed by reference.

Depending on the environment, the Unix domain or the optional connect timeout may not be available.

The socket will by default be opened in blocking mode. You can switch it to non-blocking mode by using `socket_set_blocking()`.

Příklad 1. fsockopen() Example

```
<?php
$fp = fsockopen ("www.example.com", 80, $errno, $errstr, 30);
if (!$fp) {
    echo "$errstr ($errno)<br>\n";
} else {
    fputs ($fp, "GET / HTTP/1.0\r\nHost: www.example.com\r\n\r\n");
    while (!feof($fp)) {
        echo fgets ($fp,128);
    }
    fclose ($fp);
}
```

```
}
?>
```

The example below shows how to retrieve the day and time from the UDP service "daytime" (port 13) in your own machine.

Příklad 2. Using UDP connection

```
<?php
$fp = fsockopen("udp://127.0.0.1", 13, $errno, $errstr);
if (!$fp) {
    echo "ERROR: $errno - $errstr<br>\n";
} else {
    fwrite($fp, "\n");
    echo fread($fp, 26);
    fclose($fp);
}
?>
```

Poznámka: The timeout parameter was introduced in PHP 3.0.9 and UDP support was added in PHP 4.

See also `pfsockopen()`, `socket_set_blocking()`, `socket_set_timeout()`, `fgets()`, `fgetss()`, `fputs()`, `fclose()`, `feof()`, and the Curl extension.

gethostbyaddr (PHP 3, PHP 4 >= 4.0.0)

Get the Internet host name corresponding to a given IP address

string **gethostbyaddr** (string *ip_address*) \linebreak

Returns the host name of the Internet host specified by *ip_address*. If an error occurs, returns *ip_address*.

See also `gethostbyname()`.

gethostbyname (PHP 3, PHP 4 >= 4.0.0)

Get the IP address corresponding to a given Internet host name

string **gethostbyname** (string *hostname*) \linebreak

Returns the IP address of the Internet host specified by *hostname*.

See also `gethostbyaddr()`.

gethostbyname1 (PHP 3, PHP 4 >= 4.0.0)

Get a list of IP addresses corresponding to a given Internet host name

array **gethostbyname1** (string *hostname*) \linebreak

Returns a list of IP addresses to which the Internet host specified by *hostname* resolves.

See also `gethostbyname()`, `gethostbyaddr()`, `checkdnsrr()`, `getmxrr()`, and the `named(8)` manual page.

getmxrr (PHP 3, PHP 4 >= 4.0.0)

Get MX records corresponding to a given Internet host name

int **getmxrr** (string *hostname*, array *mxhosts* [, array *weight*]) \linebreak

Searches DNS for MX records corresponding to *hostname*. Returns `TRUE` if any records are found; returns `FALSE` if no records were found or if an error occurred.

A list of the MX records found is placed into the array *mxhosts*. If the *weight* array is given, it will be filled with the weight information gathered.

See also `checkdnsrr()`, `gethostbyname()`, `gethostbyname1()`, `gethostbyaddr()`, and the `named(8)` manual page.

getprotobyname (PHP 4 >= 4.0.0)

Get protocol number associated with protocol name

int **getprotobyname** (string *name*) \linebreak

getprotobyname() returns the protocol number associated with the protocol *name* as per `/etc/protocols`.

See also: `getprotobynumber()`.

getprotobynumber (PHP 4 >= 4.0.0)

Get protocol name associated with protocol number

string **getprotobynumber** (int *number*) \linebreak

getprotobynumber() returns the protocol name associated with protocol *number* as per `/etc/protocols`.

See also: `getprotobyname()`.

getservbyname (PHP 4 >= 4.0.0)

Get port number associated with an Internet service and protocol

```
int getservbyname ( string service, string protocol) \linebreak
```

getservbyname() returns the Internet port which corresponds to *service* for the specified *protocol* as per */etc/services*. *protocol* is either "tcp" or "udp" (in lowercase).

See also: getservbyport().

getservbyport (PHP 4 >= 4.0.0)

Get Internet service which corresponds to port and protocol

```
string getservbyport ( int port, string protocol) \linebreak
```

getservbyport() returns the Internet service associated with *port* for the specified *protocol* as per */etc/services*. *protocol* is either "tcp" or "udp" (in lowercase).

See also: getservbyname().

ip2long (PHP 4 >= 4.0.0)

Converts a string containing an (IPv4) Internet Protocol dotted address into a proper address.

```
int ip2long ( string ip_address) \linebreak
```

The function **ip2long()** generates an IPv4 Internet network address from its Internet standard format (dotted string) representation.

Příklad 1. ip2long() Example

```
<?php
$ip = gethostbyname("www.example.com");
$out = "The following URLs are equivalent:<br>\n";
$out .= "http://www.example.com/, http://".$ip."/, and http://".sprintf("%u",ip2long($ip))."/";
echo $out;
?>
```

Poznámka: Because PHP's integer type is signed, and many IP addresses will result in negative integers, you need to use the "%u" formatter of `sprintf()` or `printf()` to get the string representation of the unsigned IP address.

This second example shows how to print a converted address with the `printf()` function :

Příklad 2. Displaying an IP address

```
<?php
$ip = gethostbyname("www.example.com");
printf("%u\n", ip2long($ip));
echo $out;
?>
```

See also: `long2ip()`

long2ip (PHP 4 >= 4.0.0)

Converts an (IPv4) Internet network address into a string in Internet standard dotted format

string **long2ip** (int proper_address) \linebreak

The function **long2ip()** generates an Internet address in dotted format (i.e.: aaa.bbb.ccc.ddd) from the proper address representation.

See also: `ip2long()`

openlog (PHP 3, PHP 4 >= 4.0.0)

Open connection to system logger

int **openlog** (string ident, int option, int facility) \linebreak

openlog() opens a connection to the system logger for a program. The string *ident* is added to each message. Values for *option* and *facility* are given below. The *option* argument is used to indicate what logging options will be used when generating a log message. The *facility* argument is used to specify what type of program is logging the message. This allows you to specify (in your machine's syslog configuration) how messages coming from different facilities will be handled. The use of **openlog()** is optional. It will automatically be called by `syslog()` if necessary, in which case *ident* will default to `FALSE`.

Tabulka 1. openlog() Options

Constant	Description
LOG_CONS	if there is an error while sending data to the system logger, write directly to the system console
LOG_NDELAY	open the connection to the logger immediately
LOG_ODELAY	(default) delay opening the connection until the first message is logged
LOG_PERROR	print log message also to standard error

Constant	Description
LOG_PID	include PID with each message

You can use one or more of this options. When using multiple options you need to OR them, i.e. to open the connection immediately, write to the console and include the PID in each message, you will use: LOG_CONS | LOG_NDELAY | LOG_PID

Tabulka 2. openlog() Facilities

Constant	Description
LOG_AUTH	security/authorization messages (use LOG_AUTHPRIV instead in systems where that constant is defined)
LOG_AUTHPRIV	security/authorization messages (private)
LOG_CRON	clock daemon (cron and at)
LOG_DAEMON	other system daemons
LOG_KERN	kernel messages
LOG_LOCAL0 ... LOG_LOCAL7	reserved for local use
LOG_LPR	line printer subsystem
LOG_MAIL	mail subsystem
LOG_NEWS	USENET news subsystem
LOG_SYSLOG	messages generated internally by syslogd
LOG_USER	generic user-level messages
LOG_UUCP	UUCP subsystem

See also `define_syslog_variables()`, `syslog()` and `closelog()`.

pfsockopen (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Open persistent Internet or Unix domain socket connection

`int pfsockopen (string hostname, int port [, int errno [, string errstr [, int timeout]]]) \linebreak`

This function behaves exactly as `fsockopen()` with the difference that the connection is not closed after the script finishes. It is the persistent version of `fsockopen()`.

socket_get_status (PHP 4 >= 4.0.0)

Returns information about an existing socket stream

`array socket_get_status (resource socketstream) \linebreak`

Returns information about an existing socket stream. This function only works on sockets created by `fsockopen()`, `pfsockopen()` or network sockets returned by `fopen()` when opening URLs. It does NOT work with sockets from the Socket extension. Currently returns four entries in the result array:

- *timed_out* (bool) - The socket timed out waiting for data
- *blocked* (bool) - The socket was blocked
- *eof* (bool) - Indicates EOF event
- *unread_bytes* (int) - Number of bytes left in the socket buffer

See also: Socket extension.

socket_set_blocking (PHP 4 >= 4.0.0)

Set blocking/non-blocking mode on a socket

`int socket_set_blocking (int socket descriptor, int mode) \linebreak`

If *mode* is `FALSE`, the given socket descriptor will be switched to non-blocking mode, and if `TRUE`, it will be switched to blocking mode. This affects calls like `fgets()` that read from the socket. In non-blocking mode an `fgets()` call will always return right away while in blocking mode it will wait for data to become available on the socket.

This function was previously called as `set_socket_blocking()` but this usage is deprecated.

socket_set_timeout (PHP 4 >= 4.0.0)

Set timeout period on a socket

`bool socket_set_timeout (int socket descriptor, int seconds, int microseconds) \linebreak`

Sets the timeout value on *socket descriptor*, expressed in the sum of *seconds* and *microseconds*.

Příklad 1. socket_set_timeout() Example

```
<?php
$fp = fsockopen("www.example.com", 80);
if(!$fp) {
    echo "Unable to open\n";
} else {
    fputs($fp, "GET / HTTP/1.0\n\n");
    $start = time();
    socket_set_timeout($fp, 2);
    $res = fread($fp, 2000);
    var_dump(socket_get_status($fp));
    fclose($fp);
    print $res;
}
?>
```

This function was previously called as **set_socket_timeout()** but this usage is deprecated.

See also: `fsockopen()` and `fopen()`.

syslog (PHP 3, PHP 4 >= 4.0.0)

Generate a system log message

int syslog (int priority, string message) \linebreak

syslog() generates a log message that will be distributed by the system logger. *priority* is a combination of the facility and the level, values for which are given in the next section. The remaining argument is the message to send, except that the two characters `%m` will be replaced by the error message string (`strerror`) corresponding to the present value of `errno`.

Tabulka 1. syslog() Priorities (in descending order)

Constant	Description
LOG_EMERG	system is unusable
LOG_ALERT	action must be taken immediately
LOG_CRIT	critical conditions
LOG_ERR	error conditions
LOG_WARNING	warning conditions
LOG_NOTICE	normal, but significant, condition
LOG_INFO	informational message
LOG_DEBUG	debug-level message

Příklad 1. Using syslog()

```
<?php
define_syslog_variables();
// open syslog, include the process ID and also send
// the log to standard error, and use a user defined
// logging mechanism
openlog("myScripLog", LOG_PID | LOG_PERROR, LOG_LOCAL0);

// some code

if (authorized_client()) {
    // do something
} else {
    // unauthorized client!
    // log the attempt
    $access = date("Y/m/d H:i:s");
```



```
        syslog(LOG_WARNING, "Unauthorized client: $access $REMOTE_ADDR ($HTTP_USER_AGENT)");  
    }  
  
    closelog();  
?>
```

For information on setting up a user defined log handler, see the `syslog.conf(5)` Unix manual page. More information on the syslog facilities and option can be found in the man pages for `syslog(3)` on Unix machines.

On Windows NT, the syslog service is emulated using the Event Log.

See also `define_syslog_variables()`, `openlog()` and `closelog()`.

LXVI. Ncurses terminal screen control functions

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

What is ncurses?

ncurses (new curses) is a free software emulation of curses in System V Rel 4.0 (and above). It uses terminfo format, supports pads, colors, multiple highlights, form characters and function key mapping.

Platforms

Ncurses is available for the following platforms:

- AIX
- BeOS
- Cygwin
- Digital Unix (aka OSF1)
- FreeBSD
- GNU/Linux
- HPUX
- IRIX
- OS/2
- SCO OpenServer
- Solaris
- SunOS

Requirements

You need the ncurses libraries and headerfiles. Download the latest version from the

<ftp://ftp.gnu.org/pub/gnu/ncurses/> or from an other GNU-Mirror.

Installation

To get these functions to work, you have to compile the CGI version of PHP with `--with-ncurses`.

Ncurses predefined constants

Error codes

On error ncurses functions return `NCURSES_ERR`.

Colors

Tabulka 1. ncurses color constants

constant	meaning
<code>NCURSES_COLOR_BLACK</code>	no color (black)
<code>NCURSES_COLOR_WHITE</code>	white
<code>NCURSES_COLOR_RED</code>	red - supported when terminal is in color mode
<code>NCURSES_COLOR_GREEN</code>	green - supported when terminal is in color mod
<code>NCURSES_COLOR_YELLOW</code>	yellow - supported when terminal is in color mod
<code>NCURSES_COLOR_BLUE</code>	blue - supported when terminal is in color mod
<code>NCURSES_COLOR_CYAN</code>	cyan - supported when terminal is in color mod
<code>NCURSES_COLOR_MAGENTA</code>	magenta - supported when terminal is in color mod

Keys

Tabulka 2. ncurses key constants

constant	meaning
<code>NCURSES_KEY_F0 - NCURSES_KEY_F64</code>	function keys F1 - F64
<code>NCURSES_KEY_DOWN</code>	down arrow
<code>NCURSES_KEY_UP</code>	up arrow
<code>NCURSES_KEY_LEFT</code>	left arrow
<code>NCURSES_KEY_RIGHT</code>	right arrow
<code>NCURSES_KEY_HOME</code>	home key (upward+left arrow)
<code>NCURSES_KEY_BACKSPACE</code>	backspace
<code>NCURSES_KEY_DL</code>	delete line

constant	meaning
NCURSES_KEY_IL	insert line
NCURSES_KEY_DC	delete character
NCURSES_KEY_IC	insert char or enter insert mode
NCURSES_KEY_EIC	exit insert char mode
NCURSES_KEY_CLEAR	clear screen
NCURSES_KEY_EOS	clear to end of screen
NCURSES_KEY_EOL	clear to end of line
NCURSES_KEY_SF	scroll one line forward
NCURSES_KEY_SR	scroll one line backward
NCURSES_KEY_NPAGE	next page
NCURSES_KEY_PPAGE	previous page
NCURSES_KEY_STAB	set tab
NCURSES_KEY_CTAB	clear tab
NCURSES_KEY_CATAB	clear all tabs
NCURSES_KEY_SRESET	soft (partial) reset
NCURSES_KEY_RESET	reset or hard reset
NCURSES_KEY_PRINT	print
NCURSES_KEY_LL	lower left
NCURSES_KEY_A1	upper left of keypad
NCURSES_KEY_A3	upper right of keypad
NCURSES_KEY_B2	center of keypad
NCURSES_KEY_C1	lower left of keypad
NCURSES_KEY_C3	lower right of keypad
NCURSES_KEY_BTAB	back tab
NCURSES_KEY_BEG	beginning
NCURSES_KEY_CANCEL	cancel
NCURSES_KEY_CLOSE	close
NCURSES_KEY_COMMAND	cmd (command)
NCURSES_KEY_COPY	copy
NCURSES_KEY_CREATE	create
NCURSES_KEY_END	end
NCURSES_KEY_EXIT	exit
NCURSES_KEY_FIND	find
NCURSES_KEY_HELP	help
NCURSES_KEY_MARK	mark
NCURSES_KEY_MESSAGE	message
NCURSES_KEY_MOVE	move
NCURSES_KEY_NEXT	next
NCURSES_KEY_OPEN	open
NCURSES_KEY_OPTIONS	options
NCURSES_KEY_PREVIOUS	previous
NCURSES_KEY_REDO	redo

constant	meaning
NCURSES_KEY_REFERENCE	ref (reference)
NCURSES_KEY_REFRESH	refresh
NCURSES_KEY_REPLACE	replace
NCURSES_KEY_RESTART	restart
NCURSES_KEY_RESUME	resume
NCURSES_KEY_SAVE	save
NCURSES_KEY_SBEG	shiftet beg (beginning)
NCURSES_KEY_SCANCEL	shifted cancel
NCURSES_KEY_SCOMMAND	shifted command
NCURSES_KEY_SCOPY	shifted copy
NCURSES_KEY_SCREATE	shifted create
NCURSES_KEY_SDC	shifted delete char
NCURSES_KEY_SDL	shifted delete line
NCURSES_KEY_SELECT	select
NCURSES_KEY_SEND	shifted end
NCURSES_KEY_SEOL	shifted end of line
NCURSES_KEY_SEXIT	shifted exit
NCURSES_KEY_SFIND	shifted find
NCURSES_KEY_SHELP	shifted help
NCURSES_KEY_SHOME	shifted home
NCURSES_KEY_SIC	shifted input
NCURSES_KEY_SLEFT	shifted left arrow
NCURSES_KEY_SMESSAGE	shifted message
NCURSES_KEY_SMOVE	shifted move
NCURSES_KEY_SNEXT	shifted next
NCURSES_KEY_SOPTIONS	shifted options
NCURSES_KEY_SPREVIOUS	shifted previous
NCURSES_KEY_SPRINT	shifted print
NCURSES_KEY_SREDO	shifted redo
NCURSES_KEY_SREPLACE	shifted replace
NCURSES_KEY_SRIGHT	shifted right arrow
NCURSES_KEY_SRSUME	shifted resume
NCURSES_KEY_SSAVE	shifted save
NCURSES_KEY_SSUSPEND	shifted suspend
NCURSES_KEY_UNDO	undo
NCURSES_KEY_MOUSE	mouse event has occurred
NCURSES_KEY_MAX	maximum key value

Mouse

Tabulka 3. mouse constants

Constant	meaning
NCURSES_BUTTON1_RELEASED - NCURSES_BUTTON4_RELEASED	button (1-4) released
NCURSES_BUTTON1_PRESSED - NCURSES_BUTTON4_PRESSED	button (1-4) pressed
NCURSES_BUTTON1_CLICKED - NCURSES_BUTTON4_CLICKED	button (1-4) clicked
NCURSES_BUTTON1_DOUBLE_CLICKED - NCURSES_BUTTON4_DOUBLE_CLICKED	button (1-4) double clicked
NCURSES_BUTTON1_TRIPLE_CLICKED - NCURSES_BUTTON4_TRIPLE_CLICKED	button (1-4) triple clicked
NCURSES_BUTTON_CTRL	ctrl pressed during click
NCURSES_BUTTON_SHIFT	shift pressed during click
NCURSES_BUTTON_ALT	alt pressed during click
NCURSES_ALL_MOUSE_EVENTS	report all mouse events
NCURSES_REPORT_MOUSE_POSITION	report mouse position

ncurses_addch (PHP 4 >= 4.1.0)

Add character at current position and advance cursor

```
int ncurses_addch ( int ch) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_addchnstr (PHP 4 >= 4.2.0)

Add attributed string with specified length at current position

```
int ncurses_addchnstr ( string s, int n) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_addchstr (PHP 4 >= 4.2.0)

Add attributed string at current position

```
int ncurses_addchstr ( string s) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_addnstr (PHP 4 >= 4.2.0)

Add string with specified length at current position

```
int ncurses_addnstr ( string s, int n) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_addstr (PHP 4 >= 4.2.0)

Output text at current position

```
int ncurses_addstr ( string text) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_assume_default_colors (PHP 4 >= 4.2.0)

Define default colors for color 0

```
int ncurses_assume_default_colors ( int fg, int bg) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_attroff (PHP 4 >= 4.1.0)

Turn off the given attributes

```
int ncurses_attroff ( int attributes) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_attron (PHP 4 >= 4.1.0)

Turn on the given attributes

```
int ncurses_attron ( int attributes) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_attrset (PHP 4 >= 4.1.0)

Set given attributes

```
int ncurses_attrset ( int attributes) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_baudrate (PHP 4 >= 4.1.0)

Returns baudrate of terminal

```
int ncurses_baudrate ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_beep (PHP 4 >= 4.1.0)

Let the terminal beep

```
int ncurses_beep ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_beep() sends an audible alert (bell) and if its not possible flashes the screen. Returns FALSE on success, otherwise TRUE.

See also: ncurses_flash()

ncurses_bkgd (PHP 4 >= 4.1.0)

Set background property for terminal screen

```
int ncurses_bkgd ( int attrchar) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_bkgdset (PHP 4 >= 4.1.0)

Control screen background

```
void ncurses_bkgdset ( int attrchar) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_border (PHP 4 >= 4.2.0)

Draw a border around the screen using attributed characters

```
int ncurses_border ( int left, int right, int top, int bottom, int tl_corner, int tr_corner, int bl_corner, int br_corner) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_can_change_color (PHP 4 >= 4.1.0)

Check if we can change terminals colors

```
bool ncurses_can_change_color ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

The function `ncurses_can_change_color()` returns `TRUE` or `FALSE`, depending on whether the terminal has color capabilities and whether the programmer can change the colors.

ncurses_cbreak (PHP 4 >= 4.1.0)

Switch of input buffering

bool **ncurses_cbreak** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_cbreak() disables line buffering and character processing (interrupt and flow control characters are unaffected), making characters typed by the user immediately available to the program.

ncurses_cbreak() returns `TRUE` or `NCURSES_ERR` if any error occurred.

See also: `ncurses_nocbreak()`

ncurses_clear (PHP 4 >= 4.1.0)

Clear screen

bool **ncurses_clear** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_clear() clears the screen completely without setting blanks. Returns `FALSE` on success, otherwise `TRUE`.

Note: **ncurses_clear()** clears the screen without setting blanks, which have the current background rendition. To clear screen with blanks, use `ncurses_erase()`.

See also: `ncurses_erase()`

ncurses_clrtoobot (PHP 4 >= 4.1.0)

Clear screen from current position to bottom

bool **ncurses_clrtoobot** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_clrtobot() erases all lines from cursor to end of screen and creates blanks. Blanks created by **ncurses_clrtobot()** have the current background rendition. Returns **TRUE** if any error occurred, otherwise **FALSE**.

See also: **ncurses_clear()**, **ncurses_clrtoeol()**

ncurses_clrtoeol (PHP 4 >= 4.1.0)

Clear screen from current position to end of line

bool **ncurses_clrtoeol** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_clrtoeol() erases the current line from cursor position to the end. Blanks created by **ncurses_clrtoeol()** have the current background rendition. Returns **TRUE** if any error occurred, otherwise **FALSE**.

See also: **ncurses_clear()**, **ncurses_clrtobot()**

ncurses_color_set (PHP 4 >= 4.1.0)

Set fore- and background color

int **ncurses_color_set** (int pair) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_curs_set (PHP 4 >= 4.1.0)

Set cursor state

`int ncurses_curs_set (int visibility) \linebreak`**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_def_prog_mode (PHP 4 >= 4.1.0)

Saves terminals (program) mode

`bool ncurses_def_prog_mode (void) \linebreak`**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_def_prog_mode() saves the current terminal modes for program (in curses) for use by **ncurses_reset_prog_mode()**. Returns **FALSE** on success, otherwise **TRUE**.

See also: **ncurses_reset_prog_mode()**

ncurses_def_shell_mode (PHP 4 >= 4.1.0)

Saves terminals (shell) mode

`bool ncurses_def_shell_mode (void) \linebreak`**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_def_shell_mode() saves the current terminal modes for shell (not in curses) for use by **ncurses_reset_shell_mode()**. Returns **FALSE** on success, otherwise **TRUE**.

See also: `ncurses_reset_shell_mode()`

`ncurses_define_key` (PHP 4 >= 4.2.0)

Define a keycode

```
int ncurses_define_key ( string definition, int keycode) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

`ncurses_delay_output` (PHP 4 >= 4.1.0)

Delay output on terminal using padding characters

```
int ncurses_delay_output ( int milliseconds) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

`ncurses_delch` (PHP 4 >= 4.1.0)

Delete character at current position, move rest of line left

```
bool ncurses_delch ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_delch() deletes the character under the cursor. All characters to the right of the cursor on the same line are moved to the left one position and the last character on the line is filled with a blank. The cursor position does not change. Returns `FALSE` on success, otherwise `TRUE`.

See also: `ncurses_deleteln()`

ncurses_deleteln (PHP 4 >= 4.1.0)

Delete line at current position, move rest of screen up

bool **ncurses_deleteln** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_deleteln() deletes the current line under cursorposition. All lines below the current line are moved up one line. The bottom line of window is cleared. Cursor position does not change. Returns `FALSE` on success, otherwise `TRUE`.

See also: `ncurses_delch()`

ncurses_delwin (PHP 4 >= 4.1.0)

Delete a ncurses window

int **ncurses_delwin** (resource window) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_doupdate (PHP 4 >= 4.1.0)

Write all prepared refreshes to terminal

bool **ncurses_doupdate** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_doupdate() compares the virtual screen to the physical screen and updates the physical screen. This way is more effective than using multiple refresh calls. Returns **FALSE** on success, **TRUE** if any error occurred.

ncurses_echo (PHP 4 >= 4.1.0)

Activate keyboard input echo

bool **ncurses_echo** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_echo() enables echo mode. All characters typed by user are echoed by **ncurses_getch()**. Returns **FALSE** on success, **TRUE** if any error occurred.

To disable echo mode use **ncurses_noecho()**.

ncurses_echochar (PHP 4 >= 4.1.0)

Single character output including refresh

int **ncurses_echochar** (int character) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_end (PHP 4 >= 4.1.0)

Stop using ncurses, clean up the screen

```
int ncurses_end ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_erase (PHP 4 >= 4.1.0)

Erase terminal screen

```
bool ncurses_erase ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_erase() fills the terminal screen with blanks. Created blanks have the current background rendition, set by **ncurses_bkgd()**. Returns **FALSE** on success, **TRUE** if any error occurred.

See also: **ncurses_bkgd()**, **ncurses_clear()**

ncurses_erasechar (PHP 4 >= 4.1.0)

Returns current erase character

```
string ncurses_erasechar ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_erasechar() returns the current erase char character.

See also: **ncurses_killchar()**

ncurses_filter (PHP 4 >= 4.1.0)

int **ncurses_filter** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_flash (PHP 4 >= 4.1.0)

Flash terminal screen (visual bell)

bool **ncurses_flash** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_flash() flashes the screen, and if its not possible, sends an audible alert (bell). Returns *FALSE* on success, otherwise *TRUE*.

See also: `ncurses_beep()`

ncurses_flushinp (PHP 4 >= 4.1.0)

Flush keyboard input buffer

bool **ncurses_flushinp** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

The **ncurses_flushinp()** throws away any typeahead that has been typed and has not yet been read by your program. Returns *FALSE* on success, otherwise *TRUE*.

ncurses_getch (PHP 4 >= 4.1.0)

Read a character from keyboard

```
int ncurses_getch ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_getmouse (PHP 4 >= 4.2.0)

Reads mouse event

```
bool ncurses_getmouse ( array mevent) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_getmouse() reads mouse event out of queue. Function **ncurses_getmouse()** will return `FALSE` if a mouse event is actually visible in the given window, otherwise it will return `TRUE`. Event options will be delivered in parameter *mevent*, which has to be an array, passed by reference (see example below). On success an associative array with following keys will be delivered:

- "id" : Id to distinguish multiple devices
- "x" : screen relative x-position in character cells
- "y" : screen relative y-position in character cells
- "z" : currently not supported
- "mmask" : Mouse action

Příklad 1. ncurses_getmouse() example

```
switch (ncurses_getch){
  case NCURSES_KEY_MOUSE:
    if (!ncurses_getmouse(&$mevent)){
```

```

        if ($mevent["mmask"] & NCURSES_MOUSE_BUTTON1_PRESSED){
            $mouse_x = $mevent["x"]; // Save mouse position
            $mouse_y = $mevent["y"];
        }
    }
    break;

    default:
        ....
}

```

See also: `ncurses_ungetmouse()`

ncurses_halfdelay (PHP 4 >= 4.1.0)

Put terminal into halfdelay mode

```
int ncurses_halfdelay ( int tenth) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_has_colors (PHP 4 >= 4.1.0)

Check if terminal has colors

```
bool ncurses_has_colors ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_has_colors() returns TRUE or FALSE depending on whether the terminal has color capacities.

See also: `ncurses_can_change_color()`

ncurses_has_ic (PHP 4 >= 4.1.0)

Check for insert- and delete-capabilities

```
bool ncurses_has_ic ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_has_ic() checks terminals insert- and delete capabilities. It returns `TRUE` when terminal has insert/delete-capabilities, otherwise `FALSE`.

See also: `ncurses_has_il()`

ncurses_has_il (PHP 4 >= 4.1.0)

Check for line insert- and delete-capabilities

```
bool ncurses_has_il ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_has_il() checks terminals insert- and delete-line capabilities. It returns `TRUE` when terminal has insert/delete-line capabilities, otherwise `FALSE`

See also: `ncurses_has_ic()`

ncurses_has_key (PHP 4 >= 4.1.0)

Check for presence of a function key on terminal keyboard

```
int ncurses_has_key ( int keycode) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_hline (PHP 4 >= 4.2.0)

Draw a horizontal line at current position using an attributed character and max. n characters long

```
int ncurses_hline ( int charattr, int n) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_inch (PHP 4 >= 4.1.0)

Get character and attribute at current position

```
string ncurses_inch ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_inch() returns the character from the current position.

ncurses_init (PHP 4 >= 4.1.0)

Initialize ncurses

```
int ncurses_init ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_init_color (PHP 4 >= 4.2.0)

Set new RGB value for color

```
int ncurses_init_color ( int color, int r, int g, int b) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_init_pair (PHP 4 >= 4.1.0)

Allocate a color pair

```
int ncurses_init_pair ( int pair, int fg, int bg) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_insch (PHP 4 >= 4.1.0)

Insert character moving rest of line including character at current position

```
int ncurses_insch ( int character) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_insdelln (PHP 4 >= 4.1.0)

Insert lines before current line scrolling down (negative numbers delete and scroll up)

```
int ncurses_insdelln ( int count) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_insertln (PHP 4 >= 4.1.0)

Insert a line, move rest of screen down

```
bool ncurses_insertln ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_insertln() inserts a new line above the current line. The bottom line will be lost.

ncurses_insstr (PHP 4 >= 4.2.0)

Insert string at current position, moving rest of line right

```
int ncurses_insstr ( string text) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_instr (PHP 4 >= 4.2.0)

Reads string from terminal screen

```
int ncurses_instr ( string buffer) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_instr() returns the number of charaters read from the current character position until end of line. *buffer* contains the characters. Attributes are stripped from the characters.

ncurses_isendwin (PHP 4 >= 4.1.0)

Ncurses is in endwin mode, normal screen output may be performed

```
bool ncurses_isendwin ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_isendwin() returns **TRUE**, if **ncurses_endwin()** has been called without any subsequent calls to **ncurses_wrefresh()**, otherwise **FALSE**.

See also: **ncurses_endwin()** **ncurses_wrefresh()**

ncurses_keyok (PHP 4 >= 4.2.0)

Enable or disable a keycode

```
int ncurses_keyok ( int keycode, bool enable) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_killchar (PHP 4 >= 4.1.0)

Returns current line kill character

bool **ncurses_killchar** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_killchar() returns the current line kill character.

See also: **ncurses_erasechar()**

ncurses_longname (PHP 4 >= 4.2.0)

Returns terminals description

string **ncurses_longname** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_longname() returns a verbose description of the terminal. The description is truncated to 128 characters. On Error **ncurses_longname()** returns NULL.

See also: **ncurses_termname()**

ncurses_mouseinterval (PHP 4 >= 4.1.0)

Set timeout for mouse button clicks

int **ncurses_mouseinterval** (int milliseconds) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mousemask (PHP 4 >= 4.2.0)

Sets mouse options

```
int ncurses_mousemask ( int newmask, int oldmask) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Function **ncurses_mousemask()** will set mouse events to be reported. By default no mouse events will be reported. The function **ncurses_mousemask()** will return a mask to indicated which of the in parameter *newmask* specified mouse events can be reported. On complete failure, it returns 0. In parameter *oldmask*, which is passed by reference **ncurses_mousemask()** returns the previous value of mouse event mask. Mouse events are represented bei NCURSES_KEY_MOUSE in the **ncurses_wgetch()** input stream. To read the event data and pop the event of of queue, call **ncurses_getmouse()**.

As a side effect, setting a zero mousemask in *newmask* turns off the mouse pointer. Setting a non zero value turns mouse pointer on.

mouse mask options can be set with the following predefined constants:

- NCURSES_BUTTON1_PRESSED
- NCURSES_BUTTON1_RELEASED
- NCURSES_BUTTON1_CLICKED
- NCURSES_BUTTON1_DOUBLE_CLICKED
- NCURSES_BUTTON1_TRIPLE_CLICKED
- NCURSES_BUTTON2_PRESSED
- NCURSES_BUTTON2_RELEASED
- NCURSES_BUTTON2_CLICKED
- NCURSES_BUTTON2_DOUBLE_CLICKED
- NCURSES_BUTTON2_TRIPLE_CLICKED
- NCURSES_BUTTON3_PRESSED
- NCURSES_BUTTON3_RELEASED
- NCURSES_BUTTON3_CLICKED
- NCURSES_BUTTON3_DOUBLE_CLICKED
- NCURSES_BUTTON3_TRIPLE_CLICKED
- NCURSES_BUTTON4_PRESSED
- NCURSES_BUTTON4_RELEASED
- NCURSES_BUTTON4_CLICKED
- NCURSES_BUTTON4_DOUBLE_CLICKED

- NCURSES_BUTTON4_TRIPLE_CLICKED
- NCURSES_BUTTON_SHIFT>
- NCURSES_BUTTON_CTRL
- NCURSES_BUTTON_ALT
- NCURSES_ALL_MOUSE_EVENTS
- NCURSES_REPORT_MOUSE_POSITION

See also: ncurses_getmouse(), ncurses_ungetmouse() **ncurses_getch()**

Příklad 1. ncurses_mousemask() example

```
$newmask = NCURSES_BUTTON1_CLICKED + NCURSES_BUTTON1_RELEASED;
$mask = ncurses_mousemask($newmask, &$oldmask);
if ($mask & $newmask){
    printf ("All specified mouse options will be supported\n");
}
```

ncurses_move (PHP 4 >= 4.1.0)

Move output position

int **ncurses_move** (int y, int x) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvaddch (PHP 4 >= 4.2.0)

Move current position and add character

int **ncurses_mvaddch** (int y, int x, int c) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvaddchnstr (PHP 4 >= 4.2.0)

Move position and add attributed string with specified length

```
int ncurses_mvaddchnstr ( int y, int x, string s, int n) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvaddchstr (PHP 4 >= 4.2.0)

Move position and add attributed string

```
int ncurses_mvaddchstr ( int y, int x, string s) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvaddnstr (PHP 4 >= 4.2.0)

Move position and add string with specified length

```
int ncurses_mvaddnstr ( int y, int x, string s, int n) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvaddstr (PHP 4 >= 4.2.0)

Move position and add string

int **ncurses_mvaddstr** (int y, int x, string s) \linebreak**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvcur (PHP 4 >= 4.2.0)

Move cursor immediately

int **ncurses_mvcur** (int old_y, int old_x, int new_y, int new_x) \linebreak**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvdelch (PHP 4 >= 4.2.0)

Move position and delete character, shift rest of line left

int **ncurses_mvdelch** (int y, int x) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvgetch (PHP 4 >= 4.2.0)

Move position and get character at new position

int **ncurses_mvgetch** (int y, int x) \linebreak**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvhline (PHP 4 >= 4.2.0)

Set new position and draw a horizontal line using an attributed character and max. n characters long

int **ncurses_mvhline** (int y, int x, int attrchar, int n) \linebreak**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvinch (PHP 4 >= 4.2.0)

Move position and get attributed character at new position

int **ncurses_mvinch** (int y, int x) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvline (unknown)

Set new position and draw a vertical line using an attributed character and max. n characters long

int **ncurses_mvline** (int y, int x, int attrchar, int n) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_mvwaddstr (PHP 4 >= 4.2.0)

Add string at new position in window

int **ncurses_mvwaddstr** (resource window, int y, int x, string text) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_napms (PHP 4 >= 4.1.0)

Sleep

int **ncurses_napms** (int milliseconds) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_newwin (PHP 4 >= 4.1.0)

Create a new window

```
int ncurses_newwin ( int rows, int cols, int y, int x) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_nl (PHP 4 >= 4.1.0)

Translate newline and carriage return / line feed

```
bool ncurses_nl ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_nocbreak (PHP 4 >= 4.1.0)

Switch terminal to cooked mode

```
bool ncurses_nocbreak ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_nocbreak() routine returns terminal to normal (cooked) mode. Initially the terminal may or may not in cbreak mode as the mode is inherited. Therefore a program should call **ncurses_cbreak()** and **ncurses_nocbreak()** explicitly. Returns **TRUE** if any error occurred, otherwise **FALSE**.

See also: **ncurses_cbreak()**

ncurses_noecho (PHP 4 >= 4.1.0)

Switch off keyboard input echo

bool **ncurses_noecho** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_noecho() prevents echoing of user typed characters. Returns **TRUE** if any error occurred, otherwise **FALSE**.

See also: **ncurses_echo()**, **ncurses_getch()**

ncurses_nonl (PHP 4 >= 4.1.0)

Do not translate newline and carriage return / line feed

bool **ncurses_nonl** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_noqiflush (PHP 4 >= 4.1.0)

Do not flush on signal characters

int **ncurses_noqiflush** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_noraw (PHP 4 >= 4.1.0)

Switch terminal out of raw mode

bool **ncurses_noraw** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_noraw() switches the terminal out of raw mode. Raw mode is similar to cbreak mode, in that characters typed are immediately passed through to the user program. The differences that are that in raw mode, the interrupt, quit, suspend and flow control characters are all passed through uninterpreted, instead of generating a signal. Returns TRUE if any error occurred, otherwise FALSE.

See also: **ncurses_raw()**, **ncurses_cbreak()**, **ncurses_nocbreak()**

ncurses_putp (PHP 4 >= 4.2.0)

int **ncurses_putp** (string text) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_qiflush (PHP 4 >= 4.1.0)

Flush on signal characters

```
int ncurses_qiflush ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_raw (PHP 4 >= 4.1.0)

Switch terminal into raw mode

```
bool ncurses_raw ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_raw() places the terminal in raw mode. Raw mode is similar to cbreak mode, in that characters typed are immediately passed through to the user program. The differences that are that in raw mode, the interrupt, quit, suspend and flow control characters are all passed through uninterpreted, instead of generating a signal. Returns TRUE if any error occurred, otherwise FALSE.

See also: `ncurses_noraw()`, `ncurses_cbreak()`, `ncurses_nocbreak()`

ncurses_refresh (PHP 4 >= 4.1.0)

Refresh screen

```
int ncurses_refresh ( int ch) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_resetty (PHP 4 >= 4.1.0)

Restores saved terminal state

bool **ncurses_resetty** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Function **ncurses_resetty()** restores the terminal state, which was previously saved by calling **ncurses_savetty()**. This function always returns `FALSE`.

See also: **ncurses_savetty()**

ncurses_savetty (PHP 4 >= 4.1.0)

Saves terminal state

bool **ncurses_savetty** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Function **ncurses_savetty()** saves the current terminal state. The saved terminal state can be restored with function **ncurses_resetty()**. **ncurses_savetty()** always returns `FALSE`.

See also: **ncurses_resetty()**

ncurses_scr_dump (PHP 4 >= 4.2.0)

Dump screen content to file

int **ncurses_scr_dump** (string filename) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_scr_init (PHP 4 >= 4.2.0)

Initialize screen from file dump

`int ncurses_scr_init (string filename) \linebreak`**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_scr_restore (PHP 4 >= 4.2.0)

Restore screen from file dump

`int ncurses_scr_restore (string filename) \linebreak`**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_scr_set (PHP 4 >= 4.2.0)

Inherit screen from file dump

`int ncurses_scr_set (string filename) \linebreak`**Varování**

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_scrl (PHP 4 >= 4.1.0)

Scroll window content up or down without changing current position

int **ncurses_scrl** (int count) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_slk_attr (PHP 4 >= 4.1.0)

Returns current soft label key attribute

bool **ncurses_slk_attr** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_slk_attr() returns the current soft label key attribute. On error returns TRUE, otherwise FALSE.

ncurses_slk_attroff (PHP 4 >= 4.1.0)

int **ncurses_slk_attroff** (int intarg) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_slk_atron (PHP 4 >= 4.1.0)

```
int ncurses_slk_atron ( int intarg) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_slk_attrset (PHP 4 >= 4.1.0)

```
int ncurses_slk_attrset ( int intarg) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_slk_clear (PHP 4 >= 4.1.0)

Clears soft labels from screen

```
bool ncurses_slk_clear ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

The function **ncurses_slk_clear()** clears soft label keys from screen. Returns TRUE on error, otherwise FALSE.

ncurses_slk_color (PHP 4 >= 4.1.0)

Sets color for soft label keys

```
int ncurses_slk_color ( int intarg) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_slk_init (PHP 4 >= 4.1.0)

Initializes soft label key functions

```
bool ncurses_slk_init ( int format) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Funtion **ncurses_slk_init()** must be called before **ncurses_initscr()** or **ncurses_newterm()** is called. If **ncurses_initscr()** eventually uses a line from stdscr to emulate the soft labels, then *format* determines how the labels are arranged of the screen. Setting *format* to 0 indicates a 3-2-3 arrangement of the labels, 1 indicates a 4-4 arrangement and 2 indicates the PC like 4-4-4 mode, but in addition an index line will be created.

ncurses_slk_noutrefresh (PHP 4 >= 4.1.0)

Copies soft label keys to virtual screen

```
bool ncurses_slk_noutrefresh ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_slk_refresh (PHP 4 >= 4.1.0)

Copies soft label keys to screen

```
bool ncurses_slk_refresh ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_slk_refresh() copies soft label keys from virtual screen to physical screen. Returns **TRUE** on error, otherwise **FALSE**.

ncurses_slk_restore (PHP 4 >= 4.1.0)

Restores soft label keys

```
bool ncurses_slk_restore ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

The function **ncurses_slk_restore()** restores the soft label keys after **ncurses_slk_clear()** has been performed.

ncurses_slk_touch (PHP 4 >= 4.1.0)

Forces output when **ncurses_slk_noutrefresh** is performed

```
bool ncurses_slk_touch ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

The **ncurses_slk_touch()** function forces all the soft labels to be output the next time a **ncurses_slk_noutrefresh()** is performed.

ncurses_standend (PHP 4 >= 4.1.0)

Stop using 'standout' attribute

```
int ncurses_standend ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_standout (PHP 4 >= 4.1.0)

Start using 'standout' attribute

```
int ncurses_standout ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_start_color (PHP 4 >= 4.1.0)

Start using colors

```
int ncurses_start_color ( void) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_termattrs (PHP 4 >= 4.1.0)

Returns a logical OR of all attribute flags supported by terminal

bool **ncurses_termattrs** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_termname (PHP 4 >= 4.2.0)

Returns terminals (short)-name

string **ncurses_termname** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

ncurses_termname() returns terminals shortname. The shortname is truncated to 14 characters. On error **ncurses_termname()** returns NULL.

See also: **ncurses_longname()**

ncurses_timeout (PHP 4 >= 4.1.0)

Set timeout for special key sequences

void **ncurses_timeout** (int millisec) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_typeahead (PHP 4 >= 4.1.0)

Specify different filedescriptor for typeahead checking

```
int ncurses_typeahead ( int fd) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_ungetch (PHP 4 >= 4.1.0)

Put a character back into the input stream

```
int ncurses_ungetch ( int keycode) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_ungetmouse (PHP 4 >= 4.2.0)

Pushes mouse event to queue

```
bool ncurses_ungetmouse ( array mevent) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

`ncurses_getmouse()` pushes a `KEY_MOUSE` event onto the unput queue and associates with this event the given state `sata` and screen-relative character cell coordinates, specified in `mevent`. Event options will be specified in associative array `mevent`:

- "id" : Id to distinguish multiple devices
- "x" : screen relative x-position in character cells
- "y" : screen relative y-position in character cells
- "z" : currently not supported
- "mmask" : Mouse action

ncurses_ungetmouse() returns FALSE on success, otherwise TRUE.

See also: ncurses_getmouse()

ncurses_use_default_colors (PHP 4 >= 4.1.0)

Assign terminal default colors to color id -1

bool **ncurses_use_default_colors** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_use_env (PHP 4 >= 4.1.0)

Control use of environment information about terminal size

void **ncurses_use_env** (bool flag) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_use_extended_names (PHP 4 >= 4.1.0)

Control use of extended names in terminfo descriptions

`int ncurses_use_extended_names (bool flag) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_vidattr (PHP 4 >= 4.1.0)

`int ncurses_vidattr (int intarg) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_vline (PHP 4 >= 4.2.0)

Draw a vertical line at current position using an attributed character and max. n characters long

`int ncurses_vline (int charattr, int n) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

ncurses_wrefresh (PHP 4 >= 4.2.0)

Refresh window on terminal screen

`int ncurses_wrefresh (resource window) \linebreak`

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

undocumented

LXVII. Lotus Notes functions

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

notes_body (PHP 4 >= 4.0.5)

Open the message msg_number in the specified mailbox on the specified server (leave serv

array **notes_body** (string server, string mailbox, int msg_number) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_copy_db (PHP 4 >= 4.0.5)

Create a note using form form_name

string **notes_copy_db** (string from_database_name, string to_database_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_create_db (PHP 4 >= 4.0.5)

Create a Lotus Notes database

bool **notes_create_db** (string database_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_create_note (PHP 4 >= 4.0.5)

Create a note using form form_name

string **notes_create_note** (string database_name, string form_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_drop_db (PHP 4 >= 4.0.5)

Drop a Lotus Notes database

bool **notes_drop_db** (string database_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_find_note (PHP 4 >= 4.0.5)

Returns a note id found in database_name. Specify the name of the note. Leaving type bla

bool **notes_find_note** (string database_name, string name [, string type]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_header_info (PHP 4 >= 4.0.5)

Open the message msg_number in the specified mailbox on the specified server (leave serv

object **notes_header_info** (string server, string mailbox, int msg_number) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_list_msgs (PHP 4 >= 4.0.5)

Returns the notes from a selected database_name

bool **notes_list_msgs** (string db) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_mark_read (PHP 4 >= 4.0.5)

Mark a note_id as read for the User user_name

string **notes_mark_read** (string database_name, string user_name, string note_id) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_mark_unread (PHP 4 >= 4.0.5)

Mark a note_id as unread for the User user_name

string **notes_mark_unread** (string database_name, string user_name, string note_id) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_nav_create (PHP 4 >= 4.0.5)

Create a navigator name, in database_name

bool **notes_nav_create** (string database_name, string name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_search (PHP 4 >= 4.0.5)

Find notes that match keywords in database_name

string **notes_search** (string database_name, string keywords) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_unread (PHP 4 >= 4.0.5)

Returns the unread note id's for the current User user_name

string **notes_unread** (string database_name, string user_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

notes_version (PHP 4 >= 4.0.5)

Get the version Lotus Notes

string **notes_version** (string database_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

LXVIII. Unified ODBC functions

In addition to normal ODBC support, the Unified ODBC functions in PHP allow you to access several databases that have borrowed the semantics of the ODBC API to implement their own API. Instead of maintaining multiple database drivers that were all nearly identical, these drivers have been unified into a single set of ODBC functions.

Poznámka: There is no ODBC involved when connecting to the above databases. The functions that you use to speak natively to them just happen to share the same names and syntax as the ODBC functions. The exception to this is iODBC. Building PHP with iODBC support enables you to use any ODBC-compliant drivers with your PHP applications. iODBC is maintained by OpenLink Software (<http://www.openlinksw.com/>). More information on iODBC, as well as a HOWTO, is available at www.iodbc.org (<http://www.iodbc.org/>).

Requirements

The following databases are supported by the Unified ODBC functions: Adabas D (<http://www.software-ag.com/adabasd/>), IBM DB2 (<http://www.ibm.com/db2/>), iODBC (<http://www.iodbc.org/>), Solid (<http://www.solidtech.com/>), and Sybase SQL Anywhere (<http://www.sybase.com/>). To access these databases you need to have the required libraries installed.

Installation

Please see the Installation on Unix Systems chapter for more information about configuring PHP with these databases.

Runtime Configuration

The behaviour of the ODBC functions is affected by settings in the global configuration file `php.ini`.

Tabulka 1. Unified ODBC Configuration Options

Name	Default	Changeable
<code>odbc.default_db *</code>	NULL	PHP_INI_ALL
<code>odbc.default_user *</code>	NULL	PHP_INI_ALL
<code>odbc.default_pw *</code>	NULL	PHP_INI_ALL
<code>odbc.allow_persistent</code>	"1"	PHP_INI_SYSTEM
<code>odbc.check_persistent</code>	"1"	PHP_INI_SYSTEM
<code>odbc.max_persistent</code>	"-1"	PHP_INI_SYSTEM
<code>odbc.max_links</code>	"-1"	PHP_INI_SYSTEM
<code>odbc.defaultlrl</code>	"4096"	PHP_INI_ALL
<code>odbc.defaultbinmode</code>	"1"	PHP_INI_ALL

Poznámka: Entries marked with * are not implemented yet.

For further details and definition of the PHP_INI_* constants see ini_set().

Here is a short explanation of the configuration directives.

odbc.default_db string

ODBC data source to use if none is specified in `odbc_connect()` or `odbc_pconnect()`.

odbc.default_user string

User name to use if none is specified in `odbc_connect()` or `odbc_pconnect()`.

odbc.default_pw string

Password to use if none is specified in `odbc_connect()` or `odbc_pconnect()`.

odbc.allow_persistent boolean

Whether to allow persistent ODBC connections.

odbc.check_persistent boolean

Check that a connection is still valid before reuse.

odbc.max_persistent integer

The maximum number of persistent ODBC connections per process.

odbc.max_links integer

The maximum number of ODBC connections per process, including persistent connections.

odbc.defaultlrl integer

Handling of LONG fields. Specifies the number of bytes returned to variables.

odbc.defaultbinmode integer

Handling of binary data.

Resource types

Toto rozšíření nemá definován žádný typ prostředku (resource).

Predefined constants

Toto rozšíření nemá definovány žádné konstanty.

odbc_autocommit (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Toggle autocommit behaviour

bool **odbc_autocommit** (resource connection_id [, bool OnOff]) \linebreak

Without the *OnOff* parameter, this function returns auto-commit status for *connection_id*. TRUE is returned if auto-commit is on, FALSE if it is off or an error occurs.

If *OnOff* is TRUE, auto-commit is enabled, if it is FALSE auto-commit is disabled. Returns TRUE on success, FALSE on failure.

By default, auto-commit is on for a connection. Disabling auto-commit is equivalent with starting a transaction.

See also `odbc_commit()` and `odbc_rollback()`.

odbc_binmode (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Handling of binary column data

int **odbc_binmode** (resource result_id, int mode) \linebreak

(ODBC SQL types affected: BINARY, VARBINARY, LONGVARBINARY)

- ODBC_BINMODE_PASSTHRU: Passthru BINARY data
- ODBC_BINMODE_RETURN: Return as is
- ODBC_BINMODE_CONVERT: Convert to char and return

When binary SQL data is converted to character C data, each byte (8 bits) of source data is represented as two ASCII characters. These characters are the ASCII character representation of the number in its hexadecimal form. For example, a binary 00000001 is converted to "01" and a binary 11111111 is converted to "FF".

Tabulka 1. LONGVARBINARY handling

binmode	longreadlen	result
ODBC_BINMODE_PASSTHRU	0	passthru
ODBC_BINMODE_RETURN	0	passthru
ODBC_BINMODE_CONVERT	0	passthru
ODBC_BINMODE_PASSTHRU	0	passthru
ODBC_BINMODE_PASSTHRU	>0	passthru
ODBC_BINMODE_RETURN	>0	return as is
ODBC_BINMODE_CONVERT	>0	return as char

If `odbc_fetch_into()` is used, passthru means that an empty string is returned for these columns.

If `result_id` is 0, the settings apply as default for new results.

Poznámka: Default for `longreadlen` is 4096 and `binmode` defaults to `ODBC_BINMODE_RETURN`. Handling of binary long columns is also affected by `odbc_longreadlen()`

odbc_close (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Close an ODBC connection

void **odbc_close** (resource connection_id) \linebreak

odbc_close() will close down the connection to the database server associated with the given connection identifier.

Poznámka: This function will fail if there are open transactions on this connection. The connection will remain open in this case.

odbc_close_all (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Close all ODBC connections

void **odbc_close_all** (void) \linebreak

odbc_close_all() will close down all connections to database server(s).

Poznámka: This function will fail if there are open transactions on a connection. This connection will remain open in this case.

odbc_columnprivileges (PHP 4 >= 4.0.0)

Returns a result identifier that can be used to fetch a list of columns and associated privileges

int **odbc_columnprivileges** (resource connection_id [, string qualifier [, string owner [, string table_name [, string column_name]]]]) \linebreak

Lists columns and associated privileges for the given table. Returns an ODBC result identifier or FALSE on failure.

The result set has the following columns:

- TABLE_QUALIFIER
- TABLE_OWNER
- TABLE_NAME
- GRANTOR
- GRANTEE
- PRIVILEGE
- IS_GRANTABLE

The result set is ordered by TABLE_QUALIFIER, TABLE_OWNER and TABLE_NAME.

The *column_name* argument accepts search patterns ('%' to match zero or more characters and '_' to match a single character).

odbc_columns (PHP 4 >= 4.0.0)

Lists the column names in specified tables. Returns a result identifier containing the information.

int odbc_columns (resource connection_id [, string qualifier [, string owner [, string table_name [, string column_name]]]]) \linebreak

Lists all columns in the requested range. Returns an ODBC result identifier or FALSE on failure.

The result set has the following columns:

- TABLE_QUALIFIER
- TABLE_OWNER
- TABLE_NAME
- COLUMN_NAME
- DATA_TYPE
- TYPE_NAME
- PRECISION
- LENGTH
- SCALE
- RADIX
- NULLABLE
- REMARKS

The result set is ordered by TABLE_QUALIFIER, TABLE_OWNER and TABLE_NAME.

The *owner*, *table_name* and *column_name* arguments accept search patterns ('%' to match zero or more characters and '_' to match a single character).

See also odbc_columnprivileges() to retrieve associated privileges.

odbc_commit (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Commit an ODBC transaction

bool **odbc_commit** (resource connection_id) \linebreak

Returns: TRUE on success, FALSE on failure. All pending transactions on *connection_id* are committed.

odbc_connect (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Connect to a datasource

resource **odbc_connect** (string dsn, string user, string password [, int cursor_type]) \linebreak

Returns an ODBC connection id or 0 (FALSE) on error.

The connection id returned by this functions is needed by other ODBC functions. You can have multiple connections open at once. The optional fourth parameter sets the type of cursor to be used for this connection. This parameter is not normally needed, but can be useful for working around problems with some ODBC drivers.

With some ODBC drivers, executing a complex stored procedure may fail with an error similar to: "Cannot open a cursor on a stored procedure that has anything other than a single select statement in it". Using SQL_CUR_USE_ODBC may avoid that error. Also, some drivers don't support the optional row_number parameter in odbc_fetch_row(). SQL_CUR_USE_ODBC might help in that case, too.

The following constants are defined for cursortype:

- SQL_CUR_USE_IF_NEEDED
- SQL_CUR_USE_ODBC
- SQL_CUR_USE_DRIVER
- SQL_CUR_DEFAULT

For persistent connections see odbc_pconnect().

odbc_cursor (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Get cursorname

string **odbc_cursor** (resource result_id) \linebreak

odbc_cursor will return a cursorname for the given result_id.

odbc_do (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Synonym for `odbc_exec()`

resource **odbc_do** (resource `conn_id`, string `query`) \linebreak

odbc_do() will execute a query on the given connection.

odbc_error (PHP 4 >= 4.0.5)

Get the last error code

string **odbc_error** ([resource `connection_id`]) \linebreak

Returns a six-digit ODBC state, or an empty string if there has been no errors. If *connection_id* is specified, the last state of that connection is returned, else the last state of any connection is returned.

See also: `odbc_errormsg()` and `odbc_exec()`.

odbc_errormsg (PHP 4 >= 4.0.5)

Get the last error message

string **odbc_errormsg** ([resource `connection_id`]) \linebreak

Returns a string containing the last ODBC error message, or an empty string if there has been no errors. If *connection_id* is specified, the last state of that connection is returned, else the last state of any connection is returned.

See also: `odbc_error()` and `odbc_exec()`.

odbc_exec (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Prepare and execute a SQL statement

resource **odbc_exec** (resource `connection_id`, string `query_string`) \linebreak

Returns `FALSE` on error. Returns an ODBC result identifier if the SQL command was executed successfully.

odbc_exec() will send an SQL statement to the database server specified by *connection_id*. This parameter must be a valid identifier returned by `odbc_connect()` or `odbc_pconnect()`.

See also: `odbc_prepare()` and `odbc_execute()` for multiple execution of SQL statements.

odbc_execute (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Execute a prepared statement

resource **odbc_execute** (resource result_id [, array parameters_array]) \linebreak

Executes a statement prepared with `odbc_prepare()`. Returns `TRUE` on successful execution; `FALSE` otherwise. The array *parameters_array* only needs to be given if you really have parameters in your statement.

Parameters in *parameter_array* will be substituted for placeholders in the prepared statement in order.

Any parameters in *parameter_array* which start and end with single quotes will be taken as the name of a file to read and send to the database server as the data for the appropriate placeholder.

Poznámka: As of PHP 4.1.1, this file reading functionality has the following restrictions:

- File reading is *not* subject to any safe mode or safe mode restrictions. This is fixed in PHP 4.2.0.
- Remote files are not supported.
- If you wish to store a string which actually begins and ends with single quotes, you must escape them or add a space or other non-single-quote character to the beginning or end of the parameter, which will prevent the parameter's being taken as a file name. If this is not an option, then you must use another mechanism to store the string, such as executing the query directly with `odbc_exec()`.

odbc_fetch_array (PHP 4 >= 4.0.2)

Fetch a result row as an associative array

array **odbc_fetch_array** (resource result [, int rownumber]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

odbc_fetch_into (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Fetch one result row into array

bool **odbc_fetch_into** (resource result_id [, int rownumber, array result_array]) \linebreak resource **odbc_fetch_into**
 (resource result_id, array result_array [, int rownumber]) \linebreak

Returns the number of columns in the result; FALSE on error. *result_array* must be passed by reference, but it can be of any type since it will be converted to type array. The array will contain the column values starting at array index 0.

As of PHP 4.0.5 the *result_array* does not need to be passed by reference any longer.

As of PHP 4.0.6 the *rownumber* cannot be passed as a constant, but rather as a variable.

As of PHP 4.2.0 the *result_array* and *rownumber* have been swapped. This allows the rownumber to be a constant again. This change will also be the last one to this function.

Příklad 1. odbc_fetch_into() pre 4.0.6 example

```
$rc = odbc_fetch_into($res_id, $my_array);
```

or

```
$rc = odbc_fetch_into($res_id, $row, $my_array);
```

```
$rc = odbc_fetch_into($res_id, 1, $my_array);
```

Příklad 2. odbc_fetch_into() 4.0.6 example

```
$rc = odbc_fetch_into($res_id, $my_array);
```

or

```
$row = 1;  
$rc = odbc_fetch_into($res_id, $row, $my_array);
```

Příklad 3. odbc_fetch_into() 4.2.0 example

```
$rc = odbc_fetch_into($res_id, $my_array);
```

or

```
$rc = odbc_fetch_into($res_id, $my_array, 2);
```

odbc_fetch_object (PHP 4 >= 4.0.2)

Fetch a result row as an object

object **odbc_fetch_object** (resource result [, int rownumber]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

odbc_fetch_row (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Fetch a row

bool **odbc_fetch_row** (resource result_id [, int row_number]) \linebreak

If **odbc_fetch_row()** was succesful (there was a row), **TRUE** is returned. If there are no more rows, **FALSE** is returned.

odbc_fetch_row() fetches a row of the data that was returned by **odbc_do()** / **odbc_exec()**. After **odbc_fetch_row()** is called, the fields of that row can be accessed with **odbc_result()**.

If *row_number* is not specified, **odbc_fetch_row()** will try to fetch the next row in the result set. Calls to **odbc_fetch_row()** with and without *row_number* can be mixed.

To step through the result more than once, you can call **odbc_fetch_row()** with *row_number* 1, and then continue doing **odbc_fetch_row()** without *row_number* to review the result. If a driver doesn't support fetching rows by number, the *row_number* parameter is ignored.

odbc_field_len (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Get the length (precision) of a field

int **odbc_field_len** (resource result_id, int field_number) \linebreak

odbc_field_len() will return the length of the field referecend by number in the given ODBC result identifier. Field numbering starts at 1.

See also: **odbc_field_scale()** to get the scale of a floating point number.

odbc_field_name (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Get the columnname

string **odbc_field_name** (resource result_id, int field_number) \linebreak

odbc_field_name() will return the name of the field occupying the given column number in the given ODBC result identifier. Field numbering starts at 1. *FALSE* is returned on error.

odbc_field_num (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Return column number

int **odbc_field_num** (resource result_id, string field_name) \linebreak

odbc_field_num() will return the number of the column slot that corresponds to the named field in the given ODBC result identifier. Field numbering starts at 1. *FALSE* is returned on error.

odbc_field_precision (PHP 4 >= 4.0.0)

Synonym for `odbc_field_len()`

string **odbc_field_precision** (resource result_id, int field_number) \linebreak

odbc_field_precision() will return the precision of the field refereced by number in the given ODBC result identifier.

See also: `odbc_field_scale()` to get the scale of a floating point number.

odbc_field_scale (PHP 4 >= 4.0.0)

Get the scale of a field

string **odbc_field_scale** (resource result_id, int field_number) \linebreak

odbc_field_scale() will return the scale of the field refereced by number in the given ODBC result identifier.

odbc_field_type (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Datatype of a field

string **odbc_field_type** (resource result_id, int field_number) \linebreak

odbc_field_type() will return the SQL type of the field refereced by number in the given ODBC result identifier. Field numbering starts at 1.

odbc_foreignkeys (PHP 4 >= 4.0.0)

Returns a list of foreign keys in the specified table or a list of foreign keys in other tables that refer to the primary key in the specified table

resource **odbc_foreignkeys** (resource connection_id, string pk_qualifier, string pk_owner, string pk_table, string fk_qualifier, string fk_owner, string fk_table) \linebreak

odbc_foreignkeys() retrieves information about foreign keys. Returns an ODBC result identifier or FALSE on failure.

The result set has the following columns:

- PKTABLE_QUALIFIER
- PKTABLE_OWNER
- PKTABLE_NAME
- PKCOLUMN_NAME
- FKTABLE_QUALIFIER
- FKTABLE_OWNER
- FKTABLE_NAME
- FKCOLUMN_NAME
- KEY_SEQ
- UPDATE_RULE
- DELETE_RULE
- FK_NAME
- PK_NAME

If *pk_table* contains a table name, **odbc_foreignkeys()** returns a result set containing the primary key of the specified table and all of the foreign keys that refer to it.

If *fk_table* contains a table name, **odbc_foreignkeys()** returns a result set containing all of the foreign keys in the specified table and the primary keys (in other tables) to which they refer.

If both *pk_table* and *fk_table* contain table names, **odbc_foreignkeys()** returns the foreign keys in the table specified in *fk_table* that refer to the primary key of the table specified in *pk_table*. This should be one key at most.

odbc_free_result (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Free resources associated with a result

bool **odbc_free_result** (resource result_id) \linebreak

Always returns TRUE.

odbc_free_result() only needs to be called if you are worried about using too much memory while your script is running. All result memory will automatically be freed when the script is finished. But,

if you are sure you are not going to need the result data anymore in a script, you may call **odbc_free_result()**, and the memory associated with *result_id* will be freed.

Poznámka: If auto-commit is disabled (see `odbc_autocommit()`) and you call **odbc_free_result()** before committing, all pending transactions are rolled back.

odbc_gettypeinfo (PHP 4 >= 4.0.0)

Returns a result identifier containing information about data types supported by the data source.

int odbc_gettypeinfo (resource connection_id [, int data_type]) \linebreak

Retrieves information about data types supported by the data source. Returns an ODBC result identifier or `FALSE` on failure. The optional argument *data_type* can be used to restrict the information to a single data type.

The result set has the following columns:

- TYPE_NAME
- DATA_TYPE
- PRECISION
- LITERAL_PREFIX
- LITERAL_SUFFIX
- CREATE_PARAMS
- NULLABLE
- CASE_SENSITIVE
- SEARCHABLE
- UNSIGNED_ATTRIBUTE
- MONEY
- AUTO_INCREMENT
- LOCAL_TYPE_NAME
- MINIMUM_SCALE
- MAXIMUM_SCALE

The result set is ordered by `DATA_TYPE` and `TYPE_NAME`.

odbc_longreadlen (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Handling of LONG columns

int **odbc_longreadlen** (resource result_id, int length) \linebreak

(ODBC SQL types affected: LONG, LONGVARBINARY) The number of bytes returned to PHP is controlled by the parameter length. If it is set to 0, Long column data is passed thru to the client.

Poznámka: Handling of LONGVARBINARY columns is also affected by odbc_binmode().

odbc_next_result (PHP 4 >= 4.0.5)

Checks if multiple results are available

bool **odbc_next_result** (resource result_id) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

odbc_num_fields (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Number of columns in a result

int **odbc_num_fields** (resource result_id) \linebreak

odbc_num_fields() will return the number of fields (columns) in an ODBC result. This function will return -1 on error. The argument is a valid result identifier returned by odbc_exec().

odbc_num_rows (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Number of rows in a result

int **odbc_num_rows** (resource result_id) \linebreak

odbc_num_rows() will return the number of rows in an ODBC result. This function will return -1 on error. For INSERT, UPDATE and DELETE statements **odbc_num_rows()** returns the number of rows affected. For a SELECT clause this can be the number of rows available.

Note: Using **odbc_num_rows()** to determine the number of rows available after a SELECT will return -1 with many drivers.

odbc_pconnect (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Open a persistent database connection

```
int odbc_pconnect ( string dsn, string user, string password [, int cursor_type]) \linebreak
```

Returns an ODBC connection id or 0 (`FALSE`) on error. This function is much like `odbc_connect()`, except that the connection is not really closed when the script has finished. Future requests for a connection with the same *dsn*, *user*, *password* combination (via `odbc_connect()` and `odbc_pconnect()`) can reuse the persistent connection.

Poznámka: Persistent connections have no effect if PHP is used as a CGI program.

For information about the optional `cursor_type` parameter see the `odbc_connect()` function. For more information on persistent connections, refer to the PHP FAQ.

odbc_prepare (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Prepares a statement for execution

```
resource odbc_prepare ( resource connection_id, string query_string) \linebreak
```

Returns `FALSE` on error.

Returns an ODBC result identifier if the SQL command was prepared successfully. The result identifier can be used later to execute the statement with `odbc_execute()`.

odbc_primarykeys (PHP 4 >= 4.0.0)

Returns a result identifier that can be used to fetch the column names that comprise the primary key for a table

```
resource odbc_primarykeys ( resource connection_id, string qualifier, string owner, string table) \linebreak
```

Returns the column names that comprise the primary key for a table. Returns an ODBC result identifier or `FALSE` on failure.

The result set has the following columns:

- TABLE_QUALIFIER
- TABLE_OWNER
- TABLE_NAME
- COLUMN_NAME
- KEY_SEQ
- PK_NAME

odbc_procedurecolumns (PHP 4 >= 4.0.0)

Retrieve information about parameters to procedures

resource **odbc_procedurecolumns** (resource connection_id [, string qualifier [, string owner [, string proc
[, string column]]]]) \linebreak

Returns the list of input and output parameters, as well as the columns that make up the result set for the specified procedures. Returns an ODBC result identifier or `FALSE` on failure.

The result set has the following columns:

- PROCEDURE_QUALIFIER
- PROCEDURE_OWNER
- PROCEDURE_NAME
- COLUMN_NAME
- COLUMN_TYPE
- DATA_TYPE
- TYPE_NAME
- PRECISION
- LENGTH
- SCALE
- RADIX
- NULLABLE
- REMARKS

The result set is ordered by PROCEDURE_QUALIFIER, PROCEDURE_OWNER, PROCEDURE_NAME and COLUMN_TYPE.

The *owner*, *proc* and *column* arguments accept search patterns ('%' to match zero or more characters and '_' to match a single character).

odbc_procedures (PHP 4 >= 4.0.0)

Get the list of procedures stored in a specific data source. Returns a result identifier containing the information.

resource **odbc_procedures** (resource connection_id [, string qualifier [, string owner [, string name]]]) \linebreak

Lists all procedures in the requested range. Returns an ODBC result identifier or `FALSE` on failure.

The result set has the following columns:

- PROCEDURE_QUALIFIER
- PROCEDURE_OWNER
- PROCEDURE_NAME
- NUM_INPUT_PARAMS
- NUM_OUTPUT_PARAMS
- NUM_RESULT_SETS
- REMARKS
- PROCEDURE_TYPE

The *owner* and *name* arguments accept search patterns ('%' to match zero or more characters and '_' to match a single character).

odbc_result (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Get result data

string **odbc_result** (resource result_id, mixed field) \linebreak

Returns the contents of the field.

field can either be an integer containing the column number of the field you want; or it can be a string containing the name of the field. For example:

```
$item_3 = odbc_result ($Query_ID, 3);
$item_val = odbc_result ($Query_ID, "val");
```

The first call to **odbc_result()** returns the value of the third field in the current record of the query result. The second function call to **odbc_result()** returns the value of the field whose field name is "val" in the current record of the query result. An error occurs if a column number parameter for a field is less than one or exceeds the number of columns (or fields) in the current record. Similarly, an error occurs if a field with a name that is not one of the fieldnames of the table(s) that is(are) being queried.

Field indices start from 1. Regarding the way binary or long column data is returned refer to **odbc_binmode()** and **odbc_longreadlen()**.

odbc_result_all (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Print result as HTML table

int **odbc_result_all** (resource result_id [, string format]) \linebreak

Returns the number of rows in the result or FALSE on error.

odbc_result_all() will print all rows from a result identifier produced by `odbc_exec()`. The result is printed in HTML table format. With the optional string argument *format*, additional overall table formatting can be done.

odbc_rollback (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Rollback a transaction

int odbc_rollback (resource *connection_id*) \linebreak

Rolls back all pending statements on *connection_id*. Returns `TRUE` on success, `FALSE` on failure.

odbc_setoption (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Adjust ODBC settings. Returns `FALSE` if an error occurs, otherwise `TRUE`.

int odbc_setoption (resource *id*, int *function*, int *option*, int *param*) \linebreak

This function allows fiddling with the ODBC options for a particular connection or query result. It was written to help find work arounds to problems in quirky ODBC drivers. You should probably only use this function if you are an ODBC programmer and understand the effects the various options will have. You will certainly need a good ODBC reference to explain all the different options and values that can be used. Different driver versions support different options.

Because the effects may vary depending on the ODBC driver, use of this function in scripts to be made publicly available is strongly discouraged. Also, some ODBC options are not available to this function because they must be set before the connection is established or the query is prepared. However, if on a particular job it can make PHP work so your boss doesn't tell you to use a commercial product, that's all that really matters.

id is a connection id or result id on which to change the settings. For `SQLSetConnectOption()`, this is a connection id. For `SQLSetStmtOption()`, this is a result id.

Function is the ODBC function to use. The value should be 1 for `SQLSetConnectOption()` and 2 for `SQLSetStmtOption()`.

Parameter *option* is the option to set.

Parameter *param* is the value for the given *option*.

Příklad 1. ODBC Setoption Examples

```
// 1. Option 102 of SQLSetConnectOption() is SQL_AUTOCOMMIT.
//    Value 1 of SQL_AUTOCOMMIT is SQL_AUTOCOMMIT_ON.
//    This example has the same effect as
//    odbc_autocommit($conn, true);

odbc_setoption ($conn, 1, 102, 1);

// 2. Option 0 of SQLSetStmtOption() is SQL_QUERY_TIMEOUT.
//    This example sets the query to timeout after 30 seconds.
```

```
$result = odbc_prepare ($conn, $sql);
odbc_setoption ($result, 2, 0, 30);
odbc_execute ($result);
```

odbc_specialcolumns (PHP 4 >= 4.0.0)

Returns either the optimal set of columns that uniquely identifies a row in the table or columns that are automatically updated when any value in the row is updated by a transaction

resource **odbc_specialcolumns** (resource connection_id, int type, string qualifier, string owner, string table, int scope, int nullable) \linebreak

When the type argument is `SQL_BEST_ROWID`, **odbc_specialcolumns()** returns the column or columns that uniquely identify each row in the table.

When the type argument is `SQL_ROWVER`, **odbc_specialcolumns()** returns the optimal column or set of columns that, by retrieving values from the column or columns, allows any row in the specified table to be uniquely identified.

Returns an ODBC result identifier or `FALSE` on failure.

The result set has the following columns:

- SCOPE
- COLUMN_NAME
- DATA_TYPE
- TYPE_NAME
- PRECISION
- LENGTH
- SCALE
- PSEUDO_COLUMN

The result set is ordered by SCOPE.

odbc_statistics (PHP 4 >= 4.0.0)

Retrieve statistics about a table

resource **odbc_statistics** (resource connection_id, string qualifier, string owner, string table_name, int unique, int accuracy) \linebreak

Get statistics about a table and it's indexes. Returns an ODBC result identifier or `FALSE` on failure.

The result set has the following columns:

- TABLE_QUALIFIER
- TABLE_OWNER
- TABLE_NAME
- NON_UNIQUE
- INDEX_QUALIFIER
- INDEX_NAME
- TYPE
- SEQ_IN_INDEX
- COLUMN_NAME
- COLLATION
- CARDINALITY
- PAGES
- FILTER_CONDITION

The result set is ordered by NON_UNIQUE, TYPE, INDEX_QUALIFIER, INDEX_NAME and SEQ_IN_INDEX.

odbc_tableprivileges (PHP 4 >= 4.0.0)

Lists tables and the privileges associated with each table

`int odbc_tableprivileges (resource connection_id [, string qualifier [, string owner [, string name]]])` \line-break

Lists tables in the requested range and the privileges associated with each table. Returns an ODBC result identifier or `FALSE` on failure.

The result set has the following columns:

- TABLE_QUALIFIER
- TABLE_OWNER
- TABLE_NAME
- GRANTOR
- GRANTEE
- PRIVILEGE
- IS_GRANTABLE

The result set is ordered by TABLE_QUALIFIER, TABLE_OWNER and TABLE_NAME.

The *owner* and *name* arguments accept search patterns ('%' to match zero or more characters and '_' to match a single character).

odbc_tables (PHP 3 >= 3.0.17, PHP 4 >= 4.0.0)

Get the list of table names stored in a specific data source. Returns a result identifier containing the information.

```
int odbc_tables ( resource connection_id [, string qualifier [, string owner [, string name [, string types]]]])  
\linebreak
```

Lists all tables in the requested range. Returns an ODBC result identifier or `FALSE` on failure.

The result set has the following columns:

- TABLE_QUALIFIER
- TABLE_OWNER
- TABLE_NAME
- TABLE_TYPE
- REMARKS

The result set is ordered by TABLE_TYPE, TABLE_QUALIFIER, TABLE_OWNER and TABLE_NAME.

The *owner* and *name* arguments accept search patterns ('%' to match zero or more characters and '_' to match a single character).

To support enumeration of qualifiers, owners, and table types, the following special semantics for the *qualifier*, *owner*, *name*, and *table_type* are available:

- If *qualifier* is a single percent character (%) and *owner* and *name* are empty strings, then the result set contains a list of valid qualifiers for the data source. (All columns except the TABLE_QUALIFIER column contain NULLs.)
- If *owner* is a single percent character (%) and *qualifier* and *name* are empty strings, then the result set contains a list of valid owners for the data source. (All columns except the TABLE_OWNER column contain NULLs.)
- If *table_type* is a single percent character (%) and *qualifier*, *owner* and *name* are empty strings, then the result set contains a list of valid table types for the data source. (All columns except the TABLE_TYPE column contain NULLs.)

If *table_type* is not an empty string, it must contain a list of comma-separated values for the types of interest; each value may be enclosed in single quotes (') or unquoted. For example, "'TABLE','VIEW'" or "TABLE, VIEW". If the data source does not support a specified table type, **odbc_tables()** does not return any results for that type.

See also `odbc_tableprivileges()` to retrieve associated privileges.

LXIX. Oracle 8 functions

These functions allow you to access Oracle8 and Oracle7 databases. It uses the Oracle8 Call-Interface (OCI8). You will need the Oracle8 client libraries to use this extension.

This extension is more flexible than the standard Oracle extension. It supports binding of global and local PHP variables to Oracle placeholders, has full LOB, FILE and ROWID support and allows you to use user-supplied define variables.

Before using this extension, make sure that you have set up your oracle environment variables properly for the Oracle user, as well as your web daemon user. The variables you might need to set are as follows:

- ORACLE_HOME
- ORACLE_SID
- LD_PRELOAD
- LD_LIBRARY_PATH
- NLS_LANG
- ORA_NLS33

After setting up the environment variables for your webserver user, be sure to also add the webserver user (nobody, www) to the oracle group.

If your webserver doesn't start or crashes at startup: Check that Apache is linked with the pthread library:

```
# ldd /www/apache/bin/httpd
libpthread.so.0 => /lib/libpthread.so.0 (0x4001c000)
libm.so.6 => /lib/libm.so.6 (0x4002f000)
libcrypt.so.1 => /lib/libcrypt.so.1 (0x4004c000)
libdl.so.2 => /lib/libdl.so.2 (0x4007a000)
libc.so.6 => /lib/libc.so.6 (0x4007e000)
/lib/ld-linux.so.2 => /lib/ld-linux.so.2 (0x40000000)
```

If the libpthread is not listed you have to reinstall Apache:

```
# cd /usr/src/apache_1.3.xx
# make clean
# LIBS=-lpthread ./config.status
# make
# make install
```

Příklad 1. OCI Hints

```

<?php
// by sergo@bacup.ru

// Use option: OCI_DEFAULT for execute command to delay execution
OCIExecute($stmt, OCI_DEFAULT);

// for retrieve data use (after fetch):

$result = OCIResult($stmt, $n);
if (is_object ($result)) $result = $result->load();

// For INSERT or UPDATE statement use:

$sql = "insert into table (field1, field2) values (field1 = 'value',
    field2 = empty_clob()) returning field2 into :field2";
OCIParse($conn, $sql);
$clob = OCINewDescriptor($conn, OCI_D_LOB);
OCIBindByName ($stmt, ":field2", &$clob, -1, OCI_B_CLOB);
OCIExecute($stmt, OCI_DEFAULT);
$clob->save ("some text");
OCICommit($conn);

?>

```

You can easily access stored procedures in the same way as you would from the commands line.

Příklad 2. Using Stored Procedures

```

<?php
// by webmaster@remoterealty.com
$sth = OCIParse ( $dbh, "begin sp_newaddress( :address_id, '$firstname',
    '$lastname', '$company', '$address1', '$address2', '$city', '$state',
    '$postalcode', '$country', :error_code );end;" );

// This calls stored procedure sp_newaddress, with :address_id being an
// in/out variable and :error_code being an out variable.
// Then you do the binding:

OCIBindByName ( $sth, ":address_id", $addr_id, 10 );
OCIBindByName ( $sth, ":error_code", $errorcode, 10 );
OCIExecute ( $sth );

?>

```


OCIBindByName (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Bind a PHP variable to an Oracle Placeholder

int **OCIBindByName** (int stmt, string ph_name, mixed & variable, int length [, int type]) \linebreak

OCIBindByName() binds the PHP variable *variable* to the Oracle placeholder *ph_name*. Whether it will be used for input or output will be determined run-time, and the necessary storage space will be allocated. The *length* parameter sets the maximum length for the bind. If you set *length* to -1 **OCIBindByName()** will use the current length of *variable* to set the maximum length.

If you need to bind an abstract Datatype (LOB/ROWID/BFILE) you need to allocate it first using **OCINewDescriptor()** function. The *length* is not used for abstract Datatypes and should be set to -1. The *type* variable tells oracle, what kind of descriptor we want to use. Possible values are: OCI_B_FILE (Binary-File), OCI_B_CFILE (Character-File), OCI_B_CLOB (Character-LOB), OCI_B_BLOB (Binary-LOB) and OCI_B_ROWID (ROWID).

Příklad 1. OCIDefineByName

```
<?php
/* OCIBindByPos example thies@thieso.net (980221)
   inserts 3 records into emp, and uses the ROWID for updating the
   records just after the insert.
*/

$conn = OCILogon("scott","tiger");

$stmt = OCIParse($conn,"insert into emp (empno, ename) ".
    "values (:empno,:ename) ".
    "returning ROWID into :rid");

$data = array(1111 => "Larry", 2222 => "Bill", 3333 => "Jim");

$rowid = OCINewDescriptor($conn,OCI_D_ROWID);

OCIBindByName($stmt,":empno",&$empno,32);
OCIBindByName($stmt,":ename",&$ename,32);
OCIBindByName($stmt,":rid",&$rowid,-1,OCI_B_ROWID);

$update = OCIParse($conn,"update emp set sal = :sal where ROWID = :rid");
OCIBindByName($update,":rid",&$rowid,-1,OCI_B_ROWID);
OCIBindByName($update,":sal",&$sal,32);

$sal = 10000;

while (list($empno,$ename) = each($data)) {
    OCIExecute($stmt);
    OCIExecute($update);
}

$rowid->free();

OCIFreeStatement($update);
OCIFreeStatement($stmt);
```

```

$stmt = OCIParse($conn,"select * from emp where empno in (1111,2222,3333)");
OCIExecute($stmt);
while (OCIFetchInto($stmt,&$arr,OCI_ASSOC)) {
    var_dump($arr);
}
OCIFreeStatement($stmt);

/* delete our "junk" from the emp table.... */
$stmt = OCIParse($conn,"delete from emp where empno in (1111,2222,3333)");
OCIExecute($stmt);
OCIFreeStatement($stmt);

OCILogoff($conn);
?>

```

Varování

It is a bad idea to use magic quotes and **OciBindByName()** simultaneously as no quoting is needed on quoted variables and any quotes magically applied will be written into your database as **OciBindByName()** is not able to distinguish magically added quotings from those added by intention.

OCICancel (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Cancel reading from cursor

```
int OCICancel ( int stmt) \linebreak
```

If you do not want read more data from a cursor, then call **OCICancel()**.

OCICollAppend (PHP 4 >= 4.0.6)

Coming soon

```
string OCICollAppend ( object collection, object object) \linebreak
```

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCICollAssign (PHP 4 >= 4.0.6)

Coming soon

string **OCICollAssign** (object collection, object object) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCICollAssignElem (PHP 4 >= 4.0.6)

Coming soon

string **OCICollAssignElem** (object collection, string ndx, string val) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCICollGetElem (PHP 4 >= 4.0.6)

Coming soon

string **OCICollGetElem** (object collection, string ndx) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCICollMax (PHP 4 >= 4.0.6)

Coming soon

string **OCICollMax** (object collection) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCICollSize (PHP 4 >= 4.0.6)

Coming soon

string **OCICollSize** (object collection) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCICollTrim (PHP 4 >= 4.0.6)

Coming soon

string **OCICollTrim** (object collection, int num) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCIColumnIsNULL (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Test whether a result column is NULL

int **OCIColumnIsNULL** (int stmt, mixed column) \linebreak

OCIColumnIsNULL() returns `TRUE` if the returned column *column* in the result from the statement *stmt* is `NULL`. You can either use the column-number (1-Based) or the column-name for the *col* parameter.

OCIColumnName (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

Returns the name of a column

string **OCIColumnName** (int stmt, int col) \linebreak

OCIColumnName() returns the name of the column corresponding to the column number (1-based) that is passed in.

Příklad 1. OCIColumnName

```
<?php
    print "<HTML><PRE>\n";
    $conn = OCILogon("scott", "tiger");
    $stmt = OCIParse($conn,"select * from emp");
    OCIExecute($stmt);
    print "<TABLE BORDER=\\"1\\">";
    print "<TR>";
    print "<TH>Name</TH>";
    print "<TH>Type</TH>";
    print "<TH>Length</TH>";
    print "</TR>";
    $ncols = OCINumCols($stmt);
    for ( $i = 1; $i <= $ncols; $i++ ) {
        $column_name = OCIColumnName($stmt,$i);
        $column_type = OCIColumnType($stmt,$i);
        $column_size = OCIColumnSize($stmt,$i);
        print "<TR>";
        print "<TD>$column_name</TD>";
        print "<TD>$column_type</TD>";
        print "<TD>$column_size</TD>";
        print "</TR>";
    }
    print "</TABLE>\n";
    OCIFreeStatement($stmt);
    OCILogoff($conn);
    print "</PRE>";
    print "</HTML>\n";
?>
```

See also **OCINumCols()**, **OCIColumnType()**, and **OCIColumnSize()**.

OCIColumnPrecision (PHP 4 >= 4.0.0)

Coming soon

int **OCIColumnPrecision** (int stmt, int col) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCIColumnScale (PHP 4 >= 4.0.0)

Coming soon

int **OCIColumnScale** (int stmt, int col) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCIColumnSize (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Return result column size

int **OCIColumnSize** (int stmt, mixed column) \linebreak

OCIColumnSize() returns the size of the column as given by Oracle. You can either use the column-number (1-Based) or the column-name for the *col* parameter.

Příklad 1. OCIColumnSize

```
<?php
    print "<HTML><PRE>\n";
    $conn = OCILogon("scott", "tiger");
    $stmt = OCIParse($conn,"select * from emp");
    OCIExecute($stmt);
    print "<TABLE BORDER=\"1\">";
    print "<TR>";
    print "<TH>Name</TH>";
    print "<TH>Type</TH>";
    print "<TH>Length</TH>";
    print "</TR>";
    $ncols = OCINumCols($stmt);
    for ( $i = 1; $i <= $ncols; $i++ ) {
        $column_name = OCIColumnName($stmt,$i);
        $column_type = OCIColumnType($stmt,$i);
        $column_size = OCIColumnSize($stmt,$i);
        print "<TR>";
```

```

        print "<TD>$column_name</TD>";
        print "<TD>$column_type</TD>";
        print "<TD>$column_size</TD>";
        print "</TR>";
    }
    print "</TABLE>";
    OCIFreeStatement($stmt);
    OCILogoff($conn);
    print "</PRE>";
    print "</HTML>\n";
?>

```

See also **OCINumCols()**, **OCIColumnName()**, and **OCIColumnSize()**.

OCIColumnType (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

Returns the data type of a column

mixed **OCIColumnType** (int stmt, int col) \linebreak

OCIColumnType() returns the data type of the column corresponding to the column number (1-based) that is passed in.

Příklad 1. OCIColumnType

```

<?php
    print "<HTML><PRE>\n";
    $conn = OCILogon("scott", "tiger");
    $stmt = OCIParse($conn,"select * from emp");
    OCIExecute($stmt);
    print "<TABLE BORDER=\"1\">";
    print "<TR>";
    print "<TH>Name</TH>";
    print "<TH>Type</TH>";
    print "<TH>Length</TH>";
    print "</TR>";
    $ncols = OCINumCols($stmt);
    for ( $i = 1; $i <= $ncols; $i++ ) {
        $column_name = OCIColumnName($stmt,$i);
        $column_type = OCIColumnType($stmt,$i);
        $column_size = OCIColumnSize($stmt,$i);
        print "<TR>";
        print "<TD>$column_name</TD>";
        print "<TD>$column_type</TD>";
        print "<TD>$column_size</TD>";
        print "</TR>";
    }
    print "</TABLE>\n";
    OCIFreeStatement($stmt);

```



```

OCILogoff($conn);
print "</PRE>";
print "</HTML>\n";
?>

```

See also **OCINumCols()**, **OCIColumnName()**, and **OCIColumnSize()**.

OCIColumnTypeRaw (PHP 4 >= 4.0.0)

Coming soon

mixed **OCIColumnTypeRaw** (int stmt, int col) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCICommit (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Commits outstanding transactions

int **OCICommit** (int connection) \linebreak

OCICommit() commits all outstanding statements for Oracle connection *connection*.

OCIDefineByName (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Use a PHP variable for the define-step during a SELECT

int **OCIDefineByName** (int stmt, string Column-Name, mixed variable [, int type]) \linebreak

OCIDefineByName() binds PHP variables for fetches of SQL-Columns. Be careful that Oracle uses ALL-UPPERCASE column-names, whereby in your select you can also write lowercase.

OCIDefineByName() expects the *Column-Name* to be in uppercase. If you define a variable that doesn't exist in your select statement, no error will be given!

If you need to define an abstract datatype (LOB/ROWID/BFILE) you need to allocate it first using **OCINewDescriptor()** function. See also the **OCIBindByName()** function.

Příklad 1. OCIDefineByName

```

<?php
/* OCIDefineByName example - thies@thieso.net (980219) */

$conn = OCILogon("scott","tiger");

$stmt = OCIParse($conn,"select empno, ename from emp");

/* the define MUST be done BEFORE ociexecute! */

OCIDefineByName($stmt,"EMPNO",$empno);
OCIDefineByName($stmt,"ENAME",$ename);

OCIExecute($stmt);

while (OCIFetch($stmt)) {
    echo "empno:". $empno. "\n";
    echo "ename:". $ename. "\n";
}

OCIFreeStatement($stmt);
OCILogoff($conn);
?>

```

OCIError (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Return the last error of *stmt|conn|global*

array **OCIError** ([int *stmt|conn|global*]) \linebreak

OCIError() returns the last error found. If the optional *stmt|conn|global* is not provided, the last error encountered is returned. If no error is found, **OCIError()** returns FALSE. **OCIError()** returns the error as an associative array. In this array, *code* consists the oracle error code and *message* the oracle errorstring.

OCIExecute (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Execute a statement

int **OCIExecute** (int *statement* [, int *mode*]) \linebreak

OCIExecute() executes a previously parsed statement. (see **OCIParse()**). The optional *mode* allows you to specify the execution-mode (default is OCI_COMMIT_ON_SUCCESS). If you don't want statements to be committed automatically specify OCI_DEFAULT as your mode.

Vrací TRUE při úspěchu, FALSE při selhání.

OCIFetch (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Fetches the next row into result-buffer

```
int OCIFetch ( int statement) \linebreak
```

OCIFetch() fetches the next row (for SELECT statements) into the internal result-buffer.

OCIFetchInto (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Fetches the next row into result-array

```
int OCIFetchInto ( int stmt, array & result [, int mode]) \linebreak
```

OCIFetchInto() fetches the next row (for SELECT statements) into the *result* array.

OCIFetchInto() will overwrite the previous content of *result*. By default *result* will contain a zero-based array of all columns that are not NULL.

The *mode* parameter allows you to change the default behaviour. You can specify more than one flag by simply adding them up (eg OCI_ASSOC+OCI_RETURN_NULLS). The known flags are:

OCI_ASSOC Return an associative array.

OCI_NUM Return an numbered array starting with zero. (DEFAULT)

OCI_RETURN_NULLS Return empty columns.

OCI_RETURN_LOBS Return the value of a LOB instead of the descriptor.

OCIFetchStatement (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Fetch all rows of result data into an array

```
int OCIFetchStatement ( int stmt, array & variable) \linebreak
```

OCIFetchStatement() fetches all the rows from a result into a user-defined array.

OCIFetchStatement() returns the number of rows fetched.

Příklad 1. OCIFetchStatement

```
<?php
/* OCIFetchStatement example mbritton@verinet.com (990624) */

$conn = OCILogon("scott","tiger");

$stmt = OCIParse($conn,"select * from emp");

OCIExecute($stmt);

$rows = OCIFetchStatement($stmt,$results);
if ( $rows > 0 ) {
    print "<TABLE BORDER=\"1\">\n";
    print "<TR>\n";
```

```

while ( list( $key, $val ) = each( $results ) ) {
    print "<TH>$key</TH>\n";
}
print "</TR>\n";

for ( $i = 0; $i < $nrows; $i++ ) {
    reset($results);
    print "<TR>\n";
    while ( $column = each($results) ) {
        $data = $column['value'];
        print "<TD>$data[$i]</TD>\n";
    }
    print "</TR>\n";
}
print "</TABLE>\n";
} else {
    echo "No data found<BR>\n";
}
print "$nrows Records Selected<BR>\n";

OCIFreeStatement($stmt);
OCILogoff($conn);
?>

```

OCIFreeCollection (PHP 4 >= 4.1.0)

Coming soon

string **OCIFreeCollection** (object lob) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCIFreeCursor (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Free all resources associated with a cursor

int **OCIFreeCursor** (int stmt) \linebreak

OCIFreeCursor() returns TRUE if successful, or FALSE if unsuccessful.

OCIFreeDesc (PHP 4 >= 4.0.0)

Deletes a large object descriptor

int **OCIFreeDesc** (object lob) \linebreak

OCIFreeDesc() returns TRUE if successful, or FALSE if unsuccessful.

OCIFreeStatement (PHP 3>= 3.0.5, PHP 4 >= 4.0.0)

Free all resources associated with a statement

int **OCIFreeStatement** (int stmt) \linebreak

OCIFreeStatement() returns TRUE if successful, or FALSE if unsuccessful.

OCIInternalDebug (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Enables or disables internal debug output

void **OCIInternalDebug** (int onoff) \linebreak

OCIInternalDebug() enables internal debug output. Set *onoff* to 0 to turn debug output off, 1 to turn it on.

OCILoadLob (PHP 4 >= 4.0.0)

Coming soon

string **OCILoadLob** (object lob) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCILogOff (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Disconnects from Oracle

int **OCILogOff** (int connection) \linebreak

OCILogOff() closes an Oracle connection.

OCILogon (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Establishes a connection to Oracle

int **OCILogon** (string username, string password [, string db]) \linebreak

OCILogon() returns an connection identifier needed for most other OCI calls. The optional third parameter can either contain the name of the local Oracle instance or the name of the entry in tnsnames.ora to which you want to connect. If the optional third parameter is not specified, PHP uses the environment variables ORACLE_SID (Oracle instance) or TWO_TASK (tnsnames.ora) to determine which database to connect to.

Connections are shared at the page level when using **OCILogon()**. This means that commits and rollbacks apply to all open transactions in the page, even if you have created multiple connections.

This example demonstrates how the connections are shared.

Příklad 1. OCILogon

```
<?php
print "<HTML><PRE>";
$db = "";

$c1 = ocilogon("scott","tiger",$db);
$c2 = ocilogon("scott","tiger",$db);

function create_table($conn)
{ $stmt = ociparse($conn,"create table scott.hallo (test varchar2(64))");
  ociexecute($stmt);
  echo $conn." created table\n\n";
}

function drop_table($conn)
{ $stmt = ociparse($conn,"drop table scott.hallo");
  ociexecute($stmt);
  echo $conn." dropped table\n\n";
}

function insert_data($conn)
{ $stmt = ociparse($conn,"insert into scott.hallo
    values('$conn' || ' ' || to_char(sysdate,'DD-MON-YY HH24:MI:SS'))");
  ociexecute($stmt,OCI_DEFAULT);
  echo $conn." inserted hallo\n\n";
}

function delete_data($conn)
{ $stmt = ociparse($conn,"delete from scott.hallo");
  ociexecute($stmt,OCI_DEFAULT);
  echo $conn." deleted hallo\n\n";
}

function commit($conn)
{ ocicommit($conn);
  echo $conn." committed\n\n";
}
```

```

function rollback($conn)
{ ocirollback($conn);
  echo $conn." rollback\n\n";
}

function select_data($conn)
{ $stmt = ociparse($conn,"select * from scott.hallo");
  ociexecute($stmt,OCI_DEFAULT);
  echo $conn."----selecting\n\n";
  while (ocifetch($stmt))
    echo $conn." <".ociresult($stmt,"TEST").">\n\n";
  echo $conn."----done\n\n";
}

create_table($c1);
insert_data($c1); // Insert a row using c1
insert_data($c2); // Insert a row using c2

select_data($c1); // Results of both inserts are returned
select_data($c2);

rollback($c1); // Rollback using c1

select_data($c1); // Both inserts have been rolled back
select_data($c2);

insert_data($c2); // Insert a row using c2
commit($c2); // commit using c2

select_data($c1); // result of c2 insert is returned

delete_data($c1); // delete all rows in table using c1
select_data($c1); // no rows returned
select_data($c2); // no rows returned
commit($c1); // commit using c1

select_data($c1); // no rows returned
select_data($c2); // no rows returned

drop_table($c1);
print "</PRE></HTML>";
?>

```

See also **OCIPLogon()** and **OCINLogon()**.

OCINewCollection (PHP 4 >= 4.0.6)

Coming soon

string **OCINewCollection** (int conn, string tdo [, string shema]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCINewCursor (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Return a new cursor (Statement-Handle)

int **OCINewCursor** (int conn) \linebreak

OCINewCursor() allocates a new statement handle on the specified connection.

Příklad 1. Using a REF CURSOR from a stored procedure

```
<?php
// suppose your stored procedure info.output returns a ref cursor in :data

$conn = OCILogon("scott","tiger");
$curs = OCINewCursor($conn);
$stmt = OCIParse($conn,"begin info.output(:data); end;");

ocibindbyname($stmt,"data",&$curs,-1,OCI_B_CURSOR);
ociexecute($stmt);
ociexecute($curs);

while (OCIFetchInto($curs,&$data)) {
    var_dump($data);
}

OCIFreeStatement($stmt);
OCIFreeCursor($curs);
OCILogoff($conn);
?>
```

Příklad 2. Using a REF CURSOR in a select statement

```
<?php
print "<HTML><BODY>";
$conn = OCILogon("scott","tiger");
$count_cursor = "CURSOR(select count(empno) num_emps from emp " .
    "where emp.deptno = dept.deptno) as EMPCNT from dept";
$stmt = OCIParse($conn,"select deptno,dname,$count_cursor");

ociexecute($stmt);
```



```

print "<TABLE BORDER=\"1\">";
print "<TR>";
print "<TH>DEPT NAME</TH>";
print "<TH>DEPT #</TH>";
print "<TH># EMPLOYEES</TH>";
print "</TR>";

while (OCIFetchInto($stmt,&$data,OCI_ASSOC)) {
    print "<TR>";
    $dname = $data["DNAME"];
    $deptno = $data["DEPTNO"];
    print "<TD>$dname</TD>";
    print "<TD>$deptno</TD>";
    ociexecute($data["EMPCNT"]);
    while (OCIFetchInto($data["EMPCNT"],&$subdata,OCI_ASSOC)) {
        $num_ems = $subdata["NUM_EMPS"];
        print "<TD>$num_ems</TD>";
    }
    print "</TR>";
}
print "</TABLE>";
print "</BODY></HTML>";
OCIFreeStatement($stmt);
OCILogoff($conn);
?>

```

OCINewDescriptor (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Initialize a new empty LOB or FILE descriptor

string **OCINewDescriptor** (int connection [, int type]) \linebreak

OCINewDescriptor() allocates storage to hold descriptors or LOB locators. Valid values for *type* are OCI_D_FILE, OCI_D_LOB, OCI_D_ROWID. For LOB descriptors, the methods load, save, and savefile are associated with the descriptor, for BFILE only the load method exists. See the second example usage hints.

Příklad 1. OCINewDescriptor

```

<?php
/* This script is designed to be called from a HTML form.
 * It expects $user, $password, $table, $where, and $commitsize
 * to be passed in from the form. The script then deletes
 * the selected rows using the ROWID and commits after each
 * set of $commitsize rows. (Use with care, there is no rollback)
 */
$conn = OCILogon($user, $password);
$stmt = OCIParse($conn,"select rowid from $table $where");
$rowid = OCINewDescriptor($conn,OCI_D_ROWID);

```

```

OCIDefineByName($stmt,"ROWID",&$rowid);
OCIExecute($stmt);
while ( OCIFetch($stmt) ) {
    $nrows = OCIRowCount($stmt);
    $delete = OCIParse($conn,"delete from $table where ROWID = :rid");
    OCIBindByName($delete,":rid",&$rowid,-1,OCI_B_ROWID);
    OCIExecute($delete);
    print "$nrows\n";
    if ( ($nrows % $commitsize) == 0 ) {
        OCICommit($conn);
    }
}
$nrows = OCIRowCount($stmt);
print "$nrows deleted...\n";
OCIFreeStatement($stmt);
OCILogoff($conn);
?>

```

```

<?php
/* This script demonstrates file upload to LOB columns
 * The formfield used for this example looks like this
 * <form action="upload.php" method="post" enctype="multipart/form-data">
 * <input type="file" name="lob_upload">
 * ...
 */
if(!isset($lob_upload) || $lob_upload == 'none'){
?>
<form action="upload.php" method="post" enctype="multipart/form-data">
Upload file: <input type="file" name="lob_upload"><br>
<input type="submit" value="Upload"> - <input type="reset">
</form>
<?php
} else {

    // $lob_upload contains the temporary filename of the uploaded file

    // see also the features section on file upload,
    // if you would like to use secure uploads

    $conn = OCILogon($user, $password);
    $lob = OCINewDescriptor($conn, OCI_D_LOB);
    $stmt = OCIParse($conn,"insert into $table (id, the_blob)
        values(my_seq.NEXTVAL, EMPTY_BLOB()) returning the_blob into :the_blob");
    OCIBindByName($stmt, ':the_blob', &$lob, -1, OCI_B_BLOB);
    OCIExecute($stmt, OCI_DEFAULT);
    if($lob->savefile($lob_upload)){
        OCICommit($conn);
        echo "Blob successfully uploaded\n";
    }else{
        echo "Couldn't upload Blob\n";
    }
    OCIFreeDesc($lob);
    OCIFreeStatement($stmt);
    OCILogoff($conn);
}

```

```
?>
```

Příklad 2. OCINewDescriptor

```
<?php
/* Calling PL/SQL stored procedures which contain clobs as input
 * parameters (PHP 4 >= 4.0.6).
 * Example PL/SQL stored procedure signature is:
 *
 * PROCEDURE save_data
 *   Argument Name          Type          In/Out Default?
 *   -----
 *   KEY                     NUMBER(38)      IN
 *   DATA                   CLOB           IN
 *
 */

$conn = OCILogon($user, $password);
$stmt = OCIParse($conn, "begin save_data(:key, :data); end;");
$clob = OCINewDescriptor($conn, OCI_D_LOB);
OCIBindByName($stmt, ':key', $key);
OCIBindByName($stmt, ':data', $clob, -1, OCI_B_CLOB);
$clob->WriteTemporary($data);
OCIExecute($stmt, OCI_DEFAULT);
OCICommit($conn);
$clob->close();
$clob->free();
OCIFreeStatement($stmt);
?>
```

OCINLogon (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Establishes a new connection to Oracle

```
int OCINLogon ( string username, string password [, string db]) \linebreak
```

OCINLogon() creates a new connection to an Oracle 8 database and logs on. The optional third parameter can either contain the name of the local Oracle instance or the name of the entry in tnsnames.ora to which you want to connect. If the optional third parameter is not specified, PHP uses the environment variables ORACLE_SID (Oracle instance) or TWO_TASK (tnsnames.ora) to determine which database to connect to.

OCINLogon() forces a new connection. This should be used if you need to isolate a set of transactions. By default, connections are shared at the page level if using **OCILogon()** or at the web server process level if using **OCIPLogon()**. If you have multiple connections open using **OCINLogon()**, all commits and rollbacks apply to the specified connection only.

This example demonstrates how the connections are separated.

Příklad 1. OCINLogon

```

<?php
print "<HTML><PRE>";
$db = "";

$c1 = ocilogon("scott","tiger",$db);
$c2 = ocinlogon("scott","tiger",$db);

function create_table($conn)
{ $stmt = ociparse($conn,"create table scott.hallo (test
varchar2(64))");
  ociexecute($stmt);
  echo $conn." created table\n\n";
}

function drop_table($conn)
{ $stmt = ociparse($conn,"drop table scott.hallo");
  ociexecute($stmt);
  echo $conn." dropped table\n\n";
}

function insert_data($conn)
{ $stmt = ociparse($conn,"insert into scott.hallo
      values('$conn' || ' ' || to_char(sysdate,'DD-MON-YY HH24:MI:SS'))");
  ociexecute($stmt,OCI_DEFAULT);
  echo $conn." inserted hallo\n\n";
}

function delete_data($conn)
{ $stmt = ociparse($conn,"delete from scott.hallo");
  ociexecute($stmt,OCI_DEFAULT);
  echo $conn." deleted hallo\n\n";
}

function commit($conn)
{ ocicommit($conn);
  echo $conn." committed\n\n";
}

function rollback($conn)
{ ocirollback($conn);
  echo $conn." rollback\n\n";
}

function select_data($conn)
{ $stmt = ociparse($conn,"select * from scott.hallo");
  ociexecute($stmt,OCI_DEFAULT);
  echo $conn."----selecting\n\n";
  while (ocifetch($stmt))
    echo $conn." <".ociresult($stmt,"TEST").">\n\n";
  echo $conn."----done\n\n";
}

create_table($c1);
insert_data($c1);

```

```

select_data($c1);
select_data($c2);

rollback($c1);

select_data($c1);
select_data($c2);

insert_data($c2);
commit($c2);

select_data($c1);

delete_data($c1);
select_data($c1);
select_data($c2);
commit($c1);

select_data($c1);
select_data($c2);

drop_table($c1);
print "</PRE></HTML>";
?>

```

See also **OCILogon()** and **OCIPLogon()**.

OCINumCols (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Return the number of result columns in a statement

int **OCINumCols** (int stmt) \linebreak

OCINumCols() returns the number of columns in a statement.

Příklad 1. OCINumCols

```

<?php
    print "<HTML><PRE>\n";
    $conn = OCILogon("scott", "tiger");
    $stmt = OCIParse($conn,"select * from emp");
    OCIExecute($stmt);
    while ( OCIFetch($stmt) ) {
        print "\n";
        $ncols = OCINumCols($stmt);
        for ( $i = 1; $i <= $ncols; $i++ ) {
            $column_name = OCIColumnName($stmt,$i);
            $column_value = OCIResult($stmt,$i);
            print $column_name . ': ' . $column_value . "\n";
        }
    }

```

```

        }
        print "\n";
    }
    OCIFreeStatement($stmt);
    OCILogoff($conn);
    print "</PRE>";
    print "</HTML>\n";
?>

```

OCIParse (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Parse a query and return a statement

int **OCIParse** (int conn, string query) \linebreak

OCIParse() parses the *query* using *conn*. It returns the statement identity if the query is valid, FALSE if not. The *query* can be any valid SQL statement or PL/SQL block.

OCILogon (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Connect to an Oracle database using a persistent connection

int **OCILogon** (string username, string password [, string db]) \linebreak

OCILogon() creates a persistent connection to an Oracle 8 database and logs on. The optional third parameter can either contain the name of the local Oracle instance or the name of the entry in tnsnames.ora to which you want to connect. If the optional third parameter is not specified, PHP uses the environment variables ORACLE_SID (Oracle instance) or TWO_TASK (tnsnames.ora) to determine which database to connect to.

See also **OCILogon()** and **OCINLogon()**.

OCIResult (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Returns column value for fetched row

mixed **OCIResult** (int statement, mixed column) \linebreak

OCIResult() returns the data for column *column* in the current row (see **OCIFetch()**). **OCIResult()** will return everything as strings except for abstract types (ROWIDs, LOBs and FILES).

OCIRollback (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Rolls back outstanding transactions

int **OCIRollback** (int connection) \linebreak

OCIRollback() rolls back all outstanding statements for Oracle connection *connection*.

OCIRowCount (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Gets the number of affected rows

int **OCIRowCount** (int statement) \linebreak

OCIRowCount() returns the number of rows affected for eg update-statements. This function will not tell you the number of rows that a select will return!

Příklad 1. OCIRowCount

```
<?php
    print "<HTML><PRE>";
    $conn = OCILogon("scott","tiger");
    $stmt = OCIParse($conn,"create table emp2 as select * from emp");
    OCIExecute($stmt);
    print OCIRowCount($stmt) . " rows inserted.<BR>";
    OCIFreeStatement($stmt);
    $stmt = OCIParse($conn,"delete from emp2");
    OCIExecute($stmt);
    print OCIRowCount($stmt) . " rows deleted.<BR>";
    OCICommit($conn);
    OCIFreeStatement($stmt);
    $stmt = OCIParse($conn,"drop table emp2");
    OCIExecute($stmt);
    OCIFreeStatement($stmt);
    OCILogOff($conn);
    print "</PRE></HTML>";
?>
```

OCISaveLob (PHP 4 >= 4.0.0)

Coming soon

string **OCISaveLob** (object lob) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCISaveLobFile (PHP 4 >= 4.0.0)

Coming soon

string **OCISaveLobFile** (object lob) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

OCIServerVersion (PHP 3 >= 3.0.4, PHP 4 >= 4.0.0)

Return a string containing server version information

string **OCIServerVersion** (int conn) \linebreak

Příklad 1. OCIServerVersion

```
<?php
    $conn = OCILogon("scott","tiger");
    print "Server Version: " . OCIServerVersion($conn);
    OCILogOff($conn);
?>
```

OCISetPrefetch (PHP 3 >= 3.0.12, PHP 4 >= 4.0.0)

Sets number of rows to be prefetched

int **OCISetPrefetch** (int stmt, int rows) \linebreak

Sets the number of top level rows to be prefetched. The default value is 1 row.

OCIStatementType (PHP 3 >= 3.0.5, PHP 4 >= 4.0.0)

Return the type of an OCI statement

string **OCIStatementType** (int stmt) \linebreak

OCIStatementType() returns one of the following values:

1. "SELECT"
2. "UPDATE"
3. "DELETE"
4. "INSERT"
5. "CREATE"
6. "DROP"
7. "ALTER"
8. "BEGIN"
9. "DECLARE"
10. "UNKNOWN"

Příklad 1. OCIStatementType() examples

```
<?php
    print "<HTML><PRE>";
    $conn = OCILogon("scott","tiger");
    $sql  = "delete from emp where deptno = 10";

    $stmt = OCIParse($conn,$sql);
    if ( OCIStatementType($stmt) == "DELETE" ) {
        die "You are not allowed to delete from this table<BR>";
    }

    OCILogoff($conn);
    print "</PRE></HTML>";
?>
```

OCIWriteLobToFile (PHP 4 >= 4.0.0)

Coming soon

void **OCIWriteLobToFile** (object lob [, string filename [, int start [, int lenght]]]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

LXX. OpenSSL funkce

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

Tato extenze využívá funkce OpenSSL (<http://www.openssl.org/>) pro tvorbu a ověřování podpisů a pečetění (kódování) a otvírání (dekódování) dat. K práci s touto extenzí potřebujete OpenSSL >= 0.9.6.

OpenSSL nabízí mnoho vlastností, které tato extenze v současnosti nepodporuje. Některé z nich mohou být v budoucnu přidány.

openssl_free_key (PHP 4 >= 4.0.4)

Uvolnit prostředky klíče

```
void openssl_free_key ( int key_identifier ) \linebreak
```

openssl_free_key() uvolní klíč asociovaný s předaným *key_identifier* z paměti.

openssl_get_privatekey (PHP 4 >= 4.0.4)

Připravit soukromý PEM klíč k použití

```
int openssl_get_privatekey ( string key [, string passphrase] ) \linebreak
```

Při úspěchu vrací klíč, při chybě `FALSE`.

openssl_get_privatekey() rozparsuje soukromý PEM klíč *key* a připraví ho k použití v dalších funkcích. Volitelný argument *passphrase* musí být předán, pokud je tento klíč zakódován (chráněn heslem).

openssl_get_publickey (PHP 4 >= 4.0.4)

Získat z certifikátu veřejný klíč a připravit ho k použití

```
int openssl_get_publickey ( string certificate ) \linebreak
```

Při úspěchu vrací identifikátor klíče, při chybě `FALSE`.

openssl_get_publickey() z X.509 certifikátu *certificate* vyextrahuje veřejný klíč a připraví ho k použití v dalších funkcích.

openssl_open (PHP 4 >= 4.0.4)

Otevřít zapečetěná data

```
bool openssl_open ( string sealed_data, string open_data, string env_key, int priv_key_id ) \linebreak
```

Při úspěchu vrací `TRUE`, při chybě `FALSE`. Úspěšně otevřená data se umístí do argumentu *open_data*.

openssl_open() otevře (dekóduje) *sealed_data* pomocí soukromého klíče asociovaného s identifikátorem *priv_key_id* a obálkou *env_key*. Tato obálka se generuje při pečetění dat a je použitelná pouze s jedním utčitým soukromým klíčem. Více informací viz `openssl_seal()`.

Příklad 1. Ukázka openssl_open()

```
// $sealed a $env_key obsahují zapečetěná data a obálku
// obojí nám bylo dáno tím, kdo data zapečetil
```

```
// získat ze souboru soukromý klíč a připravit ho
$fp = fopen("/src/openssl-0.9.6/demos/sign/key.pem", "r");
$priv_key = fread($fp, 8192);
fclose($fp);
$pkid = openssl_get_privatekey($priv_key);

// dekodovat data a uložit je v $open
if (openssl_open($sealed, $open, $env_key, $pkid))
    echo "tady jsou otevřená data: ", $open;
else
    echo "nepodařilo se otevřít data";

// uvolnit klíč z paměti
openssl_free_key($pkid);
```

Viz také `openssl_seal()`.

openssl_seal (PHP 4 >= 4.0.4)

Zapečetit (zakódovat) data

int openssl_seal (string data, string sealed_data, array env_keys, array pub_key_ids) \linebreak

Při úspěchu vrátí délku zapečetěných dat, při chybě FALSE. Úspěšně zapečetěná data se umístí do argumentu *sealed_data*, a obálka do *env_keys*.

openssl_seal() zapečetí (zakóduje) *data* pomocí RC4 s náhodně generovaným tajným klíčem. Tento klíč se zakóduje všemi veřejnými klíči asociovanými s identifikátory v *pub_key_ids* a zakódované klíče se vrátí v *env_keys*. To znamená, že lze poslat zapečetěná data více příjemcům (za předpokladu, že máme jejich veřejné klíče). Každý z příjemců musí obdržet zapečetěná data a obálku, která byla zakódována jeho veřejným klíčem.

Příklad 1. Ukázka openssl_seal()

```
// $data obsahuje data určená k zapečetění

// získat veřejné klíče našich příjemců a připravit je
$fp = fopen("/src/openssl-0.9.6/demos/maurice/cert.pem", "r");
$cert = fread($fp, 8192);
fclose($fp);
$pk1 = openssl_get_publickey($cert);
// opakovat pro druhého příjemce
$fp = fopen("/src/openssl-0.9.6/demos/sign/cert.pem", "r");
$cert = fread($fp, 8192);
fclose($fp);
$pk2 = openssl_get_publickey($cert);

// zapečetit zprávu, pouze majitelé $pk1 a $pk2 mohou dekodovat $sealed pomocí
// $keys[0] a $keys[1].
openssl_seal($data, $sealed, $keys, array($pk1,$pk2));
```

```
// uvolnit klíče z paměti
openssl_free_key($pk1);
openssl_free_key($pk2);
```

Viz také `openssl_open()`.

openssl_sign (PHP 4 >= 4.0.4)

Generate signature

bool openssl_sign (string data, string signature, int priv_key_id) \linebreak

Při úspěchu vrací TRUE, při chybě FALSE. Úspěšně vytvořený podpis se umístí v *signature*.

openssl_sign() vypočítá podpis pro daná specified *data* pomocí SHA1 hashe a následně jej zakóduje soukromým klíčem asociovaným s *priv_key_id*. Pozn.: samotná data nejsou kódována.

Příklad 1. openssl_sign() example

```
// $data obsahuje data určená k podpisu

// získat ze souboru soukromý klíč a připravit ho
$fp = fopen("/src/openssl-0.9.6/demos/sign/key.pem", "r");
$priv_key = fread($fp, 8192);
fclose($fp);
$pkeyid = openssl_get_privatekey($priv_key);

// vytvořit podpis
openssl_sign($data, $signature, $pkeyid);

// uvolnit klíč z paměti
openssl_free_key($pkeyid);
```

Viz také `openssl_verify()`.

openssl_verify (PHP 4 >= 4.0.4)

Ověřit podpis

int openssl_verify (string data, string signature, int pub_key_id) \linebreak

Vrací 1, pokud je podpis správný, 0, pokud je nesprávný, a -1 při chybě.

openssl_verify() ověřuje, zda je *signature* správný pro *data* pomocí veřejného klíče asociovaného s *pub_key_id*. Musí to být veřejný klíč odpovídající soukromému klíči použitému k podpisu.

Příklad 1. Ukázka openssl_verify()

```
// $data a $signature obsahují data a podpis

// získat z certifikátu veřejný klíč a připravit ho
$fp = fopen("/src/openssl-0.9.6/demos/sign/cert.pem", "r");
$cert = fread($fp, 8192);
fclose($fp);
$pubkeyid = openssl_get_publickey($cert);

// zjistit, jestli je podpis v pořádku
$ok = openssl_verify($data, $signature, $pubkeyid);
if ($ok == 1)
    echo "dobře";
elseif ($ok == 0)
    echo "špatně";
else
    echo "nejhůř, při kontrole podpisu došlo k chybě";

// uvolnit klíč z paměti
openssl_free_key($pubkeyid);
```

Viz také openssl_sign().

LXXI. Oracle functions

Ora_Bind (PHP 3, PHP 4 >= 4.0.0)

bind a PHP variable to an Oracle parameter

int **ora_bind** (int cursor, string PHP variable name, string SQL parameter name, int length [, int type])
 \linebreak

Returns TRUE if the bind succeeds, otherwise FALSE. Details about the error can be retrieved using the ora_error() and ora_errorcode() functions.

This function binds the named PHP variable with a SQL parameter. The SQL parameter must be in the form ":name". With the optional type parameter, you can define whether the SQL parameter is an in/out (0, default), in (1) or out (2) parameter. As of PHP 3.0.1, you can use the constants ORA_BIND_INOUT, ORA_BIND_IN and ORA_BIND_OUT instead of the numbers.

ora_bind must be called after ora_parse() and before ora_exec(). Input values can be given by assignment to the bound PHP variables, after calling ora_exec() the bound PHP variables contain the output values if available.

```
<?php
ora_parse($curs, "declare tmp INTEGER; begin tmp := :in; :out := tmp; :x := 7.77; end;")
ora_bind($curs, "result", ":x", $len, 2);
ora_bind($curs, "input", ":in", 5, 1);
ora_bind($curs, "output", ":out", 5, 2);
$input = 765;
ora_exec($curs);
echo "Result: $result<BR>Out: $output<BR>In: $input";
?>
```

Ora_Close (PHP 3, PHP 4 >= 4.0.0)

close an Oracle cursor

int **ora_close** (int cursor) \linebreak

Returns TRUE if the close succeeds, otherwise FALSE. Details about the error can be retrieved using the ora_error() and ora_errorcode() functions.

This function closes a data cursor opened with ora_open().

Ora_ColumnName (PHP 3, PHP 4 >= 4.0.0)

get name of Oracle result column

string **Ora_ColumnName** (int cursor, int column) \linebreak

Returns the name of the field/column *column* on the cursor *cursor*. The returned name is in all uppercase letters. Column 0 is the first column.

Ora_ColumnSize (PHP 3, PHP 4 >= 4.0.0)

get size of Oracle result column

```
int Ora_ColumnSize ( int cursor, int column) \linebreak
```

Returns the size of the Oracle column *column* on the cursor *cursor*. Column 0 is the first column.

Ora_ColumnType (PHP 3, PHP 4 >= 4.0.0)

get type of Oracle result column

```
string Ora_ColumnType ( int cursor, int column) \linebreak
```

Returns the Oracle data type name of the field/column *column* on the cursor *cursor*. Column 0 is the first column. The returned type will be one of the following:

```
"VARCHAR2 "  
"VARCHAR "  
"CHAR "  
"NUMBER "  
"LONG "  
"LONG RAW "  
"ROWID "  
"DATE "  
"CURSOR "
```

Ora_Commit (PHP 3, PHP 4 >= 4.0.0)

commit an Oracle transaction

```
int ora_commit ( int conn) \linebreak
```

Returns `TRUE` on success, `FALSE` on error. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

This function commits an Oracle transaction. A transaction is defined as all the changes on a given connection since the last commit/rollback, autocommit was turned off or when the connection was established.

Ora_CommitOff (PHP 3, PHP 4 >= 4.0.0)

disable automatic commit

```
int ora_commitoff ( int conn) \linebreak
```

Returns `TRUE` on success, `FALSE` on error. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

This function turns off automatic commit after each `ora_exec()`.

Ora_CommitOn (PHP 3, PHP 4 >= 4.0.0)

enable automatic commit

`int ora_commiton (int conn) \linebreak`

This function turns on automatic commit after each `ora_exec()` on the given connection.

Returns `TRUE` on success, `FALSE` on error. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

Ora_Do (PHP 3, PHP 4 >= 4.0.0)

Parse, Exec, Fetch

`int ora_do (int conn, string query) \linebreak`

This function is quick combination of `ora_parse()`, `ora_exec()` and `ora_fetch()`. It will parse and execute a statement, then fetch the first result row.

Returns `TRUE` on success, `FALSE` on error. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

See also `ora_parse()`, `ora_exec()`, and `ora_fetch()`.

Ora_Error (PHP 3, PHP 4 >= 4.0.0)

get Oracle error message

`string Ora_Error (int cursor_or_connection) \linebreak`

Returns an error message of the form `XXX-NNNNN` where `XXX` is where the error comes from and `NNNNN` identifies the error message.

Poznámka: Support for connection ids was added in 3.0.4.

On UNIX versions of Oracle, you can find details about an error message like this: `$ oerr ora 00001 00001, 00000, "unique constraint (%s.%s) violated" // *Cause: An update or insert statement attempted to insert a duplicate key // For Trusted ORACLE configured in DBMS MAC mode, you may see // this message if a duplicate entry exists at a different level. // *Action: Either remove the unique restriction or do not insert the key`

Ora_ErrorCode (PHP 3, PHP 4 >= 4.0.0)

get Oracle error code

```
int Ora_ErrorCode ( int cursor_or_connection) \linebreak
```

Returns the numeric error code of the last executed statement on the specified cursor or connection.

Poznámka: Support for connection ids was added in 3.0.4.

Ora_Exec (PHP 3, PHP 4 >= 4.0.0)

execute parsed statement on an Oracle cursor

```
int ora_exec ( int cursor) \linebreak
```

Returns `TRUE` on success, `FALSE` on error. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

See also `ora_parse()`, `ora_fetch()`, and `ora_do()`.

Ora_Fetch (PHP 3, PHP 4 >= 4.0.0)

fetch a row of data from a cursor

```
int ora_fetch ( int cursor) \linebreak
```

Returns `TRUE` (a row was fetched) or `FALSE` (no more rows, or an error occurred). If an error occurred, details can be retrieved using the `ora_error()` and `ora_errorcode()` functions. If there was no error, `ora_errorcode()` will return 0.

Retrieves a row of data from the specified cursor.

See also `ora_parse()`, `ora_exec()`, and `ora_do()`.

Ora_Fetch_Into (PHP 3, PHP 4 >= 4.0.0)

Fetch a row into the specified result array

```
int ora_fetch_into ( int cursor, array result [, int flags]) \linebreak
```

You can fetch a row into an array with this function.

Příklad 1. Oracle fetch into array

```
<?php
array($results);
ora_fetch_into($cursor, &$results);
echo $results[0];
echo $results[1];
?>
```

Note that you need to fetch the array by reference.

See also `ora_parse()`, `ora_exec()`, `ora_fetch()`, and `ora_do()`.

Ora_GetColumn (PHP 3, PHP 4 >= 4.0.0)

get data from a fetched column

mixed **ora_getcolumn** (int cursor, mixed column) \linebreak

Returns the column data. If an error occurs, `FALSE` is returned and `ora_errorcode()` will return a non-zero value. Note, however, that a test for `FALSE` on the results from this function may be `TRUE` in cases where there is not error as well (`NULL` result, empty string, the number 0, the string "0").

Fetches the data for a column or function result.

Ora_Logoff (PHP 3, PHP 4 >= 4.0.0)

close an Oracle connection

int **ora_logoff** (int connection) \linebreak

Returns `TRUE` on success, `FALSE` on error. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

Logs out the user and disconnects from the server.

See also `ora_logon()`.

Ora_Logon (PHP 3, PHP 4 >= 4.0.0)

open an Oracle connection

int **ora_logon** (string user, string password) \linebreak

Establishes a connection between PHP and an Oracle database with the given username and password.

Connections can be made using `SQL*Net` by supplying the TNS name to `user` like this:

```
$conn = Ora_Logon("user<emphasis>@TNSNAME</emphasis>", "pass");
```

If you have character data with non-ASCII characters, you should make sure that `NLS_LANG` is set in your environment. For server modules, you should set it in the server's environment before starting the server.

Returns a connection index on success, or `FALSE` on failure. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

Ora_Numcols (PHP 3, PHP 4 >= 4.0.0)

Returns the number of columns

```
int ora_numcols ( int cursor_ind) \linebreak
```

ora_numcols() returns the number of columns in a result. Only returns meaningful values after an parse/exec/fetch sequence.

See also `ora_parse()`, `ora_exec()`, `ora_fetch()`, and `ora_do()`.

Ora_Numrows (PHP 3, PHP 4 >= 4.0.0)

Returns the number of rows

```
int ora_numrows ( int cursor_ind) \linebreak
```

ora_numrows() returns the number of rows in a result.

Ora_Open (PHP 3, PHP 4 >= 4.0.0)

open an Oracle cursor

```
int ora_open ( int connection) \linebreak
```

Opens an Oracle cursor associated with connection.

Returns a cursor index or `FALSE` on failure. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

Ora_Parse (PHP 3, PHP 4 >= 4.0.0)

parse an SQL statement

int ora_parse (int cursor_ind, string sql_statement, int defer) \linebreak

This function parses an SQL statement or a PL/SQL block and associates it with the given cursor.

Vrací `TRUE` při úspěchu, `FALSE` při selhání.

See also `ora_exec()`, `ora_fetch()`, and `ora_do()`.

Ora_pLogon (PHP 3, PHP 4 >= 4.0.0)

Open a persistent Oracle connection

int ora_plogon (string user, string password) \linebreak

Establishes a persistent connection between PHP and an Oracle database with the given username and password.

See also `ora_logon()`.

Ora_Rollback (PHP 3, PHP 4 >= 4.0.0)

roll back transaction

int ora_rollback (int connection) \linebreak

This function undoes an Oracle transaction. (See `ora_commit()` for the definition of a transaction.)

Returns `TRUE` on success, `FALSE` on error. Details about the error can be retrieved using the `ora_error()` and `ora_errorcode()` functions.

LXXII. Ovrimos SQL functions

Ovrimos SQL Server, is a client/server, transactional RDBMS combined with Web capabilities and fast transactions.

Ovrimos SQL Server is available at www.ovrimos.com (<http://www.ovrimos.com/>). To enable ovrimos support in PHP just compile php with the '--with-ovrimos' parameter to configure script. You'll need to install the sqlcli library available in the Ovrimos SQL Server distribution.

Příklad 1. Connect to Ovrimos SQL Server and select from a system table

```
<?php
$conn = ovrimos_connect ("server.domain.com", "8001", "admin", "password");
if ($conn != 0) {
    echo ("Connection ok!");
    $res = ovrimos_exec ($conn, "select table_id, table_name from sys.tables");
    if ($res != 0) {
        echo "Statement ok!";
        ovrimos_result_all ($res);
        ovrimos_free_result ($res);
    }
    ovrimos_close($conn);
}
?>
```

This will just connect to SQL Server.

ovrimos_close (PHP 4 >= 4.0.3)

Closes the connection to ovrimos

void **ovrimos_close** (int connection) \linebreak

ovrimos_close() is used to close the specified connection.

ovrimos_close() closes a connection to Ovrimos. This has the effect of rolling back uncommitted transactions.

ovrimos_commit (PHP 4 >= 4.0.3)

Commits the transaction

int **ovrimos_commit** (int connection_id) \linebreak

ovrimos_commit() is used to commit the transaction.

ovrimos_commit() commits the transaction.

ovrimos_connect (PHP 4 >= 4.0.3)

Connect to the specified database

int **ovrimos_connect** (string host, string db, string user, string password) \linebreak

ovrimos_connect() is used to connect to the specified database.

ovrimos_connect() returns a connection id (greater than 0) or 0 for failure. The meaning of 'host' and 'port' are those used everywhere in Ovrimos APIs. 'Host' is a host name or IP address and 'db' is either a database name, or a string containing the port number.

Příklad 1. ovrimos_connect() Example

```

<?php
$conn = ovrimos_connect ( "server.domain.com", "8001", "admin", "password");
if ($conn != 0) {
    echo "Connection ok!";
    $res=ovrimos_exec ($conn, "select table_id, table_name from sys.tables");
    if ($res != 0) {
        echo "Statement ok!";
        ovrimos_result_all ($res);
        ovrimos_free_result ($res);
    }
    ovrimos_close($conn);
}
?>

```

The above example will connect to the database and print out the specified table.

ovrimos_cursor (PHP 4 >= 4.0.3)

Returns the name of the cursor

```
int ovrimos_cursor ( int result_id) \linebreak
```

ovrimos_cursor() is used to get the name of the cursor.

ovrimos_cursor() returns the name of the cursor. Useful when wishing to perform positioned updates or deletes.

ovrimos_exec (PHP 4 >= 4.0.3)

Executes an SQL statement

```
int ovrimos_exec ( int connection_id, string query) \linebreak
```

ovrimos_exec() is used to execute an SQL statement.

ovrimos_exec() executes an SQL statement (query or update) and returns a result_id or FALSE. Evidently, the SQL statement should not contain parameters.

ovrimos_execute (PHP 4 >= 4.0.3)

Executes a prepared SQL statement

```
bool ovrimos_execute ( int result_id [, array parameters_array]) \linebreak
```

ovrimos_execute() is used to execute an SQL statement.

ovrimos_execute() executes a prepared statement. Returns TRUE or FALSE. If the prepared statement contained parameters (question marks in the statement), the correct number of parameters should be passed in an array. Notice that I don't follow the PHP convention of placing just the name of the optional parameter inside square brackets. I couldn't bring myself on liking it.

ovrimos_fetch_into (PHP 4 >= 4.0.3)

Fetches a row from the result set

```
bool ovrimos_fetch_into ( int result_id, array result_array [, string how [, int rownumber]]) \linebreak
```

ovrimos_fetch_into() is used to fetch a row from the result set.

ovrimos_fetch_into() fetches a row from the result set into 'result_array', which should be passed by reference. Which row is fetched is determined by the two last parameters. 'how' is one of 'Next' (default), 'Prev', 'First', 'Last', 'Absolute', corresponding to forward direction from current

position, backward direction from current position, forward direction from the start, backward direction from the end and absolute position from the start (essentially equivalent to 'first' but needs 'rownumber'). Case is not significant. 'Rownumber' is optional except for absolute positioning. Returns TRUE or FALSE.

Příklad 1. A fetch into example

```
<?php
$conn=ovrimos_connect ("neptune", "8001", "admin", "password");
if ($conn!=0) {
    echo "Connection ok!";
    $res=ovrimos_exec ($conn,"select table_id, table_name from sys.tables");
    if ($res != 0) {
        echo "Statement ok!";
        if (ovrimos_fetch_into ($res, &$row)) {
            list ($table_id, $table_name) = $row;
            echo "table_id=".$table_id.", table_name=".$table_name."\n";
            if (ovrimos_fetch_into ($res, &$row)) {
                list ($table_id, $table_name) = $row;
                echo "table_id=".$table_id.", table_name=".$table_name."\n";
            } else {
                echo "Next: error\n";
            }
        } else {
            echo "First: error\n";
        }
        ovrimos_free_result ($res);
    }
    ovrimos_close($conn);
}
?>
```

This example will fetch a row.

ovrimos_fetch_row (PHP 4 >= 4.0.3)

Fetches a row from the result set

bool **ovrimos_fetch_row** (int result_id [, int how [, int row_number]]) \linebreak

ovrimos_fetch_row() is used to fetch a row from the result set.

ovrimos_fetch_row() fetches a row from the result set. Column values should be retrieved with other calls. Returns TRUE or FALSE.

Příklad 1. A fetch row example

```
<?php
$conn = ovrimos_connect ("remote.host", "8001", "admin", "password");
```

```

if ($conn != 0) {
    echo "Connection ok!";
    $res=ovrimos_exec ($conn, "select table_id, table_name from sys.tables");
    if ($res != 0) {
        echo "Statement ok!";
        if (ovrimos_fetch_row ($res, "First")) {
            $table_id = ovrimos_result ($res, 1);
            $table_name = ovrimos_result ($res, 2);
            echo "table_id=".$table_id.", table_name=".$table_name."\n";
            if (ovrimos_fetch_row ($res, "Next")) {
                $table_id = ovrimos_result ($res, "table_id");
                $table_name = ovrimos_result ($res, "table_name");
                echo "table_id=".$table_id.", table_name=".$table_name."\n";
            } else {
                echo "Next: error\n";
            }
        } else {
            echo "First: error\n";
        }
        ovrimos_free_result ($res);
    }
    ovrimos_close($conn);
}
?>

```

This will fetch a row and print the result.

ovrimos_field_len (PHP 4 >= 4.0.3)

Returns the length of the output column

```
int ovrimos_field_len ( int result_id, int field_number) \linebreak
```

ovrimos_field_len() is used to get the length of the output column with number *field_number*, in result *result_id*.

ovrimos_field_len() returns the length of the output column at the (1-based) index specified.

ovrimos_field_name (PHP 4 >= 4.0.3)

Returns the output column name

```
int ovrimos_field_name ( int result_id, int field_number) \linebreak
```

ovrimos_field_name() is used to get the output column name.

ovrimos_field_name() returns the output column name at the (1-based) index specified.

ovrimos_field_num (PHP 4 >= 4.0.3)

Returns the (1-based) index of the output column

```
int ovrimos_field_num ( int result_id, string field_name) \linebreak
```

ovrimos_field_num() is used to get the (1-based) index of the output column.

ovrimos_field_num() returns the (1-based) index of the output column specified by name, or `FALSE`.

ovrimos_field_type (PHP 4 >= 4.0.3)

Returns the (numeric) type of the output column

```
int ovrimos_field_type ( int result_id, int field_number) \linebreak
```

ovrimos_field_type() is used to get the (numeric) type of the output column.

ovrimos_field_type() returns the (numeric) type of the output column at the (1-based) index specified.

ovrimos_free_result (PHP 4 >= 4.0.3)

Frees the specified result_id

```
bool ovrimos_free_result ( int result_id) \linebreak
```

ovrimos_free_result() is used to free the result_id.

ovrimos_free_result() frees the specified result_id *result_id*. Returns `TRUE`.

ovrimos_longreadlen (PHP 4 >= 4.0.3)

Specifies how many bytes are to be retrieved from long datatypes

```
int ovrimos_longreadlen ( int result_id, int length) \linebreak
```

ovrimos_longreadlen() is used to specify how many bytes are to be retrieved from long datatypes.

ovrimos_longreadlen() specifies how many bytes are to be retrieved from long datatypes (long varchar and long varbinary). Default is zero. It currently sets this parameter the specified result set. Returns `TRUE`.

ovrimos_num_fields (PHP 4 >= 4.0.3)

Returns the number of columns

```
int ovrimos_num_fields ( int result_id) \linebreak
```

ovrimos_num_fields() is used to get the number of columns.

ovrimos_num_fields() returns the number of columns in a result_id resulting from a query.

ovrimos_num_rows (PHP 4 >= 4.0.3)

Returns the number of rows affected by update operations

int ovrimos_num_rows (int result_id) \linebreak

ovrimos_num_rows() is used to get the number of rows affected by update operations.

ovrimos_num_rows() returns the number of rows affected by update operations.

ovrimos_prepare (PHP 4 >= 4.0.3)

Prepares an SQL statement

int ovrimos_prepare (int connection_id, string query) \linebreak

ovrimos_prepare() is used to prepare an SQL statement.

ovrimos_prepare() prepares an SQL statement and returns a result_id (or FALSE on failure).

Příklad 1. Connect to Ovrimos SQL Server and prepare a statement

```
<?php
$conn=ovrimos_connect ("db_host", "8001", "admin", "password");
if ($conn!=0) {
    echo "Connection ok!";
    $res=ovrimos_prepare ($conn, "select table_id, table_name
                                from sys.tables where table_id=1");

    if ($res != 0) {
        echo "Prepare ok!";
        if (ovrimos_execute ($res)) {
            echo "Execute ok!\n";
            ovrimos_result_all ($res);
        } else {
            echo "Execute not ok!";
        }
        ovrimos_free_result ($res);
    } else {
        echo "Prepare not ok!\n";
    }
    ovrimos_close($conn);
}
?>
```

This will connect to Ovrimos SQL Server, prepare a statement and the execute it.

ovrimos_result (PHP 4 >= 4.0.3)

Retrieves the output column

`int ovrimos_result (int result_id, mixed field) \linebreak`

ovrimos_result() is used to retrieve the output column.

ovrimos_result() retrieves the output column specified by 'field', either as a string or as an 1-based index.

ovrimos_result_all (PHP 4 >= 4.0.3)

Prints the whole result set as an HTML table

`bool ovrimos_result_all (int result_id [, string format]) \linebreak`

ovrimos_result_all() is used to print an HTML table containing the whole result set.

ovrimos_result_all() prints the whole result set as an HTML table. Returns TRUE or FALSE.

Příklad 1. Prepare a statement, execute, and view the result

```
<?php
$conn = ovrimos_connect ("db_host", "8001", "admin", "password");
if ($conn != 0) {
    echo "Connection ok!";
    $res = ovrimos_prepare ($conn, "select table_id, table_name
                                from sys.tables where table_id = 7");

    if ($res != 0) {
        echo "Prepare ok!";
        if (ovrimos_execute ($res, array(3))) {
            echo "Execute ok!\n";
            ovrimos_result_all ($res);
        } else {
            echo "Execute not ok!";
        }
        ovrimos_free_result ($res);
    } else {
        echo "Prepare not ok!\n";
    }
    ovrimos_close($conn);
}
?>
```

This will execute an SQL statement and print the result in an HTML table.

Příklad 2. Ovrimos_result_all with meta-information

```

<?php
$conn = ovrimos_connect ("db_host", "8001", "admin", "password");
if ($conn != 0) {
    echo "Connection ok!";
    $res = ovrimos_exec ($conn, "select table_id, table_name
                                from sys.tables where table_id = 1")

    if ($res != 0) {
        echo "Statement ok! cursor=".ovrimos_cursor ($res)."\n";
        $colnb = ovrimos_num_fields ($res);
        echo "Output columns=".$colnb."\n";
        for ($i=1; $i <= $colnb; $i++) {
            $name = ovrimos_field_name ($res, $i);
            $type = ovrimos_field_type ($res, $i);
            $len = ovrimos_field_len ($res, $i);
            echo "Column ".$i." name=".$name." type=".$type." len=".$len."\n";
        }
        ovrimos_result_all ($res);
        ovrimos_free_result ($res);
    }
    ovrimos_close($conn);
}
?>

```

Příklad 3. ovrimos_result_all example

```

<?php
$conn = ovrimos_connect ("db_host", "8001", "admin", "password");
if ($conn != 0) {
    echo "Connection ok!";
    $res = ovrimos_exec ($conn, "update test set i=5");
    if ($res != 0) {
        echo "Statement ok!";
        echo ovrimos_num_rows ($res)." rows affected\n";
        ovrimos_free_result ($res);
    }
    ovrimos_close($conn);
}
?>

```


ovrimos_rollback (PHP 4 >= 4.0.3)

Rolls back the transaction

```
int ovrimos_rollback ( int connection_id) \linebreak
```

ovrimos_rollback() is used to roll back the transaction.

ovrimos_rollback() rolls back the transaction.

LXXIII. Output Control funkce

Output Control funkce (funkce pro řízení výstupu) vám umožňují ovládat, kdy se odešle výstup skriptu. To může být užitečné v několika různých situacích, zvláště pokud potřebujete poslat browseru hlavičky poté, co váš skript začal odesílat data. Output Control funkce neovlivňují hlavičky odeslané pomocí `header()` nebo `setcookie()`, pouze funkce jako `echo()` a data mezi bloky PHP kódu.

Příklad 1. Ukázka řízení výstupu

```
<?php

ob_start();
echo "Hello\n";

setcookie ("cookie", "cookiedata");

ob_end_flush();

?>
```

Ve výše uvedené ukázce se výstup z `echo()` uloží ve výstupním bufferu až do volání `ob_end_flush()`. Mezitím volání `setcookie()` úspěšně uložilo cookie bez vyvolání chyby. (Normálně nemůžete odeslat do browseru hlavičky poté, co už byla odeslána data.)

Viz také `header()` a `setcookie()`.

flush (PHP 3, PHP 4 >= 4.0.0)

Odeslat výstupní buffer

void **flush** (void) \linebreak

Vyprázdní výstupní buffery PHP a jakéhokoli backendu, který PHP používá (CGI, web server, atd.)
Odešle veškerý dosavadní výstup do uživatelského browseru.

Poznámka: flush() nemá žádný účinek na bufferovací schéma vašeho webserveru nebo browseru na klientské straně.

Některé servery, zvláště na Win32, bufferují výstup až do ukončení běhu skriptu bez ohledu na **flush()**, a až potom odešlou výstup browseru.

Browser může také bufferovat svůj vstup před zobrazením. Například Netscape bufferuje text do té doby než přijme konec řádku nebo začátek tagu, a nezobrazí tabulku, dokud nedostane `</table>` nejzjevnější tabulky.

ob_end_clean (PHP 4 >= 4.0.0)

Vyčistit (vymazat) výstupní buffer a vypnout bufferování výstupu

void **ob_end_clean** (void) \linebreak

Tato funkce odhodí obsah výstupního bufferu a vypne bufferování výstupu.

Viz také `ob_start()` a `ob_end_flush()`.

ob_end_flush (PHP 4 >= 4.0.0)

Vyprázdnit (odeslat) výstupní buffer a vypnout bufferování výstupu

void **ob_end_flush** (void) \linebreak

Tato funkce odešle obsah výstupního bufferu (pokud nějaký je) a vypne bufferování výstupu. Pokud chcete obsah výstupního bufferu dále zpracovávat, musíte před **ob_end_flush()** zavolat `ob_get_contents()`, protože obsah bufferu se po **ob_end_flush()** odhodí.

Viz také `ob_start()`, `ob_get_contents()` a `ob_end_clean()`.

ob_get_contents (PHP 4 >= 4.0.0)

Vrátit obsah výstupního bufferu

string **ob_get_contents** (void) \linebreak

Tato funkce vrátí obsah výstupního bufferu nebo `FALSE`, pokud bufferování výstupu není aktivováno.

Viz také `ob_start()` a `ob_get_length()`.

ob_get_length (PHP 4 >= 4.0.2)

Vrátit délku výstupního buffer

```
string ob_get_length ( void) \linebreak
```

Tato funkce vrátí délku obsahu výstupního bufferu nebo This will return the length of the contents in the output buffer, nebo `FALSE`, pokud bufferování výstupu není aktivováno.

Viz také `ob_start()` a `ob_get_contents()`.

ob_implicit_flush (PHP 4 >= 4.0.0)

Vypnout/zapnout implicitní flush

```
void ob_implicit_flush ( [int flag]) \linebreak
```

ob_implicit_flush() vypne nebo zapne implicitní flushování (pokud nedostane žádný *flag*, default je zapnout). Implicitní flushování způsobí flush po každém vygenerování výstupu, takže už nebudou potřeba explicitní volání `flush()`.

Zapnutí implicitního flushování zruší bufferování výstupu, a aktuální obsah výstupních bufferů se odešle jako při volání `ob_end_flush()`.

Viz také `flush()`, `ob_start()` a `ob_end_flush()`.

ob_start (PHP 4 >= 4.0.0)

Zapnout bufferování výstupu

```
void ob_start ( [string output_callback]) \linebreak
```

Tato funkce zapíná bufferování výstupu. Pokud je bufferování výstupu aktivováno, žádný výstup ze skriptu se neodešle, místo toho se ukládá v interním bufferu.

Obsah tohoto interního bufferu je možno zkopírovat do proměnné typu string pomocí `ob_get_contents()`. K odeslání obsahu interního bufferu použijte `ob_end_flush()`. Naprotitomu `ob_end_clean()` tiše odstraní obsah výstupního bufferu.

Můžete zadat volitelný název callback funkce, která se automaticky zavolá s obsahem bufferu jako argumentem. Tato funkce musí přijímat řetězec a vracet řetězec. Tato funkce bude volána při `ob_end_flush()` a dostane obsah výstupního bufferu jako svůj argument. Musí vrátit nový výstupní buffer, který se pak vytiskne.

Výstupní buffery se dají stackovat, tzn. můžete zavolat **ob_start()** zatímco je aktivní další **ob_start()**. Je potřeba pouze správný počet volání **ob_end_flush()**. Pokud je aktivních více output callback funkcí, výstup je filtrován postupně přes každou z nich tak jak jsou do sebe vnořené.

Příklad 1. Ukázka callback funkce

```

<?php
function c($str) {
    // Druu Chunusun mut dum Kuntrubuß...
    return nl2br(ereg_replace("[aeiou]", "u", $str));
}

function d($str) {
    return strip_tags($str);
}
?>

<?php ob_start("c"); ?>
Drei Chinesen mit dem Kontrabaß...
<?php ob_start("d"); ?>
<h1>..saßen auf der Straße und erzählten sich was...</h1>
<?php ob_end_flush(); ?>
... da kam die Polizei, ja was ist denn das?
<?php ob_end_flush(); ?>

?>

```

Viz také `ob_get_contents()`, `ob_end_flush()`, `ob_end_clean()`, and `ob_implicit_flush()`

LXXIV. Object property and method call overloading

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

The purpose of this extension is to allow overloading of object property access and method calls. Only one function is defined in this extension, `overload()` which takes the name of the class that should have this functionality enabled. The class named has to define appropriate methods if it wants to have this functionality: `__get()`, `__set()` and `__call()` respectively for getting/setting a property, or calling a method. This way overloading can be selective. Inside these handler functions the overloading is disabled so you can access object properties normally.

Some simple examples on using the `overload()` function:

Příklad 1. Overloading a PHP class

```
<?php

class OO
{
    var $a = 111;
    var $elem = array('b' => 9, 'c' => 42);

    // Callback method for getting a property
    function __get($prop_name, &$prop_value)
    {
        if (isset($this->elem[$prop_name])) {
            $prop_value = $this->elem[$prop_name];
            return true;
        } else {
            return false;
        }
    }

    // Callback method for setting a property
    function __set($prop_name, $prop_value)
    {
        $this->elem[$prop_name] = $prop_value;
        return true;
    }
}

// Here we overload the OO object
overload('OO');

$o = new OO;
print "\$o->a: $o->a\n"; // print: $o->a:
print "\$o->b: $o->b\n"; // print: $o->b: 9
```

```
print "\$o->c: $o->c\n"; // print: $o->c: 42
print "\$o->d: $o->d\n"; // print: $o->d:

// add a new item to the $elem array in OO
$o->x = 56;

// instantiate stdClass (it is built-in in PHP 4)
// $val is not overloaded!
$val = new stdClass;
$val->prop = 555;

// Set "a" to be an array with the $val object in it
// But __set() will put this in the $elem array
$o->a = array($val);
var_dump($o->a[0]->prop);

?>
```

Varování

As this is an experimental extension, not all things work. There is no `__call()` support currently, you can only overload the get and set operations for properties. You cannot invoke the original overloading handlers of the class, and `__set()` only works to one level of property access.

overload (PHP 4 >= 4.2.0)

Enable property and method call overloading for a class

```
void overload ( [string class_name]) \linebreak
```

The **overload()** function will enable property and method call overloading for a class identified by *class_name*. See an example in the introductory section of this part.

LXXV. PDF funkce

Introduction

Pokud máte PDF knihovnu od Thomase Merze (dostupná z <http://www.pdflib.com/pdflib/index.html>), můžete používat PDF funkce na tvorbu PDF souborů; ke kompilaci budete potřebovat také JPEG knihovnu (<ftp://ftp.uu.net/graphics/jpeg/>) a TIFF knihovnu (<http://www.libtiff.org/>). Tyto dvě knihovny poměrně často dělají potíže při konfiguraci PHP. Při řešení případných problémů se řiďte chybovými zprávami configure skriptu.

Věnujte prosím pozornost výborné dokumentaci pdflib, která je součástí distribuce zdrojového kódu. Poskytuje velmi dobrý přehled schopností pdflib. Většina funkcí pdflib a příslušného PHP modulu má stejné jméno. Argumenty jsou také identické. Pokud chcete tento modul využívat opravdu efektivně, měli byste chápat také některé z konceptů PDF nebo Postscriptu. Všechny rozměry a koordináty se udávají v Postscriptových bodech. Obecně je 72 PostScriptových bodů na palec, ale závisí to na výstupním rozlišení.

Existuje další PHP modul na tvorbu PDF dokumentů, založený na ClibPDF od firmy FastIO (<http://www.fastio.com/>). Má mírně jinou API. Detaily viz ClibPDF funkce.

Tento PDF modul zavádí nový typ proměnné. Nazývá se *pdfdoc*. *pdfdoc* je pointer na PDF dokument a téměř všechny funkce ho vyžadují jako svůj první argument.

Zmatek se starými verzemi pdflib

Od úplného začátku podpory PDF v PHP — od pdflib 0.6 — došlo k mnoha změnám zvláště v API pdflib. Většinu těchto změn PHP nějak zakrylo, některé vyžadovaly změnu PHP API. Od pdflib 3.x se API snad stabilizovala, a PHP 4 přijala tuto verzi jako minimální pro podporu PDF. Následkem toho mnoho funkcí dříve či později zmizí nebo bude nahrazeno alternativami. Podpora pdflib 0.6 už byla naprosto ukončena. Následující tabulka vyjmenovává všechny funkce, které jsou od PHP 4.0.2 zastaralé a měly by být nahrazeny jejich novějšími verzemi.

Tabulka 1. Zastaralé funkce a jejich náhrady

Stará funkce	Náhrada
<code>pdf_put_image()</code>	Není potřeba.
<code>pdf_get_font()</code>	<code>pdf_get_value()</code> s "font" jako druhý argument.
<code>pdf_get_fontsize()</code>	<code>pdf_get_value()</code> s "fontsize" jako druhý argument.
<code>pdf_get_fontname()</code>	<code>pdf_get_parameter()</code> s "fontname" jako druhý argument.
<code>pdf_set_info_creator()</code>	<code>pdf_set_info()</code> s "Creator" jako druhý argument.
<code>pdf_set_info_title()</code>	<code>pdf_set_info()</code> s "Title" jako druhý argument.
<code>pdf_set_info_subject()</code>	<code>pdf_set_info()</code> s "Subject" jako druhý argument.
<code>pdf_set_info_author()</code>	<code>pdf_set_info()</code> s "Author" jako druhý argument.

Stará funkce	Náhrada
pdf_set_info_keywords()	pdf_set_info() s "Keywords" jako druhý argument.
pdf_set_leading()	pdf_set_value() s "leading" jako druhý argument.
pdf_set_text_rendering()	pdf_set_value() s "textrendering" jako druhý argument.
pdf_set_text_rise()	pdf_set_value() s "textrise" jako druhý argument.
pdf_set_horiz_scaling()	pdf_set_value() s "horizscaling" jako druhý argument.
pdf_set_text_matrix()	neexistuje
pdf_set_char_spacing()	pdf_set_value() s "charspacing" jako druhý argument.
pdf_set_word_spacing()	pdf_set_value() s "wordspacing" jako druhý argument.
pdf_set_transition()	pdf_set_parameter() s "transition" jako druhý argument.
pdf_set_duration()	pdf_set_value() s "duration" jako druhý argument.
pdf_open_gif()	pdf_open_image_file() s "gif" jako druhý argument.
pdf_open_jpeg()	pdf_open_image_file() s "jpeg" jako druhý argument.
pdf_open_tiff()	pdf_open_image_file() s "tiff" jako druhý argument.
pdf_open_png()	pdf_open_image_file() s "png" jako druhý argument.
pdf_get_imagewidth()	pdf_get_value() s "imagewidth" jako druhý argument a obrázkem jako třetí argument.
pdf_get_imageheight()	pdf_get_value() s "imageheight" jako druhý argument a obrázkem jako třetí argument.
()	()

Rady pro instalaci pdflib 3.x

Od pdflib 3.0 by se pdflib měla konfigurovat s volbou `--enable-shared-pdflib`.

Problémy se staršími verzemi pdflib

Pokud používáte pdflib 2.01, zkontrolujte, jak je tato knihovna nainstalována. Měli byste mít soubor `libpdf.so`, nebo link na něj. Verze 2.01 vytváří soubor `libpdf2.01.so`, který se nedá najít při linkování

testovacího souboru v configure. Budete muset vytvořit symbolický link z libpdf.so na libpdf2.01.so.

Ve verzi 2.20 přibily další změny v API pdflib a podpora čínských a japonských fontů. Pokud používáte pdflib 2.20 buďte opatrní při generování PDF dokumentů v paměti. Do verze pdflib 3.0 by mohlo být nestabilní. Argument kódování v pdf_set_font() se změnil na řetězec. To znamená, že místo např. 4 musíte použít 'winansi'.

Pokud používáte pdflib 2.30, nemáte k dispozici pdf_set_text_matrix(). Přestala být podporována. Obecnou radou je zjistit si případné změny v release notes používané verze pdflib.

Žádná verze PHP 4 od data 9. března 2000 nepodporuje pdflib starší než 3.0. Na druhou stranu, PHP 3 by se nemělo používat s novější verzí pdflib než 2.01.

Ukázky

Většina funkcí se používá docela snadno. Nejtěžší je zřejmě vůbec nějaký jednoduchý PDF dokument vůbec vytvořit. Následující ukázka by měla pomoci začít. Vytvoří soubor test.pdf s jednou stránkou. Tato stránka obsahuje text "Times Roman outlined" napsaný 30ti bodovým obrysem. Text je také podtržený.

Příklad 1. Tvorba PDF dokumentu s pdflib

```
<?php
$fp = fopen("test.pdf", "w");
$pdf = pdf_open($fp);
pdf_set_info($pdf, "Author", "Uwe Steinmann");
pdf_set_info($pdf, "Title", "Test for PHP wrapper of PDFlib 2.0");
pdf_set_info($pdf, "Creator", "See Author");
pdf_set_info($pdf, "Subject", "Testing");
pdf_begin_page($pdf, 595, 842);
pdf_add_outline($pdf, "Page 1");
pdf_set_font($pdf, "Times-Roman", 30, "host");
pdf_set_value($pdf, "textrendering", 1);
pdf_show_xy($pdf, "Times Roman outlined", 50, 750);
pdf_moveto($pdf, 50, 740);
pdf_lineto($pdf, 330, 740);
pdf_stroke($pdf);
pdf_end_page($pdf);
pdf_close($pdf);
fclose($fp);
echo "<A HREF=getpdf.php>finished</A>";
?>
```

Skript getpdf.php pouze vrátí vytvořený pdf dokument.

```
<?php
$fp = fopen("test.pdf", "r");
header("Content-type: application/pdf");
fpassthru($fp);
fclose($fp);
?>
```

Distribuce pdflib obsahuje rozsáhlejší ukázkou, která obsahuje sérii stránek s analogovými hodinami. Tato ukázka převedená do PHP vypadá takto (stejnou ukázkou najdete v dokumentaci k clibpdf modulu):

Příklad 2. pdfclock ukázka z pdflib distribuce

```
<?php
$pdffilename = "clock.pdf";
$radius = 200;
$margin = 20;
$pagecount = 40;

$fp = fopen($pdffilename, "w");
$pdf = pdf_open($fp);
pdf_set_info($pdf, "Creator", "pdf_clock.php3");
pdf_set_info($pdf, "Author", "Uwe Steinmann");
pdf_set_info($pdf, "Title", "Analog Clock");

while($pagecount-- > 0) {
    pdf_begin_page($pdf, 2 * ($radius + $margin), 2 * ($radius + $margin));

    pdf_set_parameter($pdf, "transition", "wipe");
    pdf_set_value($pdf, "duration", 0.5);

    pdf_translate($pdf, $radius + $margin, $radius + $margin);
    pdf_save($pdf);
    pdf_setrgbcolor($pdf, 0.0, 0.0, 1.0);

    /* minute strokes */
    pdf_setlinewidth($pdf, 2.0);
    for ($alpha = 0; $alpha < 360; $alpha += 6) {
        pdf_rotate($pdf, 6.0);
        pdf_moveto($pdf, $radius, 0.0);
        pdf_lineto($pdf, $radius-$margin/3, 0.0);
        pdf_stroke($pdf);
    }

    pdf_restore($pdf);
    pdf_save($pdf);

    /* 5 minute strokes */
    pdf_setlinewidth($pdf, 3.0);
    for ($alpha = 0; $alpha < 360; $alpha += 30) {
        pdf_rotate($pdf, 30.0);
        pdf_moveto($pdf, $radius, 0.0);
        pdf_lineto($pdf, $radius-$margin, 0.0);
        pdf_stroke($pdf);
    }

    $ltime = getdate();
```

```

/* draw hour hand */
pdf_save($pdf);
pdf_rotate($pdf, -(($ltime['minutes']/60.0)+$ltime['hours']-3.0)*30.0);
pdf_moveto($pdf, -$radius/10, -$radius/20);
pdf_lineto($pdf, $radius/2, 0.0);
pdf_lineto($pdf, -$radius/10, $radius/20);
pdf_closepath($pdf);
pdf_fill($pdf);
pdf_restore($pdf);

/* draw minute hand */
pdf_save($pdf);
pdf_rotate($pdf, -(($ltime['seconds']/60.0)+$ltime['minutes']-15.0)*6.0);
pdf_moveto($pdf, -$radius/10, -$radius/20);
pdf_lineto($pdf, $radius * 0.8, 0.0);
pdf_lineto($pdf, -$radius/10, $radius/20);
pdf_closepath($pdf);
pdf_fill($pdf);
pdf_restore($pdf);

/* draw second hand */
pdf_setrgbcolor($pdf, 1.0, 0.0, 0.0);
pdf_setlinewidth($pdf, 2);
pdf_save($pdf);
pdf_rotate($pdf, -(($ltime['seconds'] - 15.0) * 6.0));
pdf_moveto($pdf, -$radius/5, 0.0);
pdf_lineto($pdf, $radius, 0.0);
pdf_stroke($pdf);
pdf_restore($pdf);

/* draw little circle at center */
pdf_circle($pdf, 0, 0, $radius/30);
pdf_fill($pdf);

pdf_restore($pdf);

pdf_end_page($pdf);
}

$pdf = pdf_close($pdf);
fclose($fp);
echo "<A HREF=getpdf.php?filename=".$pdffilename.">finished</A>";
?>

```

PHP skript `getpdf.php` pouze vrátí vytvořený PDF dokument.

```

<?php
$fp = fopen($filename, "r");
header("Content-type: application/pdf");
fpassthru($fp);
fclose($fp);
?>

```

pdf_add_annotation (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Adds annotation

void **pdf_add_annotation** (int pdf document, double llx, double lly, double urx, double ury, string title, string content) \linebreak

Funkce **pdf_add_annotation()** adds a note with the lower left corner at (*llx*, *lly*) and the upper right corner at (*urx*, *ury*).

pdf_add_outline (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Adds bookmark for current page

int **pdf_add_outline** (int pdf document, string text [, int parent [, int open]]) \linebreak

Funkce **pdf_add_outline()** function adds a bookmark with text *text* that points to the current page. The bookmark is inserted as a child of *parent* and is by default open if *open* is not 0. The return value is an identifier for the bookmark which can be used as a parent for other bookmarks. Therefore you can build up hierarchies of bookmarks.

Unfortunately pdflib does not make a copy of the string, which forces PHP to allocate the memory. Currently this piece of memory is not been freed by any PDF function but it will be taken care of by the PHP memory manager.

pdf_arc (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Draws an arc

void **pdf_arc** (int pdf document, double x-coor, double y-coor, double radius, double start, double end) \linebreak

Funkce **pdf_arc()** function draws an arc with center at point (*x-coor*, *y-coor*) and radius *radius*, starting at angle *start* and ending at angle *end*.

Viz také pdf_circle(), pdf_stroke().

pdf_begin_page (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Začít novou stranu

void **pdf_begin_page** (int pdf document, double width, double height) \linebreak

Funkce **pdf_begin_page()** začne novou stránku s výškou *height* a šířkou *width*. Pokud chcete vytvořit validní dokument, musíte zavolat tuto funkci a pdf_end_page() přinejmenším jednou.

Viz také pdf_end_page().

pdf_circle (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Draws a circle

void **pdf_circle** (int pdf document, double x-coor, double y-coor, double radius) \linebreak

Funkce **pdf_circle()** function draws a circle with center at point (*x-coor*, *y-coor*) and radius *radius*.

Viz také pdf_arc(), pdf_stroke().

pdf_clip (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Clips to current path

void **pdf_clip** (int pdf document) \linebreak

Funkce **pdf_clip()** function clips all drawing to the current path.

pdf_close (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Zavřít PDF dokument

void **pdf_close** (int pdf document) \linebreak

Funkce **pdf_close()** zavře PDF dokument.

Viz také pdf_open(), fclose().

pdf_close_image (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Closes an image

void **pdf_close_image** (int image) \linebreak

Funkce **pdf_close_image()** function closes an image which has been opened with any of the **pdf_open_xxx()** functions.

Viz také pdf_open_jpeg(), pdf_open_gif(), pdf_open_memory_image().

pdf_closepath (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Closes path

void **pdf_closepath** (int pdf document) \linebreak

Funkce **pdf_closepath()** function closes the current path. This means, it draws a line from current point to the point where the first line was started. Many functions like **pdf_moveto()**, **pdf_circle()** and **pdf_rect()** start a new path.

pdf_closepath_fill_stroke (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Closes, fills and strokes current path

```
void pdf_closepath_fill_stroke ( int pdf document) \linebreak
```

Funkce **pdf_closepath_fill_stroke()** function closes, fills the interior of the current path with the current fill color and draws current path.

Viz také **pdf_closepath()**, **pdf_stroke()**, **pdf_fill()**, **pdf_setgray_fill()**, **pdf_setgray()**, **pdf_setrgbcolor_fill()**, **pdf_setrgbcolor()**.

pdf_closepath_stroke (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Closes path and draws line along path

```
void pdf_closepath_stroke ( int pdf document) \linebreak
```

Funkce **pdf_closepath_stroke()** function is a combination of **pdf_closepath()** and **pdf_stroke()**. It also clears the path.

Viz také **pdf_closepath()**, **pdf_stroke()**.

pdf_continue_text (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Outputs text in next line

```
void pdf_continue_text ( int pdf document, string text) \linebreak
```

Funkce **pdf_continue_text()** function outputs the string in *text* in the next line. The distance between the lines can be set with **pdf_set_leading()**.

Viz také **pdf_show_xy()**, **pdf_set_leading()**, **pdf_set_text_pos()**.

pdf_curveto (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Draws a curve

```
void pdf_curveto ( int pdf document, double x1, double y1, double x2, double y2, double x3, double y3) \linebreak
```

Funkce **pdf_curveto()** function draws a Bezier curve from the current point to the point (*x3*, *y3*) using (*x1*, *y1*) and (*x2*, *y2*) as control points.

Viz také `pdf_moveto()`, `pdf_lineto()`, `pdf_stroke()`.

pdf_end_page (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Ukončit stranu

```
void pdf_end_page ( int pdf document) \linebreak
```

Funkce **pdf_end_page()** ukončí stranu. Jakmile je strana ukončena, nedá se už upravovat.

Viz také `pdf_begin_page()`.

pdf_endpath (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Ends current path

```
void pdf_endpath ( int pdf document) \linebreak
```

Funkce **pdf_endpath()** function ends the current path but does not close it.

Viz také `pdf_closepath()`.

pdf_execute_image (PHP 3>= 3.0.7)

Places a stored image on the page

```
void pdf_execute_image ( int pdf document, int image, double x-coor, double y-coor, double scale) \linebreak
```

Funkce **pdf_execute_image()** function displays an image that has been put in the PDF file with the `pdf_put_image()` function on the current page at the given coordinates.

The image can be scaled while displaying it. A scale of 1.0 will show the image in the original size.

Poznámka: This function has become meaningless with version 2.01 of pdf-lib. It will just output a warning.

Příklad 1. Multiple show of an image

```
<?php
$im = ImageCreate(100, 100);
$coll = ImageColorAllocate($im, 80, 45, 190);
ImageFill($im, 10, 10, $coll);
$pim = pdf_open_memory_image($pdf, $im);
pdf_put_image($pdf, $pim);
pdf_execute_image($pdf, $pim, 100, 100, 1);
pdf_execute_image($pdf, $pim, 200, 200, 2);
pdf_close_image($pdf, $pim);
```

?>

pdf_fill (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Fills current path

void **pdf_fill** (int pdf document) \linebreak

Funkce **pdf_fill()** function fills the interior of the current path with the current fill color.

Viz také pdf_closepath(), pdf_stroke(), pdf_setgray_fill(), pdf_setgray(), pdf_setrgbcolor_fill(), pdf_setrgbcolor().

pdf_fill_stroke (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Fills and strokes current path

void **pdf_fill_stroke** (int pdf document) \linebreak

Funkce **pdf_fill_stroke()** function fills the interior of the current path with the current fill color and draws current path.

Viz také pdf_closepath(), pdf_stroke(), pdf_fill(), pdf_setgray_fill(), pdf_setgray(), pdf_setrgbcolor_fill(), pdf_setrgbcolor().

pdf_get_image_height (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Returns height of an image

string **pdf_get_image_height** (int pdf document, int image) \linebreak

Funkce **pdf_get_image_height()** function returns the heights of a pdf image in pixel.

Viz také pdf_open_image_file(), pdf_open_memory_image(), pdf_get_image_width().

pdf_get_image_width (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Returns width of an image

string **pdf_get_image_width** (int pdf document, int image) \linebreak

Funkce **pdf_get_image_width()** function returns the widths of a pdf image in pixel.

Viz také pdf_open_image_file(), pdf_open_memory_image(), pdf_get_image_height().

pdf_get_parameter (PHP 4)

Zjistit hodnotu parametru

string **pdf_get_parameter** (int pdf document, string name [, double modifier]) \linebreak

Funkce **pdf_get_parameter()** function gets several parameters of pdflib which are of the type string. The function parameter *modifier* characterizes the parameter to get. If the modifier is not needed it has to be 0 or not passed at all.

Viz také pdf_get_value(), pdf_set_value(), pdf_set_parameter().

pdf_get_value (PHP 4)

Gets certain numerical value

double **pdf_get_value** (int pdf document, string name [, double modifier]) \linebreak

Funkce **pdf_get_value()** function gets several numerical parameters of pdflib. The function parameter *modifier* characterizes the parameter to get. If the modifier is not needed it has to be 0 or not passed at all.

Viz také pdf_set_value(), pdf_get_parameter(), pdf_set_parameter().

pdf_lineto (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Draws a line

void **pdf_lineto** (int pdf document, double x-coor, double y-coor) \linebreak

Funkce **pdf_lineto()** function draws a line from the current point to the point with coordinates (*x-coor*, *y-coor*).

Viz také pdf_moveto(), pdf_curveto(), pdf_stroke().

pdf_moveto (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets current point

void **pdf_moveto** (int pdf document, double x-coor, double y-coor) \linebreak

Funkce **pdf_moveto()** function sets the current point to the coordinates *x-coor* and *y-coor*.

pdf_open (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Otevřít nový PDF dokument

int **pdf_open** (int file) \linebreak

Funkce **pdf_open()** otvírá nový PDF dokument. Odpovídající soubor musí být otevřen funkcí `fopen()` a jeho deskriptor předán jako argument *file*. Pokud této funkci nepředáte žádné argumenty, dokument bude vytvořen v paměti a vrácen stránku po stránce buď na stdout (standardní výstup) nebo do browseru.

Poznámka: Návrátová hodnota je potřeba jako první argument pro všechny ostatní funkce zapisující do PDF dokumentu.

Viz také `fopen()`, `pdf_close()`.

pdf_open_gif (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Opens a GIF image

int **pdf_open_gif** (int pdf document, string filename) \linebreak

Funkce **pdf_open_gif()** function opens an image stored in the file with the name *filename*. The format of the image has to be gif. The function returns a pdf image identifier.

Poznámka: This function shouldn't be used anymore. Please use the function `pdf_open_image_file()` instead.

Příklad 1. Including a gif image

```
<?php
$im = pdf_open_gif($pdf, "test.gif");
pdf_place_image($pdf, $im, 100, 100, 1);
pdf_close_image($pdf, $im);
?>
```

Viz také `pdf_close_image()`, `pdf_open_jpeg()`, `pdf_open_memory_image()`, `pdf_execute_image()`, `pdf_place_image()`, `pdf_put_image()`.

pdf_open_image_file (PHP 3 CVS only, PHP 4 >= 4.0.0)

Reads an image from a file

int **pdf_open_image_file** (int PDF-document, string format, string filename) \linebreak

The function **pdf_open_image_file()** reads an image of format *format* from the file *filename*. Possible formats are 'png', 'tiff', 'jpeg' and 'gif'. The function returns a pdf image identifier.

Příklad 1. Inserting an image

```
<?php
$vim = pdf_open_image_file($pdf, "png", "picture.png");
pdf_place_image($pdf, $vim, 100, 100, 1);
pdf_close_image($pdf, $vim);
?>
```

Viz také pdf_close_image(), pdf_open_jpeg(), pdf_open_gif(), pdf_open_tiff(), pdf_open_png(), pdf_execute_image(), pdf_place_image(), pdf_put_image().

pdf_open_jpeg (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Opens a JPEG image

```
int pdf_open_jpeg ( int pdf document, string filename) \linebreak
```

Funkce **pdf_open_jpeg()** function opens an image stored in the file with the name *filename*. The format of the image has to be jpeg. The function returns a pdf image identifier.

Poznámka: This function shouldn't be used anymore. Please use the function pdf_open_image_file() instead.

Viz také pdf_close_image(), pdf_open_gif(), pdf_open_png(), pdf_open_memory_image(), pdf_execute_image(), pdf_place_image(), pdf_put_image().

pdf_open_memory_image (PHP 3 >= 3.0.10, PHP 4 >= 4.0.0)

Opens an image created with PHP's image functions

```
int pdf_open_memory_image ( int pdf document, int image) \linebreak
```

Funkce **pdf_open_memory_image()** function takes an image created with the PHP's image functions and makes it available for the PDF dokument. The function returns a pdf image identifier.

Příklad 1. Including a memory image

```
<?php
$im = ImageCreate(100, 100);
$col = ImageColorAllocate($im, 80, 45, 190);
ImageFill($im, 10, 10, $col);
$vim = pdf_open_memory_image($pdf, $im);
ImageDestroy($im);
pdf_place_image($pdf, $vim, 100, 100, 1);
pdf_close_image($pdf, $vim);
?>
```

Viz také `pdf_close_image()`, `pdf_open_jpeg()`, `pdf_open_gif()`, `pdf_open_png()`, `pdf_execute_image()`, `pdf_place_image()`, `pdf_put_image()`.

pdf_open_png (PHP 4 >= 4.0.0)

Opens a PNG image

`int pdf_open_png (int pdf, string png_file) \linebreak`

Funkce **pdf_open_png()** function opens an image stored in the file with the name *filename*. The format of the image has to be png. The function returns a pdf image identifier.

Poznámka: This function shouldn't be used anymore. Please use the function `pdf_open_image_file()` instead.

Příklad 1. Including a PNG image

```
<?php
$im = pdf_open_png ($pdf, "test.png");
pdf_place_image ($pdf, $im, 100, 100, 1);
pdf_close_image ($pdf, $im);
?>
```

Viz také `pdf_close_image()`, `pdf_open_jpeg()`, `pdf_open_gif()`, `pdf_open_memory_image()`, `pdf_execute_image()`, `pdf_place_image()`, `pdf_put_image()`.

pdf_open_tiff (PHP 4 >= 4.0.0)

Opens a TIFF image

`int pdf_open_tiff (int PDF-document, string filename) \linebreak`

Funkce **pdf_open_tiff()** function opens an image stored in the file with the name *filename*. The format of the image has to be tiff. The function returns a pdf image identifier.

Poznámka: This function shouldn't be used anymore. Please use the function `pdf_open_image_file()` instead.

Viz také `pdf_close_image()`, `pdf_open_gif()`, `pdf_open_jpeg()`, `pdf_open_png()`, `pdf_open_memory_image()`, `pdf_execute_image()`, `pdf_place_image()`, `pdf_put_image()`.

pdf_place_image (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Places an image on the page

```
void pdf_place_image ( int pdf document, int image, double x-coor, double y-coor, double scale) \linebreak
```

Funkce **pdf_place_image()** function places an image on the page at postion (*x-coor*, *x-coor*). The image can be scaled at the same time.

Viz také pdf_put_image().

pdf_put_image (PHP 3>= 3.0.7)

Stores an image in the PDF for later use

```
void pdf_put_image ( int pdf document, int image) \linebreak
```

Funkce **pdf_put_image()** function places an image in the PDF file without showing it. The stored image can be displayed with the pdf_execute_image() function as many times as needed. This is useful when using the same image multiple times in order to keep the file size small. Using **pdf_put_image()** and pdf_execute_image() is highly recommended for larger images (several kb) if they show up more than once in the document.

Poznámka: This function has become meaningless with version 2.01 of pdfplib. It will just output a warning.

Viz také **pdf_put_image()**, pdf_place_image(), pdf_execute_image().

pdf_rect (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Draws a rectangle

```
void pdf_rect ( int pdf document, double x-coor, double y-coor, double width, double height) \linebreak
```

Funkce **pdf_rect()** function draws a rectangle with its lower left corner at point (*x-coor*, *y-coor*). This width is set to *width*. This height is set to *height*.

Viz také pdf_stroke().

pdf_restore (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Restores formerly saved environment

```
void pdf_restore ( int pdf document) \linebreak
```

Funkce **pdf_restore()** function restores the environment saved with pdf_save(). It works like the postscript command grestore.

Příklad 1. Save and Restore

```
<?php pdf_save($pdf);
// do all kinds of rotations, transformations, ...
pdf_restore($pdf) ?>
```

Viz také pdf_save().

pdf_rotate (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets rotation

```
void pdf_rotate ( int pdf document, double angle) \linebreak
```

Funkce **pdf_rotate()** function sets the rotation in degrees to *angle*.

pdf_save (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Saves the current environment

```
void pdf_save ( int pdf document) \linebreak
```

Funkce **pdf_save()** function saves the current environment. It works like the postscript command gsave. Very useful if you want to translate or rotate an object without affecting other objects.

pdf_save() should always be followed by pdf_restore() to restore the environment before **pdf_save()**.

Viz také pdf_restore().

pdf_scale (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets scaling

```
void pdf_scale ( int pdf document, double x-scale, double y-scale) \linebreak
```

Funkce **pdf_scale()** function sets the scaling factor in both directions. The following example scales x and y direction by 72. The following line will therefore be drawn one inch in both directions.

Příklad 1. Scaling

```
<?php pdf_scale($pdf, 72.0, 72.0);
pdf_lineto($pdf, 1, 1);
pdf_stroke($pdf);
?>
```


pdf_set_border_color (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Sets color of border around links and annotations

```
void pdf_set_border_color ( int pdf document, double red, double green, double blue) \linebreak
```

Funkce **pdf_set_border_color()** function sets the color of the surrounding box of links and annotations. The three color components have to have a value between 0.0 and 1.0.

Viz také pdf_set_border_style(), pdf_set_border_dash().

pdf_set_border_dash (PHP 4)

Sets dash style of border around links and annotations

```
void pdf_set_border_dash ( int pdf document, double black, double white) \linebreak
```

Funkce **pdf_set_border_dash()** function sets the length of black and white areas of a dashed line of the surrounding box of links and annotations.

Viz také pdf_set_border_style(), pdf_set_border_color().

pdf_set_border_style (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Sets style of border around links and annotations

```
void pdf_set_border_style ( int pdf document, string style, double width) \linebreak
```

Funkce **pdf_set_border_style()** function sets the style and width of the surrounding box of links and annotations. Arguments *style* can be 'solid' or 'dashed'.

Viz také pdf_set_border_color(), pdf_set_border_dash().

pdf_set_char_spacing (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets character spacing

```
void pdf_set_char_spacing ( int pdf document, double space) \linebreak
```

Funkce **pdf_set_char_spacing()** function sets the spacing between characters.

Viz také pdf_set_word_spacing(), pdf_set_leading().

pdf_set_duration (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets duration between pages

```
void pdf_set_duration ( int pdf document, double duration) \linebreak
```

Funkce **pdf_set_duration()** function set the duration between following pages in seconds.

Viz také pdf_set_transition().

pdf_set_font (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Určit font a velikost

```
void pdf_set_font ( int pdf document, string font name, double size, string encoding [, int embed]) \linebreak
```

Funkce **pdf_set_font()** nastaví platný font, velikost, a kódování. Pokud používáte pdflib 0.6, budete muset poskytnout Adobe Font Metrics (afm soubory) pro daný font ve font cestě (default je ./fonts). Pokud používáte PHP 3 nebo pdflib ve verzi starší než 2.20, čtvrtý argument *encoding* může mít následující hodnoty: 0 = builtin, 1 = pdfdoc, 2 = macroman, 3 = macexpert, 4 = winansi. Při *encoding* větší než 4 a menší než 0 se použije winansi. Většinou je to správná volba. Pokud používáte PHP 4 a pdflib ve verzi >= 2.20, argument *encoding* se změnil na řetězec. Používejte 'winansi', 'builtin', 'host', 'macroman' atd. Pokud má poslední argument hodnotu 1, font se vloží do PDF dokumentu. Vložit font je obvykle dobrý nápad, pokud tento font není příliš rozšířený a nemůžete zaručit, že osoba, která váš dokument čte, má přístup k fontům v dokumentu použitým. Font se vloží pouze jednou, i když voláte **pdf_set_font()** několikrát.

Poznámka: Pokud se má vytvořit validní PDF dokument, tato funkce se musí volat až po pdf_begin_page().

Poznámka: Pokud v .upr souboru odkazujete na nějaký font, ujistěte se, že jméno v afm souboru a jméno fontu jsou stejné. Jinak se font vloží vícekrát. (Díky Paulu Haddonovi za toto zjištění.)

pdf_set_horiz_scaling (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets horizontal scaling of text

```
void pdf_set_horiz_scaling ( int pdf document, double scale) \linebreak
```

Funkce **pdf_set_horiz_scaling()** function sets the horizontal scaling to *scale* percent.

pdf_set_info (PHP 4)

Vyplnit položku informací o dokumentu

```
void pdf_set_info ( int pdf document, string fieldname, string value) \linebreak
```

Funkce **pdf_set_info()** vyplní informační pole PDF dokumentu. Možné hodnoty argumentu *fieldname* jsou 'Subject', 'Title', 'Creator', 'Author', 'Keywords' a jeden uživatelsky definovaný název. Může být volána před začátkem stránky.

Příklad 1. Zadání informací o dokumentu

```
<?php
$fd = fopen("test.pdf", "w");
$pdfdoc = pdf_open($fd);
pdf_set_info($pdfdoc, "Author", "Uwe Steinmann");
pdf_set_info($pdfdoc, "Creator", "Uwe Steinmann");
pdf_set_info($pdfdoc, "Title", "Testing Info Fields");
pdf_set_info($pdfdoc, "Subject", "Test");
pdf_set_info($pdfdoc, "Keywords", "Test, Fields");
pdf_set_info($pdfdoc, "CustomField", "What ever makes sense");
pdf_begin_page($pdfdoc, 595, 842);
pdf_end_page($pdfdoc);
pdf_close($pdfdoc);
?>
```

Poznámka: Tato funkce nahrazuje **pdf_set_info_keywords()**, **pdf_set_info_title()**, **pdf_set_info_subject()**, **pdf_set_info_creator()** a **pdf_set_info_sybject()**.

pdf_set_leading (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Nastavit vzdálenost mezi řádky

```
void pdf_set_leading ( int pdf document, double distance) \linebreak
```

Funkce **pdf_set_leading()** nastavuje vzdálenost mezi řádky textu. Toto nastavení se použije, pokud se text tvoří pomocí **pdf_continue_text()**.

Viz také **pdf_continue_text()**.

pdf_set_parameter (PHP 4 >= 4.0.0)

Nastavit určité parametry

```
void pdf_set_parameter ( int pdf document, string name, string value) \linebreak
```

Funkce **pdf_set_parameter()** nastaví určité parametry pdflib, které jsou typu string.

Viz také **pdf_get_value()**, **pdf_set_value()**, **pdf_get_parameter()**.

pdf_set_text_matrix (PHP 3>= 3.0.6)

Sets the text matrix

```
void pdf_set_text_matrix ( int pdf document, array matrix) \linebreak
```

Funkce **pdf_set_text_matrix()** function sets a matrix which describes a transformation applied on the current text font. The matrix has to be passed as an array with six elements.

Poznámka: This function is not available anymore since pdflib 2.3

pdf_set_text_pos (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Sets text position

```
void pdf_set_text_pos ( int pdf document, double x-coor, double y-coor) \linebreak
```

Funkce **pdf_set_text_pos()** function sets the position of text for the next pdf_show() function call.

Viz také pdf_show(), pdf_show_xy().

pdf_set_text_rendering (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Determines how text is rendered

```
void pdf_set_text_rendering ( int pdf document, int mode) \linebreak
```

Funkce **pdf_set_text_rendering()** function determines how text is rendered. The possible values for *mode* are 0=fill text, 1=stroke text, 2=fill and stroke text, 3=invisible, 4=fill text and add it to clipping path, 5=stroke text and add it to clipping path, 6=fill and stroke text and add it to clipping path, 7=add it to clipping path.

pdf_set_text_rise (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Sets the text rise

```
void pdf_set_text_rise ( int pdf document, double rise) \linebreak
```

Funkce **pdf_set_text_rise()** function sets the text rising to *rise* points.

pdf_set_transition (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Sets transition between pages

```
void pdf_set_transition ( int pdf document, int transition) \linebreak
```

Funkce **pdf_set_transition()** function set the transition between following pages. The value of *transition* can be

- 0 for none,
- 1 for two lines sweeping across the screen reveal the page,
- 2 for multiple lines sweeping across the screen reveal the page,

3 for a box reveals the page,
 4 for a single line sweeping across the screen reveals the page,
 5 for the old page dissolves to reveal the page,
 6 for the dissolve effect moves from one screen edge to another,
 7 for the old page is simply replaced by the new page (default)

Viz také `pdf_set_duration()`.

pdf_set_value (PHP 4)

Sets certain numerical value

void **pdf_set_value** (int pdf document, string name, double value) \linebreak

Funkce **pdf_set_value()** function sets several numerical parameters of pdflib.

Viz také `pdf_get_value()`, `pdf_get_parameter()`, `pdf_set_parameter()`.

pdf_set_word_spacing (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets spacing between words

void **pdf_set_word_spacing** (int pdf document, double space) \linebreak

Funkce **pdf_set_word_spacing()** function sets the spacing between words.

Viz také `pdf_set_char_spacing()`, `pdf_set_leading()`.

pdf_setdash (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets dash pattern

void **pdf_setdash** (int pdf document, double white, double black) \linebreak

Funkce **pdf_setdash()** function sets the dash pattern *white* white points and *black* black points.

If both are 0 a solid line is set.

pdf_setflat (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets flatness

void **pdf_setflat** (int pdf document, double value) \linebreak

Funkce **pdf_setflat()** function sets the flatness to a value between 0 and 100.

pdf_setgray (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets drawing and filling color to gray value

void **pdf_setgray** (int pdf document, double gray value) \linebreak

Funkce **pdf_setgray()** function sets the current drawing and filling color to the given gray value.

Viz také pdf_setrgbcolor_stroke(), pdf_setrgbcolor_fill().

pdf_setgray_fill (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets filling color to gray value

void **pdf_setgray_fill** (int pdf document, double gray value) \linebreak

Funkce **pdf_setgray_fill()** function sets the current gray value to fill a path.

Viz také pdf_setrgbcolor_fill().

pdf_setgray_stroke (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets drawing color to gray value

void **pdf_setgray_stroke** (int pdf document, double gray value) \linebreak

Funkce **pdf_setgray_stroke()** function sets the current drawing color to the given gray value.

Viz také pdf_setrgbcolor_stroke().

pdf_setlinecap (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets linecap parameter

void **pdf_setlinecap** (int pdf document, int value) \linebreak

Funkce **pdf_setlinecap()** function sets the linecap parameter between a value of 0 and 2.

pdf_setlinejoin (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets linejoin parameter

void **pdf_setlinejoin** (int pdf document, long value) \linebreak

Funkce **pdf_setlinejoin()** function sets the linejoin parameter between a value of 0 and 2.

pdf_setlinewidth (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets line width

```
void pdf_setlinewidth ( int pdf document, double width) \linebreak
```

Funkce **pdf_setlinewidth()** function sets the line width to *width*.

pdf_setmiterlimit (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets miter limit

```
void pdf_setmiterlimit ( int pdf document, double value) \linebreak
```

Funkce **pdf_setmiterlimit()** function sets the miter limit to a value greater of equal than 1.

pdf_setrgbcolor (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets drawing and filling color to rgb color value

```
void pdf_setrgbcolor ( int pdf document, double red value, double green value, double blue value) \linebreak
```

Funkce **pdf_setrgbcolor_stroke()** function sets the current drawing and filling color to the given rgb color value.

Viz také **pdf_setrgbcolor_stroke()**, **pdf_setrgbcolor_fill()**.

pdf_setrgbcolor_fill (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets filling color to rgb color value

```
void pdf_setrgbcolor_fill ( int pdf document, double red value, double green value, double blue value) \linebreak
```

Funkce **pdf_setrgbcolor_fill()** function sets the current rgb color value to fill a path.

Viz také **pdf_setrgbcolor_fill()**.

pdf_setrgbcolor_stroke (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets drawing color to rgb color value

```
void pdf_setrgbcolor_stroke ( int pdf document, double red value, double green value, double blue value) \linebreak
```

Funkce **pdf_setrgbcolor_stroke()** function sets the current drawing color to the given rgb color value.

Viz také **pdf_setrgbcolor_stroke()**.

pdf_show (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Umístit text na aktuální pozici

```
void pdf_show ( int pdf document, string text) \linebreak
```

Funkce **pdf_show()** umístí řetězec *text* na současnou pozici s využitím aktuálního fontu.

Viz také **pdf_show_xy()**, **pdf_show_boxed()**, **pdf_set_text_pos()**, **pdf_set_font()**.

pdf_show_boxed (PHP 4 >= 4.0.0)

Vytisknout text v rámečku

```
int pdf_show_boxed ( int pdf document, string text, double x-coor, double y-coor, double width, double height, string mode [, string feature]) \linebreak
```

Funkce **pdf_show_boxed()** vytiskne řetězec *text* v rámečku s levým dolním rohem na (*x-coor*, *y-coor*). Rozměry rámečku jsou *height* x *width*. Argument *mode* determines how the text is type set. Pokud jsou *width* a *height* nula, *mode* může být "left", "right" nebo "center". Pokud jsou *width* nebo *height* různé od nuly, může být také "justify" nebo "fulljustify".

Pokud má argument *feature* hodnotu "blind", text se nezobrazí.

Vrací počet znaků které nebyly zpracovány, protože se nevešly do rámečku.

Viz také **pdf_show()**, **pdf_show_xy()**.

pdf_show_xy (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Vytisknout text na určené pozici

```
void pdf_show_xy ( int pdf document, string text, double x-coor, double y-coor) \linebreak
```

Funkce **pdf_show_xy()** vytiskne řetězec *text* na pozici (*x-coor*, *y-coor*).

Viz také **pdf_show()**, **pdf_show_boxed()**.

pdf_skew (PHP 4 >= 4.0.0)

Skews the coordinate system

```
void pdf_skew ( int pdf document, double alpha, double beta) \linebreak
```

Funkce **pdf_skew()** function skew the coordinate system by *alpha* (x) and *beta* (y) degrees. *alpha* and *beta* may not be 90 or 270 degrees.

pdf_stringwidth (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Returns width of text using current font

double **pdf_stringwidth** (int pdf document, string text) \linebreak

Funkce **pdf_stringwidth()** function returns the width of the string in *text* by using the current font. It requires a font to be set before with **pdf_set_font()**.

Viz také **pdf_set_font()**.

pdf_stroke (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Draws line along path

void **pdf_stroke** (int pdf document) \linebreak

Funkce **pdf_stroke()** function draws a line along current path. The current path is the sum of all line drawing. Without this function the line would not be drawn.

Viz také **pdf_closepath()**, **pdf_closepath_stroke()**.

pdf_translate (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Sets origin of coordinate system

void **pdf_translate** (int pdf document, double x-coor, double y-coor) \linebreak

Funkce **pdf_translate()** function sets the origin of coordinate system to the point (*x-coor*, *y-coor*) relative the current origin. The following example draws a line from (0, 0) to (200, 200) relative to the initial coordinate system. You have to set the current point after **pdf_translate()** and before you start drawing more objects.

Příklad 1. Translation

```
<?php pdf_moveto($pdf, 0, 0);
pdf_lineto($pdf, 100, 100);
pdf_stroke($pdf);
pdf_translate($pdf, 100, 100);
pdf_moveto($pdf, 0, 0);
pdf_lineto($pdf, 100, 100);
pdf_stroke($pdf);
?>
```

LXXVI. Funkce pro práci s Verisign Payflow Pro

Tato extenze umožňuje zpracovávat kreditní karty a provádět jiné finanční transakce pomocí Verisign Payment Services (dříve Signio, <http://www.verisign.com/payment/>).

Tyto funkce jsou dostupné pouze pokud bylo PHP zkompileováno s `--with-pfpro[=DIR]`. Budete potřebovat SDK pro vaši platformu, který se dá po registraci stáhnout z manažerského rozhraní (https://testmanager.signio.com/Downloads/Downloads_secure.htm).

Pokud jste si stáhli správný SDK, zkopírujte následující soubory z `lib` adresáře této distribuce: `pfpro.h` do `/usr/local/include` a `libpfpro.so` do `/usr/local/lib`.

Při využívání těchto funkcí můžete vynechat volání `pfpro_init()` a `pfpro_cleanup()`, tato extenze to udělá podle potřeby automaticky. Tyto funkce jsou ale přesto dostupné pro případ, že byste potřebovali zpracovávat velké množství transakcí a vyžadovali naprostou kontrolu nad touto knihovnou. Mezi `pfpro_init()` a `pfpro_cleanup()` můžete provést libovolné množství transakcí.

Tyto funkce byly přidány v PHP 4.0.2.

Poznámka: Tyto funkce poskytují pouze spojení s Verisign Payment Services. Kompletní detaily vyžadovaných parametrů viz Payflow Pro Developer's Guide.

pfpro_cleanup (PHP 4 >= 4.0.2)

Zavřít Payflow Pro knihovnu

void **pfpro_cleanup** (void) \linebreak

pfpro_cleanup() se používá k čistému vypnutí Payflow Pro knihovny. Měla by se volat po provedení všech transakcí a před ukončením skriptu. Tuto funkci nicméně volat nemusíte, tato extenze automaticky zavolá **pfpro_cleanup()** při ukončení skriptu.

Viz také pfpro_init().

pfpro_init (PHP 4 >= 4.0.2)

Inicializovat Payflow Pro knihovnu

void **pfpro_init** (void) \linebreak

pfpro_init() se používá k inicializaci Payflow Pro knihovny. Tuto funkci volat nemusíte, tato extenze automaticky zavolá **pfpro_init()** před první transakcí.

Viz také pfpro_cleanup().

pfpro_process (PHP 4 >= 4.0.2)

Zpracovat transakci s Payflow Pro

array **pfpro_process** (array parameters [, string address [, int port [, int timeout [, string proxy address [, int proxy port [, string proxy login [, string proxy password]]]]]]) \linebreak

Vrací asociativní pole obsahující odpověď.

pfpro_process() zpracuje transakci s Payflow Pro. První argument je asociativní pole obsahující klíče a hodnoty, které se zakódují a odešlou zpracovateli.

Druhý argument je volitelný a určuje server, ke kterému se připojit. Default je "test.signio.com", takže pokud chcete zpracovávat skutečné transakce, budete chtít tento argument nastavit na "connect.signio.com".

Třetí argument určuje port, ke kterému se připojit. Default je 443, standardní SSL port.

Čtvrtý argument určuje v sekundách, jaký časový limit se má použít. Default je 30 sekund. Tento časový limit vstupuje v platnost v okamžiku spojení se zpracovatelem, a tak by váš skript mohl potenciálně běžet velmi dlouhou dobu, pokud by nastaly problémy s DNS nebo sítí.

Pátý argument určuje hostname vaší případné SSL proxy. Šestý argument specifikuje port.

Sedmý a osmý argument určují přihlašovací jméno a heslo na tuto proxy.

Tato funkce vrací asociativní pole klíčů a hodnot odpovědi.

Poznámka: Kompletní detaily vyžadovaných parametrů viz Payflow Pro Developer's Guide.

Příklad 1. Ukázka Payflow Pro

```

<?php

pfpro_init();

$transaction = array(USER => 'login',
    PWD => 'heslo',
    TRXTYPE => 'S',
    TENDER => 'C',
    AMT => 1.50,
    ACCT => '4111111111111111',
    EXPDATE => '0904'
);

$response = pfpro_process($transaction);

if (!$response) {
    die("Nepodařilo se spojit s Verisign.\n");
}

echo "Response kód Verisignu byl " . $response[RESULT];
echo ", což znamená: " . $response[RESPMSG] . "\n";

echo "\nPožadavek na transakci: ";
print_r($transaction);

echo "\nOdpověď: ";
print_r($response);

pfpro_cleanup();

?>

```

pfpro_process_raw (PHP 4 >= 4.0.2)

Zpracovat raw transakci s Payflow Pro

string **pfpro_process_raw** (string parameters [, string address [, int port [, int timeout [, string proxy address [, int proxy port [, string proxy logon [, string proxy password]]]]]]]) \linebreak

Vrací řetězec obsahující odpověď.

pfpro_process_raw() zpracuje raw řetězec transakce s Payflow Pro. Opravdu byste ale měli používat **pfpro_process()**, protože pravidla kódování těchto transakcí jsou nestandardní.

První argument je v tomto případě řetězec obsahující raw požadavek na transakci. Všechny ostatní argumenty jsou stejné jako u **pfpro_process()**. Návrátová hodnota je řetězec obsahující raw odpověď.

Poznámka: Kompletní detaily vyžadovaných parametrů a pravidel kódování viz Payflow Pro Developer's Guide. Dobře vám radíme, používejte radši **pfpro_process()**.

Příklad 1. Ukázka Payflow Pro raw

```

<?php

pfpro_init();

$response = pfpro_process("USER=mylogin&PWD[5]=m&ndy&TRXTYPE=S&TENDER=C&AMT=1.50&ACCT=41

if (!$response) {
    die("Nepodařilo se spojit s Verisign.\n");
}

echo "Raw odpověď Verisignu byla ".$response;

pfpro_cleanup();

?>

```

pfpro_version (PHP 4 >= 4.0.2)

Vrátit verzi Payflow Pro knihovny

string **pfpro_version** (void) \linebreak

pfpro_version() vrací řetězec obsahující verzi Payflow Pro knihovny. V čase psaní tohoto manuálu to bylo L211.

LXXVII. PHP volby & informace

assert (PHP 4 >= 4.0.0)

Ověřit, jestli je výrok neplatný

```
int assert ( string|bool assertion) \linebreak
```

assert() ověří předanou *assertion* a provede příslušnou akci, pokud je výsledek `FALSE`.

Pokud je předaná *assertion* řetězec, vyhodnotí se funkcí **assert()** jako PHP kód. Výhody řetězcové *assertion* jsou menší režie, když je kontrola výroků vypnutá, a zprávy obsahující *assertion* výraz, když výrok selže.

Kontrola výroků by se měla používat jen pro odlaďování skriptů. Můžete je použít na kontrolu podmínek, které by měly být vždycky `TRUE`, a které jinak indikují nějaké chyby v programování, nebo na kontrolu existence určitých vlastností, jako jsou funkce obsažené v extenzích, nebo určité systémové limity a vlastnosti.

Výroky by se neměly používat pro běžné operace jako kontrola vstupních parametrů. Jako základní pravidlo platí, že váš kód by měl fungovat správně, pokud není kontrola výroků aktivována.

Chování funkce **assert()** lze konfigurovat skrze `assert_options()` nebo `.ini` direktivy popsané na manuálové stránce této funkce.

assert_options (PHP 4 >= 4.0.0)

Nastavit/získat různé příznaky výroků

```
mixed assert_options ( int what [, mixed value]) \linebreak
```

S použitím funkce **assert_options()** můžete nastavit různé řídicí volby funkce `assert()`, nebo jen získat jejich současné nastavení.

Tabulka 1. Volby výroků

volba	ini parametr	výchozí hodnota	popis
<code>ASSERT_ACTIVE</code>	<code>assert.active</code>	1	zapne <code>assert()</code> vyhodnocování
<code>ASSERT_WARNING</code>	<code>assert.warning</code>	1	vytvoří PHP varování pro každý selhavší výrok
<code>ASSERT_BAIL</code>	<code>assert.bail</code>	0	ukončí provádění skriptu, pokud výrok selže
<code>ASSERT_QUIET_EVAL</code>	<code>assert.quiet_eval</code>	0	vypne <code>error_reporting</code> během vyhodnocování výrazů výroků
<code>ASSERT_CALLBACK</code>	<code>assert_callback</code>	(<code>NULL</code>)	uživatelská funkce, která se zavolá pro každý selhavší výrok

assert_options() vrací původní nastavení volby, nebo `FALSE` při chybě.

dl (PHP 3, PHP 4 >= 4.0.0)

Načíst extenzi PHP za běhu

int **dl** (string library) \linebreak

Načte extenzi PHP definovanou v *library*. Viz také konfigurační direktivu *extension_dir*.

extension_loaded (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

zjistit, jestli je extenze načtená

bool **extension_loaded** (string name) \linebreak

Vrací TRUE, pokud je extenze identifikovaná argumentem *name* načtena. Názvy různých extenzí můžete vidět, pokud použijete `phpinfo()`.

Viz také `phpinfo()`.

Poznámka: Tato funkce byla přidána v PHP 3.0.10.

get_cfg_var (PHP 3, PHP 4 >= 4.0.0)

Získat hodnotu volby z konfigurace PHP

string **get_cfg_var** (string varname) \linebreak

Vrátí současnou hodnotu konfigurační proměnné PHP určené argumentem *varname*, nebo FALSE pokud dojde k chybě.

Nevrací konfigurační hodnoty nastavené při kompilaci PHP a nechte konfigurační soubor Apache (použití `php3_configuration_option` direktiv).

Pokud chcete zjistit, jestli daný systém používá konfigurační soubor, zkuste získat hodnotu konfigurační volby `cfg_file_path`. Pokud je tato dostupná, používá se konfigurační soubor.

get_current_user (PHP 3, PHP 4 >= 4.0.0)

Získat jméno vlastníka současného PHP skriptu

string **get_current_user** (void) \linebreak

Vrátí jméno vlastníka současného PHP skriptu.

Viz také `getmyuid()`, `getmypid()`, `getmyinode()`, a `getlastmod()`.

get_extension_funcs (PHP 4 >= 4.0.0)

Vrátit pole jmen funkcí určitého modulu

array **get_extension_funcs** (string module_name) \linebreak

Tato funkce vrací jména všech funkcí definovaných v modulu určeném argumentem *module_name*.

Například následující řádky

```
print_r (get_extension_funcs ("xml"));
print_r (get_extension_funcs ("gd"));
```

vytisknou seznam všech funkcí v modulech xml a gd.

Viz také: get_loaded_extensions()

get_included_files (PHP 4 >= 4.0.0)

Vrátit pole jmen všech souborů, které byly ve skriptu načteny pomocí include_once()

array **get_included_files** (void) \linebreak

Tato funkce vrátí asociativní pole jmen všech souborů, které byly načteny do skriptu pomocí include_once(). Indexy tohoto pole jsou názvy souborů použitých v include_once() bez přípony ".php".

Poznámka: Od verze PHP 4.0.1pl2 tato funkce předpokládá, že soubory v include_once končí příponou ".php", jiné přípony nefungují.

Viz také: require_once(), include_once(), get_required_files()

get_loaded_extensions (PHP 4 >= 4.0.0)

Vrátit pole se jmény všech zkompileovaných a načtených modulů (extenzí)

array **get_loaded_extensions** (void) \linebreak

Tato funkce vrací jména všech modulů (extenzí) zkompileovaných a načtených do PHP interpretu.

Například následující řádek

```
print_r (get_loaded_extensions());
```

vypíše seznam podobný tomuto:

```

Array
(
    [0] => xml
    [1] => wddx
    [2] => standard
    [3] => session
    [4] => posix
    [5] => pgsql
    [6] => pcre
    [7] => gd
    [8] => ftp
    [9] => db
    [10] => Calendar
    [11] => bcmath
)

```

Viz také: `get_extension_funcs()`.

get_magic_quotes_gpc (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Získat současné aktivní nastavení `magic_quotes_gpc`

`long get_magic_quotes_gpc (void) \linebreak`

Vrátí současné aktivní nastavení `magic_quotes_gpc`. (0 pro vypnuto, 1 pro zapnuto).

Viz také `get_magic_quotes_runtime()`, `set_magic_quotes_runtime()`.

get_magic_quotes_runtime (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Vrátit současné aktivní nastavení `magic_quotes_runtime`

`long get_magic_quotes_runtime (void) \linebreak`

Vrátí současné aktivní nastavení `magic_quotes_runtime`. (0 pro vypnuto, 1 pro zapnuto).

Viz také `get_magic_quotes_gpc()`, `set_magic_quotes_runtime()`.

get_required_files (PHP 4 >= 4.0.0)

Vrátit pole jmen všech souborů, které byly v určitém skriptu načteny pomocí `require_once()`

`array get_required_files (void) \linebreak`

Tato funkce vrátí asociativní pole jmen všech souborů, které byly načteny do probíhajícího skriptu pomocí `require_once()`. Indexy tohoto pole jsou názvy souborů použitých v `require_once()` bez přípony `".php"`.

Následující příklad

Příklad 1. Tisk require()ovaných a include()ovaných souborů

```
<?php

require_once ("local.php");
require_once ("../inc/global.php");

for ($i=1; $i<5; $i++)
    include "util".$i.".php";

    echo "Required_once files\n";
    print_r (get_required_files());

    echo "Included_once files\n";
    print_r (get_included_files());
?>
```

vygeneruje následující výstup:

```
Required_once files
Array
(
    [local] => local.php
    [../inc/global] => /full/path/to/inc/global.php
)

Included_once files
Array
(
    [util1] => util1.php
    [util2] => util2.php
    [util3] => util3.php
    [util4] => util4.php
)
```

Poznámka: Od verze PHP 4.0.1pl2 tato funkce předpokládá, že soubory v `required_once` končí příponou ".php", jiné přípony nefungují.

Viz také: `require_once()`, `include_once()`, `get_included_files()`

getenv (PHP 3, PHP 4 >= 4.0.0)

Získat hodnotu systémové proměnné

string **getenv** (string varname) \linebreak

Vrátí hodnotu systémové proměnné *varname*, nebo FALSE při chybě.

```
$ip = getenv ("REMOTE_ADDR"); // získá IP adresu uživatele
```

Seznam všech systémových proměnných si můžete prohlédnout použitím `phpinfo()`. Význam mnoha z nich najdete v CGI specifikaci (<http://hoohoo.ncsa.uiuc.edu/cgi/>), zvláště na stránce o systémových proměnných (<http://hoohoo.ncsa.uiuc.edu/cgi/env.html>).

Poznámka: Tato funkce nefunguje v ISAPI módu.

getlastmod (PHP 3, PHP 4 >= 4.0.0)

Získat čas poslení modifikace skriptu

int **getlastmod** (void) \linebreak

Vrátí čas poslení modifikace současné stránky. Návrátová hodnota je Unixový timestamp, vhodný jako vstup pro `date()`. Při chybě vrací FALSE.

Příklad 1. getlastmod() příklad

```
// outputs e.g. 'Last modified: March 04 1998 20:43:59.'
echo "Last modified: ".date ("F d Y H:i:s.", getlastmod());
```

See also `date()`, `getmyuid()`, `get_current_user()`, `getmyinode()`, and `getmypid()`.

getmyinode (PHP 3, PHP 4 >= 4.0.0)

Získat inode současného skriptu

int **getmyinode** (void) \linebreak

Vrátí inode současného skriptu, nebo FALSE při chybě.

Viz také `getmyuid()`, `get_current_user()`, `getmypid()`, and `getlastmod()`.

Poznámka: Tato funkce není podporována na Windows systémech.

getmypid (PHP 3, PHP 4 >= 4.0.0)

Získat process ID PHP

```
int getmypid ( void) \linebreak
```

Vrátí process ID současného PHP procesu, nebo FALSE při chybě.

Varování

Process ID nejsou unikátní, a jsou tudíž slabým zdrojem entropie.
Nedoporučujeme používat PIDy v prostředích závislých na bezpečnosti.

Viz také `getmyuid()`, `get_current_user()`, `getmyinode()`, a `getlastmod()`.

getmyuid (PHP 3, PHP 4 >= 4.0.0)

Získat UID majitele PHP skriptu

```
int getmyuid ( void) \linebreak
```

Vrátí user ID současného skriptu, nebo FALSE při chybě.

Viz také `getmypid()`, `get_current_user()`, `getmyinode()`, a `getlastmod()`.

getrusage (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Získat informace o současném využití zdrojů

```
array getrusage ( [int who]) \linebreak
```

Toto je rozhraní ke to `getrusage(2)`. Vrátí asociativní pole obsahující všechna data vrácená systémovým voláním. Pokud je `who` 1, `getrusage` se zavolá s `RUSAGE_CHILDREN`.

Všechny položky jsou přístupné skrze svá dokumentovaná jména.

Příklad 1. Getrusage příklad

```
$dat = getrusage();
echo $dat["ru_nswap"];           # počet swapů
echo $dat["ru_majflt"];          # počet page faultů
echo $dat["ru_utime.tv_sec"];    # využitý uživatelský čas (sekundy)
echo $dat["ru_utime.tv_usec"];  # využitý uživatelský čas (mikrosekundy)
```

Další detaily viz man stránka `getrusage(2)` na vašem systému.

ini_alter (PHP 4 >= 4.0.0)

Změnit hodnotu konfigurační volby

string **ini_alter** (string varname, string newvalue) \linebreak

Změní hodnotu konfigurační volby, vrátí `FALSE` při selhání, a předchozí hodnotu konfigurační volby při úspěchu.

Poznámka: Toto je alias k `ini_set()`

Viz také `ini_get()`, `ini_restore()`, `ini_set()`

ini_get (PHP 4 >= 4.0.0)

Získat hodnotu konfigurační volby

string **ini_get** (string varname) \linebreak

Vrátí hodnotu konfigurační volby při úspěchu, `FALSE` při selhání.

Viz také `ini_alter()`, `ini_restore()`, `ini_set()`

ini_restore (PHP 4 >= 4.0.0)

Obnovit původní hodnotu konfigurační volby

string **ini_restore** (string varname) \linebreak

Obnoví původní hodnotu konfigurační volby.

Viz také `ini_alter()`, `ini_get()`, `ini_set()`

ini_set (PHP 4 >= 4.0.0)

Změnit hodnotu konfigurační volby

string **ini_set** (string varname, string newvalue) \linebreak

Změní hodnotu konfigurační volby, vrátí `FALSE` při selhání, a předchozí hodnotu konfigurační volby při úspěchu.

Viz také `ini_alter()`, `ini_get()`, `ini_restore()`

php_logo_guid (PHP 4 >= 4.0.0)

Get the logo guid

string **php_logo_guid** (void) \linebreak

Poznámka: Tato funkcionalita byla přidána v PHP 4 Beta 4.

Viz také `phpinfo()`, `phpversion()`, `phpcredits()`

php_sapi_name (PHP 4)

Vrátit typ rozhraní mezi web serverem a PHP Returns the type of interface between web server and PHP

string **php_sapi_name** (void) \linebreak

php_sapi_name() vrátí řetězec popisující malými písmeny typ rozhraní mezi web serverem a PHP (Server API, SAPI). U CGI PHP je tento řetězec "cgi", u mod_php pro Apache je tento řetězec "apache" a tak dále.

Příklad 1. php_sapi_name() Example

```
$sapi_type = php_sapi_name();
if ($sapi_type == "cgi")
    print "Používáte CGI PHP\n";
else
    print "Nepoužíváte CGI PHP\n";
```

php_uname (PHP 4 >= 4.0.2)

Vrátit informaci o operačním systému, na kterém bylo PHP zkompileováno

string **php_uname** (void) \linebreak

php_uname() vrátí řetězec s popisem operačního systému, na kterém bylo PHP zkompileováno.

Příklad 1. php_uname() Example

```
if (substr(php_uname(), 0, 7) == "Windows") {
    die("Pardon, tento skript na Windows nefunguje.\n");
}
```

phpcredits (PHP 4 >= 4.0.0)

Vytisknout credits pro PHP

`void phpcredits (int flag) \linebreak`

Tato funkce vytiskne credits vč. seznamu vývojářů PHP, modulů, atd. Generuje příslušný HTML kód, kterým se tyto informace vkládají do stránky. Je třeba předat argument indikující co se vytiskne (předdefinovaná konstanta flag, viz níže). Například k vytištění všeobecných credits můžete někde ve svém kódu použít:

```
...
phpcredits(CREDITS_GENERAL);
...
```

A pokud chcete vytisknout užší kruh vývojářů a dokumentační skupinu na samostatné stránce, použijte:

```
<?php
phpcredits(CREDITS_GROUP + CREDITS_DOCS + CREDITS_FULLPAGE);
?>
```

A pokud chcete vložit všechny credits do vlastní stránky, pomůže vám následující kód:

```
<html>
<head>
  <title>Má stránka s credits</title>
</head>
<body>
  <?php
  // váš vlastní kód
  phpcredits(CREDITS_ALL + CREDITS_FULLPAGE);
  // další kód
  ?>
</body>
</html>
```

Tabulka 1. Předdefinované phpcredits() příznaky

název	popis
-------	-------

název	popis
CREDITS_ALL	Všechny credits, ekvivalentní k: CREDITS_DOCS + CREDITS_GENERAL + CREDITS_GROUP + CREDITS_MODULES + CREDITS_FULLPAGE. Vygeneruje kompletní samostatnou HTML stránku s příslušnými tagy.
CREDITS_DOCS	Credits dokumentačního týmu
CREDITS_FULLPAGE	Obvykle se používá v kombinaci s jinými příznaky. Indikuje, že se má vytisknout kompletní samostatná HTML stránka, včetně informací indikovaných jinými příznaky.
CREDITS_GENERAL	Všeobecné credits: Design a koncept jazyka, autoři PHP 4.0 a SAPI modul.
CREDITS_GROUP	Seznam užšího kruhu vývojářů
CREDITS_MODULES	Seznam rozšiřujících modulů (extenzí) PHP a jejich autorů
CREDITS_SAPI	Seznam server API modulů PHP a jejich autorů

Viz také `phpinfo()`, `phpversion()`, `php_logo_guid()`.

phpinfo (PHP 3, PHP 4 >= 4.0.0)

Vytisknout spoustu informací o PHP

`int phpinfo ([int what]) \linebreak`

Vytiskne velké množství informací o současném stavu PHP. To zahrnuje informace o kompilačních volbách a extenzích, verzi PHP, informaci o serveru a systému (pokud je PHP zkompileováno jako modul), PHP prostředí, verzi OS, cesty, hlavní a lokální hodnoty konfiguračních voleb, HTTP hlavičky, a PHP licenci.

Výstup se dá upravit předáním jednou nebo více z následujících hodnot uložených ve volitelném argumentu *what*.

- INFO_GENERAL
- INFO_CREDITS
- INFO_CONFIGURATION
- INFO_MODULES
- INFO_ENVIRONMENT
- INFO_VARIABLES
- INFO_LICENSE
- INFO_ALL

Viz také `phpversion()`, `phpcredits()`, `php_logo_guid()`

phpversion (PHP 3, PHP 4 >= 4.0.0)

Získat současnou verzi PHP

string **phpversion** (void) \linebreak

Vrátí řetězec obsahující verzi právě běžícího PHP parseru.

Příklad 1. **phpversion()** example

```
// prints e.g. 'Současná verze PHP: 3.0rel-dev'
echo "Současná verze PHP: ".phpversion();
```

Viz také `phpinfo()`, `phpcredits()`, `php_logo_guid()`

putenv (PHP 3, PHP 4 >= 4.0.0)

Nastavit hodnotu systémové proměnné

void **putenv** (string setting) \linebreak

Přidá *setting* do prostředí serveru.

Příklad 1. Nastavení systémové proměnné

```
putenv ("UNIQID=$uniqid");
```

set_magic_quotes_runtime (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Nastavit současnou aktivní hodnotu `magic_quotes_runtime`

long **set_magic_quotes_runtime** (int new_setting) \linebreak

Nastaví současnou aktivní konfigurační volby `magic_quotes_runtime`. (0 vypnuto, 1 zapnuto)

Viz také `get_magic_quotes_gpc()`, `get_magic_quotes_runtime()`.

set_time_limit (PHP 3, PHP 4 >= 4.0.0)

Omezit maximální dobu průběhu skriptu

void **set_time_limit** (int seconds) \linebreak

Určí počet sekund po které může skript běžet. Pokud je dosaženo tohoto času, skript vrátí fatální chybu. Standardní limit je 30 sekund, nebo, pokud existuje, hodnota direktivy `max_execution_time` definovaná v konfiguračním souboru. Pokud je *seconds* nula, neexistuje žádný časový limit.

set_time_limit() při svém zavolání restartuje čítač času od nuly. Jinými slovy, pokud je limit standardních 30 sekund a po 25 sekundách provádění skriptu dojde k volání `set_time_limit(20)`, tento skript poběží celkem 45 sekund předtím, než skončí na časovém limitu.

Všimněte si, že **set_time_limit()** nemá žádný účinek, když PHP běží v bezpečném módu. Obejít to lze jedine vypnutím bezpečného módu nebo změnou časového limitu v konfiguračním souboru.

zend_logo_guid (PHP 4 >= 4.0.0)

Získat zend guid

string **zend_logo_guid** (void) \linebreak

Poznámka: Tato funkcionálita byla přidána v PHP 4 Beta 4.

LXXVIII. POSIX functions

This module contains an interface to those functions defined in the IEEE 1003.1 (POSIX.1) standards document which are not accessible through other means. POSIX.1 for example defined the `open()`, `read()`, `write()` and `close()` functions, too, which traditionally have been part of PHP 3 for a long time. Some more system specific functions have not been available before, though, and this module tries to remedy this by providing easy access to these functions.

posix_ctermid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Get path name of controlling terminal

string **posix_ctermid** (void) \linebreak

Needs to be written.

posix_getcwd (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Pathname of current directory

string **posix_getcwd** (void) \linebreak

Needs to be written ASAP.

posix_getegid (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return the effective group ID of the current process

int **posix_getegid** (void) \linebreak

Return the numeric effective group ID of the current process. See also `posix_getgrgid()` for information on how to convert this into a useable group name.

posix_geteuid (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return the effective user ID of the current process

int **posix_geteuid** (void) \linebreak

Return the numeric effective user ID of the current process. See also `posix_getpwuid()` for information on how to convert this into a useable username.

posix_getgid (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return the real group ID of the current process

int **posix_getgid** (void) \linebreak

Return the numeric real group ID of the current process. See also `posix_getgrgid()` for information on how to convert this into a useable group name.

posix_getgrgid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Return info about a group by group id

array **posix_getgrgid** (int gid) \linebreak

Needs to be written.

posix_getgrnam (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Return info about a group by name

array **posix_getgrnam** (string name) \linebreak

Needs to be written.

posix_getgroups (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return the group set of the current process

array **posix_getgroups** (void) \linebreak

Returns an array of integers containing the numeric group ids of the group set of the current process. See also `posix_getgrgid()` for information on how to convert this into useable group names.

posix_getlogin (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Return login name

string **posix_getlogin** (void) \linebreak

Returns the login name of the user owning the current process. See `posix_getpwnam()` for information how to get more information about this user.

posix_getpgid (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Get process group id for job control

int **posix_getpgid** (int pid) \linebreak

Returns the process group identifier of the process *pid*.

This is not a POSIX function, but is common on BSD and System V systems. If your system does not support this function at system level, this PHP function will always return `FALSE`.

posix_getpgrp (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return the current process group identifier

```
int posix_getpgrp ( void) \linebreak
```

Return the process group identifier of the current process. See POSIX.1 and the getpgrp(2) manual page on your POSIX system for more information on process groups.

posix_getpid (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return the current process identifier

```
int posix_getpid ( void) \linebreak
```

Return the process identifier of the current process.

posix_getppid (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return the parent process identifier

```
int posix_getppid ( void) \linebreak
```

Return the process identifier of the parent process of the current process.

posix_getpwnam (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Return info about a user by username

```
array posix_getpwnam ( string username) \linebreak
```

Returns an associative array containing information about a user referenced by an alphanumeric username, passed in the *username* parameter.

The array elements returned are:

Tabulka 1. The user information array

Element	Description
name	The name element contains the username of the user. This is a short, usually less than 16 character "handle" of the user, not her real, full name. This should be the same as the <i>username</i> parameter used when calling the function, and hence redundant.

Element	Description
passwd	The passwd element contains the user's password in an encrypted format. Often, for example on a system employing "shadow" passwords, an asterisk is returned instead.
uid	User ID of the user in numeric form.
gid	The group ID of the user. Use the function <code>posix_getgrgid()</code> to resolve the group name and a list of its members.
gecos	GECOS is an obsolete term that refers to the finger information field on a Honeywell batch processing system. The field, however, lives on, and its contents have been formalized by POSIX. The field contains a comma separated list containing the user's full name, office phone, office number, and home phone number. On most systems, only the user's full name is available.
dir	This element contains the absolute path to the home directory of the user.
shell	The shell element contains the absolute path to the executable of the user's default shell.

posix_getpwuid (PHP 3 >= 3.0.13, PHP 4 >= 4.0.0)

Return info about a user by user id

array **posix_getpwuid** (int uid) \linebreak

Returns an associative array containing information about a user referenced by a numeric user ID, passed in the *uid* parameter.

The array elements returned are:

Tabulka 1. The user information array

Element	Description
name	The name element contains the username of the user. This is a short, usually less than 16 character "handle" of the user, not her real, full name.
passwd	The passwd element contains the user's password in an encrypted format. Often, for example on a system employing "shadow" passwords, an asterisk is returned instead.
uid	User ID, should be the same as the <i>uid</i> parameter used when calling the function, and hence redundant.

Element	Description
gid	The group ID of the user. Use the function <code>posix_getgrgid()</code> to resolve the group name and a list of its members.
gecos	GECOS is an obsolete term that refers to the finger information field on a Honeywell batch processing system. The field, however, lives on, and its contents have been formalized by POSIX. The field contains a comma separated list containing the user's full name, office phone, office number, and home phone number. On most systems, only the user's full name is available.
dir	This element contains the absolute path to the home directory of the user.
shell	The shell element contains the absolute path to the executable of the user's default shell.

posix_getrlimit (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return info about system resource limits

array **posix_getrlimit** (void) \linebreak

Needs to be written ASAP.

posix_getsid (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Get the current sid of the process

int **posix_getsid** (int pid) \linebreak

Return the sid of the process *pid*. If *pid* is 0, the sid of the current process is returned.

This is not a POSIX function, but is common on System V systems. If your system does not support this function at system level, this PHP function will always return `FALSE`.

posix_getuid (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Return the real user ID of the current process

int **posix_getuid** (void) \linebreak

Return the numeric real user ID of the current process. See also `posix_getpwuid()` for information on how to convert this into a useable username.

posix_isatty (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Determine if a file descriptor is an interactive terminal

```
bool posix_isatty ( int fd) \linebreak
```

Needs to be written.

posix_kill (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Send a signal to a process

```
bool posix_kill ( int pid, int sig) \linebreak
```

Send the signal *sig* to the process with the process identifier *pid*. Returns `FALSE`, if unable to send the signal, `TRUE` otherwise.

See also the `kill(2)` manual page of your POSIX system, which contains additional information about negative process identifiers, the special pid 0, the special pid -1, and the signal number 0.

posix_mkfifo (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Create a fifo special file (a named pipe)

```
bool posix_mkfifo ( string pathname, int mode) \linebreak
```

posix_mkfifo() creates a special `FIFO` file which exists in the file system and acts as a bidirectional communication endpoint for processes.

The second parameter *mode* has to be given in octal notation (e.g. 0644). The permission of the newly created `FIFO` also depends on the setting of the current `umask()`. The permissions of the created file are `(mode & ~umask)`.

Poznámka: Pokud je zapnut bezpečný režim (safe-mode), PHP kontroluje, zda adresář, ve kterém pracujete, má stejné UID jako spuštěný skript.

posix_setegid (PHP 4 >= 4.0.2)

Set the effective GID of the current process

```
bool posix_setegid ( int gid) \linebreak
```

Set the effective group ID of the current process. This is a privileged function and you need appropriate privileges (usually root) on your system to be able to perform this function.

Returns `TRUE` on success, `FALSE` otherwise.

posix_seteuid (PHP 4 >= 4.0.2)

Set the effective UID of the current process

bool **posix_seteuid** (int uid) \linebreak

Set the real user ID of the current process. This is a privileged function and you need appropriate privileges (usually root) on your system to be able to perform this function.

Returns `TRUE` on success, `FALSE` otherwise. See also `posix_setgid()`.

posix_setgid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Set the GID of the current process

bool **posix_setgid** (int gid) \linebreak

Set the real group ID of the current process. This is a privileged function and you need appropriate privileges (usually root) on your system to be able to perform this function. The appropriate order of function calls is **posix_setgid()** first, `posix_setuid()` last.

Returns `TRUE` on success, `FALSE` otherwise.

posix_setpgid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

set process group id for job control

int **posix_setpgid** (int pid, int pgid) \linebreak

Let the process *pid* join the process group *pgid*. See POSIX.1 and the `setsid(2)` manual page on your POSIX system for more informations on process groups and job control. Returns `TRUE` on success, `FALSE` otherwise.

posix_setsid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Make the current process a session leader

int **posix_setsid** (void) \linebreak

Make the current process a session leader. See POSIX.1 and the `setsid(2)` manual page on your POSIX system for more informations on process groups and job control. Returns the session id.

posix_setuid (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Set the UID of the current process

bool **posix_setuid** (int uid) \linebreak

Set the real user ID of the current process. This is a privileged function and you need appropriate privileges (usually root) on your system to be able to perform this function.

Returns `TRUE` on success, `FALSE` otherwise. See also `posix_setgid()`.

posix_times (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Get process times

array **posix_times** (void) \linebreak

Returns a hash of strings with information about the current process CPU usage. The indices of the hash are

- ticks - the number of clock ticks that have elapsed since reboot.
- utime - user time used by the current process.
- stime - system time used by the current process.
- cutime - user time used by current process and children.
- cstime - system time used by current process and children.

posix_ttyname (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Determine terminal device name

string **posix_ttyname** (int fd) \linebreak

Needs to be written.

posix_uname (PHP 3>= 3.0.10, PHP 4 >= 4.0.0)

Get system name

array **posix_uname** (void) \linebreak

Returns a hash of strings with information about the system. The indices of the hash are

- sysname - operating system name (e.g. Linux)
- nodename - system name (e.g. valiant)
- release - operating system release (e.g. 2.2.10)
- version - operating system version (e.g. #4 Tue Jul 20 17:01:36 MEST 1999)
- machine - system architecture (e.g. i586)
- domainname - DNS domainname (e.g. php.net)

domainname is a GNU extension and not part of POSIX.1, so this field is only available on GNU systems or when using the GNU libc.

Posix requires that you must not make any assumptions about the format of the values, e.g. you cannot rely on three digit version numbers or anything else returned by this function.

LXXIX. PostgreSQL functions

Postgres, developed originally in the UC Berkeley Computer Science Department, pioneered many of the object-relational concepts now becoming available in some commercial databases. It provides SQL92/SQL99 language support, transaction integrity and type extensibility. PostgreSQL is an open source descendant of this original Berkeley code.

PostgreSQL database is Open Source product and available without cost. To use PostgreSQL support, you need PostgreSQL 6.5 or later. PostgreSQL 7.0 or later to enable all PostgreSQL module feature. PostgreSQL supports many character encoding including multibyte character encoding. The current version and more information about PostgreSQL is available at <http://www.postgresql.org/>.

In order to enable PostgreSQL support, `--with-pgsql [=DIR]` is required when you compile PHP. If shared object module is available, PostgreSQL module may be loaded using extension directive in `php.ini` or `dl()` function. Supported ini directives are described in `php.ini-dist` which comes

with source distribution.

Varování

Using the PostgreSQL module with PHP 4.0.6 is not recommended due to a bug in the notice message handling code. Use 4.1.0 or later.

Varování

PostgreSQL function names will be changed in 4.2.0 release to confirm to current coding standards. Most of new names will have additional underscores, e.g. `pg_lo_open()`. Some functions are renamed to different name for consistency. e.g. `pg_exec()` to `pg_query()`. Older names can be used in 4.2.0 and a few releases from 4.2.0, but they may be deleted in the future.

Tabulka 1. Function names changed

Old name	New name
<code>pg_exec()</code>	<code>pg_query()</code>
<code>pg_getlastoid()</code>	<code>pg_last_oid()</code>
<code>pg_cmdtuples()</code>	<code>pg_affected_rows()</code>
<code>pg_numrows()</code>	<code>pg_num_rows()</code>
<code>pg_numfields()</code>	<code>pg_num_fields()</code>
<code>pg_fieldname()</code>	<code>pg_field_name()</code>
<code>pg_fieldsize()</code>	<code>pg_field_size()</code>
<code>pg_fieldnum()</code>	<code>pg_field_num()</code>
<code>pg_fieldprtlen()</code>	<code>pg_fieldprtlen()</code>
<code>pg_fieldisnull()</code>	<code>pg_field_is_null()</code>
<code>pg_freeresult()</code>	<code>pg_free_result()</code>
<code>pg_result()</code>	<code>pg_fetch_result()</code>
<code>pg_loreadall()</code>	<code>pg_lo_read_all()</code>
<code>pg_locreate()</code>	<code>pg_lo_create()</code>
<code>pg_lounlink()</code>	<code>pg_lo_unlink()</code>
<code>pg_loopen()</code>	<code>pg_lo_unlink()</code>
<code>pg_loclose()</code>	<code>pg_lo_close()</code>
<code>pg_loread()</code>	<code>pg_lo_read()</code>
<code>pg_lowrite()</code>	<code>pg_lo_write()</code>
<code>pg_loimport()</code>	<code>pg_lo_import()</code>
<code>pg_loexport()</code>	<code>pg_lo_export()</code>

The old `pg_connect()/pg_pconnect()` syntax will be deprecated to support asynchronous connections in the future. Please use a connection string for `pg_connect()` and `pg_pconnect()`.

Not all functions are supported by all builds. It depends on your libpq (The PostgreSQL C Client interface) version and how libpq is compiled. If there is missing function, libpq does not support the

feature required for the function.

It is also important that you use newer libpq than PostgreSQL Server to be connected. If you use libpq older than PostgreSQL Server expects, you may have problems.

Since version 6.3 (03/02/1998) PostgreSQL uses unix domain sockets by default. TCP port will NOT be opened by default. A table is shown below describing these new connection possibilities. This socket will be found in `/tmp/.s.PGSQL.5432`. This option can be enabled with the `'-i'` flag to **postmaster** and it's meaning is: "listen on TCP/IP sockets as well as Unix domain sockets".

Tabulka 2. Postmaster and PHP

Postmaster	PHP	Status
postmaster &	<code>pg_connect("dbname=MyDbName");</code>	OK;
postmaster -i &	<code>pg_connect("dbname=MyDbName");</code>	OK;
postmaster &	<code>pg_connect("host=localhost dbname=MyDbName");</code>	Unable to connect to PostgreSQL server: connectDB() failed: Is the postmaster running and accepting TCP/IP (with -i) connection at 'localhost' on port '5432'? in /path/to/file.php on line 20.
postmaster -i &	<code>pg_connect("host=localhost dbname=MyDbName");</code>	OK

A connection to PostgreSQL server can be established with the following value pairs set in the command string: **`$conn = pg_connect("host=myHost port=myPort tty=myTTY options=myOptions dbname=myDB user=myUser password=myPassword ");`**

The previous syntax of: **`$conn = pg_connect ("host", "port", "options", "tty", "dbname")`** has been deprecated.

Environmental variables affect PostgreSQL server/client behavior. For example, PostgreSQL module will lookup PGHOST environment variable when the hostname is omitted in the connection string. Supported environment variables are different from version to version. Refer to PostgreSQL Programmer's Manual (libpq - Environment Variables) for details.

Make sure you set environment variables for appropriate user. Use `$_ENV` or `getenv()` to check which environment variables are available to the current process.

Příklad 1. Setting default parameters

```
PGHOST=pgsql.example.com
PGPORT=7890
PGDATABASE=web-system
PGUSER=web-user
PGPASSWORD=secret
PGDATESTYLE=ISO
PGTZ=JST
PGCLIENTENCODING=EUC-JP
```



```
export PGHOST PGPORT PGDATABASE PGUSER PGPASSWORD PGDATESTYLE PGTZ PGCLIENTENCODING
```

Starting with PostgreSQL 7.1.0, you can store up to 1GB into a field of type text. In older versions, this was limited to the block size (default was 8KB, maximum was 32KB, defined at compile time)

To use the large object (lo) interface, it is required to enclose large object functions within a transaction block. A transaction block starts with a SQL statement **BEGIN** and if the transaction was valid ends with **COMMIT** or **END**. If the transaction fails the transaction should be closed with **ROLLBACK** or **ABORT**.

Příklad 2. Using Large Objects

```
<?php
    $database = pg_connect ("dbname=jacarta");
    pg_query ($database, "begin");
    $oid = pg_lo_create ($database);
    echo "$oid\n";
    $handle = pg_lo_open ($database, $oid, "w");
    echo "$handle\n";
    pg_lo_write ($handle, "large object data");
    pg_lo_close ($handle);
    pg_query ($database, "commit");
?>
```

You should not close the connection to the PostgreSQL server before closing the large object.

pg_affected_rows (PHP 4 >= 4.2.0)

Returns number of affected records(tuples)

int **pg_affected_rows** (resource result) \linebreak

pg_affected_rows() returns the number of tuples (instances/records/rows) affected by INSERT, UPDATE, and DELETE queries executed by **pg_query()**. If no tuple is affected by this function, it will return 0.

Příklad 1. pg_affected_rows()

```
<?php
    $result = pg_query ($conn, "INSERT INTO publisher VALUES ('Author')");
    $cmdtuples = pg_affected_rows ($result);
    echo $cmdtuples . " tuples are affected.";
?>
```

Poznámka: This function used to be called `pg_cmdtuples()`.

See also **pg_query()** and **pg_num_rows()**.

pg_cancel_query (PHP 4 >= 4.2.0)

Cancel async query

bool **pg_cancel_query** (resource connection) \linebreak

pg_cancel_query() cancel asynchronous query sent by **pg_send_query()**. You cannot cancel query executed by **pg_query()**.

See also **pg_send_query()** and **pg_connection_busy()**

pg_client_encoding (PHP 3 CVS only, PHP 4 >= 4.0.3)

Get the client encoding

string **pg_client_encoding** ([resource connection]) \linebreak

pg_client_encoding() returns the client encoding as the string. The returned string should be either : SQL_ASCII, EUC_JP, EUC_CN, EUC_KR, EUC_TW, UNICODE, MULE_INTERNAL, LATINX (X=1...9), KOI8, WIN, ALT, SJIS, BIG5, WIN1250.

Poznámka: This function requires PHP-4.0.3 or higher and PostgreSQL-7.0 or higher. If libpq is compiled without multibyte encoding support, **pg_set_client_encoding()** always return

"SQL_ASCII". Supported encoding depends on PostgreSQL version. Refer to PostgreSQL manual for details to enable multibyte support and encoding supported.

The function used to be called **pg_clientencoding()**.

See also `pg_set_client_encoding()`.

pg_close (PHP 3, PHP 4 >= 4.0.0)

Close a PostgreSQL connection

bool **pg_close** (resource connection) \linebreak

pg_close() closes the non-persistent connection to a PostgreSQL database associated with the given *connection* resource. Vrací TRUE při úspěchu, FALSE při selhání.

Poznámka: Using **pg_close()** is not usually necessary, as non-persistent open connections are automatically closed at the end of the script.

If there is open large object resource on the connection, do not close the connection before closing all large object resources.

pg_connect (PHP 3, PHP 4 >= 4.0.0)

Open a PostgreSQL connection

resource **pg_connect** (string connection_string) \linebreak

pg_connect() returns a connection resource that is needed by other PostgreSQL functions.

pg_connect() opens a connection to a PostgreSQL database specified by the *connection_string*. It returns a connection resource on success. It returns FALSE if the connection could not be made. *connection_string* should be a quoted string.

Příklad 1. Using pg_connect

```
<?php
$dbconn = pg_connect ("dbname=mary");
//connect to a database named "mary"
$dbconn2 = pg_connect ("host=localhost port=5432 dbname=mary");
// connect to a database named "mary" on "localhost" at port "5432"
$dbconn3 = pg_connect ("host=sheep port=5432 dbname=mary user=lamb password=foo");
//connect to a database named "mary" on the host "sheep" with a username and password
$conn_string = "host=sheep port=5432 dbname=test user=lamb password=bar";
$dbconn4 = pg_connect ($conn_string);
//connect to a database named "test" on the host "sheep" with a username and password
?>
```

The arguments available for *connection_string* includes *host*, *port*, *tty*, *options*, *dbname*, *user*, and *password*.

If a second call is made to **pg_connect()** with the same *connection_string*, no new connection will be established, but instead, the connection resource of the already opened connection will be returned. You can have multiple connections to the same database if you use different connection string.

The old syntax with multiple parameters **\$conn = pg_connect ("host", "port", "options", "tty", "dbname")** has been deprecated.

See also **pg_pconnect()**, **pg_close()**, **pg_host()**, **pg_port()**, **pg_tty()**, **pg_options()** and **pg_dbname()**.

pg_connection_busy (PHP 4 >= 4.2.0)

Get connection is busy or not

bool pg_connection_busy (resource connection) \linebreak

pg_connection_busy() returns **TRUE** if the connection is busy. If it is busy, a previous query is still executing. If **pg_get_result()** is called, it will be blocked.

See also **pg_connection_status()** and **pg_get_result()**

pg_connection_reset (PHP 4 >= 4.2.0)

Reset connection (reconnect)

bool pg_connection_reset (resource connection) \linebreak

pg_connection_reset() resets the connection. It is useful for error recovery. Vrací **TRUE** při úspěchu, **FALSE** při selhání.

See also **pg_connect()**, **pg_pconnect()** and **pg_connection_status()**

pg_connection_status (PHP 4 >= 4.2.0)

Get connection status

int pg_connection_status (resource connection) \linebreak

pg_connection_status() returns a connection status. Possible statuses are **PGSQL_CONNECTION_OK** and **PGSQL_CONNECTION_BAD**.

See also **pg_connection_busy()**.

pg_convert (PHP 4 CVS only)

Convert associative array value into suitable for SQL statement.

array **pg_convert** (resource connection, string table_name, array assoc_array [, int options]) \linebreak
pg_convert() check and convert `assoc_array` suitable for SQL statement.

Poznámka: This function is experimental.

See also `pg_metadata()`

pg_copy_from (PHP 4 >= 4.2.0)

Insert records into a table from an array

int **pg_copy_from** (int connection, string table_name, array rows [, string delimiter [, string null_as]]) \linebreak

pg_copy_from() insert records into a table from `rows`. It issues `COPY` command internally to insert records. Vrací `TRUE` při úspěchu, `FALSE` při selhání.

See also `pg_copy_to()`

pg_copy_to (PHP 4 >= 4.2.0)

Copy a table to an array

int **pg_copy_to** (int connection, string table_name [, string delimiter [, string null_as]]) \linebreak

pg_copy_to() copies a table to an array. The resulting array is returned. It returns `FALSE` on failure.

See also `pg_copy_from()`

pg_dbname (PHP 3, PHP 4 >= 4.0.0)

Get the database name

string **pg_dbname** (resource connection) \linebreak

pg_dbname() returns the name of the database that the given PostgreSQL *connection* resource. It returns `FALSE`, if *connection* is not a valid PostgreSQL connection resource.

pg_delete (PHP 4 CVS only)

Delete records.

long **pg_delete** (resource connection, string table_name, array assoc_array [, int options]) \linebreak

pg_delete() deletes record condition specified by `assoc_array` which has `field=>value`. If option is specified, `pg_convert()` is applied to `assoc_array` with specified option.

Příklad 1. pg_delete

```

<?php
    $db = pg_connect ('dbname=foo');
    // This is safe, since $_POST is converted automatically
    $res = pg_delete($db, 'post_log', $_POST);
    if ($res) {
        echo "POST data is deleted: $res\n";
    }
    else {
        echo "User must have sent wrong inputs\n";
    }
?>

```

Poznámka: This function is experimental.

See also `pg_convert()`

pg_end_copy (PHP 4 >= 4.0.3)

Sync with PostgreSQL backend

bool **pg_end_copy** ([resource connection]) \linebreak

pg_end_copy() syncs the PostgreSQL frontend (usually a web server process) with the PostgreSQL server after doing a copy operation performed by `pg_put_line()`. **pg_end_copy()** must be issued, otherwise the PostgreSQL server may get out of sync with the frontend and will report an error. Vrací TRUE při úspěchu, FALSE při selhání.

For further details and an example, see also `pg_put_line()`.

pg_escape_bytea (PHP 4 >= 4.2.0)

Escape binary for bytea type

string **pg_escape_bytea** (string data) \linebreak

pg_escape_bytea() escapes string for bytea datatype. It returns escaped string.

Poznámka: When you SELECT bytea type, PostgreSQL returns octal byte value prefixed by \. (e.g. \032) Users are supposed to convert back to binary format by yourself.

This function requires PostgreSQL 7.2 or later. With PostgreSQL 7.2.0 and 7.2.1, bytea type must be casted when you enable multi-byte support. i.e. `INSERT INTO test_table (image) VALUES ('$image_escaped'::bytea);` PostgreSQL 7.2.2 or later does not need cast.

Exception is when client and backend character encoding does not match, there may be multi-byte stream error. User must cast to bytea to avoid this error.

Newer PostgreSQL will support unescape function. Support for built-in unescape function will be added when it's available.

See also `pg_escape_string()`

pg_escape_string (PHP 4 >= 4.2.0)

Escape string for text/char type

string **pg_escape_string** (string data) \linebreak

pg_escape_string() escapes string for text/char datatype. It returns escaped string for PostgreSQL. Use of this function is recommended instead of addslashes().

Poznámka: This function requires PostgreSQL 7.2 or later.

See also `pg_escape_bytea()`

pg_fetch_array (PHP 3 >= 3.0.1, PHP 4 >= 4.0.0)

Fetch a row as an array

array **pg_fetch_array** (resource result, int row [, int result_type]) \linebreak

pg_fetch_array() returns an array that corresponds to the fetched row (tuples/records). It returns FALSE, if there are no more rows.

pg_fetch_array() is an extended version of `pg_fetch_row()`. In addition to storing the data in the numeric indices (field index) to the result array, it also stores the data in associative indices (field name) by default.

row is row (record) number to be retrieved. First row is 0.

result_type is optional parameter controls how return value is initialized. *result_type* is a constant and can take the following values: PGSQL_ASSOC, PGSQL_NUM, and PGSQL_BOTH.

pg_fetch_array() returns associative array that has field name as key for PGSQL_ASSOC. field index as key with PGSQL_NUM and both field name/index as key with PGSQL_BOTH. Default is PGSQL_BOTH.

Poznámka: *result_type* was added in PHP 4.0.

pg_fetch_array() is NOT significantly slower than using **pg_fetch_row()**, while it provides a significant ease of use.

See also **pg_fetch_row()** and **pg_fetch_object()** and **pg_fetch_result()**.

Příklad 1. PostgreSQL fetch array

```
<?php
$conn = pg_pconnect ("dbname=publisher");
if (!$conn) {
    echo "An error occurred.\n";
    exit;
}

$result = pg_query ($conn, "SELECT * FROM authors");
if (!$result) {
    echo "An error occurred.\n";
    exit;
}

$arr = pg_fetch_array ($result, 0, PGSQL_NUM);
echo $arr[0] . " <- array\n";

$arr = pg_fetch_array ($result, 1, PGSQL_ASSOC);
echo $arr["author"] . " <- array\n";
?>
```

Poznámka: From 4.1.0, *row* became optional. Calling **pg_fetch_array()** will increment internal row counter by 1.

pg_fetch_object (PHP 3 >= 3.0.1, PHP 4 >= 4.0.0)

Fetch a row as an object

object **pg_fetch_object** (resource result, int row [, int result_type]) \linebreak

pg_fetch_object() returns an object with properties that correspond to the fetched row. It returns FALSE if there are no more rows or error.

pg_fetch_object() is similar to **pg_fetch_array()**, with one difference - an object is returned, instead of an array. Indirectly, that means that you can only access the data by the field names, and not by their offsets (numbers are illegal property names).

row is row (record) number to be retrieved. First row is 0.

Speed-wise, the function is identical to `pg_fetch_array()`, and almost as quick as `pg_fetch_row()` (the difference is insignificant).

Poznámka: From 4.3.0, `result_type` is default to `PGSQL_ASSOC` while older versions' default was `PGSQL_BOTH`. There is no use for numeric property, since numeric property name is invalid in PHP.

`result_type` may be deleted in future versions.

See also `pg_query()`, `pg_fetch_array()`, `pg_fetch_row()` and `pg_fetch_result()`.

Příklad 1. Postgres fetch object

```
<?php
$database = "verlag";
$db_conn = pg_connect ("host=localhost port=5432 dbname=$database");
if (!$db_conn): ?>
    <H1>Failed connecting to postgres database <?php echo $database ?></H1> <?php
    exit;
endif;

$qu = pg_query ($db_conn, "SELECT * FROM verlag ORDER BY autor");
$row = 0; // postgres needs a row counter other dbs might not

while ($data = pg_fetch_object ($qu, $row)) {
    echo $data->autor." (";
    echo $data->jahr ."): ";
    echo $data->titel."<BR>";
    $row++;
}
?>
<PRE>
<?php
$fields[] = Array ("autor", "Author");
$fields[] = Array ("jahr", " Year");
$fields[] = Array ("titel", " Title");

$row= 0; // postgres needs a row counter other dbs might not
while ($data = pg_fetch_object ($qu, $row)) {
    echo "-----\n";
    reset ($fields);
    while (list (,$item) = each ($fields)):
        echo $item[1].": ".$data->$item[0]."\n";
    endwhile;
    $row++;
}
echo "-----\n";
?>
</PRE>
<?php
pg_free_result ($qu);
pg_close ($db_conn);
?>
```

Poznámka: From 4.1.0, *row* became optional. Calling **pg_fetch_object()** will increment internal row counter counter by 1.

pg_fetch_result (PHP 4 >= 4.2.0)

Returns values from a result resource

mixed **pg_fetch_result** (resource result, int row, mixed field) \linebreak

pg_fetch_result() returns values from a *result* resource returned by **pg_query()**. *row* is integer. *field* is field name(string) or field index (integer). The *row* and *field* specify what cell in the table of results to return. Row numbering starts from 0. Instead of naming the field, you may use the field index as an unquoted number. Field indices start from 0.

PostgreSQL has many built in types and only the basic ones are directly supported here. All forms of integer, boolean and void types are returned as integer values. All forms of float, and real types are returned as float values. All other types, including arrays are returned as strings formatted in the same default PostgreSQL manner that you would see in the **psql** program.

pg_fetch_row (PHP 3>= 3.0.1, PHP 4 >= 4.0.0)

Get a row as an enumerated array

array **pg_fetch_row** (resource result, int row) \linebreak

pg_fetch_row() fetches one row of data from the result associated with the specified *result* resource. The row (record) is returned as an array. Each result column is stored in an array offset, starting at offset 0.

It returns an array that corresponds to the fetched row, or **FALSE** if there are no more rows.

See also: **pg_query()**, **pg_fetch_array()**, **pg_fetch_object()** and **pg_fetch_result()**.

Příklad 1. Postgres fetch row

```
<?php
$conn = pg_pconnect ("dbname=publisher");
if (!$conn) {
    echo "An error occured.\n";
    exit;
}

$result = pg_query ($conn, "SELECT * FROM authors");
if (!$result) {
    echo "An error occured.\n";
```

```

        exit;
    }

    $num = pg_num_rows($result);

    for ($i=0; $i < $num; $i++) {
        $r = pg_fetch_row($result, $i);

        for ($j=0; $j < count($r); $j++) {
            echo "$r[$j]&nbsp;";
        }

        echo "<BR>";
    }

    ?>

```

Poznámka: From 4.1.0, *row* became optional. Calling **pg_fetch_row()** will increment internal row counter by 1.

pg_field_is_null (PHP 4 >= 4.2.0)

Test if a field is NULL

int **pg_field_is_null** (resource result, int row, mixed field) \linebreak

pg_field_is_null() test if a field is NULL or not. It returns 1 if the field in the given row is NULL. It returns 0 if the field in the given row is NOT NULL. Field can be specified as column index (number) or fieldname (string). Row numbering starts at 0.

Poznámka: This function used to be called `pg_fieldisnull()`.

pg_field_name (PHP 4 >= 4.2.0)

Returns the name of a field

string **pg_field_name** (resource result, int field_number) \linebreak

pg_field_name() returns the name of the field occupying the given *field_number* in the given PostgreSQL *result* resource. Field numbering starts from 0.

Poznámka: This function used to be called `pg_fieldname()`.

See also `pg_field_num()`.

pg_field_num (PHP 4 >= 4.2.0)

Returns the field number of the named field

`int pg_field_num (resource result, string field_name) \linebreak`

pg_field_num() will return the number of the column (field) slot that corresponds to the *field_name* in the given PostgreSQL *result* resource. Field numbering starts at 0. This function will return -1 on error.

Poznámka: This function used to be called `pg_fieldnum()`.

See also `pg_field_name()`.

pg_field_prtlen (PHP 4 >= 4.2.0)

Returns the printed length

`int pg_field_prtlen (resource result, int row_number, string field_name) \linebreak`

pg_field_prtlen() returns the actual printed length (number of characters) of a specific value in a PostgreSQL *result*. Row numbering starts at 0. This function will return -1 on an error.

Poznámka: This function used to be called `pg_field_prtlen()`.

See also `pg_field_size()`.

pg_field_size (PHP 4 >= 4.2.0)

Returns the internal storage size of the named field

`int pg_field_size (resource result, int field_number) \linebreak`

pg_field_size() returns the internal storage size (in bytes) of the field number in the given PostgreSQL *result*. Field numbering starts at 0. A field size of -1 indicates a variable length field. This function will return `FALSE` on error.

Poznámka: This function used to be called `pg_fieldsize()`.

See also **pg_field_len()** and `pg_field_type()`.

pg_field_type (PHP 4 >= 4.2.0)

Returns the type name for the corresponding field number

string **pg_field_type** (resource result, int field_number) \linebreak

pg_field_type() returns a string containing the type name of the given *field_number* in the given PostgreSQL *result* resource. Field numbering starts at 0.

Poznámka: This function used to be called `pg_field_type()`.

See also **pg_field_len()** and **pg_field_name()**.

pg_free_result (PHP 4 >= 4.2.0)

Free result memory

bool **pg_free_result** (resource result) \linebreak

pg_free_result() only needs to be called if you are worried about using too much memory while your script is running. All result memory will automatically be freed when the script is finished. But, if you are sure you are not going to need the result data anymore in a script, you may call **pg_free_result()** with the *result* resource as an argument and the associated result memory will be freed. It returns true on success and false if an error occurs.

Poznámka: This function used to be called `pg_free_result()`.

See also **pg_query()**.

pg_get_result (PHP 4 >= 4.2.0)

Get asynchronous query result

resource **pg_get_result** ([resource connection]) \linebreak

pg_get_result() get result resource from async query executed by **pg_send_query()**. **pg_send_query()** can send multiple queries to PostgreSQL server and **pg_get_result()** is used to get query result one by one. It returns result resource. If there is no more results, it returns `FALSE`.

pg_host (PHP 3, PHP 4 >= 4.0.0)

Returns the host name associated with the connection

string **pg_host** (resource connection) \linebreak

pg_host() returns the host name of the given PostgreSQL *connection* resource is connected to.

See also **pg_connect()** and **pg_pconnect()**.

pg_insert (PHP 4 CVS only)

Insert array into table.

bool **pg_insert** (resource connection, string table_name, array assoc_array [, int options]) \linebreak

pg_insert() inserts *assoc_array* which has *field=>value* into table specified as *table_name*. If *options* is specified, **pg_convert()** is applied to *assoc_array* with specified option.

Příklad 1. pg_insert

```
<?php
    $db = pg_connect ( 'dbname=foo' );
    // This is safe, since $_POST is converted automatically
    $res = pg_insert($db, 'post_log', $_POST);
    if ($res) {
        echo "POST data is succesfully logged\n";
    }
    else {
        echo "User must have sent wrong inputs\n";
    }
?>
```

Poznámka: This function is experimental.

See also **pg_convert()**

pg_last_error (PHP 4 >= 4.2.0)

Get the last error message string of a connection

string **pg_last_error** (resource connection) \linebreak

pg_last_error() returns the last error message for given *connection*.

Error messages may be overwritten by internal PostgreSQL(libpq) function calls. It may not return appropriate error message, if multiple errors are occurred inside a PostgreSQL module function.

Use **pg_result_error()**, **pg_result_status()** and **pg_connection_status()** for better error handling.

Poznámka: This function used to be called **pg_errormessage()**.

See also `pg_result_error()`.

pg_last_notice (PHP 4 >= 4.0.6)

Returns the last notice message from PostgreSQL server

string **pg_last_notice** (resource connection) \linebreak

pg_last_notice() returns the last notice message from the PostgreSQL server specified by *connection*. The PostgreSQL server sends notice messages in several cases, e.g. if the transactions can't be continued. With **pg_last_notice()**, you can avoid issuing useless queries, by checking whether the notice is related to the transaction or not.

Varování

This function is EXPERIMENTAL and it is not fully implemented yet.

pg_last_notice() was added in PHP 4.0.6. However, PHP 4.0.6 has problem with notice message handling. Use of the PostgreSQL module with PHP 4.0.6 is not recommended even if you are not using **pg_last_notice()**.

This function is fully implemented in PHP 4.3.0. PHP earlier than PHP 4.3.0 ignores database connection parameter.

Notice message tracking can be set to optional by setting 1 for `pgsql.ignore_notice` ini from PHP 4.3.0.

Notice message logging can be set to optional by setting 0 for `pgsql.log_notice` ini from PHP 4.3.0. Unless `pgsql.ignore_notice` is set to 0, notice message cannot be logged.

See also `pg_query()` and `pg_last_error()`.

pg_last_oid (PHP 4 >= 4.2.0)

Returns the last object's oid

int **pg_last_oid** (resource result) \linebreak

pg_last_oid() is used to retrieve the `oid` assigned to an inserted tuple (record) if the result resource is used from the last command sent via `pg_query()` and was an SQL INSERT. Returns a positive integer if there was a valid `oid`. It returns `FALSE` if an error occurs or the last command sent via `pg_query()` was not an INSERT or INSERT is failed.

OID field became an optional field from PostgreSQL 7.2. When OID field is not defined in a table, programmer must use `pg_result_status()` to check if record is inserted successfully or not.

Poznámka: This function used to be called `pg_getlastoid()`.

See also `pg_query()` and `pg_result_status()`

pg_lo_close (PHP 4 >= 4.2.0)

Close a large object

bool **pg_lo_close** (resource *large_object*) \linebreak

pg_lo_close() closes a Large Object. *large_object* is a resource for the large object from **pg_lo_open()**.

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: This function used to be called `pg_loclose()`.

See also **pg_lo_open()**, **pg_lo_create()** and **pg_lo_import()**.

pg_lo_create (PHP 4 >= 4.2.0)

Create a large object

int **pg_lo_create** (resource *connection*) \linebreak

pg_lo_create() creates a Large Object and returns the *oid* of the large object. *connection* specifies a valid database connection opened by **pg_connect()** or **pg_pconnect()**. PostgreSQL access modes `INV_READ`, `INV_WRITE`, and `INV_ARCHIVE` are not supported, the object is created always with both read and write access. `INV_ARCHIVE` has been removed from PostgreSQL itself (version 6.3 and above). It returns large object *oid* otherwise. It returns `FALSE`, if an error occurred,

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: This function used to be called `pg_locreate()`.

pg_lo_export (PHP 4 >= 4.2.0)

Export a large object to file

bool **pg_lo_export** (int *oid*, string *pathname* [, resource *connection*]) \linebreak

The *oid* argument specifies *oid* of the large object to export and the *pathname* argument specifies the *pathname* of the file. It returns `FALSE` if an error occurred, `TRUE` otherwise.

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: This function used to be called `pg_loexport()`.

See also **pg_lo_import()**.

pg_lo_import (PHP 4 >= 4.2.0)

Import a large object from file

```
int pg_lo_import ( string pathname [, resource connection]) \linebreak
```

The *pathname* argument specifies the pathname of the file to be imported as a large object. It returns `FALSE` if an error occurred, oid of the just created large object otherwise.

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: Pokud je zapnut bezpečný režim (safe-mode), PHP kontroluje, zda soubory/adresáře, se kterými pracujete, mají stejné UID jako spuštěný skript.

Poznámka: This function used to be called `pg_loimport()`.

See also `pg_lo_export()` and `pg_lo_open()`.

pg_lo_open (PHP 4 >= 4.2.0)

Open a large object

```
resource pg_lo_open ( resource connection, int oid, string mode) \linebreak
```

pg_lo_open() open a Large Object and returns large object resource. The resource encapsulates information about the connection. *oid* specifies a valid large object oid and *mode* can be either "r", "w", or "rw". It returns `FALSE` if there is an error.

Varování

Do not close the database connection before closing the large object resource.

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: This function used to be called `pg_loopen()`.

See also `pg_lo_close()` and `pg_lo_create()`.

pg_lo_read (PHP 4 >= 4.2.0)

Read a large object

```
string pg_lo_read ( resource large_object, int len) \linebreak
```

pg_lo_read() reads at most *len* bytes from a large object and returns it as a string. *large_object* specifies a valid large object resource and *len* specifies the maximum allowable size of the large object segment. It returns `FALSE` if there is an error.

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: This function used to be called `pg_loread()`.

See also `pg_lo_read_all()`.

pg_lo_read_all (PHP 4 >= 4.2.0)

Read a entire large object and send straight to browser

```
int pg_lo_read_all ( resource large_object) \linebreak
```

pg_lo_read_all() reads a large object and passes it straight through to the browser after sending all pending headers. Mainly intended for sending binary data like images or sound. It returns number of bytes read. It returns `FALSE`, if an error occurred.

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: This function used to be called `pg_loreadall()`.

See also `pg_lo_read()`.

pg_lo_seek (PHP 4 >= 4.2.0)

Seeks position of large object

```
bool pg_lo_seek ( resource large_object, int offset [, int whence]) \linebreak
```

pg_lo_seek() seeks position of large object resource. *whence* is `PGSQL_SEEK_SET`, `PGSQL_SEEK_CUR` or `PGSQL_SEEK_END`.

See also `pg_lo_tell()`.

pg_lo_tell (PHP 4 >= 4.2.0)

Returns current position of large object

```
int pg_lo_tell ( resource large_object) \linebreak
```

pg_lo_tell() returns current position (offset from the beginning of large object).

See also `pg_lo_seek()`.

pg_lo_unlink (PHP 4 >= 4.2.0)

Delete a large object

bool **pg_lo_unlink** (resource connection, int oid) \linebreak

pg_lo_unlink() deletes a large object with the *oid*. It returns TRUE on success, otherwise returns FALSE.

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: This function used to be called `pg_lo_unlink()`.

See also `pg_lo_create()` and `pg_lo_import()`.

pg_lo_write (PHP 4 >= 4.2.0)

Write a large object

int **pg_lo_write** (resource large_object, string data) \linebreak

pg_lo_write() writes at most to a large object from a variable *data* and returns the number of bytes actually written, or FALSE in the case of an error. *large_object* is a large object resource from `pg_lo_open()`.

To use the large object (lo) interface, it is necessary to enclose it within a transaction block.

Poznámka: This function used to be called `pg_lo_write()`.

See also `pg_lo_create()` and `pg_lo_open()`.

pg_metadata (PHP 4 CVS only)

Get metadata for table.

array **pg_metadata** (resource connection, string table_name) \linebreak

pg_metadata() returns table definition for *table_name* as array. If there is error, it returns FALSE

Poznámka: This function is experimental.

See also `pg_convert()`

pg_num_fields (PHP 4 >= 4.2.0)

Returns the number of fields

```
int pg_num_fields ( resource result) \linebreak
```

pg_num_fields() returns the number of fields (columns) in a PostgreSQL *result*. The argument is a result resource returned by **pg_query()**. This function will return -1 on error.

Poznámka: This function used to be called `pg_numfields()`.

See also **pg_num_rows()** and **pg_affected_rows()**.

pg_num_rows (PHP 4 >= 4.2.0)

Returns the number of rows

```
int pg_num_rows ( resource result) \linebreak
```

pg_num_rows() will return the number of rows in a PostgreSQL *result* resource. *result* is a query result resource returned by **pg_query()**. This function will return -1 on error.

Poznámka: Use **pg_affected_rows()** to get number of rows affected by INSERT, UPDATE and DELETE query.

Poznámka: This function used to be called `pg_numrows()`.

See also **pg_num_fields()** and **pg_affected_rows()**.

pg_options (PHP 3, PHP 4 >= 4.0.0)

Get the options associated with the connection

```
string pg_options ( resource connection) \linebreak
```

pg_options() will return a string containing the options specified on the given PostgreSQL *connection* resource.

pg_pconnect (PHP 3, PHP 4 >= 4.0.0)

Open a persistent PostgreSQL connection

```
int pg_pconnect ( string connection_string) \linebreak
```

pg_pconnect() opens a connection to a PostgreSQL database. It returns a connection resource that is needed by other PostgreSQL functions.

For a description of the *connection_string* parameter, see **pg_connect()**.

To enable persistent connection, the `pgsql.allow_persistent` `php.ini` directive must be set to "On" (which is the default). The maximum number of persistent connection can be defined with the `pgsql.max_persistent` `php.ini` directive (defaults to -1 for no limit). The total number of connections can be set with the `pgsql.max_links` `php.ini` directive.

pg_close() will not close persistent links generated by **pg_pconnect()**.

See also **pg_connect()**.

pg_port (PHP 3, PHP 4 >= 4.0.0)

Return the port number associated with the connection

```
int pg_port ( resource connection ) \linebreak
```

pg_port() returns the port number that the given PostgreSQL *connection* resource is connected to.

pg_put_line (PHP 4 >= 4.0.3)

Send a NULL-terminated string to PostgreSQL backend

```
bool pg_put_line ( [resource connection, string data] ) \linebreak
```

pg_put_line() sends a NULL-terminated string to the PostgreSQL backend server. This is useful for example for very high-speed inserting of data into a table, initiated by starting a PostgreSQL copy-operation. That final NULL-character is added automatically. Vrací TRUE při úspěchu, FALSE při selhání.

Poznámka: The application must explicitly send the two characters "\." on the last line to indicate to the backend that it has finished sending its data.

See also **pg_end_copy()**.

Příklad 1. High-speed insertion of data into a table

```
<?php
    $conn = pg_pconnect ( "dbname=foo" );
    pg_query($conn, "create table bar (a int4, b char(16), d float8)");
    pg_query($conn, "copy bar from stdin");
    pg_put_line($conn, "3\thello world\t4.5\n");
    pg_put_line($conn, "4\tgoodbye world\t7.11\n");
    pg_put_line($conn, "\\.\n");
    pg_end_copy($conn);
?>
```

pg_query (PHP 4 >= 4.2.0)

Execute a query

resource **pg_query** (resource connection, string query) \linebreak

pg_query() returns a query result resource if query could be executed. It returns `FALSE` on failure or if connection is not a valid connection. Details about the error can be retrieved using the `pg_last_error()` function if connection is valid. `pg_last_error()` sends an SQL statement to the PostgreSQL database specified by the *connection* resource. The *connection* must be a valid connection that was returned by `pg_connect()` or `pg_pconnect()`. The return value of this function is an query result resource to be used to access the results from other PostgreSQL functions such as `pg_fetch_array()`.

Poznámka: *connection* is a optional parameter for **pg_query()**. If *connection* is not set, default connection is used. Default connection is the last connection made by `pg_connect()` or `pg_pconnect()`.

Although *connection* can be omitted, it is not recommended, since it could be a cause of hard to find bug in script.

Poznámka: This function used to be called `pg_exec()`. `pg_exec()` is still available for compatibility reasons but users are encouraged to use the newer name.

See also `pg_connect()`, `pg_pconnect()`, `pg_fetch_array()`, `pg_fetch_object()`, `pg_num_rows()`, and `pg_affected_rows()`.

pg_result_error (PHP 4 >= 4.2.0)

Get error message associated with result

string **pg_result_error** (resource result) \linebreak

pg_result_error() returns error message associated with *result* resource. Therefore, user has better chance to get better error message than `pg_last_error()`.

See also `pg_query()`, `pg_send_query()`, `pg_get_result()`, `pg_last_error()` and `pg_last_notice()`

pg_result_status (PHP 4 >= 4.2.0)

Get status of query result

```
int pg_result_status ( resource result) \linebreak
```

pg_result_status() returns status of result resource. Possible return values are PGSQL_EMPTY_QUERY, PGSQL_COMMAND_OK, PGSQL_TUPLES_OK, PGSQL_COPY_TO, PGSQL_COPY_FROM, PGSQL_BAD_RESPONSE, PGSQL_NONFATAL_ERROR and PGSQL_FATAL_ERROR.

See also `pg_connection_status()`.

pg_select (PHP 4 CVS only)

Select records.

```
array pg_select ( resource connection, string table_name, array assoc_array [, int options]) \linebreak
```

pg_select() selects records specified by `assoc_array` which has `field=>value`. For successful query, it returns array contains all records and fields that match the condition specified by `assoc_array`. If `options` is specified, `pg_convert()` is applied to `assoc_array` with specified option.

Příklad 1. pg_select

```
<?php
$db = pg_connect ('dbname=foo');
// This is safe, since $_POST is converted automatically
$rec = pg_select($db, 'post_log', $_POST);
if ($rec) {
    echo "Records selected\n";
    var_dump($rec);
}
else {
    echo "User must have sent wrong inputs\n";
}
?>
```

Poznámka: This function is experimental.

See also `pg_convert()`

pg_send_query (PHP 4 >= 4.2.0)

Send asynchronous query

```
bool pg_send_query ( resource connection, string query) \linebreak bool pg_send_query ( string query) \linebreak
```

pg_send_query() send asynchronous query to the *connection*. Unlike **pg_query()**, it can send multiple query to PostgreSQL and get the result one by one using **pg_get_result()**. Script execution is not block while query is executing. Use **pg_connection_busy()** to check connection is busy (i.e. query is executing) Query may be canceled by calling **pg_cancel_query()**.

Although, user can send multiple query at once. User cannot send multiple query over busy connection. If query is sent while connection is busy, it waits until last query is finished and discards all result.

See also **pg_query()**, **pg_cancel_query()**, **pg_get_result()** and **pg_connection_busy()**

pg_set_client_encoding (PHP 3 CVS only, PHP 4 >= 4.0.3)

Set the client encoding

```
int pg_set_client_encoding ( [resource connection, string encoding]) \linebreak
```

pg_set_client_encoding() sets the client encoding and return 0 if success or -1 if error.

encoding is the client encoding and can be either : SQL_ASCII, EUC_JP, EUC_CN, EUC_KR, EUC_TW, UNICODE, MULE_INTERNAL, LATINX (X=1...9), KOI8, WIN, ALT, SJIS, BIG5, WIN1250. Available encoding depends on your PostgreSQL and libpq version. Refer to PostgreSQL manual for supported encodings for your PostgreSQL.

Poznámka: This function requires PHP-4.0.3 or higher and PostgreSQL-7.0 or higher. Supported encoding depends on PostgreSQL version. Refer to PostgreSQL manual for details.

The function used to be called **pg_setclientencoding()**.

See also **pg_client_encoding()**.

pg_trace (PHP 4)

Enable tracing a PostgreSQL connection

```
bool pg_trace ( string pathname [, string mode [, resource connection]]) \linebreak
```

pg_trace() enables tracing of the PostgreSQL frontend/backend communication to a debugging file specified as *pathname*. To fully understand the results, one needs to be familiar with the internals of PostgreSQL communication protocol. For those who are not, it can still be useful for tracing errors in queries sent to the server, you could do for example **grep '^To backend' trace.log** and see what query actually were sent to the PostgreSQL server. For more information, refer to PostgreSQL manual.

Filename and *mode* are the same as in `fopen()` (*mode* defaults to 'w'), *connection* specifies the connection to trace and defaults to the last one opened.

It returns `TRUE` if *pathname* could be opened for logging, `FALSE` otherwise.

See also `fopen()` and `pg_untrace()`.

pg_tty (PHP 3, PHP 4 >= 4.0.0)

Return the tty name associated with the connection

string **pg_tty** (resource connection) \linebreak

pg_tty() returns the tty name that server side debugging output is sent to on the given PostgreSQL *connection* resource.

pg_untrace (PHP 4)

Disable tracing of a PostgreSQL connection

bool **pg_untrace** ([resource connection]) \linebreak

Stop tracing started by `pg_trace()`. *connection* specifies the connection that was traced and defaults to the last one opened.

Returns always `TRUE`.

See also `pg_trace()`.

pg_update (PHP 4 CVS only)

Update table.

long **pg_update** (resource connection, string table_name, array condition, array data [, int options]) \linebreak

pg_update() updates records that matches condition with data. If options is specified, `pg_convert()` is applied to `assoc_array` with specified options.

Příklad 1. pg_update

```
<?php
$db = pg_connect ('dbname=foo');
$data = array('field1'=>'AA', 'field2'=>'BB');
// This is safe, since $_POST is converted automatically
$res = pg_update($db, 'post_log', $_POST, $data);
if ($res) {
    echo "Data is updated: $res\n";
}
else {
```

```
        echo "User must have sent wrong inputs\n";  
    }  
?>
```

Poznámka: This function is experimental.

See also `pg_convert()`

LXXX. Process Control Functions

Process Control support in PHP implements the Unix style of process creation, program execution, signal handling and process termination. Process Control should not be enabled within a webserver environment and unexpected results may happen if any Process Control functions are used within a webserver environment.

This documentation is intended to explain the general usage of each of the Process Control functions. For detailed information about Unix process control you are encouraged to consult your systems documentation including `fork(2)`, `waitpid(2)` and `signal(2)` or a comprehensive reference such as *Advanced Programming in the UNIX Environment* by W. Richard Stevens (Addison-Wesley).

Process Control support in PHP is not enabled by default. You will need to use the `--enable-pcntl` configuration option when compiling PHP to enable Process Control support.

Poznámka: Currently, this module will not function on non-Unix platforms (Windows).

The following list of signals are supported by the Process Control functions. Please see your systems `signal(7)` man page for details of the default behavior of these signals.

Tabulka 1. Supported Signals

SIGFPE	SIGCONT	SIGKILL
SIGSTOP	SIGUSR1	SIGTSTP
SIGHUP	SIGUSR2	SIGTTIN
SIGINT	SIGSEGV	SIGTOU
SIGQUIT	SIGPIPE	SIGURG
SIGILL	SIGALRM	SIGXCPU
SIGTRAP	SIGTERM	SIGXFSZ
SIGABRT	SIGSTKFLT	SIGVTALRM
SIGIOT	SIGCHLD	SIGPROF
SIGBUS	SIGCLD	SIGWINCH
SIGPOLL	SIGIO	SIGPWR
SIGSYS		

Process Control Example

This example forks off a daemon process with a signal handler.

Příklad 1. Process Control Example

```
<?php

$pid = pcntl_fork();
if ($pid == -1) {
```

```

        die("could not fork");
    } else if ($pid) {
        exit(); // we are the parent
    } else {
        // we are the child
    }

    // detach from the controlling terminal
    if (!posix_setsid()) {
        die("could not detach from terminal");
    }

    // setup signal handlers
    pcntl_signal(SIGTERM, "sig_handler");
    pcntl_signal(SIGHUP, "sig_handler");

    // loop forever performing tasks
    while(1) {

        // do something interesting here

    }

    function sig_handler($signo) {

        switch($signo) {
            case SIGTERM:
                // handle shutdown tasks
                exit;
                break;
            case SIGHUP:
                // handle restart tasks
                break;
            default:
                // handle all other signals
        }
    }

}

?>

```

pcntl_exec (PHP 4 >= 4.2.0)

Executes specified program in current process space

bool **pcntl_exec** (string path [, array args [, array envs]]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

pcntl_fork (PHP 4 >= 4.1.0)

Forks the currently running process

int **pcntl_fork** (void) \linebreak

The **pcntl_fork()** function creates a child process that differs from the parent process only in its PID and PPID. Please see your system's fork(2) man page for specific details as to how fork works on your system.

On success, the PID of the child process is returned in the parent's thread of execution, and a 0 is returned in the child's thread of execution. On failure, a -1 will be returned in the parent's context, no child process will be created, and a PHP error is raised.

Příklad 1. pcntl_fork() Example

```
<?php

$pid = pcntl_fork();
if ($pid == -1) {
    die("could not fork");
} else if ($pid) {
    // we are the parent
} else {
    // we are the child
}

?>
```

See also `pcntl_waitpid()` and `pcntl_signal()`.

pcntl_signal (PHP 4 >= 4.1.0)

Installs a signal handler

bool **pcntl_signal** (int signo, mixed handle) \linebreak

The **pcntl_signal()** function installs a new signal handler for the signal indicated by *signo*. The signal handler is set to *handler* which may be the name of a user created function, or either of the two global constants SIG_IGN or SIG_DFL.

pcntl_signal() returns TRUE on success or FALSE on failure.

Příklad 1. pcntl_signal() Example

```
<?php

// signal handler function
function sig_handler($signo) {

    switch($signo) {
        case SIGTERM:
            // handle shutdown tasks
            exit;
            break;
        case SIGHUP:
            // handle restart tasks
            break;
        case SIGUSR1:
            print "Caught SIGUSR1...\n";
            break;
        default:
            // handle all other signals
    }
}

print "Installing signal handler...\n";

// setup signal handlers
pcntl_signal(SIGTERM, "sig_handler");
pcntl_signal(SIGHUP, "sig_handler");
pcntl_signal(SIGUSR1, "sig_handler");

print "Generating signal SIGTERM to self...\n";

// send SIGUSR1 to current process id
posix_kill(posix_getpid(), SIGUSR1);

print "Done\n"

?>
```

See also pcntl_fork() and pcntl_waitpid().

pcntl_waitpid (PHP 4 >= 4.1.0)

Waits on or returns the status of a forked child

```
int pcntl_waitpid ( int pid, int status, int options) \linebreak
```

The **pcntl_waitpid()** function suspends execution of the current process until a child as specified by the *pid* argument has exited, or until a signal is delivered whose action is to terminate the current process or to call a signal handling function. If a child as requested by *pid* has already exited by the time of the call (a so-called "zombie" process), the function returns immediately. Any system resources used by the child are freed. Please see your system's waitpid(2) man page for specific details as to how waitpid works on your system.

pcntl_waitpid() returns the process ID of the child which exited, -1 on error or zero if WNOHANG was used and no child was available

The value of *pid* can be one of the following:

Tabulka 1. possible values for *pid*

< -1	wait for any child process whose process group ID is equal to the absolute value of <i>pid</i> .
-1	wait for any child process; this is the same behaviour that the wait function exhibits.
0	wait for any child process whose process group ID is equal to that of the calling process.
> 0	wait for the child whose process ID is equal to the value of <i>pid</i> .

pcntl_waitpid() will store status information in the *status* parameter which can be evaluated using the following functions: pcntl_wifexited(), pcntl_wifstopped(), pcntl_wifsignaled(), pcntl_wexitstatus(), pcntl_wtermsig() and pcntl_wstopsig().

The value of *options* is the value of zero or more of the following two global constants OR'ed together:

Tabulka 2. possible values for *options*

WNOHANG	return immediately if no child has exited.
WUNTRACED	return for children which are stopped, and whose status has not been reported.

See also pcntl_fork(), pcntl_signal(), pcntl_wifexited(), pcntl_wifstopped(), pcntl_wifsignaled(), pcntl_wexitstatus(), pcntl_wtermsig() and pcntl_wstopsig().

pcntl_wexitstatus (PHP 4 >= 4.1.0)

Returns the return code of a terminated child

int **pcntl_wexitstatus** (int status) \linebreak

Returns the return code of a terminated child. This function is only useful if `pcntl_wifexited()` returned `TRUE`.

The parameter *status* is the status parameter supplied to a successful call to `pcntl_waitpid()`.

See also `pcntl_waitpid()` and `pcntl_wifexited()`.

pcntl_wifexited (PHP 4 >= 4.1.0)

Returns `TRUE` if status code represents a successful exit

int **pcntl_wifexited** (int status) \linebreak

Returns `TRUE` if the child status code represents a successful exit.

The parameter *status* is the status parameter supplied to a successful call to `pcntl_waitpid()`.

See also `pcntl_waitpid()` and `pcntl_wexitstatus()`.

pcntl_wifsignaled (PHP 4 >= 4.1.0)

Returns `TRUE` if status code represents a termination due to a signal

int **pcntl_wifsignaled** (int status) \linebreak

Returns `TRUE` if the child process exited because of a signal which was not caught.

The parameter *status* is the status parameter supplied to a successful call to `pcntl_waitpid()`.

See also `pcntl_waitpid()` and `pcntl_signal()`.

pcntl_wifstopped (PHP 4 >= 4.1.0)

Returns `TRUE` if child process is currently stopped

int **pcntl_wifstopped** (int status) \linebreak

Returns `TRUE` if the child process which caused the return is currently stopped; this is only possible if the call to `pcntl_waitpid()` was done using the option `WUNTRACED`.

The parameter *status* is the status parameter supplied to a successful call to `pcntl_waitpid()`.

See also `pcntl_waitpid()`.

pcntl_wstopsig (PHP 4 >= 4.1.0)

Returns the signal which caused the child to stop

int **pcntl_wstopsig** (int status) \linebreak

Returns the number of the signal which caused the child to stop. This function is only useful if `pcntl_wifstopped()` returned `TRUE`.

The parameter *status* is the status parameter supplied to a successful call to `pcntl_waitpid()`.

See also `pcntl_waitpid()` and `pcntl_wifstopped()`.

pcntl_wtermsig (PHP 4 >= 4.1.0)

Returns the signal which caused the child to terminate

`int pcntl_wtermsig (int status) \linebreak`

Returns the number of the signal that caused the child process to terminate. This function is only useful if `pcntl_wifsignaled()` returned `TRUE`.

The parameter *status* is the status parameter supplied to a successful call to `pcntl_waitpid()`.

See also `pcntl_waitpid()`, `pcntl_signal()` and `pcntl_wifsignaled()`.

LXXXI. Funkce Spouštění Programů

escapeshellarg (PHP 4 >= 4.0.3)

ouvozovkování řetězce pro použití jako argument shellu

string **escapeshellarg** (string arg) \linebreak

EscapeShellArg() přidá jednoduché uvozovky na začátek a konec řetězce a ouvozovkuje/escapes všechny výskyty jednoduchých uvozovek, takže tento řetězec můžete přímo předat shell funkci, přičemž tento bude brán jako bezpečný argument. Tato funkce by se měla používat k oescapování jednotlivých argumentů určených pro shell funkce pocházejících z uživatelského vstupu. Shell funkce zahrnující `exec()`, `system()` a backtick operator. Standardní použití:

```
system("ls ".EscapeShellArg($dir))
```

Viz také `exec()`, `popen()`, `system()`, a backtick operátor.

escapeshellcmd (PHP 3, PHP 4 >= 4.0.0)

escape shellovské metaznaky

string **escapeshellcmd** (string command) \linebreak

EscapeShellCmd() oescapuje všechny znaky v řetězci, které by se daly použít ke zneužití shellového příkazu k vykonání libovolných příkazů. Tato funkce by se měla používat k zabezpečení toho, aby všechna data pocházející z uživatelského vstupu byla oescapována přetím, než budou předána funkci `exec()` nebo `system()`, nebo backtick operátoru. Standardní použití:

```
$e = EscapeShellCmd($userinput);
system("echo $e"); // tady nás nezajímá, jestli jsou v $e mezery
$f = EscapeShellCmd($filename);
system("touch \" /tmp/$f\"; ls -l \" /tmp/$f\""); // a tady ano, proto použijeme uvozovky
```

Viz také `escapeshellarg()`, `exec()`, `popen()`, `system()`, a backtick operátor.

exec (PHP 3, PHP 4 >= 4.0.0)

Provést externí program

string **exec** (string command [, string array [, int return_var]]) \linebreak

exec() provádí předaný *command*, nicméně nic netiskne. Pouze vrátí poslední řádek výstupu daného příkazu. Pokud potřebujete provést příkaz a nechat všechna data z tohoto příkazu předat rovnou bez jakéhokoli zásahu, použijte funkci **PassThru()**.

Pokud je přítomen argument *array*, předané pole se naplní všemi řádky výstupu daného příkazu. Pozn.: Pokud toto pole už obsahuje nějaké prvky, **exec()** připojí tento výstup na konec tohoto pole. Pokud nechcete, aby tato funkce připojovala prvky na konec daného pole, zavolejte na toto pole **unset()** předtím, než ho předáte funkci **exec()**.

Pokud je vedle argumentu *array* přítomen argument *return_var*, návratová hodnota provedeného příkazu se zapíše do této proměnné.

Pozn.: Pokud chcete používat v této funkci data z uživatelského vstupu, měli byste používat **EscapeShellCmd()**, abyste měli jistotu, že uživatelé nevmanipulují systém do provádění libovolných příkazů.

Pozn.: Pokud touto funkcí nainiciujete nějaký program a chcete ho nechat běžet v pozadí, musíte se zajistit přeměrování výstupu z tohoto programu do souboru nebo jiného výstupního streamu, jinak se PHP zasekne až do ukončení běhu tohoto programu.

Viz také **system()**, **PassThru()**, **popen()**, **EscapeShellCmd()**, a backtick operátor.

passthru (PHP 3, PHP 4 >= 4.0.0)

Vykonat externí program a zobrazit nezpracovaný výstup

```
void passthru ( string command [, int return_var] ) \linebreak
```

Funkce **passthru()** se podobá funkci **exec()** v tom ohledu, že provede *command*. Pokud je přítomen argument *return_var*, návratová hodnota tohoto příkazu se umístí sem. Tato funkce by se měla používat místo **exec()** a **system()**, pokud jsou výstupem daného příkazu binární data, která je potřeba odeslat přímo do browseru. Běžným použitím této funkce vykonat např. *pbmplus* utility, které mohou poslat stream obrázku na stdout. Nastavením content-type na *image/gif* a zavoláním *pbmplus* programu k odeslání gifu na stdout gifu můžete vytvořit PHP skripty, které přímo tvoří obrázky.

Pozn.: Pokud touto funkcí nainiciujete nějaký program a chcete ho nechat běžet v pozadí, musíte se zajistit přeměrování výstupu z tohoto programu do souboru nebo jiného výstupního streamu, jinak se PHP zasekne až do ukončení běhu tohoto programu.

Viz také **exec()**, **system()**, **popen()**, **EscapeShellCmd()**, a backtick operátor.

system (PHP 3, PHP 4 >= 4.0.0)

Provést externí program a zobrazit výstup

```
string system ( string command [, int return_var] ) \linebreak
```

system() je verzi stejnojmenné C funkce; vykoná předaný *command* a zobrazí výstup. Pokud jí předáte proměnnou jako druhý argument, návratová hodnota provedeného příkazu se zapíše do této proměnné.

Pozn.: Pokud chcete používat v této funkci data z uživatelského vstupu, měli byste používat **EscapeShellCmd()**, abyste měli jistotu, že uživatelé nevmanipulují systém do provádění libovolných příkazů.

Pozn.: Pokud touto funkcí nainiciujete nějaký program a chcete ho nechat běžet v pozadí, musíte se zajistit přeměrování výstupu z tohoto programu do souboru nebo jiného výstupního streamu, jinak se PHP zasekne až do ukončení běhu tohoto programu.

Pokud PHP běží jako modul serveru, **system()** také automaticky flushne výstupní buffer web serveru po každém řádku výstupu.

Při úspěchu vrací poslední řádek výstupu příkazu, při selhání `FALSE`.

Pokud potřebujete provést příkaz a nechat všechna data z tohoto příkazu předat rovnou bez jakéhokoli zásahu, použijte funkci **PassThru()**.

Viz také `exec()`, **PassThru()**, `popen()`, **EscapeShellCmd()**, a backtick operátor.

LXXXII. Printer functions

These functions are only available under Windows 9.x, ME, NT4 and 2000. They have been added in PHP 4 (4.0.4).

printer_abort (unknown)

Deletes the printer's spool file

void **printer_abort** (resource handle) \linebreak

This function deletes the printers spool file.

handle must be a valid handle to a printer.

Příklad 1. printer_abort() example

```
$handle = printer_open();
printer_abort($handle);
printer_close($handle);
```

printer_close (unknown)

Close an open printer connection

void **printer_close** (resource handle) \linebreak

This function closes the printer connection. **printer_close()** also closes the active device context.

handle must be a valid handle to a printer.

Příklad 1. printer_close() example

```
$handle = printer_open();
printer_close($handle);
```

printer_create_brush (unknown)

Create a new brush

mixed **printer_create_brush** (int style, string color) \linebreak

The function creates a new brush and returns a handle to it. A brush is used to fill shapes. For an example see `printer_select_brush()`. *color* must be a color in RGB hex format, i.e. "000000" for black, *style* must be one of the following constants:

- `PRINTER_BRUSH_SOLID`: creates a brush with a solid color.
- `PRINTER_BRUSH_DIAGONAL`: creates a brush with a 45-degree upward left-to-right hatch (/).
- `PRINTER_BRUSH_CROSS`: creates a brush with a cross hatch (+).

- `PRINTER_BRUSH_DIAGCROSS`: creates a brush with a 45 cross hatch (x).
- `PRINTER_BRUSH_FDIAGONAL`: creates a brush with a 45-degree downward left-to-right hatch (\).
- `PRINTER_BRUSH_HORIZONTAL`: creates a brush with a horizontal hatch (-).
- `PRINTER_BRUSH_VERTICAL`: creates a brush with a vertical hatch (|).
- `PRINTER_BRUSH_CUSTOM`: creates a custom brush from an BMP file. The second parameter is used to specify the BMP instead of the RGB color code.

printer_create_dc (unknown)

Create a new device context

void **printer_create_dc** (resource handle) \linebreak

The function creates a new device context. A device context is used to customize the graphic objects of the document. *handle* must be a valid handle to a printer.

Příklad 1. printer_create_dc() example

```
$handle = printer_open();
printer_start_doc($handle);
printer_start_page($handle);

printer_create_dc($handle);
/* do some stuff with the dc */
printer_set_option($handle, PRINTER_TEXT_COLOR, "333333");
printer_draw_text($handle, 1, 1, "text");
printer_delete_dc($handle);

/* create another dc */
printer_create_dc($handle);
printer_set_option($handle, PRINTER_TEXT_COLOR, "000000");
printer_draw_text($handle, 1, 1, "text");
/* do some stuff with the dc */

printer_delete_dc($handle);

printer_endpage($handle);
printer_end_doc($handle);
printer_close($handle);
```


printer_create_font (unknown)

Create a new font

mixed **printer_create_font** (string face, int height, int width, int font_weight, bool italic, bool underline, bool strikeout, int orientaton) \linebreak

The function creates a new font and returns a handle to it. A font is used to draw text. For an example see `printer_select_font()`. *face* must be a string specifying the font face. *height* specifies the font height, and *width* the font width. The *font_weight* specifies the font weight (400 is normal), and can be one of the following predefined constants.

- `PRINTER_FW_THIN`: sets the font weight to thin (100).
- `PRINTER_FW_ULTRALIGHT`: sets the font weight to ultra light (200).
- `PRINTER_FW_LIGHT`: sets the font weight to light (300).
- `PRINTER_FW_NORMAL`: sets the font weight to normal (400).
- `PRINTER_FW_MEDIUM`: sets the font weight to medium (500).
- `PRINTER_FW_BOLD`: sets the font weight to bold (700).
- `PRINTER_FW_ULTRABOLD`: sets the font weight to ultra bold (800).
- `PRINTER_FW_HEAVY`: sets the font weight to heavy (900).

italic can be `TRUE` or `FALSE`, and sets whether the font should be italic.

underline can be `TRUE` or `FALSE`, and sets whether the font should be underlined.

strikeout can be `TRUE` or `FALSE`, and sets whether the font should be striked out.

orientation specifies a rotation. For an example see `printer_select_font()`.

printer_create_pen (unknown)

Create a new pen

mixed **printer_create_pen** (int style, int width, string color) \linebreak

The function creates a new pen and returns a handle to it. A pen is used to draw lines and curves. For an example see `printer_select_pen()`. *color* must be a color in RGB hex format, i.e. "000000" for black, *width* specifies the width of the pen whereas *style* must be one of the following constants:

- `PRINTER_PEN_SOLID`: creates a solid pen.
- `PRINTER_PEN_DASH`: creates a dashed pen.
- `PRINTER_PEN_DOT`: creates a dotted pen.
- `PRINTER_PEN_DASHDOT`: creates a pen with dashes and dots.
- `PRINTER_PEN_DASHDOTDOT`: creates a pen with dashes and double dots.
- `PRINTER_PEN_INVISIBLE`: creates an invisible pen.

printer_delete_brush (unknown)

Delete a brush

bool **printer_delete_brush** (resource handle) \linebreak

The function deletes the selected brush. For an example see `printer_select_brush()`. It returns `TRUE` on success, or `FALSE` otherwise. *handle* must be a valid handle to a brush.

printer_delete_dc (unknown)

Delete a device context

bool **printer_delete_dc** (resource handle) \linebreak

The function deletes the device context and returns `TRUE` on success, or `FALSE` if an error occurred. For an example see `printer_create_dc()`. *handle* must be a valid handle to a printer.

printer_delete_font (unknown)

Delete a font

bool **printer_delete_font** (resource handle) \linebreak

The function deletes the selected font. For an example see `printer_select_font()`. It returns `TRUE` on success, or `FALSE` otherwise. *handle* must be a valid handle to a font.

printer_delete_pen (unknown)

Delete a pen

bool **printer_delete_pen** (resource handle) \linebreak

The function deletes the selected pen. For an example see `printer_select_pen()`. It returns `TRUE` on success, or `FALSE` otherwise. *handle* must be a valid handle to a pen.

printer_draw_bmp (unknown)

Draw a bmp

void **printer_draw_bmp** (resource handle, string filename, int x, int y) \linebreak

The function simply draws an bmp the bitmap *filename* at position *x*, *y*. *handle* must be a valid handle to a printer.

The function returns `TRUE` on success, or otherwise `FALSE`.

Příklad 1. printer_draw_bmp() example

```

$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

printer_draw_bmp($handle, "c:\\image.bmp", 1, 1);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);

```

printer_draw_chord (unknown)

Draw a chord

void **printer_draw_chord** (resource handle, int rec_x, int rec_y, int rec_x1, int rec_y1, int rad_x, int rad_y, int rad_x1, int rad_y1) \linebreak

The function simply draws an chord. *handle* must be a valid handle to a printer.

rec_x is the upper left x coordinate of the bounding rectangle.

rec_y is the upper left y coordinate of the bounding rectangle.

rec_x1 is the lower right x coordinate of the bounding rectangle.

rec_y1 is the lower right y coordinate of the bounding rectangle.

rad_x is x coordinate of the radial defining the beginning of the chord.

rad_y is y coordinate of the radial defining the beginning of the chord.

rad_x1 is x coordinate of the radial defining the end of the chord.

rad_y1 is y coordinate of the radial defining the end of the chord.

Příklad 1. printer_draw_chord() example

```

$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$pen = printer_create_pen(PRINTER_PEN_SOLID, 2, "000000");
printer_select_pen($handle, $pen);

$brush = printer_create_brush(PRINTER_BRUSH_SOLID, "2222FF");
printer_select_brush($handle, $brush);

printer_draw_chord($handle, 1, 1, 500, 500, 1, 1, 500, 1);

printer_delete_brush($brush);
printer_delete_pen($pen);

```

```
printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);
```

printer_draw_ellipse (unknown)

Draw an ellipse

void **printer_draw_ellipse** (resource handle, int ul_x, int ul_y, int lr_x, int lr_y) \linebreak

The function simply draws an ellipse. *handle* must be a valid handle to a printer.

ul_x is the upper left x coordinate of the ellipse.

ul_y is the upper left y coordinate of the ellipse.

lr_x is the lower right x coordinate of the ellipse.

lr_y is the lower right y coordinate of the ellipse.

Příklad 1. printer_draw_ellipse() example

```
$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$pen = printer_create_pen(PRINTER_PEN_SOLID, 2, "000000");
printer_select_pen($handle, $pen);

$brush = printer_create_brush(PRINTER_BRUSH_SOLID, "2222FF");
printer_select_brush($handle, $brush);

printer_draw_ellipse($handle, 1, 1, 500, 500);

printer_delete_brush($brush);
printer_delete_pen($pen);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);
```

printer_draw_line (unknown)

Draw a line

void **printer_draw_line** (resource printer_handle, int from_x, int from_y, int to_x, int to_y) \linebreak

The function simply draws a line from position *from_x*, *from_y* to position *to_x*, *to_y* using the selected pen. *printer_handle* must be a valid handle to a printer.

Příklad 1. `printer_draw_line()` example

```
$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$pen = printer_create_pen(PRINTER_PEN_SOLID, 30, "000000");
printer_select_pen($handle, $pen);

printer_draw_line($handle, 1, 10, 1000, 10);
printer_draw_line($handle, 1, 60, 500, 60);

printer_delete_pen($pen);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);
```

`printer_draw_pie` (unknown)

Draw a pie

```
void printer_draw_pie ( resource handle, int rec_x, int rec_y, int rec_x1, int rec_y1, int rad1_x, int rad1_y,
int rad2_x, int rad2_y) \linebreak
```

The function simply draws an pie. *handle* must be a valid handle to a printer.

rec_x is the upper left x coordinate of the bounding rectangle.

rec_y is the upper left y coordinate of the bounding rectangle.

rec_x1 is the lower right x coordinate of the bounding rectangle.

rec_y1 is the lower right y coordinate of the bounding rectangle.

rad1_x is x coordinate of the first radial's ending.

rad1_y is y coordinate of the first radial's ending.

rad2_x is x coordinate of the second radial's ending.

rad2_y is y coordinate of the second radial's ending.

Příklad 1. `printer_draw_chord()` example

```
$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$pen = printer_create_pen(PRINTER_PEN_SOLID, 2, "000000");
```

```

printer_select_pen($handle, $pen);

$brush = printer_create_brush(PRINTER_BRUSH_SOLID, "2222FF");
printer_select_brush($handle, $brush);

printer_draw_pie($handle, 1, 1, 500, 500, 1, 1, 500, 1);

printer_delete_brush($brush);
printer_delete_pen($pen);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);

```

printer_draw_rectangle (unknown)

Draw a rectangle

void printer_draw_rectangle (resource handle, int ul_x, int ul_y, int lr_x, int lr_y) \linebreak

The function simply draws a rectangle.

handle must be a valid handle to a printer.

ul_x is the upper left x coordinate of the rectangle.

ul_y is the upper left y coordinate of the rectangle.

lr_x is the lower right x coordinate of the rectangle.

lr_y is the lower right y coordinate of the rectangle.

Příklad 1. printer_draw_rectangle() example

```

$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$pen = printer_create_pen(PRINTER_PEN_SOLID, 2, "000000");
printer_select_pen($handle, $pen);

$brush = printer_create_brush(PRINTER_BRUSH_SOLID, "2222FF");
printer_select_brush($handle, $brush);

printer_draw_rectangle($handle, 1, 1, 500, 500);

printer_delete_brush($brush);
printer_delete_pen($pen);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);

```

printer_draw_roundrect (unknown)

Draw a rectangle with rounded corners

```
void printer_draw_roundrect ( resource handle, int ul_x, int ul_y, int lr_x, int lr_y, int width, int height)
\linebreak
```

The function simply draws a rectangle with rounded corners.

handle must be a valid handle to a printer.

ul_x is the upper left x coordinate of the rectangle.

ul_y is the upper left y coordinate of the rectangle.

lr_x is the lower right x coordinate of the rectangle.

lr_y is the lower right y coordinate of the rectangle.

width is the width of the ellipse.

height is the height of the ellipse.

Příklad 1. printer_draw_roundrect() example

```
$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$pen = printer_create_pen(PRINTER_PEN_SOLID, 2, "000000");
printer_select_pen($handle, $pen);

$brush = printer_create_brush(PRINTER_BRUSH_SOLID, "2222FF");
printer_select_brush($handle, $brush);

printer_draw_roundrect($handle, 1, 1, 500, 500, 200, 200);

printer_delete_brush($brush);
printer_delete_pen($pen);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);
```

printer_draw_text (unknown)

Draw text

```
void printer_draw_text ( resource printer_handle, string text, int x, int y) \linebreak
```

The function simply draws *text* at position *x, y* using the selected font. *printer_handle* must be a valid handle to a printer.

Příklad 1. `printer_draw_text()` example

```
$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$font = printer_create_font("Arial",72,48,400,false,false,false,0);
printer_select_font($handle, $font);
printer_draw_text($handle, "test", 10, 10);
printer_delete_font($font);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);
```

`printer_end_doc` (unknown)

Close document

bool **printer_end_doc** (resource handle) \linebreak

Closes a new document in the printer spooler. The document is now ready for printing. For an example see `printer_start_doc()`. *handle* must be a valid handle to a printer.

`printer_end_page` (unknown)

Close active page

bool **printer_end_page** (resource handle) \linebreak

The function closes the active page in the active document. For an example see `printer_start_doc()`. *handle* must be a valid handle to a printer.

`printer_get_option` (unknown)

Retrieve printer configuration data

mixed **printer_get_option** (resource handle, string option) \linebreak

The function retrieves the configuration setting of *option*. *handle* must be a valid handle to a printer. Take a look at `printer_set_option()` for the settings that can be retrieved, additionally the following settings can be retrieved:

- `PRINTER_DEVICENAME` returns the devicename of the printer.
- `PRINTER_DRIVERVERSION` returns the printer driver version.

Příklad 1. `printer_get_option()` example

```
$handle = printer_open();
print printer_get_option($handle, PRINTER_DRIVERVERSION);
printer_close($handle);
```

printer_list (unknown)

Return an array of printers attached to the server

array **printer_list** (int *enumtype* [, string *name* [, int *level*]]) \linebreak

The function enumerates available printers and their capabilities. *level* sets the level of information request. Can be 1,2,4 or 5. *enumtype* must be one of the following predefined constants:

- `PRINTER_ENUM_LOCAL`: enumerates the locally installed printers.
- `PRINTER_ENUM_NAME`: enumerates the printer of *name*, can be a server, domain or print provider.
- `PRINTER_ENUM_SHARED`: this parameter can't be used alone, it has to be OR'ed with other parameters, i.e. `PRINTER_ENUM_LOCAL` to detect the locally shared printers.
- `PRINTER_ENUM_DEFAULT`: (Win9.x only) enumerates the default printer.
- `PRINTER_ENUM_CONNECTIONS`: (WinNT/2000 only) enumerates the printers to which the user has made connections.
- `PRINTER_ENUM_NETWORK`: (WinNT/2000 only) enumerates network printers in the computer's domain. Only valid if *level* is 1.
- `PRINTER_ENUM_REMOTE`: (WinNT/2000 only) enumerates network printers and print servers in the computer's domain. Only valid if *level* is 1.

Příklad 1. `printer_list()` example

```
/* detect locally shared printer */
var_dump( printer_list(PRINTER_ENUM_LOCAL | PRINTER_ENUM_SHARED) );
```

printer_logical_fontheight (unknown)

Get logical font height

int **printer_logical_fontheight** (resource handle, int height) \linebreak

The function calculates the logical font height of *height*. *handle* must be a valid handle to a printer.

Příklad 1. printer_logical_fontheight() example

```
$handle = printer_open();
print printer_logical_fontheight($handle, 72);
printer_close($handle);
```

printer_open (unknown)

Open connection to a printer

mixed **printer_open** ([string devicename]) \linebreak

This function tries to open a connection to the printer *devicename*, and returns a handle on success or FALSE on failure.

If no parameter was given it tries to open a connection to the default printer (if not specified in `php.ini` as `printer.default_printer`, `php` tries to detect it).

printer_open() also starts a device context.

Příklad 1. printer_open() example

```
$handle = printer_open("HP Deskjet 930c");
$handle = printer_open();
```

printer_select_brush (unknown)

Select a brush

void **printer_select_brush** (resource printer_handle, resource brush_handle) \linebreak

The function selects a brush as the active drawing object of the actual device context. A brush is used to fill shapes. If you draw an rectangle the brush is used to draw the shapes, while the pen is used to draw the border. If you haven't selected a brush before drawing shapes, the shape won't be filled. *printer_handle* must be a valid handle to a printer. *brush_handle* must be a valid handle to a brush.

Příklad 1. printer_select_brush() example

```

$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$pen = printer_create_pen(PRINTER_PEN_SOLID, 2, "000000");
printer_select_pen($handle, $pen);
$brush = printer_create_brush(PRINTER_BRUSH_CUSTOM, "c:\\brush.bmp");
printer_select_brush($handle, $brush);

printer_draw_rectangle($handle, 1,1,500,500);

printer_delete_brush($brush);

$brush = printer_create_brush(PRINTER_BRUSH_SOLID, "000000");
printer_select_brush($handle, $brush);
printer_draw_rectangle($handle, 1,501,500,1001);
printer_delete_brush($brush);

printer_delete_pen($pen);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);

```

printer_select_font (unknown)

Select a font

void **printer_select_font** (resource printer_handle, resource font_handle) \linebreak

The function selects a font to draw text. *printer_handle* must be a valid handle to a printer. *font_handle* must be a valid handle to a font.

Příklad 1. printer_select_font() example

```

$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$font = printer_create_font("Arial", 148, 76, PRINTER_FW_MEDIUM, false, false, false, -
50);
printer_select_font($handle, $font);
printer_draw_text($handle, "PHP is simply cool", 40, 40);
printer_delete_font($font);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);

```

printer_select_pen (unknown)

Select a pen

```
void printer_select_pen ( resource printer_handle, resource pen_handle) \linebreak
```

The function selects a pen as the active drawing object of the actual device context. A pen is used to draw lines and curves. I.e. if you draw a single line the pen is used. If you draw an rectangle the pen is used to draw the borders, while the brush is used to fill the shape. If you haven't selected a pen before drawing shapes, the shape won't be outlined. *printer_handle* must be a valid handle to a printer. *pen_handle* must be a valid handle to a pen.

Příklad 1. printer_select_pen() example

```
$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

$pen = printer_create_pen(PRINTER_PEN_SOLID, 30, "2222FF");
printer_select_pen($handle, $pen);

printer_draw_line($handle, 1, 60, 500, 60);

printer_delete_pen($pen);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);
```

printer_set_option (unknown)

Configure the printer connection

```
bool printer_set_option ( resource handle, int option, mixed value) \linebreak
```

The function sets the following options for the current connection: *handle* must be a valid handle to a printer. For *option* can be one of the following constants:

- *PRINTER_COPIES*: sets how many copies should be printed, *value* must be an integer.
- *PRINTER_MODE*: specifies the type of data (text, raw or emf), *value* must be a string.
- *PRINTER_TITLE*: specifies the name of the document, *value* must be a string.
- *PRINTER_ORIENTATION*: specifies the orientation of the paper, *value* can be either *PRINTER_ORIENTATION_PORTRAIT* or *PRINTER_ORIENTATION_LANDSCAPE*

- *PRINTER_RESOLUTION_Y*: specifies the y-resolution in DPI, *value* must be an integer.
- *PRINTER_RESOLUTION_X*: specifies the x-resolution in DPI, *value* must be an integer.
- *PRINTER_PAPER_FORMAT*: specifies the predefined paper format, set *value* to *PRINTER_FORMAT_CUSTOM* if you want to specify a custom format with *PRINTER_PAPER_WIDTH* and *PRINTER_PAPER_LENGTH*. *value* can be one of the following constants.
 - *PRINTER_FORMAT_CUSTOM*: let's you specify a custom paper format.
 - *PRINTER_FORMAT_LETTER*: specifies standard letter format (8 1/2- by 11-inches).
 - *PRINTER_FORMAT_LEGAL*: specifies standard legal format (8 1/2- by 14-inches).
 - *PRINTER_FORMAT_A3*: specifies standard A3 format (297- by 420-millimeters).
 - *PRINTER_FORMAT_A4*: specifies standard A4 format (210- by 297-millimeters).
 - *PRINTER_FORMAT_A5*: specifies standard A5 format (148- by 210-millimeters).
 - *PRINTER_FORMAT_B4*: specifies standard B4 format (250- by 354-millimeters).
 - *PRINTER_FORMAT_B5*: specifies standard B5 format (182- by 257-millimeter).
 - *PRINTER_FORMAT_FOLIO*: specifies standard FOLIO format (8 1/2- by 13-inch).
- *PRINTER_PAPER_LENGTH*: if *PRINTER_PAPER_FORMAT* is set to *PRINTER_FORMAT_CUSTOM*, *PRINTER_PAPER_LENGTH* specifies a custom paper length in mm, *value* must be an integer.
- *PRINTER_PAPER_WIDTH*: if *PRINTER_PAPER_FORMAT* is set to *PRINTER_FORMAT_CUSTOM*, *PRINTER_PAPER_WIDTH* specifies a custom paper width in mm, *value* must be an integer.
- *PRINTER_SCALE*: specifies the factor by which the printed output is to be scaled. the page size is scaled from the physical page size by a factor of *scale*/100. for example if you set the scale to 50, the output would be half of it's original size. *value* must be an integer.
- *PRINTER_BACKGROUND_COLOR*: specifies the background color for the actual device context, *value* must be a string containing the rgb information in hex format i.e. "005533".
- *PRINTER_TEXT_COLOR*: specifies the text color for the actual device context, *value* must be a string containing the rgb information in hex format i.e. "005533".
- *PRINTER_TEXT_ALIGN*: specifies the text alignment for the actual device context, *value* can be combined through OR'ing the following constants:
 - *PRINTER_TA_BASELINE*: text will be aligned at the base line.
 - *PRINTER_TA_BOTTOM*: text will be aligned at the bottom.
 - *PRINTER_TA_TOP*: text will be aligned at the top.
 - *PRINTER_TA_CENTER*: text will be aligned at the center.
 - *PRINTER_TA_LEFT*: text will be aligned at the left.
 - *PRINTER_TA_RIGHT*: text will be aligned at the right.

Příklad 1. printer_set_option() example

```
$handle = printer_open();
printer_set_option($handle, PRINTER_SCALE, 75);
printer_set_option($handle, PRINTER_TEXT_ALIGN, PRINTER_TA_LEFT);
printer_close($handle);
```

printer_start_doc (unknown)

Start a new document

```
bool printer_start_doc ( resource handle [, string document]) \linebreak
```

The function creates a new document in the printer spooler. A document can contain multiple pages, it's used to schedule the print job in the spooler. *handle* must be a valid handle to a printer. The optional parameter *document* can be used to set an alternative document name.

Příklad 1. printer_start_doc() example

```
$handle = printer_open();
printer_start_doc($handle, "My Document");
printer_start_page($handle);

printer_end_page($handle);
printer_end_doc($handle);
printer_close($handle);
```

printer_start_page (unknown)

Start a new page

```
bool printer_start_page ( resource handle) \linebreak
```

The function creates a new page in the active document. For an example see `printer_start_doc()`. *handle* must be a valid handle to a printer.

printer_write (unknown)

Write data to the printer

```
bool printer_write ( resource handle, string content) \linebreak
```

Writes *content* directly to the printer, and returns TRUE on success or FALSE if it failed.
handle must be a valid handle to a printer.

Příklad 1. printer_write() example

```
$handle = printer_open();  
printer_write($handle, "Text to print");  
printer_close($handle);
```

LXXXIII. Pspell Functions

These functions allow you to check the spelling of a word and offer suggestions.

You need the aspell and pspell libraries, available from <http://aspell.sourceforge.net/> and <http://pspell.sourceforge.net/> respectively, and add the `--with-pspell[=dir]` option when compiling php.

pspell_add_to_personal (PHP 4 >= 4.0.2)

Add the word to a personal wordlist

int **pspell_add_to_personal** (int dictionary_link, string word) \linebreak

pspell_add_to_personal() adds a word to the personal wordlist. If you used **pspell_new_config()** with **pspell_config_personal()** to open the dictionary, you can save the wordlist later with **pspell_save_wordlist()**. Please, note that this function will not work unless you have pspell .11.2 and aspell .32.5 or later.

Příklad 1. pspell_add_to_personal()

```
$pspell_config = pspell_config_create ("en");
pspell_config_personal ($pspell_config, "/var/dictionaries/custom.pws");
$pspell_link = pspell_new_config ($pspell_config);

pspell_add_to_personal ($pspell_link, "Vlad");
pspell_save_wordlist ($pspell_link);
```

pspell_add_to_session (PHP 4 >= 4.0.2)

Add the word to the wordlist in the current session

int **pspell_add_to_session** (int dictionary_link, string word) \linebreak

pspell_add_to_session() adds a word to the wordlist associated with the current session. It is very similar to **pspell_add_to_personal**()

pspell_check (PHP 4 >= 4.0.2)

Check a word

bool **pspell_check** (int dictionary_link, string word) \linebreak

pspell_check() checks the spelling of a word and returns TRUE if the spelling is correct, FALSE if not.

Příklad 1. pspell_check()

```
$pspell_link = pspell_new ("en");

if (pspell_check ($pspell_link, "testt")) {
    echo "This is a valid spelling";
}
```

```

} else {
    echo "Sorry, wrong spelling";
}

```

pspell_clear_session (PHP 4 >= 4.0.2)

Clear the current session

int **pspell_clear_session** (int dictionary_link) \linebreak

pspell_clear_session() clears the current session. The current wordlist becomes blank, and, for example, if you try to save it with **pspell_save_wordlist()**, nothing happens.

Příklad 1. pspell_add_to_personal()

```

$pspell_config = pspell_config_create ("en");
pspell_config_personal ($pspell_config, "/var/dictionaries/custom.pws");
$pspell_link = pspell_new_config ($pspell_config);

pspell_add_to_personal ($pspell_link, "Vlad");
pspell_clear_session ($pspell_link);
pspell_save_wordlist ($pspell_link);    //"Vlad" will not be saved

```

pspell_config_create (PHP 4 >= 4.0.2)

Create a config used to open a dictionary

int **pspell_config_create** (string language [, string spelling [, string jargon [, string encoding]]]) \linebreak

pspell_config_create() has a very similar syntax to **pspell_new()**. In fact, using **pspell_config_create()** immediately followed by **pspell_new_config()** will produce the exact same result. However, after creating a new config, you can also use **pspell_config_***() functions before calling **pspell_new_config()** to take advantage of some advanced functionality.

The language parameter is the language code which consists of the two letter ISO 639 language code and an optional two letter ISO 3166 country code after a dash or underscore.

The spelling parameter is the requested spelling for languages with more than one spelling such as English. Known values are 'american', 'british', and 'canadian'.

The jargon parameter contains extra information to distinguish two different words lists that have the same language and spelling parameters.

The encoding parameter is the encoding that words are expected to be in. Valid values are 'utf-8', 'iso8859-*', 'koi8-r', 'viscii', 'cp1252', 'machine unsigned 16', 'machine unsigned 32'. This parameter is largely untested, so be careful when using.

The mode parameter is the mode in which spellchecker will work. There are several modes available:

- PSPELL_FAST - Fast mode (least number of suggestions)
- PSPELL_NORMAL - Normal mode (more suggestions)
- PSPELL_BAD_SPELLERS - Slow mode (a lot of suggestions)

For more information and examples, check out inline manual pspell website:<http://pspell.sourceforge.net/>.

Příklad 1. pspell_config_create()

```
$pspell_config = pspell_config_create ("en");
pspell_config_personal ($pspell_config, "/var/dictionaries/custom.pws");
pspell_config_repl ($pspell_config, "/var/dictionaries/custom.repl");
$pspell_link = pspell_new_personal ($pspell_config, "en");
```

pspell_config_ignore (PHP 4 >= 4.0.2)

Ignore words less than N characters long

int **pspell_config_ignore** (int dictionary_link, int n) \linebreak

pspell_config_ignore() should be used on a config before calling pspell_new_config(). This function allows short words to be skipped by the spellchecker. Words less than n characters will be skipped.

Příklad 1. pspell_config_ignore()

```
$pspell_config = pspell_config_create ("en");
pspell_config_ignore($pspell_config, 5);
$pspell_link = pspell_new_config($pspell_config);
pspell_check($pspell_link, "abcd"); //will not result in an error
```

pspell_config_mode (PHP 4 >= 4.0.2)

Change the mode number of suggestions returned

```
int pspell_config_mode ( int dictionary_link, int mode) \linebreak
```

pspell_config_mode() should be used on a config before calling **pspell_new_config()**. This function determines how many suggestions will be returned by **pspell_suggest()**.

The mode parameter is the mode in which spellchecker will work. There are several modes available:

- **PSPELL_FAST** - Fast mode (least number of suggestions)
- **PSPELL_NORMAL** - Normal mode (more suggestions)
- **PSPELL_BAD_SPELLERS** - Slow mode (a lot of suggestions)

Příklad 1. **pspell_config_mode()**

```
$pspell_config = pspell_config_create ("en");
pspell_config_mode($pspell_config, PSPELL_FAST);
$pspell_link = pspell_new_config($pspell_config);
pspell_check($pspell_link, "thecat");
```

pspell_config_personal (PHP 4 >= 4.0.2)

Set a file that contains personal wordlist

```
int pspell_config_personal ( int dictionary_link, string file) \linebreak
```

pspell_config_personal() should be used on a config before calling **pspell_new_config()**. The personal wordlist will be loaded and used in addition to the standard one after you call **pspell_new_config()**. If the file does not exist, it will be created. The file is also the file where **pspell_save_wordlist()** will save personal wordlist to. The file should be writable by whoever php runs as (e.g. nobody). Please, note that this function will not work unless you have pspell .11.2 and aspell .32.5 or later.

Příklad 1. **pspell_config_personal()**

```
$pspell_config = pspell_config_create ("en");
pspell_config_personal ($pspell_config, "/var/dictionaries/custom.pws");
$pspell_link = pspell_new_config ($pspell_config);
pspell_check ($pspell_link, "thecat");
```

pspell_config_repl (PHP 4 >= 4.0.2)

Set a file that contains replacement pairs

```
int pspell_config_repl ( int dictionary_link, string file) \linebreak
```

pspell_config_repl() should be used on a config before calling **pspell_new_config()**. The replacement pairs improve the quality of the spellchecker. When a word is misspelled, and a proper suggestion was not found in the list, **pspell_store_replacement()** can be used to store a replacement pair and then **pspell_save_wordlist()** to save the wordlist along with the replacement pairs. The file should be writable by whoever php runs as (e.g. nobody). Please, note that this function will not work unless you have pspell .11.2 and aspell .32.5 or later.

Příklad 1. pspell_config_repl()

```
$pspell_config = pspell_config_create ("en");
pspell_config_personal ($pspell_config, "/var/dictionaries/custom.pws");
pspell_config_repl ($pspell_config, "/var/dictionaries/custom.repl");
$pspell_link = pspell_new_config ($pspell_config);
pspell_check ($pspell_link, "thecat");
```

pspell_config_runtogether (PHP 4 >= 4.0.2)

Consider run-together words as valid compounds

```
int pspell_config_runtogether ( int dictionary_link, bool flag) \linebreak
```

pspell_config_runtogether() should be used on a config before calling **pspell_new_config()**. This function determines whether run-together words will be treated as legal compounds. That is, "thecat" will be a legal compound, although there should be a space between the two words. Changing this setting only affects the results returned by **pspell_check()**; **pspell_suggest()** will still return suggestions.

Příklad 1. pspell_config_runtogether()

```
$pspell_config = pspell_config_create ("en");
pspell_config_runtogether ($pspell_config, true);
$pspell_link = pspell_new_config ($pspell_config);
pspell_check ($pspell_link, "thecat");
```

pspell_config_save_repl (PHP 4 >= 4.0.2)

Determine whether to save a replacement pairs list along with the wordlist

```
int pspell_config_save_repl ( int dictionary_link, bool flag) \linebreak
```

pspell_config_save_repl() should be used on a config before calling **pspell_new_config()**. It determines whether **pspell_save_wordlist()** will save the replacement pairs along with the wordlist. Usually there is no need to use this function because if **pspell_config_repl()** is used, the replacement pairs will be saved by **pspell_save_wordlist()** anyway, and if it is not, the replacement pairs will not be saved. Please, note that this function will not work unless you have pspell .11.2 and aspell .32.5 or later.

pspell_new (PHP 4 >= 4.0.2)

Load a new dictionary

```
int pspell_new ( string language [, string spelling [, string jargon [, string encoding [, int mode]]]]) \linebreak
```

pspell_new() opens up a new dictionary and returns the dictionary link identifier for use in other pspell functions.

The language parameter is the language code which consists of the two letter ISO 639 language code and an optional two letter ISO 3166 country code after a dash or underscore.

The spelling parameter is the requested spelling for languages with more than one spelling such as English. Known values are 'american', 'british', and 'canadian'.

The jargon parameter contains extra information to distinguish two different words lists that have the same language and spelling parameters.

The encoding parameter is the encoding that words are expected to be in. Valid values are 'utf-8', 'iso8859-*', 'koi8-r', 'viscii', 'cp1252', 'machine unsigned 16', 'machine unsigned 32'. This parameter is largely untested, so be careful when using.

The mode parameter is the mode in which spellchecker will work. There are several modes available:

- **PSPELL_FAST** - Fast mode (least number of suggestions)
- **PSPELL_NORMAL** - Normal mode (more suggestions)
- **PSPELL_BAD_SPELLERS** - Slow mode (a lot of suggestions)
- **PSPELL_RUN_TOGETHER** - Consider run-together words as legal compounds. That is, "thecat" will be a legal compound, although there should be a space between the two words. Changing this setting only affects the results returned by **pspell_check()**; **pspell_suggest()** will still return suggestions.

Mode is a bitmask constructed from different constants listed above. However, **PSPELL_FAST**, **PSPELL_NORMAL** and **PSPELL_BAD_SPELLERS** are mutually exclusive, so you should select only one of them.

For more information and examples, check out inline manual pspell
website:<http://pspell.sourceforge.net/>.

Příklad 1. pspell_new()

```
$pspell_link = pspell_new ( "en", "", "", "",  
                           ( PSpell_FAST | PSpell_RUN_TOGETHER ) );
```

pspell_new_config (PHP 4 >= 4.0.2)

Load a new dictionary with settings based on a given config

```
int pspell_new_config ( int config) \linebreak
```

pspell_new_config() opens up a new dictionary with settings specified in a config, created with with **pspell_config_create()** and modified with **pspell_config_***() functions. This method provides you with the most flexibility and has all the functionality provided by **pspell_new()** and **pspell_new_personal()**.

The config parameter is the one returned by **pspell_config_create()** when the config was created.

Příklad 1. pspell_new_config()

```
$pspell_config = pspell_config_create ( "en" );  
pspell_config_personal ( $pspell_config, "/var/dictionaries/custom.pws" );  
pspell_config_repl ( $pspell_config, "/var/dictionaries/custom.repl" );  
$pspell_link = pspell_new_config ( $pspell_config );
```

pspell_new_personal (PHP 4 >= 4.0.2)

Load a new dictionary with personal wordlist

```
int pspell_new_personal ( string personal, string language [, string spelling [, string jargon [, string encoding  
[, int mode]]]]) \linebreak
```

pspell_new_personal() opens up a new dictionary with a personal wordlist and returns the dictionary link identifier for use in other pspell functions. The wordlist can be modified and saved with **pspell_save_wordlist()**, if desired. However, the replacement pairs are not saved. In order to save replacement pairs, you should create a config using **pspell_config_create()**, set the personal

wordlist file with `pspell_config_personal()`, set the file for replacement pairs with `pspell_config_repl()`, and open a new dictionary with `pspell_new_config()`.

The `personal` parameter specifies the file where words added to the personal list will be stored. It should be an absolute filename beginning with `'/'` because otherwise it will be relative to `$HOME`, which is `"/root"` for most systems, and is probably not what you want.

The `language` parameter is the language code which consists of the two letter ISO 639 language code and an optional two letter ISO 3166 country code after a dash or underscore.

The `spelling` parameter is the requested spelling for languages with more than one spelling such as English. Known values are `'american'`, `'british'`, and `'canadian'`.

The `jargon` parameter contains extra information to distinguish two different words lists that have the same language and spelling parameters.

The `encoding` parameter is the encoding that words are expected to be in. Valid values are `'utf-8'`, `'iso8859-*'`, `'koi8-r'`, `'viscii'`, `'cp1252'`, `'machine unsigned 16'`, `'machine unsigned 32'`. This parameter is largely untested, so be careful when using.

The `mode` parameter is the mode in which spellchecker will work. There are several modes available:

- `PSpell_FAST` - Fast mode (least number of suggestions)
- `PSpell_NORMAL` - Normal mode (more suggestions)
- `PSpell_BAD_SPELLERS` - Slow mode (a lot of suggestions)
- `PSpell_RUN_TOGETHER` - Consider run-together words as legal compounds. That is, "thecat" will be a legal compound, although there should be a space between the two words. Changing this setting only affects the results returned by `pspell_check()`; `pspell_suggest()` will still return suggestions.

Mode is a bitmask constructed from different constants listed above. However, `PSpell_FAST`, `PSpell_NORMAL` and `PSpell_BAD_SPELLERS` are mutually exclusive, so you should select only one of them.

For more information and examples, check out inline manual `pspell` website: <http://pspell.sourceforge.net/>.

Příklad 1. `pspell_new_personal()`

```
$pspell_link = pspell_new_personal ( "/var/dictionaries/custom.pws",
                                     "en", "", "", "", PSpell_FAST|PSpell_RUN_TOGETHER );
```

pspell_save_wordlist (PHP 4 >= 4.0.2)

Save the personal wordlist to a file

```
int pspell_save_wordlist ( int dictionary_link ) \linebreak
```


pspell_save_wordlist() saves the personal wordlist from the current session. The dictionary has to be open with **pspell_new_personal()**, and the location of files to be saved specified with **pspell_config_personal()** and (optionally) **pspell_config_repl()**. Please, note that this function will not work unless you have pspell .11.2 and aspell .32.5 or later.

Příklad 1. **pspell_add_to_personal()**

```
$pspell_config = pspell_config_create ("en");
pspell_config_personal ($pspell_config, "/tmp/dicts/newdict");
$pspell_link = pspell_new_config ($pspell_config);

pspell_add_to_personal ($pspell_link, "Vlad");
pspell_save_wordlist ($pspell_link);
```

pspell_store_replacement (PHP 4 >= 4.0.2)

Store a replacement pair for a word

int **pspell_store_replacement** (int dictionary_link, string misspelled, string correct) \linebreak

pspell_store_replacement() stores a replacement pair for a word, so that replacement can be returned by **pspell_suggest()** later. In order to be able to take advantage of this function, you have to use **pspell_new_personal()** to open the dictionary. In order to permanently save the replacement pair, you have to use **pspell_config_personal()** and **pspell_config_repl()** to set the path where to save your custom wordlists, and then use **pspell_save_wordlist()** for the changes to be written to disk. Please, note that this function will not work unless you have pspell .11.2 and aspell .32.5 or later.

Příklad 1. **pspell_store_replacement()**

```
$pspell_config = pspell_config_create ("en");
pspell_config_personal ($pspell_config, "/var/dictionaries/custom.pws");
pspell_config_repl ($pspell_config, "/var/dictionaries/custom.repl");
$pspell_link = pspell_new_config ($pspell_config);

pspell_store_replacement ($pspell_link, $misspelled, $correct);
pspell_save_wordlist ($pspell_link);
```

pspell_suggest (PHP 4 >= 4.0.2)

Suggest spellings of a word

array **pspell_suggest** (int dictionary_link, string word) \linebreak

pspell_suggest() returns an array of possible spellings for the given word.

Příklad 1. pspell_suggest()

```
$pspell_link = pspell_new ("en");

if (!pspell_check ($pspell_link, "testt")) {
    $suggestions = pspell_suggest ($pspell_link, "testt");

    foreach ($suggestions as $suggestion) {
        echo "Possible spelling: $suggestion<br>";
    }
}
```

LXXXIV. GNU Readline

`readline()` funkce implementují rozhraní ke GNU Readline knihovně. Tyto funkce poskytují editovatelné příkazové řádky. Příkladem může být způsob, jakým vám Bash umožňuje vkládat znaky nebo listovat historií příkazů pomocí kláves pro pohyb kurzoru. Z interaktivní povahy této knihovny vyplývá, že není příliš užitečná pro psaní webových aplikací, ale může být užitečná při psaní skriptů, které se mají spouštět z příkazové řádky.

Domovskou stránkou GNU Readline projektu je <http://cnswww.cns.cwru.edu/~chet/readline/rltop.html>. Udržuje jej Chet Ramey, který je také autorem Bashe.

readline (PHP 4 >= 4.0.0)

Přečíst řádek

string **readline** ([string prompt]) \linebreak

Tato funkce vrátí jeden řádek od uživatele. Můžete specifikovat řetězec, který se má uživateli zobrazit jako výzva. Z vráceného řádku je odstraněna sekvence konce řádku. Do historie tento řádek musíte přidat sami pomocí `readline_add_history()`.

Příklad 1. readline()

```
//ziska 3 prikazy uzivatele
for ($i=0; $i < 3; $i++) {
    $line = readline ("Command: ");
    readline_add_history ($line);
}

//vypise historii
print_r (readline_list_history());

//vypise promenne
print_r (readline_info());
```

readline_add_history (PHP 4 >= 4.0.0)

Přidat řádek do historie

void **readline_add_history** (string line) \linebreak

Tato funkce přidá řádek do historie příkazové řádky.

readline_clear_history (PHP 4 >= 4.0.0)

Smazat historii

boolean **readline_clear_history** (void) \linebreak

Tato funkce smaže celou historii příkazové řádky.

readline_completion_function (PHP 4 >= 4.0.0)

Zaregistrovat dokončující funkci

boolean **readline_completion_function** (string line) \linebreak

Tato funkce zaregistruje dokončující funkci. Musíte zadat název existující funkce, která přijímá částečný příkaz a vrací pole možných protějšků. Toto je stejná funkcionality jakou dostanete, pokud v Bashi zmáčknete klávesu tab.

readline_info (PHP 4 >= 4.0.0)

Zjistit/nastavit různé interní proměnné readline

mixed **readline_info** ([string varname [, string newvalue]]) \linebreak

Při volání bez argumentů tato funkce vrátí pole hodnot pro všechna nastavení, která readline používá. Prvky jsou indexovány podle následujících hodnot: done, end, erase_empty_line, library_version, line_buffer, mark, pending_input, point, prompt, readline_name a terminal_name.

Při volání s jedním argumentem vrátí hodnotu tohoto nastavení. Při volání se dvěma argumenty se nastavení zmení na danou hodnotu.

readline_list_history (PHP 4 >= 4.0.0)

Vypsát historii

array **readline_list_history** (void) \linebreak

Tato funkce vrátí pole celé historie příkazové řádky. Prvky jsou indexovány integery, počínaje nulou.

readline_read_history (PHP 4 >= 4.0.0)

Vrátit historii

boolean **readline_read_history** (string filename) \linebreak

Tato funkce přečte historii příkazové řádky ze souboru.

readline_write_history (PHP 4 >= 4.0.0)

Zapsat historii

boolean **readline_write_history** (string filename) \linebreak

Tato funkce zapíše historii příkazové řádky do souboru.

LXXXV. GNU Recode funkce

Tento modul obsahuje rozhraní ke GNU Recode knihovně, verze 3.5. Pokud chcete používat funkce definované v tomto modulu, musíte zkompilovat váš PHP interpreter s `--with-recode`. K tomu potřebujete mít na svém systému nainstalovanou GNU Recode 3.5 nebo vyšší.

GNU Recode knihovna konvertuje soubory mezi různými znakovými sadami a kódováními. Když nelze dosáhnout přesné konverze, může se uchýlit k aproximacím. Tato knihovna rozeznává nebo produkuje téměř 150 různých znakových sad, a je schopná konvertovat soubory mezi téměř libovolným párem. Podporuje většinu znakových sad z RFC 1345.

recode (PHP 4 >= 4.0.0)

Překóduje řetězec podle požadavku

string **recode_string** (string request, string string) \linebreak

Poznámka: Toto je alias k `recode_string()`. Byl přidán v PHP 4.

recode_file (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Překóduje soubor na soubor podle požadavku

boolean **recode_file** (string request, resource input, resource output) \linebreak

Překóduje soubor odkazovaný deskriptorem *input* do souboru odkazovaném deskriptorem *output* podle požadavku *request*. Pokud se nepodařilo požadavek provést, vrací `FALSE`, jinak `TRUE`.

Tato funkce v současnosti nezpracovává deskriptory odkazující na vzdálené soubory (URL). Oba deskriptory musí ukazovat na místní soubory.

Příklad 1. Základní příklad `recode_file()`

```
$input = fopen ('input.txt', 'r');
$output = fopen ('output.txt', 'w');
recode_file ("us..flat", $input, $output);
```

recode_string (PHP 3>= 3.0.13, PHP 4 >= 4.0.0)

Překóduje řetězec podle požadavku

string **recode_string** (string request, string string) \linebreak

Překóduje řetězec *string* podle požadavku *request*. Vrací překódovaný řetězec nebo `FALSE`, pokud nebylo možné provést požadavek na překódování.

Jednoduchý požadavek na překódování může být "lat1..iso646-de". Detailní instrukce k požadavkům viz GNU Recode dokumentaci u vaší instalace.

Příklad 1. Základní `recode_string()` příklad:

```
print recode_string ("us..flat", "Následující znak má diakritické znaménko: &acute;");
```

LXXXVI. Regular Expression Functions (Perl-Compatible)

The syntax for patterns used in these functions closely resembles Perl. The expression should be enclosed in the delimiters, a forward slash (/), for example. Any character can be used for delimiter as long as it's not alphanumeric or backslash (\). If the delimiter character has to be used in the expression itself, it needs to be escaped by backslash. Since PHP 4.0.4, you can also use Perl-style (), {}, [], and <> matching delimiters.

The ending delimiter may be followed by various modifiers that affect the matching. See Pattern Modifiers.

PHP also supports regular expressions using a POSIX-extended syntax using the POSIX-extended regex functions..

Requirements

Regular expression support is provided by the PCRE library package, which is open source software, written by Philip Hazel, and copyright by the University of Cambridge, England. It is available at <ftp://ftp.csx.cam.ac.uk/pub/software/programming/pcre/>.

Installation

Beginning with PHP 4.2.0 this function are enabled by default. For older versions you have to configure and compile PHP with `--with-pcre-regex[=DIR]` in order to use these functions. You can disable the pcre functions with `--without-pcre-regex`.

Runtime Configuration

Toto rozšíření nemá definováno žádné konfigurační direktivy.

Resource types

Toto rozšíření nemá definován žádný typ prostředku (resource).

Predefined constants

PREG_PATTERN_ORDER PREG_SET_ORDER PREG_SPLIT_NO_EMPTY

PREG_SPLIT_DELIM_CAPTURE

Examples

Příklad 1. Examples of valid patterns

- `/<\/w+>/`
- `|(\d{3})-\d+|Sm`
- `/^(?i)php[34]/`
- `{^\s+(\s+)?$}`

Příklad 2. Examples of invalid patterns

- `/href='(.*)'` - missing ending delimiter
- `^w+\s*\w+/\J` - unknown modifier 'J'
- `1-\d3-\d3-\d4|` - missing starting delimiter

Pattern Modifiers (unknown)

Describes possible modifiers in regex patterns

The current possible PCRE modifiers are listed below. The names in parentheses refer to internal PCRE names for these modifiers.

i (PCRE_CASELESS)

If this modifier is set, letters in the pattern match both upper and lower case letters.

m (PCRE_MULTILINE)

By default, PCRE treats the subject string as consisting of a single "line" of characters (even if it actually contains several newlines). The "start of line" metacharacter (^) matches only at the start of the string, while the "end of line" metacharacter (\$) matches only at the end of the string, or before a terminating newline (unless *D* modifier is set). This is the same as Perl.

When this modifier is set, the "start of line" and "end of line" constructs match immediately following or immediately before any newline in the subject string, respectively, as well as at the very start and end. This is equivalent to Perl's /m modifier. If there are no "\n" characters in a subject string, or no occurrences of ^ or \$ in a pattern, setting this modifier has no effect.

s (PCRE_DOTALL)

If this modifier is set, a dot metacharacter in the pattern matches all characters, including newlines. Without it, newlines are excluded. This modifier is equivalent to Perl's /s modifier. A negative class such as [^a] always matches a newline character, independent of the setting of this modifier.

x (PCRE_EXTENDED)

If this modifier is set, whitespace data characters in the pattern are totally ignored except when escaped or inside a character class, and characters between an unescaped # outside a character class and the next newline character, inclusive, are also ignored. This is equivalent to Perl's /x modifier, and makes it possible to include comments inside complicated patterns. Note, however, that this applies only to data characters. Whitespace characters may never appear within special character sequences in a pattern, for example within the sequence (? (which introduces a conditional subpattern.

e

If this modifier is set, preg_replace() does normal substitution of backreferences in the replacement string, evaluates it as PHP code, and uses the result for replacing the search string.

Only preg_replace() uses this modifier; it is ignored by other PCRE functions.

A (PCRE_ANCHORED)

If this modifier is set, the pattern is forced to be "anchored", that is, it is constrained to match only at the start of the string which is being searched (the "subject string"). This effect can also be achieved by appropriate constructs in the pattern itself, which is the only way to do it in Perl.

D (PCRE_DOLLAR_ENDONLY)

If this modifier is set, a dollar metacharacter in the pattern matches only at the end of the subject string. Without this modifier, a dollar also matches immediately before the final character if it is a newline (but not before any other newlines). This modifier is ignored if *m* modifier is set. There is no equivalent to this modifier in Perl.

S

When a pattern is going to be used several times, it is worth spending more time analyzing it in order to speed up the time taken for matching. If this modifier is set, then this extra analysis is performed. At present, studying a pattern is useful only for non-anchored patterns that do not have a single fixed starting character.

U (PCRE_UNGREEDY)

This modifier inverts the "greediness" of the quantifiers so that they are not greedy by default, but become greedy if followed by "?". It is not compatible with Perl. It can also be set by a (?U) modifier setting within the pattern.

X (PCRE_EXTRA)

This modifier turns on additional functionality of PCRE that is incompatible with Perl. Any backslash in a pattern that is followed by a letter that has no special meaning causes an error, thus reserving these combinations for future expansion. By default, as in Perl, a backslash followed by a letter with no special meaning is treated as a literal. There are at present no other features controlled by this modifier.

u (PCRE_UTF8)

This modifier turns on additional functionality of PCRE that is incompatible with Perl. Pattern strings are treated as UTF-8. This modifier is available from PHP 4.1.0 or greater.

Pattern Syntax (unknown)

Describes PCRE regex syntax

The PCRE library is a set of functions that implement regular expression pattern matching using the same syntax and semantics as Perl 5, with just a few differences (see below). The current implementation corresponds to Perl 5.005.

The differences described here are with respect to Perl 5.005.

1. By default, a whitespace character is any character that the C library function `isspace()` recognizes, though it is possible to compile PCRE with alternative character type tables. Normally `isspace()` matches space, formfeed, newline, carriage return, horizontal tab, and vertical tab. Perl 5 no longer includes vertical tab in its set of whitespace characters. The `\v` escape that was in the Perl documentation for a long time was never in fact recognized. However, the character itself was treated as whitespace at least up to 5.002. In 5.004 and 5.005 it does not match `\s`.
2. PCRE does not allow repeat quantifiers on lookahead assertions. Perl permits them, but they do not mean what you might think. For example, `(?!a){3}` does not assert that the next three characters are not "a". It just asserts that the next character is not "a" three times.
3. Capturing subpatterns that occur inside negative lookahead assertions are counted, but their entries in the offsets vector are never set. Perl sets its numerical variables from any such patterns that are matched before the assertion fails to match something (thereby succeeding), but only if the negative lookahead assertion contains just one branch.

4. Though binary zero characters are supported in the subject string, they are not allowed in a pattern string because it is passed as a normal C string, terminated by zero. The escape sequence `"\0"` can be used in the pattern to represent a binary zero.
5. The following Perl escape sequences are not supported: `\l`, `\u`, `\L`, `\U`, `\E`, `\Q`. In fact these are implemented by Perl's general string-handling and are not part of its pattern matching engine.
6. The Perl `\G` assertion is not supported as it is not relevant to single pattern matches.
7. Fairly obviously, PCRE does not support the `(?{code})` construction.
8. There are at the time of writing some oddities in Perl 5.005_02 concerned with the settings of captured strings when part of a pattern is repeated. For example, matching "aba" against the pattern `/^a(b)?+$/` sets `$2` to the value "b", but matching "aabbaa" against `/^aa(bb)?+$/` leaves `$2` unset. However, if the pattern is changed to `/^aa(b(b))?+$/` then `$2` (and `$3`) get set. In Perl 5.004 `$2` is set in both cases, and that is also TRUE of PCRE. If in the future Perl changes to a consistent state that is different, PCRE may change to follow.
9. Another as yet unresolved discrepancy is that in Perl 5.005_02 the pattern `/^a(?:1a|b)+$/` matches the string "a", whereas in PCRE it does not. However, in both Perl and PCRE `/^a?a/` matched against "a" leaves `$1` unset.
10. PCRE provides some extensions to the Perl regular expression facilities:
 - a. Although lookbehind assertions must match fixed length strings, each alternative branch of a lookbehind assertion can match a different length of string. Perl 5.005 requires them all to have the same length.
 - b. If `PCRE_DOLLAR_ENDONLY` is set and `PCRE_MULTILINE` is not set, the `$` meta-character matches only at the very end of the string.
 - c. If `PCRE_EXTRA` is set, a backslash followed by a letter with no special meaning is faulted.
 - d. If `PCRE_UNGREEDY` is set, the greediness of the repetition quantifiers is inverted, that is, by default they are not greedy, but if followed by a question mark they are.

Introduction

The syntax and semantics of the regular expressions supported by PCRE are described below. Regular expressions are also described in the Perl documentation and in a number of other books, some of which have copious examples. Jeffrey Friedl's "Mastering Regular Expressions", published by O'Reilly (ISBN 1-56592-257-3), covers them in great detail. The description here is intended as reference documentation. A regular expression is a pattern that is matched against a subject string from left to right. Most characters stand for themselves in a pattern, and match the corresponding characters in the subject. As a trivial example, the pattern `The quick brown fox` matches a portion of a subject string that is identical to itself.

Meta-characters

The power of regular expressions comes from the ability to include alternatives and repetitions in the pattern. These are encoded in the pattern by the use of *meta-characters*, which do not stand for themselves but instead are interpreted in some special way.

There are two different sets of meta-characters: those that are recognized anywhere in the pattern except within square brackets, and those that are recognized in square brackets. Outside square brackets, the meta-characters are as follows:

<code>\</code>	general escape character with several uses
<code>^</code>	assert start of subject (or line, in multiline mode)
<code>\$</code>	assert end of subject (or line, in multiline mode)
<code>.</code>	match any character except newline (by default)
<code>[</code>	start character class definition
<code>]</code>	end character class definition
<code>/</code>	start of alternative branch
<code>(</code>	start subpattern
<code>)</code>	end subpattern
<code>?</code>	extends the meaning of <code>(</code> , also 0 or 1 quantifier, also quantifier minimizer
<code>*</code>	0 or more quantifier
<code>+</code>	1 or more quantifier
<code>{</code>	start min/max quantifier
<code>}</code>	end min/max quantifier

Part of a pattern that is in square brackets is called a "character class". In a character class the only meta-characters are:

<code>\</code>	general escape character
<code>^</code>	negate the class, but only if the first character
<code>-</code>	indicates character range
<code>/</code>	terminates the character class

The following sections describe the use of each of the meta-characters.

backslash

The backslash character has several uses. Firstly, if it is followed by a non-alphameric character, it takes away any special meaning that character may have. This use of backslash as an escape character applies both inside and outside character classes.

For example, if you want to match a "*" character, you write "*" in the pattern. This applies whether or not the following character would otherwise be interpreted as a meta-character, so it is always safe to precede a non-alphameric with "\" to specify that it stands for itself. In particular, if you want to match a backslash, you write "\\".

If a pattern is compiled with the PCRE_EXTENDED option, whitespace in the pattern (other than in a character class) and characters between a "#" outside a character class and the next newline character are ignored. An escaping backslash can be used to include a whitespace or "#" character as part of the pattern.

A second use of backslash provides a way of encoding non-printing characters in patterns in a visible manner. There is no restriction on the appearance of non-printing characters, apart from the binary zero that terminates a pattern, but when a pattern is being prepared by text editing, it is usually easier to use one of the following escape sequences than the binary character it represents:

<code>\a</code>	alarm, that is, the BEL character (hex 07)
<code>\cx</code>	"control-x", where x is any character
<code>\e</code>	escape (hex 1B)
<code>\f</code>	formfeed (hex 0C)
<code>\n</code>	newline (hex 0A)

<code>\r</code>	carriage return (hex 0D)
<code>\t</code>	tab (hex 09)
<code>\xhh</code>	character with hex code hh
<code>\ddd</code>	character with octal code ddd, or backreference

The precise effect of "`\cx`" is as follows: if "`x`" is a lower case letter, it is converted to upper case. Then bit 6 of the character (hex 40) is inverted. Thus "`\cz`" becomes hex 1A, but "`\c{`" becomes hex 3B, while "`\c;`" becomes hex 7B.

After "`\x`", up to two hexadecimal digits are read (letters can be in upper or lower case).

After "`\0`" up to two further octal digits are read. In both cases, if there are fewer than two digits, just those that are present are used. Thus the sequence "`\0\x\07`" specifies two binary zeros followed by a BEL character. Make sure you supply two digits after the initial zero if the character that follows is itself an octal digit.

The handling of a backslash followed by a digit other than 0 is complicated. Outside a character class, PCRE reads it and any following digits as a decimal number. If the number is less than 10, or if there have been at least that many previous capturing left parentheses in the expression, the entire sequence is taken as a *back reference*. A description of how this works is given later, following the discussion of parenthesized subpatterns.

Inside a character class, or if the decimal number is greater than 9 and there have not been that many capturing subpatterns, PCRE re-reads up to three octal digits following the backslash, and generates a single byte from the least significant 8 bits of the value. Any subsequent digits stand for themselves. For example:

<code>\040</code>	is another way of writing a space
<code>\40</code>	is the same, provided there are fewer than 40 previous capturing subpatterns
<code>\7</code>	is always a back reference
<code>\11</code>	might be a back reference, or another way of writing a tab
<code>\011</code>	is always a tab
<code>\0113</code>	is a tab followed by the character "3"

`\113`

is the character with octal code 113 (since there can be no more than 99 back references)

`\377`

is a byte consisting entirely of 1 bits

`\81`

is either a back reference, or a binary zero followed by the two characters "8" and "1"

Note that octal values of 100 or greater must not be introduced by a leading zero, because no more than three octal digits are ever read.

All the sequences that define a single byte value can be used both inside and outside character classes. In addition, inside a character class, the sequence `"\b"` is interpreted as the backspace character (hex 08). Outside a character class it has a different meaning (see below).

The third use of backslash is for specifying generic character types:

`\d`

any decimal digit

`\D`

any character that is not a decimal digit

`\s`

any whitespace character

`\S`

any character that is not a whitespace character

`\w`

any "word" character

`\W`

any "non-word" character

Each pair of escape sequences partitions the complete set of characters into two disjoint sets. Any given character matches one, and only one, of each pair.

A "word" character is any letter or digit or the underscore character, that is, any character which can be part of a Perl `"word"`. The definition of letters and digits is controlled by PCRE's character tables, and may vary if locale-specific matching is taking place (see "Locale support" above). For example, in the "fr" (French) locale, some character codes greater than 128 are used for accented letters, and these are matched by `\w`.

These character type sequences can appear both inside and outside character classes. They each match one character of the appropriate type. If the current matching point is at the end of the subject string, all of them fail, since there is no character to match.

The fourth use of backslash is for certain simple assertions. An assertion specifies a condition that has to be met at a particular point in a match, without consuming any characters from the subject

string. The use of subpatterns for more complicated assertions is described below. The backslashed assertions are

<code>\b</code>	word boundary
<code>\B</code>	not a word boundary
<code>\A</code>	start of subject (independent of multiline mode)
<code>\Z</code>	end of subject or newline at end (independent of multiline mode)
<code>\z</code>	end of subject (independent of multiline mode)

These assertions may not appear in character classes (but note that "`\b`" has a different meaning, namely the backspace character, inside a character class).

A word boundary is a position in the subject string where the current character and the previous character do not both match `\w` or `\W` (i.e. one matches `\w` and the other matches `\W`), or the start or end of the string if the first or last character matches `\w`, respectively.

The `\A`, `\Z`, and `\z` assertions differ from the traditional circumflex and dollar (described below) in that they only ever match at the very start and end of the subject string, whatever options are set. They are not affected by the `PCRE_NOTBOL` or `PCRE_NOTEOL` options. The difference between `\Z` and `\z` is that `\Z` matches before a newline that is the last character of the string as well as at the end of the string, whereas `\z` matches only at the end.

Circumflex and dollar

Outside a character class, in the default matching mode, the circumflex character is an assertion which is true only if the current matching point is at the start of the subject string. Inside a character class, circumflex has an entirely different meaning (see below).

Circumflex need not be the first character of the pattern if a number of alternatives are involved, but it should be the first thing in each alternative in which it appears if the pattern is ever to match that branch. If all possible alternatives start with a circumflex, that is, if the pattern is constrained to match only at the start of the subject, it is said to be an "anchored" pattern. (There are also other constructs that can cause a pattern to be anchored.)

A dollar character is an assertion which is `TRUE` only if the current matching point is at the end of the subject string,

or immediately before a newline character that is the last character in the string (by default). Dollar need not be the last character of the pattern if a number of alternatives are involved, but it should be the last item in any branch in which it appears. Dollar has no special meaning in a character class.

The meaning of dollar can be changed so that it matches only at the very end of the string, by setting the `PCRE_DOLLAR_ENDONLY` option at compile or matching time. This does not affect the `\Z` assertion.

The meanings of the circumflex and dollar characters are changed if the `PCRE_MULTILINE` option is set. When this is the case, they match immediately after and immediately before an internal `"\n"` character, respectively, in addition to matching at the start and end of the subject string. For example, the pattern `/^abc$/` matches the subject string `"def\nabc"` in multiline mode, but not otherwise. Consequently, patterns that are anchored in single line mode because all branches start with `"^"` are not anchored in multiline mode. The `PCRE_DOLLAR_ENDONLY` option is ignored if `PCRE_MULTILINE` is set.

Note that the sequences `\A`, `\Z`, and `\z` can be used to match the start and end of the subject in both modes, and if all branches of a pattern start with `\A` it is always anchored, whether `PCRE_MULTILINE` is set or not.

FULL STOP

Outside a character class, a dot in the pattern matches any one character in the subject, including a non-printing character, but not (by default) newline. If the `PCRE_DOTALL` option is set, then dots match newlines as well. The handling of dot is entirely independent of the handling of circumflex and dollar, the only relationship being that they both involve newline characters. Dot has no special meaning in a character class.

Square brackets

An opening square bracket introduces a character class, terminated by a closing square bracket. A closing square bracket on its own is not special. If a closing square bracket is required as a member of the class, it should be the first data character in the class (after an initial cir-

cumflex, if present) or escaped with a backslash.

A character class matches a single character in the subject; the character must be in the set of characters defined by the class, unless the first character in the class is a circumflex, in which case the subject character must not be in the set defined by the class. If a circumflex is actually required as a member of the class, ensure it is not the first character, or escape it with a backslash.

For example, the character class `[aeiou]` matches any lower case vowel, while `^[aeiou]` matches any character that is not a lower case vowel. Note that a circumflex is just a convenient notation for specifying the characters which are in the class by enumerating those that are not. It is not an assertion: it still consumes a character from the subject string, and fails if the current pointer is at the end of the string.

When caseless matching is set, any letters in a class represent both their upper case and lower case versions, so for example, a caseless `[aeiou]` matches "A" as well as "a", and a caseless `^[aeiou]` does not match "A", whereas a caseful version would.

The newline character is never treated in any special way in character classes, whatever the setting of the `PCRE_DOTALL` or `PCRE_MULTILINE` options is. A class such as `^[a]` will always match a newline.

The minus (hyphen) character can be used to specify a range of characters in a character class. For example, `[d-m]` matches any letter between d and m, inclusive. If a minus character is required in a class, it must be escaped with a backslash or appear in a position where it cannot be interpreted as indicating a range, typically as the first or last character in the class.

It is not possible to have the literal character "]" as the end character of a range. A pattern such as `[W-]46]` is interpreted as a class of two characters ("W" and "-") followed by a literal string "46]", so it would match "W46]" or "-46]". However, if the "]" is escaped with a backslash it is interpreted as the end of range, so `[W-\\]46]` is interpreted as a single class containing a range followed by two separate characters. The octal or hexadecimal representation of "]" can also be used to end a range.

Ranges operate in ASCII collating sequence. They can also be used for characters specified numerically, for example `[\\000-\\037]`. If a range that includes letters is used when caseless matching is set, it matches the letters in either

case. For example, `[W-c]` is equivalent to `[][\^_‘wxyzabc]`, matched caselessly, and if character tables for the "fr" locale are in use, `[\xc8-\xcb]` matches accented E characters in both cases.

The character types `\d`, `\D`, `\s`, `\S`, `\w`, and `\W` may also appear in a character class, and add the characters that they match to the class. For example, `[\dABCDEF]` matches any hexadecimal digit. A circumflex can conveniently be used with the upper case character types to specify a more restricted set of characters than the matching lower case type. For example, the class `[\^W_]` matches any letter or digit, but not underscore.

All non-alphameric characters other than `\`, `-`, `^` (at the start) and the terminating `]` are non-special in character classes, but it does no harm if they are escaped.

Vertical bar

Vertical bar characters are used to separate alternative patterns. For example, the pattern

```
gilbert|sullivan
```

matches either "gilbert" or "sullivan". Any number of alternatives may appear, and an empty alternative is permitted (matching the empty string). The matching process tries each alternative in turn, from left to right, and the first one that succeeds is used. If the alternatives are within a subpattern (defined below), "succeeds" means matching the rest of the main pattern as well as the alternative in the subpattern.

Internal option setting

The settings of `PCRE_CASELESS`, `PCRE_MULTILINE`, `PCRE_DOTALL`, and `PCRE_EXTENDED` can be changed from within the pattern by a sequence of Perl option letters enclosed between `"(?"` and `")"`. The option letters are

```
i for PCRE_CASELESS
m for PCRE_MULTILINE
s for PCRE_DOTALL
x for PCRE_EXTENDED
```

For example, `(?im)` sets caseless, multiline matching. It is also possible to unset these options by preceding the letter with a hyphen, and a combined setting and unsetting such as `(?im-sx)`, which sets `PCRE_CASELESS` and `PCRE_MULTILINE` while unsetting `PCRE_DOTALL` and `PCRE_EXTENDED`, is also permitted. If a letter appears both before and after the hyphen, the option is unset.

The scope of these option changes depends on where in the pattern the setting occurs. For settings that are outside any subpattern (defined below), the effect is the same as if the options were set or unset at the start of matching. The following patterns all behave in exactly the same way:

```
(?i)abc
a(?i)bc
ab(?i)c
abc(?i)
```

which in turn is the same as compiling the pattern `abc` with `PCRE_CASELESS` set. In other words, such "top level" settings apply to the whole pattern (unless there are other changes inside subpatterns). If there is more than one setting of the same option at top level, the rightmost setting is used.

If an option change occurs inside a subpattern, the effect is different. This is a change of behaviour in Perl 5.005. An option change inside a subpattern affects only that part of the subpattern that follows it, so

```
(a(?i)b)c
```

matches `abc` and `aBc` and no other strings (assuming `PCRE_CASELESS` is not used). By this means, options can be made to have different settings in different parts of the pattern. Any changes made in one alternative do carry on into subsequent branches within the same subpattern. For example,

```
(a(?i)b|c)
```

matches `"ab"`, `"aB"`, `"c"`, and `"C"`, even though when matching `"C"` the first branch is abandoned before the option setting. This is because the effects of option settings happen at compile time. There would be some very weird behaviour otherwise.

The PCRE-specific options `PCRE_UNGREEDY` and `PCRE_EXTRA` can be changed in the same way as the Perl-compatible options by

using the characters U and X respectively. The (?X) flag setting is special in that it must always occur earlier in the pattern than any of the additional features it turns on, even when it is at top level. It is best put at the start.

subpatterns

Subpatterns are delimited by parentheses (round brackets), which can be nested. Marking part of a pattern as a subpattern does two things:

1. It localizes a set of alternatives. For example, the pattern

```
cat(aract|erpillar|)
```

matches one of the words "cat", "cataract", or "caterpillar". Without the parentheses, it would match "cataract", "erpillar" or the empty string.

2. It sets up the subpattern as a capturing subpattern (as defined above). When the whole pattern matches, that portion of the subject string that matched the subpattern is passed back to the caller via the *ovector* argument of **pcre_exec()**. Opening parentheses are counted from left to right (starting from 1) to obtain the numbers of the capturing subpatterns.

For example, if the string "the red king" is matched against the pattern

```
the ((red|white) (king|queen))
```

the captured substrings are "red king", "red", and "king", and are numbered 1, 2, and 3.

The fact that plain parentheses fulfil two functions is not always helpful. There are often times when a grouping subpattern is required without a capturing requirement. If an opening parenthesis is followed by "?:", the subpattern does not do any capturing, and is not counted when computing the number of any subsequent capturing subpatterns. For example, if the string "the white queen" is matched against the pattern

```
the (?:red|white) (king|queen)
```

the captured substrings are "white queen" and "queen", and are numbered 1 and 2. The maximum number of captured sub-

strings is 99, and the maximum number of all subpatterns, both capturing and non-capturing, is 200.

As a convenient shorthand, if any option settings are required at the start of a non-capturing subpattern, the option letters may appear between the "?" and the ":". Thus the two patterns

```
(?i:saturday|sunday)
(?:(?i)saturday|sunday)
```

match exactly the same set of strings. Because alternative branches are tried from left to right, and options are not reset until the end of the subpattern is reached, an option setting in one branch does affect subsequent branches, so the above patterns match "SUNDAY" as well as "Saturday".

Repetition

Repetition is specified by quantifiers, which can follow any of the following items:

- a single character, possibly escaped
- the `.` metacharacter
- a character class
- a back reference (see next section)
- a parenthesized subpattern (unless it is an assertion - see below)

The general repetition quantifier specifies a minimum and maximum number of permitted matches, by giving the two numbers in curly brackets (braces), separated by a comma. The numbers must be less than 65536, and the first must be less than or equal to the second. For example:

```
z{2,4}
```

matches "zz", "zzz", or "zzzz". A closing brace on its own is not a special character. If the second number is omitted, but the comma is present, there is no upper limit; if the second number and the comma are both omitted, the quantifier specifies an exact number of required matches. Thus

```
[aeiou]{3,}
```

matches at least 3 successive vowels, but may match many more, while

```
\d{8}
```

matches exactly 8 digits. An opening curly bracket that appears in a position where a quantifier is not allowed, or one that does not match the syntax of a quantifier, is taken as a literal character. For example, `{,6}` is not a quantifier, but a literal string of four characters.

The quantifier `{0}` is permitted, causing the expression to behave as if the previous item and the quantifier were not present.

For convenience (and historical compatibility) the three most common quantifiers have single-character abbreviations:

- `*` is equivalent to `{0,}`
- `+` is equivalent to `{1,}`
- `?` is equivalent to `{0,1}`

It is possible to construct infinite loops by following a subpattern that can match no characters with a quantifier that has no upper limit, for example:

```
(a?)*
```

Earlier versions of Perl and PCRE used to give an error at compile time for such patterns. However, because there are cases where this can be useful, such patterns are now accepted, but if any repetition of the subpattern does in fact match no characters, the loop is forcibly broken.

By default, the quantifiers are "greedy", that is, they match as much as possible (up to the maximum number of permitted times), without causing the rest of the pattern to fail. The classic example of where this gives problems is in trying to match comments in C programs. These appear between the sequences `/*` and `*/` and within the sequence, individual `*` and `/` characters may appear. An attempt to match C comments by applying the pattern

```
/\*.*/
```

to the string

```
/* first command */ not comment /* second comment */
```

fails, because it matches the entire string due to the greediness of the `.*` item.

However, if a quantifier is followed by a question mark, then it ceases to be greedy, and instead matches the minimum number of times possible, so the pattern


```
/\*.*?\*/
```

does the right thing with the C comments. The meaning of the various quantifiers is not otherwise changed, just the preferred number of matches. Do not confuse this use of question mark with its use as a quantifier in its own right. Because it has two uses, it can sometimes appear doubled, as in

```
\d??\d
```

which matches one digit by preference, but can match two if that is the only way the rest of the pattern matches.

If the `PCRE_UNGREEDY` option is set (an option which is not available in Perl) then the quantifiers are not greedy by default, but individual ones can be made greedy by following them with a question mark. In other words, it inverts the default behaviour.

When a parenthesized subpattern is quantified with a minimum repeat count that is greater than 1 or with a limited maximum, more store is required for the compiled pattern, in proportion to the size of the minimum or maximum.

If a pattern starts with `.*` or `{0,}` and the `PCRE_DOTALL` option (equivalent to Perl's `/s`) is set, thus allowing the `.` to match newlines, then the pattern is implicitly anchored, because whatever follows will be tried against every character position in the subject string, so there is no point in retrying the overall match at any position after the first. PCRE treats such a pattern as though it were preceded by `\A`. In cases where it is known that the subject string contains no newlines, it is worth setting `PCRE_DOTALL` when the pattern begins with `.*` in order to obtain this optimization, or alternatively using `^` to indicate anchoring explicitly.

When a capturing subpattern is repeated, the value captured is the substring that matched the final iteration. For example, after

```
(tweedle[dume]{3}\s*)+
```

has matched "tweedledum tweedledee" the value of the captured substring is "tweedledee". However, if there are nested capturing subpatterns, the corresponding captured values may have been set in previous iterations. For example, after

```
/(a(b))+/
```

matches "aba" the value of the second captured substring is

"b".

BACK REFERENCES

Outside a character class, a backslash followed by a digit greater than 0 (and possibly further digits) is a back reference to a capturing subpattern earlier (i.e. to its left) in the pattern, provided there have been that many previous capturing left parentheses.

However, if the decimal number following the backslash is less than 10, it is always taken as a back reference, and causes an error only if there are not that many capturing left parentheses in the entire pattern. In other words, the parentheses that are referenced need not be to the left of the reference for numbers less than 10. See the section entitled "Backslash" above for further details of the handling of digits following a backslash.

A back reference matches whatever actually matched the capturing subpattern in the current subject string, rather than anything matching the subpattern itself. So the pattern

```
(sens|respons)e and \1bility
```

matches "sense and sensibility" and "response and responsibility", but not "sense and responsibility". If careful matching is in force at the time of the back reference, then the case of letters is relevant. For example,

```
((?i)rah)\s+\1
```

matches "rah rah" and "RAH RAH", but not "RAH rah", even though the original capturing subpattern is matched caselessly.

There may be more than one back reference to the same subpattern. If a subpattern has not actually been used in a particular match, then any back references to it always fail. For example, the pattern

```
(a|(bc))\2
```

always fails if it starts to match "a" rather than "bc". Because there may be up to 99 back references, all digits following the backslash are taken as part of a potential back reference number. If the pattern continues with a digit character, then some delimiter must be used to terminate the back reference. If the `PCRE_EXTENDED` option is set, this can

be whitespace. Otherwise an empty comment can be used.

A back reference that occurs inside the parentheses to which it refers fails when the subpattern is first used, so, for example, `(a\1)` never matches. However, such references can be useful inside repeated subpatterns. For example, the pattern

```
(a|b\1)+
```

matches any number of "a"s and also "aba", "ababaa" etc. At each iteration of the subpattern, the back reference matches the character string corresponding to the previous iteration. In order for this to work, the pattern must be such that the first iteration does not need to match the back reference. This can be done using alternation, as in the example above, or by a quantifier with a minimum of zero.

Assertions

An assertion is a test on the characters following or preceding the current matching point that does not actually consume any characters. The simple assertions coded as `\b`, `\B`, `\A`, `\Z`, `\z`, `^` and `$` are described above. More complicated assertions are coded as subpatterns. There are two kinds: those that look ahead of the current position in the subject string, and those that look behind it.

An assertion subpattern is matched in the normal way, except that it does not cause the current matching position to be changed. Lookahead assertions start with `(?=` for positive assertions and `(?!` for negative assertions. For example,

```
\w+(?=;)
```

matches a word followed by a semicolon, but does not include the semicolon in the match, and

```
foo(?!bar)
```

matches any occurrence of "foo" that is not followed by "bar". Note that the apparently similar pattern

```
(?!foo)bar
```

does not find an occurrence of "bar" that is preceded by something other than "foo"; it finds any occurrence of "bar" whatsoever, because the assertion `(?!foo)` is always TRUE when the next three characters are "bar". A lookbehind

assertion is needed to achieve this effect.

Lookbehind assertions start with `(?<=` for positive assertions and `(?<!` for negative assertions. For example,

```
(?<!foo)bar
```

does find an occurrence of "bar" that is not preceded by "foo". The contents of a lookbehind assertion are restricted such that all the strings it matches must have a fixed length. However, if there are several alternatives, they do not all have to have the same fixed length. Thus

```
(?<=bullock|donkey)
```

is permitted, but

```
(?<!dogs?|cats?)
```

causes an error at compile time. Branches that match different length strings are permitted only at the top level of a lookbehind assertion. This is an extension compared with Perl 5.005, which requires all branches to match the same length of string. An assertion such as

```
(?<=ab(c|de))
```

is not permitted, because its single top-level branch can match two different lengths, but it is acceptable if rewritten to use two top-level branches:

```
(?<=abc|abde)
```

The implementation of lookbehind assertions is, for each alternative, to temporarily move the current position back by the fixed width and then try to match. If there are insufficient characters before the current position, the match is deemed to fail. Lookbehinds in conjunction with once-only subpatterns can be particularly useful for matching at the ends of strings; an example is given at the end of the section on once-only subpatterns.

Several assertions (of any sort) may occur in succession. For example,

```
(?<=\d{3})(?<!999)foo
```

matches "foo" preceded by three digits that are not "999". Notice that each of the assertions is applied independently at the same point in the subject string. First there is a check that the previous three characters are all digits, then there is a check that the same three characters are not

"999". This pattern does not match "foo" preceded by six characters, the first of which are digits and the last three of which are not "999". For example, it doesn't match "123abcfoo". A pattern to do that is

```
(?<=\d{3}...)(?!999)foo
```

This time the first assertion looks at the preceding six characters, checking that the first three are digits, and then the second assertion checks that the preceding three characters are not "999".

Assertions can be nested in any combination. For example,

```
(?<=(?!foo)bar)baz
```

matches an occurrence of "baz" that is preceded by "bar" which in turn is not preceded by "foo", while

```
(?<=\d{3})(?!999...)foo
```

is another pattern which matches "foo" preceded by three digits and any three characters that are not "999".

Assertion subpatterns are not capturing subpatterns, and may not be repeated, because it makes no sense to assert the same thing several times. If any kind of assertion contains capturing subpatterns within it, these are counted for the purposes of numbering the capturing subpatterns in the whole pattern. However, substring capturing is carried out only for positive assertions, because it does not make sense for negative assertions.

Assertions count towards the maximum of 200 parenthesized subpatterns.

Once-only subpatterns

With both maximizing and minimizing repetition, failure of what follows normally causes the repeated item to be re-evaluated to see if a different number of repeats allows the rest of the pattern to match. Sometimes it is useful to prevent this, either to change the nature of the match, or to cause it fail earlier than it otherwise might, when the author of the pattern knows there is no point in carrying on.

Consider, for example, the pattern `\d+foo` when applied to the subject line

123456bar

After matching all 6 digits and then failing to match "foo", the normal action of the matcher is to try again with only 5 digits matching the `\d+` item, and then with 4, and so on, before ultimately failing. Once-only subpatterns provide the means for specifying that once a portion of the pattern has matched, it is not to be re-evaluated in this way, so the matcher would give up immediately on failing to match "foo" the first time. The notation is another kind of special parenthesis, starting with `(?>` as in this example:

`(?>\d+)bar`

This kind of parenthesis "locks up" the part of the pattern it contains once it has matched, and a failure further into the pattern is prevented from backtracking into it. Backtracking past it to previous items, however, works as normal.

An alternative description is that a subpattern of this type matches the string of characters that an identical standalone pattern would match, if anchored at the current point in the subject string.

Once-only subpatterns are not capturing subpatterns. Simple cases such as the above example can be thought of as a maximizing repeat that must swallow everything it can. So, while both `\d+` and `\d+?` are prepared to adjust the number of digits they match in order to make the rest of the pattern match, `(?>\d+)` can only match an entire sequence of digits.

This construction can of course contain arbitrarily complicated subpatterns, and it can be nested.

Once-only subpatterns can be used in conjunction with look-behind assertions to specify efficient matching at the end of the subject string. Consider a simple pattern such as

`abcd$`

when applied to a long string which does not match. Because matching proceeds from left to right, PCRE will look for each "a" in the subject and then see if what follows matches the rest of the pattern. If the pattern is specified as

`^.*abcd$`

then the initial `.*` matches the entire string at first, but when this fails (because there is no following "a"), it backtracks to match all but the last character, then all but

the last two characters, and so on. Once again the search for "a" covers the entire string, from right to left, so we are no better off. However, if the pattern is written as

```
^(?>.*)(?<=abcd)
```

then there can be no backtracking for the `.*` item; it can match only the entire string. The subsequent lookbehind assertion does a single test on the last four characters. If it fails, the match fails immediately. For long strings, this approach makes a significant difference to the processing time.

When a pattern contains an unlimited repeat inside a subpattern that can itself be repeated an unlimited number of times, the use of a once-only subpattern is the only way to avoid some failing matches taking a very long time indeed. The pattern

```
(\D+|<\d+>)*[!?]
```

matches an unlimited number of substrings that either consist of non-digits, or digits enclosed in `<>`, followed by either `!` or `?`. When it matches, it runs quickly. However, if it is applied to

```
aaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaa
```

it takes a long time before reporting failure. This is because the string can be divided between the two repeats in a large number of ways, and all have to be tried. (The example used `[!?]` rather than a single character at the end, because both PCRE and Perl have an optimization that allows for fast failure when a single character is used. They remember the last single character that is required for a match, and fail early if it is not present in the string.) If the pattern is changed to

```
((?>\D+)|<\d+>)*[!?]
```

sequences of non-digits cannot be broken, and failure happens quickly.

Conditional subpatterns

It is possible to cause the matching process to obey a subpattern conditionally or to choose between two alternative subpatterns, depending on the result of an assertion, or whether a previous capturing subpattern matched or not. The

two possible forms of conditional subpattern are

```
(?(condition)yes-pattern)
(?(condition)yes-pattern|no-pattern)
```

If the condition is satisfied, the yes-pattern is used; otherwise the no-pattern (if present) is used. If there are more than two alternatives in the subpattern, a compile-time error occurs.

There are two kinds of condition. If the text between the parentheses consists of a sequence of digits, then the condition is satisfied if the capturing subpattern of that number has previously matched. Consider the following pattern, which contains non-significant white space to make it more readable (assume the `PCRE_EXTENDED` option) and to divide it into three parts for ease of discussion:

```
( \( \)? [^()]+ (?(1) \) )
```

The first part matches an optional opening parenthesis, and if that character is present, sets it as the first captured substring. The second part matches one or more characters that are not parentheses. The third part is a conditional subpattern that tests whether the first set of parentheses matched or not. If they did, that is, if subject started with an opening parenthesis, the condition is `TRUE`, and so the yes-pattern is executed and a closing parenthesis is required. Otherwise, since no-pattern is not present, the subpattern matches nothing. In other words, this pattern matches a sequence of non-parentheses, optionally enclosed in parentheses.

If the condition is not a sequence of digits, it must be an assertion. This may be a positive or negative lookahead or lookbehind assertion. Consider this pattern, again containing non-significant white space, and with the two alternatives on the second line:

```
(?(?=[^a-z]*[a-z])
 \d{2}-[a-z]{3}-\d{2} | \d{2}-\d{2}-\d{2} )
```

The condition is a positive lookahead assertion that matches an optional sequence of non-letters followed by a letter. In other words, it tests for the presence of at least one letter in the subject. If a letter is found, the subject is matched against the first alternative; otherwise it is matched against the second. This pattern matches strings in one of the two forms `dd-aaa-dd` or `dd-dd-dd`, where `aaa` are letters and `dd` are digits.

Comments

The sequence `(?#` marks the start of a comment which continues up to the next closing parenthesis. Nested parentheses are not permitted. The characters that make up a comment play no part in the pattern matching at all.

If the `PCRE_EXTENDED` option is set, an unescaped `#` character outside a character class introduces a comment that continues up to the next newline character in the pattern.

Recursive patterns

Consider the problem of matching a string in parentheses, allowing for unlimited nested parentheses. Without the use of recursion, the best that can be done is to use a pattern that matches up to some fixed depth of nesting. It is not possible to handle an arbitrary nesting depth. Perl 5.6 has provided an experimental facility that allows regular expressions to recurse (amongst other things). The special item `(?R)` is provided for the specific case of recursion. This PCRE pattern solves the parentheses problem (assume the `PCRE_EXTENDED` option is set so that white space is ignored):

```
\( ( (?>[^\()]+) | (?R) )* \)
```

First it matches an opening parenthesis. Then it matches any number of substrings which can either be a sequence of non-parentheses, or a recursive match of the pattern itself (i.e. a correctly parenthesized substring). Finally there is a closing parenthesis.

This particular example pattern contains nested unlimited repeats, and so the use of a once-only subpattern for matching strings of non-parentheses is important when applying the pattern to strings that do not match. For example, when it is applied to

```
(aaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaaa())
```

it yields "no match" quickly. However, if a once-only subpattern is not used, the match runs for a very long time indeed because there are so many different ways the `+` and `*` repeats can carve up the subject, and all have to be tested before failure can be reported.

The values set for any capturing subpatterns are those from the outermost level of the recursion at which the subpattern value is set. If the pattern above is matched against

$$(ab(cd)ef)$$

the value for the capturing parentheses is "ef", which is the last value taken on at the top level. If additional parentheses are added, giving

$$\begin{array}{cc} \wedge & \wedge \\ \wedge & \wedge \text{ then the} \end{array}$$

is "ab(cdef)", the contents of the top level parentheses. If there are more than 15 capturing parentheses in a pattern, PCRE has to obtain extra memory to store data during a recursion, which it does by using `pcre_malloc`, freeing it via `pcre_free` afterwards. If no memory can be obtained, it saves data for the first 15 capturing parentheses only, as there is no way to give an out-of-memory error from within a recursion.

Performances

Certain items that may appear in patterns are more efficient than others. It is more efficient to use a character class like `[aeiou]` than a set of alternatives such as `(a|e|i|o|u)`. In general, the simplest construction that provides the required behaviour is usually the most efficient. Jeffrey Friedl's book contains a lot of discussion about optimizing regular expressions for efficient performance.

When a pattern begins with `.` and the `PCRE_DOTALL` option is set, the pattern is implicitly anchored by PCRE, since it can match only at the start of a subject string. However, if `PCRE_DOTALL` is not set, PCRE cannot make this optimization, because the `.` metacharacter does not then match a newline, and if the subject string contains newlines, the pattern may match from the character immediately following one of them instead of from the very start. For example, the pattern

(.*) second

matches the subject "first\nand second" (where \n stands for a newline character) with the first captured substring being "and". In order to do this, PCRE has to retry the match starting after every newline in the subject.

If you are using such a pattern with subject strings that do not contain newlines, the best performance is obtained by setting `PCRE_DOTALL`, or starting the pattern with `^.` to indicate explicit anchoring. That saves PCRE from having to

scan along the subject looking for a newline to restart at.

Beware of patterns that contain nested indefinite repeats. These can take a long time to run when applied to a string that does not match. Consider the pattern fragment

```
(a+)*
```

This can match "aaaa" in 33 different ways, and this number increases very rapidly as the string gets longer. (The * repeat can match 0, 1, 2, 3, or 4 times, and for each of those cases other than 0, the + repeats can match different numbers of times.) When the remainder of the pattern is such that the entire match is going to fail, PCRE has in principle to try every possible variation, and this can take an extremely long time.

An optimization catches some of the more simple cases such as

```
(a+)*b
```

where a literal character follows. Before embarking on the standard matching procedure, PCRE checks that there is a "b" later in the subject string, and if there is not, it fails the match immediately. However, when there is no following literal this optimization cannot be used. You can see the difference by comparing the behaviour of

```
(a+)*\d
```

with the pattern above. The former gives a failure almost instantly when applied to a whole line of "a" characters, whereas the latter takes an appreciable time with strings longer than about 20 characters.

preg_grep (PHP 4 >= 4.0.0)

Return array entries that match the pattern

array **preg_grep** (string pattern, array input) \linebreak

preg_grep() returns the array consisting of the elements of the *input* array that match the given *pattern*.

Since PHP 4.0.4, the results returned by **preg_grep()** are indexed using the keys from the input array. If this behavior is undesirable, use `array_values()` on the array returned by **preg_grep()** to reindex the values.

Příklad 1. preg_grep() example

```
// return all array elements
// containing floating point numbers
$fl_array = preg_grep ("/^(\d+)?\.\d+$/", $array);
```

preg_match (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Perform a regular expression match

int preg_match (string *pattern*, string *subject* [, array *matches*]) \linebreak

Searches *subject* for a match to the regular expression given in *pattern*.

If *matches* is provided, then it is filled with the results of search. *\$matches*[0] will contain the text that matched the full pattern, *\$matches*[1] will have the text that matched the first captured parenthesized subpattern, and so on.

Returns **TRUE** if a match for *pattern* was found in the subject string, or **FALSE** if not match was found or an error occurred.

Příklad 1. Find the string of text "php"

```
// the "i" after the pattern delimiter indicates a case-insensitive search
if (preg_match ("/php/i", "PHP is the web scripting language of choice.")) {
    print "A match was found.";
} else {
    print "A match was not found.";
}
```

Příklad 2. find the word "web"

```
// the \b in the pattern indicates a word boundary, so only the distinct
// word "web" is matched, and not a word partial like "webbing" or "cobweb"
if (preg_match ("/\bweb\b/i", "PHP is the web scripting language of choice.")) {
    print "A match was found.";
} else {
    print "A match was not found.";
}
if (preg_match ("/\bweb\b/i", "PHP is the website scripting language of choice.")) {
    print "A match was found.";
} else {
    print "A match was not found.";
}
```

Příklad 3. Getting the domain name out of a URL

```
// get host name from URL
preg_match("/^(http:\\\\\/)?([^\\/]+)/i",
"http://www.php.net/index.html", $matches);
$host = $matches[2];
// get last two segments of host name
preg_match("/[^\.\\/]+\.[^\.\\/]+$/", $host, $matches);
echo "domain name is: ".$matches[0]."\n";
```

This example will produce:

```
domain name is: php.net
```

See also `preg_match_all()`, `preg_replace()`, and `preg_split()`.

preg_match_all (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Perform a global regular expression match

int **preg_match_all** (string *pattern*, string *subject*, array *matches* [, int *order*]) \linebreak

Searches *subject* for all matches to the regular expression given in *pattern* and puts them in *matches* in the order specified by *order*.

After the first match is found, the subsequent searches are continued on from end of the last match.

order can be one of two things:

PREG_PATTERN_ORDER

Orders results so that `$matches[0]` is an array of full pattern matches, `$matches[1]` is an array of strings matched by the first parenthesized subpattern, and so on.

```
preg_match_all ("|<[^>]+>(.*?)</[^>]+>|U",
"<b>example: </b><div align=left>this is a test</div>",
$out, PREG_PATTERN_ORDER);
print $out[0][0].", ".$out[0][1]."\n";
print $out[1][0].", ".$out[1][1]."\n";
```

This example will produce:

```
<b>example: </b>, <div align=left>this is a test</div>
example: , this is a test
```

So, \$out[0] contains array of strings that matched full pattern, and \$out[1] contains array of strings enclosed by tags.

PREG_SET_ORDER

Orders results so that \$matches[0] is an array of first set of matches, \$matches[1] is an array of second set of matches, and so on.

```
preg_match_all ("|<[^>]+>(.*?)</[^>]+>|U",
    "<b>example: </b><div align=left>this is a test</div>",
    $out, PREG_SET_ORDER);
print $out[0][0].", ".$out[0][1]."\n";
print $out[1][0].", ".$out[1][1]."\n";
```

This example will produce:

```
<b>example: </b>, example:
<div align=left>this is a test</div>, this is a test
```

In this case, \$matches[0] is the first set of matches, and \$matches[0][0] has text matched by full pattern, \$matches[0][1] has text matched by first subpattern and so on. Similarly, \$matches[1] is the second set of matches, etc.

If *order* is not specified, it is assumed to be PREG_PATTERN_ORDER.

Returns the number of full pattern matches, or FALSE if no match is found or an error occurred.

Příklad 1. Getting all phone numbers out of some text.

```
preg_match_all ("/\((? (\d{3})? \)? (? (1) [\-\s] ) \d{3}-\d{4}/x",
    "Call 555-1212 or 1-800-555-1212", $phones);
```

Příklad 2. Find matching HTML tags (greedy)

```
// The \2 is an example of backreferencing. This tells pcre that
// it must match the second set of parentheses in the regular expression
// itself, which would be the ([\w]+) in this case. The extra backslash is
// required because the string is in double quotes.
```

```
$html = "<b>bold text</b><a href=howdy.html>click me</a>";

preg_match_all ( "/(<([\w]+)[^>]*>)(.*)(<\/\2>)/", $html, $matches);

for ($i=0; $i< count($matches[0]); $i++) {
    echo "matched: ".$matches[0][$i]."\n";
    echo "part 1: ".$matches[1][$i]."\n";
    echo "part 2: ".$matches[3][$i]."\n";
    echo "part 3: ".$matches[4][$i]."\n\n";
}
```

This example will produce:

```
matched: <b>bold text</b>
part 1: <b>
part 2: bold text
part 3: </b>

matched: <a href=howdy.html>click me</a>
part 1: <a href=howdy.html>
part 2: click me
part 3: </a>
```

See also `preg_match()`, `preg_replace()`, and `preg_split()`.

preg_quote (PHP 3 >= 3.0.9, PHP 4 >= 4.0.0)

Quote regular expression characters

string **preg_quote** (string *str* [, string *delimiter*]) \linebreak

preg_quote() takes *str* and puts a backslash in front of every character that is part of the regular expression syntax. This is useful if you have a run-time string that you need to match in some text and the string may contain special regex characters.

If the optional *delimiter* is specified, it will also be escaped. This is useful for escaping the delimiter that is required by the PCRE functions. The `/` is the most commonly used delimiter.

The special regular expression characters are:

```
. \ + * ? [ ^ ] $ ( ) { } = ! < > | :
```

Příklad 1.

```
$keywords = "$40 for a g3/400";
$keywords = preg_quote ($keywords, "/");
echo $keywords; // returns \$40 for a g3\400
```

Příklad 2. Italicizing a word within some text

```
// In this example, preg_quote($word) is used to keep the
// asterisks from having special meaning to the regular
// expression.

$textbody = "This book is *very* difficult to find.";
$word = "*very*";
$textbody = preg_replace ("/".preg_quote($word)."/",
                          "<i>".$word."</i>",
                          $textbody);
```

preg_replace (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Perform a regular expression search and replace

mixed **preg_replace** (mixed pattern, mixed replacement, mixed subject [, int limit]) \linebreak

Searches *subject* for matches to *pattern* and replaces them with *replacement*. If *limit* is specified, then only *limit* matches will be replaced; if *limit* is omitted or is -1, then all matches are replaced.

Replacement may contain references of the form `\\n` or (since PHP 4.0.4) `$n`, with the latter form being the preferred one. Every such reference will be replaced by the text captured by the *n*'th parenthesized pattern. *n* can be from 0 to 99, and `\\0` or `$0` refers to the text matched by the whole pattern. Opening parentheses are counted from left to right (starting from 1) to obtain the number of the capturing subpattern.

If matches are found, the new *subject* will be returned, otherwise *subject* will be returned unchanged.

Every parameter to **preg_replace()** can be an array.

If *subject* is an array, then the search and replace is performed on every entry of *subject*, and the return value is an array as well.

If *pattern* and *replacement* are arrays, then **preg_replace()** takes a value from each array and uses them to do search and replace on *subject*. If *replacement* has fewer values than *pattern*, then empty string is used for the rest of replacement values. If *pattern* is an array and *replacement* is a string, then this replacement string is used for every value of *pattern*. The converse would not make sense, though.

`/e` modifier makes **preg_replace()** treat the *replacement* parameter as PHP code after the appropriate references substitution is done. Tip: make sure that *replacement* constitutes a valid PHP code string, otherwise PHP will complain about a parse error at the line containing **preg_replace()**.

Příklad 1. Replacing several values

```
$patterns = array ("/(19|20)(\d{2})-(\d{1,2})-(\d{1,2})/",
                  "^\\s*{(\w+)}\\s*=/" );
$replace = array ("\\3/\\4/\\1\\2", "\\1 =");
print preg_replace ($patterns, $replace, "{startDate} = 1999-5-27");
```

This example will produce:

```
$startDate = 5/27/1999
```

Příklad 2. Using `/e` modifier

```
preg_replace ("(<\/?)(\w+)([>]*>)/e",
              "'\\1'.strtoupper('\\2').'\\3'",
              $html_body);
```

This would capitalize all HTML tags in the input text.

Příklad 3. Convert HTML to text

```
// $document should contain an HTML document.
// This will remove HTML tags, javascript sections
// and white space. It will also convert some
// common HTML entities to their text equivalent.

$search = array ("<script[^>]*?>.*?</script>'si", // Strip out javascript
                 "<[\/\!] *? [<>] *?>'si", // Strip out html tags
                 "([\r\n])[\s]+'", // Strip out white space
                 '"#34;'i", // Replace html entities
                 '&#38;'i",
                 '&#60;'i",
                 '&#62;'i",
                 '&#160;'i",
                 '&#161;'i",
                 '&#162;'i",
                 '&#163;'i",
                 '&#169;'i",
                 '&#(\d+);'e"); // evaluate as php
```

```

$replace = array ( " ",
                  " ",
                  "\\1",
                  "\"",
                  "&",
                  "<",
                  ">",
                  " ",
                  chr(161),
                  chr(162),
                  chr(163),
                  chr(169),
                  "chr(\\1)" );

$text = preg_replace ($search, $replace, $document);

```

Poznámka: Parameter *limit* was added after PHP 4.0.1pl2.

See also `preg_match()`, `preg_match_all()`, and `preg_split()`.

preg_replace_callback (PHP 4 >= 4.0.5)

Perform a regular expression search and replace using a callback

mixed **preg_replace_callback** (mixed pattern, mixed callback, mixed subject [, int limit]) \linebreak

The behavior of this function is almost identical to `preg_replace()`, except for the fact that instead of *replacement* parameter, one should specify a *callback* that will be called and passed an array of matched elements in the subject string. The callback should return the replacement string. This function was added in PHP 4.0.5.

See also `preg_replace()`.

preg_split (PHP 3 >= 3.0.9, PHP 4 >= 4.0.0)

Split string by a regular expression

array **preg_split** (string pattern, string subject [, int limit [, int flags]]) \linebreak

Poznámka: Parameter *flags* was added in PHP 4 Beta 3.

Returns an array containing substrings of *subject* split along boundaries matched by *pattern*.

If *limit* is specified, then only substrings up to *limit* are returned, and if *limit* is -1, it actually means "no limit", which is useful for specifying the *flags*.

flags can be any combination of the following flags (combined with bitwise | operator):

PREG_SPLIT_NO_EMPTY

If this flag is set, only non-empty pieces will be returned by **preg_split()**.

PREG_SPLIT_DELIM_CAPTURE

If this flag is set, parenthesized expression in the delimiter pattern will be captured and returned as well. This flag was added for 4.0.5.

Příklad 1. preg_split() example : Get the parts of a search string.

```
// split the phrase by any number of commas or space characters,
// which include " ", \r, \t, \n and \f
$keywords = preg_split ("/[\s,]+/", "hypertext language, programming");
```

Příklad 2. Splitting a string into component characters.

```
$str = 'string';
$chars = preg_split('///', $str, -1, PREG_SPLIT_NO_EMPTY);
print_r($chars);
```

See also **spliti()**, **split()**, **implode()**, **preg_match()**, **preg_match_all()**, and **preg_replace()**.

LXXXVII. qtdom functions

qdom_error (PHP 4 >= 4.0.5)

Returns the error string from the last QDOM operation or FALSE if no errors occurred

string **qdom_error** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

qdom_tree (PHP 4 >= 4.0.4)

creates a tree of an xml string

object **qdom_tree** (string) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

LXXXVIII. Regular Expression Functions (POSIX Extended)

Poznámka: PHP also supports regular expressions using a Perl-compatible syntax using the PCRE functions. Those functions support non-greedy matching, assertions, conditional subpatterns, and a number of other features not supported by the POSIX-extended regular expression syntax.

Varování

These regular expression functions are not binary-safe. The PCRE functions are.

Regular expressions are used for complex string manipulation in PHP. The functions that support regular expressions are:

- `ereg()`
- `ereg_replace()`
- `eregi()`
- `eregi_replace()`
- `split()`
- `spliti()`

These functions all take a regular expression string as their first argument. PHP uses the POSIX extended regular expressions as defined by POSIX 1003.2. For a full description of POSIX regular expressions see the `regex` man pages included in the `regex` directory in the PHP distribution. It's in manpage format, so you'll want to do something along the lines of **man /usr/local/src/regex/regex.7** in order to read it.

Příklad 1. Regular Expression Examples

```
ereg ("abc", $string);
/* Returns true if "abc"
   is found anywhere in $string. */

ereg ("^abc", $string);
/* Returns true if "abc";
   is found at the beginning of $string. */

ereg ("abc$", $string);
/* Returns true if "abc"
   is found at the end of $string. */

eregi ("(ozilla.[23]|MSIE.3)", $HTTP_USER_AGENT);
/* Returns true if client browser
   is Netscape 2, 3 or MSIE 3. */
```

```

ereg ("([[:alnum:]]+) ([[:alnum:]]+) ([[:alnum:]]+)", $string,$regs);
/* Places three space separated words
   into $regs[1], $regs[2] and $regs[3]. */

$string = ereg_replace ("^", "<br />", $string);
/* Put a <br /> tag at the beginning of $string. */

$string = ereg_replace ("$", "<br />", $string);
/* Put a <br /> tag at the end of $string. */

$string = ereg_replace ("\n", "", $string);
/* Get rid of any newline
   characters in $string. */

```

ereg (PHP 3, PHP 4 >= 4.0.0)

Regular expression match

```
int ereg ( string pattern, string string [, array regs) \linebreak
```

Poznámka: `preg_match()`, which uses a Perl-compatible regular expression syntax, is often a faster alternative to **ereg()**.

Searches a *string* for matches to the regular expression given in *pattern*.

If matches are found for parenthesized substrings of *pattern* and the function is called with the third argument *regs*, the matches will be stored in the elements of the array *regs*. `$regs[1]` will contain the substring which starts at the first left parenthesis; `$regs[2]` will contain the substring starting at the second, and so on. `$regs[0]` will contain a copy of the complete string matched.

Poznámka: Up to (and including) PHP 4.1.0 `$regs` will be filled with exactly ten elements, even though more or fewer than ten parenthesized substrings may actually have matched. This has no effect on **ereg()**'s ability to match more substrings. If no matches are found, `$regs` will not be altered by **ereg()**.

Searching is case sensitive.

Returns `TRUE` if a match for *pattern* was found in *string*, or `FALSE` if no matches were found or an error occurred.

The following code snippet takes a date in ISO format (YYYY-MM-DD) and prints it in DD.MM.YYYY format:

Příklad 1. ereg() Example

```
if (ereg ("([0-9]{4})-([0-9]{1,2})-([0-9]{1,2})", $date, $regs)) {
    echo "$regs[3].$regs[2].$regs[1]";
} else {
    echo "Invalid date format: $date";
}
```

See also `ereg()`, `ereg_replace()`, `eregi_replace()`, and `preg_match()`.

ereg_replace (PHP 3, PHP 4 >= 4.0.0)

Replace regular expression

```
string ereg_replace ( string pattern, string replacement, string string) \linebreak
```


Poznámka: `preg_replace()`, which uses a Perl-compatible regular expression syntax, is often a faster alternative to `ereg_replace()`.

This function scans *string* for matches to *pattern*, then replaces the matched text with *replacement*.

The modified string is returned. (Which may mean that the original string is returned if there are no matches to be replaced.)

If *pattern* contains parenthesized substrings, *replacement* may contain substrings of the form `\\digit`, which will be replaced by the text matching the digit'th parenthesized substring; `\\0` will produce the entire contents of string. Up to nine substrings may be used. Parentheses may be nested, in which case they are counted by the opening parenthesis.

If no matches are found in *string*, then *string* will be returned unchanged.

For example, the following code snippet prints "This was a test" three times:

Příklad 1. `ereg_replace()` Example

```
$string = "This is a test";
echo ereg_replace (" is", " was", $string);
echo ereg_replace ("( )is", "\\1was", $string);
echo ereg_replace ("(( )is)", "\\2was", $string);
```

One thing to take note of is that if you use an integer value as the *replacement* parameter, you may not get the results you expect. This is because `ereg_replace()` will interpret the number as the ordinal value of a character, and apply that. For instance:

Příklad 2. `ereg_replace()` Example

```
<?php
/* This will not work as expected. */
$num = 4;
$string = "This string has four words.";
$string = ereg_replace('four', $num, $string);
echo $string; /* Output: 'This string has  words.' */

/* This will work. */
$num = '4';
$string = "This string has four words.";
$string = ereg_replace('four', $num, $string);
echo $string; /* Output: 'This string has 4 words.' */
?>
```

Příklad 3. Replace URLs with links

```
$text = ereg_replace("[[:alpha:]]+://[^<>[:space:]]+[[:alnum:]]/",
    "<a href=\"\\0\">\\0</a>", $text);
```

See also `ereg()`, `eregi()`, `eregi_replace()`, `str_replace()`, and `preg_match()`.

eregi (PHP 3, PHP 4 >= 4.0.0)

case insensitive regular expression match

int **eregi** (string pattern, string string [, array regs]) \linebreak

This function is identical to `ereg()` except that this ignores case distinction when matching alphabetic characters.

Příklad 1. eregi() example

```
if (eregi("z", $string)) {
    echo "'$string' contains a 'z' or 'Z'!";
}
```

See also `ereg()`, `ereg_replace()`, and `eregi_replace()`.

eregi_replace (PHP 3, PHP 4 >= 4.0.0)

replace regular expression case insensitive

string **eregi_replace** (string pattern, string replacement, string string) \linebreak

This function is identical to `ereg_replace()` except that this ignores case distinction when matching alphabetic characters.

See also `ereg()`, `eregi()`, and `ereg_replace()`.

split (PHP 3, PHP 4 >= 4.0.0)

split string into array by regular expression

array **split** (string pattern, string string [, int limit]) \linebreak

Poznámka: `preg_split()`, which uses a Perl-compatible regular expression syntax, is often a faster alternative to `split()`.

Returns an array of strings, each of which is a substring of *string* formed by splitting it on boundaries formed by the regular expression *pattern*. If *limit* is set, the returned array will contain a maximum of *limit* elements with the last element containing the whole rest of *string*. If an error occurs, `split()` returns FALSE.

To split off the first four fields from a line from `/etc/passwd`:

Příklad 1. `split()` Example

```
list($user,$pass,$uid,$gid,$extra)= split (":", $passwd_line, 5);
```

Poznámka: If there are *n* occurrences of *pattern*, the returned array will contain *n*+1 items. For example, if there is no occurrence of *pattern*, an array with only one element will be returned. Of course, this is also true if *string* is empty.

To parse a date which may be delimited with slashes, dots, or hyphens:

Příklad 2. `split()` Example

```
$date = "04/30/1973"; // Delimiters may be slash, dot, or hyphen
list ($month, $day, $year) = split ('[/.-]', $date);
echo "Month: $month; Day: $day; Year: $year<br>\n";
```

Note that *pattern* is case-sensitive.

Note that if you don't require the power of regular expressions, it is faster to use `explode()`, which doesn't incur the overhead of the regular expression engine.

For users looking for a way to emulate Perl's `@chars = split("", $str)` behaviour, please see the examples for `preg_split()`.

Please note that *pattern* is a regular expression. If you want to split on any of the characters which are considered special by regular expressions, you'll need to escape them first. If you think `split()` (or any other regex function, for that matter) is doing something weird, please read the file `regex.7`, included in the `regex/` subdirectory of the PHP distribution. It's in manpage format, so you'll want to do something along the lines of `man /usr/local/src/regex/regex.7` in order to read it.

See also: `preg_split()`, `spliti()`, `explode()`, `implode()`, `chunk_split()`, and `wordwrap()`.

spliti (PHP 4)

Split string into array by regular expression case insensitive

array **spliti** (string pattern, string string [, int limit]) \linebreak

This function is identical to `split()` except that this ignores case distinction when matching alphabetic characters.

See also **preg_split()**, **split()**, **explode()**, and **implode()**.

sql_regcase (PHP 3, PHP 4 >= 4.0.0)

Make regular expression for case insensitive match

string **sql_regcase** (string string) \linebreak

Returns a valid regular expression which will match *string*, ignoring case. This expression is *string* with each character converted to a bracket expression; this bracket expression contains that character's uppercase and lowercase form if applicable, otherwise it contains the original character twice.

Příklad 1. sql_regcase() Example

```
echo sql_regcase ("Foo bar");
```

prints

```
[Ff][Oo][Oo] [Bb][Aa][Rr]
```

.

This can be used to achieve case insensitive pattern matching in products which support only case sensitive regular expressions.

LXXXIX. Funkce pro práci se semaforey a sdílenou pamětí

Tato extenze poskytuje semaforové funkce využívající System V semaforey. Semaforey se dají používat k poskytování exkluzivního přístupu k prostředkům na daném systému, nebo k omezení počtu procesů, které mohou současně používat určitý prostředek.

Tato extenze také poskytuje funkce pro práci se sdílenou pamětí využívající System V sdílenou paměť. Sdílená paměť se dá používat k poskytování přístupu ke globálním proměnným. Různí httpd-daemoni a dokonce i jiné programy (např. Perl, C, ...) mohou k těmto datům přistupovat, a vytvořit tak globální výměnu dat. Pamatuje, že sdílená paměť *není* chráněna proti simultánním přístupům. K synchronizaci použijte semaforey.

Tabulka 1. Omezení sdílené paměti systémem Unix

SHMMAX	max. velikost sdílené paměti, normálně 131072 bytů
SHMMIN	min. velikost sdílené paměti, normálně 1 byte
SHMMNI	max. počet segmentů sdílené paměti, normálně 100
SHMSEG	max. počet segmentů sdílené paměti na proces, normálně 6

Poznámka: Tyto funkce nefungují na Windows.

sem_acquire (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Získat semafor

```
int sem_acquire ( int sem_identifier ) \linebreak
```

Při úspěchu vrátí TRUE, při chybě FALSE.

sem_acquire() blokuje (pokud je potřeba) až do získání semaforu. Proces pokoušející se získat semafor, který už získal bude blokovat navěky, pokud by získání tohoto semaforu způsobilo překročení jeho hodnoty *max_acquire*.

Po zpracování požadavku se všechny získané, ale explicitně neuvolněné semaforey uvolní automaticky, a vygeneruje se varování.

Viz také: *sem_get()* a *sem_release()*.

sem_get (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Získat id semaforu

```
int sem_get ( int key [, int max_acquire [, int perm]]) \linebreak
```

Vrací identifikátor semaforu nebo FALSE.

sem_get() vrací id, které se dá použít k přístupu k System V semaforu s daným klíčem. Podle potřeby se vytvoří nový semafor s přístupovými právy definovanými v *perm* (default je 0666). Počet procesů, které mohou tento semafor získat současně je *max_acquire* (default je 1). Tato hodnota je ale nastavena pouze pokud tento proces zjistí, že k tomuto semaforu není současně připojen jiný proces.

Druhé volání **sem_get()** se stejným *key* vrátí jiný identifikátor semaforu, ale oba identifikátory ukazují na stejný semafor.

Viz také: *sem_acquire()* a *sem_release()*.

Poznámka: Tato funkce nefunguje na Windows.

sem_release (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Uvolnit semafor

```
int sem_release ( int sem_identifier ) \linebreak
```

Při úspěchu vrátí TRUE, jinak FALSE.

sem_release() uvolní semafor, pokud ho volající proces drží, jinak se vygeneruje varování.

Po uvolnění může být semafor znovu získán pomocí *sem_acquire()*.

Viz také: *sem_get()* a *sem_acquire()*.

Poznámka: Tato funkce nefunguje na Windows.

shm_attach (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Vytvořit nebo otevřít segment sdílené paměti

```
int shm_attach ( int key [, int memsize [, int perm]]) \linebreak
```

shm_attach() vrací id, které se dá použít k přístupu k System V sdílené paměti s daným klíčem; první volání vytvoří segment paměti o velikosti *mem_size* (default: *sysvshm.init_mem* v konfiguračním souboru, jinak 10000 bytů) a s volitelnými právy (default: 0666).

Druhé volání **shm_attach()** se stejným *key* vrátí jiný identifikátor, ale oba ukazují na stejnou sdílenou paměť. *memsize* a *perm* se v takovém případě ignorují.

Poznámka: Tato funkce nefunguje na Windows.

shm_detach (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Odpojit se od segmentu sdílené paměti

```
int shm_detach ( int shm_identifier) \linebreak
```

shm_detach() odpojuje od sdílené paměti identifikované *shm_identifier* vytvořeným *shm_attach()*. Pamatujte, že tato sdílená paměť dál existuje a drží si data.

shm_get_var (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Vrátit proměnnou ze sdílené paměti

```
mixed shm_get_var ( int id, int variable_key) \linebreak
```

shm_get_var() vrací proměnnou s daným *variable_key*. Proměnná zůstává ve sdílené paměti.

Poznámka: Tato funkce nefunguje na Windows.

shm_put_var (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Vložit nebo modifikovat proměnnou do sdílené paměti

```
int shm_put_var ( int shm_identifier, int variable_key, mixed variable) \linebreak
```

Vloží nebo modifikuje *variable* s daným *variable_key*. Všechny typy proměnných (double, int, string, array) jsou podporovány.

Poznámka: Tato funkce nefunguje na Windows.

shm_remove (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Odstranit sdílenou paměť ze systému

int **shm_remove** (int shm_identifier) \linebreak

Odstraní sdílenou paměť z UNIXového systému. Všechna data v ní budou zničena.

Poznámka: Tato funkce nefunguje na Windows.

shm_remove_var (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Odstranit proměnnou ze sdílené paměti

int **shm_remove_var** (int id, int variable_key) \linebreak

Odstraní proměnnou s daným *variable_key* a uvolní zabranou paměť.

Poznámka: Tato funkce nefunguje na Windows.

XC. SESAM database functions

SESAM/SQL-Server is a mainframe database system, developed by Fujitsu Siemens Computers, Germany. It runs on high-end mainframe servers using the operating system BS2000/OSD.

In numerous productive BS2000 installations, SESAM/SQL-Server has proven ...

- the ease of use of Java-, Web- and client/server connectivity,
- the capability to work with an availability of more than 99.99%,
- the ability to manage tens and even hundreds of thousands of users.

Now there is a PHP3 SESAM interface available which allows database operations via PHP-scripts.

Configuration notes: There is no standalone support for the PHP SESAM interface, it works only as an integrated Apache module. In the Apache PHP module, this SESAM interface is configured using Apache directives.

Tabulka 1. SESAM Configuration directives

Directive	Meaning
<code>php3_sesam_oml</code>	<p>Name of BS2000 PLAM library containing the loadable SESAM driver modules. Required for using SESAM functions. Example:</p> <pre>php3_sesam_oml \$.SYSLNK.SESAM-SQL.030</pre>
<code>php3_sesam_configfile</code>	<p>Name of SESAM application configuration file. Required for using SESAM functions. Example:</p> <pre>php3_sesam_configfile \$SESAM.SESAM.CONF.AW</pre> <p>It will usually contain a configuration like (see SESAM reference manual):</p> <pre>CNF=B NAM=K NOTYPE</pre>
<code>php3_sesam_messagecatalog</code>	<p>Name of SESAM message catalog file. In most cases, this directive is not necessary. Only if the SESAM message file is not installed in the system's BS2000 message file table, it can be set with this directive. Example:</p> <pre>php3_sesam_messagecatalog \$.SYSMES.SESAM-SQL.030</pre>

In addition to the configuration of the PHP/SESAM interface, you have to configure the SESAM-Database server itself on your mainframe as usual. That means:

- starting the SESAM database handler (DBH), and
- connecting the databases with the SESAM database handler

To get a connection between a PHP script and the database handler, the `CNF` and `NAM` parameters of the selected SESAM configuration file must match the id of the started database handler.

In case of distributed databases you have to start a SESAM/SQL-DCN agent with the distribution table including the host and database names.

The communication between PHP (running in the POSIX subsystem) and the database handler (running outside the POSIX subsystem) is realized by a special driver module called SQLSCI and SESAM connection modules using common memory. Because of the common memory access, and because PHP is a static part of the web server, database accesses are very fast, as they do not require remote accesses via ODBC, JDBC or UTM.

Only a small stub loader (SESMOD) is linked with PHP, and the SESAM connection modules are pulled in from SESAM's OML PLAM library. In the configuration, you must tell PHP the name of this PLAM library, and the file link to use for the SESAM configuration file (As of SESAM V3.0, SQLSCI is available in the SESAM Tool Library, which is part of the standard distribution).

Because the SQL command quoting for single quotes uses duplicated single quotes (as opposed to a single quote preceded by a backslash, used in some other databases), it is advisable to set the PHP configuration directives `php3_magic_quotes_gpc` and `php3_magic_quotes_sybase` to `On` for all PHP scripts using the SESAM interface.

Runtime considerations: Because of limitations of the BS2000 process model, the driver can be loaded only after the Apache server has forked off its server child processes. This will slightly slow down the initial SESAM request of each child, but subsequent accesses will respond at full speed.

When explicitly defining a Message Catalog for SESAM, that catalog will be loaded each time the driver is loaded (i.e., at the initial SESAM request). The BS2000 operating system prints a message after successful load of the message catalog, which will be sent to Apache's `error_log` file. BS2000 currently does not allow suppression of this message, it will slowly fill up the log.

Make sure that the SESAM OML PLAM library and SESAM configuration file are readable by the user id running the web server. Otherwise, the server will be unable to load the driver, and will not allow to call any SESAM functions. Also, access to the database must be granted to the user id under which the Apache server is running. Otherwise, connections to the SESAM database handler will fail.

Cursor Types: The result cursors which are allocated for SQL "select type" queries can be either "sequential" or "scrollable". Because of the larger memory overhead needed by "scrollable" cursors, the default is "sequential".

When using "scrollable" cursors, the cursor can be freely positioned on the result set. For each "scrollable" query, there are global default values for the scrolling type (initialized to: `SESAM_SEEK_NEXT`) and the scrolling offset which can either be set once by `sesam_seek_row()` or each time when fetching a row using `sesam_fetch_row()`. When fetching a row using a

"scrollable" cursor, the following post-processing is done for the global default values for the scrolling type and scrolling offset:

Tabulka 2. Scrolled Cursor Post-Processing

Scroll Type	Action
SESAM_SEEK_NEXT	none
SESAM_SEEK_PRIOR	none
SESAM_SEEK_FIRST	set scroll type to SESAM_SEEK_NEXT
SESAM_SEEK_LAST	set scroll type to SESAM_SEEK_PRIOR
SESAM_SEEK_ABSOLUTE	Auto-Increment internal offset value
SESAM_SEEK_RELATIVE	none. (maintain global default <i>offset</i> value, which allows for, e.g., fetching each 10th row backwards)

Porting note: Because in the PHP world it is natural to start indexes at zero (rather than 1), some adaptations have been made to the SESAM interface: whenever an indexed array is starting with index 1 in the native SESAM interface, the PHP interface uses index 0 as a starting point. E.g., when retrieving columns with `sesam_fetch_row()`, the first column has the index 0, and the subsequent columns have indexes up to (but not including) the column count (`$array["count"]`). When porting SESAM applications from other high level languages to PHP, be aware of this changed interface. Where appropriate, the description of the respective php sesam functions include a note that the index is zero based.

Security concerns: When allowing access to the SESAM databases, the web server user should only have as little privileges as possible. For most databases, only read access privilege should be granted. Depending on your usage scenario, add more access rights as you see fit. Never allow full control to any database for any user from the 'net! Restrict access to php scripts which must administer the database by using password control and/or SSL security.

Migration from other SQL databases: No two SQL dialects are ever 100% compatible. When porting SQL applications from other database interfaces to SESAM, some adaption may be required. The following typical differences should be noted:

- Vendor specific data types

Some vendor specific data types may have to be replaced by standard SQL data types (e.g., `TEXT` could be replaced by `VARCHAR(max. size)`).

- Keywords as SQL identifiers

In SESAM (as in standard SQL), such identifiers must be enclosed in double quotes (or

renamed).

- Display length in data types

SESAM data types have a precision, not a display length. Instead of `int(4)` (intended use: integers up to '9999'), SESAM requires simply `int` for an implied size of 31 bits. Also, the only datetime data types available in SESAM are: `DATE`, `TIME(3)` and `TIMESTAMP(3)`.

- SQL types with vendor-specific `unsigned`, `zerofill`, or `auto_increment` attributes

`Unsigned` and `zerofill` are not supported. `Auto_increment` is automatic (use `"INSERT ... VALUES(*, ...)"` instead of `"... VALUES(0, ...)"` to take advantage of SESAM-implied auto-increment.

- `int ... DEFAULT '0000'`

Numeric variables must not be initialized with string constants. Use **DEFAULT 0** instead. To initialize variables of the datetime SQL data types, the initialization string must be prefixed with the respective type keyword, as in: `CREATE TABLE exmpl (xtime timestamp(3) DEFAULT TIMESTAMP '1970-01-01 00:00:00.000' NOT NULL);`

- `$count = xxxx_num_rows();`

Some databases promise to guess/estimate the number of the rows in a query result, even though the returned value is grossly incorrect. SESAM does not know the number of rows in a query result before actually fetching them. If you REALLY need the count, try **SELECT COUNT(...) WHERE ...**, it will tell you the number of hits. A second query will (hopefully) return the results.

- **DROP TABLE thename;**

In SESAM, in the **DROP TABLE** command, the table name must be either followed by the keyword `RESTRICT` or `CASCADE`. When specifying `RESTRICT`, an error is returned if there are dependent objects (e.g., `VIEWS`), while with `CASCADE`, dependent objects will be deleted along with the specified table.

Notes on the use of various SQL types: SESAM does not currently support the `BLOB` type. A future version of SESAM will have support for `BLOB`.

At the PHP interface, the following type conversions are automatically applied when retrieving SQL fields:

Tabulka 3. SQL to PHP Type Conversions

SQL Type	PHP Type
SMALLINT, INTEGER	integer
NUMERIC, DECIMAL, FLOAT, REAL, DOUBLE	float
DATE, TIME, TIMESTAMP	string
VARCHAR, CHARACTER	string

When retrieving a complete row, the result is returned as an array. Empty fields are not filled in, so you will have to check for the existence of the individual fields yourself (use `isset()` or `empty()` to test for empty fields). That allows more user control over the appearance of empty fields (than in the case of an empty string as the representation of an empty field).

Support of SESAM's "multiple fields" feature: The special "multiple fields" feature of SESAM allows a column to consist of an array of fields. Such a "multiple field" column can be created like this:

Příklad 1. Creating a "multiple field" column

```
CREATE TABLE multi_field_test (
    pkey CHAR(20) PRIMARY KEY,
    multi(3) CHAR(12)
)
```

and can be filled in using:

Příklad 2. Filling a "multiple field" column

```
INSERT INTO multi_field_test (pkey, multi(2..3) )
VALUES ( 'Second', <'first_val', 'second_val'>)
```

Note that (like in this case) leading empty sub-fields are ignored, and the filled-in values are collapsed, so that in the above example the result will appear as `multi(1..2)` instead of `multi(2..3)`.

When retrieving a result row, "multiple columns" are accessed like "inlined" additional columns. In the example above, "pkey" will have the index 0, and the three "multi(1..3)" columns will be accessible as indices 1 through 3.

For specific SESAM details, please refer to the SESAM/SQL-Server documentation (english) (http://its.siemens.de/lobs/its/techinf/oltp/sesam/manuals/index_en.htm) or the SESAM/SQL-Server documentation (german) (http://its.siemens.de/lobs/its/techinf/oltp/sesam/manuals/index_gr.htm), both available online, or use the respective manuals.

sesam_affected_rows (PHP 3 CVS only)

Get number of rows affected by an immediate query

int sesam_affected_rows (string *result_id*) \linebreak

result_id is a valid result id returned by *sesam_query()*.

Returns the number of rows affected by a query associated with *result_id*.

The **sesam_affected_rows()** function can only return useful values when used in combination with "immediate" SQL statements (updating operations like INSERT, UPDATE and DELETE) because SESAM does not deliver any "affected rows" information for "select type" queries. The number returned is the number of affected rows.

See also: *sesam_query()* and *sesam_execimm()*

```
$result = sesam_execimm ("DELETE FROM PHONE WHERE LASTNAME = '".strtoupper ($name)."'");
if (!$result) {
    ... error ...
}
print sesam_affected_rows ($result).
    " entries with last name ".$name." deleted.\n"
```

sesam_commit (PHP 3 CVS only)

Commit pending updates to the SESAM database

bool sesam_commit (void) \linebreak

Returns: TRUE on success, FALSE on errors

sesam_commit() commits any pending updates to the database.

Note that there is no "auto-commit" feature as in other databases, as it could lead to accidental data loss. Uncommitted data at the end of the current script (or when calling *sesam_disconnect()*) will be discarded by an implied *sesam_rollback()* call.

See also: *sesam_rollback()*.

Příklad 1. Committing an update to the SESAM database

```
<?php
if (sesam_connect ("mycatalog", "myschema", "otto")) {
    if (!sesam_execimm ("INSERT INTO mytable VALUES (*, 'Small Test', <0, 8, 15>)))
        die("insert failed");
    if (!sesam_commit())
        die("commit failed");
}
?>
```

sesam_connect (PHP 3 CVS only)

Open SESAM database connection

bool **sesam_connect** (string catalog, string schema, string user) \linebreak

Returns `TRUE` if a connection to the SESAM database was made, or `FALSE` on error.

sesam_connect() establishes a connection to an SESAM database handler task. The connection is always "persistent" in the sense that only the very first invocation will actually load the driver from the configured SESAM OML PLAM library. Subsequent calls will reuse the driver and will immediately use the given catalog, schema, and user.

When creating a database, the "*catalog*" name is specified in the SESAM configuration directive `//ADD-SQL-DATABASE-CATALOG-LIST ENTRY-1 = *CATALOG(CATALOG-NAME = catalogname,...)`

The "*schema*" references the desired database schema (see SESAM handbook).

The "*user*" argument references one of the users which are allowed to access this "*catalog*" / "*schema*" combination. Note that "*user*" is completely independent from both the system's user id's and from HTTP user/password protection. It appears in the SESAM configuration only.

See also `sesam_disconnect()`.

Příklad 1. Connect to a SESAM database

```
<?php
if (!sesam_connect ("mycatalog", "myschema", "otto")
    die("Unable to connect to SESAM");
?>
```

sesam_diagnostic (PHP 3 CVS only)

Return status information for last SESAM call

array **sesam_diagnostic** (void) \linebreak

Returns an associative array of status and return codes for the last SQL query/statement/command. Elements of the array are:

Element	Contents
---------	----------

Tabulka 1. Status information returned by sesam_diagnostic()

Element	Contents
\$array["sqlstate"]	5 digit SQL return code (see the SESAM manual for the description of the possible values of SQLSTATE)
\$array["rowcount"]	number of affected rows in last update/insert/delete (set after "immediate" statements only)
\$array["errmsg"]	"human readable" error message string (set after errors only)
\$array["errcol"]	error column number of previous error (0-based; or -1 if undefined. Set after errors only)
\$array["errlin"]	error line number of previous error (0-based; or -1 if undefined. Set after errors only)

In the following example, a syntax error (E SEW42AE ILLEGAL CHARACTER) is displayed by including the offending SQL statement and pointing to the error location:

Příklad 1. Displaying SESAM error messages with error position

```
<?php
// Function which prints a formatted error message,
// displaying a pointer to the syntax error in the
// SQL statement
function PrintReturncode ($exec_str) {
    $err = Sesam_Diagnostic();
    $colspan=4; // 4 cols for: sqlstate, errlin, errcol, rowcount
    if ($err["errlin"] == -1)
        --$colspan;
    if ($err["errcol"] == -1)
        --$colspan;
    if ($err["rowcount"] == 0)
        --$colspan;
    echo "<TABLE BORDER>\n";
    echo "<TR><TH COLSPAN=".$colspan."><FONT COLOR=red>ERROR:</FONT> ".
    htmlspecialchars($err["errmsg"])."</TH></TR>\n";
    if ($err["errcol"] >= 0) {
        echo "<TR><TD COLSPAN=".$colspan."><PRE>\n";
        $errstmt = $exec_str."\n";
        for ($lin=0; $errstmt != ""; ++$lin) {
            if ($lin != $err["errlin"]) { // $lin is less or greater than errlin
                if (!( $i = strchr ($errstmt, "\n")))
                    $i = "";
                $line = substr ($errstmt, 0, strlen($errstmt)-strlen($i)+1);
                $errstmt = substr($i, 1);
                if ($line != "\n")
                    print htmlspecialchars ($line);
            } else {
                if (!( $i = strchr ($errstmt, "\n")))

```



```

        $i = "";
        $line = substr ($errstmt, 0, strlen ($errstmt)-strlen($i)+1);
        $errstmt = substr($i, 1);
        for ($col=0; $col < $err["errcol"]; ++$col)
            echo (substr($line, $col, 1) == "\t") ? "\t" : ".";
        echo "<FONT COLOR=RED><BLINK>\\</BLINK></FONT>\n";
        print "<FONT COLOR=\"#880000\">".htmlspecialchars($line)."</FONT>";
        for ($col=0; $col < $err["errcol"]; ++$col)
            echo (substr ($line, $col, 1) == "\t") ? "\t" : ".";
        echo "<FONT COLOR=RED><BLINK></BLINK></FONT>\n";
    }
}
echo "</PRE></TD></TR>\n";
}
echo "<TR>\n";
echo " <TD>sqlstate=" . $err["sqlstate"] . "</TD>\n";
if ($err["errlin"] != -1)
    echo " <TD>errlin=" . $err["errlin"] . "</TD>\n";
if ($err["errcol"] != -1)
    echo " <TD>errcol=" . $err["errcol"] . "</TD>\n";
if ($err["rowcount"] != 0)
    echo " <TD>rowcount=" . $err["rowcount"] . "</TD>\n";
echo "</TR>\n";
echo "</TABLE>\n";
}

if (!sesam_connect ("mycatalog", "phoneno", "otto"))
    die ("cannot connect");

$stmt = "SELECT * FROM phone\n".
        " WHERE@ LASTNAME='KRAEMER'\n".
        " ORDER BY FIRSTNAME";
if (!($result = sesam_query ($stmt)))
    PrintReturncode ($stmt);
?>

```

See also: `sesam_errormsg()` for simple access to the error string only

sesam_disconnect (PHP 3 CVS only)

Detach from SESAM connection

bool sesam_disconnect (void) \linebreak

Returns: always TRUE.

sesam_disconnect() closes the logical link to a SESAM database (without actually disconnecting and unloading the driver).

Note that this isn't usually necessary, as the open connection is automatically closed at the end of the script's execution. Uncommitted data will be discarded, because an implicit `sesam_rollback()` is executed.

sesam_disconnect() will not close the persistent link, it will only invalidate the currently defined "*catalog*", "*schema*" and "*user*" triple, so that any sesam function called after **sesam_disconnect()** will fail.

See also: **sesam_connect()**.

Příklad 1. Closing a SESAM connection

```
if (sesam_connect ("mycatalog", "myschema", "otto")) {
    ... some queries and stuff ...
    sesam_disconnect();
}
```

sesam_errormsg (PHP 3 CVS only)

Returns error message of last SESAM call

string **sesam_errormsg** (void) \linebreak

Returns the SESAM error message associated with the most recent SESAM error.

```
if (!sesam_execimm ($stmt))
    printf ("%s<br>\n", sesam_errormsg());
```

See also: **sesam_diagnostic()** for the full set of SESAM SQL status information

sesam_execimm (PHP 3 CVS only)

Execute an "immediate" SQL-statement

string **sesam_execimm** (string query) \linebreak

Returns: A SESAM "result identifier" on success, or FALSE on error.

sesam_execimm() executes an "immediate" statement (i.e., a statement like UPDATE, INSERT or DELETE which returns no result, and has no INPUT or OUTPUT variables). "select type" queries can not be used with **sesam_execimm()**. Sets the *affected_rows* value for retrieval by the **sesam_affected_rows()** function.

Note that **sesam_query()** can handle both "immediate" and "select-type" queries. Use **sesam_execimm()** only if you know beforehand what type of statement will be executed. An attempt to use SELECT type queries with **sesam_execimm()** will return `$err["sqlstate"] == "42SBW"`.

The returned "result identifier" can not be used for retrieving anything but the `sesam_affected_rows()`; it is only returned for symmetry with the `sesam_query()` function.

```
$stmt = "INSERT INTO mytable VALUES ('one', 'two')";
$result = sesam_execimm ($stmt);
$serr = sesam_diagnostic();
print ("sqlstate = ".$serr["sqlstate"]."\n".
       "Affected rows = ".$serr["rowcount"]." == ".
       sesam_affected_rows($result)."\n");
```

See also: `sesam_query()` and `sesam_affected_rows()`.

sesam_fetch_array (PHP 3 CVS only)

Fetch one row as an associative array

array **sesam_fetch_array** (string result_id [, int whence [, int offset]]) \linebreak

Returns an array that corresponds to the fetched row, or `FALSE` if there are no more rows.

sesam_fetch_array() is an alternative version of `sesam_fetch_row()`. Instead of storing the data in the numeric indices of the result array, it stores the data in associative indices, using the field names as keys.

result_id is a valid result id returned by `sesam_query()` (select type queries only!).

For the valid values of the optional *whence* and *offset* parameters, see the `sesam_fetch_row()` function for details.

sesam_fetch_array() fetches one row of data from the result associated with the specified result identifier. The row is returned as an associative array. Each result column is stored with an associative index equal to its column (aka. field) name. The column names are converted to lower case.

Columns without a field name (e.g., results of arithmetic operations) and empty fields are not stored in the array. Also, if two or more columns of the result have the same column names, the later column will take precedence. In this situation, either call `sesam_fetch_row()` or make an alias for the column.

```
SELECT TBL1.COL AS FOO, TBL2.COL AS BAR FROM TBL1, TBL2
```

A special handling allows fetching "multiple field" columns (which would otherwise all have the same column names). For each column of a "multiple field", the index name is constructed by appending the string "(n)" where n is the sub-index of the multiple field column, ranging from 1 to its declared repetition factor. The indices are NOT zero based, in order to match the nomenclature used in the respective query syntax. For a column declared as:

```
CREATE TABLE ... ( ... MULTI(3) INT )
```

the associative indices used for the individual "multiple field" columns would be "multi(1)", "multi(2)", and "multi(3)" respectively.

Subsequent calls to **sesam_fetch_array()** would return the next (or prior, or n'th next/prior, depending on the scroll attributes) row in the result set, or FALSE if there are no more rows.

Příklad 1. SESAM fetch array

```
<?php
$result = sesam_query ("SELECT * FROM phone\n".
    " WHERE LASTNAME='".strtoupper($name)."' \n".
    " ORDER BY FIRSTNAME", 1);

if (!$result) {
    ... error ...
}

// print the table:
print "<TABLE BORDER>\n";
while (($row = sesam_fetch_array ($result)) && count ($row) > 0) {
    print " <TR>\n";
    print " <TD>".htmlspecialchars ($row["firstname"])."</TD>\n";
    print " <TD>".htmlspecialchars ($row["lastname"])."</TD>\n";
    print " <TD>".htmlspecialchars ($row["phoneno"])."</TD>\n";
    print " </TR>\n";
}
print "</TABLE>\n";
sesam_free_result ($result);
?>
```

See also: **sesam_fetch_row()** which returns an indexed array.

sesam_fetch_result (PHP 3 CVS only)

Return all or part of a query result

mixed **sesam_fetch_result** (string result_id [, int max_rows]) \linebreak

Returns a mixed array with the query result entries, optionally limited to a maximum of *max_rows* rows. Note that both row and column indexes are zero-based.

Tabulka 1. Mixed result set returned by sesam_fetch_result()

Array Element	Contents
int \$arr["count"]	number of columns in result set (or zero if this was an "immediate" query)
int \$arr["rows"]	number of rows in result set (between zero and <i>max_rows</i>)

Array Element	Contents
bool \$arr["truncated"]	TRUE if the number of rows was at least <i>max_rows</i> , FALSE otherwise. Note that even when this is TRUE, the next sesam_fetch_result() call may return zero rows because there are no more result entries.
mixed \$arr[col][row]	result data for all the fields at row(<i>row</i>) and column(<i>col</i>), (where the integer index <i>row</i> is between 0 and \$arr["rows"]-1, and <i>col</i> is between 0 and \$arr["count"]-1). Fields may be empty, so you must check for the existence of a field by using the php <code>isset()</code> function. The type of the returned fields depend on the respective SQL type declared for its column (see SESAM overview for the conversions applied). SESAM "multiple fields" are "inlined" and treated like a sequence of columns.

Note that the amount of memory used up by a large query may be gigantic. Use the *max_rows* parameter to limit the maximum number of rows returned, unless you are absolutely sure that your result will not use up all available memory.

See also: `sesam_fetch_row()`, and `sesam_field_array()` to check for "multiple fields". See the description of the `sesam_query()` function for a complete example using **sesam_fetch_result()**.

sesam_fetch_row (PHP 3 CVS only)

Fetch one row as an array

array **sesam_fetch_row** (string *result_id* [, int *whence* [, int *offset*]]) \linebreak

Returns an array that corresponds to the fetched row, or FALSE if there are no more rows.

The number of columns in the result set is returned in an associative array element \$array["count"]. Because some of the result columns may be empty, the `count()` function can not be used on the result row returned by **sesam_fetch_row()**.

result_id is a valid result id returned by `sesam_query()` (select type queries only!).

whence is an optional parameter for a fetch operation on "scrollable" cursors, which can be set to the following predefined constants:

Tabulka 1. Valid values for "*whence*" parameter

Value	Constant	Meaning
0	SESAM_SEEK_NEXT	read sequentially (after fetch, the internal default is set to SESAM_SEEK_NEXT)
1	SESAM_SEEK_PRIOR	read sequentially backwards (after fetch, the internal default is set to SESAM_SEEK_PRIOR)

Value	Constant	Meaning
2	SESAM_SEEK_FIRST	rewind to first row (after fetch, the default is set to SESAM_SEEK_NEXT)
3	SESAM_SEEK_LAST	seek to last row (after fetch, the default is set to SESAM_SEEK_PRIOR)
4	SESAM_SEEK_ABSOLUTE	seek to absolute row number given as <i>offset</i> (Zero-based. After fetch, the internal default is set to SESAM_SEEK_ABSOLUTE, and the internal offset value is auto-incremented)
5	SESAM_SEEK_RELATIVE	seek relative to current scroll position, where <i>offset</i> can be a positive or negative offset value.

This parameter is only valid for "scrollable" cursors.

When using "scrollable" cursors, the cursor can be freely positioned on the result set. If the *whence* parameter is omitted, the global default values for the scrolling type (initialized to:

SESAM_SEEK_NEXT, and settable by `sesam_seek_row()`) are used. If *whence* is supplied, its value replaces the global default.

offset is an optional parameter which is only evaluated (and required) if *whence* is either SESAM_SEEK_RELATIVE or SESAM_SEEK_ABSOLUTE. This parameter is only valid for "scrollable" cursors.

sesam_fetch_row() fetches one row of data from the result associated with the specified result identifier. The row is returned as an array (indexed by values between 0 and `$array["count"]-1`). Fields may be empty, so you must check for the existence of a field by using the `php isset()` function. The type of the returned fields depend on the respective SQL type declared for its column (see SESAM overview for the conversions applied). SESAM "multiple fields" are "inlined" and treated like a sequence of columns.

Subsequent calls to **sesam_fetch_row()** would return the next (or prior, or n'th next/prior, depending on the scroll attributes) row in the result set, or `FALSE` if there are no more rows.

Příklad 1. SESAM fetch rows

```
<?php
$result = sesam_query ("SELECT * FROM phone\n".
    " WHERE LASTNAME='".strtoupper($name)."' \n".
    " ORDER BY FIRSTNAME", 1);

if (!$result) {
    ... error ...
}

// print the table in backward order
print "<TABLE BORDER>\n";
$row = sesam_fetch_row ($result, SESAM_SEEK_LAST);
while (is_array ($row)) {
    print " <TR>\n";
    for ($col = 0; $col < $row["count"]; ++$col) {
        print " <TD>".htmlspecialchars ($row[$col])."</TD>\n";
    }
}
```

```

    }
    print " </TR>\n";
    // use implied SESAM_SEEK_PRIOR
    $row = sesam_fetch_row ($result);
}
print "</TABLE>\n";
sesam_free_result ($result);
?>

```

See also: `sesam_fetch_array()` which returns an associative array, and `sesam_fetch_result()` which returns many rows per invocation.

sesam_field_array (PHP 3 CVS only)

Return meta information about individual columns in a result

array **sesam_field_array** (string *result_id*) \linebreak

result_id is a valid result id returned by `sesam_query()`.

Returns a mixed associative/indexed array with meta information (column name, type, precision, ...) about individual columns of the result after the query associated with *result_id*.

Tabulka 1. Mixed result set returned by `sesam_field_array()`

Array Element	Contents
int \$arr["count"]	Total number of columns in result set (or zero if this was an "immediate" query). SESAM "multiple fields" are "inlined" and treated like the respective number of columns.
string \$arr[col]["name"]	column name for column(<i>col</i>), where <i>col</i> is between 0 and \$arr["count"]-1. The returned value can be the empty string (for dynamically computed columns). SESAM "multiple fields" are "inlined" and treated like the respective number of columns, each with the same column name.
string \$arr[col]["count"]	The "count" attribute describes the repetition factor when the column has been declared as a "multiple field". Usually, the "count" attribute is 1. The first column of a "multiple field" column however contains the number of repetitions (the second and following column of the "multiple field" contain a "count" attribute of 1). This can be used to detect "multiple fields" in the result set. See the example shown in the <code>sesam_query()</code> description for a sample use of the "count" attribute.

Array Element	Contents
string \$arr[col]["type"]	<p>php variable type of the data for column(col), where col is between 0 and \$arr["count"]-1. The returned value can be one of</p> <ul style="list-style-type: none"> • integer • float • string <p>depending on the SQL type of the result. SESAM "multiple fields" are "inlined" and treated like the respective number of columns, each with the same php type.</p>
string \$arr[col]["sqltype"]	<p>SQL variable type of the column data for column(col), where col is between 0 and \$arr["count"]-1. The returned value can be one of</p> <ul style="list-style-type: none"> • "CHARACTER" • "VARCHAR" • "NUMERIC" • "DECIMAL" • "INTEGER" • "SMALLINT" • "FLOAT" • "REAL" • "DOUBLE" • "DATE" • "TIME" • "TIMESTAMP" <p>describing the SQL type of the result. SESAM "multiple fields" are "inlined" and treated like the respective number of columns, each with the same SQL type.</p>
string \$arr[col]["length"]	<p>The SQL "length" attribute of the SQL variable in column(col), where col is between 0 and \$arr["count"]-1. The "length" attribute is used with "CHARACTER" and "VARCHAR" SQL types to specify the (maximum) length of the string variable. SESAM "multiple fields" are "inlined" and treated like the respective number of columns, each with the same length attribute.</p>

Array Element	Contents
string \$arr[col]["precision"]	The "precision" attribute of the SQL variable in column(<i>col</i>), where <i>col</i> is between 0 and \$arr["count"]-1. The "precision" attribute is used with numeric and time data types. SESAM "multiple fields" are "inlined" and treated like the respective number of columns, each with the same precision attribute.
string \$arr[col]["scale"]	The "scale" attribute of the SQL variable in column(<i>col</i>), where <i>col</i> is between 0 and \$arr["count"]-1. The "scale" attribute is used with numeric data types. SESAM "multiple fields" are "inlined" and treated like the respective number of columns, each with the same scale attribute.

See the `sesam_query()` function for an example of the `sesam_field_array()` use.

sesam_field_name (PHP 3 CVS only)

Return one column name of the result set

```
int sesam_field_name ( string result_id, int index) \linebreak
```

Returns the name of a field (i.e., the column name) in the result set, or `FALSE` on error.

For "immediate" queries, or for dynamic columns, an empty string is returned.

Poznámka: The column index is zero-based, not one-based as in SESAM.

See also: `sesam_field_array()`. It provides an easier interface to access the column names and types, and allows for detection of "multiple fields".

sesam_free_result (PHP 3 CVS only)

Releases resources for the query

```
int sesam_free_result ( string result_id) \linebreak
```

Releases resources for the query associated with *result_id*. Returns `FALSE` on error.

sesam_num_fields (PHP 3 CVS only)

Return the number of fields/columns in a result set

int **sesam_num_fields** (string result_id) \linebreak

After calling `sesam_query()` with a "select type" query, this function gives you the number of columns in the result. Returns an integer describing the total number of columns (aka. fields) in the current *result_id* result set or FALSE on error.

For "immediate" statements, the value zero is returned. The SESAM "multiple field" columns count as their respective dimension, i.e., a three-column "multiple field" counts as three columns.

See also: `sesam_query()` and `sesam_field_array()` for a way to distinguish between "multiple field" columns and regular columns.

sesam_query (PHP 3 CVS only)

Perform a SESAM SQL query and prepare the result

string **sesam_query** (string query [, bool scrollable]) \linebreak

Returns: A SESAM "result identifier" on success, or FALSE on error.

A "result_id" resource is used by other functions to retrieve the query results.

sesam_query() sends a query to the currently active database on the server. It can execute both "immediate" SQL statements and "select type" queries. If an "immediate" statement is executed, then no cursor is allocated, and any subsequent `sesam_fetch_row()` or `sesam_fetch_result()` call will return an empty result (zero columns, indicating end-of-result). For "select type" statements, a result descriptor and a (scrollable or sequential, depending on the optional boolean *scrollable* parameter) cursor will be allocated. If *scrollable* is omitted, the cursor will be sequential.

When using "scrollable" cursors, the cursor can be freely positioned on the result set. For each "scrollable" query, there are global default values for the scrolling type (initialized to: `SESAM_SEEK_NEXT`) and the scrolling offset which can either be set once by `sesam_seek_row()` or each time when fetching a row using `sesam_fetch_row()`.

For "immediate" statements, the number of affected rows is saved for retrieval by the `sesam_affected_rows()` function.

See also: `sesam_fetch_row()` and `sesam_fetch_result()`.

Příklad 1. Show all rows of the "phone" table as a html table

```
<?php
if (!sesam_connect ("phonedb", "demo", "otto"))
    die ("cannot connect");
$result = sesam_query ("select * from phone");
if (!$result) {
    $err = sesam_diagnostic();
    die ($err["errmsg"]);
}
echo "<TABLE BORDER>\n";
// Add title header with column names above the result:
if ($cols = sesam_field_array ($result)) {
    echo " <TR><TH COLSPAN=". $cols["count"]. ">Result:</TH></TR>\n";
    echo " <TR>\n";
    for ($col = 0; $col < $cols["count"]; ++$col) {
        $colattr = $cols[$col];
```

```

/* Span the table head over SESAM's "Multiple Fields": */
if ($colattr["count"] > 1) {
    echo "    <TH COLSPAN=" . $colattr["count"] . ">" . $colattr["name"] .
        "(1.." . $colattr["count"] . ")</TH>\n";
    $col += $colattr["count"] - 1;
} else
    echo "    <TH>" . $colattr["name"] . "</TH>\n";
}
echo " </TR>\n";
}

do {
    // Fetch the result in chunks of 100 rows max.
    $ok = sesam_fetch_result ($result, 100);
    for ($row=0; $row < $ok["rows"]; ++$row) {
        echo " <TR>\n";
        for ($col = 0; $col < $ok["cols"]; ++$col) {
            if (isset($ok[$col][$row]))
                echo "    <TD>" . $ok[$col][$row] . "</TD>\n";
            } else {
                echo "    <TD>-empty-</TD>\n";
            }
        }
        echo " </TR>\n";
    }
}
while ($ok["truncated"]) { // while there may be more data
    echo "</TABLE>\n";
}
// free result id
sesam_free_result($result);
?>

```

sesam_rollback (PHP 3 CVS only)

Discard any pending updates to the SESAM database

bool **sesam_rollback** (void) \linebreak

Returns: TRUE on success, FALSE on errors

sesam_rollback() discards any pending updates to the database. Also affected are result cursors and result descriptors.

At the end of each script, and as part of the **sesam_disconnect()** function, an implied **sesam_rollback()** is executed, discarding any pending changes to the database.

See also: **sesam_commit()**.

Příklad 1. Discarding an update to the SESAM database

```

<?php
if (sesam_connect ("mycatalog", "myschema", "otto")) {
    if (sesam_execimm ("INSERT INTO mytable VALUES (*, 'Small Test', <0, 8, 15>)")
        && sesam_execimm ("INSERT INTO othertable VALUES (*, 'Another Test', 1)"))
        sesam_commit();
    else
        sesam_rollback();
}
?>

```

sesam_seek_row (PHP 3 CVS only)

Set scrollable cursor mode for subsequent fetches

bool **sesam_seek_row** (string result_id, int whence [, int offset]) \linebreak

result_id is a valid result id (select type queries only, and only if a "scrollable" cursor was requested when calling sesam_query()).

whence sets the global default value for the scrolling type, it specifies the scroll type to use in subsequent fetch operations on "scrollable" cursors, which can be set to the following predefined constants:

Tabulka 1. Valid values for "*whence*" parameter

Value	Constant	Meaning
0	SESAM_SEEK_NEXT	read sequentially
1	SESAM_SEEK_PRIOR	read sequentially backwards
2	SESAM_SEEK_FIRST	fetch first row (after fetch, the default is set to SESAM_SEEK_NEXT)
3	SESAM_SEEK_LAST	fetch last row (after fetch, the default is set to SESAM_SEEK_PRIOR)
4	SESAM_SEEK_ABSOLUTE	fetch absolute row number given as <i>offset</i> (Zero-based. After fetch, the default is set to SESAM_SEEK_ABSOLUTE, and the offset value is auto-incremented)

Value	Constant	Meaning
5	SESAM_SEEK_RELATIVE	fetch relative to current scroll position, where <i>offset</i> can be a positive or negative offset value (this also sets the default "offset" value for subsequent fetches).

offset is an optional parameter which is only evaluated (and required) if *whence* is either SESAM_SEEK_RELATIVE or SESAM_SEEK_ABSOLUTE.

sesam_settransaction (PHP 3 CVS only)

Set SESAM transaction parameters

bool **sesam_settransaction** (int isolation_level, int read_only) \linebreak

Returns: TRUE if the values are valid, and the **settransaction()** operation was successful, FALSE otherwise.

sesam_settransaction() overrides the default values for the "isolation level" and "read-only" transaction parameters (which are set in the SESAM configuration file), in order to optimize subsequent queries and guarantee database consistency. The overridden values are used for the next transaction only.

sesam_settransaction() can only be called before starting a transaction, not after the transaction has been started already.

To simplify the use in php scripts, the following constants have been predefined in php (see SESAM handbook for detailed explanation of the semantics):

Tabulka 1. Valid values for "*Isolation_Level*" parameter

Value	Constant	Meaning
1	SESAM_TXISOL_READ_UNCOMMITTED	Read Uncommitted
2	SESAM_TXISOL_READ_COMMITTED	Read Committed
3	SESAM_TXISOL_REPEATABLE_READ	Repeatable Read
4	SESAM_TXISOL_SERIALIZABLE	Serializable

Tabulka 2. Valid values for "*Read_Only*" parameter

Value	Constant	Meaning
0	SESAM_TXREAD_READWRITE	Read/Write
1	SESAM_TXREAD_READONLY	Read-Only

The values set by **sesam_settransaction()** will override the default setting specified in the SESAM configuration file.

Příklad 1. Setting SESAM transaction parameters

```
<?php
sesam_settransaction (SESAM_TXISOL_REPEATABLE_READ,
                      SESAM_TXREAD_READONLY) ;
?>
```

XCI. Session handling functions

Session support in PHP consists of a way to preserve certain data across subsequent accesses. This enables you to build more customized applications and increase the appeal of your web site.

If you are familiar with the session management of PHPLIB, you will notice that some concepts are similar to PHP's session support.

A visitor accessing your web site is assigned an unique id, the so-called session id. This is either stored in a cookie on the user side or is propagated in the URL.

The session support allows you to register arbitrary numbers of variables to be preserved across requests. When a visitor accesses your site, PHP will check automatically (if session.auto_start is set to 1) or on your request (explicitly through session_start() or implicitly through session_register()) whether a specific session id has been sent with the request. If this is the case, the prior saved environment is recreated.

All registered variables are serialized after the request finishes. Registered variables which are undefined are marked as being not defined. On subsequent accesses, these are not defined by the session module unless the user defines them later.

The track_vars and register_globals configuration settings influence how the session variables get stored and restored.

Poznámka: As of PHP 4.0.3, track_vars is always turned on.

Poznámka: As of PHP 4.1.0, \$_SESSION is available as global variable just like \$_POST, \$_GET, \$_REQUEST and so on. Not like \$HTTP_SESSION_VARS, \$_SESSION is always global. Therefore, global should not be used for \$_SESSION.

If track_vars is enabled and register_globals is disabled, only members of the global associative array \$HTTP_SESSION_VARS can be registered as session variables. The restored session variables will only be available in the array \$HTTP_SESSION_VARS.

Příklad 1. Registering a variable with track_vars enabled

```
<?php
session_start();
if (isset($HTTP_SESSION_VARS['count'])) {
    $HTTP_SESSION_VARS['count']++;
}
else {
    $HTTP_SESSION_VARS['count'] = 0;
}
?>
```

Use of \$_SESSION (or \$HTTP_SESSION_VARS with PHP 4.0.6 or less) is recommended for security and code readability. With \$_SESSION or \$HTTP_SESSION_VARS, there is no need to use

`session_register()/session_unregister()/session_is_registered()` functions. Users can access session variable like a normal variable.

Příklad 2. Registering a variable with `$_SESSION`.

```
<?php
session_start();
// Use $HTTP_SESSION_VARS with PHP 4.0.6 or less
if (!isset($_SESSION['count'])) {
    $_SESSION['count'] = 0;
} else {
    $_SESSION['count']++;
}
?>
```

Příklad 3. Unregistering a variable with `$_SESSION`.

```
<?php
session_start();
// Use $HTTP_SESSION_VARS with PHP 4.0.6 or less
unset($_SESSION['count']);
?>
```

If `register_globals` is enabled, then all global variables can be registered as session variables and the session variables will be restored to corresponding global variables. Since PHP must know which global variables are registered as session variables, users must register variables with `session_register()` function while `$HTTP_SESSION_VARS/$_SESSION` does not need to use `session_register()`.

Výstraha

If you are using `$HTTP_SESSION_VARS/$_SESSION` and disable `register_globals`, do not use `session_register()`, `session_is_registered()` and `session_unregister()`.

If you enable `register_globals`, `session_unregister()` should be used since session variables are registered as global variables when session data is deserialized. Disabling `register_globals` is recommended for both security and performance reason.

Příklad 4. Registering a variable with `register_globals` enabled

```
<?php
if (!session_is_registered('count')) {
    session_register("count");
    $count = 0;
}
```



```

else {
    $count++;
}
?>

```

If both `track_vars` and `register_globals` are enabled, then the global variables and the `$HTTP_SESSION_VARS/$_SESSION` entries will reference the same value for already registered variables.

If user use `session_register()` to register session variable, `$HTTP_SESSION_VARS/$_SESSION` will not have these variable in array until it is loaded from session storage. (i.e. until next request)

There are two methods to propagate a session id:

- Cookies
- URL parameter

The session module supports both methods. Cookies are optimal, but since they are not reliable (clients are not bound to accept them), we cannot rely on them. The second method embeds the session id directly into URLs.

PHP is capable of doing this transparently when compiled with `--enable-trans-sid`. If you enable this option, relative URIs will be changed to contain the session id automatically. Alternatively, you can use the constant `SID` which is defined, if the client did not send the appropriate cookie. `SID` is either of the form `session_name=session_id` or is an empty string.

The following example demonstrates how to register a variable, and how to link correctly to another page using `SID`.

Příklad 5. Counting the number of hits of a single user

```

<?php
if (!session_is_registered('count')) {
    session_register('count');
    $count = 1;
}
else {
    $count++;
}
?>

```

```

Hello visitor, you have seen this page <?php echo $count; ?> times.<p>;

```

```

<?php
# the <?php echo SID?> (<?=SID?> can be used if short tag is enabled)
# is necessary to preserve the session id
# in the case that the user has disabled cookies
?>

```

```

To continue, <A HREF="nextpage.php?<?php echo SID?>">click here</A>

```

The `<?=SID?>` is not necessary, if `--enable-trans-sid` was used to compile PHP.

Poznámka: Non-relative URLs are assumed to point to external sites and hence don't append the SID, as it would be a security risk to leak the SID to a different server.

To implement database storage, or any other storage method, you will need to use `session_set_save_handler()` to create a set of user-level storage functions.

The session management system supports a number of configuration options which you can place in your `php.ini` file. We will give a short overview.

- `session.save_handler` defines the name of the handler which is used for storing and retrieving data associated with a session. Defaults to `files`.
- `session.save_path` defines the argument which is passed to the save handler. If you choose the default files handler, this is the path where the files are created. Defaults to `/tmp`. If `session.save_path`'s path depth is more than 2, garbage collection will not be performed.

Varování

If you leave this set to a world-readable directory, such as `/tmp` (the default), other users on the server may be able to hijack sessions by getting the list of files in that directory.

- `session.name` specifies the name of the session which is used as cookie name. It should only contain alphanumeric characters. Defaults to `PHPSESSID`.
- `session.auto_start` specifies whether the session module starts a session automatically on request startup. Defaults to 0 (disabled).
- `session.cookie_lifetime` specifies the lifetime of the cookie in seconds which is sent to the browser. The value 0 means "until the browser is closed." Defaults to 0.
- `session.serialize_handler` defines the name of the handler which is used to serialize/deserialize data. Currently, a PHP internal format (name `php`) and WDDX is supported (name `wddx`). WDDX is only available, if PHP is compiled with WDDX support. Defaults to `php`.
- `session.gc_probability` specifies the probability that the gc (garbage collection) routine is started on each request in percent. Defaults to 1.
- `session.gc_maxlifetime` specifies the number of seconds after which data will be seen as 'garbage' and cleaned up.
- `session.referer_check` contains the substring you want to check each HTTP Referer for. If the Referer was sent by the client and the substring was not found, the embedded session id will be marked as invalid. Defaults to the empty string.
- `session.entropy_file` gives a path to an external resource (file) which will be used as an additional entropy source in the session id creation process. Examples are `/dev/random` or

`/dev/urandom` which are available on many Unix systems.

- `session.entropy_length` specifies the number of bytes which will be read from the file specified above. Defaults to 0 (disabled).
- `session.use_cookies` specifies whether the module will use cookies to store the session id on the client side. Defaults to 1 (enabled).
- `session.cookie_path` specifies path to set in `session_cookie`. Defaults to `/`.
- `session.cookie_domain` specifies domain to set in `session_cookie`. Default is none at all.
- `session.cache_limiter` specifies cache control method to use for session pages (none/nocache/private/private_no_expire/public). Defaults to `nocache`.
- `session.cache_expire` specifies time-to-live for cached session pages in minutes, this has no effect for `nocache` limiter. Defaults to 180.
- `session.use_trans_sid` whether transparent sid support is enabled or not if enabled by compiling with `--enable-trans-sid`. Defaults to 1 (enabled).
- `url_rewriter.tags` specifies which html tags are rewritten to include session id if transparent sid support is enabled. Defaults to
`a=href,area=href,frame=src,input=src,form=fakeentry`

Poznámka: Session handling was added in PHP 4.0.

session_cache_expire (PHP 4 >= 4.2.0)

Return current cache expire

```
int session_cache_expire ( [int new_cache_expire]) \linebreak
```

session_cache_expire() returns current cache expire. If *new_cache_expire* is given, the current cache expire is replaced with *new_cache_expire*.

session_cache_limiter (PHP 4 >= 4.0.3)

Get and/or set the current cache limiter

```
string session_cache_limiter ( [string cache_limiter]) \linebreak
```

session_cache_limiter() returns the name of the current cache limiter. If *cache_limiter* is specified, the name of the current cache limiter is changed to the new value.

The cache limiter controls the cache control HTTP headers sent to the client. These headers determine the rules by which the page content may be cached. Setting the cache limiter to `nocache`, for example, would disallow any client-side caching. A value of `public`, however, would permit caching. It can also be set to `private`, which is slightly more restrictive than `public`.

In `private` mode, `Expires` header sent to the client, may cause confusion for some browser including Mozilla. You can avoid this problem with `private_no_expire` mode. `Expires` header is never sent to the client in this mode.

Poznámka: `private_no_expire` was added in PHP 4.2.0dev.

The cache limiter is reset to the default value stored in `session.cache_limiter` at request startup time. Thus, you need to call **session_cache_limiter()** for every request (and before `session_start()` is called).

Příklad 1. session_cache_limiter() examples

```
<?php

# set the cache limiter to 'private'

session_cache_limiter('private');
$cache_limiter = session_cache_limiter();

echo "The cache limiter is now set to $cache_limiter<p>";
?>
```

session_decode (PHP 4 >= 4.0.0)

Decodes session data from a string

bool **session_decode** (string *data*) \linebreak

session_decode() decodes the session data in *data*, setting variables stored in the session.

session_destroy (PHP 4 >= 4.0.0)

Destroys all data registered to a session

bool **session_destroy** (void) \linebreak

session_destroy() destroys all of the data associated with the current session. It does not unset any of the global variables associated with the session, or unset the session cookie.

This function returns TRUE on success and FALSE on failure to destroy the session data.

Příklad 1. Destroying a session

```

<?php

// Initialize the session.
// If you are using session_name("something"), don't forget it now!
session_start();
// Unset all of the session variables.
session_unset();
// Finally, destroy the session.
session_destroy();

?>

```

Příklad 2. Destroying a session with \$_SESSION

```

<?php

// Initialize the session.
// If you are using session_name("something"), don't forget it now!
session_start();
// Unset all of the session variables.
$_SESSION = array();
// Finally, destroy the session.
session_destroy();

?>

```

session_encode (PHP 4 >= 4.0.0)

Encodes the current session data as a string

string **session_encode** (void) \linebreak

session_encode() returns a string with the contents of the current session encoded within.

session_get_cookie_params (PHP 4 >= 4.0.0)

Get the session cookie parameters

array **session_get_cookie_params** (void) \linebreak

The **session_get_cookie_params()** function returns an array with the current session cookie information, the array contains the following items:

- "lifetime" - The lifetime of the cookie.
- "path" - The path where information is stored.
- "domain" - The domain of the cookie.
- "secure" - The cookie should only be sent over secure connections. (This item was added in PHP 4.0.4.)

session_id (PHP 4 >= 4.0.0)

Get and/or set the current session id

string **session_id** ([string id]) \linebreak

session_id() returns the session id for the current session. If *id* is specified, it will replace the current session id.

The constant SID can also be used to retrieve the current name and session id as a string suitable for adding to URLs.

session_is_registered (PHP 4 >= 4.0.0)

Find out if a variable is registered in a session

bool **session_is_registered** (string name) \linebreak

session_is_registered() returns TRUE if there is a variable with the name *name* registered in the current session.

Poznámka: If `$_SESSION` (or `$HTTP_SESSION_VARS` for PHP 4.0.6 or less) is used, use `isset()` to check a variable is registered in `$_SESSION`.

Výstraha

If you are using `$HTTP_SESSION_VARS`/`$_SESSION`, do not use `session_register()`, **`session_is_registered()`** and `session_unregister()`.

session_module_name (PHP 4 >= 4.0.0)

Get and/or set the current session module

string **session_module_name** ([string module]) \linebreak

session_module_name() returns the name of the current session module. If *module* is specified, that module will be used instead.

session_name (PHP 4 >= 4.0.0)

Get and/or set the current session name

string **session_name** ([string name]) \linebreak

session_name() returns the name of the current session. If *name* is specified, the name of the current session is changed to its value.

The session name references the session id in cookies and URLs. It should contain only alphanumeric characters; it should be short and descriptive (i.e. for users with enabled cookie warnings). The session name is reset to the default value stored in `session.name` at request startup time. Thus, you need to call **session_name()** for every request (and before `session_start()` or `session_register()` are called).

Příklad 1. session_name() examples

```
<?php

// set the session name to WebsiteID

$previous_name = session_name("WebsiteID");

echo "The previous session name was $previous_name<p>";
?>
```

session_readonly (unknown)

Begin session - reinitializes freed variables, but no writeback on request end

void **session_readonly** (void) \linebreak

Read in session data without locking the session data. Changing session data is not possible, but frameset performance will be improved.

session_register (PHP 4 >= 4.0.0)

Register one or more variables with the current session

bool **session_register** (mixed name [, mixed ...]) \linebreak

session_register() accepts a variable number of arguments, any of which can be either a string holding the name of a variable or an array consisting of variable names or other arrays. For each name, **session_register()** registers the global variable with that name in the current session.

Výstraha

This registers a *global* variable. If you want to register a session variable inside a function, you need to make sure to make it global using **global()** or use the session arrays as noted below.

Výstraha

If you are using `$HTTP_SESSION_VARS/$_SESSION`, do not use **session_register()**, **session_is_registered()** and **session_unregister()**.

This function returns `TRUE` when all of the variables are successfully registered with the session.

If `session_start()` was not called before this function is called, an implicit call to `session_start()` with no parameters will be made.

You can also create a session variable by simply setting the appropriate member of the `$HTTP_SESSION_VARS` or `$_SESSION` (PHP >= 4.1.0) array.

```
$barney = "A big purple dinosaur.";
session_register("barney");
```

```
$HTTP_SESSION_VARS["zim"] = "An invader from another planet.";
```

```
# the auto-global $_SESSION array was introduced in PHP 4.1.0
$_SESSION["spongebob"] = "He's got square pants.";
```


Poznámka: It is not currently possible to register resource variables in a session. For example, you can not create a connection to a database and store the connection id as a session variable and expect the connection to still be valid the next time the session is restored. PHP functions that return a resource are identified by having a return type of `resource` in their function definitions. A list of functions that return resources are available in the resource types appendix.

If `$_SESSION` (or `$HTTP_SESSION_VARS` for PHP 4.0.6 or less) is used, assign variable to `$_SESSION`. i.e. `$_SESSION['var'] = 'ABC';`

See also `session_is_registered()` and `session_unregister()`.

session_save_path (PHP 4 >= 4.0.0)

Get and/or set the current session save path

string **session_save_path** ([string path]) \linebreak

session_save_path() returns the path of the current directory used to save session data. If *path* is specified, the path to which data is saved will be changed.

Poznámka: On some operating systems, you may want to specify a path on a filesystem that handles lots of small files efficiently. For example, on Linux, reiserfs may provide better performance than ext2fs.

session_set_cookie_params (PHP 4 >= 4.0.0)

Set the session cookie parameters

void **session_set_cookie_params** (int lifetime [, string path [, string domain [, bool secure]]]) \linebreak

Set cookie parameters defined in the `php.ini` file. The effect of this function only lasts for the duration of the script.

Poznámka: The *secure* parameter was added in PHP 4.0.4.

session_set_save_handler (PHP 4 >= 4.0.0)

Sets user-level session storage functions

void **session_set_save_handler** (string open, string close, string read, string write, string destroy, string gc) \linebreak

session_set_save_handler() sets the user-level session storage functions which are used for storing and retrieving data associated with a session. This is most useful when a storage method other than those supplied by PHP sessions is preferred. i.e. Storing the session data in a local database.

Poznámka: You must set the configuration option *session.save_handler* to *user* in your *php.ini* file for **session_set_save_handler()** to take effect.

Poznámka: The "write" handler is not executed until after the output stream is closed. Thus, output from debugging statements in the "write" handler will never be seen in the browser. If debugging output is necessary, it is suggested that the debug output be written to a file instead.

The following example provides file based session storage similar to the PHP sessions default save handler *files*. This example could easily be extended to cover database storage using your favorite PHP supported database engine.

Read function must return string value always to make save handler work as expected. Return empty string if there is no data to read. Return values from other handlers are converted to boolean expression. TRUE for success, FALSE for failure.

Příklad 1. session_set_save_handler() example

```
<?php
function open ($save_path, $session_name) {
    global $sess_save_path, $sess_session_name;

    $sess_save_path = $save_path;
    $sess_session_name = $session_name;
    return(true);
}

function close() {
    return(true);
}

function read ($id) {
    global $sess_save_path, $sess_session_name;

    $sess_file = "$sess_save_path/sess_$id";
    if ($fp = @fopen($sess_file, "r")) {
        $sess_data = fread($fp, filesize($sess_file));
        return($sess_data);
    } else {
        return(""); // Must return "" here.
    }
}

function write ($id, $sess_data) {
    global $sess_save_path, $sess_session_name;

    $sess_file = "$sess_save_path/sess_$id";
```

```

        if ($fp = @fopen($sess_file, "w")) {
            return(fwrite($fp, $sess_data));
        } else {
            return(false);
        }
    }

}

function destroy ($id) {
    global $sess_save_path, $sess_session_name;

    $sess_file = "$sess_save_path/sess_$id";
    return(@unlink($sess_file));
}

/*****
 * WARNING - You will need to implement some *
 * sort of garbage collection routine here. *
 *****/
function gc ($maxlifetime) {
    return true;
}

session_set_save_handler ("open", "close", "read", "write", "destroy", "gc");

session_start();

// proceed to use sessions normally

?>

```

session_start (PHP 4 >= 4.0.0)

Initialize session data

bool **session_start** (void) \linebreak

session_start() creates a session (or resumes the current one based on the session id being passed via a GET variable or a cookie).

If you want to use a named session, you must call **session_name()** before calling **session_start()**.

This function always returns **TRUE**.

Poznámka: If you are using cookie-based sessions, you must call **session_start()** before anything is output to the browser.

session_start() will register internal output handler for URL rewriting when **trans-sid** is enabled. If a user uses **ob_gzhandler** or like with **ob_start()**, the order of output handler is important for proper output. For example, user must register **ob_gzhandler** before session start.

Poznámka: Use of `zlib.output_compression` is recommended rather than `ob_gzhandler`

session_unregister (PHP 4 >= 4.0.0)

Unregister a variable from the current session

bool **session_unregister** (string *name*) \linebreak

session_unregister() unregisters (forgets) the global variable named *name* from the current session.

This function returns `TRUE` when the variable is successfully unregistered from the session.

Poznámka: If `$_SESSION` (or `$HTTP_SESSION_VARS` for PHP 4.0.6 or less) is used, use `unset()` to unregister a session variable.

Výstraha

This function doesn't unset the corresponding global variable for *name*, it only prevents the variable from being saved as part of the session. You must call `unset()` to remove the corresponding global variable.

Výstraha

If you are using `$HTTP_SESSION_VARS`/`$_SESSION`, do not use `session_register()`, `session_is_registered()` and **`session_unregister()`**.

session_unset (PHP 4 >= 4.0.0)

Free all session variables

void **session_unset** (void) \linebreak

The **`session_unset()`** function free's all session variables currently registered.

Poznámka: If `$_SESSION` (or `$HTTP_SESSION_VARS` for PHP 4.0.6 or less) is used, use `unset()` to unregister session variable. i.e. `$_SESSION = array();`

session_write_close (PHP 4 >= 4.0.4)

Write session data and end session

void **session_write_close** (void) \linebreak

End the current session and store session data.

Session data is usually stored after your script terminated without the need to call **session_write_close()**, but as session data is locked to prevent concurrent writes only one script may operate on a session at any time. When using framesets together with sessions you will experience the frames loading one by one due to this locking. You can reduce the time needed to load all the frames by ending the session as soon as all changes to session variables are done.

XCII. Funkce pro práci se sdílenou pamětí

Shmop snadno použitelná sada funkcí, která PHP umožňuje číst, zapisovat, vytvářet a mazat segmenty UNIXové sdílené paměti. Tyto funkce na Windows nefungují, protože tento systém nepodporuje sdílenou paměť. Pokud chcete shmop používat, budete muset PHP zkompileovat s `--enable-shmop`.

Poznámka: Názvy funkcí popisovaných v této kapitole začínají v PHP 4.0.3 na **shm_()**, ale od PHP 4.0.4 se jejich názvy změnily na **shmop_()**.

Příklad 1. Přehled operací se sdílenou pamětí

```
<?php

// Vytvořit 100 bytový blok sdílené paměti se system id 0xff3
$shm_id = shmop_open(0xff3, "c", 0644, 100);
if(!$shm_id) {
echo "Nepodařilo se vytvořit segment sdílené paměti\n";
}

// Zjistit velikost bloku sdílené paměti
$shm_size = shmop_size($shm_id);
echo "SHM blok o velikosti : ".$shm_size. " byl vytvořen.\n";

// Zapišeme do sdílené paměti zkušební řetězec
$shm_bytes_written = shmop_write($shm_id, "my shared memory block", 0);
if($shm_bytes_written != strlen("můj blok sdílené paměti")) {
echo "Nepodařilo se zapsat kompletní data\n";
}

// Načteme řetězec zpátky
$my_string = shmop_read($shm_id, 0, $shm_size);
if(!$my_string) {
echo "Nepodařilo se číst z bloku sdílené paměti\n";
}
echo "Data ve sdílené paměti byla: ".$my_string."\n";

//Smažeme tento blok a zavřeme segment sdílené paměti
if(!shmop_delete($shm_id)) {
echo "Nepodařilo se smazat blok sdílené paměti.";
}
shmop_close($shm_id);

?>
```

shmop_close (PHP 4 >= 4.0.4)

Zavřít blok sdílené paměti

int **shmop_close** (int shmid) \linebreak

shmop_close() se používá k zavření bloku sdílené paměti.

shmop_close() přijímá *shmid*, což je identifikátor bloku sdílené paměti vytvořený funkcí **shmop_open()**.

Příklad 1. Zavření bloku sdílené paměti

```
<?php
shmop_close($shm_id);
?>
```

Tato ukázka zavře blok sdílené paměti pojmenovaný *\$shm_id*.

shmop_delete (PHP 4 >= 4.0.4)

Smazat blok sdílené paměti

int **shmop_delete** (int shmid) \linebreak

shmop_delete() se používá ke smazání bloku sdílené paměti.

shmop_delete() přijímá *shmid*, což je identifikátor bloku sdílené paměti vytvořený funkcí **shmop_open()**. Při úspěchu vrátí 1, jinak 0.

Příklad 1. Smazání bloku sdílené paměti

```
<?php
shmop_delete($shm_id);
?>
```

Tato ukázka smaže blok sdílené paměti pojmenovaný *\$shm_id*.

shmop_open (PHP 4 >= 4.0.4)

Vytvořit nebo otevřít blok sdílené paměti

int **shmop_open** (int key, string flags, int mode, int size) \linebreak

shmop_open() vytvoří nebo otevře blok sdílené paměti.

shmop_open() přijímá 4 argumenty: klíč, což je system id bloku sdílené paměti; tento argument může být předán jako desítkové nebo hexadecimální číslo. Druhý argument jsou parametry:

- "a" pro přístup (nastavuje IPC_EXCL) tento parametr použijte, pokud chcete otevřít existující segment sdílené paměti
- "c" pro vytvoření (nastavuje IPC_CREATE) tento parametr použijte, pokud chcete vytvořit nový segment sdílené paměti

Třetí argument je mód, což jsou přístupová práva, která chcete tomuto segmentu přiřadit; jsou stejná jako práva pro soubory. Přístupová práva musí být předána jako oktalové číslo, např. 0644. Poslední argument je velikost bloku sdílené paměti, který chcete vytvořit, v bytech.

Poznámka: Pozn.: Pokud otvíráte existující segment paměti, 3. 4. argument by měly být předány jako 0. Při úspěchu **shmop_open()** vrací id, které můžete použít k přístupu na tento segment sdílené paměti.

Příklad 1. Vytvoření bloku sdílené paměti

```
<?php
$shm_id = shmop_open(0x0fff, "c", 0644, 100);
?>
```

Tato ukázka otevřela blok sdílené paměti se system id 0x0fff.

shmop_read (PHP 4 >= 4.0.4)

Přečíst data z bloku sdílené paměti

string **shmop_read** (int shmid, int start, int count) \linebreak

shmop_read() čte řetězec z bloku sdílené paměti.

shmop_read() přijímá 3 argumenty: *shmid*, což je id bloku sdílené paměti vytvořeného funkcí **shmop_open()**, *start*, což je offset na kterém má čtení začít, a *count*, což je počet bytů, které se mají přečíst.

Příklad 1. Čtení bloku sdílené paměti

```
<?php
$shm_data = shmop_read($shm_id, 0, 50);
?>
```

Tato ukázka přečte z bloku sdílené paměti 50 bytů a umístí načtená data do *\$shm_data*.

shmop_write (PHP 4 >= 4.0.4)

Zapsat data do bloku sdílené paměti

```
int shmop_write ( int shmid, string data, int offset) \linebreak
```

shmop_write() zapíše řetězec do bloku sdílené paměti.

shmop_write() přijímá 3 argumenty: *shmid*, což je id bloku sdílené paměti vytvořeného funkcí **shmop_open()**, *data*, což je řetězec, který se zapíše do bloku sdílené paměti, a *offset*, což je offset na kterém má zápis začít.

Příklad 1. Zápis do bloku sdílené paměti

```
<?php
$shm_bytes_written = shmop_write($shm_id, $my_string, 0);
?>
```

Tato ukázka zapíše data obsažená v *\$my_string* do bloku sdílené paměti, a *\$shm_bytes_written* obsahuje počet zapsaných bytů.

shmop_size (PHP 4 >= 4.0.4)

Zjistit velikost bloku sdílené paměti

```
int shmop_size ( int shmid) \linebreak
```

shmop_size() se používá ke zjištění velikosti bloku sdílené paměti v bytech.

shmop_size() přijímá *shmid*, což je identifikátor vytvořený funkcí **shmop_open()**. **shmop_size()** vrací integer představující počet bytů, které blok sdílené paměti zabírá.

Příklad 1. Zjištění velikosti bloku sdílené paměti

```
<?php
$shm_size = shmop_size($shm_id);
?>
```

Tato ukázka zapíše velikost bloku sdílené paměti určeného identifikátorem *\$shm_id* do *\$shm_size*.

XCIII. Shockwave Flash functions

PHP offers the ability to create Shockwave Flash files via Paul Haeberli's libswf module. You can download libswf at <ftp://ftp.sgi.com/cgi/graphics/grafica/flash>. Once you have libswf all you need to do is to configure `--with-swf[=DIR]` where DIR is a location containing the directories include and lib. The include directory has to contain the swf.h file and the lib directory has to contain the libswf.a file. If you unpack the libswf distribution the two files will be in one directory. Consequently you will have to copy the files to the proper location manually.

Once you've successfully installed PHP with Shockwave Flash support you can then go about creating Shockwave files from PHP. You would be surprised at what you can do, take the following code:

Příklad 1. SWF example

```
<?php
swf_openfile ("test.swf", 256, 256, 30, 1, 1, 1);
swf_ortho2 (-100, 100, -100, 100);
swf_defineline (1, -70, 0, 70, 0, .2);
swf_definerect (4, 60, -10, 70, 0, 0);
swf_definerect (5, -60, 0, -70, 10, 0);
swf_addcolor (0, 0, 0, 0);

swf_definefont (10, "Mod");
swf_fontsize (5);
swf_fontslant (10);
swf_definetext (11, "This be Flash wit PHP!", 1);

swf_pushmatrix ();
swf_translate (-50, 80, 0);
swf_placeobject (11, 60);
swf_popmatrix ();

for ($i = 0; $i < 30; $i++) {
    $p = $i/(30-1);
    swf_pushmatrix ();
    swf_scale (1-($p*.9), 1, 1);
    swf_rotate (60*$p, 'z');
    swf_translate (20+20*$p, $p/1.5, 0);
    swf_rotate (270*$p, 'z');
    swf_addcolor ($p, 0, $p/1.2, -$p);
    swf_placeobject (1, 50);
    swf_placeobject (4, 50);
    swf_placeobject (5, 50);
    swf_popmatrix ();
    swf_showframe ();
}

for ($i = 0; $i < 30; $i++) {
    swf_removeobject (50);
    if (($i%4) == 0) {
        swf_showframe ();
    }
}
```

```
swf_startdoaction ();  
swf_actionstop ();  
swf_enddoaction ();  
  
swf_closefile ();  
?>
```

Poznámka: SWF support was added in PHP 4 RC2.

The libswf does not have support for Windows. The development of that library has been stopped, and the source is not available to port it to another systems.

For up to date SWF support take a look at the MING functions.

swf_actiongeturl (PHP 4 >= 4.0.0)

Get a URL from a Shockwave Flash movie

```
void swf_actiongeturl ( string url, string target) \linebreak
```

The **swf_actionGetUrl()** function gets the URL specified by the parameter *url* with the target *target*.

swf_actiongotoframe (PHP 4 >= 4.0.0)

Play a frame and then stop

```
void swf_actiongotoframe ( int framenummer) \linebreak
```

The **swf_actionGotoFrame()** function will go to the frame specified by *framenummer*, play it, and then stop.

swf_actiongotolabel (PHP 4 >= 4.0.0)

Display a frame with the specified label

```
void swf_actiongotolabel ( string label) \linebreak
```

The **swf_actionGotoLabel()** function displays the frame with the label given by the *label* parameter and then stops.

swf_actionnextframe (PHP 4 >= 4.0.0)

Go foward one frame

```
void swf_actionnextframe ( void) \linebreak
```

Go foward one frame.

swf_actionplay (PHP 4 >= 4.0.0)

Start playing the flash movie from the current frame

```
void swf_actionplay ( void) \linebreak
```

Start playing the flash movie from the current frame.

swf_actionprevframe (PHP 4 >= 4.0.0)

Go backwards one frame

```
void swf_actionprevframe ( void) \linebreak
```

swf_actionsettarget (PHP 4 >= 4.0.0)

Set the context for actions

```
void swf_actionsettarget ( string target) \linebreak
```

The **swf_actionSetTarget()** function sets the context for all actions. You can use this to control other flash movies that are currently playing.

swf_actionstop (PHP 4 >= 4.0.0)

Stop playing the flash movie at the current frame

```
void swf_actionstop ( void) \linebreak
```

Stop playing the flash movie at the current frame.

swf_actiontogglequality (PHP 4 >= 4.0.0)

Toggle between low and high quality

```
void swf_actiontogglequality ( void) \linebreak
```

Toggle the flash movie between high and low quality.

swf_actionwaitforframe (PHP 4 >= 4.0.0)

Skip actions if a frame has not been loaded

```
void swf_actionwaitforframe ( int framenummer, int skipcount) \linebreak
```

The **swf_actionWaitForFrame()** function will check to see if the frame, specified by the *framenummer* parameter has been loaded, if not it will skip the number of actions specified by the *skipcount* parameter. This can be useful for "Loading..." type animations.

swf_addbuttonrecord (PHP 4 >= 4.0.0)

Controls location, appearance and active area of the current button

```
void swf_addbuttonrecord ( int states, int shapeid, int depth) \linebreak
```

The **swf_addbuttonrecord()** function allows you to define the specifics of using a button. The first parameter, *states*, defines what states the button can have, these can be any or all of the following constants: BSHitTest, BSDown, BSOVer or BSUp. The second parameter, the *shapeid* is the look of the button, this is usually the object id of the shape of the button. The *depth* parameter is the placement of the button in the current frame.

Příklad 1. swf_addbuttonrecord() function example

```
swf_startButton ($objid, TYPE_MENUBUTTON);
    swf_addButtonRecord (BSDown|BSOver, $buttonImageId, 340);
    swf_onCondition (MenuEnter);
        swf_actionGetUrl ("http://www.designmultimedia.com", "_level1");
    swf_onCondition (MenuExit);
        swf_actionGetUrl ("", "_level1");
swf_endButton ();
```

swf_addcolor (PHP 4 >= 4.0.0)

Set the global add color to the rgba value specified

```
void swf_addcolor ( float r, float g, float b, float a) \linebreak
```

The **swf_addcolor()** function sets the global add color to the *rgba* color specified. This color is then used (implicitly) by the *swf_placeobject()*, *swf_modifyobject()* and the *swf_addbuttonrecord()* functions. The color of the object will be add by the *rgba* values when the object is written to the screen.

Poznámka: The *rgba* values can be either positive or negative.

swf_closefile (PHP 4 >= 4.0.0)

Close the current Shockwave Flash file

```
void swf_closefile ( [int return_file]) \linebreak
```

Close a file that was opened by the *swf_openfile()* function. If the *return_file* parameter is set then the contents of the SWF file are returned from the function.

Příklad 1. Creating a simple flash file based on user input and outputting it and saving it in a database

```

<?php

// The $text variable is submitted by the
// user

// Global variables for database
// access (used in the swf_savedata() function)
$DBHOST = "localhost";
$DBUSER = "sterling";
$DBPASS = "secret";

swf_openfile ("php://stdout", 256, 256, 30, 1, 1, 1);

    swf_definefont (10, "Ligon-Bold");
        swf_fontsize (12);
        swf_fontslant (10);

    swf_definetext (11, $text, 1);

    swf_pushmatrix ();
        swf_translate (-50, 80, 0);
        swf_placeobject (11, 60);
    swf_popmatrix ();

    swf_showframe ();

    swf_startdoaction ();
        swf_actionstop ();
    swf_enddoaction ();

$data = swf_closefile (1);

$data ?
    swf_savedata ($data) :
    die ("Error could not save SWF file");

// void swf_savedata (string data)
// Save the generated file a database
// for later retrieval
function swf_savedata ($data)
{
    global $DBHOST,
        $DBUSER,
        $DBPASS;

    $dbh = @mysql_connect ($DBHOST, $DBUSER, $DBPASS);

    if (!$dbh) {
        die (sprintf ("Error [%d]: %s",
            mysql_errno (), mysql_error ()));
    }

    $stmt = "INSERT INTO swf_files (file) VALUES ('$data')";

```

```

    $sth = @mysql_query ($stmt, $dbh);

    if (!$sth) {
        die (sprintf ("Error [%d]: %s",
                      mysql_errno (), mysql_error ()));
    }

    @mysql_free_result ($sth);
    @mysql_close ($dbh);
}
?>

```

swf_definebitmap (PHP 4 >= 4.0.0)

Define a bitmap

```
void swf_definebitmap ( int objid, string image_name) \linebreak
```

The **swf_definebitmap()** function defines a bitmap given a GIF, JPEG, RGB or FI image. The image will be converted into a Flash JPEG or Flash color map format.

swf_definefont (PHP 4 >= 4.0.0)

Defines a font

```
void swf_definefont ( int fontid, string fontname) \linebreak
```

The **swf_definefont()** function defines a font given by the *fontname* parameter and gives it the id specified by the *fontid* parameter. It then sets the font given by *fontname* to the current font.

swf_defineline (PHP 4 >= 4.0.0)

Define a line

```
void swf_defineline ( int objid, float x1, float y1, float x2, float y2, float width) \linebreak
```

The **swf_defineline()** defines a line starting from the x coordinate given by *x1* and the y coordinate given by *y1* parameter. Up to the x coordinate given by the *x2* parameter and the y coordinate given by the *y2* parameter. It will have a width defined by the *width* parameter.

swf_definepoly (PHP 4 >= 4.0.0)

Define a polygon

```
void swf_definepoly ( int objid, array coords, int npoints, float width) \linebreak
```

The **swf_definepoly()** function defines a polygon given an array of x, y coordinates (the coordinates are defined in the parameter *coords*). The parameter *npoints* is the number of overall points that are contained in the array given by *coords*. The *width* is the width of the polygon's border, if set to 0.0 the polygon is filled.

swf_definerect (PHP 4 >= 4.0.0)

Define a rectangle

```
void swf_definerect ( int objid, float x1, float y1, float x2, float y2, float width) \linebreak
```

The **swf_definerect()** defines a rectangle with an upper left hand coordinate given by the x, *x1*, and the y, *y1*. And a lower right hand coordinate given by the x coordinate, *x2*, and the y coordinate, *y2*. Width of the rectangles border is given by the *width* parameter, if the width is 0.0 then the rectangle is filled.

swf_definetext (PHP 4 >= 4.0.0)

Define a text string

```
void swf_definetext ( int objid, string str, int docenter) \linebreak
```

Define a text string (the *str* parameter) using the current font and font size. The *docenter* is where the word is centered, if *docenter* is 1, then the word is centered in x.

swf_endbutton (PHP 4 >= 4.0.0)

End the definition of the current button

```
void swf_endbutton ( void) \linebreak
```

The **swf_endButton()** function ends the definition of the current button.

swf_enddoaction (PHP 4 >= 4.0.0)

End the current action

```
void swf_enddoaction ( void) \linebreak
```

Ends the current action started by the **swf_startdoaction()** function.

swf_endshape (PHP 4 >= 4.0.0)

Completes the definition of the current shape

```
void swf_endshape ( void) \linebreak
```

The **swf_endshape()** completes the definition of the current shape.

swf_endsymbol (PHP 4 >= 4.0.0)

End the definition of a symbol

```
void swf_endsymbol ( void) \linebreak
```

The **swf_endsymbol()** function ends the definition of a symbol that was started by the **swf_startsymbol()** function.

swf_fontsize (PHP 4 >= 4.0.0)

Change the font size

```
void swf_fontsize ( float size) \linebreak
```

The **swf_fontsize()** function changes the font size to the value given by the *size* parameter.

swf_fontslant (PHP 4 >= 4.0.0)

Set the font slant

```
void swf_fontslant ( float slant) \linebreak
```

Set the current font slant to the angle indicated by the *slant* parameter. Positive values create a forward slant, negative values create a negative slant.

swf_fonttracking (PHP 4 >= 4.0.0)

Set the current font tracking

```
void swf_fonttracking ( float tracking) \linebreak
```

Set the font tracking to the value specified by the *tracking* parameter. This function is used to increase the spacing between letters and text, positive values increase the space and negative values decrease the space between letters.

swf_getbitmapinfo (PHP 4 >= 4.0.0)

Get information about a bitmap

array **swf_getbitmapinfo** (int bitmapid) \linebreak

The **swf_getbitmapinfo()** function returns an array of information about a bitmap given by the *bitmapid* parameter. The returned array has the following elements:

- "size" - The size in bytes of the bitmap.
- "width" - The width in pixels of the bitmap.
- "height" - The height in pixels of the bitmap.

swf_getfontinfo (PHP 4 >= 4.0.0)

The height in pixels of a capital A and a lowercase x

array **swf_getfontinfo** (void) \linebreak

The **swf_getfontinfo()** function returns an associative array with the following parameters:

- Aheight - The height in pixels of a capital A.
- xheight - The height in pixels of a lowercase x.

swf_getframe (PHP 4 >= 4.0.0)

Get the frame number of the current frame

int **swf_getframe** (void) \linebreak

The **swf_getframe()** function gets the number of the current frame.

swf_labelframe (PHP 4 >= 4.0.0)

Label the current frame

void **swf_labelframe** (string name) \linebreak

Label the current frame with the name given by the *name* parameter.

swf_lookat (PHP 4 >= 4.0.0)

Define a viewing transformation

```
void swf_lookat ( float view_x, float view_y, float view_z, float reference_x, float reference_y, float reference_z, float twist) \linebreak
```

The **swf_lookat()** function defines a viewing transformation by giving the viewing position (the parameters *view_x*, *view_y*, and *view_z*) and the coordinates of a reference point in the scene, the reference point is defined by the *reference_x*, *reference_y*, and *reference_z* parameters. The *twist* controls the rotation along with viewer's z axis.

swf_modifyobject (PHP 4 >= 4.0.0)

Modify an object

```
void swf_modifyobject ( int depth, int how) \linebreak
```

Updates the position and/or color of the object at the specified depth, *depth*. The parameter *how* determines what is updated. *how* can either be the constant MOD_MATRIX or MOD_COLOR or it can be a combination of both (MOD_MATRIX|MOD_COLOR).

MOD_COLOR uses the current mulcolor (specified by the function **swf_mulcolor()**) and **addcolor** (specified by the function **swf_addcolor()**) to color the object. MOD_MATRIX uses the current matrix to position the object.

swf_mulcolor (PHP 4 >= 4.0.0)

Sets the global multiply color to the rgba value specified

```
void swf_mulcolor ( float r, float g, float b, float a) \linebreak
```

The **swf_mulcolor()** function sets the global multiply color to the *rgba* color specified. This color is then used (implicitly) by the **swf_placeobject()**, **swf_modifyobject()** and the **swf_addbuttonrecord()** functions. The color of the object will be multiplied by the *rgba* values when the object is written to the screen.

Poznámka: The *rgba* values can be either positive or negative.

swf_nextid (PHP 4 >= 4.0.0)

Returns the next free object id

```
int swf_nextid ( void) \linebreak
```

The **swf_nextid()** function returns the next available object id.

swf_oncondition (PHP 4 >= 4.0.0)

Describe a transition used to trigger an action list

```
void swf_oncondition ( int transition) \linebreak
```

The **swf_onCondition()** function describes a transition that will trigger an action list. There are several types of possible transitions, the following are for buttons defined as TYPE_MENUBUTTON:

- IdletoOverUp
- OverUptoIdle
- OverUptoOverDown
- OverDowntoOverUp
- IdletoOverDown
- OutDowntoIdle
- MenuEnter (IdletoOverUp|IdletoOverDown)
- MenuExit (OverUptoIdle|OverDowntoIdle)

For TYPE_PUSHBUTTON there are the following options:

- IdletoOverUp
- OverUptoIdle
- OverUptoOverDown
- OverDowntoOverUp
- OverDowntoOutDown
- OutDowntoOverDown
- OutDowntoIdle
- ButtonEnter (IdletoOverUp|OutDowntoOverDown)
- ButtonExit (OverUptoIdle|OverDowntoOutDown)

swf_openfile (PHP 4 >= 4.0.0)

Open a new Shockwave Flash file

```
void swf_openfile ( string filename, float width, float height, float framerate, float r, float g, float b) \linebreak
```

The **swf_openfile()** function opens a new file named *filename* with a width of *width* and a height of *height* a frame rate of *framerate* and background with a red color of *r* a green color of *g* and a blue color of *b*.

The **swf_openfile()** must be the first function you call, otherwise your script will cause a segfault. If you want to send your output to the screen make the filename: "php://stdout" (support for this is in 4.0.1 and up).

swf_ortho (PHP 4)

Defines an orthographic mapping of user coordinates onto the current viewport

```
void swf_ortho ( float xmin, float xmax, float ymin, float ymax, float zmin, float zmax) \linebreak
```

The **swf_ortho()** function defines a orthographic mapping of user coordinates onto the current viewport.

swf_ortho2 (PHP 4 >= 4.0.0)

Defines 2D orthographic mapping of user coordinates onto the current viewport

```
void swf_ortho2 ( float xmin, float xmax, float ymin, float ymax) \linebreak
```

The **swf_ortho2()** function defines a two dimensional orthographic mapping of user coordinates onto the current viewport, this defaults to one to one mapping of the area of the Flash movie. If a perspective transformation is desired, the **swf_perspective ()** function can be used.

swf_perspective (PHP 4 >= 4.0.0)

Define a perspective projection transformation

```
void swf_perspective ( float fovy, float aspect, float near, float far) \linebreak
```

The **swf_perspective()** function defines a perspective projection transformation. The *fovy* parameter is field-of-view angle in the y direction. The *aspect* parameter should be set to the aspect ratio of the viewport that is being drawn onto. The *near* parameter is the near clipping plane and the *far* parameter is the far clipping plane.

Poznámka: Various distortion artifacts may appear when performing a perspective projection, this is because Flash players only have a two dimensional matrix. Some are not to pretty.

swf_placeobject (PHP 4 >= 4.0.0)

Place an object onto the screen

```
void swf_placeobject ( int objid, int depth) \linebreak
```

Places the object specified by *objid* in the current frame at a depth of *depth*. The *objid* parameter and the *depth* must be between 1 and 65535.

This uses the current mulcolor (specified by **swf_mulcolor()**) and the current addcolor (specified by **swf_addcolor()**) to color the object and it uses the current matrix to position the object.

Poznámka: Full RGBA colors are supported.

swf_polarview (PHP 4 >= 4.0.0)

Define the viewer's position with polar coordinates

```
void swf_polarview ( float dist, float azimuth, float incidence, float twist) \linebreak
```

The **swf_polarview()** function defines the viewer's position in polar coordinates. The *dist* parameter gives the distance between the viewpoint to the world space origin. The *azimuth* parameter defines the azimuthal angle in the x,y coordinate plane, measured in distance from the y axis. The *incidence* parameter defines the angle of incidence in the y,z plane, measured in distance from the z axis. The incidence angle is defined as the angle of the viewport relative to the z axis. Finally the *twist* specifies the amount that the viewpoint is to be rotated about the line of sight using the right hand rule.

swf_popmatrix (PHP 4 >= 4.0.0)

Restore a previous transformation matrix

```
void swf_popmatrix ( void) \linebreak
```

The **swf_popmatrix()** function pushes the current transformation matrix back onto the stack.

swf_posround (PHP 4 >= 4.0.0)

Enables or Disables the rounding of the translation when objects are placed or moved

```
void swf_posround ( int round) \linebreak
```

The **swf_posround()** function enables or disables the rounding of the translation when objects are placed or moved, there are times when text becomes more readable because rounding has been enabled. The *round* is whether to enable rounding or not, if set to the value of 1, then rounding is enabled, if set to 0 then rounding is disabled.

swf_pushmatrix (PHP 4 >= 4.0.0)

Push the current transformation matrix back unto the stack

```
void swf_pushmatrix ( void) \linebreak
```

The **swf_pushmatrix()** function pushes the current transformation matrix back onto the stack.

swf_removeobject (PHP 4 >= 4.0.0)

Remove an object

```
void swf_removeobject ( int depth) \linebreak
```

Removes the object at the depth specified by *depth*.

swf_rotate (PHP 4 >= 4.0.0)

Rotate the current transformation

```
void swf_rotate ( float angle, string axis) \linebreak
```

The **swf_rotate()** rotates the current transformation by the angle given by the *angle* parameter around the axis given by the *axis* parameter. Valid values for the axis are 'x' (the x axis), 'y' (the y axis) or 'z' (the z axis).

swf_scale (PHP 4 >= 4.0.0)

Scale the current transformation

```
void swf_scale ( float x, float y, float z) \linebreak
```

The **swf_scale()** scales the x coordinate of the curve by the value of the *x* parameter, the y coordinate of the curve by the value of the *y* parameter, and the z coordinate of the curve by the value of the *z* parameter.

swf_setfont (PHP 4 >= 4.0.0)

Change the current font

```
void swf_setfont ( int fontid) \linebreak
```

The **swf_setfont()** sets the current font to the value given by the *fontid* parameter.

swf_setframe (PHP 4 >= 4.0.0)

Switch to a specified frame

```
void swf_setframe ( int framenum) \linebreak
```

The **swf_setframe()** changes the active frame to the frame specified by *framenum*.

swf_shapearc (PHP 4 >= 4.0.0)

Draw a circular arc

```
void swf_shapearc ( float x, float y, float r, float ang1, float ang2) \linebreak
```

The **swf_shapeArc()** function draws a circular arc from angle A given by the *ang1* parameter to angle B given by the *ang2* parameter. The center of the circle has an x coordinate given by the *x* parameter and a y coordinate given by the *y*, the radius of the circle is given by the *r* parameter.

swf_shapecurveto (PHP 4 >= 4.0.0)

Draw a quadratic bezier curve between two points

```
void swf_shapecurveto ( float x1, float y1, float x2, float y2) \linebreak
```

The **swf_shapecurveto()** function draws a quadratic bezier curve from the current location, though the x coordinate given by *x1* and the y coordinate given by *y1* to the x coordinate given by *x2* and the y coordinate given by *y2*. The current position is then set to the x,y coordinates given by the *x2* and *y2* parameters

swf_shapecurveto3 (PHP 4 >= 4.0.0)

Draw a cubic bezier curve

```
void swf_shapecurveto3 ( float x1, float y1, float x2, float y2, float x3, float y3) \linebreak
```

Draw a cubic bezier curve using the x,y coordinate pairs *x1, y1* and *x2,y2* as off curve control points and the x,y coordinate *x3, y3* as an endpoint. The current position is then set to the x,y coordinate pair given by *x3,y3*.

swf_shapefillbitmapclip (PHP 4 >= 4.0.0)

Set current fill mode to clipped bitmap

```
void swf_shapefillbitmapclip ( int bitmapid) \linebreak
```

Sets the fill to bitmap clipped, empty spaces will be filled by the bitmap given by the *bitmapid* parameter.

swf_shapefillbitmaptile (PHP 4 >= 4.0.0)

Set current fill mode to tiled bitmap

```
void swf_shapefillbitmaptile ( int bitmapid) \linebreak
```

Sets the fill to bitmap tile, empty spaces will be filled by the bitmap given by the *bitmapid* parameter (tiled).

swf_shapefilloff (PHP 4 >= 4.0.0)

Turns off filling

```
void swf_shapefilloff ( void ) \linebreak
```

The **swf_shapeFillOff()** function turns off filling for the current shape.

swf_shapefillsolid (PHP 4 >= 4.0.0)

Set the current fill style to the specified color

```
void swf_shapefillsolid ( float r, float g, float b, float a ) \linebreak
```

The **swf_shapeFillSolid()** function sets the current fill style to solid, and then sets the fill color to the values of the *rgba* parameters.

swf_shapelinesolid (PHP 4 >= 4.0.0)

Set the current line style

```
void swf_shapelinesolid ( float r, float g, float b, float a, float width ) \linebreak
```

The **swf_shapeLineSolid()** function sets the current line style to the color of the *rgba* parameters and width to the *width* parameter. If 0.0 is given as a width then no lines are drawn.

swf_shapelineto (PHP 4 >= 4.0.0)

Draw a line

```
void swf_shapelineto ( float x, float y ) \linebreak
```

The **swf_shapeLineTo()** draws a line to the x,y coordinates given by the *x* parameter & the *y* parameter. The current position is then set to the x,y parameters.

swf_shapemoveto (PHP 4 >= 4.0.0)

Move the current position

```
void swf_shapemoveto ( float x, float y ) \linebreak
```

The **swf_shapeMoveTo()** function moves the current position to the x coordinate given by the *x* parameter and the y position given by the *y* parameter.

swf_showframe (PHP 4 >= 4.0.0)

Display the current frame

```
void swf_showframe ( void) \linebreak
```

The **swf_showframe** function will output the current frame.

swf_startbutton (PHP 4 >= 4.0.0)

Start the definition of a button

```
void swf_startbutton ( int objid, int type) \linebreak
```

The **swf_startbutton()** function starts off the definition of a button. The *type* parameter can either be `TYPE_MENUBUTTON` or `TYPE_PUSHBUTTON`. The `TYPE_MENUBUTTON` constant allows the focus to travel from the button when the mouse is down, `TYPE_PUSHBUTTON` does not allow the focus to travel when the mouse is down.

swf_startdoaction (PHP 4 >= 4.0.0)

Start a description of an action list for the current frame

```
void swf_startdoaction ( void) \linebreak
```

The **swf_startdoaction()** function starts the description of an action list for the current frame. This must be called before actions are defined for the current frame.

swf_startshape (PHP 4 >= 4.0.0)

Start a complex shape

```
void swf_startshape ( int objid) \linebreak
```

The **swf_startshape()** function starts a complex shape, with an object id given by the *objid* parameter.

swf_startsymbol (PHP 4 >= 4.0.0)

Define a symbol

```
void swf_startsymbol ( int objid) \linebreak
```

Define an object id as a symbol. Symbols are tiny flash movies that can be played simultaneously. The *objid* parameter is the object id you want to define as a symbol.

swf_textwidth (PHP 4 >= 4.0.0)

Get the width of a string

```
float swf_textwidth ( string str) \linebreak
```

The **swf_textwidth()** function gives the width of the string, *str*, in pixels, using the current font and font size.

swf_translate (PHP 4 >= 4.0.0)

Translate the current transformations

```
void swf_translate ( float x, float y, float z) \linebreak
```

The **swf_translate()** function translates the current transformation by the *x*, *y*, and *z* values given.

swf_viewport (PHP 4 >= 4.0.0)

Select an area for future drawing

```
void swf_viewport ( float xmin, float xmax, float ymin, float ymax) \linebreak
```

The **swf_viewport()** function selects an area for future drawing for *xmin* to *xmax* and *ymin* to *ymax*, if this function is not called the area defaults to the size of the screen.

XCIV. SNMP functions

In order to use the SNMP functions on Unix you need to install the UCD SNMP (<http://net-snmp.sourceforge.net/>) package. On Windows these functions are only available on NT and not on Win95/98.

Important: In order to use the UCD SNMP package, you need to define NO_ZEROLENGTH_COMMUNITY to 1 before compiling it. After configuring UCD SNMP, edit config.h and search for NO_ZEROLENGTH_COMMUNITY. Uncomment the #define line. It should look like this afterwards:

```
#define NO_ZEROLENGTH_COMMUNITY 1
```

If you see strange segmentation faults in combination with SNMP commands, you did not follow the above instructions. If you do not want to recompile UCD SNMP, you can compile PHP with the --enable-ucd-snmp-hack switch which will work around the misfeature.

snmp_get_quick_print (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Fetch the current value of the UCD library's quick_print setting

```
bool snmp_get_quick_print ( void) \linebreak
```

Returns the current value stored in the UCD Library for quick_print. quick_print is off by default.

```
$quickprint = snmp_get_quick_print();
```

Above function call would return FALSE if quick_print is off, and TRUE if quick_print is on.

snmp_get_quick_print() is only available when using the UCD SNMP library. This function is not available when using the Windows SNMP library.

See: **snmp_set_quick_print()** for a full description of what quick_print does.

snmp_set_quick_print (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Set the value of quick_print within the UCD SNMP library

```
void snmp_set_quick_print ( bool quick_print) \linebreak
```

Sets the value of quick_print within the UCD SNMP library. When this is set (1), the SNMP library will return 'quick printed' values. This means that just the value will be printed. When quick_print is not enabled (default) the UCD SNMP library prints extra information including the type of the value (i.e. IPAddress or OID). Additionally, if quick_print is not enabled, the library prints additional hex values for all strings of three characters or less.

Setting quick_print is often used when using the information returned rather than displaying it.

```
snmp_set_quick_print(0);
$a = snmpget("127.0.0.1", "public", ".1.3.6.1.2.1.2.2.1.9.1");
echo "$a<BR>\n";
snmp_set_quick_print(1);
$a = snmpget("127.0.0.1", "public", ".1.3.6.1.2.1.2.2.1.9.1");
echo "$a<BR>\n";
```

The first value printed might be: 'Timeticks: (0) 0:00:00.00', whereas with quick_print enabled, just '0:00:00.00' would be printed.

By default the UCD SNMP library returns verbose values, quick_print is used to return only the value.

Currently strings are still returned with extra quotes, this will be corrected in a later release.

snmp_set_quick_print() is only available when using the UCD SNMP library. This function is not available when using the Windows SNMP library.

snmpget (PHP 3, PHP 4 >= 4.0.0)

Fetch an SNMP object

string **snmpget** (string hostname, string community, string object_id [, int timeout [, int retries]]) \linebreak

Returns SNMP object value on success and FALSE on error.

The **snmpget()** function is used to read the value of an SNMP object specified by the *object_id*. SNMP agent is specified by the *hostname* and the read community is specified by the *community* parameter.

```
$syscontact = snmpget("127.0.0.1", "public", "system.SysContact.0");
```

snmprealwalk (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Return all objects including their respective object id withing the specified one

array **snmprealwalk** (string host, string community, string object_id [, int timeout [, int retries]]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

snmpset (PHP 3>= 3.0.12, PHP 4 >= 4.0.0)

Set an SNMP object

bool **snmpset** (string hostname, string community, string object_id, string type, mixed value [, int timeout [, int retries]]) \linebreak

Sets the specified SNMP object value, returning TRUE on success and FALSE on error.

The **snmpset()** function is used to set the value of an SNMP object specified by the *object_id*. SNMP agent is specified by the *hostname* and the read community is specified by the *community* parameter.

snmpwalk (PHP 3, PHP 4 >= 4.0.0)

Fetch all the SNMP objects from an agent

array **snmpwalk** (string hostname, string community, string object_id [, int timeout [, int retries]]) \linebreak

Returns an array of SNMP object values starting from the *object_id* as root and FALSE on error.

snmpwalk() function is used to read all the values from an SNMP agent specified by the *hostname*. *Community* specifies the read community for that agent. A NULL *object_id* is taken as the root of the SNMP objects tree and all objects under that tree are returned as an array. If *object_id* is specified, all the SNMP objects below that *object_id* are returned.

```
$a = snmpwalk("127.0.0.1", "public", "");
```

Above function call would return all the SNMP objects from the SNMP agent running on localhost. One can step through the values with a loop

```
for ($i=0; $i < count($a); $i++) {
    echo $a[$i];
}
```

snmpwalkoid (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Query for a tree of information about a network entity

array **snmpwalkoid** (string hostname, string community, string object_id [, int timeout [, int retries]]) \linebreak

Returns an associative array with object ids and their respective object value starting from the *object_id* as root and FALSE on error.

snmpwalkoid() function is used to read all object ids and their respective values from an SNMP agent specified by the *hostname*. *Community* specifies the read *community* for that agent. A NULL *object_id* is taken as the root of the SNMP objects tree and all objects under that tree are returned as an array. If *object_id* is specified, all the SNMP objects below that *object_id* are returned.

The existence of **snmpwalkoid()** and **snmpwalk()** has historical reasons. Both functions are provided for backward compatibility.

```
$a = snmpwalkoid("127.0.0.1", "public", "");
```


Above function call would return all the SNMP objects from the SNMP agent running on localhost. One can step through the values with a loop

```
for (reset($a); $i = key($a); next($a)) {  
    echo "$i: $a[$i]<br>\n";  
}
```

XCV. Socket functions

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

The socket extension implements a low-level interface to the socket communication functions, providing the possibility to act as a socket server as well as a client.

The socket functions described here are part of an extension to PHP which must be enabled at compile time by giving the `--enable-sockets` option to **configure**.

For a more generic client-side socket interface, see `fsockopen()` and `pfssockopen()`.

When using these functions, it is important to remember that while many of them have identical names to their C counterparts, they often have different declarations. Please be sure to read the descriptions to avoid confusion.

That said, those unfamiliar with socket programming can still find a lot of useful material in the appropriate Unix man pages, and there is a great deal of tutorial information on socket programming in C on the web, much of which can be applied, with slight modifications, to socket programming in PHP.

Příklad 1. Socket example: Simple TCP/IP server

This example shows a simple talkback server. Change the address and port variables to suit your setup and execute. You may then connect to the server with a command similar to: **telnet 192.168.1.53 10000** (where the address and port match your setup). Anything you type will then be output on the server side, and echoed back to you. To disconnect, enter 'quit'.

```
#!/usr/local/bin/php -q
<?php
error_reporting (E_ALL);

/* Allow the script to hang around waiting for connections. */
set_time_limit (0);

/* Turn on implicit output flushing so we see what we're getting
 * as it comes in. */
ob_implicit_flush ();

$address = '192.168.1.53';
$port = 10000;

if (($sock = socket_create (AF_INET, SOCK_STREAM, 0)) < 0) {
    echo "socket_create() failed: reason: " . socket_strerror ($sock) . "\n";
}

if (($ret = socket_bind ($sock, $address, $port)) < 0) {
    echo "socket_bind() failed: reason: " . socket_strerror ($ret) . "\n";
}
```

```

if (($ret = socket_listen ($sock, 5)) < 0) {
    echo "socket_listen() failed: reason: " . socket_strerror ($ret) . "\n";
}

do {
    if (($msgsock = socket_accept($sock)) < 0) {
        echo "socket_accept() failed: reason: " . socket_strerror ($msgsock) . "\n";
        break;
    }
    /* Send instructions. */
    $msg = "\nWelcome to the PHP Test Server. \n" .
        "To quit, type 'quit'. To shut down the server type 'shutdown'. \n";
    socket_write($msgsock, $msg, strlen($msg));

    do {
        if (FALSE === ($buf = socket_read ($msgsock, 2048))) {
            echo "socket_read() failed: reason: " . socket_strerror ($ret) . "\n";
            break 2;
        }
        if (!$buf = trim ($buf)) {
            continue;
        }
        if ($buf == 'quit') {
            break;
        }
        if ($buf == 'shutdown') {
            socket_close ($msgsock);
            break 2;
        }
        $talkback = "PHP: You said '$buf'. \n";
        socket_write ($msgsock, $talkback, strlen ($talkback));
        echo "$buf\n";
    } while (true);
    socket_close ($msgsock);
} while (true);

socket_close ($sock);
?>

```

Příklad 2. Socket example: Simple TCP/IP client

This example shows a simple, one-shot HTTP client. It simply connects to a page, submits a HEAD request, echoes the reply, and exits.

```

<?php
error_reporting (E_ALL);

echo "<h2>TCP/IP Connection</h2>\n";

/* Get the port for the WWW service. */
$service_port = getservbyname ('www', 'tcp');

```

```

/* Get the IP address for the target host. */
$address = gethostbyname ('www.example.com');

/* Create a TCP/IP socket. */
$socket = socket_create (AF_INET, SOCK_STREAM, 0);
if ($socket < 0) {
    echo "socket_create() failed: reason: " . socket_strerror ($socket) . "\n";
} else {
    echo "OK.\n";
}

echo "Attempting to connect to '$address' on port '$service_port'...";
$result = socket_connect ($socket, $address, $service_port);
if ($result < 0) {
    echo "socket_connect() failed.\nReason: ($result) " . socket_strerror($result) . "\n";
} else {
    echo "OK.\n";
}

$in = "HEAD / HTTP/1.0\r\n\r\n";
$out = "";

echo "Sending HTTP HEAD request...";
socket_write ($socket, $in, strlen ($in));
echo "OK.\n";

echo "Reading response:\n\n";
while ($out = socket_read ($socket, 2048)) {
    echo $out;
}

echo "Closing socket...";
socket_close ($socket);
echo "OK.\n\n";
?>

```

socket_accept (PHP 4 >= 4.1.0)

Accepts a connection on a socket

```
int socket_accept ( resource socket) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

After the socket *socket* has been created using `socket_create()`, bound to a name with `socket_bind()`, and told to listen for connections with `socket_listen()`, this function will accept incoming connections on that socket. Once a successful connection is made, a new socket descriptor is returned, which may be used for communication. If there are multiple connections queued on the socket, the first will be used. If there are no pending connections, **socket_accept()** will block until a connection becomes present. If *socket* has been made non-blocking using `socket_set_blocking()` or `socket_set_nonblock()`, an error code will be returned.

The socket descriptor returned by **socket_accept()** may not be used to accept new connections. The original listening socket *socket*, however, remains open and may be reused.

Returns a new socket descriptor on success, or a negative error code on failure. This code may be passed to `socket_strerror()` to get a textual explanation of the error.

See also `socket_bind()`, `socket_connect()`, `socket_listen()`, `socket_create()`, and `socket_strerror()`.

socket_bind (PHP 4 >= 4.1.0)

Binds a name to a socket

```
int socket_bind ( resource socket, string address [, int port]) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

socket_bind() binds the name given in *address* to the socket described by *socket*, which must be a valid socket descriptor created with `socket_create()`.

The *address* parameter is either an IP address in dotted-quad notation (e.g. 127.0.0.1), if the socket is of the `AF_INET` family; or the pathname of a Unix-domain socket, if the socket family is `AF_UNIX`.

The *port* parameter is only used when connecting to an `AF_INET` socket, and designates the port on the remote host to which a connection should be made.

Returns zero on success, or a negative error code on failure. This code may be passed to `socket_strerror()` to get a textual explanation of the error.

See also `socket_connect()`, `socket_listen()`, `socket_create()`, and `socket_strerror()`.

socket_close (PHP 4 >= 4.1.0)

Closes a socket descriptor

bool **socket_close** (resource socket) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

socket_close() closes the file (or socket) descriptor given by *socket*.

Note that **socket_close()** should not be used on PHP file descriptors created with `fopen()`, `popen()`, `fsockopen()`, or **pssockopen()**; it is meant for sockets created with `socket_create()` or `socket_accept()`.

Returns `TRUE` on success, or `FALSE` if an error occurs (i.e., *socket* is invalid).

See also `socket_bind()`, `socket_listen()`, `socket_create()`, and `socket_strerror()`.

socket_connect (PHP 4 >= 4.1.0)

Initiates a connection on a socket

bool **socket_connect** (resource socket, string address [, int port]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Initiates a connection using the socket descriptor *socket*, which must be a valid socket descriptor created with `socket_create()`.

The *address* parameter is either an IP address in dotted-quad notation (e.g. 127.0.0.1), if the socket is of the `AF_INET` family; or the pathname of a Unix-domain socket, if the socket family is `AF_UNIX`.

The *port* parameter is only used when connecting to an `AF_INET` socket, and designates the port on the remote host to which a connection should be made.

Vrací `TRUE` při úspěchu, `FALSE` při selhání. This code may be passed to `socket_strerror()` to get a textual explanation of the error.

See also `socket_bind()`, `socket_listen()`, `socket_create()`, and `socket_strerror()`.

socket_create (PHP 4 >= 4.1.0)

Create a socket (endpoint for communication)

resource **socket_create** (int domain, int type, int protocol) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Creates a communication endpoint (a socket), and returns a descriptor to the socket.

The *domain* parameter sets the domain. Currently, AF_INET and AF_UNIX are understood.

The *type* parameter selects the socket type. This is one of SOCK_STREAM, SOCK_DGRAM, SOCK_SEQPACKET, SOCK_RAW, SOCK_RDM, or SOCK_PACKET.

protocol sets the protocol.

Returns a valid socket descriptor on success, or a negative error code on failure. This code may be passed to socket_strerror() to get a textual explanation of the error.

For more information on the usage of **socket_create()**, as well as on the meanings of the various parameters, see the Unix man page socket (2).

See also socket_accept(), socket_bind(), socket_connect(), socket_listen(), and socket_strerror().

socket_create_listen (PHP 4 >= 4.1.0)

Opens a socket on port to accept connections

resource **socket_create_listen** (int port [, int backlog]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_create_pair (PHP 4 >= 4.1.0)

Creates a pair of indistinguishable sockets and stores them in fds.

bool **socket_create_pair** (int domain, int type, int protocol, array &fd) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_fd_alloc (4.1.0 - 4.1.2 only)

Allocates a new file descriptor set

resource **socket_fd_alloc** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_fd_clear (4.1.0 - 4.1.2 only)

Clears (a) file descriptor(s) from a set

bool **socket_fd_clear** (resource set, mixed socket) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_fd_free (4.1.0 - 4.1.2 only)

Deallocates a file descriptor set

bool **socket_fd_free** (resource set) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_fd_isset (4.1.0 - 4.1.2 only)

Checks to see if a file descriptor is set within the file descriptor set

bool **socket_fd_isset** (resource set, resource socket) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_fd_set (4.1.0 - 4.1.2 only)

Adds (a) file descriptor(s) to a set

bool **socket_fd_set** (resource set, mixed socket) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_fd_zero (4.1.0 - 4.1.2 only)

Clears a file descriptor set

bool **socket_fd_zero** (resource set) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_getopt (PHP 4 >= 4.1.0)

Gets socket options for the socket

mixed **socket_getopt** (resource socket, int level, int optname) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_getpeername (PHP 4 >= 4.1.0)

Given an fd, stores a string representing sa.sin_addr and the value of sa.sin_port into addr and port describing the remote side of a socket

bool **socket_getpeername** (resource socket, string &addr [, int &port]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_getsockname (PHP 4 >= 4.1.0)

Given an fd, stores a string representing sa.sin_addr and the value of sa.sin_port into addr and port describing the local side of a socket

bool **socket_getsockname** (resource socket, string &addr [, int &port]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_iovec_add (PHP 4 >= 4.1.0)

Adds a new vector to the scatter/gather array

bool **socket_iovec_add** (resource iovec, int iov_len) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_iovec_alloc (PHP 4 >= 4.1.0)

...]) Builds a 'struct iovec' for use with sendmsg, recvmsg, writev, and readv

resource **socket_iovec_alloc** (int num_vectors [, int]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_iovec_delete (PHP 4 >= 4.1.0)

Deletes a vector from an array of vectors

bool **socket_iovec_delete** (resource iovec, int iov_pos) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_iovec_fetch (PHP 4 >= 4.1.0)

Returns the data held in the iovec specified by iovec_id[iovec_position]

string **socket_iovec_fetch** (resource iovec, int iovec_position) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_iovec_free (PHP 4 >= 4.1.0)

Frees the iovec specified by iovec_id

bool **socket_iovec_free** (resource iovec) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_iovec_set (PHP 4 >= 4.1.0)

Sets the data held in iovec_id[iovec_position] to new_val

bool **socket_iovec_set** (resource iovec, int iovec_position, string new_val) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_last_error (PHP 4 >= 4.1.0)

Returns/Clears the last error on the socket

int **socket_last_error** (resource socket) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_listen (PHP 4 >= 4.1.0)

Listens for a connection on a socket

int **socket_listen** (resource socket, int backlog) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

After the socket *socket* has been created using `socket_create()` and bound to a name with `socket_bind()`, it may be told to listen for incoming connections on *socket*. A maximum of *backlog* incoming connections will be queued for processing.

socket_listen() is applicable only to sockets with type `SOCK_STREAM` or `SOCK_SEQPACKET`.

Returns zero on success, or a negative error code on failure. This code may be passed to `socket_strerror()` to get a textual explanation of the error.

See also `socket_accept()`, `socket_bind()`, `socket_connect()`, `socket_create()`, and `socket_strerror()`.

socket_read (PHP 4 >= 4.1.0)

Reads from a socket

string **socket_read** (resource socket_des, int length [, int type]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

The function **socket_read()** reads from socket *socket_des* created by the `socket_accept()` function the number of bytes set by *length*. Otherwise you can use `\n`, `\t` or `\0` to end reading. Returns data, or FALSE if **socket_read()** failed.

Optional *type* parameter is a named constant:

- `PHP_BINARY_READ` - use the system **socket_read()** (Default in PHP $\geq 4.1.0$)
- `PHP_NORMAL_READ` - reading stops at `\n` or `\r`. (Default in PHP $\leq 4.0.6$)

See also `socket_accept()`, `socket_bind()`, `socket_connect()`, `socket_listen()`, `socket_strerror()`, and `socket_write()`.

socket_readv (PHP 4 $\geq 4.1.0$)

Reads from an fd, using the scatter-gather array defined by *iovec_id*

bool **socket_readv** (resource socket, resource *iovec_id*) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_recv (PHP 4 $\geq 4.1.0$)

Receives data from a connected socket

string **socket_recv** (resource socket, int len, int flags) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_recvfrom (PHP 4 >= 4.1.0)

Receives data from a socket, connected or not

int **socket_recvfrom** (resource socket, string &buf, int len, int flags, string &name [, int &port]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_recvmsg (PHP 4 >= 4.1.0)

Used to receive messages on a socket, whether connection-oriented or not

bool **socket_recvmsg** (resource socket, resource iovec, array &control, int &controllen, int &flags, string &addr [, int &port]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_select (PHP 4 >= 4.1.0)

Runs the select() system call on the sets mentioned with a timeout specified by tv_sec and tv_usec

int **socket_select** (resource read_fd, resource write_fd, resource except_fd, int tv_sec [, int tv_usec]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_send (PHP 4 >= 4.1.0)

Sends data to a connected socket

int **socket_send** (resource socket, string buf, int len, int flags) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_sendmsg (PHP 4 >= 4.1.0)

Sends a message to a socket, regardless of whether it is connection-oriented or not

bool **socket_sendmsg** (resource socket, resource iovec, int flags, string addr [, int port]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_sendto (PHP 4 >= 4.1.0)

Sends a message to a socket, whether it is connected or not

int **socket_sendto** (resource socket, string buf, int len, int flags, string addr [, int port]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_set_nonblock (PHP 4 >= 4.1.0)

Sets nonblocking mode for file descriptor fd

bool **socket_set_nonblock** (resource socket) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_setopt (PHP 4 >= 4.1.0)

Sets socket options for the socket

bool **socket_setopt** (resource socket, int level, int optname, int) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_shutdown (PHP 4 >= 4.1.0)

Shuts down a socket for receiving, sending, or both.

bool **socket_shutdown** (resource socket [, int how]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

socket_strerror (PHP 4 >= 4.1.0)

Return a string describing a socket error

string **socket_strerror** (int errno) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

socket_strerror() takes as its *errno* parameter the return value of one of the socket functions, and returns the corresponding explanatory text. This makes it a bit more pleasant to figure out why something didn't work; for instance, instead of having to track down a system include file to find out what '-111' means, you just pass it to **socket_strerror()**, and it tells you what happened.

Příklad 1. socket_strerror() example

```
<?php
if (($socket = socket_create (AF_INET, SOCK_STREAM, 0)) < 0) {
    echo "socket_create() failed: reason: " . socket_strerror ($socket) . "\n";
}

if (($ret = socket_bind ($socket, '127.0.0.1', 80)) < 0) {
    echo "socket_bind() failed: reason: " . socket_strerror ($ret) . "\n";
}
?>
```

The expected output from the above example (assuming the script is not run with root privileges):

```
bind() failed: reason: Permission denied
```

See also `socket_accept()`, `socket_bind()`, `socket_connect()`, `socket_listen()`, and `socket_create()`.

socket_write (PHP 4 >= 4.1.0)

Write to a socket

```
int socket_write ( resource socket_des, string &buffer, int length) \linebreak
```

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

The function **socket_write()** writes to the socket *socket_des* from *&buffer* the number of bytes set by *length*.

See also `socket_accept()`, `socket_bind()`, `socket_connect()`, `socket_listen()`, `socket_read()`, and `socket_strerror()`.

socket_writev (PHP 4 >= 4.1.0)

Writes to a file descriptor, fd, using the scatter-gather array defined by `iovec_id`

bool **socket_writev** (resource socket, resource iovec_id) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

XCVI. Funkce pro práci s řetězci

Všechny tyto funkce různými způsoby pracují s řetězci. Některé specializovanější funkce najdete v sekcích regulárních výrazů a manipulace s URL.

Informace o chování řetězců, zvláště v souvislosti s použitím jednoduchých uvozovek, dvojitéch uvozovek a escape sekvencí viz položku Řetězce v sekci Typy tohoto manuálu.

addslashes (PHP 4 >= 4.0.0)

Opatřit řetězec lomítky ve stylu jazyka C

string **addslashes** (string *str*, string *charlist*) \linebreak

Vrací řetězec se zpětnými lomítky před znaky, které jsou vypsané v argumentu *charlist*. XXX Escapes \n, \r atd. podobně jako v C, znaky s ASCII kódem nižším než 32 a vyšším než 126 se převedou na osmičkovou reprezentaci. V *charlist* můžete udat rozsah, např. "\0..\37", což by XXX escapoval všechny znaky s ASCII kódem mezi 0 a 31.

Příklad 1. Ukázka addslashes()

```
$escaped = addslashes ($not_escaped, "\0..\37!@\177..\377");
```

Poznámka: Přidáno v PHP4b3-dev.

Viz také: stripslashes(), stripslashes(), htmlspecialchars(), htmlspecialchars() a quotemeta().

addslashes (PHP 3, PHP 4 >= 4.0.0)

Opatřit řetězec lomítky

string **addslashes** (string *str*) \linebreak

Vrací řetězec se zpětnými lomítky před znaky, které potřebují XXX be quoted v databázových dotazech apod. Tyto znaky jsou jednoduchá uvozovka ('), dvojitá uvozovka ("), zpětné lomítko (\) a NUL (NULL byte).

Viz také: stripslashes(), htmlspecialchars() a quotemeta().

bin2hex (PHP 3>= 3.0.9, PHP 4 >= 4.0.0)

Převést binární data na hexadecimální reprezentaci

string **bin2hex** (string *str*) \linebreak

Vrací ASCII řetězec obsahující hexadecimální reprezentaci *str*. Konverze probíhá po bytech, horní slabika první.

chop (PHP 3, PHP 4 >= 4.0.0)

Odstranit netisknutelné znaky z konce řetězce

string **chop** (string str) \linebreak

Vrací předaný řetězec bez netisknutelných znaků (vč. konců řádku) na konci.

Příklad 1. Ukázka chop()

```
$trimmed = chop ($line);
```

Poznámka: **chop()** se liší do Perlowské funkce *chop()*, která z řetězce odstraňuje poslední znak.

Viz také: trim(), ltrim(), rtrim() a **chop()**.

chr (PHP 3, PHP 4 >= 4.0.0)

Vrátit určitý znak

string **chr** (int ascii) \linebreak

Vrací řetězec jednoho znaku obsahující znak specifikovaný argumentem *ascii*.

Příklad 1. Ukázka chr()

```
$str .= chr (27); /* přidá escape znak na konec $str */
```

```
/* Toto je většinou užitečnější */
```

```
$str = sprintf ("Řetězec končí escape znakem: %c", 27);
```

Tato funkce se doplňuje s funkcí ord(). Viz také: sprintf() s formátovacím řetězcem %c.

chunk_split (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Rozdělit řetězec na menší části

string **chunk_split** (string string [, int chunklen [, string end]]) \linebreak

Dá se použít k rozdělení řetězce na menší části, což může být užitečné např. při uvádění výstupu z base64_encode do souladu se sémantikou RFC 2045. Každých *chunklen* (defaultně 76) znaků vloží řetězec *end* (defaultně "\r\n"). Vrací nový řetězec, původní zůstává beze změny.

Příklad 1. Ukázka chunk_split()

```
# naformátuje $data s použitím RFC 2045 sémantiky
```

```
$new_string = chunk_split (base64_encode($data));
```

Tato funkce je výrazně rychlejší než `ereg_replace()`.

Poznámka: Tato funkce byla přidána v 3.0.6.

convert_cyr_string (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Převést z jedné znakové sady Azbuky do jiné

string **convert_cyr_string** (string str, string from, string to) \linebreak

Tato funkce převede daný řetězec z jedné znakové sady azbuky do jiné. Argumenty *from* a *to* jsou jednotlivé znaky, které představují zdrojovou a cílovou znakovou sadu Azbuky. Podporované typy jsou:

- k - koi8-r
- w - windows-1251
- i - iso8859-5
- a - x-cp866
- d - x-cp866
- m - x-mac-cyrillic

count_chars (PHP 4 >= 4.0.0)

Vrátit informace o znacích použitých v řetězci

mixed **count_chars** (string string [, mode]) \linebreak

Počítá počet výskytů všech byte hodnot (0..255) v *string* a vrací je různými způsoby. Volitelný argument *Mode* má defaultní hodnotu 0. V závislosti na *mode* vrací **count_chars()** jednu z následujících možností:

- 0 - pole s klíči tvořenými byte hodnotami a hodnotami tvořenými četností každého bytu.
- 1 - stejné jako 0, ale vrací pouze byte hodnoty s četností vyšší než nula.
- 2 - stejné jako 0, ale vrací pouze byte hodnoty s četností rovnou nule.
- 3 - vrací řetězec obsahující všechny použité byte hodnoty.
- 4 - vrací řetězec obsahující všechny nepoužité byte hodnoty.

Poznámka: Tato funkce byla přidána v PHP 4.0.

crc32 (PHP 4)

Spočítat crc32 XXX polynomial řetězce

```
int crc32 ( string str ) \linebreak
```

Generuje 32bitový XXX polynomial kontrolního součtu pro *str*. Obvykle se používá ke kontrole integrity přenášených dat.

Viz také: md5().

crypt (PHP 3, PHP 4 >= 4.0.0)

Zašifrovat řetězec algoritmem DES

```
string crypt ( string str [, string salt] ) \linebreak
```

crypt() zašifruje řetězec pomocí standardní Unixovské šifrovací metody DES. Argumenty jsou řetězec k zašifrování a volitelný dvouznakový XXX salt, na kterém se šifrování založí. Více informací viz Unixovská man stránka vaší crypt funkce.

Pokud není poskytnut XXX salt argument, PHP jej náhodně vygeneruje.

Některé operační systémy podporují více typů šifrování. Někdy se standardní DES šifrování nahrazuje šifrovacím algoritmem založeným na MD5. Typ šifrování se zvolí podle XXX salt argumentu. Při instalaci PHP zjistí schopnosti funkce crypt a XXX bude přijímat XXX salt pro jiné typy šifrování. Při absenci XXX salt PHP defaultně automaticky vygeneruje standardní dvouznakový DES XXX salt, nicméně pokud je defaultním typem šifrování na daném systému MD5, vygeneruje náhodný XXX salt kompatibilní s MD5. PHP vytváří konstantu CRYPT_SALT_LENGTH, která vám řekne, jestli se na váš systém hodí běžný dvouznakový XXX salt nebo delší dvanáctiznakový MD5 XXX salt.

Pokud používáte poskytnutý XXX salt, měli byste si být vědomi toho, že se generuje jednou. Pokud tuto funkci voláte rekurzivně, může to mít účinek na vzhled, a, do určité míry, bezpečnost.

U standardního DES šifrování **crypt()** přidá XXX salt jako první dva znaky výstupu.

Na systémech, kde funkce **crypt()** podporuje více typů šifrování se následující konstanty nastaví na 0 nebo 1 podle toho, jestli je daný typ dostupný:

- CRYPT_STD_DES - Standardní DES šifrování s dvouznakovým XXX SALT
- CRYPT_EXT_DES - Rozšířené DES šifrování s devítiznakovým XXX SALT
- CRYPT_MD5 - MD5 šifrování s dvanáctiznakovým XXX SALT začínajícím \$1\$
- CRYPT_BLOWFISH - Rozšířené DES šifrování s šestnáctiznakovým XXX SALT začínajícím \$2\$

Neexistuje žádná decrypt funkce, protože **crypt()** používá jednosměrný algoritmus.

Viz také: md5().

echo (unknown)

Vytisknout jeden nebo více řetězců

echo (string arg1 [, string argn...]) \linebreak

Outputs all parameters.

echo() vlastně není funkce (je to jazykový konstrukt), takže u něj nemusíte používat závorky.

Příklad 1. Ukázka echo()

```
echo "Hello World";
```

```
echo "Toto zabírá  
několik řádků. Konce řádků se  
vytisknou také";
```

```
echo "Toto zabírá\nněkolik řádků. Konce řádků se\nvytisknou také.";
```

Poznámka: Pokud chcete echo předat více argumentů, argumenty dokonce uzavřít nesmíte.

Viz také: print(), printf() a flush().

explode (PHP 3, PHP 4 >= 4.0.0)

Rozdělit řetězec na jiném řetězci

array **explode** (string separator, string string [, int limit]) \linebreak

Vrací pole řetězců, z nichž každý je částí argumentu *string* vzniklý jeho rozdělením na hranicích tvořených řetězcem *delim*. Pokud je definován *limit*, vrácené pole bude obsahovat maximálně *limit* prvků, a poslední prvek bude obsahovat celý zbytek *string*.

Poznámka: Argument *limit* byl přidán v PHP 4.0.1

Příklad 1. Ukázka explode()

```
$pizza = "piece1 piece2 piece3 piece4 piece5 piece6";  
$pieces = explode (" ", $pizza);
```

Poznámka: I když `implode()` může z historických důvodů přijímat argumenty v obou možných pořadích, **`explode()`** nemůže. Musíte se ujistit, že je argument *separator* před argumentem *string*.

Viz také: `split()` a `implode()`.

get_html_translation_table (PHP 4 >= 4.0.0)

Vrátit překladovou tabulku používanou v `htmlspecialchars()` a `htmlentities()`

string **get_html_translation_table** (int table [, int quote_style]) \linebreak

get_html_translation_table() vrací překladovou tabulku, která se interně používá ve funkcích `htmlspecialchars()` a `htmlentities()`. Dvě nové konstanty (`HTML_ENTITIES`, `HTML_SPECIALCHARS`) vám umožňují určit, kterou tabulku chcete. A stejně jako u funkcí `htmlspecialchars()` a `htmlentities()` můžete případně určit *quote_style* se kterým pracujete. Defaultní hodnota je ENT_COMPAT mód. Viz popis těchto módů u `htmlspecialchars()`.

Příklad 1. Ukázka na překladovou tabulku

```
$trans = get_html_translation_table (HTML_ENTITIES);
$str = "Hallo & <Frau> & Krämer";
$encoded = strtr ($str, $trans);
```

Proměnná `$encoded` teď obsahuje: "Hallo & <Frau> & & Krämer".

Skvělé je, že pomocí `array_flip()` můžete změnit směr překladu.

```
$trans = array_flip ($trans);
$original = strtr ($str, $trans);
```

Obsahem `$original` je: "Hallo & <Frau> & Krämer".

Poznámka: Tato funkce byla přidána v PHP 4.0.

Viz také: `htmlspecialchars()`, `htmlentities()`, `strtr()` a `array_flip()`.

get_meta_tags (PHP 3>= 3.0.4, PHP 4 >= 4.0.0)

Získat hodnoty content atributů všech meta tagů v souboru a vrátit pole

array **get_meta_tags** (string filename [, int use_include_path]) \linebreak

Otevře *filename*, přečte ho po řádcích, a vyhledá `<meta>` tagy ve tvaru

Příklad 1. Ukázka na Meta Tagy

```
<meta name="author" content="name">
<meta name="tags" content="php3 documentation">
</head> <!-- tady čtení skončí -->
```

(věnujte pozornost koncům řádků - PHP používá ke čtení vstupu nativní funkci, takže Macovský soubor na Unixu nebude fungovat).

Hodnota atributu name se ve vráceném poli stává klíčem, hodnota atributu content hodnotou tohoto pole, takže ho můžete snadno projít nebo získat jednotlivé hodnoty pomocí standardních funkcí pro práci s poli. Zvláštní znaky v hodnotě atributu name jsou nahrazeny znakem '_', zbytek se převede na malá písmena.

Pokud je `use_include_path` rovno 1, PHP se pokusí otevřít soubor v standardní include cestě.

hebrew (PHP 3, PHP 4 >= 4.0.0)

Převést logický Hebrejský text na vizuální text

```
string hebrew ( string hebrew_text [, int max_chars_per_line]) \linebreak
```

Volitelný argument `max_chars_per_line` indikuje maximální počet znaků na řádek výstupu. Funkce se snaží nerozdělovat slova.

Viz také: `hebrevc()`.

hebrevc (PHP 3, PHP 4 >= 4.0.0)

Převést logický Hebrejský text na vizuální text s konverzí konců řádků

```
string hebrevc ( string hebrew_text [, int max_chars_per_line]) \linebreak
```

Tato funkce se podobá `hebrew()` s tím rozdílem, že převádí konce řádků (`\n`) na "`
\n`". Volitelný argument `max_chars_per_line` indikuje maximální počet znaků na řádek výstupu. Funkce se snaží nerozdělovat slova.

Viz také: `hebrew()`.

htmlentities (PHP 3, PHP 4 >= 4.0.0)

Převést všechny použitelné znaky na HTML entity

```
string htmlentities ( string string [, int quote_style]) \linebreak
```

Tato funkce je ve všem shodná s `htmlspecialchars()` kromě toho, že na HTML entity se převedou všechny znaky, které mají odpovídající entity. Stejně jako `htmlspecialchars()` přijímá volitelný druhý argument, který indikuje, co se má stát s jednoduchými a dvojítymi uvozovkami. `ENT_COMPAT`

(default) převede pouze dvojité uvozovky, ENT_QUOTES převede dvojité i jednoduché uvozovky, a ENT_NOQUOTES ponechá jednoduché i dvojité uvozovky bez konverze.

V současnosti se používá znaková sada ISO-8859-1. Volitelný druhý argument byl přidán v PHP 3.0.17 a PHP 4.0.3.

Viz také: htmlspecialchars() a nl2br().

htmlspecialchars (PHP 3, PHP 4 >= 4.0.0)

Převést zvláštní znaky na HTML entity

string **htmlspecialchars** (string string [, int quote_style]) \linebreak

Některé znaky mají v HTML zvláštní význam, a pokud si mají zachovat běžný význam, měly by být reprezentovány HTML entitami. Tato funkce vrací řetězec, ve kterém došlo k některým z těchto konverzí; provádějí se ty překlady, které jsou v každodenním programování pro web nejužitečnější. Pokud požadujete překlad všech znakových entit HTML, použijte htmlentities().

Tato funkce je užitečná, pokud se chcete chránit před případným výskytem HTML v textu dodaném uživateli, například u aplikací typu kniha hostů nebo diskusní skupina. Volitelný druhý argument, quote_style, určuje, co se má stát s jednoduchými a dvojitými uvozovkami. Defaultní mód, ENT_COMPAT, je zpětně kompatibilní mód, konvertuje pouze dvojité uvozovky a jednoduché uvozovky ponechává nepřeložené. Pokud zadáte ENT_QUOTES, přeloží se jednoduché i dvojité uvozovky, a pokud zadáte ENT_NOQUOTES, oba druhy zůstanou bez překladu.

Dochází k těmto překladům:

- '&' (ampersand) se stává '&'
- '"' (dvojitá uvozovka) se stává '",' when ENT_NOQUOTES is not set.
- "'" (jednoduchá uvozovka) se stává '',' only when ENT_QUOTES is set.
- '<' (menší než) se stává '<'
- '>' (větší než) se stává '>'

Příklad 1. Ukázka htmlspecialchars()

```
$new = htmlspecialchars("<a href='test'>Test</a>", ENT_QUOTES);
```

Poznámka: tato funkce provádí pouze výše uvedené překlady. Kompletní překlad entit viz htmlentities(). Volitelný druhý argument byl přidán v PHP 3.0.17 a PHP 4.0.3.

Viz také: htmlentities() a nl2br().

implode (PHP 3, PHP 4 >= 4.0.0)

Spojit prvky pole pomocí řetězce

string **implode** (string glue, array pieces) \linebreak

Vrací řetězec obsahující řetězcovou reprezentaci všech prvků pole v původním pořadí s řetězcem *glue* mezi každými dvěma prvky.

Příklad 1. Ukázka implode()

```
$colon_separated = implode (":", $array);
```

Poznámka: implode() může z historických důvodů přijímat argumenty v obou možných pořadích. Kvůli konzistenci s explode() se ale doporučuje používat dokumentované pořadí argumentů.

Viz také: explode(), join() a split().

join (PHP 3, PHP 4 >= 4.0.0)

Spojit prvky pole pomocí řetězce

```
string join ( string glue, array pieces) \linebreak
```

Funkce **join()** je alias k implode(), a je ve všech ohledech stejná.

Viz také: explode(), implode() a split().

levenshtein (PHP 3 >= 3.0.17, PHP 4)

Spočítat XXX Levenshteinovu vzdálenost mezi dvěma řetězci

```
int levenshtein ( string str1, string str2) \linebreak int levenshtein ( string str1, string str2, int cost_ins, int cost_rep, int cost_del) \linebreak int levenshtein ( string str1, string str2, function cost) \linebreak
```

Tato funkce vrací XXX Levenshtein-Distance mezi předanými řetězci nebo -1, pokud délka jednoho z předaných řetězců přesáhne omezení 255 znaků (255 by mělo být pro běžná porovnání víc než dost, a nikdo se zdravým rozumem nebude v PHP dělat genetickou analýzu).

Levenshteinova vzdálenost se definuje jako minimální počet znaku, které musíte nahradit, vložit nebo smazat, abyste změnili *str1* na *str2*. Složitost tohoto algoritmu je $O(m \cdot n)$, kde n a m jsou délky *str1* a *str2* (celkem slušné v porovnání se similar_text(), který je $O(\max(n,m)^3)$, ale i tak drahé).

Ve své nejjednodušší podobě tato funkce pouze vezme dva řetězce jako argumenty a spočítá počet vložení, nahrazení a smazání nutných k transformaci *str1* na *str2*.

Druhá varianta přijme tři další argumenty, které definují náklady na operace vložení, nahrazení a smazání. Tato varianta je všeobecnější a přizpůsobivější než varianta první, ale ne tak výkonná.

Třetí varianta (zatím neimplementovaná) bude nejvšeobecnější a nejpřizpůsobivější, ale také nejpomalejší alternativou. Bude volat uživatelskou funkci, která určí náklady na všechny možné operace.

Tato uživatelská funkce se bude volat s následujícími argumenty:

- operace, která se má provést: 'I', 'R' or 'D'
- původní znak v řetězci 1
- původní znak v řetězci 2
- pozice v řetězci 1
- pozice v řetězci 2
- znaky zbývající v řetězci 1
- znaky zbývající v řetězci 2

Tato uživatelská funkce musí vrátit kladné celé číslo vyčísľující náklady na tuto konkrétní operaci, ale může se rozhodnout použít pouze některé z přijatých argumentů.

Tento přístup nabízí možnost zohlednit důležitost určitých symbolů (znaků) a/nebo rozdíly mezi nimi, či dokonce kontext, ve kterém se vyskytují při určování nákladů na vložení, změnu nebo smazání, ale za cenu ztráty všech optimalizací využití CPU registru a XXX cache misses, které byly zapracovány do předchozích dvou variant.

Viz také: `soundex()`, `similar_text()` a `metaphone()`.

ltrim (PHP 3, PHP 4 >= 4.0.0)

Odstranit netisknutelné znaky ze začátku řetězce

string **ltrim** (string str) \linebreak

Tato funkce ořízne netisknutelné znaky ze začátku řetězce a vrátí oříznutý řetězec. Netisknutelné znaky, které se v současnosti odstraňují, jsou: "\n", "\r", "\t", "\v", "\0", a prostá mezera.

Viz také: `chop()`, `rtrim()` a `trim()`.

md5 (PHP 3, PHP 4 >= 4.0.0)

Spočítat MD5 XXX hash řetězce

string **md5** (string str) \linebreak

Spočítá MD5 XXX hash argumentu *str* pomocí MD5 Message-Digest Algoritmu společnosti RSA Data Security, Inc. (<http://www.faqs.org/rfcs/rfc1321.html>).

Viz také: `crc32()`.

metaphone (PHP 4 >= 4.0.0)

Spočítat metaphone klíč řetězce

string **metaphone** (string str) \linebreak

Spočítá metaphone klíč argumentu *str*.

metaphone(), podobně jako **soundex()**, vytvoří stejný klíč pro podobně znějící slova. Je přesnější než **soundex()**, protože zná základní pravidla anglické výslovnosti. Metaphone klíče mají proměnlivou délku.

Metaphone vyvinul Lawrence Philips <lphilips@verity.com>. Je popsáno v ["Practical Algorithms for Programmers", Binstock & Rex, Addison Wesley, 1995].

Poznámka: Tato funkce byla přidána v PHP 4.0.

nl2br (PHP 3, PHP 4 >= 4.0.0)

Převede konce řádků na HTML konce řádků

string **nl2br** (string string) \linebreak

Vrací *string*, ve kterém je před každý konec řádku vložen tag '
'.

Viz také: **htmlspecialchars()**, **htmlentities()** a **wordwrap()**.

ord (PHP 3, PHP 4 >= 4.0.0)

Vrátit ASCII hodnotu znaku

int **ord** (string string) \linebreak

Vrací ASCII hodnotu prvního znaku v *string*. Tato funkce doplňuje **chr()**.

Příklad 1. Ukázka ord()

```
if (ord ($str) == 10) {
    echo "Prvním znakem \$str je line feed.\n";
}
```

Viz také: **chr()**.

parse_str (PHP 3, PHP 4 >= 4.0.0)

Roparovat řetězec do proměnných

void **parse_str** (string str [, array arr]) \linebreak

Rozparsuje řetězec jako kdyby to byl querystring předaný v URL a definuje příslušné proměnné v současném scope. Pokud je předán druhý argument *arr*, proměnné se místo toho uloží do této proměnné jako pole.

Příklad 1. Using parse_str()

```
$str = "first=value&second[]=this+works&second[]=another";
parse_str($str);
echo $first;      /* vytiskne "value" */
echo $second[0]; /* vytiskne "this works" */
echo $second[1]; /* vytiskne "another" */
```

print (unknown)

Vytisknout řetězec

print (string *arg*) \linebreak

Vytiskne *arg*.

Viz také: echo(), printf() a flush().

printf (PHP 3, PHP 4 >= 4.0.0)

Vytisknout formátovaný řetězec

int **printf** (string *format* [, mixed *args*]) \linebreak

Vytvoří výstup podle argumentu *format*, který je popsán v dokumentaci sprintf().

Viz také: print(), sprintf(), sscanf(), fscanf() a flush().

quoted_printable_decode (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Převést quoted-printable řetězec na osmibitový řetězec

string **quoted_printable_decode** (string *str*) \linebreak

Tato funkce vrací osmibitový binární řetězec odpovídající dekodovanému quoted printable řetězci.

Tato funkce je podobná imap_qprint() s tou výjimkou, že tato funkce nevyžaduje IMAP modul.

quotemeta (PHP 3, PHP 4 >= 4.0.0)

Opatřit lomítky metaznaky

string **quotemeta** (string *str*) \linebreak

Vrací verzi *str* se zpětným lomítkem před všemi výskyty následujících znaků:

. \ \ + * ? [^] (\$)

Viz také: addslashes(), htmlentities(), htmlspecialchars(), nl2br() a stripslashes().

rtrim (PHP 3, PHP 4 >= 4.0.0)

Odstranit netisknutelné znaky z konce řetězce

string **rtrim** (string *str*) \linebreak

Vrací předaný řetězec bez netisknutelných znaků (vč. konců řádku) na konci. Toto je alias k chop().

Příklad 1. Ukázka rtrim()

```
$trimmed = rtrim ($line);
```

Viz také: trim(), ltrim() a **rtrim**().

setlocale (PHP 3, PHP 4 >= 4.0.0)

Set locale information

string **setlocale** (string *category*, string *locale*) \linebreak

category je řetězec určující kategorii funkcí ovlivněných nastavením locale:

- LC_ALL pro všechny níže uvedené kategorie
- LC_COLLATE pro porovnávání řetězců - v PHP v současnosti neimplementováno
- LC_CTYPE pro klasifikaci a konverzi znaků, např. strtoupper()
- LC_MONETARY pro localeconv() - v PHP v současnosti neimplementováno
- LC_NUMERIC pro oddělovač desetinných míst
- LC_TIME pro formátování data a času pomocí strftime()

Pokud je *locale* prázdný řetězec (""), názvy locale se nastaví na hodnoty systémových proměnných se stejnými jmény jako mají výše uvedené kategorie, nebo z "LANG".

Pokud je *locale* nula nebo "0", locale se nezmění, pouze se vrátí současná hodnota.

setlocale() vrací nové aktuální locale nebo FALSE, pokud na dotyčné platformě není funkcionální locale implementována, zadané locale neexistuje, nebo je název kategorie neplatný. Neplatný název kategorie také vyvolá varování.

similar_text (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Spočítat podobnost dvou řetězců

```
int similar_text ( string first, string second [, double percent]) \linebreak
```

similar_text() spočítá podobnost dvou řetězců podle Oliver [1993]. Pozn.: Tato implementace nepoužívá stack jako v Oliverově pseudokódu, nýbrž rekurzivní volání, což může či nemusí celý proces zrychlit. Komplexita tohoto algoritmu je $O(N^2)$ kde N je délka nejdelšího řetězce.

Pokud je **similar_text()** předán třetí argument (odkazem), spočítá tato funkce podobnost v procentech. Vrací počet znaků shodných v obou řetězcích.

soundex (PHP 3, PHP 4 >= 4.0.0)

Spočítat soundex klíč řetězce

```
string soundex ( string str) \linebreak
```

Spočítá soundex klíč *str*.

Soundex klíče mají tu vlastnost, že slova vyslovovaná podobně produkují shodné soundex klíče, a dají se proto využít ke zjednodušení hledání v databázích, kde znáte výslovnost, ale ne hláskování. Tato funkce vrací řetězec dlouhý 4 znaky začínající písmenem.

Tato konkrétní soundex funkce je popsána Donaldem Knuthem v "The Art Of Computer Programming, vol. 3: Sorting And Searching", Addison-Wesley (1973), pp. 391-392.

Příklad 1. Soundex ukázky

```
soundex ("Euler") == soundex ("Ellery") == 'E460';
soundex ("Gauss") == soundex ("Ghosh") == 'G200';
soundex ("Hilbert") == soundex ("Heilbronn") == 'H416';
soundex ("Knuth") == soundex ("Kant") == 'K530';
soundex ("Lloyd") == soundex ("Ladd") == 'L300';
soundex ("Lukasiewicz") == soundex ("Lissajous") == 'L222';
```

sprintf (PHP 3, PHP 4 >= 4.0.0)

Vrátit formátovaný řetězec

```
string sprintf ( string format [, mixed args]) \linebreak
```

Vrací řetězec vytvořený podle formátovacího řetězce *format*.

Formátovací řetězec se skládá z nula nebo více direktiv: běžných znaků (kromě %), které se přímo kopírují do výsledku, a *převodních specifikací*, z nichž každá přijímá jeden argument. Toto platí pro **sprintf()** i printf().

Každá převodní specifikace se skládá ze znaku procenta (%), následovaného jedním nebo více z těchto znaků, v tomto pořadí:

1. Volitelný *padding specifier*, který určuje, jaký znak se použije na doplnění výsledku na správnou délku řetězce. Může to být mezera nebo 0 (písmeno nula). Default je nula. Jiný doplňující znak můžete zadat tak, že před něj předřadíte jednoduchou uvozovku ('). Viz ukázky níže.
2. Volitelný *alignment specifier*, který určuje, jestli se má výsledek zarovnat doleva nebo doprava. Default je doprava, pomlčka (-) to změní na doleva.
3. Volitelné číslo *width specifier*, které určuje, kolik znaků (minimálně) má obsahovat výsledek převodu.
4. Volitelný *precision specifier*, který určuje, kolik desetinných míst se má zobrazit u čísel s desetinnou čárkou. Tento přepínač nemá žádný vliv na jiné typy než double. (Další funkci užitečnou na formátování čísel je `number_format()`.)
5. *type specifier*, který určuje, za jaký typ se mají data argumentu považovat. Možné typy:
 - % - a doslovný znak procenta. Nevyžaduje se žádný argument.
 - b - argument se považuje za integer a je prezentován jako binární číslo.
 - c - argument se považuje za integer a je prezentován jako znak s touto ASCII hodnotou.
 - d - argument se považuje za integer a je prezentován jako desítkové číslo.
 - f - argument se považuje za double a je prezentován jako číslo s plovoucí desetinou čárkou.
 - o - argument se považuje za integer a je prezentován jako oktalové číslo.
 - s - argument se považuje za řetězec a je takto prezentován.
 - x - the argument se považuje za integer a je prezentován jako hexadecimální číslo (s malými písmeny).
 - X - argument se považuje za integer a je prezentován jako hexadecimální číslo (s kapitálkami).

Viz také: `printf()`, `scanf()`, `fscanf()` a `number_format()`.

Příklad 1. Ukázka `sprintf()`: zero-padded integers

```
$isodate = sprintf ("%04d-%02d-%02d", $year, $month, $day);
```

Příklad 2. Ukázka `sprintf()`: formatting currency

```
$money1 = 68.75;
$money2 = 54.35;
$money = $money1 + $money2;
// echo $money will output "123.1";
$formatted = sprintf ("%01.2f", $money);
// echo $formatted will output "123.10"
```

sscanf (PHP 4)

Rozparsovat vstupní řetězec podle formátu

mixed **sscanf** (string str, string format [, string var1]) \linebreak

Funkce **sscanf()** je vstupním analogem **printf()**. **sscanf()** čte řetězec *str* a interpretuje ho podle formátu *format*. Pokud jsou jí předány pouze dva argumenty, vrací rozparsované hodnoty v poli.

Příklad 1. Ukázka sscanf()

```
// zjištění sériového čísla
$serial = sscanf("SN/2350001", "SN/%d");
// a data výroby
$mandate = "January 01 2000";
list($month, $day, $year) = sscanf($mandate, "%s %d %d");
echo "Zboží $serial bylo vyrobeno: $year-" . substr($month, 0, 3) . "-" . $day . "\n";
```

Pokud jsou jí předány volitelné argumenty, vrací tato funkce počet přiřazených hodnot. Volitelné argumenty musí být předány odkazem.

Příklad 2. Ukázka sscanf() - použití volitelných argumentů

```
// zjistit informace o autorovi a vygenerovat DocBook záznam
$auth = "24\tLewis Carroll";
$n = sscanf($auth, "%d\t%s %s", &$id, &$first, &$last);
echo "<author id='\$id'>
<firstname>$first</firstname>
<surname>$last</surname>
</author>\n";
```

Viz také: **fscanf()**, **printf()** a **sprintf()**.

str_pad (PHP 4)

Doplnit řetězec jiným řetězcem na určitou délku

string **str_pad** (string input, int pad_length [, string pad_string [, int pad_type]]) \linebreak

str_pad() doplní řetězec *input* zleva, zprava nebo z obou stran na danou délku. Pokud jí není předán volitelný argument *pad_string*, doplní se *input* mezerami, jinak se doplní znaky z *pad_string*.

Volitelný argument *pad_type* může nabýt hodnot **STR_PAD_RIGHT**, **STR_PAD_LEFT** nebo **STR_PAD_BOTH**. Default je **STR_PAD_RIGHT**.

Pokud je hodnota *pad_length* negativní nebo menší než je délka *input*, k doplnění nedojde.

Příklad 1. Ukázka str_pad()

```
$input = "Alien";
print str_pad($input, 10); // produces "Alien      "
print str_pad($input, 10, "-", STR_PAD_LEFT); // produces "-----Alien"
print str_pad($input, 10, "_", STR_PAD_BOTH); // produces "__Alien__"
```

str_repeat (PHP 4 >= 4.0.0)

Opakovat řetězec

string **str_repeat** (string input, int multiplier) \linebreak

Vrací *input_str* *multiplier* krát opakovaný. *multiplier* musí být větší než 0.

Příklad 1. Ukázka str_repeat()

```
echo str_repeat ("-", 10);
```

This will output "-=-=-=-=-=-=-=-=-".

Poznámka: Tato funkce byla přidána v PHP 4.0.

str_replace (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Nahradit všechny výskyty jednoho řetězce v jiném dalším řetězcem

string **str_replace** (string needle, string str, string haystack) \linebreak

Tato funkce nahradí všechny výskyty *needle* v argumentu *haystack* argumentem *str*. Pokud nepotřebujete složitá pravidla pro nahrazování, měli byste vždy použít tuto funkci místo `ereg_replace()`.

Příklad 1. Ukázka str_replace()

```
$bodytag = str_replace ("%body%", "black", "<body text=%body%>");
```

Tato funkce je XXX binárně bezpečná.

Poznámka: Funkce **str_replace()** byla přidána v PHP 3.0.6, ale až do verze PHP 3.0.8 fungovala špatně.

Viz také: `ereg_replace()` a `strtr()`.

strcasecmp (PHP 3 >= 3.0.2, PHP 4 >= 4.0.0)

Binárně bezpečné case-insensitive porovnání řetězců

int **strcasecmp** (string str1, string str2) \linebreak

Pokud je *str1* méně než *str2* vrací < 0; pokud je *str1* větší než *str2* vrací > 0, a 0, pokud jsou stejné.

Příklad 1. Ukázka strcasecmp()

```

$var1 = "Hello";
$var2 = "hello";
if (!strcasecmp ($var1, $var2)) {
    echo 'v case-insensitive textovém porovnání se $var1 rovná $var2';
}

```

Viz také: ereg(), strcmp(), substr(), strpos(), strncasecmp() a strstr().

strchr (PHP 3, PHP 4 >= 4.0.0)

Najít první výskyt znaku

string **strchr** (string haystack, string needle) \linebreak

Tato funkce je alias k strstr(), a je ve všech směrech identická.

strcmp (PHP 3, PHP 4 >= 4.0.0)

Binárně bezpečně porovnat řetězce

int **strcmp** (string str1, string str2) \linebreak

Pokud je *str1* méně než *str2*, vrací < 0; pokud je *str1* větší než *str2*, vrací > 0, a 0, pokud jsou stejné.

Pozn.: toto srovnání je case-sensitive.

Viz také: ereg(), strcasecmp(), substr(), strpos(), strncasecmp(), strncmp() a strstr().

strcspn (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Najít délku úvodního segmentu neodpovídajícího masce

int **strcspn** (string str1, string str2) \linebreak

Vrací délku úvodního segmentu *str1*, který *neobsahuje* žádný ze znaků *str2*.

Viz také: `strspn()`.

strip_tags (PHP 3 >= 3.0.8, PHP 4 >= 4.0.0)

Odstranit z řetězce HTML a PHP tagy

string **strip_tags** (string str [, string allowable_tags]) \linebreak

Tato funkce se snaží odstranit z předaného řetězce všechny HTML a PHP tagy. It errors on the side of caution in case of incomplete or bogus tags. It uses the same tag stripping state machine as the `fgetss()` function.

Volitelný druhý argument můžete použít k určení tagů, které se nemají odstranit.

Poznámka: Argument *allowable_tags* byl přidán v PHP 3.0.13, PHP 4 b3.

stripslashes (PHP 4 >= 4.0.0)

Un-quote string quoted with `addslashes()`

string **stripslashes** (string str) \linebreak

Vrací řetězec bez odstraněných zpětných lomítek. Rozeznává Céčkové `\n`, `\r` ..., oktalové a hexadecimální reprezentace.

Poznámka: Tato funkce byla přidána v PHP4b3-dev.

Viz také: `addslashes()`.

stripslashes (PHP 3, PHP 4 >= 4.0.0)

Un-quote string quoted with `addslashes()`

string **stripslashes** (string str) \linebreak

Vrací řetězec bez odstraněných zpětných lomítek. (`\ '` se stává `'` a pod.) Zdvojená zpětná lomítka se spojují do jednoduchých.

Viz také: `addslashes()`.

stristr (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Case-insensitive strstr()

string **stristr** (string haystack, string needle) \linebreak

Vrací *haystack* od prvního výskytu *needle* do konce. *needle* a *haystack* se zkoumají bez ohledu na velikost písmen.

Pokud *needle* nenajde, vrací FALSE.

Pokud *needle* není řetězec, převede se na integer a použije se jako XXX ordinal hodnota znaku.

Viz také: strchr(), strchr(), substr() a ereg().

strlen (PHP 3, PHP 4 >= 4.0.0)

Zjistit délku řetězce

int **strlen** (string str) \linebreak

Vrací délku (počet znaků) argumentu *string*.

strnatcasecmp (PHP 4 >= 4.0.0)

Case-insensitive textové porovnání s využitím "natural order" algoritmu

int **strnatcasecmp** (string str1, string str2) \linebreak

Tato funkce implementuje srovnávací algoritmus který třídí alfanumerické řetězce stejným způsobem jako člověk. Chování této funkce se podobá strnatcmp() s tou výjimkou, že porovnání je case-insensitive. Více informací viz stránka Martina Poola Natural Order String Comparison (<http://naturalordersort.org/>).

Podobně jako jiné funkce pro porovnávání řetězců i tato vrací < 0 pokud je *str1* menší než *str2*; > 0 pokud je *str1* větší než *str2*, a 0 pokud jsou shodné.

Viz také: ereg(), strcasecmp(), substr(), stristr(), strcmp(), strncmp(), strncasecmp(), strnatcmp() a strstr().

strnatcmp (PHP 4 >= 4.0.0)

Porovnání řetězců algoritmem "přirozeného třídění"

int **strnatcmp** (string str1, string str2) \linebreak

Tato funkce implementuje srovnávací algoritmus který třídí alfanumerické řetězce stejným způsobem jako člověk, toto se popisuje jako "přirozené třídění". Ukázka rozdílu mezi tímto algoritmem a běžnými počítačovými algoritmy pro řazení řetězců (např. strcmp()):

```
$arr1 = $arr2 = array ( "img12.png", "img10.png", "img2.png", "img1.png" );
```

```
echo "Standardní porovnávání řetězců\n";
usort($arr1,"strcmp");
print_r($arr1);
echo "\nPřirozené porovnávání řetězců\n";
usort($arr2,"strnatcmp");
print_r($arr2);
```

Výše uvedený kód vygeneruje následující výstup:

```
Standardní porovnávání řetězců
Array
(
    [0] => img1.png
    [1] => img10.png
    [2] => img12.png
    [3] => img2.png
)

Přirozené porovnávání řetězců
Array
(
    [0] => img1.png
    [1] => img2.png
    [2] => img10.png
    [3] => img12.png
)
```

Více informací viz stránka Martina Poola Natural Order String Comparison (<http://naturalordersort.org/>).

Podobně jako jiné funkce pro porovnávání řetězců i tato vrátí < 0 pokud je *str1* menší než *str2*; > 0 pokud je *str1* větší než *str2*, a 0 pokud jsou shodné.

Pozn.: toto porovnání je case-sensitive.

Viz také: `ereg()`, `strcasecmp()`, `substr()`, `stristr()`, `strcmp()`, `strncmp()`, `strncasecmp()`, `strnatcasecmp()`, `strstr()`, `natsort()` a `natcasesort()`.

strncasecmp (PHP 4 >= 4.0.2)

Binárně bezpečné case-insensitive porovnání prvních *n* znaků řetězců

int strncasecmp (string *str1*, string *str2*, int *len*) \linebreak

Tato funkce se podobá `strcasecmp()`, s tím rozdílem, že můžete určit (maximální) počet znaků (*len*) z každého z řetězců, které se použijí při porovnání. Pokud je některý z řetězců kratší než *len*, pak se pro porovnání použije délka tohoto řetězce.

Pokud je *str1* méně než *str2*, vrátí < 0; pokud je *str1* větší než *str2*, vrátí > 0, a 0, pokud jsou stejné.

Viz také: `ereg()`, `strcasecmp()`, `strcmp()`, `substr()`, `stristr()` a `strstr()`.

strncmp (PHP 4 >= 4.0.0)

Binárně bezpečné porovnání prvních *n* znaků v řetězcích

int strncmp (string *str1*, string *str2*, int *len*) \linebreak

This function is similar to `strcmp()`, with the difference that you can specify the (upper limit of the) number of characters (*len*) from each string to be used in the comparison. If any of the strings is shorter than *len*, then the length of that string will be used for the comparison.

Vrací < 0 pokud je *str1* menší než *str2*; > 0 pokud je *str1* větší než *str2*, a 0 pokud jsou shodné.

Pozn.: toto srovnání je case-sensitive.

Viz také: `ereg()`, `strncasecmp()`, `strcasecmp()`, `substr()`, `stristr()`, `strcmp()` a `strstr()`.

strpos (PHP 3, PHP 4 >= 4.0.0)

Najít pozici prvního výskytu řetězce

int strpos (string *haystack*, string *needle* [, int *offset*]) \linebreak

Vrací číselnou pozici prvního výskytu *needle* v řetězci *haystack*. Narozdíl od `strrpos()` tato funkce přijme jako argument *needle* řetězec více znaků, a celý tento řetězec se použije.

Pokud *needle* nenajde, vrací FALSE.

Poznámka: Návrátové hodnoty "znak nalezen na pozici 0" a "znak nenalezen" se dají snadno zaměnit. Tady je návod, jak zjistit tento rozdíl:

```
// v PHP 4.0b3 a novějších:
$pos = strpos ($mystring, "b");
if ($pos === false) { // tři rovnítká
    // nenalezeno...
}

// ve verzích starších než 4.0b3:
$pos = strpos ($mystring, "b");
if (is_string ($pos) && !$pos) {
    // nenalezeno...
}
```

Pokud *needle* není řetězec, převede se na integer a použije se jako XXX ordinal hodnota znaku.

Volitelný argument *offset* vám umožňuje určit na které pozici v *haystack* má hledání začít. Vracená pozice je i tak relativní k začátku *haystack*.

Viz také: `strrpos()`, `strchr()`, `substr()`, `stristr()` a `strstr()`.

strrchr (PHP 3, PHP 4 >= 4.0.0)

Najít poslední výskyt znaku v řetězci

string **strrchr** (string haystack, string needle) \linebreak

Tato funkce vrátí tu část *haystack*, která začíná poslením výskytem *needle* a pokračuje do konce *haystack*.

Pokud *needle* nenajde, vrátí FALSE.

Pokud *needle* obsahuje více než jeden znak, použije se první z nich.

Pokud *needle* není řetězec, převede se na integer a použije se jako XXX ordinal hodnota znaku.

Příklad 1. Ukázka strrchr()

```
// získat poslední adresář v $PATH
$dir = substr (strrchr ($PATH, ":"), 1);

// získat všechno po posledním konci řádku
$text = "Řádek 1\nŘádek 2\nŘádek 3";
$last = substr (strrchr ($text, 10), 1 );
```

Viz také: substr(), stristr() a strstr().

strrev (PHP 3, PHP 4 >= 4.0.0)

Obrátit řetězec

string **strrev** (string string) \linebreak

Vrací *string* v opačném pořadí.

strrpos (PHP 3, PHP 4 >= 4.0.0)

Najít pozici posledního výskytu znaku v řetězci

int **strrpos** (string haystack, char needle) \linebreak

Vrací číselnou pozici posledního výskytu *needle* v řetězci *haystack*. *needle* může být jen jeden znak dlouhá. Pokud obsahuje více znaků, použije se první z nich.

Pokud *needle* nenajde, vrátí FALSE.

Poznámka: Návrátové hodnoty "znak nalezen na pozici 0" a "znak nenalezen" se dají snadno zaměnit. Tady je návod, jak zjistit tento rozdíl:

```
// v PHP 4.0b3 a novějších:
$pos = strrpos ($mystring, "b");
if ($pos === false) { // tři rovnítko
```



```

        // nenalezeno...
    }

    // ve verzích starších než 4.0b3:
    $pos = strpos ($mystring, "b");
    if (is_string ($pos) && !$pos) {
        // nenalezeno...
    }

```

Pokud *needle* není řetězec, převede se na integer a použije se jako XXX ordinal hodnota znaku.

Viz také: `strpos()`, `strchr()`, `substr()`, `stristr()` a `strstr()`.

strspn (PHP 3>= 3.0.3, PHP 4 >= 4.0.0)

Zjistit délku úvodního segmentu odpovídajícího masce

`int strspn (string str1, string str2)` \linebreak

Vrací úvodního segmentu *str1*, který se skládá výhradně ze znaků v *str2*.

```
strspn ("42 je odpověď, co je otázka...", "1234567890");
```

vrátí 2.

Viz také: `strcspn()`.

strstr (PHP 3, PHP 4 >= 4.0.0)

Najít první výskyt řetězce

`string strstr (string haystack, string needle)` \linebreak

Vrací část *haystack* od prvního výskytu *needle* do konce.

Pokud *needle* nenajde, vrací FALSE.

Pokud *needle* není řetězec, převede se na integer a použije se jako XXX ordinal hodnota znaku.

Poznámka: Pozn.: tato funkce je case-sensitive. Pro case-insensitive hledání použijte `stristr()`.

Příklad 1. Ukázka strstr()

```
$email = 'sterling@designmultimedia.com';
$domain = strstr ($email, '@');
print $domain; // vytiskne @designmultimedia.com
```

Viz také: strstr(), strrchr(), substr() a ereg().

strtok (PHP 3, PHP 4 >= 4.0.0)

Tokenize string

string **strtok** (string arg1, string arg2) \linebreak

strtok() is used to tokenize a string. That is, if you have a string like "This is an example string" you could tokenize this string into its individual words by using the space character as the token.

Příklad 1. Ukázka strtok()

```
$string = "This is an example string";
$tok = strtok ($string, " ");
while ($tok) {
    echo "Word=$tok<br>";
    $tok = strtok ( " ");
}
```

Note that only the first call to strtok uses the string argument. Every subsequent call to strtok only needs the token to use, as it keeps track of where it is in the current string. To start over, or to tokenize a new string you simply call strtok with the string argument again to initialize it. Note that you may put multiple tokens in the token parameter. The string will be tokenized when any one of the characters in the argument are found.

Also be careful that your tokens may be equal to "0". This evaluates to `FALSE` in conditional expressions.

Viz také: split() a explode().

strtolower (PHP 3, PHP 4 >= 4.0.0)

Změnit řetězec na malá písmena

string **strtolower** (string str) \linebreak

Vrací *string* se všemi alfabetskými znaky změněnými na malá písmena.

Pozn.: co je 'alfabetický' je dáno aktuálním místním nastavením. Například ve standardním "C" locale se znaky jako přehlasované a (Ä) nepřevedou.

Příklad 1. Ukázka strtolower()

```
$str = "Mary Had A Little Lamb and She LOVED It So";
$str = strtolower($str);
print $str; # vytiskne mary had a little lamb and she loved it so
```

Viz také: strtoupper() a ucfirst().

strtoupper (PHP 3, PHP 4 >= 4.0.0)

Změnit řetězec na velká písmena

string **strtoupper** (string string) \linebreak

Vrací *string* se všemi alfabetskými znaky změněnými na velká písmena.

Pozn.: co je 'alfabetický' je dáno aktuálním místním nastavením. Například ve standardním "C" locale se znaky jako přehlasované á (ä) nepřevědou.

Příklad 1. Ukázka strtoupper()

```
$str = "Mary Had A Little Lamb and She LOVED It So";
$str = strtoupper ($str);
print $str; # vytiskne MARY HAD A LITTLE LAMB AND SHE LOVED IT SO
```

Viz také: strtolower() a ucfirst().

strtr (PHP 3, PHP 4 >= 4.0.0)

Přeložit určité znaky

string **strtr** (string str, string from, string to) \linebreak

Tato funkce upraví *str* tak, že všechny výskyty všech znaků ve *from* přeloží na odpovídající znaky v *to* a vrátí výsledek.

Pokud jsou *from* a *to* různě dlouhé, přebývající znaky z delšího z těch dvou se ignorují.

Příklad 1. Ukázka strtr()

```
$addr = strtr($addr, "äĺö", "aao");
```

strtr() se dá také volat pouze se dvěma argumenty. Při volání se dvěma argumenty se chová takto: *from* musí být pole obsahující páry řetězců, které se zamění ve zdrojovém řetězci. **strtr()** vždy hledá nejdelší možnou shodu a *NENAHRAZUJE* ty části řetězce, na kterých už pracovala.

Ukázky:

```
$trans = array ("ahoj" => "nazdar", "nazdar" => "ahoj");
echo strstr("nazdar lidi, řekl jsem ahoj", $trans) . "\n";
```

Výsledek: "ahoj lidi, řekl jsem nazdar",

Poznámka: Tato vlastnost (dva argumenty) byla přidána v PHP 4.0.

Viz také: `ereg_replace()`.

substr (PHP 3, PHP 4 >= 4.0.0)

Vrátit část řetězce

string **substr** (string string, int start [, int length]) \linebreak

substr() vrací část argumentu *string* určenou argumenty *start* a *length*.

Pokud je *start* pozitivní, vrácený řetězec začne *start*-tým znakem řetězce *string*, počítáno od nuly. Například v řetězci 'abcdef' je znakem na 0-té pozici 'a', znakem na pozici 2 je 'c', atd.

Příklady:

```
$rest = substr ("abcdef", 1); // vrátí "bcdef"
$rest = substr ("abcdef", 1, 3); // vrátí "bcd"
```

Pokud je *start* negativní, vrácený řetězec začne *start*-tým znakem od konce argumentu *string*.

Příklady:

```
$rest = substr ("abcdef", -1); // vrátí "f"
$rest = substr ("abcdef", -2); // vrátí "ef"
$rest = substr ("abcdef", -3, 1); // vrátí "d"
```

Pokud je argument *length* kladný, vrácený řetězec skončí *length* znaků od *start*. Pokud by to znamenalo řetězec se zápornou délkou (*start* je za *length*), vrácený řetězec bude sestávat z jediného znaku na pozici *start*.

Pokud je argument *length* kladný, vrácený řetězec skončí *length* znaků od konce argumentu *string*. Pokud by to znamenalo řetězec se zápornou délkou, vrácený řetězec bude sestávat z jediného znaku na pozici *start*.

Příklady:

```
$rest = substr ("abcdef", 1, -1); // vrátí "bcde"
```

Viz také: `strchr()` a `ereg()`.

substr_count (PHP 4 >= 4.0.0)

Spočítat počet výskytů řetězce

`int substr_count (string haystack, string needle)` \linebreak

substr_count() vrací počet výskytů řetězce *needle* v řetězci *haystack* string.

Příklad 1. Ukázka substr_count()

```
print substr_count("This is a test", "is"); // prints out 2
```

substr_replace (PHP 4 >= 4.0.0)

Nahradiť část řetězce jiným řetězcem

`string substr_replace (string string, string replacement, int start [, int length])` \linebreak

substr_replace() nahrazuje část řetězce *string* ohraničenou argumenty *start* a (volitelně) *length* řetězcem v argumentu *replacement*. Vrací výsledek.

Pokud je *start* pozitivní, náhrada začne na *start*-tém znaku argumentu *string*.

Pokud je *start* negativní, náhrada začne na *start*-tém znaku od konce argumentu *string*.

Pokud je přítomen *length*, a je pozitivní, představuje délku části argumentu *string*, která bude nahrazena. Pokud je negativní, představuje počet znaků od konce *string*, kde má nahrazování skončit. Pokud přítomen není, bere se standardně `strlen(string)`; tj. nahrazování končí na konci argumentu *string*.

Příklad 1. Ukázka substr_replace()

```
<?php
$var = 'ABCDEFGH:/MNRPQR/';
echo "Originál: $var<br>\n";

/* Tyto dva příklady nahradí celý obsah proměnné $var řetězcem 'bob'. */
echo substr_replace ($var, 'bob', 0) . "<br>\n";
echo substr_replace ($var, 'bob', 0, strlen ($var)) . "<br>\n";

/* Toto vloží 'bob' na začátek $var. */
echo substr_replace ($var, 'bob', 0, 0) . "<br>\n";

/* Tyto dva příklady nahradí 'MNRPQR' ve $var řetězcem 'bob'. */
echo substr_replace ($var, 'bob', 10, -1) . "<br>\n";
echo substr_replace ($var, 'bob', -7, -1) . "<br>\n";
```

```
/* Toto z $var odstraní 'MNRPQR'. */
echo substr_replace ($var, "", 10, -1) . "<br>\n";
?>
```

Viz také `str_replace()` a `substr()`.

Poznámka: Funkce **`substr_replace()`** byla přidána v PHP 4.0.

trim (PHP 3, PHP 4 >= 4.0.0)

Odstranit netisknutelné znaky ze začátku a konce řetězce

string **trim** (string str) \linebreak

Tato funkce odstraňuje netisknutelné znaky ze začátku a konce řetězce a vrací řetězec bez těchto znaků. Netisknutelné znaky, které se v současnosti odstraňují, jsou: "\n", "\r", "\t", "\v", "\0", a mezera.

Viz také `chop()`, `rtrim()` a `ltrim()`.

ucfirst (PHP 3, PHP 4 >= 4.0.0)

Změní první písmeno řetězce na velké

string **ucfirst** (string str) \linebreak

Změní první znak argumentu *str*, pokud je tento znak alfabetský.

Pozn.: co znamená 'alfabetický' určuje aktuální místní nastavení (locale). Například ve standardním "C" locale se znaky jako přehlasované a (ä) nepřevědou.

Příklad 1. Ukázka ucfirst()

```
$text = 'mary had a little lamb and she loved it so.';
$text = ucfirst ($text); // $text is now Mary had a little lamb
                        // and she loved it so.
```

Viz také `strtoupper()` a `strtolower()`.

ucwords (PHP 3 >= 3.0.3, PHP 4 >= 4.0.0)

Změnit první znak každého slova v řetězci na velké písmeno

string **ucwords** (string *str*) \linebreak

Změní první znak každého slova v argumentu *str* na velké písmeno, pokud je tento znak alfabetycký.

Příklad 1. Ukázka ucwords()

```
$text = "mary had a little lamb and she loved it so.";
$text = ucwords($text); // $text is now: Mary Had A Little
                        // Lamb And She Loved It So.
```

Poznámka: Definice slova je: jakýkoli řetězec znaků, který následuje bezprostředně po netisknutelném znaku (to jsou: mezera, posun o tiskovou stranu, přesun na novou řádku, návrat vozíku, horizontální tabelátor a vertikální tabelátor0.

Viz také strtoupper(), strtolower() and ucfirst().

wordwrap (PHP 4 >= 4.0.2)

Zalámat řetězec na daný počet znaků pomocí break znaku

string **wordwrap** (string *str* [, int *width* [, string *break* [, int *cut*]]]) \linebreak

Zaláme řetězec *str* na sloupci určeném (volitelným) argumentem *break*.

Pokud není zadán argument *width* nebo *break*, **wordwrap()** automaticky zaláme řádky řetězce na sloupci 75 znakem '\n' (konec řádku).

Pokud má argument *cut* hodnotu 1, řetězec se na určenou šířku zalomí vždy. Takže pokud máte slovo delší než je daná šířka, rozdělí se. (Viz druhý příklad.)

Poznámka: Argument *cut* byl přidán PHP 4.0.3.

Příklad 1. Ukázka wordwrap()

```
$text = "Rychlá hnědá liška přeskočila líného psa.";
$newtext = wordwrap( $text, 20 );

echo "$newtext\n";
```

Tato ukázka by zobrazila:

```
Rychlá hnědá liška
přeskočila líného psa.
```

Příklad 2. Ukázka wordwrap()

```
$text = "Velmi dlouhé sloooooooooooooovo.";  
$newtext = wordwrap( $text, 8, "\n", 1);  
  
echo "$newtext\n";
```

Tato ukázka by zobrazila:

```
Velmi  
dlouhé  
sloooooo  
ooooovo.
```

Viz také: nl2br().

XCVII. Sybase functions

sybase_affected_rows (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

get number of affected rows in last query

```
int sybase_affected_rows ( [int link_identifier]) \linebreak
```

Returns: The number of affected rows by the last query.

sybase_affected_rows() returns the number of rows affected by the last INSERT, UPDATE or DELETE query on the server associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed.

This command is not effective for SELECT statements, only on statements which modify records. To retrieve the number of rows returned from a SELECT, use `sybase_num_rows()`.

Poznámka: This function is only available using the CT library interface to Sybase, and not the DB library.

sybase_close (PHP 3, PHP 4 >= 4.0.0)

close Sybase connection

```
bool sybase_close ( int link_identifier) \linebreak
```

Returns: TRUE on success, FALSE on error

sybase_close() closes the link to a Sybase database that's associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed.

Note that this isn't usually necessary, as non-persistent open links are automatically closed at the end of the script's execution.

sybase_close() will not close persistent links generated by `sybase_pconnect()`.

See also: `sybase_connect()`, `sybase_pconnect()`.

sybase_connect (PHP 3, PHP 4 >= 4.0.0)

open Sybase server connection

```
int sybase_connect ( string servername, string username, string password [, string charset]) \linebreak
```

Returns: A positive Sybase link identifier on success, or FALSE on error.

sybase_connect() establishes a connection to a Sybase server. The servername argument has to be a valid servername that is defined in the 'interfaces' file.

In case a second call is made to **sybase_connect()** with the same arguments, no new link will be established, but instead, the link identifier of the already opened link will be returned.

The link to the server will be closed as soon as the execution of the script ends, unless it's closed earlier by explicitly calling `sybase_close()`.

See also `sybase_pconnect()`, `sybase_close()`.

sybase_data_seek (PHP 3, PHP 4 >= 4.0.0)

move internal row pointer

bool **sybase_data_seek** (int result_identifier, int row_number) \linebreak

Returns: TRUE on success, FALSE on failure

sybase_data_seek() moves the internal row pointer of the Sybase result associated with the specified result identifier to pointer to the specified row number. The next call to `sybase_fetch_row()` would return that row.

See also: **sybase_data_seek()**.

sybase_fetch_array (PHP 3, PHP 4 >= 4.0.0)

fetch row as array

array **sybase_fetch_array** (int result) \linebreak

Returns: An array that corresponds to the fetched row, or FALSE if there are no more rows.

sybase_fetch_array() is an extended version of `sybase_fetch_row()`. In addition to storing the data in the numeric indices of the result array, it also stores the data in associative indices, using the field names as keys.

An important thing to note is that using **sybase_fetch_array()** is NOT significantly slower than using `sybase_fetch_row()`, while it provides a significant added value.

For further details, also see `sybase_fetch_row()`.

sybase_fetch_field (PHP 3, PHP 4 >= 4.0.0)

get field information

object **sybase_fetch_field** (int result [, int field_offset]) \linebreak

Returns an object containing field information.

sybase_fetch_field() can be used in order to obtain information about fields in a certain query result. If the field offset isn't specified, the next field that wasn't yet retrieved by **sybase_fetch_field()** is retrieved.

The properties of the object are:

- name - column name. if the column is a result of a function, this property is set to computed#N, where #N is a serial number.

- `column_source` - the table from which the column was taken
- `max_length` - maximum length of the column
- `numeric` - 1 if the column is numeric
- `type` - datatype of the column

See also `sybase_field_seek()`

sybase_fetch_object (PHP 3, PHP 4 >= 4.0.0)

fetch row as object

```
int sybase_fetch_object ( int result) \linebreak
```

Returns: An object with properties that correspond to the fetched row, or `FALSE` if there are no more rows.

sybase_fetch_object() is similar to `sybase_fetch_array()`, with one difference - an object is returned, instead of an array. Indirectly, that means that you can only access the data by the field names, and not by their offsets (numbers are illegal property names).

Speed-wise, the function is identical to `sybase_fetch_array()`, and almost as quick as `sybase_fetch_row()` (the difference is insignificant).

See also: `sybase_fetch_array()` and `sybase_fetch_row()`.

sybase_fetch_row (PHP 3, PHP 4 >= 4.0.0)

get row as enumerated array

```
array sybase_fetch_row ( int result) \linebreak
```

Returns: An array that corresponds to the fetched row, or `FALSE` if there are no more rows.

sybase_fetch_row() fetches one row of data from the result associated with the specified result identifier. The row is returned as an array. Each result column is stored in an array offset, starting at offset 0.

Subsequent call to **sybase_fetch_row()** would return the next row in the result set, or `FALSE` if there are no more rows.

See also: `sybase_fetch_array()`, `sybase_fetch_object()`, `sybase_data_seek()`, **sybase_fetch_lengths()**, and `sybase_result()`.

sybase_field_seek (PHP 3, PHP 4 >= 4.0.0)

set field offset

```
int sybase_field_seek ( int result, int field_offset) \linebreak
```

Seeks to the specified field offset. If the next call to `sybase_fetch_field()` won't include a field offset, this field would be returned.

See also: `sybase_fetch_field()`.

sybase_free_result (PHP 3, PHP 4 >= 4.0.0)

free result memory

bool **sybase_free_result** (int result) \linebreak

sybase_free_result() only needs to be called if you are worried about using too much memory while your script is running. All result memory will automatically be freed when the script ends. You may call **sybase_free_result()** with the result identifier as an argument and the associated result memory will be freed.

sybase_get_last_message (PHP 3, PHP 4 >= 4.0.0)

Returns the last message from the server

string **sybase_get_last_message** (void) \linebreak

sybase_get_last_message() returns the last message reported by the server.

sybase_min_client_severity (PHP 3, PHP 4 >= 4.0.0)

Sets minimum client severity

void **sybase_min_client_severity** (int severity) \linebreak

sybase_min_client_severity() sets the minimum client severity level.

Poznámka: This function is only available using the CT library interface to Sybase, and not the DB library.

See also: `sybase_min_server_severity()`.

sybase_min_error_severity (PHP 3, PHP 4 >= 4.0.0)

Sets minimum error severity

void **sybase_min_error_severity** (int severity) \linebreak

sybase_min_error_severity() sets the minimum error severity level.

See also: `sybase_min_message_severity()`.

sybase_min_message_severity (PHP 3, PHP 4 >= 4.0.0)

Sets minimum message severity

```
void sybase_min_message_severity ( int severity) \linebreak
```

sybase_min_message_severity() sets the minimum message severity level.

See also: `sybase_min_error_severity()`.

sybase_min_server_severity (PHP 3, PHP 4 >= 4.0.0)

Sets minimum server severity

```
void sybase_min_server_severity ( int severity) \linebreak
```

sybase_min_server_severity() sets the minimum server severity level.

Poznámka: This function is only available using the CT library interface to Sybase, and not the DB library.

See also: `sybase_min_client_severity()`.

sybase_num_fields (PHP 3, PHP 4 >= 4.0.0)

get number of fields in result

```
int sybase_num_fields ( int result) \linebreak
```

sybase_num_fields() returns the number of fields in a result set.

See also: `sybase_db_query()`, `sybase_query()`, `sybase_fetch_field()`, `sybase_num_rows()`.

sybase_num_rows (PHP 3, PHP 4 >= 4.0.0)

get number of rows in result

```
int sybase_num_rows ( int result) \linebreak
```

sybase_num_rows() returns the number of rows in a result set.

See also: `sybase_db_query()`, `sybase_query()` and, `sybase_fetch_row()`.

sybase_pconnect (PHP 3, PHP 4 >= 4.0.0)

open persistent Sybase connection

```
int sybase_pconnect ( string servername, string username, string password [, string charset]) \linebreak
```

Returns: A positive Sybase persistent link identifier on success, or `FALSE` on error

sybase_pconnect() acts very much like **sybase_connect()** with two major differences.

First, when connecting, the function would first try to find a (persistent) link that's already open with the same host, username and password. If one is found, an identifier for it will be returned instead of opening a new connection.

Second, the connection to the SQL server will not be closed when the execution of the script ends. Instead, the link will remain open for future use (**sybase_close()** will not close links established by **sybase_pconnect()**).

This type of links is therefore called 'persistent'.

sybase_query (PHP 3, PHP 4 >= 4.0.0)

send Sybase query

```
int sybase_query ( string query, int link_identifier) \linebreak
```

Returns: A positive Sybase result identifier on success, or `FALSE` on error.

sybase_query() sends a query to the currently active database on the server that's associated with the specified link identifier. If the link identifier isn't specified, the last opened link is assumed. If no link is open, the function tries to establish a link as if **sybase_connect()** was called, and use it.

See also: **sybase_db_query()**, **sybase_select_db()**, and **sybase_connect()**.

sybase_result (PHP 3, PHP 4 >= 4.0.0)

get result data

```
string sybase_result ( int result, int row, mixed field) \linebreak
```

Returns: The contents of the cell at the row and offset in the specified Sybase result set.

sybase_result() returns the contents of one cell from a Sybase result set. The field argument can be the field's offset, or the field's name, or the field's table dot field's name (tablename.fieldname). If the column name has been aliased ('select foo as bar from...'), use the alias instead of the column name.

When working on large result sets, you should consider using one of the functions that fetch an entire row (specified below). As these functions return the contents of multiple cells in one function call, they're MUCH quicker than **sybase_result()**. Also, note that specifying a numeric offset for the field argument is much quicker than specifying a fieldname or tablename.fieldname argument.

Recommended high-performance alternatives: **sybase_fetch_row()**, **sybase_fetch_array()**, and **sybase_fetch_object()**.

sybase_select_db (PHP 3, PHP 4 >= 4.0.0)

select Sybase database

bool **sybase_select_db** (string database_name, int link_identifier) \linebreak

Returns: TRUE on success, FALSE on error

sybase_select_db() sets the current active database on the server that's associated with the specified link identifier. If no link identifier is specified, the last opened link is assumed. If no link is open, the function will try to establish a link as if **sybase_connect()** was called, and use it.

Every subsequent call to **sybase_query()** will be made on the active database.

See also: **sybase_connect()**, **sybase_pconnect()**, and **sybase_query()**

XCVIII. URL Functions

base64_decode (PHP 3, PHP 4 >= 4.0.0)

Dekódovat data kódovaná pomocí MIME base64

string **base64_decode** (string encoded_data) \linebreak

base64_decode() dekoduje *encoded_data* a vrátí původní data. Vracená data mohou být binární

Viz také: base64_encode(), RFC 2045 sekce 6.8.

base64_encode (PHP 3, PHP 4 >= 4.0.0)

Zakódovat data pomocí MIME base64

string **base64_encode** (string data) \linebreak

base64_encode() vrátí *data* zakódovaný pomocí base64. Toto kódování je navrženo tak, aby umožnilo binárním datům přežít transport přenosovými vrstvami, které nejsou osmibitové, jako jsou například těla emailů.

Data kódovaná pomocí base64 zabírají o zhruba 33% prostoru více než původní data.

Viz také: base64_decode(), chunk_split(), RFC-2045 sekce 6.8.

parse_url (PHP 3, PHP 4 >= 4.0.0)

Rozebrat URL a vrátit její komponenty

array **parse_url** (string url) \linebreak

Tato funkce vrátí asociativní pole všech komponent URL přítomných v *url*. Ty mohou být: "scheme", "host", "port", "user", "pass", "path", "query" a "fragment".

rawurldecode (PHP 3, PHP 4 >= 4.0.0)

Dekódovat URL-kódovaný řetězec

string **rawurldecode** (string str) \linebreak

Vrátí řetězec, ve kterém sekvence znaku procent (%) následových dvěma šestnáctkovými číslicemi byly nahrazeny prostými znaky. Například řetězec

foo%20bar%40baz

dekóduje na

foo bar@baz

.

Viz také: rawurlencode(), urldecode(), urlencode().

rawurlencode (PHP 3, PHP 4 >= 4.0.0)

URL-kódovat podle RFC1738

string **rawurlencode** (string str) \linebreak

Vrátí řetězec, ve kterém byly všechny nealfanumerické znaky kromě

_
-.

nahrazeny znakem procent (%) následovaným dvěma šestnáctkovými číslicemi. To je kódování popsané v RFC1738 na ochranu prostých znaků před interpretací jako zvláštní oddělovače v URL a na ochranu URL před komolením přenosovými systémy se znakovými konvencemi (jako jsou některé emailové systémy). Například, pokud chcete k FTP URL přidat heslo:

Příklad 1. Příklad rawurlencode() č. 1

```
echo '<A HREF="ftp://user:', rawurlencode ('foo @+%/'),  
      '@ftp.my.com/x.txt">';
```

Nebo, pokud předáváte informace v komponentě URL obsahující info o cestě:

Příklad 2. Příklad rawurlencode() č. 2

```
echo '<A HREF="http://x.com/department_list_script/',  
      rawurlencode ('sales and marketing/Miami'), '>';
```

Viz také: rawurldecode(), urldecode(), urlencode().

urldecode (PHP 3, PHP 4 >= 4.0.0)

Dekódovat URL-kódovaný řetězec

string **urldecode** (string str) \linebreak

Dekóduje všechny %## kódy v daném řetězci. Vrátí dekodovaný řetězec.

Příklad 1. Příklad urldecode()

```
$a = split ('&', $querystring);  
$i = 0;  
while ($i < count ($a)) {  
    $b = split ('=', $a [$i]);  
    echo 'Hodnota argumentu ', htmlspecialchars (urldecode ($b [0])),  
        ' je ', htmlspecialchars (urldecode ($b [1])), "<BR>";  
    $i++;  
}
```

Viz také `urlencode()`, `rawurlencode()`, `rawurldecode()`.

urlencode (PHP 3, PHP 4 >= 4.0.0)

URL-kódovat řetězec

string **urlencode** (string str) \linebreak

Vrátí řetězec, ve kterém byly všechny nealfanumerické znaky kromě `-_.` nahrazeny znakem procent (`%`) následovaným dvěma šestnáctovými číslicemi a mezery kódovány jako znaky plus (`+`).

Kódování je stejné jako u dat postovaných z WWW formuláře, tj. stejně jako u `application/x-www-form-urlencoded` typu. To se liší od RFC1738 kódování (viz `rawurlencode()`) v tom, že z historických důvodů se mezery kódují jako znaky plus (`+`). Tato funkce je vhodná při kódování řetězce, který se má použít jako query část URL jako příhodný způsob předání proměnných na další stránku:

Příklad 1. Příklad urlencode()

```
echo '<A HREF="mycgi?foo=', urlencode ($userinput), '>';
```

Poznámka: pozor při předávání proměnných, které by mohly odpovídat HTML entitám. Věci jako `©` a `£` browser analyzuje a místo požadovaného jména proměnné použije odpovídající entitu. To je zřejmý problém, na který W3C upozorňuje už léta. Příručka je tady: <http://www.w3.org/TR/html4/appendix/notes.html#h-B.2.2> PHP podporuje změnu oddělovače argumentů na středník doporučený W3C skrze `.ini` direktivu `arg_separator`. Bohužel, většina uživatelských programů neposílá data z formulářů v tomto formátu. Přenositelnější formou je použít jako oddělovač `©`; místo `&`. Na to nemusíte měnit `arg_separator`. Nechte ho na `&`, ale kódujte URL pomocí `htmlentities()` (`urlencode($data)`).

Příklad 2. Příklad na urlencode/htmlentities()

```
echo '<A HREF="mycgi?foo=', htmlentities (urlencode ($userinput) ), '>';
```

Viz také `urldecode()`, `htmlentities()`, `rawurldecode()`, `rawurlencode()`.

XCIX. Variable Functions

For information on how variables behave, see the Variables entry in the Language Reference section of the manual.

doubleval (PHP 3, PHP 4 >= 4.0.0)

Alias of floatval()

This function is an alias of floatval().

Poznámka: This alias is a left-over from a function-renaming. In older versions of PHP you'll need to use this alias of the floatval() function, because floatval() wasn't yet available in that version.

empty (unknown)

Determine whether a variable is set

boolean **empty** (mixed var) \linebreak

Poznámka: **empty()** is a language construct.

This is the opposite of (boolean) *var*, except that no warning is generated when the variable is not set. See converting to boolean for more information.

```
$var = 0;

if (empty($var)) { // evaluates true
    echo '$var is either 0 or not set at all';
}

if (!isset($var)) { // evaluates false
    echo '$var is not set at all';
}
```

Note that this is meaningless when used on anything which isn't a variable; i.e. **empty (addslashes (\$name))** has no meaning since it would be checking whether something which isn't a variable is a variable with a FALSE value.

See also `isset()` and `unset()`.

floatval (PHP 4 >= 4.2.0)

Get float value of a variable

float **floatval** (mixed var) \linebreak

Returns the float value of *var*.

Var may be any scalar type. You cannot use **floatval()** on arrays or objects.

```
$var = '122.34343The';
$float_value_of_var = floatval ($var);
print $float_value_of_var; // prints 122.34343
```

See also `intval()`, `strval()`, `settype()` and Type juggling.

get_defined_vars (PHP 4 >= 4.0.4)

Returns an array of all defined variables

array **get_defined_vars** (void) \linebreak

This function returns an multidimensional array containing a list of all defined variables, be them environment, server or user-defined variables.

```
$b = array(1,1,2,3,5,8);

$arr = get_defined_vars();

// print $b
print_r($arr["b"]);

// print path to the PHP interpreter (if used as a CGI)
// e.g. /usr/local/bin/php
echo $arr["_"];

// print the command-line paramaters if any
print_r($arr["argv"]);

// print all the server vars
print_r($arr["HTTP_SERVER_VARS"]);

// print all the available keys for the arrays of variables
print_r(array_keys(get_defined_vars()));
```

See also **get_defined_functions()** and **get_defined_constants()**.

get_resource_type (PHP 4 >= 4.0.2)

Returns the resource type

string **get_resource_type** (resource handle) \linebreak

This function returns a string representing the type of the resource passed to it. If the parameter is not a valid resource, it generates an error.

```
$c = mysql_connect();
echo get_resource_type($c). "\n";
// prints: mysql link

$fp = fopen("foo", "w");
echo get_resource_type($fp). "\n";
// prints: file

$doc = new_xmldoc("1.0");
echo get_resource_type($doc->doc). "\n";
// prints: domxml document
```

gettype (PHP 3, PHP 4 >= 4.0.0)

Get the type of a variable

string **gettype** (mixed var) \linebreak

Returns the type of the PHP variable *var*.

Varování

Never use **gettype()** to test for a certain type, since the returned string may be subject to change in a future version. In addition, it is slow too, as it involves string comparison .

Instead, use the `is_*` functions.

Possible values for the returned string are:

- "boolean" (since PHP 4)
- "integer"
- "double" (for historical reasons "double" is returned in case of a float, and not simply "float")
- "string"
- "array"
- "object"

- "resource" (since PHP 4)
- "NULL" (since PHP 4)
- "user function" (PHP 3 only, deprecated)
- "unknown type"

For PHP 4, you should use `function_exists()` and `method_exists()` to replace the prior usage of **gettype()** on a function.

See also `settype()`, `is_array()`, `is_bool()`, `is_float()`, `is_integer()`, `is_null()`, `is_numeric()`, `is_object()`, `is_resource()`, `is_scalar()`, and `is_string()`.

import_request_variables (PHP 4 >= 4.1.0)

Import GET/POST/Cookie variables into the global scope

bool import_request_variables (string types [, string prefix]) \linebreak

Imports GET/POST/Cookie variables into the global scope. It is useful if you disabled `register_globals`, but would like to see some variables in the global scope.

Using the *types* parameter, you can specify, which request variables to import. You can use 'G', 'P' and 'C' characters respectively for GET, POST and Cookie. These characters are not case sensitive, so you can also use any combination of 'g', 'p' and 'c'. POST includes the uploaded file informations. Note, that the order of the letters matters, as using "gp", the POST variables will overwrite GET variables with the same name. Any other other letters then GPC are discarded.

Poznámka: Although the *prefix* argument is optional, you will get a notice level error, if you specify no prefix, or specify an empty string as a prefix. This is a possible security hazard. Notice level errors are not displayed using the default error reporting level.

```
// This will import GET and POST vars
// with an "rvar_" prefix
import_request_variables("gP", "rvar_");
```

See also `register_globals` and `track_vars`.

intval (PHP 3, PHP 4 >= 4.0.0)

Get integer value of a variable

int intval (mixed var [, int base]) \linebreak

Returns the integer value of *var*, using the specified base for the conversion (the default is base 10).

var may be any scalar type. You cannot use **intval()** on arrays or objects.

Poznámka: The *base* argument for **intval()** has no effect unless the *var* argument is a string.

See also `floatval()`, `strval()`, `settype()` and Type juggling.

is_array (PHP 3, PHP 4 >= 4.0.0)

Finds whether a variable is an array

`bool is_array (mixed var) \linebreak`

Returns `TRUE` if *var* is an array, `FALSE` otherwise.

See also `is_float()`, `is_int()`, `is_integer()`, `is_string()`, and `is_object()`.

is_bool (PHP 4 >= 4.0.0)

Finds out whether a variable is a boolean

`bool is_bool (mixed var) \linebreak`

Returns `TRUE` if the *var* parameter is a boolean.

See also `is_array()`, `is_float()`, `is_int()`, `is_integer()`, `is_string()`, and `is_object()`.

is_callable (PHP 4 >= 4.0.6)

Find out whether the argument is a valid callable construct

`bool is_callable (mixed var [, bool syntax_only [, string callable_name]]) \linebreak`

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

is_double (PHP 3, PHP 4 >= 4.0.0)

Alias of `is_float()`

This function is an alias of `is_float()`.

is_float (PHP 3, PHP 4 >= 4.0.0)

Finds whether a variable is a float

bool **is_float** (mixed var) \linebreak

Returns TRUE if *var* is a float, FALSE otherwise.

Poznámka: To test if a variable is a number or a numeric string (such as form input, which is always a string), you must use `is_numeric()`.

See also `is_bool()`, `is_int()`, `is_integer()`, `is_numeric()`, `is_string()`, `is_array()`, and `is_object()`,

is_int (PHP 3, PHP 4 >= 4.0.0)

Find whether a variable is an integer

bool **is_int** (mixed var) \linebreak

Returns TRUE if *var* is an integer FALSE otherwise.

Poznámka: To test if a variable is a number or a numeric string (such as form input, which is always a string), you must use `is_numeric()`.

See also `is_bool()`, `is_float()`, `is_integer()`, `is_numeric()`, `is_string()`, `is_array()`, and `is_object()`.

is_integer (PHP 3, PHP 4 >= 4.0.0)

Alias of `is_int()`

This function is an alias of `is_int()`.

is_long (PHP 3, PHP 4 >= 4.0.0)

Alias of `is_int()`

This function is an alias of `is_int()`.

is_null (PHP 4 >= 4.0.4)

Finds whether a variable is `NULL`

`bool is_null (mixed var) \linebreak`

Returns `TRUE` if `var` is `null`, `FALSE` otherwise.

See also `is_bool()`, `is_numeric()`, `is_float()`, `is_int()`, `is_string()`, `is_object()`, `is_array()`, `is_integer()`, and `is_real()`

is_numeric (PHP 4 >= 4.0.0)

Finds whether a variable is a number or a numeric string

`bool is_numeric (mixed var) \linebreak`

Returns `TRUE` if `var` is a number or a numeric string, `FALSE` otherwise.

See also `is_bool()`, `is_float()`, `is_int()`, `is_string()`, `is_object()`, `is_array()`, and `is_integer()`.

is_object (PHP 3, PHP 4 >= 4.0.0)

Finds whether a variable is an object

`bool is_object (mixed var) \linebreak`

Returns `TRUE` if `var` is an object, `FALSE` otherwise.

See also `is_bool()`, `is_int()`, `is_integer()`, `is_float()`, `is_string()`, and `is_array()`.

is_real (PHP 3, PHP 4 >= 4.0.0)

Alias of `is_float()`

This function is an alias of `is_float()`.

is_resource (PHP 4 >= 4.0.0)

Finds whether a variable is a resource

`bool is_resource (mixed var) \linebreak`

`is_resource()` returns `TRUE` if the variable given by the `var` parameter is a resource, otherwise it returns `FALSE`.

See the documentation on the resource-type for more information.

is_scalar (PHP 4 >= 4.0.5)

Finds whether a variable is a scalar

bool **is_scalar** (mixed var) \linebreak

is_scalar() returns TRUE if the variable given by the *var* parameter is a scalar, otherwise it returns FALSE.

Scalar variables are those containing an integer, float, string or boolean. Types array, object and resource or not scalar.

```

function show_var($var) {
    if (is_scalar($var)) {
        echo $var;
    } else {
        var_dump($var);
    }
}

$pi = 3.1416;
$proteins = array("hemoglobin", "cytochrome c oxidase", "ferredoxin");

show_var($pi);
// prints: 3.1416

show_var($proteins)
// prints:
// array(3) {
//     [0]=>
//     string(10) "hemoglobin"
//     [1]=>
//     string(20) "cytochrome c oxidase"
//     [2]=>
//     string(10) "ferredoxin"
// }

```

Poznámka: **is_scalar()** does not consider resource type values to be scalar as resources are abstract datatypes which are currently based on integers. This implementation detail should not be relied upon, as it may change.

See also **is_bool()**, **is_numeric()**, **is_float()**, **is_int()**, **is_real()**, **is_string()**, **is_object()**, **is_array()**, and **is_integer()**.

is_string (PHP 3, PHP 4 >= 4.0.0)

Finds whether a variable is a string

bool **is_string** (mixed var) \linebreak

Returns TRUE if *var* is a string, FALSE otherwise.

See also `is_bool()`, `is_int()`, `is_integer()`, `is_float()`, `is_real()`, `is_object()`, and `is_array()`.

isset (unknown)

Determine whether a variable is set

boolean **isset** (mixed var [, mixed var [, ...]]) \linebreak

Poznámka: `isset()` is a language construct.

Returns TRUE if *var* exists; FALSE otherwise.

If a variable has been unset with `unset()`, it will no longer be `isset()`. `isset()` will return FALSE if testing a variable that has been set to NULL. Also note that a NULL byte ("`\0`") is not equivalent to the PHP NULL constant.

```

$a = "test";
$b = "anothertest";

echo isset ($a); // TRUE
echo isset ($a, $b) //TRUE

unset ($a);
echo isset ($a); // FALSE
echo isset ($a, $b); //FALSE

$foo = NULL;
print isset ($foo); // FALSE

```

See also `empty()` and `unset()`.

print_r (PHP 4 >= 4.0.0)

Prints human-readable information about a variable

void **print_r** (mixed expression) \linebreak

print_r() displays information about a variable in a way that's readable by humans. If given a string, integer or float, the value itself will be printed. If given an array, values will be presented in a format that shows keys and elements. Similar notation is used for objects.

Remember that **print_r()** will move the array pointer to the end. Use `reset()` to bring it back to beginning.

Tip: Jako pro cokoliv, co posílá své výsledky přímo do prohlížeče, můžete použít funkce pro řízení výstupu k zachycení výstupu této funkce a jeho uložení - například - do řetězce (string).

```
<pre>
<?php
    $a = array ('a' => 'apple', 'b' => 'banana', 'c' => array ('x','y','z'));
    print_r ($a);
?>
</pre>
```

Which will output:

```
<pre>
Array
(
    [a] => apple
    [b] => banana
    [c] => Array
        (
            [0] => x
            [1] => y
            [2] => z
        )
)
</pre>
```

Poznámka: Prior to PHP 4.0.4, **print_r()** will continue forever if given an array or object that contains a direct or indirect reference to itself. An example is `print_r($GLOBALS)` because `$GLOBALS` is itself a global variable that contains a reference to itself.

See also `ob_start()`, `var_dump()`, and `var_export()`.

serialize (PHP 3 >= 3.0.5, PHP 4 >= 4.0.0)

Generates a storable representation of a value

string **serialize** (mixed value) \linebreak

serialize() returns a string containing a byte-stream representation of *value* that can be stored anywhere.

This is useful for storing or passing PHP values around without losing their type and structure.

To make the serialized string into a PHP value again, use **unserialize()**. **serialize()** handles all types, except the resource-type. You can even **serialize()** arrays that contain references to itself. References inside the array/object you are **serialize()**ing will also be stored.

Poznámka: In PHP 3, object properties will be serialized, but methods are lost. PHP 4 removes that limitation and restores both properties and methods. Please see the Serializing Objects section of Classes and Objects for more information.

Příklad 1. serialize() example

```
// $session_data contains a multi-dimensional array with session
// information for the current user. We use serialize() to store
// it in a database at the end of the request.

$conn = odbc_connect ("webdb", "php", "chicken");
$stmt = odbc_prepare ($conn,
    "UPDATE sessions SET data = ? WHERE id = ?");
$sqldata = array (serialize($session_data), $PHP_AUTH_USER);
if (!odbc_execute ($stmt, &$sqldata)) {
    $stmt = odbc_prepare($conn,
        "INSERT INTO sessions (id, data) VALUES(?, ?)");
    if (!odbc_execute($stmt, &$sqldata)) {
        /* Something went wrong. Bitch, whine and moan. */
    }
}
```

See Also: **unserialize()**.

settype (PHP 3, PHP 4 >= 4.0.0)

Set the type of a variable

bool **settype** (mixed var, string type) \linebreak

Set the type of variable *var* to *type*.

Possible values of *type* are:

- "boolean" (or, since PHP 4.2.0, "bool")
- "integer" (or, since PHP 4.2.0, "int")
- "float" (only possible since PHP 4.2.0, for older versions use the deprecated variant "double")
- "string"
- "array"
- "object"
- "null" (since PHP 4.0.8)

Returns TRUE if successful; otherwise returns FALSE.

Příklad 1. `settype()` example

```
$foo = "5bar"; // string
$bar = true;   // boolean

settype($foo, "integer"); // $foo is now 5    (integer)
settype($bar, "string");  // $bar is now "1"  (string)
```

See also `gettype()`, type-casting and type-juggling.

strval (PHP 3, PHP 4 >= 4.0.0)

Get string value of a variable

string **strval** (mixed var) \linebreak

Returns the string value of *var*. See the documentation on string for more information on converting to string.

var may be any scalar type. You cannot use **strval()** on arrays or objects.

See also `floatval()`, `intval()`, `settype()` and Type juggling.

unserialize (PHP 3 >= 3.0.5, PHP 4 >= 4.0.0)

Creates a PHP value from a stored representation

mixed **unserialize** (string str) \linebreak

unserialize() takes a single serialized variable (see `serialize()`) and converts it back into a PHP value. The converted value is returned, and can be an integer, float, string, array or object.

Poznámka: It's possible to set a callback-function which will be called, if an undefined class should be instantiated during unserializing. (to prevent getting an incomplete object `__PHP_Incomplete_Class`.) Use your `php.ini`, `ini_set()` or `.htaccess`-file to define `'unserialize_callback_func'`. Everytime an undefined class should be instantiated, it'll be called. To disable this feature just empty this setting.

Příklad 1. unserialize_callback_func example

```
$serialized_object='O:1:"a":1:{s:5:"value";s:3:"100";}';

ini_set('unserialize_callback_func','mycallback'); // set your callback_function

function mycallback($classname) {
    // just include a file containing your classdefinition
    // you get $classname to figure out which classdefinition is required
}
```

Poznámka: In PHP 3, methods are not preserved when unserializing a serialized object. PHP 4 removes that limitation and restores both properties and methods. Please see the Serializing Objects section of Classes and Objects or more information.

Příklad 2. unserialize() example

```
// Here, we use unserialize() to load session data to the
// $session_data array from the string selected from a database.
// This example complements the one described with serialize().

$conn = odbc_connect ("webdb", "php", "chicken");
$stmt = odbc_prepare ($conn, "SELECT data FROM sessions WHERE id = ?");
$sqldata = array ($PHP_AUTH_USER);
if (!odbc_execute ($stmt, &$sqldata) || !odbc_fetch_into ($stmt, &$tmp)) {
    // if the execute or fetch fails, initialize to empty array
    $session_data = array();
} else {
    // we should now have the serialized data in $tmp[0].
    $session_data = unserialize ($tmp[0]);
    if (!is_array ($session_data)) {
        // something went wrong, initialize to empty array
        $session_data = array();
    }
}
```

See Also: `serialize()`.

unset (unknown)

Unset a given variable

```
void unset ( mixed var [, mixed var [, ...]]) \linebreak
```

Poznámka: `unset()` is a language construct.

`unset()` destroys the specified variables. Note that in PHP 3, `unset()` will always return `TRUE` (actually, the integer value 1). In PHP 4, however, `unset()` is no longer a true function: it is now a statement. As such no value is returned, and attempting to take the value of `unset()` results in a parse error.

Příklad 1. unset() example

```
// destroy a single variable
unset ($foo);

// destroy a single element of an array
unset ($bar['quux']);

// destroy more than one variable
unset ($foo1, $foo2, $foo3);
```

The behavior of `unset()` inside of a function can vary depending on what type of variable you are attempting to destroy.

If a globalized variable is `unset()` inside of a function, only the local variable is destroyed. The variable in the calling environment will retain the same value as before `unset()` was called.

```
function destroy_foo() {
    global $foo;
    unset($foo);
}

$foo = 'bar';
destroy_foo();
echo $foo;
```

The above example would output:

```
bar
```

If a variable that is PASSED BY REFERENCE is **unset()** inside of a function, only the local variable is destroyed. The variable in the calling environment will retain the same value as before **unset()** was called.

```
function foo(&$bar) {
    unset($bar);
    $bar = "blah";
}

$bar = 'something';
echo "$bar\n";

foo($bar);
echo "$bar\n";
```

The above example would output:

```
something
something
```

If a static variable is **unset()** inside of a function, **unset()** destroys the variable and all its references.

```
function foo() {
    static $a;
    $a++;
    echo "$a\n";
    unset($a);
}

foo();
foo();
foo();
```

The above example would output:

```
1
```

2
3

If you would like to **unset()** a global variable inside of a function, you can use the `$GLOBALS` array to do so:

```
function foo() {
    unset($GLOBALS['bar']);
}

$bar = "something";
foo();
```

See also `isset()` and `empty()`.

var_dump (PHP 3>= 3.0.5, PHP 4 >= 4.0.0)

Dumps information about a variable

void **var_dump** (mixed expression [, mixed expression [, ...]] \linebreak

This function returns structured information about one or more expressions that includes its type and value. Arrays are explored recursively with values indented to show structure.

Tip: Jako pro cokoliv, co posílá své výsledky přímo do prohlížeče, můžete použít funkce pro řízení výstupu k zachycení výstupu této funkce a jeho uložení - například - do řetězce (string).

Compare **var_dump()** to `print_r()`.

```
<pre>
<?php
$a = array (1, 2, array ("a", "b", "c"));
var_dump ($a);

/* output:
array(3) {
  [0]=>
  int(1)
  [1]=>
  int(2)
  [2]=>
  array(3) {
    [0]=>
```

```

        string(1) "a"
        [1]=>
        string(1) "b"
        [2]=>
        string(1) "c"
    }
}

*/

$b = 3.1;
$c = TRUE;
var_dump($b,$c);

/* output:
float(3.1)
bool(true)

*/
?>
</pre>

```

var_export (PHP 4 >= 4.2.0)

Outputs or returns a string representation of a variable

mixed **var_export** (mixed expression [, bool return]) \linebreak

This function returns structured information about the variable that is passed to this function. It is similar to `var_dump()` with the exception that the returned representation is valid PHP code.

You can also return the variable representation by using `TRUE` as second parameter to this function.

Compare **var_export()** to `var_dump()`.

```

<pre>
<?php
$a = array (1, 2, array ("a", "b", "c"));
var_export ($a);

/* output:
array (
  0 => 1,
  1 => 2,
  2 =>
    array (
      0 => 'a',
      1 => 'b',
      2 => 'c',
    ),
),

```

```
)  
*/  
  
$b = 3.1;  
$v = var_export($b, TRUE);  
echo $v;  
  
/* output:  
3.1  
*/  
?>  
</pre>
```

C. vpopmail functions

vpopmail_add_alias_domain (PHP 4 >= 4.0.5)

Add an alias for a virtual domain

bool **vpopmail_add_alias_domain** (string domain, string aliasdomain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_add_alias_domain_ex (PHP 4 >= 4.0.5)

Add alias to an existing virtual domain

bool **vpopmail_add_alias_domain_ex** (string olddomain, string newdomain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_add_domain (PHP 4 >= 4.0.5)

Add a new virtual domain

bool **vpopmail_add_domain** (string domain, string dir, int uid, int gid) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_add_domain_ex (PHP 4 >= 4.0.5)

Add a new virtual domain

bool **vpopmail_add_domain_ex** (string domain, string passwd [, string quota [, string bounce [, bool apop]]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_add_user (PHP 4 >= 4.0.5)

Add a new user to the specified virtual domain

bool **vpopmail_add_user** (string user, string domain, string password [, string gecost [, bool apop]]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_alias_add (PHP 4 >= 4.1.0)

insert a virtual alias

bool **vpopmail_alias_add** (string user, string domain, string alias) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_alias_del (PHP 4 >= 4.1.0)

deletes all virtual aliases of a user

bool **vpopmail_alias_del** (string user, string domain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_alias_del_domain (PHP 4 >= 4.1.0)

deletes all virtual aliases of a domain

bool **vpopmail_alias_del_domain** (string domain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_alias_get (PHP 4 >= 4.1.0)

get all lines of an alias for a domain

array **vpopmail_alias_get** (string alias, string domain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_alias_get_all (PHP 4 >= 4.1.0)

get all lines of an alias for a domain

array **vpopmail_alias_get_all** (string domain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_auth_user (PHP 4 >= 4.0.5)

Attempt to validate a username/domain/password. Returns true/false

bool **vpopmail_auth_user** (string user, string domain, string password [, string apop]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_del_domain (PHP 4 >= 4.0.5)

Delete a virtual domain

bool **vpopmail_del_domain** (string domain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_del_domain_ex (PHP 4 >= 4.0.5)

Delete a virtual domain

bool **vpopmail_del_domain_ex** (string domain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_del_user (PHP 4 >= 4.0.5)

Delete a user from a virtual domain

bool **vpopmail_del_user** (string user, string domain) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_error (PHP 4 >= 4.0.5)

Get text message for last vpopmail error. Returns string

string **vpopmail_error** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_passwd (PHP 4 >= 4.0.5)

Change a virtual user's password

bool **vpopmail_passwd** (string user, string domain, string password) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

vpopmail_set_user_quota (PHP 4 >= 4.0.5)

Sets a virtual user's quota

bool **vpopmail_set_user_quota** (string user, string domain, string quota) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

Cl. W32api functions

w32api_deftype (PHP 4 >= 4.2.0)

Defines a type for use with other w32api_functions

int **w32api_deftype** (string typename, string member1_type, string member1_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

w32api_init_dtype (PHP 4 >= 4.2.0)

Creates an instance to the data type typename and fills it with the values val1, val2, the function then returns a DYNAPARM which can be passed when invoking a function as a parameter

resource **w32api_init_dtype** (string typename, mixed val1, mixed val2) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

w32api_invoke_function (unknown)

Invokes function funcname with the arguments passed after the function name

mixed **w32api_invoke_function** (string funcname) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

w32api_register_function (PHP 4 >= 4.2.0)

Registers function function_name from library with PHP

bool **w32api_register_function** (string library, string function_name) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

w32api_set_call_method (PHP 4 >= 4.2.0)

Sets the calling method used

void **w32api_set_call_method** (int method) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

CII. WDDX funkce

Tyto funkce jsou určeny pro práci s WDDX (<http://www.openwddx.org/>).

Pokud chcete používat WDDX, budete muset nainstalovat expat knihovnu (která je u Apache 1.3.7 a vyšších) a zkompilovat PHP s `--with-xml` a `--enable-wddx`.

Pozn.: všechny funkce které serializují proměnné používají první element pole k rozhodnutí jestli se toto pole serializuje do pole nebo struktury. Pokud má první element řetězec jako index, serializuje se do struktury, jinak do pole.

Příklad 1. Serializace jediné hodnoty

```
<?php
print wddx_serialize_value("PHP to WDDX packet example", "PHP packet");
?>
```

Tato ukázka vytvoří:

```
<wddxPacket version='1.0'><header comment='PHP packet' /><data>
<string>PHP to WDDX packet example</string></data></wddxPacket>
```

Příklad 2. Použití inkrementálních paketů

```
<?php
$pi = 3.1415926;
$packet_id = wddx_packet_start("PHP");
wddx_add_vars($packet_id, "pi");

/* Suppose $cities came from database */
$cities = array("Austin", "Novato", "Seattle");
wddx_add_vars($packet_id, "cities");

$packet = wddx_packet_end($packet_id);
print $packet;
?>
```

Tato ukázka vytvoří:

```
<wddxPacket version='1.0'><header comment='PHP' /><data><struct>
<var name='pi'><number>3.1415926</number></var><var name='cities'>
<array length='3'><string>Austin</string><string>Novato</string>
<string>Seattle</string></array></var></struct></data></wddxPacket>
```

wddx_add_vars (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Přidat proměnné do WDDX paketu s určeným ID

wddx_add_vars (int packet_id, mixed name_var [, mixed ...]) \linebreak

wddx_add_vars() se používá k serializaci předaných proměnných a přidání výsledku do paketu specifikovaného *packet_id*. Proměnné určené k serializaci se udávají stejně jako u **wddx_serialize_vars()**.

wddx_deserialize (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Deserializovat WDDX paket

mixed **wddx_deserialize** (string packet) \linebreak

wddx_deserialized() přijímá řetězec *packet* a deserializuje ho. Vrací výsledek, což může být řetězec, číslo, nebo pole. Pozn.: Struktury se deserializují do asociativních polí.

wddx_packet_end (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Ukončit WDDX paket se zadaným ID

string **wddx_packet_end** (int packet_id) \linebreak

wddx_packet_end() ukončí WDDX paket určený argumentem *packet_id* a vrací řetězec obsahující tento paket.

wddx_packet_start (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Začít nový WDDX paket obsahující strukturu

int **wddx_packet_start** ([string comment]) \linebreak

wddx_packet_start() se používá k započetí nového WDDX paketu pro inkrementální přidávání proměnných. Přijímá volitelný řetězec *comment* a vrací ID paketu pro použití v dalších funkcích. Uvnitř paketu automaticky vytváří definici struktury která bude obsahovat přidané proměnné.

wddx_serialize_value (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Serializovat jedinou hodnotu do WDDX paketu

string **wddx_serialize_value** (mixed var [, string comment]) \linebreak

wddx_serialize_value() se používá k vytvoření WDDX paketu z jediné dané hodnoty. Přijímá hodnotu obsaženou ve *var* a volitelný řetězec *comment*, který se použije v hlavičce paketu, a vrací WDDX paket.

wddx_serialize_vars (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Serializovat proměnné do WDDX paketu

string **wddx_serialize_vars** (mixed var_name [, mixed ...]) \linebreak

wddx_serialize_vars() se používá k vytvoření WDDX paketu se strukturou která obsahuje serializovanou reprezentaci předaných proměnných.

wddx_serialize_vars() přijímá proměnný počet argumentů, každý z nich může být buď řetězec obsahující název proměnné, nebo pole názvů proměnných, nebo jiné pole atd.

Příklad 1. wddx_serialize_vars example

```
<?php
$a = 1;
$b = 5.5;
$c = array("blue", "orange", "violet");
$d = "colors";

$c1vars = array("c", "d");
print wddx_serialize_vars("a", "b", $c1vars);
?>
```

Výše uvedená ukázka vytvoří:

```
<wddxPacket version='1.0'><header/><data><struct><var name='a'><number>1</number></var>
<var name='b'><number>5.5</number></var><var name='c'><array length='3'>
<string>blue</string><string>orange</string><string>violet</string></array></var>
<var name='d'><string>colors</string></var></struct></data></wddxPacket>
```


CIII. XML parser functions

Introduction

About XML

XML (eXtensible Markup Language) is a data format for structured document interchange on the Web. It is a standard defined by The World Wide Web consortium (W3C). Information about XML and related technologies can be found at <http://www.w3.org/XML/>.

Installation

This extension uses expat, which can be found at <http://www.jclark.com/xml/>. The Makefile that comes with expat does not build a library by default, you can use this make rule for that:

```
libexpat.a: $(OBJS)
    ar -rc $@ $(OBJS)
    ranlib $@
```

A source RPM package of expat can be found at <http://sourceforge.net/projects/expat/>.

Note that if you are using Apache-1.3.7 or later, you already have the required expat library. Simply configure PHP using `--with-xml` (without any additional path) and it will automatically use the expat library built into Apache.

On UNIX, run **configure** with the `--with-xml` option. The expat library should be installed somewhere your compiler can find it. If you compile PHP as a module for Apache 1.3.9 or later, PHP will automatically use the bundled expat library from Apache. You may need to set `CPPFLAGS` and `LDFLAGS` in your environment before running **configure** if you have installed expat somewhere exotic.

Build PHP. *Tada!* That should be it.

About This Extension

This PHP extension implements support for James Clark's expat in PHP. This toolkit lets you parse, but not validate, XML documents. It supports three source character encodings also provided by PHP: `US-ASCII`, `ISO-8859-1` and `UTF-8`. `UTF-16` is not supported.

This extension lets you create XML parsers and then define *handlers* for different XML events. Each XML parser also has a few parameters you can adjust.

The XML event handlers defined are:

Tabulka 1. Supported XML handlers

PHP function to set handler	Event description
-----------------------------	-------------------

PHP function to set handler	Event description
<code>xml_set_element_handler()</code>	Element events are issued whenever the XML parser encounters start or end tags. There are separate handlers for start tags and end tags.
<code>xml_set_character_data_handler()</code>	Character data is roughly all the non-markup contents of XML documents, including whitespace between tags. Note that the XML parser does not add or remove any whitespace, it is up to the application (you) to decide whether whitespace is significant.
<code>xml_set_processing_instruction_handler()</code>	PHP programmers should be familiar with processing instructions (PIs) already. <code><?php ?></code> is a processing instruction, where <i>php</i> is called the "PI target". The handling of these are application-specific, except that all PI targets starting with "XML" are reserved.
<code>xml_set_default_handler()</code>	What goes not to another handler goes to the default handler. You will get things like the XML and document type declarations in the default handler.
<code>xml_set_unparsed_entity_decl_handler()</code>	This handler will be called for declaration of an unparsed (NDATA) entity.
<code>xml_set_notation_decl_handler()</code>	This handler is called for declaration of a notation.
<code>xml_set_external_entity_ref_handler()</code>	This handler is called when the XML parser finds a reference to an external parsed general entity. This can be a reference to a file or URL, for example. See the external entity example for a demonstration.

Case Folding

The element handler functions may get their element names *case-folded*. Case-folding is defined by the XML standard as "a process applied to a sequence of characters, in which those identified as non-uppercase are replaced by their uppercase equivalents". In other words, when it comes to XML, case-folding simply means uppercasing.

By default, all the element names that are passed to the handler functions are case-folded. This behaviour can be queried and controlled per XML parser with the `xml_parser_get_option()` and `xml_parser_set_option()` functions, respectively.

Error Codes

The following constants are defined for XML error codes (as returned by `xml_parse()`):

`XML_ERROR_NONE`
`XML_ERROR_NO_MEMORY`

```

XML_ERROR_SYNTAX
XML_ERROR_NO_ELEMENTS
XML_ERROR_INVALID_TOKEN
XML_ERROR_UNCLOSED_TOKEN
XML_ERROR_PARTIAL_CHAR
XML_ERROR_TAG_MISMATCH
XML_ERROR_DUPLICATE_ATTRIBUTE
XML_ERROR_JUNK_AFTER_DOC_ELEMENT
XML_ERROR_PARAM_ENTITY_REF
XML_ERROR_UNDEFINED_ENTITY
XML_ERROR_RECURSIVE_ENTITY_REF
XML_ERROR_ASYNC_ENTITY
XML_ERROR_BAD_CHAR_REF
XML_ERROR_BINARY_ENTITY_REF
XML_ERROR_ATTRIBUTE_EXTERNAL_ENTITY_REF
XML_ERROR_MISPLACED_XML_PI
XML_ERROR_UNKNOWN_ENCODING
XML_ERROR_INCORRECT_ENCODING
XML_ERROR_UNCLOSED_CDATA_SECTION
XML_ERROR_EXTERNAL_ENTITY_HANDLING

```

Character Encoding

PHP's XML extension supports the Unicode (<http://www.unicode.org/>) character set through different *character encodings*. There are two types of character encodings, *source encoding* and *target encoding*. PHP's internal representation of the document is always encoded with UTF-8.

Source encoding is done when an XML document is parsed. Upon creating an XML parser, a source encoding can be specified (this encoding can not be changed later in the XML parser's lifetime). The supported source encodings are ISO-8859-1, US-ASCII and UTF-8. The former two are single-byte encodings, which means that each character is represented by a single byte. UTF-8 can encode characters composed by a variable number of bits (up to 21) in one to four bytes. The default source encoding used by PHP is ISO-8859-1.

Target encoding is done when PHP passes data to XML handler functions. When an XML parser is created, the target encoding is set to the same as the source encoding, but this may be changed at any point. The target encoding will affect character data as well as tag names and processing instruction targets.

If the XML parser encounters characters outside the range that its source encoding is capable of representing, it will return an error.

If PHP encounters characters in the parsed XML document that can not be represented in the chosen target encoding, the problem characters will be "demoted". Currently, this means that such characters

are replaced by a question mark.

Some Examples

Here are some example PHP scripts parsing XML documents.

XML Element Structure Example

This first example displays the structure of the start elements in a document with indentation.

Příklad 1. Show XML Element Structure

```
$file = "data.xml";
$depth = array();

function startElement($parser, $name, $attrs) {
    global $depth;
    for ($i = 0; $i < $depth[$parser]; $i++) {
        print "  ";
    }
    print "$name\n";
    $depth[$parser]++;
}

function endElement($parser, $name) {
    global $depth;
    $depth[$parser]--;
}

$xml_parser = xml_parser_create();
xml_set_element_handler($xml_parser, "startElement", "endElement");
if (!$fp = fopen($file, "r")) {
    die("could not open XML input");
}

while ($data = fread($fp, 4096)) {
    if (!xml_parse($xml_parser, $data, feof($fp))) {
        die(sprintf("XML error: %s at line %d",
            xml_error_string(xml_get_error_code($xml_parser)),
            xml_get_current_line_number($xml_parser)));
    }
}
xml_parser_free($xml_parser);
```

XML Tag Mapping Example

Příklad 2. Map XML to HTML

This example maps tags in an XML document directly to HTML tags. Elements not found in the "map array" are ignored. Of course, this example will only work with a specific XML document type.

```
$file = "data.xml";
$map_array = array(
    "BOLD"      => "B",
    "EMPHASIS" => "I",
    "LITERAL"  => "TT"
);

function startElement($parser, $name, $attrs) {
    global $map_array;
    if ($htmltag = $map_array[$name]) {
        print "<$htmltag>";
    }
}

function endElement($parser, $name) {
    global $map_array;
    if ($htmltag = $map_array[$name]) {
        print "</$htmltag>";
    }
}

function characterData($parser, $data) {
    print $data;
}

$xml_parser = xml_parser_create();
// use case-folding so we are sure to find the tag in $map_array
xml_parser_set_option($xml_parser, XML_OPTION_CASE_FOLDING, true);
xml_set_element_handler($xml_parser, "startElement", "endElement");
xml_set_character_data_handler($xml_parser, "characterData");
if (!$fp = fopen($file, "r")) {
    die("could not open XML input");
}

while ($data = fread($fp, 4096)) {
    if (!xml_parse($xml_parser, $data, feof($fp))) {
        die(sprintf("XML error: %s at line %d",
            xml_error_string(xml_get_error_code($xml_parser)),
            xml_get_current_line_number($xml_parser)));
    }
}
xml_parser_free($xml_parser);
```

XML External Entity Example

This example highlights XML code. It illustrates how to use an external entity reference handler to include and parse other documents, as well as how PIs can be processed, and a way of determining "trust" for PIs containing code.

XML documents that can be used for this example are found below the example (xmltest.xml and xmltest2.xml.)

Příklad 3. External Entity Example

```
<?php
$file = "xmltest.xml";

function trustedFile($file) {
    // only trust local files owned by ourselves
    if (!eregi("^[a-z]+://", $file)
        && fileowner($file) == getmyuid()) {
        return true;
    }
    return false;
}

function startElement($parser, $name, $attribs) {
    print "<<font color=\"#0000cc\">$name</font>";
    if (sizeof($attribs)) {
        while (list($k, $v) = each($attribs)) {
            print " <font color=\"#009900\">$k</font>=<font
                color=\"#990000\">$v</font>\"";
        }
    }
    print ">";
}

function endElement($parser, $name) {
    print "</<font color=\"#0000cc\">$name</font>>";
}

function characterData($parser, $data) {
    print "<b>$data</b>";
}

function PIHandler($parser, $target, $data) {
    switch (strtolower($target)) {
        case "php":
            global $parser_file;
            // If the parsed document is "trusted", we say it is safe
            // to execute PHP code inside it. If not, display the code
            // instead.
```

```

        if (trustedFile($parser_file[$parser])) {
            eval($data);
        } else {
            printf("Untrusted PHP code: <i>%s</i>",
                htmlspecialchars($data));
        }
        break;
    }
}

function defaultHandler($parser, $data) {
    if (substr($data, 0, 1) == "&" && substr($data, -1, 1) == ";") {
        printf('<font color="#aa00aa">%s</font>',
            htmlspecialchars($data));
    } else {
        printf('<font size="-1">%s</font>',
            htmlspecialchars($data));
    }
}

function externalEntityRefHandler($parser, $openEntityNames, $base, $systemId,
    $publicId) {
    if ($systemId) {
        if (!list($parser, $fp) = new_xml_parser($systemId)) {
            printf("Could not open entity %s at %s\n", $openEntityNames,
                $systemId);
            return false;
        }
        while ($data = fread($fp, 4096)) {
            if (!xml_parse($parser, $data, feof($fp))) {
                printf("XML error: %s at line %d while parsing entity %s\n",
                    xml_error_string(xml_get_error_code($parser)),
                    xml_get_current_line_number($parser), $openEntityNames);
                xml_parser_free($parser);
                return false;
            }
        }
        xml_parser_free($parser);
        return true;
    }
    return false;
}

function new_xml_parser($file) {
    global $parser_file;

    $xml_parser = xml_parser_create();
    xml_parser_set_option($xml_parser, XML_OPTION_CASE_FOLDING, 1);
    xml_set_element_handler($xml_parser, "startElement", "endElement");
    xml_set_character_data_handler($xml_parser, "characterData");
    xml_set_processing_instruction_handler($xml_parser, "PIHandler");
    xml_set_default_handler($xml_parser, "defaultHandler");
    xml_set_external_entity_ref_handler($xml_parser, "externalEntityRefHandler");

    if (!($fp = @fopen($file, "r"))) {
        return false;
    }
}

```

```

    if (!is_array($parser_file)) {
        settype($parser_file, "array");
    }
    $parser_file[$xml_parser] = $file;
    return array($xml_parser, $fp);
}

if (!(list($xml_parser, $fp) = new_xml_parser($file))) {
    die("could not open XML input");
}

print "<pre>";
while ($data = fread($fp, 4096)) {
    if (!xml_parse($xml_parser, $data, feof($fp))) {
        die(sprintf("XML error: %s at line %d\n",
            xml_error_string(xml_get_error_code($xml_parser)),
            xml_get_current_line_number($xml_parser)));
    }
}
print "</pre>";
print "parse complete\n";
xml_parser_free($xml_parser);

?>

```

Příklad 4. xmltest.xml

```

<?xml version='1.0'?>
<!DOCTYPE chapter SYSTEM "/just/a/test.dtd" [
<!ENTITY plainEntity "FOO entity">
<!ENTITY systemEntity SYSTEM "xmltest2.xml">
]>
<chapter>
<TITLE>Title &plainEntity;</TITLE>
<para>
<informaltable>
<tgroup cols="3">
<tbody>
<row><entry>a1</entry><entry morerows="1">b1</entry><entry>c1</entry></row>
<row><entry>a2</entry><entry>c2</entry></row>
<row><entry>a3</entry><entry>b3</entry><entry>c3</entry></row>
</tbody>
</tgroup>
</informaltable>
</para>
&systemEntity;
<section id="about">
<title>About this Document</title>
<para>
<!-- this is a comment -->
<?php print 'Hi! This is PHP version '.phpversion(); ?>
</para>

```



```
</section>  
</chapter>
```

This file is included from `xmltest.xml`:

Příklad 5. `xmltest2.xml`

```
<?xml version="1.0"?>  
<!DOCTYPE foo [  
<!ENTITY testEnt "test entity">  
>  
<foo>  
  <element attrib="value"/>  
  &testEnt;  
  <?php print "This is some more PHP code being executed."; ?>  
</foo>
```

utf8_decode (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Converts a string with ISO-8859-1 characters encoded with UTF-8 to single-byte ISO-8859-1.

string **utf8_decode** (string *data*) \linebreak

This function decodes *data*, assumed to be UTF-8 encoded, to ISO-8859-1.

See utf8_encode() for an explanation of UTF-8 encoding.

utf8_encode (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

encodes an ISO-8859-1 string to UTF-8

string **utf8_encode** (string *data*) \linebreak

This function encodes the string *data* to UTF-8, and returns the encoded version. UTF-8 is a standard mechanism used by Unicode for encoding *wide character* values into a byte stream. UTF-8 is transparent to plain ASCII characters, is self-synchronized (meaning it is possible for a program to figure out where in the bytestream characters start) and can be used with normal string comparison functions for sorting and such. PHP encodes UTF-8 characters in up to four bytes, like this:

Tabulka 1. UTF-8 encoding

bytes	bits	representation
1	7	0bbbbbbb
2	11	110bbbb 10bbbbbb
3	16	1110bbbb 10bbbbbb 10bbbbbb
4	21	11110bbb 10bbbbbb 10bbbbbb 10bbbbbb

Each *b* represents a bit that can be used to store character data.

xml_error_string (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

get XML parser error string

string **xml_error_string** (int *code*) \linebreak

code

An error code from xml_get_error_code().

Returns a string with a textual description of the error code *code*, or FALSE if no description was found.

xml_get_current_byte_index (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

get current byte index for an XML parser

```
int xml_get_current_byte_index ( resource parser) \linebreak
```

parser

A reference to the XML parser to get byte index from.

This function returns `FALSE` if *parser* does not refer to a valid parser, or else it returns which byte index the parser is currently at in its data buffer (starting at 0).

xml_get_current_column_number (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Get current column number for an XML parser

```
int xml_get_current_column_number ( resource parser) \linebreak
```

parser

A reference to the XML parser to get column number from.

This function returns `FALSE` if *parser* does not refer to a valid parser, or else it returns which column on the current line (as given by `xml_get_current_line_number()`) the parser is currently at.

xml_get_current_line_number (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

get current line number for an XML parser

```
int xml_get_current_line_number ( resource parser) \linebreak
```

parser

A reference to the XML parser to get line number from.

This function returns `FALSE` if *parser* does not refer to a valid parser, or else it returns which line the parser is currently at in its data buffer.

xml_get_error_code (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

get XML parser error code

```
int xml_get_error_code ( resource parser) \linebreak
```

parser

A reference to the XML parser to get error code from.

This function returns `FALSE` if *parser* does not refer to a valid parser, or else it returns one of the error codes listed in the error codes section.

xml_parse (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

start parsing an XML document

```
bool xml_parse ( resource parser, string data [, bool is_final]) \linebreak
```

parser

A reference to the XML parser to use.

data

Chunk of data to parse. A document may be parsed piece-wise by calling **xml_parse()** several times with new data, as long as the *is_final* parameter is set and `TRUE` when the last data is parsed.

is_final (optional)

If set and `TRUE`, *data* is the last piece of data sent in this parse.

When the XML document is parsed, the handlers for the configured events are called as many times as necessary, after which this function returns `TRUE` or `FALSE`.

`TRUE` is returned if the parse was successful, `FALSE` if it was not successful, or if *parser* does not refer to a valid parser. For unsuccessful parses, error information can be retrieved with `xml_get_error_code()`, `xml_error_string()`, `xml_get_current_line_number()`, `xml_get_current_column_number()` and `xml_get_current_byte_index()`.

xml_parse_into_struct (PHP 3>= 3.0.8, PHP 4 >= 4.0.0)

Parse XML data into an array structure

```
int xml_parse_into_struct ( resource parser, string data, array &values, array &index) \linebreak
```

This function parses an XML file into 2 parallel array structures, one (*index*) containing pointers to the location of the appropriate values in the *values* array. These last two parameters must be passed by reference.

Below is an example that illustrates the internal structure of the arrays being generated by the function. We use a simple `note` tag embedded inside a `para` tag, and then we parse this and print out the structures generated:

```

$simple = "<para><note>simple note</note></para>";
$p = xml_parser_create();
xml_parse_into_struct($p,$simple,$vals,$index);
xml_parser_free($p);
echo "Index array\n";
print_r($index);
echo "\nVals array\n";
print_r($vals);

```

When we run that code, the output will be:

```

Index array
Array
(
    [PARAM] => Array
        (
            [0] => 0
            [1] => 2
        )

    [NOTE] => Array
        (
            [0] => 1
        )
)

Vals array
Array
(
    [0] => Array
        (
            [tag] => PARAM
            [type] => open
            [level] => 1
        )

    [1] => Array
        (
            [tag] => NOTE
            [type] => complete
            [level] => 2
            [value] => simple note
        )

    [2] => Array
        (
            [tag] => PARAM
            [type] => close
            [level] => 1
        )
)

```

Event-driven parsing (based on the expat library) can get complicated when you have an XML document that is complex. This function does not produce a DOM style object, but it generates structures amenable of being transversed in a tree fashion. Thus, we can create objects representing the data in the XML file easily. Let's consider the following XML file representing a small database of aminoacids information:

Příklad 1. moldb.xml - small database of molecular information

```
<?xml version="1.0"?>
<moldb>

  <molecule>
    <name>Alanine</name>
    <symbol>ala</symbol>
    <code>A</code>
    <type>hydrophobic</type>
  </molecule>

  <molecule>
    <name>Lysine</name>
    <symbol>lys</symbol>
    <code>K</code>
    <type>charged</type>
  </molecule>

</moldb>
```

And some code to parse the document and generate the appropriate objects:

Příklad 2. parsemoldb.php - parses moldb.xml into an array of molecular objects

```
<?php

class AminoAcid {
    var $name; // aa name
    var $symbol; // three letter symbol
    var $code; // one letter code
    var $type; // hydrophobic, charged or neutral

    function AminoAcid ($aa) {
        foreach ($aa as $k=>$v)
            $this->$k = $aa[$k];
    }
}

function readDatabase($filename) {
    // read the xml database of aminoacids
```

```

$data = implode("",file($filename));
$parser = xml_parser_create();
xml_parser_set_option($parser,XML_OPTION_CASE_FOLDING,0);
xml_parser_set_option($parser,XML_OPTION_SKIP_WHITE,1);
xml_parse_into_struct($parser,$data,$values,$tags);
xml_parser_free($parser);

// loop through the structures
foreach ($tags as $key=>$val) {
    if ($key == "molecule") {
        $molranges = $val;
        // each contiguous pair of array entries are the
        // lower and upper range for each molecule definition
        for ($i=0; $i < count($molranges); $i+=2) {
            $offset = $molranges[$i] + 1;
            $len = $molranges[$i + 1] - $offset;
            $tdb[] = parseMol(array_slice($values, $offset, $len));
        }
    } else {
        continue;
    }
}
return $tdb;
}

function parseMol($mvalues) {
    for ($i=0; $i < count($mvalues); $i++)
        $mol[$mvalues[$i]["tag"]] = $mvalues[$i]["value"];
    return new AminoAcid($mol);
}

$db = readDatabase("molddb.xml");
echo "** Database of AminoAcid objects:\n";
print_r($db);

?>

```

After executing `parsemolddb.php`, the variable `$db` contains an array of `AminoAcid` objects, and the output of the script confirms that:

```

** Database of AminoAcid objects:
Array
(
    [0] => aminoacid Object
        (
            [name] => Alanine
            [symbol] => ala
            [code] => A
            [type] => hydrophobic
        )

    [1] => aminoacid Object
        (

```

```

        [name] => Lysine
        [symbol] => lys
        [code] => K
        [type] => charged
    )
)

```

xml_parser_create (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

create an XML parser

resource **xml_parser_create** ([string encoding]) \linebreak

encoding (optional)

Which character encoding the parser should use. The following character encodings are supported:
 ISO-8859-1 (default)
 US-ASCII
 UTF-8

This function creates an XML parser and returns a handle for use by other XML functions. Returns FALSE on failure.

xml_parser_create_ns (PHP 4 >= 4.0.5)

Create an XML parser

resource **xml_parser_create_ns** ([string encoding [, string sep]]) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xml_parser_free (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

Free an XML parser

bool **xml_parser_free** (resource parser) \linebreak

parser

A reference to the XML parser to free.

This function returns `FALSE` if *parser* does not refer to a valid parser, or else it frees the parser and returns `TRUE`.

xml_parser_get_option (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

get options from an XML parser

mixed **xml_parser_get_option** (resource *parser*, int *option*) \linebreak

parser

A reference to the XML parser to get an option from.

option

Which option to fetch. See `xml_parser_set_option()` for a list of options.

This function returns `FALSE` if *parser* does not refer to a valid parser, or if the option could not be set. Else the option's value is returned.

See `xml_parser_set_option()` for the list of options.

xml_parser_set_option (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

set options in an XML parser

bool **xml_parser_set_option** (resource *parser*, int *option*, mixed *value*) \linebreak

parser

A reference to the XML parser to set an option in.

option

Which option to set. See below.

value

The option's new value.

This function returns `FALSE` if *parser* does not refer to a valid parser, or if the option could not be set. Else the option is set and `TRUE` is returned.

The following options are available:

Tabulka 1. XML parser options

Option constant	Data type	Description
<code>XML_OPTION_CASE_FOLDING</code>	Integer	Controls whether case-folding is enabled for this XML parser. Enabled by default.
<code>XML_OPTION_TARGET_ENCODING</code>	String	Sets which target encoding to use in this XML parser. By default, it is set to the same as the source encoding used by <code>xml_parser_create()</code> . Supported target encodings are ISO-8859-1, US-ASCII and UTF-8.

xml_set_character_data_handler (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

set up character data handler

bool **xml_set_character_data_handler** (resource *parser*, string *handler*) \linebreak

Sets the character data handler function for the XML parser *parser*. *handler* is a string containing the name of a function that must exist when `xml_parse()` is called for *parser*.

The function named by *handler* must accept two parameters: ***handler*** (resource *parser*, string *data*) \linebreak

parser

The first parameter, *parser*, is a reference to the XML parser calling the handler.

data

The second parameter, *data*, contains the character data as a string.

If a handler function is set to an empty string, or `FALSE`, the handler in question is disabled.

`TRUE` is returned if the handler is set up, `FALSE` if *parser* is not a parser.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

xml_set_default_handler (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

set up default handler

bool **xml_set_default_handler** (resource *parser*, string *handler*) \linebreak

Sets the default handler function for the XML parser *parser*. *handler* is a string containing the name of a function that must exist when `xml_parse()` is called for *parser*.

The function named by *handler* must accept two parameters: ***handler*** (resource parser, string data) \linebreak

parser

The first parameter, *parser*, is a reference to the XML parser calling the handler.

data

The second parameter, *data*, contains the character data. This may be the XML declaration, document type declaration, entities or other data for which no other handler exists.

If a handler function is set to an empty string, or FALSE, the handler in question is disabled.

TRUE is returned if the handler is set up, FALSE if *parser* is not a parser.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

xml_set_element_handler (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

set up start and end element handlers

bool **xml_set_element_handler** (resource parser, string start_element_handler, string end_element_handler) \linebreak

Sets the element handler functions for the XML parser *parser*. *start_element_handler* and *end_element_handler* are strings containing the names of functions that must exist when `xml_parse()` is called for *parser*.

The function named by *start_element_handler* must accept three parameters: ***start_element_handler*** (resource parser, string name, array attrs) \linebreak

parser

The first parameter, *parser*, is a reference to the XML parser calling the handler.

name

The second parameter, *name*, contains the name of the element for which this handler is called. If case-folding is in effect for this parser, the element name will be in uppercase letters.

attrs

The third parameter, *attrs*, contains an associative array with the element's attributes (if any). The keys of this array are the attribute names, the values are the attribute values. Attribute names are case-folded on the same criteria as element names. Attribute values are *not* case-folded.

The original order of the attributes can be retrieved by walking through *attrs* the normal way, using `each()`. The first key in the array was the first attribute, and so on.

The function named by *end_element_handler* must accept two parameters:
end_element_handler (resource parser, string name) \linebreak

parser

The first parameter, *parser*, is a reference to the XML parser calling the handler.

name

The second parameter, *name*, contains the name of the element for which this handler is called.
 If case-folding is in effect for this parser, the element name will be in uppercase letters.

If a handler function is set to an empty string, or FALSE, the handler in question is disabled.

TRUE is returned if the handlers are set up, FALSE if *parser* is not a parser.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

xml_set_end_namespace_decl_handler (PHP 4 >= 4.0.5)

Set up character data handler

bool **xml_set_end_namespace_decl_handler** (resource pind, string hdl) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

xml_set_external_entity_ref_handler (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

set up external entity reference handler

bool **xml_set_external_entity_ref_handler** (resource parser, string handler) \linebreak

Sets the external entity reference handler function for the XML parser *parser*. *handler* is a string containing the name of a function that must exist when *xml_parse()* is called for *parser*.

The function named by *handler* must accept five parameters, and should return an integer value. If the value returned from the handler is `FALSE` (which it will be if no value is returned), the XML parser will stop parsing and `xml_get_error_code()` will return `XML_ERROR_EXTERNAL_ENTITY_HANDLING`. ***handler*** (resource parser, string open_entity_names, string base, string system_id, string public_id) \linebreak

parser

The first parameter, *parser*, is a reference to the XML parser calling the handler.

open_entity_names

The second parameter, *open_entity_names*, is a space-separated list of the names of the entities that are open for the parse of this entity (including the name of the referenced entity).

base

This is the base for resolving the system identifier (*system_id*) of the external entity. Currently this parameter will always be set to an empty string.

system_id

The fourth parameter, *system_id*, is the system identifier as specified in the entity declaration.

public_id

The fifth parameter, *public_id*, is the public identifier as specified in the entity declaration, or an empty string if none was specified; the whitespace in the public identifier will have been normalized as required by the XML spec.

If a handler function is set to an empty string, or `FALSE`, the handler in question is disabled.

`TRUE` is returned if the handler is set up, `FALSE` if *parser* is not a parser.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

xml_set_notation_decl_handler (PHP 3>= 3.0.6, PHP 4 >= 4.0.0)

set up notation declaration handler

bool **xml_set_notation_decl_handler** (resource parser, string handler) \linebreak

Sets the notation declaration handler function for the XML parser *parser*. *handler* is a string containing the name of a function that must exist when `xml_parse()` is called for *parser*.

A notation declaration is part of the document's DTD and has the following format:

```
<!NOTATION
    name {system_id |
    public_id}>
```

See section 4.7 of the XML 1.0 spec (<http://www.w3.org/TR/1998/REC-xml-19980210#Notations>) for the definition of notation declarations.

The function named by *handler* must accept five parameters: **handler** (resource parser, string notation_name, string base, string system_id, string public_id) \linebreak

parser

The first parameter, *parser*, is a reference to the XML parser calling the handler.

notation_name

This is the notation's *name*, as per the notation format described above.

base

This is the base for resolving the system identifier (*system_id*) of the notation declaration. Currently this parameter will always be set to an empty string.

system_id

System identifier of the external notation declaration.

public_id

Public identifier of the external notation declaration.

If a handler function is set to an empty string, or FALSE, the handler in question is disabled.

TRUE is returned if the handler is set up, FALSE if *parser* is not a parser.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

xml_set_object (PHP 4 >= 4.0.0)

Use XML Parser within an object

void **xml_set_object** (resource parser, object &object) \linebreak

This function allows to use *parser* inside *object*. All callback functions could be set with `xml_set_element_handler()` etc and assumed to be methods of *object*.

```
<?php
class xml {
    var $parser;

    function xml()
    {
        $this->parser = xml_parser_create();

        xml_set_object($this->parser, &$this);
        xml_set_element_handler($this->parser, "tag_open", "tag_close");
        xml_set_character_data_handler($this->parser, "cdata");
    }
}
```

```

    }

    function parse($data)
    {
        xml_parse($this->parser, $data);
    }

    function tag_open($parser, $tag, $attributes)
    {
        var_dump($parser, $tag, $attributes);
    }

    function cdata($parser, $cdata)
    {
        var_dump($parser, $cdata);
    }

    function tag_close($parser, $tag)
    {
        var_dump($parser, $tag);
    }

} // end of class xml

$xml_parser = new xml();
$xml_parser->parse("<A ID='hallo'>PHP</A>");
?>

```

xml_set_processing_instruction_handler (PHP 3>= 3.0.6, PHP 4 >=

4.0.0)

Set up processing instruction (PI) handler

bool **xml_set_processing_instruction_handler** (resource parser, string handler) \linebreak

Sets the processing instruction (PI) handler function for the XML parser *parser*. *handler* is a string containing the name of a function that must exist when `xml_parse()` is called for *parser*.

A processing instruction has the following format:

```

<?
    target
    data?>

```

You can put PHP code into such a tag, but be aware of one limitation: in an XML PI, the PI end tag (`?>`) can not be quoted, so this character sequence should not appear in the PHP code you embed with PIs in XML documents. If it does, the rest of the PHP code, as well as the "real" PI end tag, will be treated as character data.

The function named by *handler* must accept three parameters: **handler** (resource parser, string target, string data) \linebreak

parser

The first parameter, *parser*, is a reference to the XML parser calling the handler.

target

The second parameter, *target*, contains the PI target.

data

The third parameter, *data*, contains the PI data.

If a handler function is set to an empty string, or FALSE, the handler in question is disabled.

TRUE is returned if the handler is set up, FALSE if *parser* is not a parser.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

xml_set_start_namespace_decl_handler (PHP 4 >= 4.0.5)

Set up character data handler

bool **xml_set_start_namespace_decl_handler** (resource pind, string hdl) \linebreak

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

xml_set_unparsed_entity_decl_handler (PHP 3 >= 3.0.6, PHP 4 >= 4.0.0)

Set up unparsed entity declaration handler

bool **xml_set_unparsed_entity_decl_handler** (resource parser, string handler) \linebreak

Sets the unparsed entity declaration handler function for the XML parser *parser*. *handler* is a string containing the name of a function that must exist when `xml_parse()` is called for *parser*.

This handler will be called if the XML parser encounters an external entity declaration with an NDATA declaration, like the following:


```
<!ENTITY name {publicId | systemId}
    NDATA notationName>
```

See section 4.2.2 of the XML 1.0 spec
(<http://www.w3.org/TR/1998/REC-xml-19980210#sec-external-ent>) for the definition of notation declared external entities.

The function named by *handler* must accept six parameters: **handler** (resource parser, string entity_name, string base, string system_id, string public_id, string notation_name) \linebreak

parser

The first parameter, *parser*, is a reference to the XML parser calling the handler.

entity_name

The name of the entity that is about to be defined.

base

This is the base for resolving the system identifier (*systemId*) of the external entity. Currently this parameter will always be set to an empty string.

system_id

System identifier for the external entity.

public_id

Public identifier for the external entity.

notation_name

Name of the notation of this entity (see `xml_set_notation_decl_handler()`).

If a handler function is set to an empty string, or `FALSE`, the handler in question is disabled.

`TRUE` is returned if the handler is set up, `FALSE` if *parser* is not a parser.

Poznámka: Místo názvu funkce může použito pole obsahující odkaz na objekt a název metody.

CIV. XMLRPC functions

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

xmlrpc_decode (PHP 4 >= 4.1.0)

Decodes XML into native PHP types

array **xmlrpc_decode** (string xml [, string encoding]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_decode_request (PHP 4 >= 4.1.0)

Decodes XML into native PHP types

array **xmlrpc_decode_request** (string xml, string method [, string encoding]) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_encode (PHP 4 >= 4.1.0)

Generates XML for a PHP value

string **xmlrpc_encode** (mixed value) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_encode_request (PHP 4 >= 4.1.0)

Generates XML for a method request

string **xmlrpc_encode_request** (string method, mixed params) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_get_type (PHP 4 >= 4.1.0)

Gets xmlrpc type for a PHP value. Especially useful for base64 and datetime strings

string **xmlrpc_get_type** (mixed value) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_parse_method_descriptions (PHP 4 >= 4.1.0)

Decodes XML into a list of method descriptions

array **xmlrpc_parse_method_descriptions** (string xml) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_server_add_introspection_data (PHP 4 >= 4.1.0)

Adds introspection documentation

int **xmlrpc_server_add_introspection_data** (resource server, array desc) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_server_call_method (PHP 4 >= 4.1.0)

Parses XML requests and call methods

mixed **xmlrpc_server_call_method** (resource server, string xml, mixed user_data [, array output_options])
 \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_server_create (PHP 4 >= 4.1.0)

Creates an xmlrpc server

resource **xmlrpc_server_create** (void) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_server_destroy (PHP 4 >= 4.1.0)

Destroys server resources

void **xmlrpc_server_destroy** (resource server) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_server_register_introspection_callback (PHP 4 >=

4.1.0)

Register a PHP function to generate documentation

bool **xmlrpc_server_register_introspection_callback** (resource server, string function) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_server_register_method (PHP 4 >= 4.1.0)

Register a PHP function to resource method matching method_name

bool **xmlrpc_server_register_method** (resource server, string method_name, string function) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

xmlrpc_set_type (PHP 4 >= 4.1.0)

Sets xmlrpc type, base64 or datetime, for a PHP string value

bool **xmlrpc_set_type** (string value, string type) \linebreak

Varování

Tato funkce je *EXPERIMENTÁLNÍ*. To znamená, že chování této funkce a její název, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tuto funkci na vlastní nebezpečí.

Varování

Tato funkce ještě není zdokumentována, k dispozici je pouze seznam argumentů.

CV. XSLT funkce

Varování

Tento modul je *EXPERIMENTÁLNÍ*. To znamená, že chování těchto funkcí a jejich názvy, přesněji řečeno COKOLI, co je zde zdokumentováno, se v budoucích verzích PHP může BEZ OHLÁŠENÍ změnit. Berte to v úvahu a používejte tento modul na vlastní nebezpečí.

Úvod

O XSLT and Sablotronu

XSLT (Extensible Stylesheet Language (XSL) Transformations) je jazyk pro transformaci XML dokumentů do jiných XML dokumentů. Je to standard definovaný The World Wide Web konsorciem (W3C). Informace o XSLT a souvisejících technologiích jsou dostupné na <http://www.w3.org/TR/xslt>.

Instalace

Tato extenze využívá Sabloton a expat, které jsou dostupné na <http://www.gingerall.com/>, a to jak binární soubory tak zdrojové kódy.

Na UNIXu spusťte **configure** s `--with-sablot`. Sablotron knihovna by měla být nainstalována na nějakém místě, kde ji váš kompilátor může najít.

O této extenzi

Tato PHP extenze implementuje podporu Sablotron od Ginger Alliance v PHP. Tato nástroj vám umožňuje transformovat XML dokumenty na jiné dokumenty, včetně nových XML dokumentů, ale také do XML a jiných cílových formátů. V podstatě poskytuje standardizovaný a přenosný systém šablon oddělující obsah a design websajty.

xslt_closelog (4.0.3 - 4.0.6 only)

Smazat log dané instance Sablotronu

bool **xslt_closelog** (resource *xh*) \linebreak

xh

Reference na XSLT parser.

Pokud *parser* neodkazuje na platný parser, nebo pokud zavření logu selže, vrátí FALSE, jinak vrátí TRUE

xslt_create (PHP 4 >= 4.0.3)

Vytvořit nový XSL procesor

resource **xslt_create** (void) \linebreak

Tato funkce vrátí handle nového XSL procesoru. Tento handle je potřeba ve všech následných voláních XSL funkcí.

xslt_errno (PHP 4 >= 4.0.3)

Vrátit číslo současné chyby

int **xslt_errno** ([int *xh*]) \linebreak

Vrací číslo současné chyby daného XSL procesoru. Pokud nedostane handle, vrátí číslo poslední chyby bez ohledu na její výskyt.

xslt_error (PHP 4 >= 4.0.3)

Vrátit text poslední chyby

mixed **xslt_error** ([int *xh*]) \linebreak

Vrací text současné chyby daného XSL procesoru. Pokud nedostane handle, vrátí text poslední chyby bez ohledu na její výskyt.

xslt_fetch_result (4.0.3 - 4.0.6 only)

Získat (pojmenovaný) výstupní buffer

```
string xslt_fetch_result ( int xh [, string result_name]) \linebreak
```

Vrací výstupní buffer XSLT procesoru identifikovaného předaným handle. Pokud nedostane jméno výstupního bufferu, vrací buffer pojmenovaný `"/_result"`.

xslt_free (PHP 4 >= 4.0.3)

Uvolnit XSLT procesor

```
void xslt_free ( resource xh) \linebreak
```

Uvolní XSLT procesor identifikovaný předaným handle.

xslt_openlog (4.0.3 - 4.0.6 only)

Určit log pro zprávy XSLT procesoru

```
bool xslt_openlog ( resource xh, string logfile [, int loglevel]) \linebreak
```

Určí log soubor, do kterého má XSLT procesor umístit všechny chybové zprávy.

xslt_output_begintransform (4.0.3 - 4.0.6 only)

Začít XSLT transformaci výstupu

```
void xslt_output_begintransform ( string xslt_filename) \linebreak
```

Tato funkce začne výstupní transformaci vašich dat. Od okamžiku, kdy zavoláte **xslt_output_begintransform()** až do chvíle kdy zavoláte **xslt_output_endtransform()** bude všechn výstup transformován XSLT stylesheetem udaným v prvním argumentu.

Příklad 1. Transformace výstupu XSLT stylesheetem pomocí DOM-XML funkcí pro generování XML

```
<?php
```

```
$xsl_file = "article.xsl";
xslt_output_begintransform($xsl_file);
```

```
$doc = new_xmldoc('1.0');
$article = $doc->new_root('article');
```

```
$article->new_child('title', 'The History of South Tyrol');
$article->new_child('author', 'Sterling Hughes');
$article->new_child('body', 'Back after WWI, Italy gained South Tyrol from
                                Austria. Since that point nothing interesting has
                                happened');
```

```
echo $doc->dumpmem();
```

```
xslt_output_endtransform();
```

xslt_output_endtransform (4.0.3 - 4.0.6 only)

Ukončit výstupní transformaci začatou pomocí xslt_output_begintransform

```
void xslt_output_endtransform ( void) \linebreak
```

xslt_output_endtransform() ukončí výstupní transformaci začatou funkcí xslt_output_begintransform(). Pokud chcete vidět výsledky výstupní transformace, musíte tuto funkci zavolat.

xslt_process (PHP 4 >= 4.0.3)

Transformovat XML data řetězcem obsahujícím XSL data

```
mixed xslt_process ( resource xh, string xml, string xsl [, string result [, array arguments [, array parameters]]]) \linebreak
```

xslt_process() přijímá jako první argument řetězec obsahující XSLT stylesheet, jako druhý argument řetězec obsahující XML data, která chcete transformovat, a jako třetí argument řetězec obsahující výsledky transformace. **xslt_process()** vrací TRUE při úspěchu a FALSE při selhání. Číslo a text chyby případně vzniklé při transformaci můžete získat pomocí xslt_errno() a xslt_error() funkcí.

Příklad 1. Použití xslt_process() k transformaci tří řetězců

```
<?php

$xmlData = '
<xsl:stylesheet
  version="1.0"
  xmlns:xsl="http://www.w3.org/1999/XSL/Transform">

<xsl:template match="article">
  <table border="1" cellpadding="2" cellspacing="1">
    <tr>
      <td width="20%">

        </td>
      <td width="80%">
        <h2><xsl:value-of select="title"></h2>
        <h3><xsl:value-of select="author"></h3>
        <br>

        <xsl:value-of select="body">
      </td>
    </tr>
```

```

        </table>
    </xsl:template>

</xsl:stylesheet>';

$xmlData = '
<?xml version="1.0"?>
<article>
    <title>Learning German</title>
    <author>Sterling Hughes</author>
    <body>
        Essential phrases:
        <br>
        <br>
        Komme sie mir sagen, woe die toilette es?<br>
        Eine grande beer bitte!<br>
        Noch einem bitte.<br>
    </body>
</article>';

if (xslt_process($xsltData, $xmlData, $result))
{
    echo "Here is the brilliant in-depth article on learning";
    echo " German: ";
    echo "<br>\n<br>";
    echo $result;
}
else
{
    echo "There was an error that occurred in the XSL transformace...\n";
    echo "\tError number: " . xslt_errno() . "\n";
    echo "\tError string: " . xslt_error() . "\n";
    exit;
}
?>

```

xslt_run (4.0.3 - 4.0.6 only)

Aplikovat na soubor XSLT stylesheet

bool **xslt_run** (resource xh, string xslt_file, string xml_data_file [, string result [, array xslt_params [, array xslt_args]]]) \linebreak

Zpracuje Zpracovat *string xml_data_file* aplikací *string xslt_file* stylesheetu. Tento stylesheet má přístup ke *xslt_params* a nastartuje se procesor s *xslt_args*. Výsledek XSLT transformace se umístí do pojmenovaného bufferu (defaultně *"/_result"*).

xslt_set_sax_handler (4.0.3 - 4.0.6 only)

Určit SAX handlery XSLT procesoru

```
bool xslt_set_sax_handler ( resource xh, array handlers) \linebreak
```

Určit SAX handlery pro handle určený v *xh*.

xslt_transform (4.0.3 - 4.0.6 only)

Provést XSLT transformaci

```
bool xslt_transform ( string xsl, string xml, string result, string params, string args, string resultBuffer) \linebreak
```

xslt_transform() poskytuje interface k pokročilejším vlastnostem Sablotronu bez nutnosti použít resource API.

CVI. YAZ functions

Introduction

This extension offers a PHP interface to the YAZ toolkit that implements the Z39.50 protocol for information retrieval. With this extension you can easily implement a Z39.50 origin (client) that searches or scans Z39.50 targets (servers) in parallel.

YAZ is available at <http://www.indexdata.dk/yaz/>. You can find news information, example scripts, etc. for this extension at <http://www.indexdata.dk/phpyaz/>.

The module hides most of the complexity of Z39.50 so it should be fairly easy to use. It supports persistent stateless connections very similar to those offered by the various SQL APIs that are available for PHP. This means that sessions are stateless but shared amongst users, thus saving the connect and initialize phase steps in most cases.

Installation

Compile YAZ and install it. Build PHP with your favourite modules and add option `--with-yaz`. Your task is roughly the following:

```
gunzip -c yaz-1.6.tar.gz|tar xf -
gunzip -c php-4.0.X.tar.gz|tar xf -
cd yaz-1.6
./configure --prefix=/usr
make
make install
cd ../php-4.0.X
./configure --with-yaz=/usr/bin
make
make install
```

Example

PHP/YAZ keeps track of connections with targets (Z-Associations). A positive integer represents the ID of a particular association.

Příklad 1. Parallel searching using YAZ()

The script below demonstrates the parallel searching feature of the API. When invoked with no arguments it prints a query form; else (arguments are supplied) it searches the targets as given in in array host.


```

$num_hosts = count ($host);
if (empty($term) || count($host) == 0) {
    echo '<form method="get">
    <input type="checkbox"
    name="host[]" value="bagel.indexdata.dk/gils">
        GILS test
    <input type="checkbox"
    name="host[]" value="localhost:9999/Default">
        local test
    <input type="checkbox" checked="1"
    name="host[]" value="z3950.bell-labs.com/books">
        BELL Labs Library
    <br>
    RPN Query:
    <input type="text" size="30" name="term">
    <input type="submit" name="action" value="Search">
    ';
} else {
    echo 'You searched for ' . htmlspecialchars($term) . '<br>';
    for ($i = 0; $i < $num_hosts; $i++) {
        $id[] = yaz_connect($host[$i]);
        yaz_syntax($id[$i], "sutrs");
        yaz_search($id[$i], "rpn", $term);
    }
    yaz_wait();
    for ($i = 0; $i < $num_hosts; $i++) {
        echo '<hr>' . $host[$i] . ":";
        $error = yaz_error($id[$i]);
        if (!empty($error)) {
            echo "Error: $error";
        } else {
            $hits = yaz_hits($id[$i]);
            echo "Result Count $hits";
        }
        echo '<dl>';
        for ($p = 1; $p <= 10; $p++) {
            $rec = yaz_record($id[$i], $p, "string");
            if (empty($rec)) continue;
            echo "<dt><b>$p</b></dt><dd>";
            echo ereg_replace("\n", "<br>\n", $rec);
            echo "</dd>";
        }
        echo '</dl>';
    }
}
}

```

yaz_addinfo (PHP 4)

Returns additional error information

```
int yaz_addinfo ( int id) \linebreak
```

Returns additional error message for target (last request). An empty string is returned if last operation was a success or if no additional information was provided by the target.

yaz_ccl_conf (PHP 4 >= 4.0.5)

Configure CCL parser

```
int yaz_ccl_conf ( int id, array config) \linebreak
```

This function configures the CCL query parser for a target with definitions of access points (CCL qualifiers) and their mapping to RPN. To map a specific CCL query to RPN afterwards call the `yaz_ccl_parse()` function. Each index of the array *config* is the name of a CCL field and the corresponding value holds a string that specifies a mapping to RPN. The mapping is a sequence of attribute-type, attribute-value pairs. Attribute-type and attribute-value is separated by an equal sign (=). Each pair is separated by white space.

Příklad 1. CCL configuration

In the example below, the CCL parser is configured to support three CCL fields: *ti*, *au* and *isbn*. Each field is mapped to their BIB-1 equivalent. It is assumed that variable *\$id* is a target ID.

```
$field["ti"] = "1=4";
$field["au"] = "1=1";
$field["isbn"] = "1=7";
yaz_ccl_conf($id,$field);
```

yaz_ccl_parse (PHP 4 >= 4.0.5)

Invoke CCL Parser

```
int yaz_ccl_parse ( int id, string query, array & result) \linebreak
```

This function invokes the CCL parser. It converts a given CCL FIND query to an RPN query which may be passed to the `yaz_search()` function to perform a search. To define a set of valid CCL fields call `yaz_ccl_conf()` prior to this function. If the supplied *query* was successfully converted to RPN, this function returns `TRUE`, and the index *rpn* of the supplied array *result* holds a valid RPN query. If the query could not be converted (because of invalid syntax, unknown field, etc.) this function returns `FALSE` and three indexes are set in the resulting array to indicate the cause of

failure: `errorcode`CCL error code (integer), `errorstring`CCL error string, and `errorpos`approximate position in query of failure (integer is character position).

yaz_close (PHP 4)

Closes a YAZ connection

```
int yaz_close ( int id) \linebreak
```

Closes the Z-association given by *id*. The *id* is a target ID as returned by a previous `yaz_connect()` command.

yaz_connect (PHP 4)

Prepares for a connection and Z-association to a Z39.50 target.

```
int yaz_connect ( string zurl [, mixed options]) \linebreak
```

This function returns a positive ID on success; zero on failure.

yaz_connect() prepares for a connection to a Z39.50 target. The `zurl` argument takes the form `host[:port][/database]`. If port is omitted 210 is used. If database is omitted Default is used. This function is non-blocking and doesn't attempt to establish a socket - it merely prepares a connect to be performed later when `yaz_wait()` is called.

If the second argument, *options*, is given as a string it is treated as the Z39.50 V2 authentication string (OpenAuth).

If *options* is given as an array the contents of the array serves as options. Note that array options are only supported for PHP 4.1.0 and later.

yaz_connect() options

user

Username for authentication.

group

Group for authentication.

password

Password for authentication.

cookie

Cookie for session (YAZ proxy).

proxy

Proxy for connection (YAZ proxy).

persistent

A boolean. If `TRUE` the connection is persistent; If `FALSE` the connection is not persistent. By default connections are persistent.

piggyback

A boolean. If `TRUE` piggyback is enabled for searches; If `FALSE` piggyback is disabled. By default piggyback is enabled. Enabling piggyback is more efficient and usually saves a network-round-trip for first time fetches of records. However, a few Z39.50 targets doesn't support piggyback or they ignore element set names. For those, piggyback should be disabled.

yaz_database (PHP 4 >= 4.0.6)

Specifies the databases within a session

`int yaz_database (int id, string databases) \linebreak`

This function specifies one or more databases to be used in search, retrieval, etc. - overriding databases specified in call to `yaz_connect()`. Multiple databases are separated by a plus sign +.

This function allows you to use different sets of databases within a session.

Returns `TRUE` on success; `FALSE` on error.

yaz_element (PHP 4)

Specifies Element-Set Name for retrieval

`int yaz_element (int id, string elementset) \linebreak`

This function is used in conjunction with `yaz_search()` and `yaz_present()` to specify the element set name for records to be retrieved. Most servers support `F` (full) and `B` (brief).

Returns `TRUE` on success; `FALSE` on error.

yaz_errno (PHP 4)

Returns error number

`int yaz_errno (int id) \linebreak`

Returns error for target (last request). A positive value is returned if the target returned a diagnostic code; a value of zero is returned if no errors occurred (success); negative value is returned for other errors (such as when the target closed connection, etc).

yaz_errno() should be called after network activity for each target - (after `yaz_wait()` returns) to determine the success or failure of the last operation (e.g. search).

yaz_error (PHP 4)

Returns error description

string **yaz_error** (int id) \linebreak

Returns error message for target (last request). An empty string is returned if last operation was a success.

yaz_error() returns an english text message corresponding to the last error number as returned by **yaz_errno()**.

yaz_hits (PHP 4)

Returns number of hits for last search

int **yaz_hits** (int id) \linebreak

yaz_hits() returns number of hits for last search.

yaz_itemorder (PHP 4 >= 4.0.5)

Prepares for Z39.50 Item Order with an ILL-Request package

int **yaz_itemorder** (array args) \linebreak

This function prepares for an Extended Services request using the Profile for the Use of Z39.50 Item Order Extended Service to Transport ILL (Profile/1). See this (<http://www.nlc-bnc.ca/iso/ill/stanprf.htm>) and the specification (<http://www.nlc-bnc.ca/iso/ill/document/standard/z-ill-1a.pdf>). The args parameter must be a hash array with information about the Item Order request to be sent. The key of the hash is the name of the corresponding ASN.1 tag path. For example, the ISBN below the Item-ID has the key item-id,ISBN.

The ILL-Request parameters are:

protocol-version-num
 transaction-id,initial-requester-id,person-or-institution-symbol,person
 transaction-id,initial-requester-id,person-or-institution-symbol,institution
 transaction-id,initial-requester-id,name-of-person-or-institution,name-of-person
 transaction-id,initial-requester-id,name-of-person-or-institution,name-of-institution
 transaction-id,transaction-group-qualifier
 transaction-id,transaction-qualifier
 transaction-id,sub-transaction-qualifier
 service-date-time,this,date
 service-date-time,this,time
 service-date-time,original,date
 service-date-time,original,time
 requester-id,person-or-institution-symbol,person
 requester-id,person-or-institution-symbol,institution
 requester-id,name-of-person-or-institution,name-of-person
 requester-id,name-of-person-or-institution,name-of-institution

responder-id,person-or-institution-symbol,person
 responder-id,person-or-institution-symbol,institution
 responder-id,name-of-person-or-institution,name-of-person
 responder-id,name-of-person-or-institution,name-of-institution
 transaction-type
 delivery-address,postal-address,name-of-person-or-institution,name-of-person
 delivery-address,postal-address,name-of-person-or-institution,name-of-institution
 delivery-address,postal-address,extended-postal-delivery-address
 delivery-address,postal-address,street-and-number
 delivery-address,postal-address,post-office-box
 delivery-address,postal-address,city
 delivery-address,postal-address,region
 delivery-address,postal-address,country
 delivery-address,postal-address,postal-code
 delivery-address,electronic-address,telecom-service-identifier
 delivery-address,electronic-address,telecom-service-address
 billing-address,postal-address,name-of-person-or-institution,name-of-person
 billing-address,postal-address,name-of-person-or-institution,name-of-institution
 billing-address,postal-address,extended-postal-delivery-address
 billing-address,postal-address,street-and-number
 billing-address,postal-address,post-office-box
 billing-address,postal-address,city
 billing-address,postal-address,region
 billing-address,postal-address,country
 billing-address,postal-address,postal-code
 billing-address,electronic-address,telecom-service-identifier
 billing-address,electronic-address,telecom-service-address
 ill-service-type
 requester-optional-messages,can-send-RECEIVED
 requester-optional-messages,can-send-RETURNED
 requester-optional-messages,requester-SHIPPED
 requester-optional-messages,requester-CHECKED-IN
 search-type,level-of-service
 search-type,need-before-date
 search-type,expiry-date
 search-type,expiry-flag
 place-on-hold
 client-id,client-name
 client-id,client-status
 client-id,client-identifier
 item-id,item-type
 item-id,call-number
 item-id,author
 item-id,title
 item-id,sub-title
 item-id,sponsoring-body
 item-id,place-of-publication
 item-id,publisher
 item-id,series-title-number
 item-id,volume-issue
 item-id,edition
 item-id,publication-date

item-id,publication-date-of-component
 item-id,author-of-article
 item-id,title-of-article
 item-id,pagination
 item-id,ISBN
 item-id,ISSN
 item-id,additional-no-letters
 item-id,verification-reference-source
 copyright-complicance
 retry-flag
 forward-flag
 requester-note
 forward-note

There are also a few parameters that are part of the Extended Services Request package and the ItemOrder package:

package-name
 user-id
 contact-name
 contact-phone
 contact-email
 itemorder-item

yaz_present (PHP 4 >= 4.0.5)

Prepares for retrieval (Z39.50 present).

```
int yaz_present ( void) \linebreak
```

This function prepares for retrieval of records after a successful search. The `yaz_range()` should be called prior to this function to specify the range of records to be retrieved.

yaz_range (PHP 4)

Specifies the maximum number of records to retrieve

```
int yaz_range ( int id, int start, int number) \linebreak
```

This function is used in conjunction with `yaz_search()` to specify the maximum number of records to retrieve (number) and the first record position (start). If this function is not invoked (only `yaz_search()`) start is set to 1 and number is set to 10.

Returns `TRUE` on success; `FALSE` on error.

yaz_record (PHP 4)

Returns a record

```
int yaz_record ( int id, int pos, string type) \linebreak
```

Returns record at position or empty string if no record exists at given position.

The **yaz_record()** function inspects a record in the current result set at the position specified. If no database record exists at the given position an empty string is returned. The argument, *type*, specifies the form of the returned record. If *type* is "string" the record is returned in a string representation suitable for printing (for XML and SUTRS). If *type* is "array" the record is returned as an array representation (for structured records).

yaz_scan (PHP 4 >= 4.0.5)

Prepares for a scan

```
int yaz_scan ( int id, string type, string startterm [, array flags]) \linebreak
```

This function prepares for a Z39.50 Scan Request. Argument *id* specifies target ID. Starting term point for the scan is given by *startterm*. The form in which is the starting term is specified is given by *type*. Currently *rpn* is supported. The optional *flags* specifies additional information to control the behaviour of the scan request. Three indexes are currently read from the flags: *number* (number of terms requested), *position* (preferred position of term) and *stepSize* (preferred step size). To actually transfer the Scan Request to the target and receive the Scan Response, **yaz_wait()** must be called. Upon completion of **yaz_wait()** call **yaz_error()** and **yaz_scan_result()** to handle the response.

The syntax of *startterm* is similar to the RPN query as described in **yaz_search()**. The *startterm* consists of zero or more @attr-operator specifications, then followed by exactly one token.

Příklad 1. PHP function that scans titles

```
function scan_titles($id, $startterm) {
    yaz_scan($id,"rpn", "@attr 1=4 " . $startterm);
    yaz_wait();
    $errno = yaz_errno($id);
    if ($errno == 0) {
        $ar = yaz_scan_result($id,&$options);
        echo 'Scan ok; ';
        $ar = yaz_scan_result($id, &$options);
        while(list($key,$val)=each($options)) {
            echo "$key = $val &nbsp;";
        }
        echo '<br><table><tr><td>';
        while(list($key,list($k, $term, $tcount))=each($ar)) {
            if (empty($k)) continue;
            echo "<tr><td>$term</td><td>";
            echo $tcount;
            echo "</td></tr>";
        }
    }
}
```



```

        echo '</table>';
    } else {
        echo "Scan failed. Error: " . yaz_error($id) . "<br>";
    }
}

```

yaz_scan_result (PHP 4 >= 4.0.5)

Returns Scan Response result

array **yaz_scan_result** (int id [, array & result]) \linebreak

Given a target ID this function returns an array with terms as received from the target in the last Scan Response. This function returns an array (0..n-1) where n is the number of terms returned. Each value is a pair where first item is term, second item is result-count. If the *result* is given it will be modified to hold additional information taken from the Scan Response: *number* (number of entries returned), *stepsize* (Step-size), *position* (position of term), *status* (Scan Status).

yaz_search (PHP 4)

Prepares for a search

int **yaz_search** (int id, string type, string query) \linebreak

yaz_search() prepares for a search on the target with given id. The type represents the query type - only "rpn" is supported now in which case the third argument specifies a Type-1 query (RPN). Like **yaz_connect()** this function is non-blocking and only prepares for a search to be executed later when **yaz_wait()** is called.

The RPN query is a textual representation of the Type-1 query as defined by the Z39.50 standard. However, in the text representation as used by YAZ a prefix notation is used, that is the operator precedes the operands. The query string is a sequence of tokens where white space is ignored is ignored unless surrounded by double quotes. Tokens beginning with an at-character (@) are considered operators, otherwise they are treated as search terms.

Tabulka 1. RPN Operators

Syntax	Description
@and query1 query2	intersection of query1 and query2
@or query1 query2	union of query1 and query2
@not query1 query2	query1 and not query2
@set name	result set reference

Syntax	Description
@attrset set query	specifies attribute-set for query. This construction is only allowed once - in the beginning of the whole query
@attr set type=value query	applies attribute to query. The type and value are integers specifying the attribute-type and attribute-value respectively. The set, if given, specifies the attribute-set.

Příklad 1. Query Examples

Query

computer

matches documents where "computer" occur. No attributes are specified.

The Query

"donald knuth"

matches documents where "donald knuth" occur.

For the query

@attr 1=4 art

attribute type is 1 (Bib-1 use), attribute value is 4 (Title), so this should match documents where `art` occur in the title.

Another more complex one:

@attrset gils @and @attr 1=4 art @attr 1=1003 "donald knuth"

The query as a whole uses the GILS attributeset. The query matches documents where `art` occur in the title and in which `donald knuth` occur in the author.

yaz_sort (PHP 4 >= 4.1.0)

Sets sorting criteria

int **yaz_sort** (int id, string criteria) \linebreak

This function sets sorting criteria and enables Z39.50 Sort. Use this function together with `yaz_search()` or `yaz_present()`. Using this function alone doesn't have any effect. If used in conjunction with `yaz_search()` a Z39.50 Sort will be sent after a search response has been received and before any records are retrieved with Z39.50 Present. The *criteria* takes the form

field1 flags1 field2 flags2 ...

where *field1* specifies primary attributes for sort, *field2* seconds, etc.. The field specifies either numerical attribute combinations consisting of type=value pairs separated by comma (e.g. 1=4, 2=1) ; or the field may specify a plain string criteria (e.g. `title`). The flags is a sequence of the following characters which may not be separated by any white space.

Sort Flags

a	Sort ascending
d	Sort descending
i	Case insensitive sorting
s	Case sensitive sorting

Příklad 1. Sort Criterias

To sort on Bib1 attribute title, case insensitive, and ascending you'd use the following sort criteria:

```
1=4 ia
```

If the secondary sorting criteria should be author, case sensitive and ascending you'd use:

```
1=4 ia 1=1003 sa
```

yaz_syntax (PHP 4)

Specifies the preferred record syntax for retrieval.

```
int yaz_syntax ( int id, string syntax) \linebreak
```

The syntax is specified as an OID (Object Identifier) in a raw dot-notation (like 1.2.840.10003.5.10) or as one of the known registered record syntaxes (sutr, usmarc, grs1, xml, etc.). This function is used in conjunction with `yaz_search()` and `yaz_present()` to specify the preferred record syntax for retrieval.

yaz_wait (PHP 4)

Wait for Z39.50 requests to complete

```
int yaz_wait ( [ array options]) \linebreak
```

This function carries out networked (blocked) activity for outstanding requests which have been prepared by the functions `yaz_connect()`, `yaz_search()`, `yaz_present()`, `yaz_scan()` and `yaz_itemorder()`. **yaz_wait()** returns when all targets have either completed all requests or aborted (in case of errors).

If the *options* array is given that holds options that change the behaviour of **yaz_wait()**.

`timeout`

Sets timeout in seconds. If a target hasn't responded within the timeout it is considered dead and **yaz_wait()** returns. The default value for timeout is 15 seconds.

CVII. Funkce pro práci s YP/NIS

NIS (dříve Yellow Pages) umožňuje síťovou správu důležitých administrativních souborů (např. soubory s hesly). Více informací viz NIS man stránka a Introduction to YP/NIS (<http://www.desy.de/~sieversm/ypdoku/ypdoku/ypdoku.html>). Existuje také kniha Managing NFS and NIS (<http://www.oreilly.com/catalog/nfs/noframes.html>) od Hala Sterna.

Pokud chcete tyto funkce zprovoznit, musíte PHP zkonfigurovat s `--with-yp` (PHP 3) nebo `--enable-yp` (PHP 4).

yp_err_string (PHP 4 >= 4.0.6)

Returns the error string associated with the previous operation

string **yp_err_string** (void) \linebreak

yp_err_string() returns the error message associated with the previous operation. Useful to indicate what exactly went wrong.

Příklad 1. Example for NIS errors

```
<?php
    echo "Error: " . yp_err_string();
?>
```

Viz také `yp_errno()`.

yp_errno (PHP 4 >= 4.0.6)

Returns the error code of the previous operation

int **yp_errno** (void) \linebreak

yp_errno() returns the error code of the previous operation.

Possible errors are:

- 1 args to function are bad
- 2 RPC failure - domain has been unbound
- 3 can't bind to server on this domain
- 4 no such map in server's domain
- 5 no such key in map
- 6 internal yp server or client error
- 7 resource allocation failure
- 8 no more records in map database
- 9 can't communicate with portmapper
- 10 can't communicate with ypbind
- 11 can't communicate with ypserv
- 12 local domain name not set
- 13 yp database is bad
- 14 yp version mismatch
- 15 access violation
- 16 database busy

Viz také `yp_err_string()`.

yp_first (PHP 3 >= 3.0.7, PHP 4 >= 4.0.0)

Vrátit první klíč/hodnota pár mapy

array **yp_first** (string domain, string map) \linebreak

yp_first() vrací první klíč/hodnota pár dané mapy v dané doméně, nebo `FALSE`.

Příklad 1. Ukázka NIS first

```
<?php
    $entry = yp_first($domain, "passwd.byname");
    $key = key($entry);
    echo "První záznam v této mapě má klíč " . $key
        . " a hodnotu " . $entry[$key];
?>
```

Viz také `yp-get-default-domain()`

yp_get_default_domain (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Zjistit defaultní NIS doménu stroje

`int yp_get_default_domain (void) \linebreak`

yp_get_default_domain() vrací defaultní doménu uzlu nebo `FALSE`. Dá se používat jako argument domény v následných voláních NIS.

NIS doména se dá popsat jako skupina map NIS. Každý server, který potřebuje vyhledat informace se připojí k určité doméně. Detailnější informace viz dokumentace zmíněná v úvodu.

Příklad 1. Ukázka defaultní domény

```
<?php
$domain = yp_get_default_domain();
echo "Defaultní NIS doména je: " . $domain;
?>
```

yp_master (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Zjistit název master NIS serveru mapy

`string yp_master (string domain, string map) \linebreak`

yp_master() vrací název master NIS serveru určité mapy.

Příklad 1. Ukázka NIS masteru

```
<?php
$number = yp_master ($domain, $mapname);
echo "Master této mapy je: " . $master;
```

```
?>
```

Viz také `yp-get-default-domain()`.

yp_match (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Vrátit odpovídající záznam

string **yp_match** (string domain, string map, string key) \linebreak

yp_match() vrací hodnotu asociovanou v dané mapě s předaným klíčem nebo `FALSE`. Klíč musí být dán přesně.

Příklad 1. Ukázka NIS match

```
<?php
$entry = yp_match ($domain, "passwd.byname", "joe");
echo "Odpovídající záznam je: " . $entry;
?>
```

V tomto případě by to mohlo být: `joe:##joe:11111:100:Joe User:/home/j/joe:/usr/local/bin/bash`

Viz také `yp-get-default-domain()`

yp_next (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Vrátit další klíč/hodnota pár mapy

array **yp_next** (string domain, string map, string key) \linebreak

yp_next() vrací další klíč/hodnota pár v mapě po daném klíči, nebo `FALSE`.

Příklad 1. Ukázka NIS next

```
<?php
$entry = yp_next ($domain, "passwd.byname", "joe");

if (!$entry) {
    echo yp_errno() . ": " . yp_err_string();
}

$key = key ($entry);

echo "Položka následující po joe má klíč " . $key
    . " a hodnotu " . $entry[$key];
?>
```


Viz také `yp-get-default-domain()`.

yp_order (PHP 3>= 3.0.7, PHP 4 >= 4.0.0)

Returns the order number for a map

int **yp_order** (string domain, string map) \linebreak

yp_order() vrací pořadové číslo mapy nebo `FALSE`.

Příklad 1. Ukázka NIS order

```
<?php
    $number = yp_order($domain,$mapname);
    echo "Pořadové číslo této mapy je: " . $order;
?>
```

Viz také: `yp-get-default-domain()`.

CVIII. Zip File Functions (Read Only Access)

This module uses the functions of the `ZZIPLib` (<http://zziplib.sourceforge.net/>) library by Guido Draheim to transparently read ZIP compressed archives and the files inside them.

Please note that `ZZIPLib` only provides a subset of functions provided in a full implementation of the ZIP compression algorithm and can only read ZIP file archives. A normal ZIP utility is needed to create the ZIP file archives read by this library.

Zip support in PHP is not enabled by default. You will need to use the `--with-zip` configuration option when compiling PHP to enable zip support. This module requires `ZZIPLib` version `>= 0.10.6`.

Poznámka: Zip support before PHP 4.1.0 is experimental. This section reflects the Zip extension as it exists in PHP 4.1.0 and later.

Example Usage

This example opens a ZIP file archive, reads each file in the archive and prints out its contents. The `test2.zip` archive used in this example is one of the test archives in the `ZZIPLib` source distribution.

Příklad 1. Zip Usage Example

```
<?php

$zip = zip_open("/tmp/test2.zip");

if ($zip) {

    while ($zip_entry = zip_read($zip)) {
        echo "Name:          " . zip_entry_name($zip_entry) . "\n";
        echo "Actual Filesize:  " . zip_entry_filesize($zip_entry) . "\n";
        echo "Compressed Size:    " . zip_entry_compressedsize($zip_entry) . "\n";
        echo "Compression Method: " . zip_entry_compressionmethod($zip_entry) . "\n";

        if (zip_entry_open($zip, $zip_entry, "r")) {
            echo "File Contents:\n";
            $buf = zip_entry_read($zip_entry, zip_entry_filesize($zip_entry));
            echo "$buf\n";

            zip_entry_close($zip_entry);
        }
        echo "\n";
    }

    zip_close($zip);
}

?>
```


zip_close (PHP 4 >= 4.1.0)

Close a Zip File Archive

void **zip_close** (resource *zip*) \linebreak

Closes a zip file archive. The parameter *zip* must be a zip archive previously opened by `zip_open()`.

This function has no return value.

See also `zip_open()` and `zip_read()`.

zip_entry_close (PHP 4 >= 4.1.0)

Close a Directory Entry

void **zip_entry_close** (resource *zip_entry*) \linebreak

Closes a directory entry specified by *zip_entry*. The parameter *zip_entry* must be a valid directory entry opened by `zip_entry_open()`.

This function has no return value.

See also `zip_entry_open()` and `zip_entry_read()`.

zip_entry_compressedsize (PHP 4 >= 4.1.0)

Retrieve the Compressed Size of a Directory Entry

int **zip_entry_compressedsize** (resource *zip_entry*) \linebreak

Returns the compressed size of the directory entry specified by *zip_entry*. The parameter *zip_entry* is a valid directory entry returned by `zip_read()`.

See also `zip_open()` and `zip_read()`.

zip_entry_compressionmethod (PHP 4 >= 4.1.0)

Retrieve the Compression Method of a Directory Entry

string **zip_entry_compressionmethod** (resource *zip_entry*) \linebreak

Returns the compression method of the directory entry specified by *zip_entry*. The parameter *zip_entry* is a valid directory entry returned by `zip_read()`.

See also `zip_open()` and `zip_read()`.

zip_entry_filesize (PHP 4 >= 4.1.0)

Retrieve the Actual File Size of a Directory Entry

int **zip_entry_filesize** (resource *zip_entry*) \linebreak

Returns the actual size of the directory entry specified by *zip_entry*. The parameter *zip_entry* is a valid directory entry returned by *zip_read()*.

See also *zip_open()* and *zip_read()*.

zip_entry_name (PHP 4 >= 4.1.0)

Retrieve the Name of a Directory Entry

string **zip_entry_name** (resource *zip_entry*) \linebreak

Returns the name of the directory entry specified by *zip_entry*. The parameter *zip_entry* is a valid directory entry returned by *zip_read()*.

See also *zip_open()* and *zip_read()*.

zip_entry_open (PHP 4 >= 4.1.0)

Open a Directory Entry for Reading

bool **zip_entry_open** (resource *zip*, resource *zip_entry* [, string *mode*]) \linebreak

Opens a directory entry in a zip file for reading. The parameter *zip* is a valid resource handle returned by *zip_open()*. The parameter *zip_entry* is a directory entry resource returned by *zip_read()*. The optional parameter *mode* can be any of the modes specified in the documentaion for *fopen()*.

Poznámka: Currently, *mode* is ignored and is always "*rb*". This is due to the fact that zip support in PHP is read only access. Please see *fopen()* for an explanation of various modes, including "*rb*".

Vrací TRUE při úspěchu, FALSE při selhání.

Poznámka: Unlike *fopen()* and other similar functions, the return value of **zip_entry_open()** only indicates the result of the operation and is not needed for reading or closing the directory entry.

See also *zip_entry_read()* and *zip_entry_close()*.

zip_entry_read (PHP 4 >= 4.1.0)

Read From an Open Directory Entry

string **zip_entry_read** (resource *zip_entry* [, int *length*]) \linebreak

Reads up to *length* bytes from an open directory entry. If *length* is not specified, then **zip_entry_read()** will attempt to read 1024 bytes. The parameter *zip_entry* is a valid directory entry returned by **zip_read()**.

Poznámka: The *length* parameter should be the uncompressed length you wish to read.

Returns the data read, or **FALSE** if the end of the file is reached.

See also **zip_entry_open()**, **zip_entry_close()** and **zip_entry_filesize()**.

zip_open (PHP 4 >= 4.1.0)

Open a Zip File Archive

resource **zip_open** (string *filename*) \linebreak

Opens a new zip archive for reading. The *filename* parameter is the filename of the zip archive to open.

Returns a resource handle for later use with **zip_read()** and **zip_close()** or returns **FALSE** if *filename* does not exist.

See also **zip_read()** and **zip_close()**.

zip_read (PHP 4 >= 4.1.0)

Read Next Entry in a Zip File Archive

resource **zip_read** (resource *zip*) \linebreak

Reads the next entry in a zip file archive. The parameter *zip* must be a zip archive previously opened by **zip_open()**.

Returns a directory entry resource for later use with the **zip_entry_...()** functions.

See also **zip_open()**, **zip_close()**, **zip_entry_open()**, and **zip_entry_read()**.

CIX. Zlib Compression Functions

This module uses the functions of zlib (<http://www.gzip.org/zlib/>) by Jean-loup Gailly and Mark Adler to transparently read and write gzip (.gz) compressed files. You have to use a zlib version >= 1.0.9 with this module.

This module contains versions of most of the filesystem functions which work with gzip-compressed files (and uncompressed files, too, but not with sockets).

Poznámka: Version 4.0.4 introduces a fopen-wrapper for .gz-files, so that you can use a special 'zlib:' URL to access compressed files transparently using the normal f*() file access functions if you prepend the filename or path with a 'zlib:' prefix when calling fopen().

In version 4.3.0, this special prefix has been changed to 'zlib:/' to prevent ambiguities with filenames containing ':'.

This feature requires a C runtime library that provides the `fopencookie()` function. To my current knowledge the GNU libc is the only library that provides this feature.

Small code example

Opens a temporary file and writes a test string to it, then it prints out the content of this file twice.

Příklad 1. Small Zlib Example

```
<?php

$filename = tempnam ('/tmp', 'zlibtest').'.gz';
print "<html>\n<head></head>\n<body>\n<pre>\n";
$s = "Only a test, test, test, test, test, test, test, test!\n";

// open file for writing with maximum compression
$zp = gzopen($filename, "w9");

// write string to file
gzwrite($zp, $s);

// close file
gzclose($zp);

// open file for reading
$zp = gzopen($filename, "r");

// read 3 char
print gzread($zp, 3);

// output until end of the file and close it.
gzpassthru($zp);

print "\n";

// open file and print content (the 2nd time).
if (readgzfile($filename) != strlen($s)) {
```

```
        echo "Error with zlib functions!";  
    }  
    unlink($filename);  
    print "</pre>\n</h1></body>\n</html>\n";  
  
?>
```


gzclose (PHP 3, PHP 4 >= 4.0.0)

Close an open gz-file pointer

```
int gzclose ( int zp) \linebreak
```

The gz-file pointed to by zp is closed.

Returns TRUE on success and FALSE on failure.

The gz-file pointer must be valid, and must point to a file successfully opened by gzopen().

gzcompress (PHP 4)

Compress a string

```
string gzcompress ( string data [, int level]) \linebreak
```

This function returns a compressed version of the input *data* using the ZLIB data format, or FALSE if an error is encountered. The optional parameter *level* can be given as 0 for no compression up to 9 for maximum compression.

For details on the ZLIB compression algorithm see the document "ZLIB Compressed Data Format Specification version 3.3 (<http://www.ietf.org/rfc/rfc1950.txt>)" (RFC 1950).

Poznámka: This is *not* the same as gzip compression, which includes some header data. See gzencode() for gzip compression.

See also gzdeflate(), gzinflate(), gzuncompress(), gzencode().

gzdeflate (PHP 4 >= 4.0.4)

Deflate a string

```
string gzdeflate ( string data [, int level]) \linebreak
```

This function returns a compressed version of the input *data* using the DEFLATE data format, or FALSE if an error is encountered. The optional parameter *level* can be given as 0 for no compression up to 9 for maximum compression.

For details on the DEFLATE compression algorithm see the document "DEFLATE Compressed Data Format Specification version 1.3 (<http://www.ietf.org/rfc/rfc1951.txt>)" (RFC 1951).

See also gzinflate(), gzcompress(), gzuncompress(), gzencode().

gzencode (PHP 4 >= 4.0.4)

Create a gzip compressed string

string **gzencode** (string *data* [, int *level* [, int *encoding_mode*]]) \linebreak

This function returns a compressed version of the input *data* compatible with the output of the **gzip** program, or FALSE if an error is encountered. The optional parameter *level* can be given as 0 for no compression up to 9 for maximum compression, if not given the default compression level will be the default compression level of the zlib library.

You can also give FORCE_GZIP (the default) or FORCE_DEFLATE as optional third parameter *encoding_mode*. If you use FORCE_DEFLATE, you get a standard zlib deflated string (inclusive zlib headers) after the gzip file header but without the trailing crc32 checksum.

Poznámka: *level* was added in PHP 4.2, before PHP 4.2 **gzencode()** only had the *data* and (optional) *encoding_mode* parameters..

The resulting data contains the appropriate headers and data structure to make a standard .gz file, e.g.:

Příklad 1. Creating a gzip file

```
<?php
    $data = implode("", file("bigfile.txt"));
    $gzdata = gzencode($data, 9);
    $fp = fopen("bigfile.txt.gz", "w");
    fwrite($fp, $gzdata);
    fclose($fp);
?>
```

For more information on the GZIP file format, see the document: GZIP file format specification version 4.3 (<http://www.ietf.org/rfc/rfc1952.txt>) (RFC 1952).

See also gzcompress(), gzuncompress(), gzdeflate(), gzinflate().

gzeof (PHP 3, PHP 4 >= 4.0.0)

Test for end-of-file on a gz-file pointer

int **gzeof** (int *zp*) \linebreak

Returns TRUE if the gz-file pointer is at EOF or an error occurs; otherwise returns FALSE.

The gz-file pointer must be valid, and must point to a file successfully opened by gzopen().

gzfile (PHP 3, PHP 4 >= 4.0.0)

Read entire gz-file into an array

array **gzfile** (string filename [, int use_include_path]) \linebreak

Identical to readgzfile(), except that **gzfile()** returns the file in an array.

You can use the optional second parameter and set it to "1", if you want to search for the file in the include_path, too.

See also readgzfile(), and gzopen().

gzgetc (PHP 3, PHP 4 >= 4.0.0)

Get character from gz-file pointer

string **gzgetc** (int zp) \linebreak

Returns a string containing a single (uncompressed) character read from the file pointed to by zp.

Returns FALSE on EOF (as does gzeof()).

The gz-file pointer must be valid, and must point to a file successfully opened by gzopen().

See also gzopen(), and gzgets().

gzgets (PHP 3, PHP 4 >= 4.0.0)

Get line from file pointer

string **gzgets** (int zp, int length) \linebreak

Returns a (uncompressed) string of up to length - 1 bytes read from the file pointed to by fp. Reading ends when length - 1 bytes have been read, on a newline, or on EOF (whichever comes first).

If an error occurs, returns FALSE.

The file pointer must be valid, and must point to a file successfully opened by gzopen().

See also gzopen(), gzgetc(), and fgets().

gzgetss (PHP 3, PHP 4 >= 4.0.0)

Get line from gz-file pointer and strip HTML tags

string **gzgetss** (int zp, int length [, string allowable_tags]) \linebreak

Identical to gzgets(), except that **gzgetss()** attempts to strip any HTML and PHP tags from the text it reads.

You can use the optional third parameter to specify tags which should not be stripped.

Poznámka: *Allowable_tags* was added in PHP 3.0.13, PHP4B3.

See also `gzgets()`, `gzopen()`, and `strip_tags()`.

gzinflate (PHP 4 >= 4.0.4)

Inflate a deflated string

string **gzinflate** (string *data* [, int *length*]) \linebreak

This function takes *data* compressed by `gzdeflate()` and returns the original uncompressed data or `FALSE` on error. The function will return an error if the uncompressed data is more than 256 times the length of the compressed input *data* or more than the optional parameter *length*.

See also `gzcompress()`, `gzuncompress()`, `gzdeflate()`, `gzencode()`.

gzopen (PHP 3, PHP 4 >= 4.0.0)

Open gz-file

int **gzopen** (string *filename*, string *mode* [, int *use_include_path*]) \linebreak

Opens a gzip (.gz) file for reading or writing. The mode parameter is as in `fopen()` ("rb" or "wb") but can also include a compression level ("wb9") or a strategy: 'f' for filtered data as in "wb6f", 'h' for Huffman only compression as in "wb1h". (See the description of `deflateInit2` in `zlib.h` for more information about the strategy parameter.)

gzopen() can be used to read a file which is not in gzip format; in this case `gzread()` will directly read from the file without decompression.

gzopen() returns a file pointer to the file opened, after that, everything you read from this file descriptor will be transparently decompressed and what you write gets compressed.

If the open fails, the function returns `FALSE`.

You can use the optional third parameter and set it to "1", if you want to search for the file in the `include_path`, too.

Příklad 1. gzopen() Example

```
$fp = gzopen ( "/tmp/file.gz", "r" );
```

See also `gzclose()`.

gzpassthru (PHP 3, PHP 4 >= 4.0.0)

Output all remaining data on a gz-file pointer

```
int gzpassthru ( int zp) \linebreak
```

Reads to EOF on the given gz-file pointer and writes the (uncompressed) results to standard output.

If an error occurs, returns `FALSE`.

The file pointer must be valid, and must point to a file successfully opened by `gzopen()`.

The gz-file is closed when **gzpassthru()** is done reading it (leaving *zp* useless).

gzputs (PHP 3, PHP 4 >= 4.0.0)

Write to a gz-file pointer

```
int gzputs ( int zp, string str [, int length]) \linebreak
```

gzputs() is an alias to `gzwrite()`, and is identical in every way.

gzread (PHP 3, PHP 4 >= 4.0.0)

Binary-safe gz-file read

```
string gzread ( int zp, int length) \linebreak
```

gzread() reads up to *length* bytes from the gz-file pointer referenced by *zp*. Reading stops when *length* (uncompressed) bytes have been read or EOF is reached, whichever comes first.

```
// get contents of a gz-file into a string
$filename = "/usr/local/something.txt.gz";
$zd = gzopen ($filename, "r");
$contents = gzread ($zd, 10000);
gzclose ($zd);
```

See also `gzwrite()`, `gzopen()`, `gzgets()`, `gzgetss()`, `gzfile()`, and `gzpassthru()`.

gzrewind (PHP 3, PHP 4 >= 4.0.0)

Rewind the position of a gz-file pointer

```
int gzrewind ( int zp) \linebreak
```

Sets the file position indicator for *zp* to the beginning of the file stream.

If an error occurs, returns 0.

The file pointer must be valid, and must point to a file successfully opened by `gzopen()`.

See also `gzseek()` and `gztell()`.

gzseek (PHP 3, PHP 4 >= 4.0.0)

Seek on a gz-file pointer

```
int gzseek ( int zp, int offset) \linebreak
```

Sets the file position indicator for the file referenced by *zp* to offset bytes into the file stream.

Equivalent to calling (in C) `gzseek(zp, offset, SEEK_SET)`.

If the file is opened for reading, this function is emulated but can be extremely slow. If the file is opened for writing, only forward seeks are supported; `gzseek` then compresses a sequence of zeroes up to the new starting position.

Upon success, returns 0; otherwise, returns -1. Note that seeking past EOF is not considered an error.

See also `gztell()` and `gzrewind()`.

gztell (PHP 3, PHP 4 >= 4.0.0)

Tell gz-file pointer read/write position

```
int gztell ( int zp) \linebreak
```

Returns the position of the file pointer referenced by *zp*; i.e., its offset into the file stream.

If an error occurs, returns `FALSE`.

The file pointer must be valid, and must point to a file successfully opened by `gzopen()`.

See also `gzopen()`, `gzseek()` and `gzrewind()`.

gzuncompress (PHP 4)

Uncompress a deflated string

```
string gzuncompress ( string data [, int length]) \linebreak
```

This function takes *data* compressed by `gzcompress()` and returns the original uncompressed data or `FALSE` on error. The function will return an error if the uncompressed data is more than 256 times the length of the compressed input *data* or more than the optional parameter *length*.

See also `gzdeflate()`, `gzinflate()`, `gzcompress()`, `gzencode()`.

gzwrite (PHP 3, PHP 4 >= 4.0.0)

Binary-safe gz-file write

```
int gzwrite ( int zp, string string [, int length]) \linebreak
```

gzwrite() writes the contents of *string* to the gz-file stream pointed to by *zp*. If the *length* argument is given, writing will stop after *length* (uncompressed) bytes have been written or the end of *string* is reached, whichever comes first.

Note that if the *length* argument is given, then the `magic_quotes_runtime` configuration option will be ignored and no slashes will be stripped from *string*.

See also `gzread()`, `gzopen()`, and `gzputs()`.

readgzfile (PHP 3, PHP 4 >= 4.0.0)

Output a gz-file

int **readgzfile** (string filename [, int use_include_path]) \linebreak

Reads a file, decompresses it and writes it to standard output.

readgzfile() can be used to read a file which is not in gzip format; in this case **readgzfile()** will directly read from the file without decompression.

Returns the number of (uncompressed) bytes read from the file. If an error occurs, `FALSE` is returned and unless the function was called as `@readgzfile`, an error message is printed.

The file *filename* will be opened from the filesystem and its contents written to standard output.

You can use the optional second parameter and set it to "1", if you want to search for the file in the `include_path`, too.

See also `gzpassthru()`, `gzfile()`, and `gzopen()`.

Část V. Extending PHP 4.0

Kapitola 24. Overview

"Extending PHP" is easier said than done. PHP has evolved to a full-fledged tool consisting of a few megabytes of source code, and to hack a system like this quite a few things have to be learned and considered. When structuring this chapter, we finally decided on the "learn by doing" approach. This is not the most scientific and professional approach, but the method that's the most fun and gives the best end results. In the following sections, you'll learn quickly how to get the most basic extensions to work almost instantly. After that, you'll learn about Zend's advanced API functionality. The alternative would have been to try to impart the functionality, design, tips, tricks, etc. as a whole, all at once, thus giving a complete look at the big picture before doing anything practical. Although this is the "better" method, as no dirty hacks have to be made, it can be very frustrating as well as energy- and time-consuming, which is why we've decided on the direct approach.

Note that even though this chapter tries to impart as much knowledge as possible about the inner workings of PHP, it's impossible to really give a complete guide to extending PHP that works 100% of the time in all cases. PHP is such a huge and complex package that its inner workings can only be understood if you make yourself familiar with it by practicing, so we encourage you to work with the source.

What Is Zend? and What Is PHP?

The name *Zend* refers to the language engine, PHP's core. The term *PHP* refers to the complete system as it appears from the outside. This might sound a bit confusing at first, but it's not that complicated (see 24-1). To implement a Web script interpreter, you need three parts:

1. The *interpreter* part analyzes the input code, translates it, and executes it.
2. The *functionality* part implements the functionality of the language (its functions, etc.).
3. The *interface* part talks to the Web server, etc.

Zend takes part 1 completely and a bit of part 2; PHP takes parts 2 and 3. Together they form the complete PHP package. Zend itself really forms only the language core, implementing PHP at its very basics with some predefined functions. PHP contains all the modules that actually create the language's outstanding capabilities.

Obrázek 24-1. The internal structure of PHP.

The following sections discuss where PHP can be extended and how it's done.

Kapitola 25. Extension Possibilities

As shown in 24-1 above, PHP can be extended primarily at three points: external modules, built-in modules, and the Zend engine. The following sections discuss these options.

External Modules

External modules can be loaded at script runtime using the function `dl()`. This function loads a shared object from disk and makes its functionality available to the script to which it's being bound. After the script is terminated, the external module is discarded from memory. This method has both advantages and disadvantages, as described in the following table:

Advantages	Disadvantages
External modules don't require recompiling of PHP.	The shared objects need to be loaded every time a script is being executed (every hit), which is very slow.
The size of PHP remains small by "outsourcing" certain functionality.	External additional files clutter up the disk.
	Every script that wants to use an external module's functionality has to specifically include a call to <code>dl()</code> , or the <code>extension</code> tag in <code>php.ini</code> needs to be modified (which is not always a suitable solution).

To sum up, external modules are great for third-party products, small additions to PHP that are rarely used, or just for testing purposes. To develop additional functionality quickly, external modules provide the best results. For frequent usage, larger implementations, and complex code, the disadvantages outweigh the advantages.

Third parties might consider using the `extension` tag in `php.ini` to create additional external modules to PHP. These external modules are completely detached from the main package, which is a very handy feature in commercial environments. Commercial distributors can simply ship disks or archives containing only their additional modules, without the need to create fixed and solid PHP binaries that don't allow other modules to be bound to them.

Built-in Modules

Built-in modules are compiled directly into PHP and carried around with every PHP process; their functionality is instantly available to every script that's being run. Like external modules, built-in modules have advantages and disadvantages, as described in the following table:

Advantages	Disadvantages
No need to load the module specifically; the functionality is instantly available.	Changes to built-in modules require recompiling of PHP.
No external files clutter up the disk; everything resides in the PHP binary.	The PHP binary grows and consumes more memory.

Built-in modules are best when you have a solid library of functions that remains relatively unchanged, requires better than poor-to-average performance, or is used frequently by many scripts

on your site. The need to recompile PHP is quickly compensated by the benefit in speed and ease of use. However, built-in modules are not ideal when rapid development of small additions is required.

The Zend Engine

Of course, extensions can also be implemented directly in the Zend engine. This strategy is good if you need a change in the language behavior or require special functions to be built directly into the language core. In general, however, modifications to the Zend engine should be avoided. Changes here result in incompatibilities with the rest of the world, and hardly anyone will ever adapt to specially patched Zend engines. Modifications can't be detached from the main PHP sources and are overridden with the next update using the "official" source repositories. Therefore, this method is generally considered bad practice and, due to its rarity, is not covered in this book.

Kapitola 26. Source Layout

Poznámka: Prior to working through the rest of this chapter, you should retrieve clean, unmodified source trees of your favorite Web server. We're working with Apache (available at <http://www.apache.org/>) and, of course, with PHP (available at <http://www.php.net/> - does it need to be said?).

Make sure that you can compile a working PHP environment by yourself! We won't go into this issue here, however, as you should already have this most basic ability when studying this chapter.

Before we start discussing code issues, you should familiarize yourself with the source tree to be able to quickly navigate through PHP's files. This is a must-have ability to implement and debug extensions.

After extracting the PHP archive, you'll see a directory layout similar to that in 26-1.

Obrázek 26-1. Main directory layout of the PHP source tree.

The following table describes the contents of the major directories.

Directory	Contents
php-4	Main PHP source files and main header files; here you'll find all of PHP's API definitions, macros, etc. (important).
ext	Repository for dynamic and built-in modules; by default, these are the "official" PHP modules that have been included in the PHP distribution.
pear	Directory for the PHP class repository. At the time of this writing, this is still in the design phase, but it's being developed.
sapi	Contains the code for the different server abstraction layers.
TSRM	Location of the "Thread Safe Resource Manager" (TSRM) for Zend and PHP.
Zend	Location of Zend's file; here you'll find all of Zend's API definitions, macros, etc. (important).

Discussing all the files included in the PHP package is beyond the scope of this chapter. However, you should take a close look at the following files:

- `php.h`, located in the main PHP directory. This file contains most of PHP's macro and API definitions.
- `zend.h`, located in the main Zend directory. This file contains most of Zend's macros and definitions.
- `zend_API.h`, also located in the Zend directory, which defines Zend's API.

You should also follow some sub-inclusions from these files; for example, the ones relating to the Zend executor, the PHP initialization file support, and such. After reading these files, take the time to navigate around the package a little to see the interdependencies of all files and modules - how they

relate to each other and especially how they make use of each other. This also helps you to adapt to the coding style in which PHP is authored. To extend PHP, you should quickly adapt to this style.

Extension Conventions

Zend is built using certain conventions; to avoid breaking its standards, you should follow the rules described in the following sections.

Macros

For almost every important task, Zend ships predefined macros that are extremely handy. The tables and figures in the following sections describe most of the basic functions, structures, and macros. The macro definitions can be found mainly in `zend.h` and `zend_API.h`. We suggest that you take a close look at these files after having studied this chapter. (Although you can go ahead and read them now, not everything will make sense to you yet.)

Memory Management

Resource management is a crucial issue, especially in server software. One of the most valuable resources is memory, and memory management should be handled with extreme care. Memory management has been partially abstracted in Zend, and you should stick to this abstraction for obvious reasons: Due to the abstraction, Zend gets full control over all memory allocations. Zend is able to determine whether a block is in use, automatically freeing unused blocks and blocks with lost references, and thus prevent memory leaks. The functions to be used are described in the following table:

Function	Description
emalloc()	Serves as replacement for malloc() .
efree()	Serves as replacement for free() .
estrdup()	Serves as replacement for strdup() .
estrndup()	Serves as replacement for strndup() . Faster than estrdup() and binary-safe. This is the recommended function.
ecalloc()	Serves as replacement for calloc() .
erealloc()	Serves as replacement for realloc() .

emalloc(), **estrdup()**, **estrndup()**, **ecalloc()**, and **erealloc()** allocate internal memory; **efree()** frees these previously allocated blocks. Memory handled by the **e*()** functions is considered local to the current process and is discarded as soon as the script executed by this process is terminated.

Varování

To allocate resident memory that survives termination of the current script, you can use **malloc()** and **free()**. This should only be done with extreme care, however, and only in conjunction with demands of the Zend API; otherwise, you risk memory leaks.

Zend also features a thread-safe resource manager to provide better native support for multithreaded

Web servers. This requires you to allocate local structures for all of your global variables to allow concurrent threads to be run. Because the thread-safe mode of Zend was not finished back when this was written, it is not yet extensively covered here.

Directory and File Functions

The following directory and file functions should be used in Zend modules. They behave exactly like their C counterparts, but provide virtual working directory support on the thread level.

Zend Function	Regular C Function
V_GETCWD()	getcwd()
V_FOPEN()	fopen()
V_OPEN()	open()
V_CHDIR()	chdir()
V_GETWD()	getwd()
V_CHDIR_FILE()	Takes a file path as an argument and changes the current working directory to that file's directory.
V_STAT()	stat()
V_LSTAT()	lstat()

String Handling

Strings are handled a bit differently by the Zend engine than other values such as integers, Booleans, etc., which don't require additional memory allocation for storing their values. If you want to return a string from a function, introduce a new string variable to the symbol table, or do something similar, you have to make sure that the memory the string will be occupying has previously been allocated, using the aforementioned **e*()** functions for allocation. (This might not make much sense to you yet; just keep it somewhere in your head for now - we'll get back to it shortly.)

Complex Types

Complex types such as arrays and objects require different treatment. Zend features a single API for these types - they're stored using hash tables.

Poznámka: To reduce complexity in the following source examples, we're only working with simple types such as integers at first. A discussion about creating more advanced types follows later in this chapter.

Kapitola 27. PHP's Automatic Build System

PHP 4 features an automatic build system that's very flexible. All modules reside in a subdirectory of the `ext` directory. In addition to its own sources, each module consists of an M4 file (for example, see http://www.gnu.org/manual/m4/html_mono/m4.html) for configuration and a `Makefile.in` file, which is responsible for compilation (the results of `autoconf` and `automake`; for example, see <http://sourceware.cygnus.com/autoconf/autoconf.html> and <http://sourceware.cygnus.com/automake/automake.html>).

Both files are generated automatically, along with `.cvsignore`, by a little shell script named `ext_skel` that resides in the `ext` directory. As argument it takes the name of the module that you want to create. The shell script then creates a directory of the same name, along with the appropriate `config.m4` and `Makefile.in` files.

Step by step, the process looks like this:

```
root@dev:/usr/local/src/php4/ext > ./ext_skel my_module
Creating directory
Creating basic files: config.m4 Makefile.in .cvsignore [done].
To use your new extension, you will have to execute the following steps:
    $ cd ..
    $ ./buildconf
    $ ./configure # (your extension is automatically enabled)
    $ vi ext/my_module/my_module.c
    $ make
Repeat the last two steps as often as necessary.
```

This instruction creates the aforementioned files. To include the new module in the automatic configuration and build process, you have to run `buildconf`, which regenerates the `configure` script by searching through the `ext` directory and including all found `config.m4` files.

Finally, running `configure` parses all configuration options and generates a makefile based on those options and the options you specify in `Makefile.in`.

27-1 shows the previously generated `Makefile.in`:

Příklad 27-1. The default `Makefile.in`.

```
# $Id: Extending_Zend_Build.xml,v 1.6 2002/03/25 08:13:46 hholzgra Exp $
LTLIBRARY_NAME      = libmy_module.la
LTLIBRARY_SOURCES    = my_module.c
LTLIBRARY_SHARED_NAME = my_module.la include
$(top_srcdir)/build/dynlib.mk
```

There's not much to tell about this one: It contains the names of the input and output files. You could also specify build instructions for other files if your module is built from multiple source files.

The default `config.m4` shown in 27-2' is a bit more complex:

Příklad 27-2. The default `config.m4`.

```
dnl $Id: Extending_Zend_Build.xml,v 1.6 2002/03/25 08:13:46 hholzgra Exp $
dnl config.m4 for extension my_module
dnl don't forget to call PHP_EXTENSION(my_module)
dnl If your extension references something external, use with:
PHP_ARG_WITH(my_module, for my_module support,
dnl Make sure that the comment is aligned:
[    --with-my_module          Include my_module support])
```

```

dnl Otherwise use enable:
PHP_ARG_ENABLE(my_module, whether to enable my_module support,
dnl Make sure that the comment is aligned:
[ --enable-my_module      Enable my_module support])
if test "$PHP_MY_MODULE" != "no"; then
dnl Action..
PHP_EXTENSION(my_module, $ext_shared)
fi

```

If you're unfamiliar with M4 files (now is certainly a good time to get familiar), this might be a bit confusing at first; but it's actually quite easy.

Note: Everything prefixed with `dnl` is treated as a comment and is not parsed.

The `config.m4` file is responsible for parsing the command-line options passed to `configure` at configuration time. This means that it has to check for required external files and do similar configuration and setup tasks.

The default file creates two configuration directives in the `configure` script: `--with-my_module` and `--enable-my_module`. Use the first option when referring external files (such as the `--with-apache` directive that refers to the Apache directory). Use the second option when the user simply has to decide whether to enable your extension. Regardless of which option you use, you should uncomment the other, unnecessary one; that is, if you're using `--enable-my_module`, you should remove support for `--with-my_module`, and vice versa.

By default, the `config.m4` file created by `ext_skel` accepts both directives and automatically enables your extension. Enabling the extension is done by using the `PHP_EXTENSION` macro. To change the default behavior to include your module into the PHP binary when desired by the user (by explicitly specifying `--enable-my_module` or `--with-my_module`), change the test for `$PHP_MY_MODULE` to `== "yes"`:

```

if test "$PHP_MY_MODULE" == "yes"; then dnl
    Action.. PHP_EXTENSION(my_module, $ext_shared)
fi

```

This would require you to use `--enable-my_module` each time when reconfiguring and recompiling PHP.

Note: Be sure to run `buildconf` every time you change `config.m4`!

We'll go into more details on the M4 macros available to your configuration scripts later in this chapter. For now, we'll simply use the default files. The sample sources on the CD-ROM all have working `config.m4` files. To include them into the PHP build process, simply copy the source directories to your PHP `ext` directory, run `buildconf`, and then include the sample modules you want by using the appropriate `--enable-*` directives with `configure`.

Kapitola 28. Creating Extensions

We'll start with the creation of a very simple extension at first, which basically does nothing more than implement a function that returns the integer it receives as parameter. 28-1 shows the source.

Příklad 28-1. A simple extension.

```
/* include standard header */
#include "php.h"

/* declaration of functions to be exported */
ZEND_FUNCTION(first_module);

/* compiled function list so Zend knows what's in this module */
zend_function_entry firstmod_functions[] =
{
    ZEND_FE(first_module, NULL)
    {NULL, NULL, NULL}
};

/* compiled module information */
zend_module_entry firstmod_module_entry =
{
    STANDARD_MODULE_HEADER,
    "First Module",
    firstmod_functions,
    NULL,
    NULL,
    NULL,
    NULL,
    NULL,
    NO_VERSION_YET,
    STANDARD_MODULE_PROPERTIES
};

/* implement standard "stub" routine to introduce ourselves to Zend */
#ifdef COMPILE_DL_FIRST_MODULE
ZEND_GET_MODULE(firstmod)
#endif

/* implement function that is meant to be made available to PHP */
ZEND_FUNCTION(first_module)
{
    long parameter;

    if (zend_parse_parameters(ZEND_NUM_ARGS() TSRMLS_CC, "l", &parameter) == FAILURE) {
        return;
    }

    RETURN_LONG(parameter);
}
```

This code contains a complete PHP module. We'll explain the source code in detail shortly, but first we'd like to discuss the build process. (This will allow the impatient to experiment before we dive into API discussions.)

Poznámka: The example source makes use of some features introduced with the Zend version used in PHP 4.1.0 and above, it won't compile with older PHP 4.0.x versions.

Compiling Modules

There are basically two ways to compile modules:

- Use the provided "make" mechanism in the `ext` directory, which also allows building of dynamic loadable modules.
- Compile the sources manually.

The first method should definitely be favored, since, as of PHP 4.0, this has been standardized into a sophisticated build process. The fact that it is so sophisticated is also its drawback, unfortunately - it's hard to understand at first. We'll provide a more detailed introduction to this later in the chapter, but first let's work with the default files.

The second method is good for those who (for some reason) don't have the full PHP source tree available, don't have access to all files, or just like to juggle with their keyboard. These cases should be extremely rare, but for the sake of completeness we'll also describe this method.

Compiling Using Make. To compile the sample sources using the standard mechanism, copy all their subdirectories to the `ext` directory of your PHP source tree. Then run `buildconf`, which will create an updated `configure` script containing appropriate options for the new extension. By default, all the sample sources are disabled, so you don't have to fear breaking your build process.

After you run `buildconf`, `configure --help` shows the following additional modules:

```
--enable-array_experiments    BOOK: Enables array experiments
--enable-call_userland         BOOK: Enables userland module
--enable-cross_conversion      BOOK: Enables cross-conversion module
--enable-first_module          BOOK: Enables first module
--enable-infoprint             BOOK: Enables infoprint module
--enable-reference_test        BOOK: Enables reference test module
--enable-resource_test         BOOK: Enables resource test module
--enable-variable_creation     BOOK: Enables variable-creation module
```

The module shown earlier in 28-1 can be enabled with `--enable-first_module` or `--enable-first_module=yes`.

Compiling Manually. To compile your modules manually, you need the following commands:

Action	Command
Compiling	<code>cc -fpic -D_COMPILE_DL=1 -I/usr/local/include -I. -I../Zend -c -o <your_object_file> <your_c_f</code>
Linking	<code>cc -shared -L/usr/local/lib -rdynamic -o <your_module_file> <your_object_file(s)></code>

The command to compile the module simply instructs the compiler to generate position-independent code (`-fpic` shouldn't be omitted) and additionally defines the constant `COMPILE_DL` to tell the module code that it's compiled as a dynamically loadable module (the test module above checks for this; we'll discuss it shortly). After these options, it specifies a number of standard include paths that should be used as the minimal set to compile the source files.

Note: All include paths in the example are relative to the directory `ext`. If you're compiling from another directory, change the pathnames accordingly. Required items are the PHP directory, the zend directory, and (if necessary), the directory in which your module resides.

The link command is also a plain vanilla command instructing linkage as a dynamic module.

You can include optimization options in the compilation command, although these have been omitted in this example (but some are included in the makefile template described in an earlier section).

Note: Compiling and linking manually as a static module into the PHP binary involves very long instructions and thus is not discussed here. (It's not very efficient to type all those commands.)

Kapitola 29. Using Extensions

Depending on the build process you selected, you should either end up with a new PHP binary to be linked into your Web server (or run as CGI), or with an .so (shared object) file. If you compiled the example file `first_module.c` as a shared object, your result file should be `first_module.so`. To use it, you first have to copy it to a place from which it's accessible to PHP. For a simple test procedure, you can copy it to your `htdocs` directory and try it with the source in 29-1. If you compiled it into the PHP binary, omit the call to `dl()`, as the module's functionality is instantly available to your scripts.

Varování

For security reasons, you *should not* put your dynamic modules into publicly accessible directories. Even though it *can* be done and it simplifies testing, you should put them into a separate directory in production environments.

Příklad 29-1. A test file for `first_module.so`.

```
<?php

// remove next comment if necessary
// dl("first_module.so");

$param = 2;
$return = first_module($param);

print("We sent '$param' and got '$return'");

?>
```

Calling this PHP file in your Web browser should give you the output shown in 29-1.

Obrázek 29-1. Output of `first_module.php`.

If required, the dynamic loadable module is loaded by calling the `dl()` function. This function looks for the specified shared object, loads it, and makes its functions available to PHP. The module exports the function `first_module()`, which accepts a single parameter, converts it to an integer, and returns the result of the conversion.

If you've gotten this far, congratulations! You just built your first extension to PHP.

Kapitola 30. Troubleshooting

Actually, not much troubleshooting can be done when compiling static or dynamic modules. The only problem that could arise is that the compiler will complain about missing definitions or something similar. In this case, make sure that all header files are available and that you specified their path correctly in the compilation command. To be sure that everything is located correctly, extract a clean PHP source tree and use the automatic build in the `ext` directory with the fresh files; this will guarantee a safe compilation environment. If this fails, try manual compilation.

PHP might also complain about missing functions in your module. (This shouldn't happen with the sample sources if you didn't modify them.) If the names of external functions you're trying to access from your module are misspelled, they'll remain as "unlinked symbols" in the symbol table. During dynamic loading and linkage by PHP, they won't resolve because of the typing errors - there are no corresponding symbols in the main binary. Look for incorrect declarations in your module file or incorrectly written external references. Note that this problem is specific to dynamic loadable modules; it doesn't occur with static modules. Errors in static modules show up at compile time.

Kapitola 31. Source Discussion

Now that you've got a safe build environment and you're able to include the modules into PHP files, it's time to discuss how everything works.

Module Structure

All PHP modules follow a common structure:

- Header file inclusions (to include all required macros, API definitions, etc.)
- C declaration of exported functions (required to declare the Zend function block)
- Declaration of the Zend function block
- Declaration of the Zend module block
- Implementation of `get_module()`
- Implementation of all exported functions

Header File Inclusions

The only header file you really have to include for your modules is `php.h`, located in the PHP directory. This file makes all macros and API definitions required to build new modules available to your code.

Tip: It's good practice to create a separate header file for your module that contains module-specific definitions. This header file should contain all the forward definitions for exported functions and include `php.h`. If you created your module using `ext_skel` you already have such a header file prepared.

Declaring Exported Functions

To declare functions that are to be exported (i.e., made available to PHP as new native functions), Zend provides a set of macros. A sample declaration looks like this:

```
ZEND_FUNCTION ( my_function );
```

`ZEND_FUNCTION` declares a new C function that complies with Zend's internal API. This means that the function is of type `void` and accepts `INTERNAL_FUNCTION_PARAMETERS` (another macro) as parameters. Additionally, it prefixes the function name with `zif`. The immediately expanded version of the above definitions would look like this:

```
void zif_my_function ( INTERNAL_FUNCTION_PARAMETERS );
```

Expanding `INTERNAL_FUNCTION_PARAMETERS` results in the following:

```
void zif_my_function( int ht
```

```

, zval * return_value
, zval * this_ptr
, int return_value_used
, zend_executor_globals * executor_globals
);
```

Since the interpreter and executor core have been separated from the main PHP package, a second API defining macros and function sets has evolved: the Zend API. As the Zend API now handles quite a few of the responsibilities that previously belonged to PHP, a lot of PHP functions have been reduced to macros aliasing to calls into the Zend API. The recommended practice is to use the Zend API wherever possible, as the old API is only preserved for compatibility reasons. For example, the types `zval` and `pval` are identical. `zval` is Zend's definition; `pval` is PHP's definition (actually, `pval` is an alias for `zval` now). As the macro `INTERNAL_FUNCTION_PARAMETERS` is a Zend macro, the above declaration contains `zval`. When writing code, you should always use `zval` to conform to the new Zend API.

The parameter list of this declaration is very important; you should keep these parameters in mind (see 31-1 for descriptions).

Tabulka 31-1. Zend's Parameters to Functions Called from PHP

Parameter	Description
<code>ht</code>	The number of arguments passed to the Zend function. You should not touch this directly, but instead use <code>zend_get_parameters_count()</code> .
<code>return_value</code>	This variable is used to pass any return values of your function back to PHP. Access to this variable is provided by the <code>zend_return()</code> macro.
<code>this_ptr</code>	Using this variable, you can gain access to the object in which your function is contained, if it's used in an object context.
<code>return_value_used</code>	This flag indicates whether an eventual return value from this function will actually be used by the caller.
<code>executor_globals</code>	This variable points to global settings of the Zend engine. You'll find this useful when creating new resources.

Declaration of the Zend Function Block

Now that you have declared the functions to be exported, you also have to introduce them to Zend. Introducing the list of functions is done by using an array of `zend_function_entry`. This array consecutively contains all functions that are to be made available externally, with the function's name as it should appear in PHP and its name as defined in the C source. Internally, `zend_function_entry` is defined as shown in 31-1.

Přiklad 31-1. Internal declaration of `zend_function_entry`.

```
typedef struct _zend_function_entry {
    char *fname;
    void (*handler)(INTERNAL_FUNCTION_PARAMETERS);
    unsigned char *func_arg_types;
} zend_function_entry;
```

Entry	Description
-------	-------------

fname	Denotes the function name as seen in PHP (for example, <code>fopen</code> , <code>mysql_connect</code> , or, in our example, <code>first_module</code>).
handler	Pointer to the C function responsible for handling calls to this function. For example, see the standard <code>zend_function_entry</code> in <code>zend.h</code> .
func_arg_types	Allows you to mark certain parameters so that they're forced to be passed by reference. You usually should use <code>ZEND_FUNC_ARG_REF</code> for this.

In the example above, the declaration looks like this:

```
zend_function_entry firstmod_functions[] =
{
    ZEND_FE(first_module, NULL)
    {NULL, NULL, NULL}
};
```

You can see that the last entry in the list always has to be `{NULL, NULL, NULL}`. This marker has to be set for Zend to know when the end of the list of exported functions is reached.

Poznámka: You *cannot* use the predefined macros for the end marker, as these would try to refer to a function named "NULL"!

The macro `ZEND_FE` (short for 'Zend Function Entry') simply expands to a structure entry in `zend_function_entry`. Note that these macros introduce a special naming scheme to your functions - your C functions will be prefixed with `zif_`, meaning that `ZEND_FE(first_module)` will refer to a C function `zif_first_module()`. If you want to mix macro usage with hand-coded entries (not a good practice), keep this in mind.

Tip: Compilation errors that refer to functions named `zif_*` relate to functions defined with `ZEND_FE`.

31-2 shows a list of all the macros that you can use to define functions.

Tabulka 31-2. Macros for Defining Functions

Macro Name	Description
<code>ZEND_FE(name, arg_types)</code>	Defines a function entry of the name <code>name</code> in <code>zend_function_entry</code> .
<code>ZEND_NAMED_FE/php_name, name, arg_types)</code>	Defines a function that will be available to PHP by the name <code>php_name</code> .
<code>ZEND_FALIAS(name, alias, arg_types)</code>	Defines an alias named <code>alias</code> for <code>name</code> . <code>arg_types</code> needs to be <code>NULL</code> .
<code>PHP_FE(name, arg_types)</code>	Old PHP API equivalent of <code>ZEND_FE</code> .
<code>PHP_NAMED_FE(runtime_name, name, arg_types)</code>	Old PHP API equivalent of <code>ZEND_NAMED_FE</code> .

Note: You can't use `ZEND_FE` in conjunction with `PHP_FUNCTION`, or `PHP_FE` in conjunction with `ZEND_FUNCTION`. However, it's perfectly legal to mix `ZEND_FE` and `ZEND_FUNCTION` with `PHP_FE` and `PHP_FUNCTION` when staying with the same macro set for each function to be declared. But mixing is *not* recommended; instead, you're advised to use the `ZEND_*` macros only.

Declaration of the Zend Module Block

This block is stored in the structure `zend_module_entry` and contains all necessary information to

describe the contents of this module to Zend. You can see the internal definition of this module in 31-2.

Příklad 31-2. Internal declaration of zend_module_entry.

```
typedef struct _zend_module_entry zend_module_entry;

struct _zend_module_entry {
    unsigned short size;
    unsigned int zend_api;
    unsigned char zend_debug;
    unsigned char zts;
    char *name;
    zend_function_entry *functions;
    int (*module_startup_func)(INIT_FUNC_ARGS);
    int (*module_shutdown_func)(SHUTDOWN_FUNC_ARGS);
    int (*request_startup_func)(INIT_FUNC_ARGS);
    int (*request_shutdown_func)(SHUTDOWN_FUNC_ARGS);
    void (*info_func)(ZEND_MODULE_INFO_FUNC_ARGS);
    char *version;
    int (*global_startup_func)(void);
    int (*global_shutdown_func)(void);

    [ Rest of the structure is not interesting here ]

};
```

Entry	Description
size, zend_api, zend_debug and zts	Usually filled with the "STANDARD_MODULE_HEADER", which fills these four members.
name	Contains the module name (for example, "File functions", "Socket functions").
functions	Points to the Zend function block, discussed in the preceding section.
module_startup_func	This function is called once upon module initialization and can be used to do one-time initialization.
module_shutdown_func	This function is called once upon module shutdown and can be used to do one-time cleanup.
request_startup_func	This function is called once upon every page request and can be used to do one-time initialization.
request_shutdown_func	This function is called once after every page request and works as counterpart to request_startup_func.
info_func	When phpinfo() is called in a script, Zend cycles through all loaded modules and calls this function.
version	The version of the module. You can use NO_VERSION_YET if you don't want to give a version.
Remaining structure elements	These are used internally and can be prefilled by using the macro STANDARD_MODULE_PROPERTIES.

In our example, this structure is implemented as follows:

```
zend_module_entry firstmod_module_entry =
{
    STANDARD_MODULE_HEADER,
    "First Module",
    firstmod_functions,
    NULL, NULL, NULL, NULL, NULL,
    NO_VERSION_YET,
    STANDARD_MODULE_PROPERTIES,
};
```


This is basically the easiest and most minimal set of values you could ever use. The module name is set to `First Module`, then the function list is referenced, after which all startup and shutdown functions are marked as being unused.

For reference purposes, you can find a list of the macros involved in declared startup and shutdown functions in 31-3. These are not used in our basic example yet, but will be demonstrated later on. You should make use of these macros to declare your startup and shutdown functions, as these require special arguments to be passed (`INIT_FUNC_ARGS` and `SHUTDOWN_FUNC_ARGS`), which are automatically included into the function declaration when using the predefined macros. If you declare your functions manually and the PHP developers decide that a change in the argument list is necessary, you'll have to change your module sources to remain compatible.

Tabulka 31-3. Macros to Declare Startup and Shutdown Functions

Macro	Description
<code>ZEND_MINIT(module)</code>	Declares a function for module startup. The generated name will be <code>zend_init_<mod</code>
<code>ZEND_MSHUTDOWN(module)</code>	Declares a function for module shutdown. The generated name will be <code>zend_mshutdown</code>
<code>ZEND_RINIT(module)</code>	Declares a function for request startup. The generated name will be <code>zend_rinit_<mod</code>
<code>ZEND_RSHUTDOWN(module)</code>	Declares a function for request shutdown. The generated name will be <code>zend_rshutdown</code>
<code>ZEND_MINFO(module)</code>	Declares a function for printing module information, used when <code>phpinfo()</code> is called. The

Creation of `get_module()`

This function is special to all dynamic loadable modules. Take a look at the creation via the `ZEND_GET_MODULE` macro first:

```
#if COMPILE_DL_FIRSTMOD
    ZEND_GET_MODULE(firstmod)
#endif
```

The function implementation is surrounded by a conditional compilation statement. This is needed since the function `get_module()` is only required if your module is built as a dynamic extension. By specifying a definition of `COMPILE_DL_FIRSTMOD` in the compiler command (see above for a discussion of the compilation instructions required to build a dynamic extension), you can instruct your module whether you intend to build it as a dynamic extension or as a built-in module. If you want a built-in module, the implementation of `get_module()` is simply left out.

`get_module()` is called by Zend at load time of the module. You can think of it as being invoked by the `dl()` call in your script. Its purpose is to pass the module information block back to Zend in order to inform the engine about the module contents.

If you don't implement a `get_module()` function in your dynamic loadable module, Zend will compliment you with an error message when trying to access it.

Implementation of All Exported Functions

Implementing the exported functions is the final step. The example function in `first_module`

looks like this:

```
ZEND_FUNCTION(first_module)
{
    long parameter;

    if (zend_parse_parameters(ZEND_NUM_ARGS() TSRMLS_CC, "l", &parameter) == FAILURE) {
        return;
    }

    RETURN_LONG(parameter);
}
```

The function declaration is done using `ZEND_FUNCTION`, which corresponds to `ZEND_FE` in the function entry table (discussed earlier).

After the declaration, code for checking and retrieving the function's arguments, argument conversion, and return value generation follows (more on this later).

Summary

That's it, basically - there's nothing more to implementing PHP modules. Built-in modules are structured similarly to dynamic modules, so, equipped with the information presented in the previous sections, you'll be able to fight the odds when encountering PHP module source files.

Now, in the following sections, read on about how to make use of PHP's internals to build powerful extensions.

Kapitola 32. Accepting Arguments

One of the most important issues for language extensions is accepting and dealing with data passed via arguments. Most extensions are built to deal with specific input data (or require parameters to perform their specific actions), and function arguments are the only real way to exchange data between the PHP level and the C level. Of course, there's also the possibility of exchanging data using predefined global values (which is also discussed later), but this should be avoided by all means, as it's extremely bad practice.

PHP doesn't make use of any formal function declarations; this is why call syntax is always completely dynamic and never checked for errors. Checking for correct call syntax is left to the user code. For example, it's possible to call a function using only one argument at one time and four arguments the next time - both invocations are syntactically absolutely correct.

Determining the Number of Arguments

Since PHP doesn't have formal function definitions with support for call syntax checking, and since PHP features variable arguments, sometimes you need to find out with how many arguments your function has been called. You can use the `ZEND_NUM_ARGS` macro in this case. In previous versions of PHP, this macro retrieved the number of arguments with which the function has been called based on the function's hash table entry, `ht`, which is passed in the `INTERNAL_FUNCTION_PARAMETERS` list. As `ht` itself now contains the number of arguments that have been passed to the function, `ZEND_NUM_ARGS` has been stripped down to a dummy macro (see its definition in `zend_API.h`). But it's still good practice to use it, to remain compatible with future changes in the call interface. *Note:* The old PHP equivalent of this macro is `ARG_COUNT`.

The following code checks for the correct number of arguments:

```
if (ZEND_NUM_ARGS() != 2) WRONG_PARAM_COUNT;
```

If the function is not called with two arguments, it exits with an error message. The code snippet above makes use of the tool macro `WRONG_PARAM_COUNT`, which can be used to generate a standard error message (see 32-1).

Obrázek 32-1. `WRONG_PARAM_COUNT` in action.

This macro prints a default error message and then returns to the caller. Its definition can also be found in `zend_API.h` and looks like this:

```
ZEND_API void wrong_param_count(void);

#define WRONG_PARAM_COUNT { wrong_param_count(); return; }
```

As you can see, it calls an internal function named **wrong_param_count()** that's responsible for printing the warning. For details on generating customized error messages, see the later section "Printing Information."

Retrieving Arguments

New parameter parsing API: This chapter documents the new Zend parameter parsing API introduced by Andrei Zmievski. It was introduced in the development stage between PHP 4.0.6 and 4.1.0 .

Parsing parameters is a very common operation and it may get a bit tedious. It would also be nice to have standardized error checking and error messages. Since PHP 4.1.0, there is a way to do just that by using the new parameter parsing API. It greatly simplifies the process of receiving parameters, but it has a drawback in that it can't be used for functions that expect variable number of parameters. But since the vast majority of functions do not fall into those categories, this parsing API is recommended as the new standard way.

The prototype for parameter parsing function looks like this:

```
int zend_parse_parameters(int num_args TSRMLS_DC, char *type_spec, ...);
```

The first argument to this function is supposed to be the number of actual parameters passed to your function, so `ZEND_NUM_ARGS()` can be used for that. The second parameter should always be `TSRMLS_CC` macro. The third argument is a string that specifies the number and types of arguments your function is expecting, similar to how `printf` format string specifies the number and format of the output values it should operate on. And finally the rest of the arguments are pointers to variables which should receive the values from the parameters.

zend_parse_parameters() also performs type conversions whenever possible, so that you always receive the data in the format you asked for. Any type of scalar can be converted to another one, but conversions between complex types (arrays, objects, and resources) and scalar types are not allowed.

If the parameters could be obtained successfully and there were no errors during type conversion, the function will return `SUCCESS`, otherwise it will return `FAILURE`. The function will output informative error messages, if the number of received parameters does not match the requested number, or if type conversion could not be performed.

Here are some sample error messages:

```
Warning - ini_get_all() requires at most 1 parameter, 2 given
Warning - wddx_deserialize() expects parameter 1 to be string, array given
```

Of course each error message is accompanied by the filename and line number on which it occurs.

Here is the full list of type specifiers:

- l - long
- d - double
- s - string (with possible null bytes) and its length
- b - boolean

- `r` - resource, stored in `zval*`
- `a` - array, stored in `zval*`
- `o` - object (of any class), stored in `zval*`
- `O` - object (of class specified by class entry), stored in `zval*`
- `z` - the actual `zval*`

The following characters also have a meaning in the specifier string:

- `|` - indicates that the remaining parameters are optional. The storage variables corresponding to these parameters should be initialized to default values by the extension, since they will not be touched by the parsing function if the parameters are not passed.
- `/` - the parsing function will call **SEPARATE_ZVAL_IF_NOT_REF()** on the parameter it follows, to provide a copy of the parameter, unless it's a reference.
- `!` - the parameter it follows can be of specified type or `NULL` (only applies to `a`, `o`, `O`, `r`, and `z`). If `NULL` value is passed by the user, the storage pointer will be set to `NULL`.

The best way to illustrate the usage of this function is through examples:

```
/* Gets a long, a string and its length, and a zval. */
long l;
char *s;
int s_len;
zval *param;
if (zend_parse_parameters(ZEND_NUM_ARGS() TSRMLS_CC,
                        "l sz", &l, &s, &s_len, &param) == FAILURE) {
    return;
}

/* Gets an object of class specified by my_ce, and an optional double. */
zval *obj;
double d = 0.5;
if (zend_parse_parameters(ZEND_NUM_ARGS() TSRMLS_CC,
                        "O|d", &obj, my_ce, &d) == FAILURE) {
    return;
}

/* Gets an object or null, and an array.
   If null is passed for object, obj will be set to NULL. */
zval *obj;
zval *arr;
if (zend_parse_parameters(ZEND_NUM_ARGS() TSRMLS_CC, "O!a", &obj, &arr) == FAILURE) {
    return;
}

/* Gets a separated array. */
zval *arr;
if (zend_parse_parameters(ZEND_NUM_ARGS() TSRMLS_CC, "a/", &arr) == FAILURE) {
    return;
}

/* Get only the first three parameters (useful for varargs functions). */
```

```

zval *z;
zend_bool b;
zval *r;
if (zend_parse_parameters(3, "zbr!", &z, &b, &r) == FAILURE) {
    return;
}

```

Note that in the last example we pass 3 for the number of received parameters, instead of **ZEND_NUM_ARGS()**. What this lets us do is receive the least number of parameters if our function expects a variable number of them. Of course, if you want to operate on the rest of the parameters, you will have to use **zend_get_parameters_array_ex()** to obtain them.

The parsing function has an extended version that allows for an additional flags argument that controls its actions.

```
int zend_parse_parameters_ex(int flags, int num_args TSRMLS_DC, char *type_spec, ...);
```

The only flag you can pass currently is **ZEND_PARSE_PARAMS_QUIET**, which instructs the function to not output any error messages during its operation. This is useful for functions that expect several sets of completely different arguments, but you will have to output your own error messages.

For example, here is how you would get either a set of three longs or a string:

```

long l1, l2, l3;
char *s;
if (zend_parse_parameters_ex(ZEND_PARSE_PARAMS_QUIET,
                             ZEND_NUM_ARGS() TSRMLS_CC,
                             "l1l", &l1, &l2, &l3) == SUCCESS) {
    /* manipulate longs */
} else if (zend_parse_parameters_ex(ZEND_PARSE_PARAMS_QUIET,
                                    ZEND_NUM_ARGS(), "s", &s, &s_len) == SUC-
CESS) {
    /* manipulate string */
} else {
    php_error(E_WARNING, "%s() takes either three long values or a string as argument",
              get_active_function_name(TSRMLS_C));
    return;
}

```

With all the abovementioned ways of receiving function parameters you should have a good handle on this process. For even more example, look through the source code for extensions that are shipped with PHP - they illustrate every conceivable situation.

Old way of retrieving arguments (deprecated)

Deprecated parameter parsing API: This API is deprecated and superseded by the new ZEND parameter parsing API.

After having checked the number of arguments, you need to get access to the arguments themselves. This is done with the help of `zend_get_parameters_ex()`:

```
zval **parameter;

if(zend_get_parameters_ex(1, &parameter) != SUCCESS)
    WRONG_PARAM_COUNT;
```

All arguments are stored in a zval container, which needs to be pointed to *twice*. The snippet above tries to retrieve one argument and make it available to us via the parameter pointer.

`zend_get_parameters_ex()` accepts at least two arguments. The first argument is the number of arguments to retrieve (which should match the number of arguments with which the function has been called; this is why it's important to check for correct call syntax). The second argument (and all following arguments) are pointers to pointers to pointers to zvals. (Confusing, isn't it?) All these pointers are required because Zend works internally with `**zval`; to adjust a local `**zval` in our function, `zend_get_parameters_ex()` requires a pointer to it.

The return value of `zend_get_parameters_ex()` can either be `SUCCESS` or `FAILURE`, indicating (unsurprisingly) success or failure of the argument processing. A failure is most likely related to an incorrect number of arguments being specified, in which case you should exit with `WRONG_PARAM_COUNT`.

To retrieve more than one argument, you can use a similar snippet:

```
zval **param1, **param2, **param3, **param4;

if(zend_get_parameters_ex(4, &param1, &param2, &param3, &param4) != SUCCESS)
    WRONG_PARAM_COUNT;
```

`zend_get_parameters_ex()` only checks whether you're trying to retrieve too many parameters. If the function is called with five arguments, but you're only retrieving three of them with `zend_get_parameters_ex()`, you won't get an error but will get the first three parameters instead. Subsequent calls of `zend_get_parameters_ex()` won't retrieve the remaining arguments, but will get the same arguments again.

Dealing with a Variable Number of Arguments/Optional Parameters

If your function is meant to accept a variable number of arguments, the snippets just described are sometimes suboptimal solutions. You have to create a line calling **zend_get_parameters_ex()** for every possible number of arguments, which is often unsatisfying.

For this case, you can use the function **zend_get_parameters_array_ex()**, which accepts the number of parameters to retrieve and an array in which to store them:

```
zval **parameter_array[4];

/* get the number of arguments */
argument_count = ZEND_NUM_ARGS();

/* see if it satisfies our minimal request (2 arguments) */
/* and our maximal acceptance (4 arguments) */
if(argument_count < 2 || argument_count > 5)
    WRONG_PARAM_COUNT;

/* argument count is correct, now retrieve arguments */
if(zend_get_parameters_array_ex(argument_count, parameter_array) != SUCCESS)
    WRONG_PARAM_COUNT;
```

First, the number of arguments is checked to make sure that it's in the accepted range. After that, **zend_get_parameters_array_ex()** is used to fill `parameter_array` with valid pointers to the argument values.

A very clever implementation of this can be found in the code handling PHP's `fsockopen()` located in `ext/standard/fsock.c`, as shown in 32-1. Don't worry if you don't know all the functions used in this source yet; we'll get to them shortly.

Příklad 32-1. PHP's implementation of variable arguments in `fsockopen()`.

```
pval **args[5];
int *sock=emalloc(sizeof(int));
int *sockp;
int arg_count=ARG_COUNT(ht);
int socketd = -1;
unsigned char udp = 0;
struct timeval timeout = { 60, 0 };
unsigned short portno;
unsigned long conv;
char *key = NULL;
FLS_FETCH();

if (arg_count > 5 || arg_count < 2 || zend_get_parameters_array_ex(arg_count, args) == FAILURE) {
    CLOSE_SOCKET(1);
    WRONG_PARAM_COUNT;
}

switch(arg_count) {
```

```

case 5:
    convert_to_double_ex(args[4]);
    conv = (unsigned long) (Z_DVAL_P(args[4]) * 1000000.0);
    timeout.tv_sec = conv / 1000000;
    timeout.tv_usec = conv % 1000000;
    /* fall-through */
case 4:
    if (!PZVAL_IS_REF(*args[3])) {
        php_error(E_WARNING, "error string argument to fsockopen not passed by reference");
    }
    pval_copy_constructor(*args[3]);
    ZVAL_EMPTY_STRING(*args[3]);
    /* fall-through */
case 3:
    if (!PZVAL_IS_REF(*args[2])) {
        php_error(E_WARNING, "error argument to fsockopen not passed by reference");
        return;
    }
    ZVAL_LONG(*args[2], 0);
    break;
}

convert_to_string_ex(args[0]);
convert_to_long_ex(args[1]);
portno = (unsigned short) Z_LVAL_P(args[1]);

key = emalloc(Z_STRLEN_P(args[0]) + 10);

```

`fsockopen()` accepts two, three, four, or five parameters. After the obligatory variable declarations, the function checks for the correct range of arguments. Then it uses a fall-through mechanism in a `switch()` statement to deal with all arguments. The `switch()` statement starts with the maximum number of arguments being passed (five). After that, it automatically processes the case of four arguments being passed, then three, by omitting the otherwise obligatory `break` keyword in all stages. After having processed the last case, it exits the `switch()` statement and does the minimal argument processing needed if the function is invoked with only two arguments.

This multiple-stage type of processing, similar to a stairway, allows convenient processing of a variable number of arguments.

Accessing Arguments

To access arguments, it's necessary for each argument to have a clearly defined type. Again, PHP's extremely dynamic nature introduces some quirks. Because PHP never does any kind of type checking, it's possible for a caller to pass any kind of data to your functions, whether you want it or not. If you expect an integer, for example, the caller might pass an array, and vice versa - PHP simply won't notice.

To work around this, you have to use a set of API functions to force a type conversion on every argument that's being passed (see 32-1).

Note: All conversion functions expect a `**zval` as parameter.

Tabulka 32-1. Argument Conversion Functions

Function	Description
<code>convert_to_boolean_ex()</code>	Forces conversion to a Boolean type. Boolean values remain untouched. Longs, d
<code>convert_to_long_ex()</code>	Forces conversion to a long, the default integer type. NULL values, Booleans, res
<code>convert_to_double_ex()</code>	Forces conversion to a double, the default floating-point type. NULL values, Bool
<code>convert_to_string_ex()</code>	Forces conversion to a string. Strings remain untouched. NULL values are conver
<code>convert_to_array_ex(value)</code>	Forces conversion to an array. Arrays remain untouched. Objects are converted to
<code>convert_to_object_ex(value)</code>	Forces conversion to an object. Objects remain untouched. NULL values are conv
<code>convert_to_null_ex(value)</code>	Forces the type to become a NULL value, meaning empty.

Poznámka: You can find a demonstration of the behavior in `cross_conversion.php` on the accompanying CD-ROM. 32-2 shows the output.

Obrázek 32-2. Cross-conversion behavior of PHP.

Using these functions on your arguments will ensure type safety for all data that's passed to you. If the supplied type doesn't match the required type, PHP forces dummy contents on the resulting value (empty strings, arrays, or objects, 0 for numeric values, `FALSE` for Booleans) to ensure a defined state.

Following is a quote from the sample module discussed previously, which makes use of the conversion functions:

```

zval **parameter;

if((ZEND_NUM_ARGS() != 1) || (zend_get_parameters_ex(1, &parameter) != SUCCESS))
{
    WRONG_PARAM_COUNT;
}

convert_to_long_ex(parameter);

RETURN_LONG(Z_LVAL_P(parameter));

```

After retrieving the parameter pointer, the parameter value is converted to a long (an integer), which also forms the return value of this function. Understanding access to the contents of the value requires a short discussion of the `zval` type, whose definition is shown in 32-2.

Příklad 32-2. PHP/Zend zval type definition.

```

typedef pval zval;

typedef struct _zval_struct zval;

typedef union _zvalue_value {
    long lval; /* long value */
    double dval; /* double value */
    struct {
        char *val;
        int len;
    } str;
    HashTable *ht; /* hash table value */
    struct {
        zend_class_entry *ce;
        HashTable *properties;
    } obj;
} zvalue_value;

struct _zval_struct {
    /* Variable information */
    zvalue_value value; /* value */
    unsigned char type; /* active type */
    unsigned char is_ref;
    short refcount;
};

```

Actually, pval (defined in `php.h`) is only an alias of zval (defined in `zend.h`), which in turn refers to `_zval_struct`. This is a most interesting structure. `_zval_struct` is the "master" structure, containing the value structure, type, and reference information. The substructure `zvalue_value` is a union that contains the variable's contents. Depending on the variable's type, you'll have to access different members of this union. For a description of both structures, see 32-2, 32-3 and 32-4.

Tabulka 32-2. Zend zval Structure

Entry	Description
value	Union containing this variable's contents. See 32-3 for a description.
type	Contains this variable's type. For a list of available types, see 32-4.
is_ref	0 means that this variable is not a reference; 1 means that this variable is a reference to another variable.
refcount	The number of references that exist for this variable. For every new reference to the value stored in this variable...

Tabulka 32-3. Zend zvalue_value Structure

Entry	Description
lval	Use this property if the variable is of the type <code>IS_LONG</code> , <code>IS_BOOLEAN</code> , or <code>IS_RESOURCE</code> .
dval	Use this property if the variable is of the type <code>IS_DOUBLE</code> .
str	This structure can be used to access variables of the type <code>IS_STRING</code> . The member <code>len</code> contains the string length.
ht	This entry points to the variable's hash table entry if the variable is an array.

obj	Use this property if the variable is of the type <code>IS_OBJECT</code> .
-----	---

Tabulka 32-4. Zend Variable Type Constants

Constant	Description
<code>IS_NULL</code>	Denotes a NULL (empty) value.
<code>IS_LONG</code>	A long (integer) value.
<code>IS_DOUBLE</code>	A double (floating point) value.
<code>IS_STRING</code>	A string.
<code>IS_ARRAY</code>	Denotes an array.
<code>IS_OBJECT</code>	An object.
<code>IS_BOOL</code>	A Boolean value.
<code>IS_RESOURCE</code>	A resource (for a discussion of resources, see the appropriate section below).
<code>IS_CONSTANT</code>	A constant (defined) value.

To access a long you access `zval.value.lval`, to access a double you use `zval.value.dval`, and so on. Because all values are stored in a union, trying to access data with incorrect union members results in meaningless output.

Accessing arrays and objects is a bit more complicated and is discussed later.

Dealing with Arguments Passed by Reference

If your function accepts arguments passed by reference that you intend to modify, you need to take some precautions.

What we didn't say yet is that under the circumstances presented so far, you don't have write access to any `zval` containers designating function parameters that have been passed to you. Of course, you can change any `zval` containers that you created within your function, but you mustn't change any `zvals` that refer to Zend-internal data!

We've only discussed the so-called `*_ex()` API so far. You may have noticed that the API functions we've used are called `zend_get_parameters_ex()` instead of `zend_get_parameters()`, `convert_to_long_ex()` instead of `convert_to_long()`, etc. The `*_ex()` functions form the so-called new "extended" Zend API. They give a minor speed increase over the old API, but as a tradeoff are only meant for providing read-only access.

Because Zend works internally with references, different variables may reference the same value. Write access to a `zval` container requires this container to contain an isolated value, meaning a value that's not referenced by any other containers. If a `zval` container were referenced by other containers and you changed the referenced `zval`, you would automatically change the contents of the other containers referencing this `zval` (because they'd simply point to the changed value and thus change their own value as well).

`zend_get_parameters_ex()` doesn't care about this situation, but simply returns a pointer to the desired `zval` containers, whether they consist of references or not. Its corresponding function in the traditional API, `zend_get_parameters()`, immediately checks for referenced values. If it finds a reference, it creates a new, isolated `zval` container; copies the referenced data into this newly allocated space; and then returns a pointer to the new, isolated value.

This action is called *zval separation* (or *pval separation*). Because the `*_ex()` API doesn't perform *zval separation*, it's considerably faster, while at the same time disabling write access.

To change parameters, however, write access is required. Zend deals with this situation in a special way: Whenever a parameter to a function is passed by reference, it performs automatic *zval separation*. This means that whenever you're calling a function like this in PHP, Zend will automatically ensure that `$parameter` is being passed as an isolated value, rendering it to a write-safe state:

```
my_function(&$parameter);
```

But this *is not* the case with regular parameters! All other parameters that are not passed by reference are in a read-only state.

This requires you to make sure that you're really working with a reference - otherwise you might produce unwanted results. To check for a parameter being passed by reference, you can use the macro `PZVAL_IS_REF`. This macro accepts a `zval*` to check if it is a reference or not. Examples are given in 32-3.

Příklad 32-3. Testing for referenced parameter passing.

```
zval *parameter;

if (zend_parse_parameters(ZEND_NUM_ARGS() TSRMLS_CC, "z", &parameter) == FAILURE)
    return;

/* check for parameter being passed by reference */
if (!PZVAL_IS_REF(*parameter)) {
{
    zend_error(E_WARNING, "Parameter wasn't passed by reference");
    RETURN_NULL();
}

/* make changes to the parameter */
ZVAL_LONG(*parameter, 10);
```

Assuring Write Safety for Other Parameters

You might run into a situation in which you need write access to a parameter that's retrieved with **zend_get_parameters_ex()** but not passed by reference. For this case, you can use the macro **SEPARATE_ZVAL**, which does a zval separation on the provided container. The newly generated zval is detached from internal data and has only a local scope, meaning that it can be changed or destroyed without implying global changes in the script context:

```
zval **parameter;

/* retrieve parameter */
zend_get_parameters_ex(1, &parameter);

/* at this stage, <parameter> still is connected */
/* to Zend's internal data buffers */

/* make <parameter> write-safe */
SEPARATE_ZVAL(parameter);

/* now we can safely modify <parameter> */
/* without implying global changes */
```

SEPARATE_ZVAL uses **emalloc()** to allocate the new zval container, which means that even if you don't deallocate this memory yourself, it will be destroyed automatically upon script termination. However, doing a lot of calls to this macro without freeing the resulting containers will clutter up your RAM.

Note: As you can easily work around the lack of write access in the "traditional" API (with **zend_get_parameters()** and so on), this API seems to be obsolete, and is not discussed further in this chapter.

Kapitola 33. Creating Variables

When exchanging data from your own extensions with PHP scripts, one of the most important issues is the creation of variables. This section shows you how to deal with the variable types that PHP supports.

Overview

To create new variables that can be seen "from the outside" by the executing script, you need to allocate a new zval container, fill this container with meaningful values, and then introduce it to Zend's internal symbol table. This basic process is common to all variable creations:

```
zval *new_variable;

/* allocate and initialize new container */
MAKE_STD_ZVAL(new_variable);

/* set type and variable contents here, see the following sections */

/* introduce this variable by the name "new_variable_name" into the symbol table */
ZEND_SET_SYMBOL(EG(active_symbol_table), "new_variable_name", new_variable);

/* the variable is now accessible to the script by using $new_variable_name */
```

The macro `MAKE_STD_ZVAL` allocates a new zval container using `ALLOC_ZVAL` and initializes it using `INIT_ZVAL`. As implemented in Zend at the time of this writing, *initializing* means setting the reference count to 1 and clearing the `is_ref` flag, but this process could be extended later - this is why it's a good idea to keep using `MAKE_STD_ZVAL` instead of only using `ALLOC_ZVAL`. If you want to optimize for speed (and you don't have to explicitly initialize the zval container here), you can use `ALLOC_ZVAL`, but this isn't recommended because it doesn't ensure data integrity.

`ZEND_SET_SYMBOL` takes care of introducing the new variable to Zend's symbol table. This macro checks whether the value already exists in the symbol table and converts the new symbol to a reference if so (with automatic deallocation of the old zval container). This is the preferred method if speed is not a crucial issue and you'd like to keep memory usage low.

Note that `ZEND_SET_SYMBOL` makes use of the Zend executor globals via the macro `EG`. By specifying `EG(active_symbol_table)`, you get access to the currently active symbol table, dealing with the active, local scope. The local scope may differ depending on whether the function was invoked from within a function.

If you need to optimize for speed and don't care about optimal memory usage, you can omit the check for an existing variable with the same value and instead force insertion into the symbol table by using `zend_hash_update()`:

```
zval *new_variable;

/* allocate and initialize new container */
MAKE_STD_ZVAL(new_variable);

/* set type and variable contents here, see the following sections */

/* introduce this variable by the name "new_variable_name" into the symbol table */
zend_hash_update(
```

```

    EG(active_symbol_table),
    "new_variable_name",
    strlen("new_variable_name") + 1,
    &new_variable,
    sizeof(zval *),
    NULL
);

```

This is actually the standard method used in most modules.

The variables generated with the snippet above will always be of local scope, so they reside in the context in which the function has been called. To create new variables in the global scope, use the same method but refer to another symbol table:

```

zval *new_variable;

// allocate and initialize new container
MAKE_STD_ZVAL(new_variable);

//
// set type and variable contents here
//

// introduce this variable by the name "new_variable_name" into the global sym-
bol table
ZEND_SET_SYMBOL(&EG(symbol_table), "new_variable_name", new_variable);

```

The macro `ZEND_SET_SYMBOL` is now being called with a reference to the main, global symbol table by referring `EG(symbol_table)`.

Note: The `active_symbol_table` variable is a pointer, but `symbol_table` is not. This is why you have to use `EG(active_symbol_table)` and `&EG(symbol_table)` as parameters to `ZEND_SET_SYMBOL` - it requires a pointer.

Similarly, to get a more efficient version, you can hardcode the symbol table update:

```

zval *new_variable;

// allocate and initialize new container
MAKE_STD_ZVAL(new_variable);

//
// set type and variable contents here
//

// introduce this variable by the name "new_variable_name" into the global sym-
bol table
zend_hash_update(
    &EG(symbol_table),
    "new_variable_name",
    strlen("new_variable_name") + 1,
    &new_variable,
    sizeof(zval *),
    NULL
);

```

33-1 shows a sample source that creates two variables - `local_variable` with a local scope and `global_variable` with a global scope (see Figure 9.7). The full example can be found on the CD-ROM.

Note: You can see that the global variable is actually not accessible from within the function. This is because it's not imported into the local scope using `global $global_variable;` in the PHP source.

Příklad 33-1. Creating variables with different scopes.

```
ZEND_FUNCTION(variable_creation)
{
    zval *new_var1, *new_var2;

    MAKE_STD_ZVAL(new_var1);
    MAKE_STD_ZVAL(new_var2);

    ZVAL_LONG(new_var1, 10);
    ZVAL_LONG(new_var2, 5);

    ZEND_SET_SYMBOL(EG(active_symbol_table), "local_variable", new_var1);
    ZEND_SET_SYMBOL(&EG(symbol_table), "global_variable", new_var2);

    RETURN_NULL();
}
```

Longs (Integers)

Now let's get to the assignment of data to variables, starting with longs. Longs are PHP's integers and are very simple to store. Looking at the `zval.value` container structure discussed earlier in this chapter, you can see that the long data type is directly contained in the union, namely in the `lval` field. The corresponding type value for longs is `IS_LONG` (see 33-2).

Příklad 33-2. Creation of a long.

```
zval *new_long;

MAKE_STD_ZVAL(new_long);

new_long->type = IS_LONG;
new_long->value.lval = 10;
```

Alternatively, you can use the macro `ZVAL_LONG`:

```
zval *new_long;

MAKE_STD_ZVAL(new_long);
ZVAL_LONG(new_long, 10);
```

Doubles (Floats)

Doubles are PHP's floats and are as easy to assign as longs, because their value is also contained directly in the union. The member in the `zval.value` container is `dval`; the corresponding type is `IS_DOUBLE`.

```
zval *new_double;

MAKE_STD_ZVAL(new_double);

new_double->type = IS_DOUBLE;
new_double->value.dval = 3.45;
```

Alternatively, you can use the macro `ZVAL_DOUBLE`:

```
zval *new_double;

MAKE_STD_ZVAL(new_double);
ZVAL_DOUBLE(new_double, 3.45);
```

Strings

Strings need slightly more effort. As mentioned earlier, all strings that will be associated with Zend's internal data structures need to be allocated using Zend's own memory-management functions. Referencing of static strings or strings allocated with standard routines is not allowed. To assign strings, you have to access the structure `str` in the `zval.value` container. The corresponding type is `IS_STRING`:

```
zval *new_string;
char *string_contents = "This is a new string variable";

MAKE_STD_ZVAL(new_string);

new_string->type = IS_STRING;
new_string->value.str.len = strlen(string_contents);
new_string->value.str.val = estrdup(string_contents);
```

Note the usage of Zend's **estrdup()** here. Of course, you can also use the predefined macro `ZVAL_STRING`:

```
zval *new_string;
char *string_contents = "This is a new string variable";

MAKE_STD_ZVAL(new_string);
ZVAL_STRING(new_string, string_contents, 1);
```

`ZVAL_STRING` accepts a third parameter that indicates whether the supplied string contents should be duplicated (using **estrdup()**). Setting this parameter to 1 causes the string to be duplicated; 0 simply uses the supplied pointer for the variable contents. This is most useful if you want to create a new variable referring to a string that's already allocated in Zend internal memory.

If you want to truncate the string at a certain position or you already know its length, you can use `ZVAL_STRINGL(zval, string, length, duplicate)`, which accepts an explicit string length to be set for the new string. This macro is faster than `ZVAL_STRING` and also binary-safe.

To create empty strings, set the string length to 0 and use `empty_string` as contents:

```
new_string->type = IS_STRING;
new_string->value.str.len = 0;
new_string->value.str.val = empty_string;
```

Of course, there's a macro for this as well (`ZVAL_EMPTY_STRING`):

```
MAKE_STD_ZVAL(new_string);
ZVAL_EMPTY_STRING(new_string);
```

Booleans

Booleans are created just like longs, but have the type `IS_BOOL`. Allowed values in `lval` are 0 and 1:

```
zval *new_bool;

MAKE_STD_ZVAL(new_bool);

new_bool->type = IS_BOOL;
new_bool->value.lval = 1;
```

The corresponding macros for this type are `ZVAL_BOOL` (allowing specification of the value) as well as `ZVAL_TRUE` and `ZVAL_FALSE` (which explicitly set the value to `TRUE` and `FALSE`, respectively).

Arrays

Arrays are stored using Zend's internal hash tables, which can be accessed using the `zend_hash_*()` API. For every array that you want to create, you need a new hash table handle, which will be stored in the `ht` member of the `zval.value` container.

There's a whole API solely for the creation of arrays, which is extremely handy. To start a new array, you call **array_init()**.

```
zval *new_array;

MAKE_STD_ZVAL(new_array);

if(array_init(new_array) != SUCCESS)
{
    // do error handling here
}
```

If **array_init()** fails to create a new array, it returns **FAILURE**.

To add new elements to the array, you can use numerous functions, depending on what you want to do. 33-1, 33-2 and 33-3 describe these functions. All functions return **FAILURE** on failure and **SUCCESS** on success.

Tabulka 33-1. Zend's API for Associative Arrays

Function	Description
add_assoc_long(zval *array, char *key, long n);()	Adds an element of type <code>long</code> .
add_assoc_unset(zval *array, char *key);()	Adds an unset element.
add_assoc_bool(zval *array, char *key, int b);()	Adds a Boolean element.
add_assoc_resource(zval *array, char *key, int r);()	Adds a resource to the array.
add_assoc_double(zval *array, char *key, double d);()	Adds a floating-point value.
add_assoc_string(zval *array, char *key, char *str, int duplicate);()	Adds a string to the array. The flag <code>duplicate</code> specifies whether the string contents have to be copied to Zend internal memory.
add_assoc_stringl(zval *array, char *key, char *str, uint length, int duplicate); ()	Adds a string with the desired length <code>length</code> to the array. Otherwise, behaves like add_assoc_string() .

Tabulka 33-2. Zend's API for Indexed Arrays, Part 1

Function	Description
add_index_long(zval *array, uint idx, long n);()	Adds an element of type <code>long</code> .
add_index_unset(zval *array, uint idx);()	Adds an unset element.
add_index_bool(zval *array, uint idx, int b);()	Adds a Boolean element.
add_index_resource(zval *array, uint idx, int r);()	Adds a resource to the array.
add_index_double(zval *array, uint idx, double d);()	Adds a floating-point value.

add_index_string(zval *array, uint idx, char *str, int duplicate);()	Adds a string to the array. The flag duplicate specifies whether the string contents have to be copied to Zend internal memory.
add_index_stringl(zval *array, uint idx, char *str, uint length, int duplicate);()	Adds a string with the desired length length to the array. This function is faster and binary-safe. Otherwise, behaves like add_index_string() .

Tabulka 33-3. Zend's API for Indexed Arrays, Part 2

Function	Description
add_next_index_long(zval *array, long n);()	Adds an element of type <code>long</code> .
add_next_index_unset(zval *array);()	Adds an unset element.
add_next_index_bool(zval *array, int b);()	Adds a Boolean element.
add_next_index_resource(zval *array, int r);()	Adds a resource to the array.
add_next_index_double(zval *array, double d);()	Adds a floating-point value.
add_next_index_string(zval *array, char *str, int duplicate);()	Adds a string to the array. The flag duplicate specifies whether the string contents have to be copied to Zend internal memory.
add_next_index_stringl(zval *array, char *str, uint length, int duplicate);()	Adds a string with the desired length length to the array. This function is faster and binary-safe. Otherwise, behaves like add_index_string() .

All these functions provide a handy abstraction to Zend's internal hash API. Of course, you can also use the hash functions directly - for example, if you already have a `zval` container allocated that you want to insert into an array. This is done using **zend_hash_update()** for associative arrays (see 33-3) and **zend_hash_index_update()** for indexed arrays (see 33-4):

Příklad 33-3. Adding an element to an associative array.

```

zval *new_array, *new_element;
char *key = "element_key";

MAKE_STD_ZVAL(new_array);
MAKE_STD_ZVAL(new_element);

if(array_init(new_array) == FAILURE)
{
    // do error handling here
}

ZVAL_LONG(new_element, 10);

if(zend_hash_update(new_array->value.ht, key, strlen(key) + 1, (void *)&new_element, sizeof(zval *), 0) == FAILURE)
{
    // do error handling here
}

```

Příklad 33-4. Adding an element to an indexed array.

```

zval *new_array, *new_element;
int key = 2;

MAKE_STD_ZVAL(new_array);
MAKE_STD_ZVAL(new_element);

if(array_init(new_array) == FAILURE)
{
    // do error handling here
}

ZVAL_LONG(new_element, 10);

if(zend_hash_index_update(new_array->value.ht, key, (void *)&new_element, sizeof(zval *))
{
    // do error handling here
}

```

To emulate the functionality of **add_next_index_***(), you can use this:

```
zend_hash_next_index_insert(ht, zval **new_element, sizeof(zval *), NULL)
```

Note: To return arrays from a function, use **array_init()** and all following actions on the predefined variable `return_value` (given as argument to your exported function; see the earlier discussion of the call interface). You do not have to use **MAKE_STD_ZVAL** on this.

Tip: To avoid having to write `new_array->value.ht` every time, you can use **HASH_OF(new_array)**, which is also recommended for compatibility and style reasons.

Objects

Since objects can be converted to arrays (and vice versa), you might have already guessed that they have a lot of similarities to arrays in PHP. Objects are maintained with the same hash functions, but there's a different API for creating them.

To initialize an object, you use the function **object_init()**:

```

zval *new_object;

MAKE_STD_ZVAL(new_object);

if(object_init(new_object) != SUCCESS)
{
    // do error handling here
}

```

You can use the functions described in 33-4 to add members to your object.

Tabulka 33-4. Zend's API for Object Creation

Function	Description
<code>add_property_long(zval *object, char *key, long l);()</code>	Adds a long to the object.
<code>add_property_unset(zval *object, char *key);()</code>	Adds an unset property to the object.
<code>add_property_bool(zval *object, char *key, int b);()</code>	Adds a Boolean to the object.
<code>add_property_resource(zval *object, char *key, long r);()</code>	Adds a resource to the object.
<code>add_property_double(zval *object, char *key, double d);()</code>	Adds a double to the object.
<code>add_property_string(zval *object, char *key, char *str, int duplicate);()</code>	Adds a string to the object.
<code>add_property_stringl(zval *object, char *key, char *str, uint length, int duplicate);()</code>	Adds a string of the specified length to the object.
<code>add_property_zval(zval *object, char *key, zval *container):()</code>	Adds a zval container to the object.

Resources

Resources are a special kind of data type in PHP. The term *resources* doesn't really refer to any special kind of data, but to an abstraction method for maintaining any kind of information. Resources are kept in a special resource list within Zend. Each entry in the list has a corresponding type definition that denotes the kind of resource to which it refers. Zend then internally manages all references to this resource. Access to a resource is never possible directly - only via a provided API. As soon as all references to a specific resource are lost, a corresponding shutdown function is called.

For example, resources are used to store database links and file descriptors. The *de facto* standard implementation can be found in the MySQL module, but other modules such as the Oracle module also make use of resources.

Poznámka: In fact, a resource can be a pointer to anything you need to handle in your functions (e.g. pointer to a structure) and the user only has to pass a single resource variable to your function.

To create a new resource you need to register a resource destruction handler for it. Since you can store any kind of data as a resource, Zend needs to know how to free this resource if its not longer needed. This works by registering your own resource destruction handler to Zend which in turn gets called by Zend whenever your resource can be freed (whether manually or automatically).

Registering your resource handler within Zend returns you the **resource type handle** for that resource. This handle is needed whenever you want to access a resource of this type later and is most of time stored in a global static variable within your extension. There is no need to worry about thread safety here because you only register your resource handler once during module initialization.

The Zend function to register your resource handler is defined as:

```
ZEND_API int zend_register_list_destructors_ex(rsrc_dtor_func_t ld, rsrc_dtor_func_t pld,
```

There are two different kinds of resource destruction handlers you can pass to this function: a handler for normal resources and a handler for persistent resources. Persistent resources are for example used for database connection. When registering a resource, either of these handlers must be given. For the other handler just pass NULL.

zend_register_list_destructors_ex() accepts the following parameters:

ld	Normal resource destruction handler callback
pld	Persistent resource destruction handler callback
type_name	A string specifying the name of your resource. It's always a good thing to specify a unique name with
module_number	The module_number is automatically available in your PHP_MINIT_FUNCTION function and therefore

The return value is a unique integer ID for your **resource type**.

The resource destruction handler (either normal or persistent resources) has the following prototype:

```
void resource_destruction_handler(zend_rsrc_list_entry *rsrc TSRMLS_DC);
```

The passed `rsrc` is a pointer to the following structure:

```
typedef struct _zend_rsrc_list_entry {
    void *ptr;
    int type;
    int refcount;
} zend_rsrc_list_entry;
```

The member `void *ptr` is the actual pointer to your resource.

Now we know how to start things, we define our own resource we want register within Zend. It is only a simple structure with two integer members:

```
typedef struct {
    int resource_link;
    int resource_type;
} my_resource;
```

Our resource destruction handler is probably going to look something like this:

```
void my_destruction_handler(zend_rsrc_list_entry *rsrc TSRMLS_DC) {

    // You most likely cast the void pointer to your structure type

    my_resource *my_rsrc = (my_resource *) rsrc->ptr;

    // Now do whatever needs to be done with your resource. Closing
    // Files, Sockets, freeing additional memory, etc.
    // Also, don't forget to actually free the memory for your resource too!

    do_whatever_needs_to_be_done_with_the_resource(my_rsrc);
}
```

Poznámka: One important thing to mention: If your resource is a rather complex structure which also contains pointers to memory you allocated during runtime you have to free them **before** freeing the resource itself!

Now that we have defined

1. what our resource is and
2. our resource destruction handler

we can go on and do the rest of the steps:

1. create a global variable within the extension holding the resource ID so it can be accessed from every function which needs it
2. define the resource name
3. write the resource destruction handler
4. and finally register the handler

```
// Somewhere in your extension, define the variable for your registered resources.
// If you wondered what 'le' stands for: it simply means 'list entry'.
static int le_myresource;

// It's nice to define your resource name somewhere
#define le_myresource_name "My type of resource"

[...]

// Now actually define our resource destruction handler
void my_destruction_handler(zend_rsrc_list_entry *rsrc TSRMLS_DC) {

    my_resource *my_rsrc = (my_resource *) rsrc->ptr;
    do_whatever_needs_to_be_done_with_the_resource(my_rsrc);
}

[...]

PHP_MINIT_FUNCTION(my_extension) {

    // Note that 'module_number' is already provided through the
    // PHP_MINIT_FUNCTION() function definition.

    le_myresource = zend_register_resource_destructors_ex(my_destruction_handler, NULL, 0);

    // You can register additional resources, initialize
    // your global vars, constants, whatever.
}
```

To actually register a new resource you use can either use the **zend_register_resource()** function or the **ZEND_REGISTER_RESOURCE()** macro, both defined in `zend_list.h`. Although the arguments for both map 1:1 it's a good idea to always use macros to be upwards compatible:

```
int ZEND_REGISTER_RESOURCE(zval *rsrc_result, void *rsrc_pointer, int rsrc_type);
```

<code>rsrc_result</code>	This is an already initialized <code>zval *</code> container.
<code>rsrc_pointer</code>	Your resource pointer you want to store.
<code>rsrc_type</code>	The type which you received when you registered the resource destruction handler. If you followed the

The return value is an unique integer identifier for that resource.

What is really going on when you register a new resource is it gets inserted in an internal list in Zend and the result is just stored in the given `zval *` container:

```

rsrc_id = zend_list_insert(rsrc_pointer, rsrc_type);

if (rsrc_result) {
    rsrc_result->value.lval = rsrc_id;
    rsrc_result->type = IS_RESOURCE;
}

return rsrc_id;
```

The returned `rsrc_id` uniquely identifies the newly registered resource. You can use the macro `RETURN_RESOURCE` to return it to the user:

```
RETURN_RESOURCE(rsrc_id)
```

Poznámka: It is common practice that if you want to return the resource immediately to the user you specify the `return_value` as the `zval *` container.

Zend now keeps track of all references to this resource. As soon as all references to the resource are lost, the destructor that you previously registered for this resource is called. The nice thing about this setup is that you don't have to worry about memory leakages introduced by allocations in your module - just register all memory allocations that your calling script will refer to as resources. As soon as the script decides it doesn't need them anymore, Zend will find out and tell you.

Now that the user got his resource, at some point he is passing it back to one of your functions. The `value.lval` inside the `zval *` container contains the key to your resource and thus can be used to fetch the resource with the following macro: `ZEND_FETCH_RESOURCE`:

```
ZEND_FETCH_RESOURCE(rsrc, rsrc_type, rsrc_id, default_rsrc_id, resource_type_name, resourc
```

<code>rsrc</code>	This is your pointer which will point to your previously registered resource.
<code>rsrc_type</code>	This is the typecast argument for your pointer, e.g. <code>myresource *</code> .
<code>rsrc_id</code>	This is the address of the <code>zval *</code> container the user passed to your function, e.g. <code>&z_resource</code>
<code>default_rsrc_id</code>	This integer specifies the default resource ID if no resource could be fetched or -1.
<code>resource_type_name</code>	This is the name of the requested resource. It's a string and is used when the resource can't be
<code>resource_type</code>	The <code>resource_type</code> you got back when registering the resource destruction handler. In our e

This macro has no return value. It is for the developers convenience and takes care of TSRMLS arguments passing and also does check if the resource could be fetched. It throws a warning message and returns the current PHP function with `NULL` if there was a problem retrieving the resource.

To force removal of a resource from the list, use the function `zend_list_delete()`. You can also force the reference count to increase if you know that you're creating another reference for a previously allocated value (for example, if you're automatically reusing a default database link). For this case, use the function `zend_list_addref()`. To search for previously allocated resource entries, use `zend_list_find()`. The complete API can be found in `zend_list.h`.

Macros for Automatic Global Variable Creation

In addition to the macros discussed earlier, a few macros allow easy creation of simple global variables. These are nice to know in case you want to introduce global flags, for example. This is somewhat bad practice, but Table 33-5 describes macros that do exactly this task. They don't need any `zval` allocation; you simply have to supply a variable name and value.

Tabulka 33-5. Macros for Global Variable Creation

Macro	Description
<code>SET_VAR_STRING(name, value)</code>	Creates a new string.
<code>SET_VAR_STRINGL(name, value, length)</code>	Creates a new string of the specified length. This macro is faster than <code>SET_VAR_STRING</code> and also binary-safe.
<code>SET_VAR_LONG(name, value)</code>	Creates a new long.
<code>SET_VAR_DOUBLE(name, value)</code>	Creates a new double.

Creating Constants

Zend supports the creation of true constants (as opposed to regular variables). Constants are accessed without the typical dollar sign (\$) prefix and are available in all scopes. Examples include `TRUE` and `FALSE`, to name just two.

To create your own constants, you can use the macros in 33-6. All the macros create a constant with the specified name and value.

You can also specify flags for each constant:

- `CONST_CS` - This constant's name is to be treated as case sensitive.
- `CONST_PERSISTENT` - This constant is persistent and won't be "forgotten" when the current process carrying this constant shuts down.

To use the flags, combine them using a binary OR:

```
// register a new constant of type "long"
REGISTER_LONG_CONSTANT("NEW_MEANINGFUL_CONSTANT", 324, CONST_CS |
CONST_PERSISTENT);
```

There are two types of macros - `REGISTER_*_CONSTANT` and `REGISTER_MAIN_*_CONSTANT`. The first type creates constants bound to the current module. These constants are dumped from the symbol table as soon as the module that registered the constant is unloaded from memory. The second type creates constants that remain in the symbol table independently of the module.

Tabulka 33-6. Macros for Creating Constants

Macro
REGISTER_LONG_CONSTANT(name, value, flags) REGISTER_MAIN_LONG_CONSTANT(name, value, flags)
REGISTER_DOUBLE_CONSTANT(name, value, flags) REGISTER_MAIN_DOUBLE_CONSTANT(name, value, flags)
REGISTER_STRING_CONSTANT(name, value, flags) REGISTER_MAIN_STRING_CONSTANT(name, value, flags)
REGISTER_STRINGL_CONSTANT(name, value, length, flags) REGISTER_MAIN_STRINGL_CONSTANT(name, value, length, flags)

Kapitola 34. Duplicating Variable Contents: The Copy Constructor

Sooner or later, you may need to assign the contents of one zval container to another. This is easier said than done, since the zval container doesn't contain only type information, but also references to places in Zend's internal data. For example, depending on their size, arrays and objects may be nested with lots of hash table entries. By assigning one zval to another, you avoid duplicating the hash table entries, using only a reference to them (at most).

To copy this complex kind of data, use the *copy constructor*. Copy constructors are typically defined in languages that support operator overloading, with the express purpose of copying complex types. If you define an object in such a language, you have the possibility of overloading the "=" operator, which is usually responsible for assigning the contents of the lvalue (result of the evaluation of the left side of the operator) to the rvalue (same for the right side).

Overloading means assigning a different meaning to this operator, and is usually used to assign a function call to an operator. Whenever this operator would be used on such an object in a program, this function would be called with the lvalue and rvalue as parameters. Equipped with that information, it can perform the operation it intends the "=" operator to have (usually an extended form of copying).

This same form of "extended copying" is also necessary for PHP's zval containers. Again, in the case of an array, this extended copying would imply re-creation of all hash table entries relating to this array. For strings, proper memory allocation would have to be assured, and so on.

Zend ships with such a function, called **zend_copy_ctor()** (the previous PHP equivalent was **pval_copy_constructor()**).

A most useful demonstration is a function that accepts a complex type as argument, modifies it, and then returns the argument:

```
zval *parameter;

if (zend_parse_parameters(ZEND_NUM_ARGS() TSRMLS_CC, "z", &parameter) == FAILURE)
    return;
}

// do modifications to the parameter here

// now we want to return the modified container:
*return_value == *parameter;
zend_copy_ctor(return_value);
```

The first part of the function is plain-vanilla argument retrieval. After the (left out) modifications, however, it gets interesting: The container of parameter is assigned to the (predefined) return_value container. Now, in order to effectively duplicate its contents, the copy constructor is called. The copy constructor works directly with the supplied argument, and the standard return values are FAILURE on failure and SUCCESS on success.

If you omit the call to the copy constructor in this example, both parameter and return_value would point to the same internal data, meaning that return_value would be an illegal additional reference to the same data structures. Whenever changes occurred in the data that parameter points to, return_value might be affected. Thus, in order to create separate copies, the copy constructor must be used.

The copy constructor's counterpart in the Zend API, the destructor **zval_dtor()**, does the opposite of the constructor.

Kapitola 35. Returning Values

Returning values from your functions to PHP was described briefly in an earlier section; this section gives the details. Return values are passed via the `return_value` variable, which is passed to your functions as argument. The `return_value` argument consists of a `zval` container (see the earlier discussion of the call interface) that you can freely modify. The container itself is already allocated, so you don't have to run `MAKE_STD_ZVAL` on it. Instead, you can access its members directly.

To make returning values from functions easier and to prevent hassles with accessing the internal structures of the `zval` container, a set of predefined macros is available (as usual). These macros automatically set the correspondent type and value, as described in 35-1 and 35-2.

Poznámka: The macros in 35-1 automatically *return* from your function, those in 35-2 only *set* the return value; they don't return from your function.

Tabulka 35-1. Predefined Macros for Returning Values from a Function

Macro	Description
<code>RETURN_RESOURCE(resource)</code>	Returns a resource.
<code>RETURN_BOOL(bool)</code>	Returns a Boolean.
<code>RETURN_NULL()</code>	Returns nothing (a NULL value).
<code>RETURN_LONG(long)</code>	Returns a long.
<code>RETURN_DOUBLE(double)</code>	Returns a double.
<code>RETURN_STRING(string, duplicate)</code>	Returns a string. The duplicate flag indicates whether the string should be duplicated using <code>estrdup()</code> .
<code>RETURN_STRINGL(string, length, duplicate)</code>	Returns a string of the specified length; otherwise, behaves like <code>RETURN_STRING</code> . This macro is faster and binary-safe, however.
<code>RETURN_EMPTY_STRING()</code>	Returns an empty string.
<code>RETURN_FALSE</code>	Returns Boolean false.
<code>RETURN_TRUE</code>	Returns Boolean true.

Tabulka 35-2. Predefined Macros for Setting the Return Value of a Function

Macro	Description
<code>RETVAL_RESOURCE(resource)</code>	Sets the return value to the specified resource.
<code>RETVAL_BOOL(bool)</code>	Sets the return value to the specified Boolean value.
<code>RETVAL_NULL</code>	Sets the return value to NULL.
<code>RETVAL_LONG(long)</code>	Sets the return value to the specified long.
<code>RETVAL_DOUBLE(double)</code>	Sets the return value to the specified double.
<code>RETVAL_STRING(string, duplicate)</code>	Sets the return value to the specified string and duplicates it to Zend internal memory if desired (see also <code>RETURN_STRING</code>).

<code>RETVAL_STRINGL(string, length, duplicate)</code>	Sets the return value to the specified string and forces the length to become length (see also <code>RETVAL_STRING</code>). This macro is faster and binary-safe, and should be used whenever the string length is known.
<code>RETVAL_EMPTY_STRING</code>	Sets the return value to an empty string.
<code>RETVAL_FALSE</code>	Sets the return value to Boolean false.
<code>RETVAL_TRUE</code>	Sets the return value to Boolean true.

Complex types such as arrays and objects can be returned by using **`array_init()`** and **`object_init()`**, as well as the corresponding hash functions on `return_value`. Since these types cannot be constructed of trivial information, there are no predefined macros for them.

Kapitola 36. Printing Information

Often it's necessary to print messages to the output stream from your module, just as `print()` would be used within a script. PHP offers functions for most generic tasks, such as printing warning messages, generating output for `phpinfo()`, and so on. The following sections provide more details. Examples of these functions can be found on the CD-ROM.

zend_printf()

`zend_printf()` works like the standard `printf()`, except that it prints to Zend's output stream.

zend_error()

`zend_error()` can be used to generate error messages. This function accepts two arguments; the first is the error type (see `zend_errors.h`), and the second is the error message.

```
zend_error(E_WARNING, "This function has been called with empty arguments");
```

36-1 shows a list of possible values (see 36-1). These values are also referred to in `php.ini`. Depending on which error type you choose, your messages will be logged.

Tabulka 36-1. Zend's Predefined Error Messages.

Error	Description
<code>E_ERROR</code>	Signals an error and terminates execution of the script immediately .
<code>E_WARNING</code>	Signals a generic warning. Execution continues.
<code>E_PARSE</code>	Signals a parser error. Execution continues.
<code>E_NOTICE</code>	Signals a notice. Execution continues. Note that by default the display of this type of error mes
<code>E_CORE_ERROR</code>	Internal error by the core; shouldn't be used by user-written modules.
<code>E_COMPILE_ERROR</code>	Internal error by the compiler; shouldn't be used by user-written modules.
<code>E_COMPILE_WARNING</code>	Internal warning by the compiler; shouldn't be used by user-written modules.

Obrázek 36-1. Display of warning messages in the browser.

Including Output in phpinfo()

After creating a real module, you'll want to show information about the module in `phpinfo()` (in addition to the module name, which appears in the module list by default). PHP allows you to create your own section in the `phpinfo()` output with the `ZEND_MINFO()` function. This function should be placed in the module descriptor block (discussed earlier) and is always called whenever a script calls `phpinfo()`.

PHP automatically prints a section in `phpinfo()` for you if you specify the `ZEND_MINFO` function, including the module name in the heading. Everything else must be formatted and printed by you.

Typically, you can print an HTML table header using `php_info_print_table_start()` and then use the standard functions `php_info_print_table_header()` and `php_info_print_table_row()`. As arguments, both take the number of columns (as integers) and the column contents (as strings). 36-1 shows a source example and its output. To print the table footer, use `php_info_print_table_end()`.

Příklad 36-1. Source code and screenshot for output in phpinfo().

```
php_info_print_table_start();
php_info_print_table_header(2, "First column", "Second column");
php_info_print_table_row(2, "Entry in first row", "Another entry");
php_info_print_table_row(2, "Just to fill", "another row here");
php_info_print_table_end();
```

Execution Information

You can also print execution information, such as the current file being executed. The name of the function currently being executed can be retrieved using the function `get_active_function_name()`. This function returns a pointer to the function name and doesn't accept any arguments. To retrieve the name of the file currently being executed, use `zend_get_executed_filename()`. This function accesses the executor globals, which are passed to it using the `TSRMLS_C` macro. The executor globals are automatically available to every function that's called directly by Zend (they're part of the `INTERNAL_FUNCTION_PARAMETERS` described earlier in this chapter). If you want to access the executor globals in another function that doesn't have them available automatically, call the macro `TSRMLS_FETCH()` once in that function; this will introduce them to your local scope.

Finally, the line number currently being executed can be retrieved using the function `zend_get_executed_lineno()`. This function also requires the executor globals as arguments. For examples of these functions, see 36-2.

Příklad 36-2. Printing execution information.

```
zend_printf("The name of the current function is %s<br>", get_active_function_name(TSRMLS_C));
```

```
zend_printf("The file currently executed is %s<br>", zend_get_executed_filename(TSRMLS_C)  
zend_printf("The current line being executed is %i<br>", zend_get_executed_lineno(TSRMLS_C
```

Kapitola 37. Startup and Shutdown Functions

Startup and shutdown functions can be used for one-time initialization and deinitialization of your modules. As discussed earlier in this chapter (see the description of the Zend module descriptor block), there are global, module, and request startup and shutdown events.

The global startup functions are called once when PHP starts up; similarly, the global shutdown functions are called once when PHP shuts down. Please note that they're really only called *once*, not when a new Apache process is being created!

The module startup and shutdown functions are called whenever a module is loaded and needs initialization; the request startup and shutdown functions are called every time a request is processed (meaning that a file is being executed).

For dynamic extensions, module and request startup/shutdown events happen at the same time.

Declaration and implementation of these functions can be done with macros; see the earlier section "Declaration of the Zend Module Block" for details.

Kapitola 38. Calling User Functions

You can call user functions from your own modules, which is very handy when implementing callbacks; for example, for array walking, searching, or simply for event-based programs.

User functions can be called with the function **call_user_function_ex()**. It requires a hash value for the function table you want to access, a pointer to an object (if you want to call a method), the function name, return value, number of arguments, argument array, and a flag indicating whether you want to perform zval separation.

```
ZEND_API int call_user_function_ex(HashTable *function_table, zval *object,
zval *function_name, zval **retval_ptr_ptr,
int param_count, zval **params[],
int no_separation);
```

Note that you don't have to specify both `function_table` and `object`; either will do. If you want to call a method, you have to supply the object that contains this method, in which case **call_user_function()** automatically sets the function table to this object's function table. Otherwise, you only need to specify `function_table` and can set `object` to `NULL`.

Usually, the default function table is the "root" function table containing all function entries. This function table is part of the compiler globals and can be accessed using the macro `CG`. To introduce the compiler globals to your function, call the macro `TSRMLS_FETCH` once.

The function name is specified in a zval container. This might be a bit surprising at first, but is quite a logical step, since most of the time you'll accept function names as parameters from calling functions within your script, which in turn are contained in zval containers again. Thus, you only have to pass your arguments through to this function. This zval must be of type `IS_STRING`.

The next argument consists of a pointer to the return value. You don't have to allocate memory for this container; the function will do so by itself. However, you have to destroy this container (using **zval_dtor()**) afterward!

Next is the parameter count as integer and an array containing all necessary parameters. The last argument specifies whether the function should perform zval separation - this should always be set to 0. If set to 1, the function consumes less memory but fails if any of the parameters need separation.

38-1 shows a small demonstration of calling a user function. The code calls a function that's supplied to it as argument and directly passes this function's return value through as its own return value.

Note the use of the constructor and destructor calls at the end - it might not be necessary to do it this way here (since they should be separate values, the assignment might be safe), but this is bulletproof.

Příklad 38-1. Calling user functions.

```
zval **function_name;
zval *retval;

if((ZEND_NUM_ARGS() != 1) || (zend_get_parameters_ex(1, &function_name) != SUCCESS))
{
    WRONG_PARAM_COUNT;
}

if((*function_name)->type != IS_STRING)
{
    zend_error(E_ERROR, "Function requires string argument");
}

TSRMLS_FETCH();
```

```

if(call_user_function_ex(CG(function_table), NULL, *function_name, &retval, 0, NULL, 0)
{
    zend_error(E_ERROR, "Function call failed");
}

zend_printf("We have %i as type<br>", retval->type);

*return_value = *retval;
zval_copy_ctor(return_value);
zval_ptr_dtor(&retval);

<?php

dl("call_userland.so");

function test_function()
{
    print("We are in the test function!<br>");

    return("hello");
}

$return_value = call_userland("test_function");

print("Return value: \"\$return_value\"<br>");
?>

```

Kapitola 39. Initialization File Support

PHP 4 features a redesigned initialization file support. It's now possible to specify default initialization entries directly in your code, read and change these values at runtime, and create message handlers for change notifications.

To create an .ini section in your own module, use the macros `PHP_INI_BEGIN()` to mark the beginning of such a section and `PHP_INI_END()` to mark its end. In between you can use `PHP_INI_ENTRY()` to create entries.

```
PHP_INI_BEGIN()
PHP_INI_ENTRY("first_ini_entry", "has_string_value", PHP_INI_ALL, NULL)
PHP_INI_ENTRY("second_ini_entry", "2", PHP_INI_SYSTEM, OnChangeSecond)
PHP_INI_ENTRY("third_ini_entry", "xyz", PHP_INI_USER, NULL)
PHP_INI_END()
```

The `PHP_INI_ENTRY()` macro accepts four parameters: the entry name, the entry value, its change permissions, and a pointer to a change-notification handler. Both entry name and value must be specified as strings, regardless of whether they really are strings or integers.

The permissions are grouped into three sections: `PHP_INI_SYSTEM` allows a change only directly in the `php3.ini` file; `PHP_INI_USER` allows a change to be overridden by a user at runtime using additional configuration files, such as `.htaccess`; and `PHP_INI_ALL` allows changes to be made without restrictions. There's also a fourth level, `PHP_INI_PERDIR`, for which we couldn't verify its behavior yet.

The fourth parameter consists of a pointer to a change-notification handler. Whenever one of these initialization entries is changed, this handler is called. Such a handler can be declared using the `PHP_INI_MH` macro:

```
PHP_INI_MH(OnChangeSecond); // handler for ini-entry "second_ini_entry"

// specify ini-entries here

PHP_INI_MH(OnChangeSecond)
{
    zend_printf("Message caught, our ini entry has been changed to %s<br>", new_value);

    return(SUCCESS);
}
```

The new value is given to the change handler as string in the variable `new_value`. When looking at the definition of `PHP_INI_MH`, you actually have a few parameters to use:

```
#define PHP_INI_MH(name) int name/php_ini_entry *entry, char *new_value,
                               uint new_value_length, void *mh_arg1,
                               void *mh_arg2, void *mh_arg3)
```

All these definitions can be found in `php_ini.h`. Your message handler will have access to a structure that contains the full entry, the new value, its length, and three optional arguments. These optional arguments can be specified with the additional macros `PHP_INI_ENTRY1` (allowing one additional argument), `PHP_INI_ENTRY2` (allowing two additional arguments), and `PHP_INI_ENTRY3` (allowing three additional arguments).

The change-notification handlers should be used to cache initialization entries locally for faster access or to perform certain tasks that are required if a value changes. For example, if a constant

connection to a certain host is required by a module and someone changes the hostname, automatically terminate the old connection and attempt a new one.

Access to initialization entries can also be handled with the macros shown in 39-1.

Tabulka 39-1. Macros to Access Initialization Entries in PHP

Macro	Description
<code>INI_INT(name)</code>	Returns the current value of entry <code>name</code> as integer (long).
<code>INI_FLT(name)</code>	Returns the current value of entry <code>name</code> as float (double).
<code>INI_STR(name)</code>	Returns the current value of entry <code>name</code> as string. <i>Note:</i> This string is not duplicated, but instead points to the original string.
<code>INI_BOOL(name)</code>	Returns the current value of entry <code>name</code> as Boolean (defined as <code>zend_bool</code> , which currently maps to <code>int</code>).
<code>INI_ORIG_INT(name)</code>	Returns the original value of entry <code>name</code> as integer (long).
<code>INI_ORIG_FLT(name)</code>	Returns the original value of entry <code>name</code> as float (double).
<code>INI_ORIG_STR(name)</code>	Returns the original value of entry <code>name</code> as string. <i>Note:</i> This string is not duplicated, but instead points to the original string.
<code>INI_ORIG_BOOL(name)</code>	Returns the original value of entry <code>name</code> as Boolean (defined as <code>zend_bool</code> , which currently maps to <code>int</code>).

Finally, you have to introduce your initialization entries to PHP. This can be done in the module startup and shutdown functions, using the macros `REGISTER_INI_ENTRIES()` and `UNREGISTER_INI_ENTRIES()`:

```
ZEND_MINIT_FUNCTION(mymodule)
{
    REGISTER_INI_ENTRIES();
}

ZEND_MSHUTDOWN_FUNCTION(mymodule)
{
    UNREGISTER_INI_ENTRIES();
}
```

Kapitola 40. Where to Go from Here

You've learned a lot about PHP. You now know how to create dynamic loadable modules and statically linked extensions. You've learned how PHP and Zend deal with internal storage of variables and how you can create and access these variables. You know quite a set of tool functions that do a lot of routine tasks such as printing informational texts, automatically introducing variables to the symbol table, and so on.

Even though this chapter often had a mostly "referential" character, we hope that it gave you insight on how to start writing your own extensions. For the sake of space, we had to leave out a lot; we suggest that you take the time to study the header files and some modules (especially the ones in the `ext/standard` directory and the MySQL module, as these implement commonly known functionality). This will give you an idea of how other people have used the API functions - particularly those that didn't make it into this chapter.

Kapitola 41. Reference: Some Configuration Macros

config.m4

The file `config.m4` is processed by `buildconf` and must contain all the instructions to be executed during configuration. For example, these can include tests for required external files, such as header files, libraries, and so on. PHP defines a set of macros that can be used in this process, the most useful of which are described in 41-1.

Tabulka 41-1. M4 Macros for `config.m4`

Macro	Description
<code>AC_MSG_CHECKING(message)</code>	Prints a "checking <message>" message.
<code>AC_MSG_RESULT(value)</code>	Gives the result to <code>AC_MSG_CHECKING</code> .
<code>AC_MSG_ERROR(message)</code>	Prints message as error and stops the configuration process.
<code>AC_DEFINE(name,value,description)</code>	Adds <code>#define</code> to <code>php_config.h</code> .
<code>AC_ADD_INCLUDE(path)</code>	Adds a compiler include path.
<code>AC_ADD_LIBRARY_WITH_PATH(libraryname,librarypath)</code>	Specifies an additional library.
<code>AC_ARG_WITH(modulename,description,unconditionaltest,conditionaltest)</code>	Quite a powerful macro, see the manual.
<code>PHP_EXTENSION(modulename, [shared])</code>	This macro is a <i>must</i> to call.

Kapitola 42. API Macros

A set of macros was introduced into Zend's API that simplify access to zval containers (see 42-1).

Tabulka 42-1. API Macros for Accessing zval Containers

Macro	Refers to
Z_LVAL(zval)	(zval).value.lval
Z_DVAL(zval)	(zval).value.dval
Z_STRVAL(zval)	(zval).value.str.val
Z_STRLEN(zval)	(zval).value.str.len
Z_ARRVAL(zval)	(zval).value.ht
Z_LVAL_P(zval)	(*zval).value.lval
Z_DVAL_P(zval)	(*zval).value.dval
Z_STRVAL_P(zval_p)	(*zval).value.str.val
Z_STRLEN_P(zval_p)	(*zval).value.str.len
Z_ARRVAL_P(zval_p)	(*zval).value.ht
Z_LVAL_PP(zval_pp)	(**zval).value.lval
Z_DVAL_PP(zval_pp)	(**zval).value.dval
Z_STRVAL_PP(zval_pp)	(**zval).value.str.val
Z_STRLEN_PP(zval_pp)	(**zval).value.str.len
Z_ARRVAL_PP(zval_pp)	(**zval).value.ht

Část VI. FAQ: Často zodpovídané otázky

Kapitola 43. Obecné informace

Tato sekce se zabývá obecnými otázkami okolo PHP: co to je a co to dělá.

1. Co je to PHP?

Z předśádky manuálu:

PHP je skriptovací jazyk vkládaný do HTML. Mnoho jeho syntaxe je vypůjčeno z C, Javy a Perlu s několika přidanými prostředky specifickými pro PHP. Cílem jazyka je umožnit vývojářům webů rychleji psát dynamicky generované stránky.

Milý úvod do PHP od Stiga Sæther Bakkena najdete tady (<http://www.zend.com/zend/art/intro.php>) na stránkách Zendu. Volně k dispozici je také mnoho materiálů PHP konference (<http://conf.php.net/>).

2. Co znamená zkratka PHP?

PHP je zkratka pro *PHP: Hypertext Preprocessor*. Mnoho lidí může mást, že první slovo akronymu je také akronym. Tomuto typu zkratk se říká rekurzívní akronym. Zvědavci mohou navštívit Free On-Line Dictionary of Computing (<http://www.foldoc.org/>), kde najdou více informací o rekurzívních akronymech.

3. Jaký je vztah mezi verzemi?

PHP/FI 2.0 je časná a již nepodporovaná verze PHP. PHP 3 je následník PHP/FI 2.0 a je mnohem lepší. PHP 4 je zatím poslední generací PHP a má pod kapotou Zend engine (<http://www.zend.com/>).

4. Mohu současně pouštět více verzí PHP?

Ano. Podívejte se do souboru `INSTALL`, který je přiložen k distribuci zdrojových souborů PHP 4. Přečtěte si i příslušný dodatek.

5. Jaké jsou rozdíly mezi PHP 3 a PHP 4?

Existuje několik článků (<http://www.zend.com/zend/art/>), které o tom napsali autoři PHP 4. Tady je seznam některých důležitějších nových prvků:

- Rozšířený API modul
- Zobecněný sestavovací (kompilační) proces pod UNIXem
- Generické rozhraní pro WWW servery, které podporuje také multithreadové servery
- Vylepšený zvýrazňovač syntaxe
- Nativní podpora HTTP sessions
- Podpora výstupního buffering
- Silnější konfigurační systém
- Reference counting

Podívejte se laskavě na What's new in PHP 4 overview (<http://www.zend.com/zend/whats-new.php>), kde najdete detailní vysvětlení těchto prvků a ještě mnohem víc. Pokud přecházíte z PHP 3 na PHP 4, přečtěte si také příslušný dodatek.

6. Myslím, že jsem našel chybu! Komu to mám říct?

Měli byste navštívit databázi chyb (PHP Bug Database) a ujistit se, zda nalezená chyba již není v seznamu známých chyb. Pokud ji tam nenajdete, použijte formulář pro ohlašování chyb. Je důležité použít databázi chyb namísto posílání zprávy do distribučního seznamu, protože chyba bude mít

přirazeno své číslo a bude potom možné, abyste se sem později vrátili a zkontrolovali stav chyby. Chybovou databázi najdete na <http://bugs.php.net/>.

Kapitola 44. E-mailové konference (mailing lists)

Tato část se zabývá záležitostmi o tom, jak můžete navázat kontakt s PHP komunitou. Nejlepším způsobem jsou e-mailové konference.

Pozn. překladatele: Čeština nemá adekvátní termín pro "mailing list". Protože se běžně používá termínů "e-mailová konference" nebo "konference", budu je používat i zde, i když to není úplně nejlepší řešení.

1. Existují nějaké e-mailové konference pro PHP?

Samozřejmě! Je mnoho konferencí pro různé záležitosti. Kompletní seznam těchto konferencí můžete najít na naší stránce Podpora (<http://www.php.net/support.php>).

Většina konferencí patří do třídy `php-general`, tedy obecné záležitosti PHP. K přihlášení pošlete zprávu na `php-general-subscribe@lists.php.net` (<mailto:php-general-subscribe@lists.php.net>). Do předmětu zprávy ani jejího těla nemusíte vkládat nic speciálního. Odhlásíte se posláním zprávy na `php-general-unsubscribe@lists.php.net` (<mailto:php-general-unsubscribe@lists.php.net>).

Přihlásit nebo odhlásit se můžete také pomocí rozhraní na webu na stránce Podpora (<http://www.php.net/support.php>).

2. Existují ještě jiné komunity?

Je jich nespočetně po celém světě. Máme např. odkazy na některé IRC servery a konference v cizích jazycích - na stránce Podpora (<http://www.php.net/support.php>).

3. Pomoc! Nedaří se mi přihlásit/odhlásit se do/z konference!

Pokud máte problémy s přihlašováním nebo odhlašováním konference `php-general`, může to být proto, že její software nemůže vyhodnotit správnou e-mailovou adresu k použití. Pokud by vaše adresa byla `joebow@example.com`, můžete poslat přihlašovací požadavek na `php-general-subscribe-joebow@example.com@lists.php.net`, resp. odhlašovací na `php-general-unsubscribe-joebow@example.com@lists.php.net`. Pro ostatní konference použijte obdobné adresy.

4. Existuje někde archiv konferencí?

Ano, seznam archivů najdete na stránce Podpora (<http://www.php.net/support.php>). Příspěvky do konferencí se archivují také jako zprávy služby news (protokol NNTP). Server této služby je k dispozici na `news://news.php.net/`. Existuje také experimentální webovské rozhraní pro news server na <http://news.php.net/>

5. Na co se mohu ptát v konferenci?

Jak je PHP den ze dne stále populárnější, provoz v konferenci `php-general` narůstal a nyní přichází 150-200 příspěvků denně. Kvůli tomu je v zájmu každého, aby používal tuto konferenci až jako poslední možnost poté, co hledal všude jinde.

Než něco pošlete do konference, podívejte se prosím do FAQ a do manuálu, zda nemůžete najít odpověď tam. Pokud ji nenajdete, prohlédněte si archivy konferencí (viz výše). Když máte problémy s instalací nebo konfigurací PHP, přečtěte si prosím všechnu přiloženou dokumentaci a soubory README. Pokud stále nemůžete najít nic, co by vám pomohlo, jste více než vítáni v konferenci.

6. Jaké informace mám přiložit k příspěvku do konference?

Příspěvky jako "PHP mi nechce fungovat! Pomozte mi! Co mám špatně?" jsou absolutně k ničemu. Pokud máte problémy se spouštěním a během PHP, musíte napsat, na jakém operačním systému ho

spouštíte, o kterou verzi PHP se jedná, jak jste ji získali (předkompilovaný balík, CVS, RPM apod.), co jste s ním udělali, kde to uvázlo, a přesnou chybovou zprávu.

To platí úplně stejně i pro jiné problémy. Měli byste přiložit informace o tom, co jste dělali, kde to uvázlo, co jste s tím zkoušeli dělat a, pokud to lze, přesnou chybovou zprávu. Máte-li problémy se zdrojovým kódem, je třeba přiložit ten kus kódu, který nepracuje. Nepřikládejte více kódu, než je třeba! Příspěvek by byl hůře čitelný a mnoho lidí by ho kvůli tomu přeskočilo. Pokud si nejste jisti, kolik informací máte přiložit do zprávy, je lépe přidat více než méně.

Jinou důležitou věcí, kterou je třeba mít na paměti, je sumarizace problému v předmětu zprávy. Předmět typu "POMOZTEEE! nebo "Co je to za problém?" bude většina čtenářů ignorovat.

Kapitola 45. Získání PHP