

New Technical Notes

Macintosh



Developer Support

Owned Resource Shortcuts

Toolbox

Revised by:
Written by: Bryan Stearns

March 1988
May 1986

To allow the Font/DA Mover to renumber desk accessories as needed when moving them between system files, desk accessories should use the “owned resource” protocol described in the Resource Manager chapter of *Inside Macintosh Volume I*.

All resource IDs in a desk accessory should be zero-based. At runtime, a routine can be called to find the current “base” value to add to a resource’s zero-based value to get the actual current ID of that resource. Then, when a resource is needed, its zero-based value can be added to the resource base value, giving the actual resource ID to be used in future Resource Manager calls.

Here’s the source to a handy routine to get the resource base value, GetResBase:

```
;FUNCTION GetResBase(driverNumber: INTEGER): INTEGER;  
;  
;GetResBase takes the driver number and returns the ID  
;of the first resource owned by that driver. This is  
;according to the private resource numbering convention  
;documented in the Resource Manager.  
  
GetResBase      FUNC  
  
    MOVE.L (SP)+,A0      ; Get return address  
    MOVE.W (SP)+,D0      ; Get driver number  
    NOT.W D0             ; Change to unit number  
    ASL.W #5,D0          ; Move it over in the word  
    ORI.W #$C000,D0      ; Add the magic bits  
    MOVE.W D0,(SP)       ; Return function result  
    JMP      (A0)         ; and return  
  
END
```

Further Reference:

- The Resource Manager
- M.PT.FontDAMover