ODBC Desktop Database Drivers--What's New

This Help file describes additions and changes made to the ODBC Desktop Database Drivers for version 2.0. These drivers include the Microsoft Access driver, the Btrieve driver, the dBASE driver, the Microsoft Excel driver, the Microsoft FoxPro driver, the Paradox driver, and the Text driver. When a change applies to one or more drivers, but not all drivers, the name of each applicable driver is shown in bold. When text has been deleted from the Help file, but for clarity is retained in this changes file, the text has been placed in brackets preceded by DELETED:.

Added Features

The following specific features have been added to the ODBC Desktop Database Drivers for version 2.0.

Architecture Changes/ Addition of Native 32-Bit Drivers

<u>Overview</u> <u>Driver ISAMs</u> <u>Hardware and Software Requirements</u>

New Data Sources

Access 2.0 Excel 5 FoxPro 2.6 Paradox 4.X Driver ISAMs

Scrollable Cursors

ODBC API Functions Affecting Cursor Support SQLGetInfo Return Values Affecting Cursor Support Positioned UPDATE and DELETE Operations

Heterogeneous Joins/Attached Table Support (Microsoft Access Driver)

Supported.

Updatable Joins

Supported. (For more information on updatable joins, see the documentation for your database management system.)

Transaction Support (Microsoft Access Driver)

API Functions Affecting Transaction Support

Procedure Invocation (Microsoft Access Driver)

CALL Statement

General Changes

The following topics show general changes made to the ODBC Desktop Database Drivers for version 2.0.

Setup Changes

Setup Options <u>ODBC Setup Dialog Box</u> <u>Data Source Conversion</u> <u>Connecting to a Data Source</u> <u>Repairing a Database (Microsoft Access)</u> <u>Compacting a Database (Microsoft Access)</u> Dynamic Changes to Data Sources <u>Adding, Modifying, and Deleting a Data Source</u> Text Format (Text Driver) <u>Define Text Format Dialog Box</u> <u>SCHEMA.INI</u>

ODBC SQL Grammar Changes SQL Statements

SQLGetInfo Changes SQLGetInfo Return Values

API Function Changes API Functions (Programming)

Data Type Changes Data Types

Error Message Changes Error Messages

Implementation Issue Changes Implementation Issues

Overview


The ODBC Desktop Database Drivers allow you to open and query a database through the Open Database Connectivity (ODBC) interface.

The application/driver architecture for Win16/Win32s applications is:

Application (16-bit) Application (32-bit) 32-Bit Thunking Driver Manager (ODBC32.DLL) ODBC Universal Thunking DLL (ODBC16UT.DLL) **ODBC** Driver Manager (ODBC.DLL) ODBC Desktop Database Driver (ODBCJT16.DLL, MSAJT200.DLL, <u>16-bit Driver ISAM</u>))

database

The application/driver architecture for Win32 applications is:



Driver ISAMs

The ODBC Desktop Database Driver ISAMs are as follows:

| Driver | 16-bit ISAM | 32-bit ISAM | Applicability |
|------------------|------------------------------------|---------------------------------------|---|
| Microsoft Access | None (Included in MSAJT200.DLL) | None (Included in MSJT2032.DLL) | Microsoft Access versions 1.0, 1.1, 2.0 |
| Btrieve | BTRV200.DLL | not available | Btrieve versions 5.1 and 6.x |
| dBase | XBS200.DLL | MSXB2032.DLL dBase versions and IV | |
| Microsoft Excel | MSXL2016.DLL | MSXL2032.DLL | Microsoft Excel versions 3.0, 4.0, 5.0 (For versions earlier than 3.0, see note below) |
| Microsoft FoxPro | XBS200.DLL | MSXB2032.DLL | Microsoft FoxPro versions 2.0, 2.5, 2.6 |
| Paradox | PDX200.DLL | MSPX2032.DLL | Paradox versions 3.5, 4.0, 4.5 |
| Text | MSTX2016.DLL | MSTX2032.DLL | ASCII Text |

Note The Microsoft Excel driver is not able to read Microsoft Excel files whose format is earlier than version 3.0. These files can be opened in a later release of Microsoft Excel and saved in version 3, 4, or 5 format that the driver is able to read.

Hardware and Software Requirements Hardware Requirements

To use the ODBC Desktop Database Drivers, you must have:

• An IBM-compatible personal computer with an 80386 or higher processor and a VGA or higher-resolution graphics card.

- A hard disk with 6MB of free disk space for 16-bit or 32-bit drivers.
- At least 4MB of random-access memory (RAM).

Software Requirements

To access data with the ODBC driver, you must have:

- The ODBC driver.
- The ODBC Driver Manager 2.0 (16-bit ODBC.DLL or 32-bit ODBC32.DLL).
- A computer running MS-DOS 3.3 or later. (MS-DOS 5.0 or later is recommended.)

Microsoft Windows 3.1 or later to install and run 16-bit drivers, or Microsoft Windows
 NT 3.5 or later to install and run 32-bit drivers. (Note that 32-bit applications can be run on

Win32s, and that 16-bit applications can be run on Windows on Windows (WOW) on Windows NT.)

 The stack size for an application using a Microsoft ODBC driver should be at least 20K.

When using Microsoft Windows NT 3.5 or later, the 32-bit driver is thread-safe, but only through the use of a global semaphore that controls access to the driver. Concurrent use of the driver will be very limited under Windows NT.

When running multiple 16-bit applications on Windows on Windows, the applications must be run in separate memory spaces. (The same memory space cannot be used because ODBC does not support multiple environments in the same process.) To run an application in a separate memory space, highlight the application's icon in the Microsoft Windows NT Program Manager, choose the File-Properties command, then choose Run in Separate Memory Space.

Data Source Conversion

If a version 2.0 driver replaces an installed version 1.0 driver, existing data sources associated with the version 1.0 driver will need to be converted before they can be used with the new driver. (Data sources to be converted can be either those associated with ODBC version 1.0 drivers, or those associated with the ODBC version 2.0 driver ODBCJT16.DLL, which was used with Microsoft Access 2.0 data sources.) This process converts all data source names (DSNs) associated with the version 1.0 driver to version 2.0 DSNs.

For Windows 3.1 or later, the keywords in the ODBC.INI files are changed. The ODBCINST.INI and ODBCISAM.INI files are also changed. For the **Microsoft Access 2.0** driver, the name of the setup DLL in ODBCINST.INI is also changed.

If you choose to install only 32-bit components, the data sources will be converted to 32-bit data sources; otherwise, the data sources will be converted to 16-bit data sources.

Converting to Version 2.0 DSNs

Data source conversion is performed when you run driver setup. For each new driver installed for which a version 1.0 driver was previously installed, you will be asked whether you want to convert the existing data sources associated with that driver. If so, choose Yes, and the conversion will be performed automatically.

When the **Text** driver is used, all converted Text DSNs will be given the same default format as the last converted DSN.

Reverting to Version 1.0 DSNs

On Windows 3.1 or later, data sources can be converted back to version 1.0. During the original conversion process, ODBC.INI, ODBCINST.INI, and ODBCISAM.INI are not deleted, but are renamed with .BAK extensions. If there are any versions of these files with BAK extensions, they are renamed with BA1 extensions; BA1 files are renamed BA2; and so on. To convert back to version 1.0, rename ODBC.BAK, ODBCINST.BAK, and ODBCISAM.BAK with INI extensions; and rename BA1, BA2, etc., back one level.

Adding, Modifying, and Deleting a Data Source

Note When the dBASE or Microsoft FoxPro driver is used, changes in the data source (DSN) setup for either driver will affect the DSN setup of the other driver. Changes to the dBASE DSN setup will change the Microsoft FoxPro DSN setup, and vice versa.

To add, modify, or delete a data source dynamically

You can call the <u>SQLConfigDataSource</u> API function to add, modify, or delete a data source dynamically. This function uses keywords to set connect options that are also set through the Setup dialog box. This function should be used when you want to add, modify, or delete a data source without displaying the Setup dialog box.

ODBC Setup Dialog Box

The ODBC Setup dialog box contains the following changed fields:

| Control | Description |
|--------------------|--|
| Collating Sequence | (This control is displayed only for the Btrieve, dBASE, Microsoft FoxPro, or Paradox driver.) |
| | The sequence in which the fields are sorted. |
| | When the Btrieve, dBASE, or Microsoft FoxPro driver is used, the sequence can be: ASCII or International. |
| | When the Paradox driver is used, the sequence can be: ASCII, International, Swedish-Finnish, or Norwegian-Danish. |
| Database | (This control is displayed only for the Microsoft Access driver.) |
| | The full path of the Microsoft Access database you want to access. Use the <u>Select</u> button to select an existing database. Use the <u>Create</u> button to create and select a new Microsoft Access database. |
| | A Microsoft Access data source can be set up without selecting or creating a database. If no database is provided upon setup, the user will be prompted to choose a database file when connecting to the data source. |
| | Use the <u>Repair</u> button to repair a damaged database. Use the <u>Compact</u> button to compact a database. |
| Define Format | (This control is displayed only for the Text driver.) |
| | Displays the <u>Define Text Format dialog box</u> and enables you to specify the <u>schema</u> for individual tables in the data source directory. |
| Directory | Displays the currently selected directory. (This does not apply to the Microsoft Access driver.) |
| | For Microsoft Excel 3.0/4.0 files, the path display is labeled "Directory", while for Microsoft Excel 5.0 files, the path display is labeled "Workbook". |
| Read Only | Designates the database as read-only. |
| Rows to Scan | (This control is displayed only for the Microsoft Excel or Text driver.) |
| | The number of rows to scan to determine the data type of each column. The data type is determined given the maximum number of kinds of data found. If data is encountered that does not match the data type guessed for the column, the data type will be returned as a NULL value. |
| | For the Microsoft Excel driver, you may enter a number from 1 to 16 for the rows to scan; however, the value will always default to 1. (A number outside the limit will return an error.) |
| | For the Text driver, you may enter a number from 1 to 32767 for the number of rows to scan; however, the value will always default to 1. (A number outside the limit will return an error.) |
| Select Directory | Displays a dialog box where you can select a directory |
| | |

| | containing the files you want to access. For Microsoft Excel 3.0/4.0 files, the path selection button is labeled "Select Directory", while for Microsoft Excel 5.0 files, the path selection button is labeled "Select Workbook". |
|-----------------|---|
| Sort Order | (This control is displayed only for the Microsoft Access driver.) |
| | Sets a default sort order for the database. Can be: |
| | General (English,French,German,Portuguese,Italian), Spanish, Dutch, Swedish/Finnish, Norwegian/Danish, Icelandic, Czech, Hungarian, Polish, Russian, Turkish, Arabic, Hebrew, Greek. |
| System Database | (This control is displayed only for the Microsoft Access driver.) |
| | The full path of the Microsoft Access <u>system database</u> to be used with the Microsoft Access database you want to access. |
| | Select the None option button if no system database will be used. |
| Version | Enables you to select the version of the files used. |
| Workbook | For Microsoft Excel 5.0 files, displays the currently selected workbook. Before you add the data source, you must use the Select Workbook button to select a directory. |
| | Worksheets within workbooks are treated as SYSTEM TABLES. Defined or named ranges within a worksheet are treated as TABLES. |

System Database

Select the System Database option button to select the system database to be used. The ODBC Microsoft Access driver prompts the user for a name and password. The default name is Admin and the default password in Microsoft Access for the Admin user is an empty string.

To increase the security of your Microsoft Access database, create a new user to replace the Admin user and delete the Admin user, or change the objects to which the Admin user has access.

Select the None option button to log into the Microsoft Access database as the Admin user; no system database will be used.

For more information about system databases and the Admin user, see the Microsoft Access documentation.

Select Directory

When defining a data source directory (for all drivers except **Microsoft Access**), specify the directory where your most commonly used files are located. The ODBC driver uses this directory as the default directory. Copy other files into this directory if they are used frequently. Alternatively, you can qualify filenames in a SELECT statement with the directory name:

SELECT * FROM C:\MYDIR\EMP

Or, you can specify a new default directory by using the **SQLSetConnectOption** function with the SQL_CURRENT_QUALIFIER option.

Paths for Additional Directories (Btrieve)

If you want to open Btrieve data files in directories other than the default, list these directories by the XTRPATH variable; for example, XTRPATH = path [; path [; path]]. This variable can be set in either of the following ways:

 Use the SET command in the AUTOEXEC.BAT file. For example, SET XTRPATH = C:\ BTRIEVE\DATA; F:\DATA.

• Use the Btrieve environment (.ENV) file. For other applications to recognize the Btrieve environment file, the file's path and filename must be specified by setting the XTRENV variable in the AUTOEXEC.BAT file (using the SET command).

The path for additional Btrieve directories can also be set in the application's initialization file. With the Microsoft Access application, for instance, the XTRPATH variable can be set in the [Btrieve ISAM] section of the ODBCDDP.INI file. If specifying the path in the Btrieve environment (.ENV) file, the path and filename of the environment file can be set in the MSACC20.INI file, rather than in AUTOEXEC.BAT.

Directory/Workbook Path Displays (Microsoft Excel)

For Microsoft Excel 3.0/4.0 files, the path display is labeled "Directory", and the path selection button is labeled "Select Directory". For Microsoft Excel 5.0 files, the path display is labeled "Workbook", and the path selection button is labeled "Select Workbook". When defining a data source directory, specify the directory where your most commonly used Microsoft Excel files are located for Microsoft Excel 3/4, or the directory where the workbook file is located for Microsoft Excel 5. The Use Current Directory control is deleted for Microsoft Excel 5.0.

Define Text Format

When the **Text** driver is used, the Define Text Format dialog box enables you to define the format for columns in a selected file. This dialog box enables you to specify the <u>schema</u> for each data table. This information is written to a <u>SCHEMA.INI</u> file in the data source directory. A separate SCHEMA.INI is created for each text data source directory.

Note The same default file format applies to all new text data tables. All files created by the CREATE TABLE statement inherit those same default format values, which are set by selecting file format values in the Define Text Format dialog box with <default> chosen in the Tables list box.

| Sectio | n | Information |
|----------------|-------------|--|
| Charao | cters | ANSI or OEM. OEM specifies a non-ANSI character set. |
| Colum Heade | n Name r | Indicates whether the columns of the first row of the selected table are to be used as column names. Either TRUE or FALSE. |
| Colum | ns | Contains a list of the column names for each column in the selected table. The order of the columns reflects the order of the columns in the table. |
| Data T | ӯре | Can be Char, Date, Float, or Integer. Date data types can be in the following formats: "dd-mmm-yy", "mm-dd-yy", "mmm-dd-yy", "yyyy-mm-dd", or "yyyy- mmm-dd". "mm" denotes numbers for months; "mmm" denotes letters for months. |
| Delimi | ter | Specifies the custom delimiter character to be used to separate columns. Enabled when the "Custom Delimiter" format is selected. Double quotations marks (") cannot be used as the delimiter character. (Note that the delimiter cannot be specified in hexadecimal or decimal format.) |
| Forma | t | Either delimited or fixed length. If delimited, indicates the type of delimiter used: comma (CSV), tab, or special character (custom). If Format is fixed-length and Column Name Header is TRUE, the first line must be comma-delimited. |
| Guess | | Automatically generates the column's data type, name, and width values for the columns in the selected table by scanning the table's contents according to the Format list box selection. Enabled when the table format is delimited. Any previously defined columns in the Columns list are cleared and replaced with new entries. If Column Name Header is not checked, column names are generated |

| Name | automatically as "F1", "F2", and so on. Note that no default value is shown in the Data Type box. Displays the name of the selected column. May be used to specify a new column name for either an existing column or a new column. |
|--------------|---|
| Rows to Scan | If Column Name Header is TRUE, the column name displayed is ignored. The number of rows that Setup or the driver will scan when setting the columns and column data types based upon existing data. |
| | You may enter a number from 1 to 32767 for the number of rows to scan; however, the value will always default to 1. (A number outside the limit will return an error.) |
| Tables | Contains a list of all files in the directory selected in the Text Setup dialog box that match the list of extensions specified. |
| Width | Selecting <default> sets the table attributes for all files in the specified directory that are not explicitly defined. When <default> is selected, the "Columns" group is disabled. The width of the column may be changed for Char columns. For other data types, the width is displayed but cannot be changed.</default></default> |

schema

The schema includes information about each table (text file) in a data source, including the table's format, the number of rows to scan to determine column types, whether the first row of the table contains column names, whether the source file is written using an OEM or ANSI codepage, and each column's name, data type, and width.

SCHEMA.INI File

When the **Text** driver is used, the SCHEMA.INI file in the data source directory contains format information for the source text files. This information is used to specify text file format at data source setup time. Each text data directory has a separate SCHEMA.INI file. File format information entered in the Define Text Format dialog box is written to the SCHEMA.INI file, which is automatically created for this purpose.

Note The same default file format applies to all new text data tables. All files created by the CREATE TABLE statement inherit those same default format values, which are set by selecting file format values in the Define Text Format dialog box with <default> chosen in the Tables list box.

| Section | Information |
|----------------|--|
| ColNameHeader | Indicates whether the first record of data will specify the column names. Either TRUE or FALSE. |
| Format | Can be FIXEDLENGTH, TABDELIMITED, CSVDELIMITED (by a comma), or DELIMITED() (by the special character specified in the parentheses). The special character is one character in length and can be in character, decimal, or hexadecimal format. If Format is FIXEDLENGTH and ColNameHeader is TRUE, the first line |
| MaxScanRows | must be comma-delimited. The number of rows to be scanned when setting a column's data type based upon existing data. |
| | You may enter a number from 1 to 32767 for the number of rows to scan; however, the value will always default to 1. (A number outside the limit will return an error.) |
| Character Set | OEM or ANSI. |
| DateTimeFormat | Indicates date and time format. Entered as a string. Should be specified if all datetime fields in the SCHEMA.INI file will be handled with the same format. If this entry is absent, the short date picture and time options in the control panel will be used. |
| CurrencySymbol | Indicates the currency symbol to be used for currency values in the text file. If this entry is absent, the value in the control panel will be used. |
| CurrencyFormat | Indicates the format for the currency symbol and value. Can be "0" (currency symbol prefix with no separation, such as \$1), "1" (currency symbol suffix with no separation, such as 1\$), "2" (currency symbol prefix with one-character separation, such as \$ 1), or "3" (currency symbol suffix with one- character separation, such as 1 \$). |

File formats in SCHEMA.INI have the following sections:

| CurrencyDigits | Indicates the number of digits used for the fractional part of a currency amount. |
|----------------------------|---|
| CurrencyNegative Format | Indicates placement of the minus sign in currency format. Can be \$1, -\$1, \$-1, \$1-, \$1, 1\$, -\$ 1, 1\$, -\$ 1, 1 \$-, \$ 1-, \$ -1, 1- \$, \$1, or 1 \$. |
| DecimalSymbol | Can be any single character used to separate the integer from the fractional part of a number. |
| NumberDigits | Indicates the number of decimal digits in the fractional portion of a number. |
| NumberLeading Zeros | Indicates whether a decimal value less than 1 and greater than -1 should contain leading zeros. Can be either "0" (no leading zeros) or "1". |
| Col1, Col2, | Column names, types, and width. If ColNameHeader is TRUE, the column names listed here are ignored. |

Connecting to a Data Source

Password Entry

Passwords must be entered at connection time, either by password in the connection string (UID and PWD for **Microsoft Access** or PWD for **Paradox**), or with the *szAuthStr* argument in the **SQLConnect** function.

Password-Protected Files

When the Paradox driver is used, after a password-protected file has been opened by a user, other users are not allowed to open the same file.

Heterogeneous Joins/Attached Tables

When the Microsoft Access driver is used, attached tables and heterogeneous joins are supported.

Opening Microsoft Excel Tables

The Microsoft Excel driver is not able to read Microsoft Excel files whose format is earlier than version 3.0. These files can be opened in a later release of Microsoft Excel and saved in version 3, 4, or 5 format that the driver is able to read.

Microsoft Excel 3 (BIFF3) and Microsoft Excel 4 (BIFF4) file formats must have a database range defined. The Microsoft Excel driver recognizes named ranges as tables. Databases specified by a named range will increase as new data is added. If any new data would overwrite existing data in a worksheet (outside the named range that represents the data), an error will be returned.

All Microsoft Excel tables (spreadsheets) that are created and opened for inserting are opened exclusive, and can be opened by only one user at a time. Otherwise, Microsoft Excel tables are opened shared. "Read Only" allows multiple users to view .XLS files.

Referential Integrity

Referential integrity is supported only for a **Microsoft Access** data source, and only if the referential integrity is set up for the data source by the **Microsoft Access** database management system.

Select Database (Advanced)

When the **Microsoft Access** driver is used, the Select button may be pressed in the Microsoft Access 2.0 Setup dialog box to select an existing database.

The Open Database dialog box contains the following fields:

| Control | Description |
|-----------|--|
| File Name | Name of the existing database file with an .MDB extension. |
| Exclusive | If the Exclusive box is selected, the database will be opened in Exclusive mode and can be accessed by only one user at a time. If the Exclusive box is cleared, the database will be opened in Shared mode and can be accessed by more than one user at a time. Performance is enhanced when running in Exclusive mode. |
| Read Only | Designates the database as read-only. |

Create Database (Advanced)

When the **Microsoft Access** driver is used, the Create button may be pressed in the Microsoft Access 2.0 Setup dialog box to create a new database.

The New Database dialog box contains the following fields:

| Control | Description |
|------------|--|
| File Name | Name of the database file with an .MDB extension. |
| Exclusive | If the Exclusive box is selected, the database will be opened in Exclusive mode and can be accessed by only one user at a time. If the Exclusive box is cleared, the database will be opened in Shared mode and can be accessed by more than one user at a time. Performance is enhanced when running in Exclusive mode. |
| Sort Order | Sets a default sort order for the database. Can be: |
| | General (English,French,German,Portuguese,Italian), Spanish, Dutch, Swedish/Finnish, Norwegian/Danish, Icelandic, Czech, Hungarian, Polish, Russian, Turkish, Arabic, Hebrew, Greek. |

Database Repair (Advanced)

When the **Microsoft Access** driver is used, if a client failure occurs during the commit process (after **SQLTransact** has been issued, but before the function returns), the affected database can be corrupted and need to be repaired. Repair can be performed either upon setup through the Microsoft Access driver setup dialog box, or programmatically by using the **SQLConfigDataSource** function.

To repair the database through the Microsoft Access driver setup dialog box, click the Repair button. Select the file and path, and then click OK.

To repair the database programmatically, include "REPAIR_DB=<path name>" in the list of attributes (*lpszAttributes*) of the **SQLConfigDataSource** function. In this function, <path name> is the full path to the Microsoft Access database.

When repairing a password-protected file, a password and user id must be entered in the advanced options dialog box (or in the list of attributes for **SQLConfigDataSource**, if repairing programmatically). The password and user id should be removed after the repair.

These operations will run the standard Microsoft Access repair process on the database. Data in Microsoft Access databases could be affected by either of these actions.

Note that a database indicated as corrupted may in fact not be corrupted. The indication may be prompted by an improper shutdown that does not clear the appropriate bits. In this and other cases, a programmer may want to keep the corruption message box transparent to the end user. This can be accomplished by passing SQL_DRIVER_NOPROMPT with the SQLDriverConnect function.

For more information about database repair in Microsoft Access, refer to the Microsoft Access help file.

Database Compaction (Advanced)

When the **Microsoft Access** driver is used, data compaction can be performed on a database file either upon setup through the Microsoft Access driver setup dialog box, or programmatically by using the **SQLConfigDataSource** function.

To perform data compaction on a database file through the Microsoft Access driver setup dialog box, click the Compact button. From the Database to Compact From dialog box, select the file and path, and then click OK. From the Database to Compact Into dialog box, select the file and path, and a sort order, and then click OK. The name of the file to compact into can be the same as the file to be compacted.

To perform data compaction on a database file programmatically, include "COMPACT_DB=<source db> <dest db> <sort order>" in the list of attributes (*lpszAttributes*) of the **SQLConfigDataSource** function. In this function, <source db> is the full path to the Microsoft Access database to be compacted and <dest db> is the full path for the compacted Microsoft Access database.

When compacting a password-protected file, a password and user id must be entered in the advanced options dialog box (or in the list of attributes for **SQLConfigDataSource**, if compacting programmatically). The password and user id should be removed after the compaction.

These operations will run the standard Microsoft Access compaction process on the database.

For more information about database compaction in Microsoft Access, refer to the Microsoft Access help file.

SQL Statements (Advanced)

For information about changes to SQL grammar, see the following topics: For Advanced Users Addition

- Additional Supported ODBC SQL Grammar
- 2 Driver-Specific SQL Grammar

2

Limitations to SQL Grammar

Positioned UPDATE and DELETE Operations

When the **Microsoft Access, Btrieve, dBASE, Microsoft FoxPro,** or **Paradox** driver is used, positioned UPDATE and DELETE operations are supported through the **SQLSetPos** function. The WHERE CURRENT OF syntax is not supported.

Procedure Invocation (Microsoft Access)

When the **Microsoft Access** driver is used, procedures can be invoked from the driver by using the **SQLExecDirect** or **SQLPrepare** function with the following syntax: {CALL *procedure-name* [(*parameter*[,*parameter*]...)]}. Note that expressions and constants are not supported as parameters to a called procedure.

Additional Supported ODBC SQL Grammar (Advanced)

The ODBC Desktop Database Drivers completely support the following additional SQL statements and clauses in the Core and Extended ODBC grammar, as changed for the Desktop Database Drivers version 2.0:

| Core and Extended grammar | Comments |
|---|---|
| ALTER TABLE statement (Core) | When the Microsoft Access, Btrieve, dBASE, Microsoft FoxPro, or Paradox driver is used, the ALTER TABLE statement is supported with add and drop table constraint definition clauses. (ALTER TABLE statements are not supported for Microsoft Excel and Text drivers.) |
| Binary Literals (Extended) | Supported. |
| EXISTS predicate (Core) | Supported. |
| Procedure Invocation (Extended) | When the Microsoft Access driver is used, procedures can be invoked from the driver by using the SQLExecDirect or SQLPrepare function with the following syntax: {CALL procedure- name [(parameter[,parameter])]}. Note that expressions are not supported as parameters to a called procedure. If a procedure name includes a dash, the name must be delimited with backquotes (`). |
| SELECT statement (Extended) (including GROUP BY, HAVING, and UNION clauses) | Supported. |
| Subqueries (SUBSELECTs) (Core) | Supported. |

Driver-Specific SQL Grammar Supported (Advanced)

The Microsoft ODBC drivers support the following driver-specific SQL grammar changes, as changed for the Desktop Database Drivers version 2.0:

| Driver-specific SQL grammar | Comments |
|-----------------------------|--|
| COUNT(expression) | Counts all non-NULL values for an expression across a predicate. This function behaves like other set functions, such as SUM, AVG, MIN, and MAX. For example: |
| | SELECT COUNT(A+B) FROM Q |
| | counts all the rows in Q where A+B does not equal NULL. |
| | When the Paradox driver is used, the COUNT function includes NULL as well as non-NULL values in the count. |
| CREATE INDEX | The syntax of the CREATE INDEX statement is: CREATE [UNIQUE] INDEX index-name ON table-name (column- identifier [ASC][DESC][, column- identifier [ASC][DESC]]) WITH <index option list> where <index list="" option=""> can be: PRIMARY DISALLOW NULL IGNORE NULL</index></index |
| | Only the Microsoft Access driver uses the DISALLOW NULL and IGNORE NULL index options. The Btrieve , dBASE , Microsoft FoxPro , and Paradox drivers accept the syntax, but ignore the presence of either option. |
| | When the Paradox driver is used, the <u>CREATE INDEX</u> statement creates Paradox primary key files and secondary files. |
| Date literals | The MM-DD-YYYY format is supported. (This has been changed from the former format of YYYY-MM-DD.) |
| DROP INDEX | When the Microsoft Access, Btrieve, dBASE, Microsoft FoxPro, or Paradox driver is used, the syntax of the DROP INDEX statement is "DROP INDEX a on b" where "a" is the name of the index and "b" is the name of the table (not DROP INDEX <i>index-name</i>). |
| | When the Paradox driver is used, the DROP INDEX statement deletes Paradox secondary index files and does not use the ODBC SQL grammar. |
| | Not supported for the Microsoft Excel or Text driver. |
| Fixed-Width Text File | When the Text driver is used, the last column of a fixed-width text file can be variable length. |

Limitations to SQL Grammar (Advanced)

| Grammar | Limitation |
|---------------------------|---|
| Aggregate functions | An aggregate function and a non- aggregate column reference cannot both be used as arguments to a single SQL statement. |
| ALTER TABLE statement | When the Btrieve , dBASE , Microsoft FoxPro , or Paradox driver is used, once an index has been created and a new record added, the structure of the table cannot be changed by the ALTER TABLE statement unless the index is dropped and the contents of the table are deleted. |
| AND predicates | A maximum of 40 supported. |
| CALL statement | Expressions are not supported as parameters to a called procedure. (Microsoft Access only) |
| Column names | Column names can contain any valid characters (for example, spaces). If column names contain any characters except letters, numbers, and underscores, the name must be delimited by enclosing it in back quotes (`). |
| | When the Microsoft Access or Microsoft Excel driver is used, column names are limited to 64 characters, and longer names generate an error. When the Paradox driver is used, the maximum column name is 25 characters. When the Text driver is used, the maximum column name is 64 characters, and longer names are truncated. |
| | When the Microsoft Excel driver is used, the '\$' character is used in place of the '!' character, which is not legal. |
| | When the Text driver is used, the driver provides a default name if a column name is not specified. For example, the driver calls the first column F1, the second column F2, and so on. |
| CONVERT function | Type conversion failures result in the affected column being set to NULL. Neither the DATE nor TIMESTAMP data |
| | type can be converted to another data type (or itself) by the CONVERT function. |
| CREATE INDEX statement | Not supported for the Microsoft Excel or Text driver. |
| | The syntax of the CREATE INDEX statement is: CREATE [UNIQUE] INDEX index-name ON table-name (column- identifier [ASC][DESC][, column- identifier [ASC][DESC]]) WITH <index< td=""></index<> |

The ODBC Desktop Database Drivers impose the following limitations on the SQL grammar, as changed for the Desktop Database Drivers version 2.0:

| | option list> where <index list="" option=""> can be: PRIMARY DISALLOW NULL IGNORE NULL</index> |
|---------------------------|--|
| | Only the Microsoft Access driver uses the DISALLOW NULL and IGNORE NULL index options. The Btrieve , dBASE , Microsoft FoxPro , and Paradox drivers accept the syntax, but ignore the presence of either option. |
| | An index can be defined on a maximum of 10 columns. If more than 10 columns are included in a CREATE INDEX statement, the index will not be recognized and the table will be treated as though no index were created. The dBASE driver cannot create an index on a LOGICAL column. |
| | When the dBASE or Microsoft FoxPro driver is used, the index created by a CREATE UNIQUE INDEX statement is actually non-unique, and duplicate values can be inserted into the indexed column. |
| | When the Paradox driver is used, a <u>unique index</u> must be defined. |
| CREATE TABLE statement | When the Microsoft Access, Btrieve, Microsoft Excel , or Paradox driver is used, and the length of a text or binary column is not specified (or is specified as 0), the column length will be set to 255. |
| | When the dBASE or Microsoft FoxPro driver is used, and the length of a text or binary column is not specified (or is specified as 0), the column length will be set to 254. |
| | A maximum of 255 columns is supported. |
| | When the Microsoft Excel5 driver is used, a worksheet cannot be created with the same name as a worksheet that was previously dropped. The DROP TABLE statement clears the worksheet, but does not delete the worksheet name. |
| Date Arithmetic | Date arithmetic is not supported for subtracting a DATE data type from a DATE data type. |
| DELETE statement | Not supported for the Text drivers. Note that the INSERT statement is supported for the Text driver. |
| DISTINCT keyword | Not supported for Long Text fields (Microsoft Access) or Memo fields (dBASE or FoxPro). |
| DROP TABLE statement | When the Microsoft Excel5 driver is used, the DROP TABLE statement clears |

| | the worksheet, but does not delete the worksheet name. The worksheet name still exists in the workbook, so another worksheet cannot be created with the same name. |
|------------------|--|
| FROM clause | The maximum number of tables in a FROM clause is 16. |
| HAVING clause | The maximum number of search conditions in a HAVING clause is 40. |
| Identifiers | If an identifier contains a space or a special symbol, the identifier must be enclosed in back quotes. A valid name is a string of no more than 64 characters, of which the first character must not be a space. Valid names cannot include control characters or the following special characters: ` #*? [].!\$. |
| | Do not use reserved words listed in the SQL grammar in Appendix C of the <i>Microsoft ODBC Programmer's</i> <i>Reference</i> as identifiers (that is, table or coumn names), unless you surround the word in back quotes (`). |
| Index Names | When the Btrieve driver is used, an index cannot have the same name as any of the column names in the table upon which the index is defined. Only 24 index "segments" are allowed per table. |
| | When the Paradox driver is used, a primary <u>index</u> must have the same name as the table upon which it is defined. Other unique or non-unique indexes must have the same name as the column upon which they are defined. |
| INSERT statement | Inserted data is truncated on the right without warning if it is too long to fit into the column. |
| | If a column reference is left out of an INSERT statement, a parameter size error is returned instead of a syntax error. |
| | Attempting to insert a value that is out of the range of a column's data type causes a NULL to be inserted into the column. |
| | A table is not updatable by the Paradox driver if a unique index is not defined on the table. (Note that this is not true for an empty table, which can be updated even if a unique index is not defined on the table.) |
| | When the Text driver is used, the length of any row must be less than or equal to 65,543 bytes. |

| LIKE predicate | If data in a column is longer than 255 characters, the LIKE comparison will be based only on the first 255 characters. A LIKE used in a procedure is supported only with constant patterns. Use of an escape clause in a LIKE |
|--------------------------|--|
| Parameterized Queries | predicate is not supported. A parameterized query can be called using the following syntax: CALL query- name [(parameter[,parameter])]. A parameterized query cannot be used in a SELECT statement: SELECT * FROM query-name WHERE column = ?. |
| Scalar Functions | Scalar functions are supported only by using the ODBC canonical format. |
| SELECT Statement | An aggregate-function column cannot be mixed with a non-aggregate column in a SELECT statement. |
| | The use of an asterisk (to select all columns) in a SELECT statement containing a GROUP BY clause is not supported. The names of the columns to be selected must be specified. The use of a vertical bar in a SELECT |
| | statement is not supported. |
| | When using a column alias in a SELECT statement, the word "as" must precede the alias. For example, "SELECT col1 as a from b". Without the "as", the statement will return an error. |
| | If an incorrect column name is entered into a SELECT statement, a SQLSTATE 07001 error, "Wrong Number of Parameters", is returned instead of a SQLSTATE S0022 error, "Column Not Found". |
| Strings | The maximum length of an SQL statement string is 65,000 characters. |
| | When the Microsoft Access driver is used, only ANSI string constants (with single quotation marks, not double quotation marks) are supported. |
| Table Names | Table names can contain any valid characters (for example, spaces). If table names contain any characters except letters, numbers, and underscores, the name must be delimited by enclosing it in back quotes (`). |
| | When the Microsoft Excel driver is used, if a table name is not qualified by a database reference, the default database is implied. |
| | The Microsoft Excel table name that references <filename> is supported for Microsoft Excel 3.0 and 4.0 files. The</filename> |

| | Microsoft Excel table name that references <workbook-name> is supported for Microsoft Excel 5.0 files. The "\$" character is used in place of the "!" character, which is not legal. Special DOS keywords CON, AUX, LPT1, and LPT2 should not be used as table names.</workbook-name> |
|----------------------------|--|
| Table references | A maximum of 16 table references can be included in any query statement. For 16-bit drivers, however, table references may be limited to a number less than 16, especially for highly complex queries, because of the compilation segment limit. |
| | For 32-bit drivers, the limit of 16 table references is always valid. |
| Views | Not supported by the Btrieve, dBASE, Microsoft Excel, Microsoft FoxPro, Paradox, or Text driver. |
| WHERE clause | The maximum number of clauses in a WHERE clause is 40. LONGVARBINARY and LONGVARCHAR columns can be searched for using literals up to 255 characters in length, but not using parameters. |
| WHERE CURRENT OF clause | Not supported. |

CREATE INDEX (Advanced)

If the keyword **UNIQUE** is specified, the ODBC Paradox driver will create a unique index. The first unique index is created as a primary index. This is a Paradox primary key file named *table-name*.PX. Primary indexes are subject to the following restrictions:

- The primary index must be created before any rows are added to the table.
- A primary index must be defined upon the first "n" columns in a table.
- Only one primary index is allowed per table.

• A table cannot be updated by the Paradox driver if a primary index is not defined on the table. (Note that this is not true for an empty table, which can be updated even if a unique index is not defined on the table.)

• The *index-name* argument for a primary index must be the same as the base name of the table, as required by Paradox.

If the keyword **UNIQUE** is omitted, the ODBC Paradox driver will create a non-unique index. This consists of two Paradox secondary index files named *table-name*.Xnn and *table-name*.Ynn, where nn is the number of the column in the table. Non-unique indexes are subject to the following restrictions:

 Before a non-unique index can be created for a table, a primary index must exist for that table.

Note that when two CREATE INDEX statements are performed, the first statement will always create a primary index with the same name as the table and the second statement will always create a non-unique index with the same name as the column. These indexes will be named this way even if different names are entered in the CREATE INDEX statements and even if the index is labeled UNIQUE in the second CREATE INDEX statement.

Data Types (Advanced)

Select the driver data types you want to display:

Microsoft Access

- Btrieve
- dBASE
- Microsoft Excel
- Microsoft FoxPro
- Paradox
- Text

Microsoft Access Data Types (Advanced)

The following table shows added, changed, or deleted data types and ODBC SQL data types for the ODBC Microsoft Access Driver. Added, changed, or deleted data types are shown in bold.

| Microsoft Access data type | Data type (CREATETABLE) | ODBC SQL data type |
|---------------------------------------|-----------------------------|------------------------------------|
| Binary | Binary | SQL_BINARY |
| Bit | Bit | SQL_BIT |
| Char | Char | SQL_VARCHAR |
| Counter | Counter | SQL_INTEGER |
| Currency | Currency | SQL_NUMERIC |
| Date/Time | DateTime | SQL_TIMESTAMP |
| Long Binary | Long Binary | LONGVARBINARY |
| Long Text | Long Text | SQL_LONGVARCHAR |
| Memo | Long Text [DELETE: Memo] | SQL_LONGVARCHAR |
| Number (FieldSize=Single) | Single [DELETE: Float] | SQL_REAL |
| Number (FieldSize=Double) | Double [DELETE: Float] | SQL_DOUBLE |
| Number (FieldSize=Byte) | Unsigned Byte | SQL_TINYINT |
| Number (FieldSize=Integer) | Short | SQL_SMALLINT |
| Number (FieldSize=Long Integer) | Long | SQL_INTEGER |
| OLE | LongBinary | SQL_LONGVARBINARY |
| Text | VarChar [DELETE:Text] | SQL_VARCHAR |
| VarBinary [DELETE: Yes/No] | VarBinary [DELETE: Bit] | SQL_VARBINARY [DELETE: SQL_BIT] |

The following table shows limitations on Microsoft Access data types.

| Data type | Limitation |
|----------------------------|--|
| BINARY or VARCHAR | Creating a BINARY or VARCHAR column of zero or unspecified length actually returns a 255-byte column. |
| BIT | Bit columns will display as 0 or 1 when a SELECT is performed, but a query making a direct comparison of a BIT data type to the number "1" will not succeed. If a direct comparison must be made, the comparison should be made to TRUE or <>0. |
| CHAR, LONGVARCHAR, VARCHAR | A zero-length string should not be inserted into a Microsoft Access CHAR, LONGVARCHAR, or VARCHAR column. |

More limitations on data types can be found in <u>Data Type Limitations</u>.

Btrieve Data Types (Advanced)

The following table shows added, changed, or deleted data types and ODBC SQL data types for the ODBC Btrieve Driver. Added, changed, or deleted data types are shown in bold.

| Btrieve data type | ODBC data type |
|-------------------|----------------------|
| DATE | SQL_DATE |
| FLOAT4 | SQL_REAL |
| FLOAT8 | SQL_DOUBLE |
| INTEGER1 | SQL_TINYINT |
| INTEGER2 | SQL_SMALLINT |
| INTEGER4 | SQL_INTEGER |
| LOGICAL1 | SQL_BIT |
| MONEY | SQL_NUMERIC |
| NOTE | SQL_LONGVARCHAR |
| STRING | SQL_ VAR CHAR |

The following table shows limitations on Btrieve data types.

| Data type | Limitation |
|----------------|--|
| LOGICAL1 | LOGICAL1 columns will display as 0 or 1 when a SELECT is performed, but a query making a direct comparison of a LOGICAL1 data type to the number "1" will not succeed. If a direct comparison must be made, the comparison should be made to TRUE or <>0. |
| STRING columns | Creating a STRING column of zero or unspecified length actually returns a 255-byte column. |

More limitations on data types can be found in <u>Data Type Limitations</u>.

dBASE Data Types (Advanced)

The following table shows added, changed, or deleted data types and ODBC SQL data types for the ODBC dBASE Driver. Added, changed, or deleted data types are shown in bold.

| dBASE data type | ODBC data type |
|---------------------|----------------------|
| Char | SQL_ VAR CHAR |
| [DELETE: Character] | — |
| Date | SQL_DATE |
| Logical | SQL_BIT |
| Memo | SQL_LONGVARCHAR |
| Numeric (BCD) | SQL_DOUBLE |

The following table shows limitations on dBASE data types.

| Data type | Limitation |
|----------------|---|
| CHAR columns | Creating a CHAR column of zero or unspecified length actually returns a 254-byte column. |
| Encrypted data | The dBASE driver does not support encrypted dBASE tables. |
| LOGICAL | LOGICAL columns will display as 0 or 1 when a SELECT is performed, but a query making a direct comparison of a LOGICAL data type to the number "1" will not succeed. If a direct comparison must be made, the comparison should be made to TRUE or <>0. The dBASE driver cannot create an index on a LOGICAL column. |

More limitations on data types can be found in Data Type Limitations.

Microsoft Excel Data Types (Advanced)

The following table shows added, changed, or deleted data types and ODBC SQL data types for the ODBC Microsoft Excel Driver. Added, changed, or deleted data types are shown in bold.

| Microsoft Excel | ODBC SQL data type |
|-----------------|----------------------|
| data type | |
| DateTime | SQL_TIMESTAMP |
| Integer | SQL_INTEGER |
| Logical | SQL_BIT |
| Number | SQL_DOUBLE |
| Text | SQL_ VAR CHAR |

The following table shows limitations on Microsoft Excel data types.

| Data type | Limitation |
|----------------|--|
| Encrypted data | The Microsoft Excel driver cannot read encrypted data. |
| Error Strings | The Microsoft Excel driver cannot return a character string for the Microsoft Excel error values (#N/A!, #VALUE!, #REF!, #DIV/0!, #NUM!, #NAME?, and #NULL!), but returns a NULL instead. |
| LOGICAL | LOGICAL columns will display as 0 or 1 when a SELECT is performed, but a query making a direct comparison of a LOGICAL data type to the number "1" will not succeed. If a direct comparison must be made, the comparison should be made to TRUE or <>0. |
| | When a LOGICAL value is returned in a column other than a LOGICAL column, the Microsoft Excel driver cannot convert that LOGICAL value to a TRUE or FALSE character string, but converts the value to NULL instead. |
| TEXT columns | Creating a TEXT column of zero or unspecified length actually returns a 255-byte column. |

More limitations on data types can be found in Data Type Limitations.

Microsoft FoxPro Data Types (Advanced)

The following table shows added, changed, or deleted data types and ODBC SQL data types for the ODBC Microsoft FoxPro Driver. Added, changed, or deleted data types are shown in bold.

| Microsoft FoxPro data type | ODBC data type |
|-------------------------------|----------------------|
| Char [DELETE: Character] | SQL_ VAR CHAR |
| Date | SQL_DATE |
| General | SQL_LONGVARBINARY |
| Logical | SQL_BIT |
| Memo | SQL_LONGVARCHAR |
| Numeric (BCD) | SQL_DOUBLE |

The following table shows limitations on Microsoft FoxPro data types.

| Data type | Limitation |
|-----------|--|
| CHAR | Creating a CHAR column of zero or unspecified length actually returns a 254-byte column. |
| LOGICAL | LOGICAL columns will display as 0 or 1 when a SELECT is performed, but a query making a direct comparison of a LOGICAL data type to the number "1" will not succeed. If a direct comparison must be made, the comparison should be made to TRUE or <>0. |

More limitations on data types can be found in <u>Data Type Limitations</u>.

Paradox Data Types (Advanced)

The following table shows added, changed, or deleted data types and ODBC SQL data types for the ODBC Paradox Driver. Added, changed, or deleted data types are shown in bold.

| Paradox data type | ODBC SQL data type |
|----------------------|-----------------------|
| Alphanumeric | SQL_ VAR CHAR |
| Date | SQL_DATE |
| Image * | SQL_LONGVARBINA RY |
| Number | SQL_DOUBLE |
| Short | SQL_SMALLINT |

* Only valid for Paradox versions 4x.

The following table shows limitations on Paradox data types.

| Data type | Limitation |
|--------------|---|
| Alphanumeric | Creating an Alphanumeric column of zero or unspecified length actually returns a 255-byte column. |

More limitations on data types can be found in <u>Data Type Limitations</u>.

Text Data Types (Advanced)

The following table shows added, changed, or deleted data types and ODBC SQL data types for the ODBC Text Driver. Added, changed, or deleted data types are shown in bold.

| Text data type | ODBC data type |
|----------------|----------------------|
| CHAR | SQL_ VAR CHAR |
| DATETIME | SQL_TIMESTAMP |
| FLOAT | SQL_DOUBLE |
| INTEGER | SQL_INTEGER |
| LONGCHAR | SQL_LONGVARCHAR |

The following table shows limitations on Text data types.

| Data type | Limitation |
|-----------|---|
| CHAR | Creating a CHAR column of zero or unspecified length actually returns a 255-bit column. |
| INTEGER | Valid values for INTEGER columns are 32767 to -32766. |

More limitations on data types can be found in <u>Data Type Limitations</u>.

Limitations to Data Types (Advanced)

The following limitations new to version 2.0 apply to data types.

| <u>D</u> ata type | Limitation |
|---------------------|--|
| All data types | Type conversion failures result in the affected column being set to NULL. |
| BIT | TRUE is represented as -1, not 1, so comparisons may not operate properly. |
| | A NULL is inserted as a 0. |
| | BIT columns will display as |
| | 0 or 1 when a SELECT is |
| | performed, but a query making a direct comparison |
| | of a BIT data type to the |
| | number "1" will not |
| | succeed. If a direct |
| | comparison must be made, |
| | the comparison should be made to TRUE or <>0. |
| | A value inserted into a |
| | column of type BIT |
| | (whether character or |
| | numeric) that isn't a 0 or a '0' is treated as TRUE. |
| | |
| | Creating a zero-length BINARY column actually |
| | returns a 255-bit BINARY |
| | column. |
| DATE | The DATE data type cannot |
| | be converted to another |
| | data type (or itself) by the CONVERT function. |
| DECIMAL (Exact | Not supported. |
| Numeric) | ···· |
| Floating-Point Data | The number of decimal |
| Types | places in a floating-point |
| | number may be limited by the number format set in |
| | the International section of |
| | the Windows Control Panel. |
| TIMESTAMP | The TIMESTAMP data type |
| | cannot be converted to |
| | itself by the CONVERT function. |
| | |
| TINYINT | TINYINT values are always |

Error Messages (Advanced)

The following table shows the error messages returned by the Driver Manager and the Driver ISAM, as changed for the Desktop Database Drivers version 2.0:

| Error message | Error location |
|-----------------------------------|---------------------------------------|
| [Microsoft][ODBC DLL]message-text | Driver Manager (16-bit ODBC.DLL or |

[Microsoft][ODBC *driver-name*][ODBC File Library]*message-text* 32-bit ODBC32.DLL) Driver ISAM (see <u>Driver ISAMs</u> <u>Table</u>)

SQLGetInfo Return Values Affecting Cursor Support

The following table lists **SQLGetInfo** return values that affect cursor support and have changed for version 2.0. This information can be retrieved by passing the listed C-language #defines to **SQLGetInfo** in the *flnfoType* argument. Where **SQLGetInfo** returns a 32-bit bitmask, a vertical bar (|) represents a bitwise OR. For more information about the values returned by **SQLGetInfo**, see the *Microsoft ODBC SDK Programmer's Reference, Version 2.0*.

| fInfoType value (#define) | Returned value |
|------------------------------|---------------------------------|
| SQL_CURSOR_COMMIT_BEHAVIOR | SQL_CB_CLOSE |
| | [DELETE: 2] |
| SQL_CURSOR_ROLLBACK_BEHAVIOR | SQL_CB_CLOSE |
| | [DELETE: 0] |
| SQL_MAX_CURSOR_NAME_LEN | 64 [DELETE: 18] |
| SQL_POS_OPERATIONS | SQL_POS_POSITION |
| | SQL_POS_REFRESH (|
| | |
| | SQL_POS_DELETE SQL_POS_ADD |
| SQL POSITIONED STATEMENTS | 0 |
| | 0 |

SQLGetInfo Return Values (Programming)

The following table lists C-language #defines for the *flnfoType* argument and the corresponding values returned by **SQLGetInfo**. Added, changed, or deleted #defines and return values are shown in bold. This information can be retrieved by passing the listed C-language #defines to **SQLGetInfo** in the *flnfoType* argument. Where **SQLGetInfo** returns a 32-bit bitmask, a vertical bar (|) represents a bitwise OR. For more information about the values return by **SQLGetInfo**, see the *Microsoft ODBC SDK Programmer's Reference, Version 2.0*.

| fInfoType value (#define) | Returned value |
|---------------------------|--|
| SQL_ACCESSIBLE_PROCEDURES | "Y" (Microsoft Access) "N" (Btrieve, dBASE, Microsoft Excel, Microsoft FoxPro, Paradox, Text) |
| SQL_ACCESSIBLE_TABLES | "Y" |
| SQL_ACTIVE_CONNECTIONS | 64 [DELETE: 0] |
| SQL_ACTIVE_STATEMENTS | 0 |
| SQL_ALTER_TABLE | SQL_AT_ADD_COLUMN SQL_AT_DROP_COLUMN (Microsoft Access, Btrieve, dBASE, Microsoft FoxPro, Paradox) 0 (Microsoft Excel, Text) |
| SQL_BOOKMARK_PERSISTANCE | SQL_BP_SCROLL SQL_BP_UPDATE |
| SQL_COLUMN_ALIAS | " Y " |
| SQL_CONCAT_NULL_BEHAVIOR | SQL_CB_NON_NULL |
| SQL_CONVERT_BIGINT | 0 |
| SQL_CONVERT_BINARY | SQL_CVT_DOUBLE SQL_CVT_FLOAT |

| | SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL SQL_CVT_SMALLINT SQL_CVT_VARCHAR [DELETE: 0] |
|--|--|
| SQL_CONVERT_BIT SQL_CONVERT_CHAR | 0 SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL SQL_CVT_SMALLINT |
| SQL_CONVERT_DATE | SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL SQL_CVT_SMALLINT |
| SQL_CONVERT_DECIMAL SQL_CONVERT_DOUBLE | SQL_CVT_VARCHAR 0 SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL SQL_CVT_SMALLINT |
| SQL_CONVERT_FLOAT | SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL SQL_CVT_SMALLINT |
| SQL_CONVERT_FUNCTIONS SQL_CONVERT_INTEGER | SQL_CVT_VARCHAR SQL_FN_CVT_CONVERT SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL SQL_CVT_SMALLINT |
| SQL_CONVERT_LONGVARBINARY | SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL SQL_CVT_SMALLINT SQL_CVT_VARCHAR |
| SQL_CONVERT_LONGVARCHAR | [DELETE: 0] SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL |

| SQL_CONVERT_NUMERIC | SQL_CVT_SMALLINT SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC |
|-----------------------|--|
| SQL_CONVERT_REAL | SQL_CVT_REAL SQL_CVT_SMALLINT SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL |
| SQL_CONVERT_SMALLINT | SQL_CVT_KEAL SQL_CVT_SMALLINT SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL |
| SQL_CONVERT_TIME | SQL_CVT_SMALLINT SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL |
| SQL_CONVERT_TIMESTAMP | SQL_CVT_SMALLINT SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL |
| SQL_CONVERT_TINYINT | SQL_CVT_SMALLINT SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL |
| SQL_CONVERT_VARBINARY | SQL_CVT_SMALLINT SQL_CVT_VARCHAR SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL |
| SQL_CONVERT_VARCHAR | SQL_CVT_SMALLINT SQL_CVT_VARCHAR [DELETE: 0] SQL_CVT_DOUBLE SQL_CVT_FLOAT SQL_CVT_FLOAT SQL_CVT_INTEGER SQL_CVT_NUMERIC SQL_CVT_REAL |

| SQL_CORRELATION_NAME | SQL_CVT_SMALLINT SQL_CVT_VARCHAR [DELETE: 0] SQL_CN_DIFFERENT |
|---|---|
| SQL_CURSOR_COMMIT_BEHAVIOR SQL CURSOR ROLLBACK BEHAVIOR | SQL_CB_CLOSE [DELETE: 2] SQL_CB_CLOSE |
| SQL_DATA_SOURCE_NAME | [DELETE: 0] The DSN from ODBC.INI, or |
| SQL DATA SOURCE READ ONLY | "" if DRIVER keyword is used in ODBC.INI "N" |
| | (Microsoft Access, Btrieve, dBASE, Microsoft FoxPro, Paradox) "Y" |
| | (Microsoft Excel, Text) [DELETE: (The driver does not check to see whether the disk drive is read- only.)] |
| SQL_DATABASE_NAME SQL_DBMS_NAME | Filename "ACCESS" [Microsoft Access] |
| | "BTRIEVE" [Btrieve] "DBASE" [dBASE] "EXCEL" [Microsoft Excel] "FOXPRO" [Microsoft FoxPro] "PARADOX" [Paradox] "TEXT" [Text] |
| SQL_DBMS_VER | "1.0", "1.1", or "2.0" [Microsoft Access] "5.1" or "6.0" [Btrieve] "3.0" or "4.0" [dBASE] "3.0", "4.0", or "5.0" [Microsoft Excel] "2.0", "2.5", or "2.6" [Microsoft FoxPro] "3.x" or "4.x" [Paradox] "1.0" [Text] |
| SQL_DEFAULT_TXN_ISOLATION | SQL_TXN_READ_COMMITTE D [Microsoft Access] |
| SQL_DRIVER_NAME | "ODBCJT16.DLL" for 16-bit, or "ODBCJT32.DLL" for 32- bit |
| SQL_DRIVER_ODBC_VER SQL_DRIVER_VER SQL_EXPRESSIONS_IN_ORDERBY | [DELETE: SIMBA.DLL] "2.01" " 2.01.nnnn" (nnnn specifies the build date.) [DELETE: 1.01] "Y" |
| SQL_EXFRESSIONS_IN_ORDERBI | SQL_FD_FETCH_NEXT SQL_FD_FETCH_FIRST SQL_FD_FETCH_LAST |

| SQL_FILE_USAGE | SQL_FD_FETCH_PRIOR SQL_FD_FETCH_ABSOLUTE SQL_FD_FETCH_RELATIVE SQL_FD_FETCH_BOOKMARK SQL_FILE_QUALIFIER (Microsoft Access, Btrieve, Microsoft Excel5.0) |
|--|---|
| SQL_GETDATA_EXTENSIONS | SQL_FILE_TABLE (dBASE, Microsoft Excel3.0/4.0, Microsoft FoxPro, Paradox, Text) SQL_GD_ANY_ORDER SQL_GD_ANY_COLUMN SQL_GD_BLOCK |
| SQL_GROUP_BY | SQL_GD_BOUND SQL_GB_GROUP_BY |
| SQL IDENTIFIER CASE | CONTAINS_SELECT SQL IC MIXED |
| SQL_IDENTIFIER_QUOTE_CHAR | "`"" (backquote) |
| | [DELETE: double quotation mark]. |
| SQL_KEYWORDS | ALPHANUMERIC, AUTOINCREMENT, BINARY, BOOLEAN, BYTE, CURRENCY, DATABASE, DATABASENAME, DATETIME, DISTINCTROW, DOUBLEFLOAT, FLOAT4, FLOAT8, GENERAL, IEEEDOUBLE, IEEESINGLE, INT, INTEGER1, INTEGER2, INTEGER4, LOGICAL, LOGICAL1, LONG, LONGBINARY, LONGCHAR, LONGTEXT, MEMO, MONEY, NOTE, NUMBER, OLEOBJECT, OWNERACCESS, PARAMETERS, PERCENT, PIVOT, REAL, SHORT, SINGLE, SINGLEFLOAT, STDEV, STDEVP, STRING, TABLEID, TEXT, TOP, TRANSFORM, UNSIGNEDBYTE, VAR, VARBINARY, VARP, YESNO |
| SQL_LOCK_TYPES | SQL_LOCK_NO_CHANGE |
| SQL_MAX_BINARY_LITERAL_LEN SQL_MAX_CHAR_LITERAL_LEN | 255 255 (Microsoft Access) 255 (Btrieve) 254 (dBASE) 255 (Microsoft Excel) 254 (Microsoft FoxPro) 255 (Paradox) 255 (Text) |

| SQL_MAX_COLUMN_NAME_LEN | 64 [Microsoft Access] 20 [Btrieve] 10 [dBASE] 64 [Microsoft Excel 5.0] 30 [Microsoft Excel 3.0/4.0] 10 [Microsoft FoxPro] 25 [Paradox] 64 [Text] 310 |
|---|---|
| SQL_MAX_COLUMNS_IN_INDEX | 32 (Microsoft Access) 0 (Limit Unknown or Not Applicable) (Btrieve, DBase, Microsoft FoxPro, Paradox) 0 (Microsoft Excel, Text) 3 10 |
| Y | , 10 |
| SQL_MAX_COLUMNS_IN_SELECT SQL_MAX_COLUMNS_IN_TABLE | 255 255 (Microsoft Access, dBASE, Microsoft Excel, Microsoft FoxPro, Paradox, Text) 254 (Btrieve) |
| SQL_MAX_CURSOR_NAME_LEN SQL_MAX_INDEX_SIZE | 64 [DELETE: 18] 255 [Microsoft Access] 4096 [Btrieve] 220 [dBASE] 0 [Microsoft Excel] 512 [Microsoft FoxPro] 1350 [Paradox] 0 [Text] |
| SQL_MAX_OWNER_NAME_LEN SQL_MAX_PROCEDURE_NAME_LEN | 0 64 [Microsoft Access] 0 [Btrieve, dBASE, Microsoft Excel, Microsoft FoxPro, Paradox, Text] |
| SQL_MAX_QUALIFIER_NAME_LEN SQL_MAX_ROW_SIZE | 66 2096 [Microsoft Access] 4096 [Btrieve] 4000 [dBASE] 65535 [Microsoft Excel] 65500 [Microsoft FoxPro 2.5 and above] 4000 [Microsoft FoxPro 2.0] 1350 [Paradox] 65535 [Text] |
| SQL_MAX_ROW_SIZE_INCLUDES_ LONG | "N" [Microsoft Access, dBase, Microsoft FoxPro, Paradox] "Y" [Btrieve, Microsoft Excel, |

| | Text] |
|------------------------------------|---|
| SQL_MAX_STATEMENT_LEN | 65000 |
| SQL_MAX_TABLE_NAME_LEN | 64 (Microsoft Access) 20 (Btrieve) 12 (dBASE) |
| | 31 (Microsoft Excel 5.0) 12 (Microsoft Excel |
| | 3.0/4.0) 12 (Microsoft FoxPro) |
| | 12 (Paradox) 12 (Text) |
| SQL_MAX_TABLES_IN_SELECT | 16 |
| SQL_MAX_USER_NAME_LEN | 0 |
| SQL_MULT_RESULT_SETS | "N" |
| SQL_MULTIPLE_ACTIVE_TXN | "Y" [DELETE: N] |
| SQL_NEED_LONG_DATA_LEN | "N" |
| | |
| SQL_NON_NULLABLE_COLUMNS | SQL_NNC_NULL |
| | [DELETE: 1] |
| SQL_NULL_COLLATION | SQL_NC_LOW |
| SQL_NUMERIC_FUNCTIONS | SQL_FN_NUM_ABS SQL_FN_NUM_ATAN |
| | SQL_FN_NUM_CEILING |
| | SQL_FN_NUM_COS |
| | SQL_FN_NUM_EXP |
| | SQL_FN_NUM_FLOOR SQL_FN_NUM_LOG |
| | SQL FN NUM MOD |
| | SQL_FN_NUM_POWER |
| | SQL_FN_NUM_RAND |
| | SQL_FN_NUM_SIGN |
| | SQL_FN_NUM_SIN SQL_FN_NUM_SQRT |
| | SQL_FN_NUM_TAN |
| SQL_ODBC_API_CONFORMANCE | SQL_OAC_LEVEL1 |
| | [DELETE: 1] |
| SQL_ODBC_SAG_CLI_CONFORMANCE | SQL_OSCC_NOT_COMPLIAN |
| | Т |
| | [DELETE: 1] |
| SQL_ODBC_SQL_CONFORMANCE | SQL_OSC_MINIMUM |
| | [DELETE: 0] |
| SQL_ODBC_SQL_OPT_IEF | "N" |
| SQL_ODBC_VER | From Driver Manager |
| SQL_ORDER_BY_COLUMNS_IN_ SELECT | "N" |
| SQL_OUTER_JOINS | "Y" |
| SQL_OWNER_TERM | |
| SQL_OWNER_USAGE | 0 |
| SQL_POS_OPERATIONS | SQL_POS_POSITION |
| | SQL_POS_REFRESH |
| | SQL_POS_UPDATE SQL_POS_DELETE |
| | SQL_POS_DELETE SQL_POS_ADD |
| | (Microsoft Access, Btrieve, |
| | dBASE, Microsoft FoxPro, |

| SQL_POSITIONED_STATEMENTS SQL_PROCEDURE_TERM | Paradox) SQL_POS_POSITION SQL_POS_REFRESH (Microsoft Excel, Text) 0 "QUERY" (Microsoft Access) |
|---|--|
| SQL_PROCEDURES | (Btrieve, dBASE, Microsoft Excel, Microsoft FoxPro, Paradox, Text) "Y" (Microsoft Access) "N" (Btrieve, dBASE, Microsoft |
| SQL_QUALIFIER_LOCATION SQL_QUALIFIER_NAME_SEPARATOR | Excel, Microsoft FoxPro, Paradox, Text) SQL_QL_START "." (Microsoft Access, Microsoft Excel 5) "\" |
| SQL_QUALIFIER_TERM | (Btrieve, dBASE, Microsoft Excel 4, Microsoft FoxPro, Paradox, Text) "Database" [Microsoft Access] "Workbook" [Microsoft Excel 5.0] "Directory" [Btrieve, DBase, Microsoft Excel |
| SQL_QUALIFIER_USAGE | 3.0/4.0, Microsoft FoxPro, Paradox, Text] [DELETE: Directory] SQL_QU_DML_STATEMENTS SQL_QU_TABLE_DEFINITION SQL_QU_INDEX_DEFINITION |
| | SQL_QU_PROCEDURE_ INVOCATION (Microsoft Access) SQL_QU_DML_STATEMENTS SQL_QU_TABLE_DEFINITION |
| | SQL_QU_INDEX_DEFINITION (Btrieve, dBASE, Microsoft FoxPro, Paradox) SQL_QU_DML_STATEMENTS |
| SQL_QUOTED_IDENTIFIER_CASE SQL_ROW_UPDATES | SQL_QU_TABLE_DEFINITION (Microsoft Excel, Text) SQL_IC_MIXED "N" [DELETE: Y] |

| SQL_SCROLL_CONCURRENCY | SQL_SCCO_READ_ONLY SQL_SCCO_LOCK SQL_SCCO_OPT_VALUES (Microsoft Access, Btrieve, dBASE, Microsoft FoxPro, Paradox) SQL_SCCO_READ_ONLY (Microsoft Excel, Text) |
|-----------------------------|---|
| SQL_SCROLL_OPTIONS | SQL_SO_FORWARD_ONLY SQL_SO_STATIC SQL_SO_KEYSET_DRIVEN |
| SQL_SEARCH_PATTERN_ESCAPE | |
| SQL_SERVER_NAME | "ACCESS" [Microsoft Access] "BTRIEVE" [Btrieve] "DBASE" [dBASE] "EXCEL" [Microsoft Excel] "FOXPRO" [Microsoft FoxPro] "PARADOX" [Paradox] "TEXT" [Text] |
| SQL_SPECIAL_CHARACTERS | "~`@#\$%^&*+=\}{"';:?/ ><,.!'[]" |
| SQL_STATIC_SENSITIVITY | SQL_SS_ADDITIONS SQL_SS_DELETIONS SQL_SS_UPDATES |
| SQL_STRING_FUNCTIONS | SQL_FN_STR_ASCII SQL_FN_STR_CHAR SQL_FN_STR_CONCAT SQL_FN_STR_LCASE SQL_FN_STR_LEFT SQL_FN_STR_LENGTH SQL_FN_STR_LOCATE SQL_FN_STR_LTRIM SQL_FN_STR_RIGHT SQL_FN_STR_RIGHT SQL_FN_STR_SPACE SQL_FN_STR_SUBSTRING SQL_FN_STR_UCASE |
| SQL_SUBQUERIES | SQL_SQ_COMPARISON SQL_SQ_EXISTS SQL_SQ_IN SQL_SQ_QUANTIFIED SQL_SQ_CORRELATED_ SUBQUERIES |
| SQL_SYSTEM_FUNCTIONS | 0 |
| SQL_TABLE_TERM | "TABLE" |
| SQL_TIMEDATE_ADD_INTERVALS | 0 |
| SQL_TIMEDATE_DIFF_INTERVALS | |
| SQL_TIMEDATE_FUNCTIONS | SQL_FN_TD_CURDATE SQL_FN_TD_CURTIME SQL_FN_TD_DAYOFMONTH SQL_FN_TD_DAYOFWEEK SQL_FN_TD_DAYOFYEAR |

SQL_FN_TD_HOUR |

| SQL_TXN_CAPABLE | SQL_FN_TD_MINUTE SQL_FN_TD_MONTH SQL_FN_TD_NOW SQL_FN_TD_SECOND SQL_FN_TD_WEEK SQL_FN_TD_YEAR SQL_TC_ALL (Microsoft Access) 0 (Btrieve, dBASE, Microsoft Excel, Microsoft FoxPro, Paradox, Text) |
|--------------------------|---|
| SQL_TXN_ISOLATION_OPTION | SQL_TXN_READ_COMMITTE |
| SQL_UNION | SQL_U_UNION_ALL SQL_U_UNION |
| SQL_USER_NAME | Not supported |

ODBC API Functions Affecting Cursor Support

The following ODBC API functions affect cursor support.

| Function | Description |
|---------------------|--|
| SQLExtendedFetch | Supported. |
| SQLSetPos | SQL_LOCK_NO_CHANGE is supported for <i>fLock</i> . SQL_LOCK_EXCLUSIVE and SQL_LOCK_UNLOCK are not supported. |
| SQLSetScrollOptions | Forward and static cursors are supported for SQL_CONCUR_READ_ONLY. Only keyset-driven cursors are supported for SQL_CONCUR_LOCK. Dynamic cursors and mixed cursors are not supported. |
| SQLSetStmtOption | The only valid keyset size (SQL_KEYSET_SIZE) is 0, because mixed and dynamic cursors are not supported. SQL_ROW_NUMBER returns 0 to indicate that a row number cannot be determined. SQL_SIMULATE_CURSOR is not supported. |

ODBC API Functions Affecting Transaction Support

The following ODBC API functions affect transaction support. Transactions are supported for the **Microsoft Access** driver only.

| Function | Description |
|---------------------|---|
| SQLSetConnectOption | SQL_TXN_ISOLATION is always SQL_TXN_READ_COMMITTED. |
| | When the Microsoft Access driver is used, the SQL_AUTOCOMMIT option may be set to either ON or OFF, because the Microsoft Access driver supports transactions. |
| | The Btrieve , dBASE , Microsoft Excel , Microsoft FoxPro , Paradox , and Text drivers only support SQL_AUTOCOMMIT being set to ON (the default state), because they do not support manual commits. |
| SQLTransact | When the Microsoft Access driver is used, COMMIT and ROLLBACK are supported. When the Microsoft Access driver is used, if a failure occurs |

during the commit process, the affected database can be repaired using the <u>Repair</u> <u>Database</u> option in the Microsoft Access driver setup, or through the use of the REPAIR_DB keyword in the **SQLConfigDataSource** function. This database repair process could corrupt the data, however.

ODBC API Functions (Programming)

The ODBC Desktop Database Drivers support all Core and Level 1 functions and the following Level 2 functions:

- SQLData Sources
- SQLDrivers
- SQLExtendedFetch
- SQLMoreResults
- SQLNativeSQL
- SQLNumParams
- SQLProcedures
- SQLProcedureColumns
- SQLSetPos
- SQLSetScrollOptions

The following table describes how the ODBC <u>Desktop Database Drivers</u> implement specific functions.

| Function | Description |
|------------------|--|
| SQLColAttributes | LONGVARBINARY and LONGVARCHAR columns are reported as SQL_UNSEARCHABLE. |
| | For LONGVARBINARY data, SQL_COLUMN_DISPLAY_SIZE is the maximum length of the column, not the maximum length of the column times 2. |
| | The SQL_COLUMN_MONEY statement option of SQLColAttributes returns FALSE for a column of Paradox data type CURRENCY, which maps to the ODBC SQL data type SQL_DOUBLE. |
| SQLConnect | When the Microsoft Access or Paradox driver is used, the PWD keyword should not include any of the special characters (see SQL_SPECIAL_CHARACTERS in <u>SQLGetInfo Return Values</u>). |
| SQLDriverConnect | SQLDriverConnect enables you to <u>connect to a driver</u> without creating a data source (DSN). When the Microsoft Access or Paradox driver is used, the PWD keyword should not include any of |

| SQLGetTypeInfo | the special characters (see SQL_SPECIAL_CHARACTERS in <u>SQLGetInfo Return Values</u>). When the Paradox driver is used, after a password-protected file has been opened by a user, other users are not allowed to open the same file. The name of the type (TYPE_NAME) returned in the table produced by SQLGetTypeInfo will be the name most commonly used by the data source. |
|---------------------|---|
| | When the Text driver is used, SQLGetTypeInfo returns a CASE_SENSITIVE value of FALSE for the text data types (CHAR and LONGCHAR), when the data types actually are case-sensitive. |
| SQLPrepare | A statement prepared with an incorrect number of columns returns an error at execution time, not upon statement preparation. |
| SQLProcedureColumns | Supported for Microsoft Access DSNs only. Pattern matching is not supported for <i>szProcName</i> . |
| | SQL_PARAM_INPUT or SQL_RESULT_COL is returned for COLUMN_TYPE. |
| SQLProcedures | SQL_PT_PROCEDURE is returned in PROCEDURE_TYPE for all procedures. |
| SQLSetConnectOption | When the Microsoft Access driver is used, SQL_TXN_ISOLATION is always SQL_TXN_READ_COMMITTED. SQL_TRANSLATE_DLL and SQL_TRANSLATE_DLL and SQL_TRANSLATION_OPTION are not supported. SQL_LOGIN_TIMEOUT is not supported. When the Microsoft Access driver is used, the SQL_AUTOCOMMIT option may be set to either ON or OFF, because the Microsoft Access driver supports transactions. The Btrieve, dBASE, Microsoft Excel, Microsoft FoxPro, Paradox, and Text drivers only support SQL_AUTOCOMMIT being set to ON (the default state), because they do not support |

| SOI SotPos | transactions. |
|---------------------|--|
| SQLSetPos | SQL_LOCK_NO_CHANGE is supported for <i>fLock</i> . SQL_LOCK_EXCLUSIVE and |
| | SQL_LOCK_UNLOCK are not |
| | supported. SQLSetPos supports updatable |
| | joins. (For more information on updatable joins, see the |
| | documentation for your database management system.) |
| SQLSetScrollOptions | Forward and static cursors are supported for |
| | SQL_CONCUR_READ_ONLY. |
| | Only keyset-driven cursors are supported for SQL CONCUR LOCK. |
| | Dynamic cursors and mixed |
| SQLSetStmtOption | cursors are not supported. The only valid keyset size |
| | (SQL_KÉYSET_SIZE) is 0, because mixed and dynamic cursors are not supported. |
| | SQL_ROW_NUMBER returns 0 to |
| | indicate that a row number cannot be determined. |
| | SQL_SIMULATE_CURSOR is not supported. |
| SQLSpecialColumns | A unique index will be returned (if |
| | one exists) for the SQL_BEST_ROWID flag in |
| | |
| | fColType. No result set will be returned for the SQL_ROWVER |
| | |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (fUnique). The fAccuracy |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (<i>fUnique</i>). The <i>fAccuracy</i> parameter is ignored. NON_UNIQUE, SEQ_IN_INDEX, |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (fUnique). The fAccuracy parameter is ignored. |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (<i>fUnique</i>). The <i>fAccuracy</i> parameter is ignored. NON_UNIQUE, SEQ_IN_INDEX, COLUMN_NAME, and COLLATION are index-dependent. NULL is always returned in the |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (<i>fUnique</i>). The <i>fAccuracy</i> parameter is ignored. NON_UNIQUE, SEQ_IN_INDEX, COLUMN_NAME, and COLLATION are index-dependent. NULL is always returned in the INDEX_QUALIFIER and PAGES columns. |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (<i>fUnique</i>). The <i>fAccuracy</i> parameter is ignored. NON_UNIQUE, SEQ_IN_INDEX, COLUMN_NAME, and COLLATION are index-dependent. NULL is always returned in the INDEX_QUALIFIER and PAGES columns. Only SQL_TABLE_STAT or SQL_INDEX_OTHER will be |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (<i>fUnique</i>). The <i>fAccuracy</i> parameter is ignored. NON_UNIQUE, SEQ_IN_INDEX, COLUMN_NAME, and COLLATION are index-dependent. NULL is always returned in the INDEX_QUALIFIER and PAGES columns. Only SQL_TABLE_STAT or |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (<i>fUnique</i>). The <i>fAccuracy</i> parameter is ignored. NON_UNIQUE, SEQ_IN_INDEX, COLUMN_NAME, and COLLATION are index-dependent. NULL is always returned in the INDEX_QUALIFIER and PAGES columns. Only SQL_TABLE_STAT or SQL_INDEX_OTHER will be returned for TYPE. CARDINALITY will be returned for the Microsoft Access driver. |
| SQLStatistics | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (<i>fUnique</i>). The <i>fAccuracy</i> parameter is ignored. NON_UNIQUE, SEQ_IN_INDEX, COLUMN_NAME, and COLLATION are index-dependent. NULL is always returned in the INDEX_QUALIFIER and PAGES columns. Only SQL_TABLE_STAT or SQL_INDEX_OTHER will be returned for TYPE. CARDINALITY will be returned for the Microsoft Access driver. CARDINALITY will not be returned for the Btrieve, dBASE , |
| SQLTables | returned for the SQL_ROWVER flag. All row IDs have a scope of SQL_SCOPE_SESSION. Filtering is based on uniqueness (<i>fUnique</i>). The <i>fAccuracy</i> parameter is ignored. NON_UNIQUE, SEQ_IN_INDEX, COLUMN_NAME, and COLLATION are index-dependent. NULL is always returned in the INDEX_QUALIFIER and PAGES columns. Only SQL_TABLE_STAT or SQL_INDEX_OTHER will be returned for TYPE. CARDINALITY will be returned for the Microsoft Access driver. CARDINALITY will not be returned |

system tables, "SYNONYM" is supported for attached tables, and "VIEW" is supported for row returning queries.

When the **Btrieve**, **dBASE**, **Microsoft Excel 3.0/4.0**, **Microsoft FoxPro**, **Paradox**, or **Text** driver is used, "TABLE" is the only table type supported.

When the **Microsoft Excel 5.0** driver is used, sheet names (tables with a "\$" on the end) are returned as "SYSTEM TABLE", and "TABLE" is returned for all other sheets.

When the **Text** driver is used, the list of files returned by SQLTables is determined by the file extensions in the Extensions List box in the ODBC Text <u>Setup dialog</u> <u>box</u>.

When the **Microsoft Access** driver is used, COMMIT and ROLLBACK via the **SQLTransact** function are supported.

When the **Btrieve**, **dBASE**, **Microsoft Excel**, **Microsoft FoxPro**, **Paradox**, or **Text** driver is used, this function supports COMMIT, but not ROLLBACK.

When the **Microsoft Access** driver is used, if a failure occurs during the commit process, the affected database can be repaired using the <u>Repair</u> <u>Database</u> option in the Microsoft Access driver setup, or through the use of the REPAIR_DB keyword in the **SQLConfigDataSource** function.

SQLTransact

SQLConfigDataSource Implementation (Programming)

The **SQLConfigDataSource** function that is used to add, modify, or delete a data source dynamically uses the following arguments.

| Keyword | Description |
|-------------------|---|
| CHARACTERSE | For the Text driver, OEM or ANSI. |
| COLNAMEHEA DER | For the Text driver, indicates whether the first record of data will specify the column names. Either TRUE or FALSE. |
| COMPACT_DB | For the Microsoft Access driver, performs <u>data</u> <u>compaction</u> on a database file. |
| CREATE_DB | For the Microsoft Access driver, creates a database file. |
| DBQ | For the Microsoft Access , Btrieve , or Paradox driver, the name of the database file. For the Microsoft Excel 5 driver, the name of the workbook file. |
| DEFAULTDIR | The path specification to the database file (for the Microsoft Access driver) or directory (for the Btrieve, dBASE, Microsoft Excel, Microsoft FoxPro, Paradox, or Text driver). |
| DESCRIPTION | A description of the data in the data source. |
| DRIVER | The path specification to the driver DLL. |
| DRIVERID | An integer ID for the driver. 25 (Microsoft Access) 20 (Btrieve) 21 (dBASEIII) 277 (dBASEIV) 534 (Microsoft Excel3) 278 (Microsoft Excel4) 22 (Microsoft Excel5) 24 (Microsoft FoxPro2.0) 280 (Microsoft FoxPro2.5) 536 (Microsoft FoxPro2.6) 26 (Paradox3) 282 (Paradox4) 27 (Toxt) |
| EXCLUSIVE | 27 (Text) Determines whether the database will be opened in exclusive mode (accessed by only one user at a time) or shared mode (accessed by more than one user at a time). Can be true (exclusive mode) or false (shared mode). (This |

| | does not apply to the Microsoft Excel or Text driver.) |
|-----------------|---|
| EXTENSIONS | Lists the filename extensions of the Text files on the data source. |
| FIL | File type (MS Access for Microsoft Access; BTRIEVE; DBASE3 or DBASE4; EXCEL 3.0, 4.0, or 5.0 for Microsoft Excel; FOXPRO 2.0, 2.5, or 2.6 for Microsoft FoxPro; PARADOX 3.x or 4.x). (This does not apply to the Text driver.) |
| FILETYPE | File type for the Text driver (Text). |
| FORMAT | For the Text driver, can be FIXEDLENGTH, TABDELIMITED, CSVDELIMITED (by a comma), or DELIMITED() (by the special character specified in the parentheses). The special character is one character in length and can be in character, decimal, or hexadecimal format. |
| JETINIPATH | Path to the initialization file. |
| MAXSCANRO WS | For the Microsoft Excel or Text driver, the number of rows to be scanned when setting a column's data type based upon existing data. For the Microsoft Excel driver, you may enter a number from 1 to 16 for the rows to scan; however, the value will always default to 1. (A number outside the limit will return an error.) For the Text driver, you may enter a number from 1 to 32767 for the number of rows to scan; however, the value will always default to 1. (A number outside the limit will return an error.) |
| PWD | For the Microsoft Access or Paradox driver, the password. |
| READONLY | TRUE to make file read-only; FALSE to make file not read- only. |
| REPAIR_DB | For the Microsoft Access driver, <u>repairs a database</u> damaged by a failure that occurs during the commit process. |
| SYSTEMDB | For the Microsoft Access |

| | driver, the path specification to system database file. |
|-----|--|
| UID | For the Microsoft Access driver, the user ID name used for login. |

SQLDriverConnect Implementation (Programming)

The following table shows the minimum keywords required to connect to each driver, and provides an example of keyword/value pairs used with **SQLDriverConnect**. For a full list of DRIVERID values, see <u>SQLConfigDataSource Implementation</u>.

Note If DBQ or DefaultDir is not specified for the **Btrieve, dBASE, Excel 3/4, FoxPro, Paradox,** or **Text** driver, the driver will connect to the current directory.

| Driver | Keywords Required | Examples |
|-----------------------|--------------------------|---|
| Microsoft Access | Driver, DBQ | Driver={Microsoft Access Driver (*.mdb)}; DBQ=c:\temp\sample.mdb |
| Btrieve | Driver | Driver={Microsoft Btrieve Driver (file.dd)}; DBQ=c:\temp |
| dBASE | Driver, DriverID | Driver={Microsoft dBASE Driver (*.dbf)}; DBQ=c:\temp; DriverID=277 |
| Microsoft Excel3/4 | Driver, DriverID | Driver={Microsoft Excel Driver (*.xls)}; DBQ=c:\temp; DriverID=278 |
| Microsoft Excel5 | Driver, DriverID, DBQ | Driver={Microsoft Excel Driver (*.xls)}; DBQ=c:\temp\sample.xls;DriverID=22 |
| Microsoft FoxPro | Driver, DriverID | Driver={Microsoft FoxPro Driver (*.dbf)}; DBQ=c:\temp;DriverID=536 |
| Paradox | Driver, DriverID | Driver={Microsoft Paradox Driver (*.db); DBQ=c:\temp;DriverID=26 |
| Text | Driver | Driver={Microsoft Text Driver (*.txt;*.csv)}; DefaultDir=c:\temp |

Implementation Issues (Programming)

The following information might affect the use of the Microsoft ODBC drivers.

| Issue | | Implementation |
|----------------|------|---|
| Read-Only Sta | itus | When the Microsoft Excel or Text driver is used, data source tables are read-only. Even though tables have read-only status, however, applications can perform insertions and updates for Microsoft Excel tables, or insertions for Text tables. |
| Translation DI | Ls | Not Supported. |

API

Application programming interface. A set of routines that an application, such as Microsoft Access, uses to request and carry out lower-level services.

character set

A character set is a set of 256 letters, numbers, and symbols specific to a country or language. Each character set is defined by a table called a code page. An OEM (Original Equipment Manufacturer) character set is any character set except the ANSI character set. The ANSI character set (code page 1007) is the character set used by Microsoft Windows.

conformance level

Some applications can use only drivers that support certain levels of functionality, or conformance levels. For example, an application might require that drivers be able to prompt the user for the password for a data source. This ability is part of the Level 1 conformance level for the application programming interface (API).

Every ODBC driver conforms to one of three API levels (Core, Level 1, or Level 2) and one of three SQL grammar levels (Minimum, Core, or Extended). Drivers may support some of the functionality in levels above their stated level.

For detailed information about conformance levels, programmers should see the *Microsoft ODBC SDK Programmer's Reference*.

data source

A data source includes the data a user wants to access and the information needed to get to that data. Examples of data sources are:

• A SQL Server database, the server on which it resides, and the network used to access that server.

• A directory containing a set of dBASE files you want to access.

DBMS

Database management system. The software used to organize, analyze, search for, update, and retrieve data.

DDL

Data definition language. Any SQL statement that can be used to define data objects and their attributes. Examples include CREATE TABLE, DROP VIEW, and GRANT statements.

DLL

Dynamic-link library. A set of routines that one or more applications can use to perform common tasks. The ODBC drivers are DLLs.

DML

Data manipulation language. Any SQL statement that can be used to manipulate data. Examples include UPDATE, INSERT, and DELETE statements.

ODBC

Open Database Connectivity. A Driver Manager and a set of ODBC drivers that enable applications to access data using SQL as a standard language.

ODBC Driver Manager A dynamic-link library (DLL) that provides access to ODBC drivers.

ODBC driver

A dynamic-link library (DLL) that an ODBC-enabled application, such as Microsoft Excel, can use to gain access to a particular data source. Each database management system (DBMS), such as Microsoft SQL Server, requires a different driver.

SQL

Structured Query Language. A language used for retrieving, updating, and managing data.

SQL statement

A command written in Structured Query Language (SQL); also known as a query. An SQL statement specifies an operation to perform, such as SELECT, DELETE, or CREATE TABLE; the tables and columns on which to perform that operation; and any constraints to that operation.

translation option

An option that specifies how a translator translates data. For example, a translation option might specify the character sets between which a translator translates character data. It might also provide a key for encryption and decryption.

translator

A dynamic-link library (DLL) that translates all data passing between an application, such as Microsoft Access, and a data source. The most common use of a translator is to translate character data between different character sets. A translator can also perform tasks such as encryption and decryption or compression and expansion.