



## **Resource Compiler for Windows NT**

Microsoft Windows Resource Compiler (RC) is a tool for the Microsoft Windows NT operating system. This document describes how to create a resource-definition (script) file, and how to compile your application's resources and add them to the application's executable file.

### **Contents**

[Including Resources in an Application](#)

[Creating a Resource-Definition File](#)

[Preprocessing Directives](#)

[Single-Line Statements](#)

[Multiline Statements](#)

[Sample Resource-Definition File](#)

[Using RC \(The RC Command Line\)](#)

[Defining Names for the Preprocessor](#)

[Renaming the Compiled Resource File](#)

[Searching for Files](#)

[Displaying Progress Messages](#)

[Resource-Definition Statements](#)

[Common Statement Parameters](#)

[Common Resource Attributes](#)

[Statement Reference](#)

[Preprocessing Reference](#)

[RC Diagnostic Messages](#)



## Including Resources in an Application

To include resources in your 32-bit Windows application, do the following:

1. Create individual resource files for cursors, icons, bitmaps, dialog boxes, and fonts. To do this, you can use Microsoft Image Editor and Dialog Editor (IMAGEDIT.EXE and DLGEDIT.EXE) and Microsoft Windows Font Editor (FONTEDIT.EXE).
2. Create a resource-definition file (*script*) that describes all the resources used by the application.
3. Compile the script into a resource (.RES) file with RC.
4. Link the compiled resource files into the application's executable file.

Unlike for the 16-bit versions of the Windows development system, you do not use RC to include compiled resources into the executable file or to mark the file as a Windows application. The linker recognizes the compiled resource files and links them to the executable file.



## Creating a Resource-Definition File

After creating individual resource files for your application's icon, cursor, font, bitmap, and dialog-box resources, you create a resource-definition file, or *script*. A script file is a text file with the extension .RC.

The script lists every resource in your application and describes some types of resources in great detail. For a resource that exists in a separate file, such as an icon or cursor, the script names the resource and the file that contains it. For some resources, such as a menu, the entire definition of the resource exists within the script .

A script file can contain the following types of information:

- Preprocessing directives, which instruct RC to perform actions on the script before compiling it. Directives can also assign values to names.
- Statements, which name and describe resources.

The following sections describe directives and statements you can use in a script. For detailed descriptions and syntax for each statement, see "[Resource-Definition Statements](#)".



## Preprocessing Directives

The following directives can be used as needed in the script to instruct RC to perform actions or to assign values to names:

<b>Directive</b>	<b>Description</b>
<b><u>#define</u></b>	Defines a specified name by assigning it a given value.
<b><u>#elif</u></b>	Marks an optional clause of a conditional-compilation block.
<b><u>#else</u></b>	Marks the last optional clause of a conditional-compilation block.
<b><u>#endif</u></b>	Marks the end of a conditional-compilation block.
<b><u>#if</u></b>	Conditionally compiles the script if a specified expression is true.
<b><u>#ifdef</u></b>	Conditionally compiles the script if a specified name is defined.
<b><u>#ifndef</u></b>	Conditionally compiles the script if a specified name is not defined.
<b><u>#include</u></b>	Copies the contents of a file into the resource-definition file.
<b><u>e</u></b>	
<b><u>#undef</u></b>	Removes the definition of the specified name.

The syntax and semantics for the RC preprocessor is the same as for a C compiler. For more information on preprocessing in RC, see "[Preprocessing Reference](#)".



## Single-Line Statements

A single-line statement can begin with any of the following keywords:

<b>Keyword</b>	<b>Description</b>
<b><u>BITMAP</u></b>	Defines a bitmap by naming it and specifying the name of the file that contains it. (To use a particular bitmap, the application requests it by name.)
<b><u>CURSOR</u></b>	Defines a cursor by naming it and specifying the name of the file that contains it. (To use a particular cursor, the application requests it by name.)
<b><u>FONT</u></b>	Specifies the name of a file that contains a font.
<b><u>ICON</u></b>	Defines an icon by naming it and specifying the name of the file that contains it. (To use a particular icon, the application requests it by name.)
<b><u>LANGUAGE</u></b>	Sets the language for all resources up to the next <b>LANGUAGE</b> statement or to the end of the file. When the <b>LANGUAGE</b> statement appears before the <b>BEGIN</b> in an <b>ACCELERATORS</b> , <b>DIALOG</b> , <b>MENU</b> , <b>RCDATA</b> , or <b>STRINGTABLE</b> resource definition, the specified language applies only to that resource.
<b><u>MESSAGETABLE</u></b>	Defines a message table by naming it and specifying the name of the file that contains it. The file is a binary resource file generated by the Message Compiler.



## Multiline Statements

A multiline statement can begin with any of the following keywords:

<b>Keyword</b>	<b>Description</b>
<b><u>ACCELERATOR</u></b>	Defines menu accelerator keys.
<b><u>S</u></b>	
<b><u>DIALOG</u></b>	Defines a template that an application can use to create dialog boxes.
<b><u>MENU</u></b>	Defines the appearance and function of a menu.
<b><u>RCDATA</u></b>	Defines data resources. Data resources let you include binary data in the executable file.
<b><u>STRINGTABLE</u></b>	Defines string resources. String resources are Unicode strings that can be loaded from the executable file.

Each of these multiline statements allows optional statements before the **BEGIN ... END** block that defines the resource. You can specify zero or more of the following statements:

<b>Statement</b>	<b>Description</b>
<b><u>CHARACTERISTICS</u></b> <i>dword</i>	User-defined information about the resource that can be used by tools that read and write resource files. The value appears in the compiled resource file. However, it is not stored in the executable file and is not used by Windows.
<b><u>LANGUAGE</u></b> <i>language</i> , <i>sublanguage</i>	Specifies the language for the resource. The parameters are constants from WINNLS.H.
<b><u>VERSION</u></b> <i>dword</i>	User-defined version number for the resource that can be used by tools that read and write resource files. The value appears in the compiled resource file. However, it is not stored in the executable file and is not used by Windows.



## Sample Resource-Definition File

The following example shows a script file that defines the resources for an application named Shapes:

```
#include "SHAPES.H"

ShapesCursor  CURSOR  SHAPES.CUR
ShapesIcon    ICON    SHAPES.ICO

ShapesMenu    MENU
  BEGIN
    POPUP "&Shape"
      BEGIN
        MENUITEM "&Clear", ID_CLEAR
        MENUITEM "&Rectangle", ID_RECT
        MENUITEM "&Triangle", ID_TRIANGLE
        MENUITEM "&Star", ID_STAR
        MENUITEM "&Ellipse", ID_ELLIPSE
      END
    END
  END
```

The **CURSOR** statement names the application's cursor resource ShapesCursor and specifies the cursor file SHAPES.CUR, which contains the image for that cursor.

The **ICON** statement names the application's icon resource ShapesIcon and specifies the icon file SHAPES.ICO, which contains the image for that icon.

The **MENU** statement defines an application menu named ShapesMenu, a pop-up menu with five menu items.

The menu definition, enclosed by the **BEGIN** and **END** keywords, specifies each menu item and the menu identifier that is returned when the user selects that item. For example, the first item on the menu, Clear, returns the menu identifier ID\_CLEAR when the user selects it. The menu identifiers are defined in the application header file, SHAPES.H.



## Using RC (The RC Command Line)

To start RC, use the **RC** command. The following line shows **RC** command-line syntax:

**RC** [*options*] *script-file*

The **RC** command's *options* parameter can include one or more of the following options:

*/?*

Displays a list of **RC** command-line options.

*/d*

Defines a symbol for the preprocessor that you can test with the **#ifdef** directive.

*/foresname*

Uses *resname* for the name of the .RES file.

*/h*

Displays a list of **RC** command-line options.

*/i*

Searches the specified directory before searching the directories specified by the INCLUDE environment variable.

*/lcodepage*

Specifies default language for compilation. For example, -l409 is equivalent to including the following statement at the top of the resource script file:

```
LANGUAGE LANG_ENGLISH, SUBLANG_ENGLISH_US
```

*/r*

Ignored. Provided for compatibility with existing makefiles.

*/v*

Displays messages that report on the progress of the compiler.

*/x*

Prevents RC from checking the INCLUDE environment variable when searching for header files or resource files.

Options are not case-sensitive, and a hyphen (-) can be used in place of a slash mark (*/*). You can combine single-letter options if they do not require any additional parameters. For example, the following two commands are equivalent:

```
RC /V /X SAMPLE.RC
rc -vz sample.rc
```

The *script-file* parameter specifies the name of the resource-definition file that contains the names, types, filenames, and descriptions of the resources to be compiled.



## Defining Names for the Preprocessor

You can specify conditional compilation in a script, based on whether a name is defined on the **RC** command line with the **/d** option, or in the file or an include file with the **#define** directive.

For example, suppose your application has a pop-up menu, the Debug menu, that should appear only with debugging versions of the application. When you compile the application for normal use, the Debug menu is not included. The following example shows the statements that can be added to the resource-definition file to define the Debug menu:

```
MainMenu MENU
BEGIN
    . . .
#ifdef DEBUG
    POPUP "&Debug"
    BEGIN
        MENUITEM "&Memory usage", ID_MEMORY
        MENUITEM "&Walk data heap", ID_WALK_HEAP
    END
#endif
END
```

When compiling resources for a debugging version of the application, you could include the Debug menu by using the following **RC** command:

```
rc -d DEBUG myapp.rc
```

To compile resources for a normal version of the application—one that does not include the Debug menu—you could use the following **RC** command:

```
rc myapp.rc
```



## Renaming the Compiled Resource File

By default, when compiling resources, RC names the compiled resource (.RES) file with the base name of the .RC file and places it in the same directory as the .RC file. CVTRES must then be invoked to convert the .RES file to a binary resource format which can be understood by the linker (.RBJ). The following example compiles MYAPP.RC and creates a compiled resource file named MYAPP.RES in the same directory as MYAPP.RC:

```
rc myapp.rc
```

The **/fo** option lets you give the resulting .RES file a name that differs from the name of the corresponding .RC file. For example, to name the resulting .RES file NEWFILE.RES, you would use the following command:

```
rc -fo newfile.res myapp.rc
```

The **/fo** option can also place the .RES file in a different directory. For example, the following command places the compiled resource file MYAPP.RES in the directory C:\SOURCE\RESOURCE:

```
rc -fo c:\source\resource\myapp.res myapp.rc
```



## Searching for Files

By default, RC searches for header files and resource files (such as icon and cursor files) first in the current directory and then in the directories specified by the INCLUDE environment variable. (The PATH environment variable has no effect on which directories RC searches.)

## Adding a Directory to Search

You can use the */i* option to add a directory to the list of directories RC searches. The compiler then searches the directories in the following order:

1. The current directory
2. The directory or directories you specify by using the */i* option, in the order in which they appear on the **RC** command line
3. The list of directories specified by the INCLUDE environment variable, in the order in which the variable lists them, unless you specify the */x* option

The following example compiles the resource-definition file MYAPP.RC:

```
rc /i c:\source\stuff /i d:\resources myapp.rc
```

When compiling the script MYAPP.RC, RC searches for header files and resource files first in the current directory, then in C:\SOURCE\STUFF and D:\RESOURCES, and then in the directories specified by the INCLUDE environment variable.

## Suppressing the INCLUDE Environment Variable

You can prevent RC from using the INCLUDE environment variable when determining the directories to search. To do so, use the */x* option. The compiler then searches for files only in the current directory and in any directories you specify by using the */i* option.

The following example compiles the script file MYAPP.RC:

```
rc /x /i c:\source\stuff myapp.rc
```

When compiling the script MYAPP.RC, RC searches for header files and resource files first in the current directory and then in C:\SOURCE\STUFF. It does not search the directories specified by the INCLUDE environment variable.



## Displaying Progress Messages

By default, RC compiles quietly. It does not display messages that report on its progress. You can, however, specify that RC is to display these messages. To do so, use the `/v` option.

The following example causes RC to report on its progress as it compiles the resource-definition file `SAMPLE.RC` and creates the compiled resource file `SAMPLE.RES`:

```
rc /v sample.rc
```



## Resource-Definition Statements

This section describes the statements that define the resources that the Resource Compiler puts in the resource (.RES) file. Once a resource is linked to the executable file, the application can load the resource as it is needed at run time.

All resource statements associate an identifying name or number with a given resource.

[Common Statement Parameters](#)

[Common Resource Attributes](#)

[ACCELERATORS Resource](#)

[AUTO3STATE Control](#)

[AUTOCHECKBOX Control](#)

[AUTORADIOBUTTON Control](#)

[BITMAP Resource](#)

[CAPTION Statement](#)

[CHARACTERISTICS Statement](#)

[CHECKBOX Control](#)

[CLASS Statement](#)

[COMBOBOX Control](#)

[CONTROL: General Control](#)

[CTEXT Control](#)

[CURSOR Resource](#)

[DEFPUSHBUTTON Control](#)

[DIALOG Resource](#)

[DIALOGEX Resource](#)

[EDITTEXT Control](#)

[EXSTYLE Statement](#)

[FONT Resource](#)

[FONT Statement](#)

[GROUPBOX Control](#)

[ICON Resource](#)

[ICON Control](#)

[LANGUAGE Statement](#)

[LISTBOX Control](#)

[LTEXT Control](#)

[MENU Resource](#)

[MENU Statement](#)

[MENUEX Statement](#)

[MENUITEM Statement](#)

[MESSAGETABLE Resource](#)

[POPUP Resource](#)

[PUSHBOX Control](#)

[PUSHBUTTON Control](#)

[RADIOBUTTON Control](#)

[RCDATA](#)

[RTEXT Control](#)

[SCROLLBAR Control](#)

[STATE3 Control](#)

[STRINGTABLE Resource](#)

[STYLE Statement](#)

[User-Defined Resource](#)

[VERSION Statement](#)

VERSIONINFO Resource



## Common Statement Parameters

This section lists parameters in common among the resource or control statements. Occasionally, a certain statement will use a parameter differently, or may ignore a parameter. The statement-specific variation is described with the statement in the alphabetical reference.

## Common Control Parameters

The general syntax for a control definition, and the meaning of each parameter is as follows:

*control* [*text*,] *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]]

Horizontal dialog units are 1/4 of the dialog base width unit. Vertical units are 1/8 of the dialog base height unit. The current dialog base units are computed from the height and width of the current system font. The **GetDialogBaseUnits** function returns the dialog base units in pixels. The coordinates are relative to the origin of the dialog box.

### Parameters

#### *control*

Keyword that indicates the type of control being defined, such as **PUSHBUTTON** or **CHECKBOX**.

#### *text*

Specifies text that is displayed with the control. The text is positioned within the control's specified dimensions, or adjacent to the control.

This parameter must contain zero or more characters enclosed in double quotation marks. Strings are automatically null-terminated and converted to Unicode in the resulting resource file, except for strings specified in *raw-data* statements. (*raw-data* can be specified in **RCDATA** and user-defined resources.) To specify a Unicode string in *raw-data*, explicitly qualify the string as a wide-character string by using the **L** prefix.

By default, the characters listed between the double quotation marks are ANSI characters and escape sequences are interpreted as byte escape sequences. If the string is preceded by the **L** prefix, the string is a wide-character string and escape sequences are interpreted as two-byte escape sequences that specify Unicode characters. If a double quotation mark is required in the text, you must include the double quotation mark twice or use the \" escape sequence.

An ampersand (&) character in the text indicates that the following character is used as a mnemonic character for the control. When the control is displayed, the ampersand is not shown, but the mnemonic character is underlined. The user can choose the control by pressing the key corresponding to the underlined mnemonic character. To use the ampersand as a character in a string, insert two ampersands (&&).

#### *id*

Specifies the control identifier. This value must be a 16-bit unsigned integer in the range 0 through 65,535 or a simple arithmetic expression that evaluates to a value in that range.

#### *x*

Specifies the x-coordinate of the left side of the control relative to the left side of the dialog box. This value must be a 16-bit unsigned integer in the range 0 through 65,535. The coordinate is in dialog units and is relative to the origin of the dialog box, window, or control containing the specified control.

#### *y*

Specifies the y-coordinate of the top side of the control relative to the top of the dialog box. This value must be a 16-bit unsigned integer in the range 0 through 65,535. The coordinate is in dialog units relative to the origin of the dialog box, window, or control containing the specified control.

#### *width*

Specifies the width of the control. This value must be a 16-bit unsigned integer in the range 1

through 65,535. The width is in 1/4-character units.

*height*

Specifies the height of the control. This value must be a 16-bit unsigned integer in the range 1 through 65,535. The height is in 1/8-character units.

*style*

Specifies the control styles. Use the bitwise OR (|) operator to combine styles.

*extended-style*

Specifies extended (WS\_EX\_\*) styles. You must specify a *style* to specify an *extended-style*. See also **EXSTYLE**.

*text*

Specifies text that is displayed with the control. The text is positioned within the control's specified dimensions, or adjacent to the control.

This parameter must contain zero or more characters enclosed in double quotation marks. Strings are automatically null-terminated and converted to Unicode in the resulting resource file, except for strings specified in *raw-data* statements. (*raw-data* can be specified in **RCDATA** and user-defined resources.) To specify a Unicode string in *raw-data*, explicitly qualify the string as a wide-character string by using the **L** prefix.

By default, the characters listed between the double quotation marks are ANSI characters and escape sequences are interpreted as byte escape sequences. If the string is preceded by the **L** prefix, the string is a wide-character string and escape sequences are interpreted as two-byte escape sequences that specify Unicode characters. If a double quotation mark is required in the text, you must include the double quotation mark twice or use the \" escape sequence.

An ampersand (&) character in the text indicates that the following character is used as a mnemonic character for the control. When the control is displayed, the ampersand is not shown, but the mnemonic character is underlined. The user can choose the control by pressing the key corresponding to the underlined mnemonic character. To use the ampersand as a character in a string, insert two ampersands (&&).

*id*

Specifies the control identifier. This value must be a 16-bit unsigned integer in the range 0 through 65,535 or a simple arithmetic expression that evaluates to a value in that range.

x

Specifies the x-coordinate of the left side of the control relative to the left side of the dialog box. This value must be a 16-bit unsigned integer in the range 0 through 65,535. The coordinate is in dialog units and is relative to the origin of the dialog box, window, or control containing the specified control.

*y*

Specifies the y-coordinate of the top side of the control relative to the top of the dialog box. This value must be a 16-bit unsigned integer in the range 0 through 65,535. The coordinate is in dialog units relative to the origin of the dialog box, window, or control containing the specified control.

*width*

Specifies the width of the control. This value must be a 16-bit unsigned integer in the range 1 through 65,535. The width is in 1/4-character units.

*height*

Specifies the height of the control. This value must be a 16-bit unsigned integer in the range 1 through 65,535. The height is in 1/8-character units.

*style*

Specifies the control styles. Use the bitwise OR (|) operator to combine styles.

*extended-style*

Specifies extended (WS\_EX\_\*) styles. You must specify a *style* to specify an *extended-style*. See also **EXSTYLE**.



## Common Resource Attributes

All resource-definition statements include a *load-mem* option that specifies the loading and memory characteristics of the resource. These attributes are divided into two groups: load attributes and memory attributes. The only attribute that is used by Win32 is the **DISCARDABLE** attribute. The remaining attribute specifiers are allowed in the script for compatibility with existing scripts, but are ignored.

### Load Attributes

The load attributes specify when the resource is to be loaded. The load parameter must be one of the following:

#### **PRELOAD**

Ignored. In 16-bit Windows, the resource is loaded with the executable file.

#### **LOADONCALL**

Ignored. In 16-bit Windows, the resource is loaded when called.

### Memory Attributes

The memory attributes specify whether the resource is fixed or movable, whether it is discardable, and whether it is pure. The memory parameter can be one or more of the following:

#### **FIXED**

Ignored. In 16-bit Windows, the resource remains at a fixed memory location.

#### **MOVEABLE**

Ignored. In 16-bit Windows, the resource can be moved if necessary in order to compact memory.

#### **DISCARDABLE**

Resource can be discarded if no longer needed.

#### **PURE**

Ignored. Accepted for compatibility with existing resource scripts.

#### **IMPURE**

Ignored. Accepted for compatibility with existing resource scripts.

The default is **DISCARDABLE** for cursor, icon, and font resources.



## ACCELERATORS Resource

*acctablename* **ACCELERATORS**

[*optional-statements*]

**BEGIN**

*event, idvalue, [type] [options]*

...

**END**

The **ACCELERATORS** statement defines one or more accelerators for an application. An accelerator is a keystroke defined by the application to give the user a quick way to perform a task. The **TranslateAccelerator** function is used to translate accelerator messages from the application queue into WM\_COMMAND or WM\_SYSCOMMAND messages.

### Parameters

*acctablename*

Specifies either a unique name or a 16-bit unsigned integer value that identifies the resource.

*optional-statements*

Zero or more of the following statements:

<b>Statement</b>	<b>Description</b>
<b><u>CHARACTERISTICS</u></b> <i>dword</i>	User-defined information about a resource that can be used by tools that read and write resource files.
<b><u>LANGUAGE</u></b> <i>language, sublanguage</i>	Specifies the language for the resource. The parameters are constants from WINNLS.H.
<b><u>VERSION</u></b> <i>dword</i>	User-defined version number for the resource that can be used by tools that read and write resource files.

*event*

Specifies the keystroke to be used as an accelerator. It can be any one of the following character types:

"char"

A single character enclosed in double quotation marks. The character can be preceded by a caret (^), meaning that the character is a control character.

Character

An integer value representing a character. The *type* parameter must be **ASCII**.

Virtual-key character

An integer value representing a virtual key. The virtual key for alphanumeric keys can be specified by placing the uppercase letter or number in double quotation marks (for example, "9" or "C").

The *type* parameter must be **VIRTKEY**.

*idvalue*

Specifies a 16-bit unsigned integer value that identifies the accelerator.

*type*

Required only when the *event* parameter is a character or a virtual-key character. The *type* parameter specifies either **ASCII** or **VIRTKEY**; the integer value of *event* is interpreted accordingly.

When **VIRTKEY** is specified and *event* contains a string, *event* must be uppercase.

*options*

Specifies the options that define the accelerator. This parameter can be one or more of the following

values:

### **NOINVERT**

Specifies that no top-level menu item is highlighted when the accelerator is used. This is useful when defining accelerators for actions such as scrolling that do not correspond to a menu item. If **NOINVERT** is omitted, a top-level menu item will be highlighted (if possible) when the accelerator is used.

### **ALT**

Causes the accelerator to be activated only if the ALT key is down.

### **SHIFT**

Causes the accelerator to be activated only if the SHIFT key is down.

### **CONTROL**

Defines the character as a control character (the accelerator is only activated if the CONTROL key is down). This has the same effect as using a caret (^) before the accelerator character in the *event* parameter.

The **ALT**, **SHIFT**, and **CONTROL** options apply only to virtual keys.

### **Example**

The following example demonstrates the use of accelerator keys:

```
1 ACCELERATORS
BEGIN
  "^C",  IDDCLEAR           ; control C
  "K",   IDDCLEAR           ; shift K
  "k",   IDDELLIPSE, ALT   ; alt k
  98,    IDIRECT, ASCII    ; b
  66,    IDDSTAR, ASCII    ; B (shift b)
  "g",   IDIRECT           ; g
  "G",   IDDSTAR           ; G (shift G)
  VK_F1, IDDCLEAR, VIRTKEY ; F1
  VK_F1, IDDSTAR, CONTROL, VIRTKEY ; control F1
  VK_F1, IDDELLIPSE, SHIFT, VIRTKEY ; shift F1
  VK_F1, IDIRECT, ALT, VIRTKEY ; alt F1
  VK_F2, IDDCLEAR, ALT, SHIFT, VIRTKEY ; alt shift F2
  VK_F2, IDDSTAR, CONTROL, SHIFT, VIRTKEY ; ctrl shift F2
  VK_F2, IDIRECT, ALT, CONTROL, VIRTKEY ; alt control F2
END
```

### **See Also**

[TranslateAccelerator](#)

[Multiline Statements](#)

[CHARACTERISTICS](#), [LANGUAGE](#), [VERSION](#)

[ACCELERATORS](#), [DIALOG](#), [MENU](#), [RCDATA](#), [STRINGTABLE](#)



## **AUTO3STATE Control**

**AUTO3STATE** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]]

The **AUTO3STATE** statement creates an automatic 3-state check box. The control is an open box with the given text positioned to the right of the box. When chosen, the box automatically advances between three states: checked, unchecked, and disabled (grayed). The control sends a message to its parent whenever the user chooses the control.

### **Parameters**

#### *style*

Specifies styles for the control, which can be a combination of the BS\_AUTO3STATE style and the following styles: WS\_TABSTOP, WS\_DISABLED, and WS\_GROUP.

The default style for this control is BS\_AUTO3STATE and WS\_TABSTOP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "Common Statement Parameters".

### **See Also**

**AUTOCHECKBOX**, **CHECKBOX**, **CONTROL**, **STATE3**



## **AUTOCHECKBOX Control**

**AUTOCHECKBOX** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]

The **AUTOCHECKBOX** statement creates an automatic check box control. The control is a small rectangle (check box) that has the specified text displayed next to it (typically, to the right). When the user chooses the control, the control highlights the rectangle and sends a message to its parent window. The **AUTOCHECKBOX** statement, which can only be used in the body of a **DIALOG** statement, defines the text, identifier, dimensions, and attributes of the control.

### **Parameters**

#### *style*

Specifies the styles of the control. This value can be a combination of the button class style **BS\_AUTOCHECKBOX** and the **WS\_TABSTOP** and **WS\_GROUP** styles.

If you do not specify a style, the default style is **BS\_AUTOCHECKBOX** and **WS\_TABSTOP**.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### **See Also**

**AUTO3STATE**, **CHECKBOX**, **CONTROL**, **STATE3**



## **AUTORADIOBUTTON Control**

**AUTORADIOBUTTON** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]]

The **AUTORADIOBUTTON** control statement specifies an automatic radio button control. This control automatically performs mutual exclusion with the other **AUTORADIOBUTTON** controls in the same group. When the button is chosen, the application is notified with BN\_CLICKED

### **Parameters**

#### *text*

The specified text appears next to the radio button.

#### *style*

Specifies styles for the automatic radio button, which can be a combination of **BUTTON**-class styles and the following styles: WS\_TABSTOP, WS\_DISABLED, and WS\_GROUP.

The default style for **AUTORADIOBUTTON** is BS\_AUTORADIOBUTTON and WS\_TABSTOP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "Common Statement Parameters".

### **See Also**

**CONTROL**, **RADIOBUTTON**



## BITMAP Resource

*nameID* **BITMAP** [*load-mem*] *filename*

The **BITMAP** resource-definition statement specifies a bitmap that an application uses in its screen display or as an item in a menu or control.

### Parameters

*nameID*

Specifies either a unique name or a 16-bit unsigned integer value identifying the resource.

*load-mem*

Specifies loading and memory attributes for the resource. For more information, see "[Common Resource Attributes](#)".

*filename*

Specifies the name of the file that contains the resource. The name must be a valid filename; it must be a full path if the file is not in the current working directory. The path can either be a quoted or non-quoted string.

### Example

The following example specifies two bitmap resources:

```
disk1  BITMAP  disk.bmp
12     BITMAP  PRELOAD  diskette.bmp
```

### See Also

**LoadBitmap**



## **CAPTION Statement**

**CAPTION** *captiontext*

The **CAPTION** statement defines the title for a dialog box. The title appears in the box's caption bar (if it has one).

The default caption is empty.

### **Parameter**

*captiontext*

Specifies a character string enclosed in double quotation marks.

### **Example**

The following example demonstrates the use of the **CAPTION** statement:

```
CAPTION "Error!"
```



## **CHARACTERISTICS Statement**

### **CHARACTERISTICS** *dword*

The **CHARACTERISTICS** statement allows the developer to specify information about a resource that can be used by tools that read and write resource-definition files. The specified *dword* value appears with the resource in the compiled .RES file. However, the value is not stored in the executable file and has no significance to Windows.

The **CHARACTERISTICS** statement appears before the **BEGIN** in an **ACCELERATORS**, **DIALOG**, **MENU**, **RCDATA**, or **STRINGTABLE** resource definition. The specified value applies only to that resource.

### **Parameter**

*dword*

A user-defined doubleword value.

### **See Also**

Multiline Statements

**CHARACTERISTICS**, **LANGUAGE**, **VERSION**,  
**ACCELERATORS**, **DIALOG**, **MENU**, **RCDATA**, **STRINGTABLE**



## CHECKBOX Control

**CHECKBOX** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]]

The **CHECKBOX** statement creates a check box control. The control is a small rectangle (check box) that has the specified text displayed next to it (typically, to the right). When the user selects the control, the control highlights the rectangle and sends a message to its parent window. The **CHECKBOX** statement, which can only be used in a **DIALOG** statement, defines the text, identifier, dimensions, and attributes of the control.

### Parameters

#### *text*

Specifies text that is displayed to the right of the control.

#### *style*

Specifies the control styles. This value can be a combination of the button class style BS\_CHECKBOX and the WS\_TABSTOP and WS\_GROUP styles.

If you do not specify a style, the default style is BS\_CHECKBOX and WS\_TABSTOP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### Example

This example creates a check-box control that is labeled "Italic":

```
CHECKBOX "Italic", 3, 10, 10, 40, 10
```

### See Also

**AUTOCHECKBOX**, **AUTO3STATE**, **STATE3**, [GetDialogBaseUnits](#)



## CLASS Statement

**CLASS** *class*

The **CLASS** statement defines the class of the dialog box. The CLASS statement appears in the optional section before a **DIALOG** statement's **BEGIN** keyword. If no class is given, the Windows standard dialog class is used.

### Parameters

*class*

Specifies a 16-bit unsigned integer or a string, enclosed in double quotation marks, that identifies the class of the dialog box. If the window procedure for the class does not process a message sent to it, it must call the DefDlgProc function to ensure that all messages are handled properly for the dialog box. A private class can use DefDlgProc as the default window procedure. The class must be registered with the cbWndExtra member of the WNDCLASS structure set to DLGWINDOWEXTRA.

### Comments

The **CLASS** statement should only be used with special cases, since it overrides the normal processing of a dialog box. The **CLASS** statement converts a dialog box to a window of the specified class; depending on the class, this could give undesirable results. Do not use the redefined control-class names with this statement.

### Example

The following example demonstrates the use of the **CLASS** statement:

```
CLASS "myclass"
```

### See Also

DIALOG, DefDlgProc



## COMBOBOX Control

**COMBOBOX** *text, id, x, y, width, height* [, *style* [, *extended-style*]]

The **COMBOBOX** statement creates a combination box control (a combo box). A combo box consists of either a static text box or an edit box combined with a list box. The list box can be displayed at all times or pulled down by the user. If the combo box contains a static text box, the text box always displays the selection (if any) in the list box portion of the combo box. If it uses an edit box, the user can type in the desired selection; the list box highlights the first item (if any) that matches what the user has entered in the edit box. The user can then select the item highlighted in the list box to complete the choice. In addition, the combo box can be owner-drawn and of fixed or variable height.

### Parameters

#### *style*

Specifies the control styles. This value can be a combination of the COMBOBOX class styles and any of the following styles: WS\_TABSTOP, WS\_GROUP, WS\_VSCROLL, and WS\_DISABLED.

If you do not specify a style, the default style is CBS\_SIMPLE and WS\_TABSTOP.

For more information on the *text, id, x, y, width, height, style,* and *extended-style* parameters, see "[Common Statement Parameters](#)".

### Example

This example creates a combo-box control with a vertical scroll bar:

```
COMBOBOX 777, 10, 10, 50, 54, CBS_SIMPLE | WS_VSCROLL | WS_TABSTOP
```



## CONTROL: General Control

**CONTROL** *text, id, class, style, x, y, width, height* [, *extended-style*]

This statement defines a user-defined control window.

### Parameters

#### *class*

Specifies a redefined name, character string, a 16-bit unsigned integer value that defines the class. This can be any one of the control classes; for a list of the control classes, see the first list following this description. If the value is a redefined name supplied by the application, it must be a string enclosed in double quotation marks.

#### *style*

Specifies a redefined name or integer value that specifies the style of the given control. The exact meaning of *style* depends on the *class* value. The sections following this description show the control classes and corresponding styles.

For more information on the *text, id, x, y, width, height, style,* and *extended-style* parameters, see "[Common Statement Parameters](#)".

The six possible control classes are described in the following sections.

## The Button Control Class

A button control is a small rectangular child window that represents a "button" that the user can turn on or off by clicking it with the mouse. Button controls can be used alone or in groups, and can either be labeled or appear without text. Button controls typically change appearance when the user clicks them.

A button can have only one of the following styles, with the exception of BS\_LEFTTEXTBS, which can be combined with check boxes and radio buttons.

### **BS\_3STATE**

Creates a button that is the same as a check box, except that the box can be grayed (dimmed) as well as checked. The grayed state is used to show that the state of the check box is not determined.

### **BS\_AUTO3STATE**

Creates a button that is the same as a three-state check box, except that the box changes its state when the user selects it. The state cycles through checked, grayed, and normal.

### **BS\_AUTOCHECKBOX**

Creates a button that is the same as a check box, except that an X appears in the check box when the user selects the box; the X disappears (is cleared) the next time the user selects the box.

### **BS\_AUTORADIOBUTTON**

Creates a button that is the same as a radio button, except that when the user selects it, the button automatically highlights itself and clears (removes the selection from) any other buttons in the same group.

### **BS\_CHECKBOX**

Creates a small square that has text displayed to its right (unless this style is combined with the BS\_LEFTTEXT style).

### **BS\_DEFPUSHBUTTON**

Creates a button that has a heavy black border. The user can select this button by pressing the ENTER key. This style is useful for enabling the user to quickly select the most likely option (the default option).

### **BS\_GROUPBOX**

Creates a rectangle in which other controls can be grouped. Any text associated with this style is

displayed in the rectangle's upper-left corner.

#### **BS\_LEFTTEXT**

Places text on the left side of the radio button or check box when combined with a radio button or check box style.

#### **BS\_OWNERDRAW**

Creates an owner-drawn button. The owner window receives a WM\_MEASUREITEM message when the button is created, and it receives a WM\_DRAWITEM message when a visual aspect of the button has changed. The BS\_OWNERDRAW style cannot be combined with any other button styles.

#### **BS\_PUSHBUTTON**

Creates a push button that posts a WM\_COMMAND message to the owner window when the user selects the button.

#### **BS\_RADIOBUTTON**

Creates a small circle that has text displayed to its right (unless this style is combined with the BS\_LEFTTEXT style). Radio buttons are usually used in groups of related but mutually exclusive choices.

### **The Combobox Control Class**

Combo-box controls consist of a selection field similar to an edit control plus a list box. The list box may be displayed at all times or may be dropped down when the user selects a "pop box" next to the selection field.

Depending on the style of the combo box, the user can or cannot edit the contents of the selection field. If the list box is visible, typing characters into the selection box will cause the first list-box entry that matches the characters typed to be highlighted. Conversely, selecting an item in the list box displays the selected text in the selection field. Combo-box control styles are described below.

#### **CBS\_SIMPLE**

Displays the list box at all times. The current selection in the list box is displayed in the edit control.

#### **CBS\_DROPDOWN**

Similar to CBS\_SIMPLE except that the list box is not displayed unless the user selects an icon next to the selection field.

#### **CBS\_DROPDOWNLIST**

Similar to CBS\_DROPDOWN except that the edit control is replaced by a static text item which displays the current selection in the list box.

#### **CBS\_OWNERDRAWFIXED**

Specifies a fixed-height owner-draw combo box. The owner of the list box is responsible for drawing its contents; the items in the list box are all the same height.

#### **CBS\_OWNERDRAWVARIABLE**

Specifies a variable-height owner-draw combo box. The owner of the list box is responsible for drawing its contents; the items in the list box can have different heights.

#### **CBS\_AUTOHSCROLL**

Scrolls the text in the edit control to the right when the user types a character at the end of the line. If this style is not set, only text that fits within the rectangular boundary is allowed.

#### **CBS\_SORT**

Sorts strings entered into the list box.

#### **CBS\_HASSTRINGS**

Specifies an owner-draw combo box that contains items consisting of strings. The combo box maintains the memory and pointers for the strings so that the application can use the LB\_GETTEXT message to retrieve the text for a particular item.

#### **CBS\_OEMCONVERT**

Converts text entered in the combo box edit control from the ANSI character set to the OEM character set and then back to ANSI. This ensures proper character conversion when the application

calls the **CharToOem** function to convert an ANSI string in the combo box to OEM characters. This style is most useful for combo boxes that contain filenames and applies only to combo boxes created with the CBS\_SIMPLE or CBS\_DROPDOWN styles.

## The Edit Control Class

An edit control is a rectangular child window in which the user can enter text from the keyboard. The user selects the control, and gives it the input focus, by clicking the mouse inside it or pressing the TAB key. The user can enter text when the control displays a flashing insertion point. The mouse can be used to move the cursor and select characters to be replaced, or to position the cursor for inserting characters. The BACKSPACE key can be used to delete characters.

Edit controls use the fixed-pitch font and display Unicode characters. They expand tab characters into as many space characters as are required to move the cursor to the next tab stop. Tab stops are assumed to be at every eighth character position. Edit control styles are described below.

### **ES\_LEFT**

Justifies the text to the left.

### **ES\_CENTER**

Centers the text. This style is valid in multiline edit controls only.

### **ES\_RIGHT**

Justifies the text to the right. This style is valid in multiline edit controls only.

### **ES\_LOWERCASE**

Converts all characters to lowercase as they are typed into the edit control.

### **ES\_UPPERCASE**

Converts all characters to uppercase as they are typed into the edit control.

### **ES\_PASSWORD**

Displays all characters as an asterisk (\*) as they are typed into the edit control. An application can use the **EM\_SETPASSWORDCHAR** message to change the character that is displayed.

### **ES\_MULTILINE**

Multiple-line edit control. (The default is single-line.) Shows as many lines of text as possible. The following four styles specify options for horizontal and vertical scrolling.

#### **ES\_AUTOVSCROLL** specified

Shows as many lines as possible and scrolls vertically when the user presses the ENTER key. (This is actually the carriage-return character, which the edit control expands to a carriage-return/line-feed combination.)

#### **ES\_AUTOVSCROLL** not specified

Shows as many lines as possible and beeps if the user presses ENTER when no more lines can be displayed.

#### **ES\_AUTOHSCROLL** specified

Scrolls horizontally when the insertion point goes past the right edge of the control. To start a new line, press the ENTER key.

#### **ES\_AUTOHSCROLL** not specified

Wraps words to the beginning of the next line when necessary. A new line is also started if the user presses ENTER. If the window size changes, the word wrap position changes, and the text is redisplayed.

Multiple-line edit controls can have scroll bars. An edit control with scroll bars processes its own scroll-bar messages. Edit controls without scroll bars scroll as described above, and process any scroll messages sent by the parent window.

### **ES\_AUTOVSCROLL**

Scrolls text automatically up one page when the user presses the ENTER key on the last line.

### **ES\_AUTOHSCROLL**

Scrolls text automatically to the right by 10 characters when the user types a character at the end of

the line. When the user presses the ENTER key, the control scrolls all text back to position 0.

#### **ES\_NOHIDSEL**

Overrides the default action, in which an edit control hides the selection when the control loses the input focus. Inverts the selection instead.

#### **ES\_OEMCONVERT**

Converts text entered in the edit control from the ANSI character set to the OEM character set and then back to ANSI. This ensures proper character conversion when the application calls the **CharToOem** function to convert an ANSI string in the edit control to OEM characters. This style is most useful for edit controls that contain filenames.

### **The Listbox Control Class**

Listbox controls consist of a list of character strings. The control is used whenever an application needs to present a list of names, such as filenames, that the user can view and select. The user can select a string by pointing to the string with the mouse and clicking a mouse button. When a string is selected, it is highlighted and a notification message is passed to the parent window. A scroll bar can be used with a listbox control to scroll lists that are too long or too wide for the control window. Listbox control styles are described below.

#### **LBS\_STANDARD**

Strings in the list box are sorted alphabetically and the parent window receives an input message whenever the user clicks or double-clicks a string. The list box contains borders on all sides.

#### **LBS\_DISABLENOSCROLL**

Shows a disabled vertical scroll bar for the list box when the box does not contain enough items to scroll. If this style is not specified, the scroll bar is hidden when the list box does not contain enough items.

#### **LBS\_EXTENDEDSEL**

The user can select multiple items using the mouse with the SHIFT and/or the CONTROL key or special key combinations.

#### **LBS\_HASSTRINGS**

An owner-draw list box contains items consisting of strings. The list box maintains the memory and pointers for the strings so the application can use the **LB\_GETTEXT** message to retrieve the text for a particular item.

#### **LBS\_NOTIFY**

The parent receives an input message whenever the user clicks or double-clicks a string.

#### **LBS\_MULTIPLESEL**

The string selection is toggled each time the user clicks or double-clicks the string. Any number of strings can be selected.

#### **LBS\_MULTICOLUMN**

The list box contains multiple columns. The list box can be scrolled horizontally. The **LB\_SETCOLUMNWIDTH** message sets the width of the columns.

#### **LBS\_NOINTEGRALHEIGHT**

The size of the list box is exactly the size specified by the application when it created the list box. Normally, Windows sizes a list box so that the list box does not display partial items.

#### **LBS\_SORT**

The strings in the list box are sorted alphabetically.

#### **LBS\_NOREDRAW**

The list-box display is not updated when changes are made. This style can be changed at any time by sending a **WM\_SETREDRAW** message.

#### **LBS\_OWNERDRAWFIXED**

The owner of the list box is responsible for drawing its contents; the items in the list box are all the same height.

#### **LBS\_OWNERDRAWVARIABLE**

The owner of the list box is responsible for drawing its contents; the items in the list box are variable in height.

### **LBS\_USETABSTOPS**

The list box is able to recognize and expand tab characters when drawing its strings. The default tab positions are set at every 32 dialog units. (A dialog unit is a horizontal or vertical distance. One horizontal dialog unit is equal to 1/4 of the current dialog base width unit. The dialog base units are computed from the height and width of the current system font. The [GetDialogBaseUnits](#) function returns the size of the dialog base units in pixels.)

### **LBS\_WANTKEYBOARDINPUT**

The owner of the list box receives WM\_VKEYTOITEM or WM\_CHARTOITEM messages whenever the user presses a key when the list box has input focus. This allows an application to perform special processing on the keyboard input.

## **The Scrollbar Control Class**

A scroll-bar control is a rectangle that contains a scroll thumb and has direction arrows at both ends. The scroll bar sends a notification message to its parent whenever the user clicks the mouse in the control. The parent is responsible for updating the thumb position, if necessary. Scroll-bar controls have the same appearance and function as the scroll bars used in ordinary windows. But unlike scroll bars, scroll-bar controls can be positioned anywhere within a window and used whenever needed to provide scrolling input for a window. Scroll bar control styles are described below.

### **SBS\_VERT**

Vertical scroll bar. If neither SBS\_RIGHTALIGN nor SBS\_LEFTALIGN is specified, the scroll bar has the height, width, and position given in the [CreateWindow](#) function.

### **SBS\_RIGHTALIGN**

Used with SBS\_VERT. The right edge of the scroll bar is aligned with the right edge of the rectangle specified by the *x*, *y*, *width*, and *height* values given in the [CreateWindow](#) function. The scroll bar has the default width for system scroll bars.

### **SBS\_LEFTALIGN**

Used with SBS\_VERT. The left edge of the scroll bar is aligned with the left edge of the rectangle specified by the *x*, *y*, *width*, and *height* values given in the [CreateWindow](#) function. The scroll bar has the default width for system scroll bars.

### **SBS\_HORZ**

Horizontal scroll bar. If neither SBS\_BOTTOMALIGN nor SBS\_TOPALIGN is specified, the scroll bar has the height, width, and position given in the [CreateWindow](#) function.

### **SBS\_TOPALIGN**

Used with SBS\_HORZ. The top edge of the scroll bar is aligned with the top edge of the rectangle specified by the *x*, *y*, *width*, and *height* values given in the [CreateWindow](#) function. The scroll bar has the default height for system scroll bars.

### **SBS\_BOTTOMALIGN**

Used with SBS\_HORZ. The bottom edge of the scroll bar is aligned with the bottom edge of the rectangle specified by the *x*, *y*, *width*, and *height* values given in the [CreateWindow](#) function. The scroll bar has the default height for system scroll bars.

### **SBS\_SIZEBOX**

Size box. If neither SBS\_SIZEBOXBOTTOMRIGHTALIGN nor SBS\_SIZEBOXTOPLEFTALIGN is specified, the size box has the height, width, and position given in the [CreateWindow](#) function.

### **SBS\_SIZEBOXTOPLEFTALIGN**

Used with SBS\_SIZEBOX. The top-left corner of the size box is aligned with the top-left corner of the rectangle specified by the *x*, *y*, *width*, and *height* values given in the [CreateWindow](#) function. The size box has the default size for system size boxes.

### **SBS\_SIZEBOXBOTTOMRIGHTALIGN**

Used with SBS\_SIZEBOX. The bottom-right corner of the size box is aligned with the bottom-right

corner of the rectangle specified by the *x*, *y*, *width*, and *height* values given in the CreateWindow function. The size box has the default size for system size boxes.

## The Static Control Class

Static controls are simple text fields, boxes, and rectangles that can be used to label, box, or separate other controls. Static controls take no input and provide no output. Static control styles are described below.

### SS\_LEFT

A simple rectangle displaying the given text flush left. The text is formatted before it is displayed. Words that would extend past the end of a line are automatically wrapped to the beginning of the next line.

### SS\_CENTER

A simple rectangle displaying the given text centered. The text is formatted before it is displayed. Words that would extend past the end of a line are automatically wrapped to the beginning of the next line.

### SS\_RIGHT

A simple rectangle displaying the given text flush right. The text is formatted before it is displayed. Words that would extend past the end of a line are automatically wrapped to the beginning of the next line.

### SS\_LEFTNOWORDWRAP

A simple rectangle displaying the given text flush left. Tabs are expanded, but words are not wrapped. Text that extends past the end of a line is clipped.

### SS\_SIMPLE

A simple rectangle with a single line of text flush left. The line of text cannot be shortened or altered in any way. (The control's parent window or dialog box must not process the WM\_CTLCOLOR message.)

### SS\_NOPREFIX

Removes any (&) characters and underlines the next character in the string. Unless this style is specified, Windows will interpret any (&) characters in the control's text to be accelerator prefix characters. If a static control is to contain text where this feature is not wanted, SS\_NOPREFIX may be added. This STATIC-control style may be included with any of the defined STATIC controls.

You can combine SS\_NOPREFIX with other styles by using the bitwise OR operator. This is most often used when filenames or other strings that may contain an (&) need to be displayed in a static control in a dialog box.

### SS\_ICON

An icon displayed in the dialog box. The given text is the name of an icon (not a filename) defined elsewhere in the resource file. For the **ICON** statement, the *width* and *height* parameters in the CreateWindow function are ignored; the icon automatically sizes itself.

### SS\_BLACKRECT

A rectangle filled with the color used to draw window frames. This color is black in the default Windows color scheme.

### SS\_GRAYRECT

A rectangle filled with the color used to fill the screen background. This color is gray in the default Windows color scheme.

### SS\_WHITERECT

A rectangle filled with the color used to fill window backgrounds. This color is white in the default Windows color scheme.

### SS\_BLACKFRAME

Box with a frame drawn with the same color as window frames. This color is black in the default Windows color scheme.

### SS\_GRAYFRAME

Box with a frame drawn with the same color as the screen background (desktop). This color is gray in the default Windows color scheme.

**SS\_WHITEFRAME**

Box with a frame drawn with the same color as window backgrounds. This color is white in the default Windows color scheme.

**SS\_USERITEM**

User-defined item.



## CTEXT Control

**CTEXT** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]]

The **CTEXT** statement creates a centered-text control. The control is a simple rectangle displaying the given text centered in the rectangle. The text is formatted before it is displayed. Words that would extend past the end of a line are automatically wrapped to the beginning of the next line. The **CTEXT** statement, which you can use only in a **DIALOG** statement, defines the text, identifier, dimensions, and attributes of the control.

### Parameters

#### *text*

Specifies text that is centered in the rectangular area of the control.

#### *style*

Specifies the control styles. This value can be any combination of the following styles: SS\_CENTER, WS\_TABSTOP, and WS\_GROUP.

If you do not specify a style, the default style is SS\_CENTER and WS\_GROUP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### Example

This example creates a centered-text control that is labeled "filename":

```
CTEXT "filename", 101, 10, 10, 100, 100
```

### See Also

[CONTROL](#), [DIALOG](#), [LTEXT](#), [RTEXT](#)



## CURSOR Resource

*nameID* **CURSOR** [*load-mem*] *filename*

The **CURSOR** statement specifies a bitmap that defines the shape of the cursor on the display screen.

### Parameters

*nameID*

Specifies either a unique name or a 16-bit unsigned integer identifying the resource.

*load-mem*

Specifies loading and memory attributes for the resource. For more information, see "[Common Resource Attributes](#)".

*filename*

Specifies the name of the file that contains the resource. The name must be a valid filename; it must be a full path if the file is not in the current working directory. The path can either be a quoted or non-quoted string.

### Comments

Icon and cursor resources can contain more than one image. If the resource is marked with the **PRELOAD** option, Windows loads all images in the resource when the application executes.

### Example

The following example specifies two cursor resources; one by name (cursor1) and the other by number (2):

```
cursor1 CURSOR bullseye.cur
2      CURSOR "d:\\cursor\\arrow.cur"
```



## DEFPUSHBUTTON Control

**DEFPUSHBUTTON** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]]

The **DEFPUSHBUTTON** statement creates a default push-button control. The control is a small rectangle with a bold outline that represents the default response for the user. The given text is displayed inside the button. The control highlights the button in the usual way when the user clicks the mouse in it and sends a message to its parent window.

### Parameters

#### *text*

Specifies text that is centered in the rectangular area of the control.

#### *style*

Specifies the control styles. This value can be a combination of the following styles:

BS\_DEFPUSHBUTTON, WS\_TABSTOP, WS\_GROUP, and WS\_DISABLED.

If you do not specify a style, the default style is BS\_DEFPUSHBUTTON and WS\_TABSTOP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### Example

This example creates a default push-button control that is labeled "Cancel":

```
DEFPUSHBUTTON "Cancel", 101, 10, 10, 24, 50
```

### See Also

**PUSHBUTTON**, **RADIOBUTTON**



## DIALOG Resource

*nameID* **DIALOG** [*load-mem*] *x*, *y*, *width*, *height*  
[*optional-statements*]

### **BEGIN**

*control-statement*

...

### **END**

The **DIALOG** statement defines a window that an application can use to create dialog boxes. The statement defines the position and dimensions of the dialog box on the screen as well as the dialog box style.

#### *nameID*

Identifies the dialog box. This is either a unique name or a unique 16-bit unsigned integer value in the range 1 to 65,535.

#### *load-mem*

Specifies loading and memory attributes for the resource. For more information, see "[Common Resource Attributes](#)".

#### *option-statements*

Specifies options for the dialog box. This can be zero or more of the following statements:

#### **CAPTION** "*text*"

Specifies the caption of the dialog box if it has a title bar. See [CAPTION](#) for more information.

#### **CHARACTERISTICS** *dword*

Specifies a user-defined double-word value for use by resource tools. This value is not used by Windows. For more information, see [CHARACTERISTICS](#).

#### **CLASS** *class*

Specifies a 16-bit unsigned integer or a string, enclosed in double quotation marks, that identifies the class of the dialog box. See [CLASS](#) for more information.

#### **LANGUAGE** *language, sublanguage*

Specifies the language of the dialog box. See [LANGUAGE](#) for more information.

#### **STYLE** *styles*

Specifies the styles of the dialog box. See [STYLE](#) for more information.

#### **EXSTYLE**=*extended-styles*

Specifies the extended styles of the dialog box. See [EXSTYLE](#) for more information.

#### **VERSION** *dword*

Specifies a user-defined doubleword value. This statement is intended for use by additional resource tools and is not used by Windows. For more information, see [VERSION](#).

For more information on the *x*, *y*, *width*, and *height* parameters, see "[Common Statement Parameters](#)".

## Comments

The [GetDialogBaseUnits](#) function returns the dialog base units in pixels. The exact meaning of the coordinates depends on the style defined by the **STYLE** option statement. For child-style dialog boxes, the coordinates are relative to the origin of the parent window, unless the dialog box has the style DS\_ABSALIGN; in that case, the coordinates are relative to the origin of the display screen.

Do not use the WS\_CHILD style with a modal dialog box. The [DialogBox](#) function always disables the parent/owner of the newly created dialog box. When a parent window is disabled, its child windows are implicitly disabled. Since the parent window of the child-style dialog box is disabled, the child-style dialog box is too.

If a dialog box has the DS\_ABSALIGN style, the dialog coordinates for its upper-left corner are relative to the screen origin instead of to the upper-left corner of the parent window. You would typically use this style when you wanted the dialog box to start in a specific part of the display no matter where the parent window may be on the screen.

The name **DIALOG** can also be used as the class-name parameter to the CreateWindow function to create a window with dialog box attributes.

### Example

The following demonstrates the usage of the **DIALOG** statement:

```
#include <windows.h>

ErrorDialog DIALOG 10, 10, 300, 110
STYLE WS_POPUP|WS_BORDER
CAPTION "Error!"
BEGIN
    CTEXT "Select One:", 1, 10, 10, 280, 12
    PUSHBUTTON "&Retry", 2, 75, 30, 60, 12
    PUSHBUTTON "&Abort", 3, 75, 50, 60, 12
    PUSHBUTTON "&Ignore", 4, 75, 80, 60, 12
END
```

### See Also

**CONTROL**, **CreateDialog**, **CreateWindow**, **DialogBox**, **GetDialogBaseUnits**  
**Multiline Statements**  
**CHARACTERISTICS**, **LANGUAGE**, **VERSION**  
**ACCELERATORS**, **DIALOG**, **MENU**, **RCDATA**, **STRINGTABLE**



## DIALOGEX Resource

The **DIALOGEX** resource is an extension of the **DIALOG** resource. In addition to the functionality offered by **DIALOG**, **DIALOGEX** allows for the following:

- Help IDs on the dialog itself as well as on controls within the dialog.
- Use of the **EXSTYLE** statement for the dialog itself as well as on controls within the dialog.
- Font weight and italic settings for the font to be used in the dialog.
- Control-specific data for controls within the dialog.
- Use of the BEDIT, IEDIT, and HEDIT predefined system class names.

### Syntax

```
nameID DIALOGEX [ load-mem] x, y, width, height [ , helpID]  
  [ optional-statements]  
  BEGIN  
    control-statement  
    . . .  
  END
```

### Parameters

#### *nameID*

Identifies the dialog box. This is either a unique name or a unique 16-bit unsigned integer value in the range 1 to 65,535.

#### *load-mem*

Specifies loading and memory attributes for the resource. For more information, see [Common Resource Attributes](#).

#### *x*

Specifies the location on the screen of the left side of the dialog, in dialog units.

#### *y*

Specifies the location on the screen of the top of the dialog, in dialog units.

#### *width*

Specifies the width of the dialog, in dialog units.

#### *height*

Specifies the height of the dialog, in dialog units.

#### *helpID*

Specifies a numeric expression indicating the ID used to identify the dialog during WM\_HELP processing.

#### *optional-statements*

Specifies options for the dialog box. This can be zero or more of the following statements:

##### **CAPTION** "*text*"

Specifies the caption of the dialog box if it has a title bar. See [CAPTION](#) for more information.

##### **CHARACTERISTICS** *DWORD*

Specifies a user-defined DWORD value for use by resource tools. This value is not used by Windows. For more information see [CHARACTERISTICS](#)

##### **CLASS** *class*

Specifies a 16-bit unsigned integer or a string, enclosed in double quotation marks ("), that identifies the class of the dialog box. See [CLASS](#) for more information.

##### **EXSTYLE**=*extended-styles*

Specifies the extended styles of the dialog box. See **EXSTYLE** for more information.

**FONT** *pointsize, typeface, weight, italic*

*pointsize*

Specifies the size, in points, of the font.

*typeface*

Specifies the name of the typeface. This name must be identical to the name defined in the [FONTS] section of WIN.INI. This parameter must be enclosed in double quotation marks ("").

*weight*

Specifies a numeric expression for the font weight (explicit FW\_\* values defined in WINGDI.H can be used by adding an include to the RC file: **#include "WINGDI.H"**)

*italic*

Indicates whether the font should be italic or not. Specify either TRUE or FALSE for the *italic* value.

**LANGUAGE** *language, sublanguage*

Specifies the language of the dialog box. See **LANGUAGE** for more information.

**MENU** *menuname*

Specifies the menu to use. This value is either the name of the menu or the integer identifier.

**STYLE** *styles*

Specifies the styles of the dialog box. See **STYLE** for more information.

**VERSION** *DWORD*

Specifies a user-defined **DWORD** value. This statement is intended for use by additional resource tools and is not used by Windows. For more information, see **VERSION**

The **DIALOGEX** body is marked with a **BEGIN** statement at the beginning of the body and an **END** statement at the end of the body. The body is made up of any number of control statements. There are four families of control statements: generic, static, button, and edit. While each of these families uses a different syntax for defining specific features of its controls, they all share a common syntax for defining the position, size, extended styles, help identification number, and control-specific data. That common syntax is:

*(controlType), x, y, cx, cy [, [exStyle] [, helpID]*

**[BEGIN**

*data-element-1 [,*

*data-element-2 [,*

*... ]]*

**END]**

*(controlType)*

Family-specific definition – described below.

*x*

Specifies the location in the dialog of the left side of the control, in dialog units.

*y*

Specifies the location in the dialog of the top of the control, in dialog units.

*cx*

Specifies the width of the control, in dialog units.

*cy*

Specifies the height of the control, in dialog units.

*exStyle*

Specifies any number of extended window styles (explicit WS\_EX\_\* style values defined in winuser.h can be used by adding an include to the RC file: **#include "winuser.h"**)

*helpID*

Specifies a numeric expression indicating the ID used to identify the control during WM\_HELP processing.

#### *controlData*

Marked by a nested **BEGIN** and **END**, specifies the control-specific data for the control. When a dialog is created, and a control in that dialog which has control-specific data is created, a pointer to that data is passed into the control's window procedure via the *IParam* to the WM\_CREATE message for that control.

Following is the family-specific syntax of the (*controlType*):

#### **Generic control:**

**CONTROL** *controlText, id, className, style*

##### *controlText*

Specifies the window text for the control. For more information, see [Common Statement Parameters](#).

##### *id*

Specifies the control identifier. For more information, see [Common Statement Parameters](#).

##### *className*

Specifies the name of the class. This may be either a string enclosed in double quotation marks ("") or one of the following predefined system classes: BUTTON, STATIC, EDIT, LISTBOX, SCROLLBAR, or COMBOBOX.

##### *style*

Specifies the window styles (explicit WS\_\*, BS\_\*, SS\_\*, ES\_\*, LBS\_\*, SBS\_\*, and CBS\_\* style values defined in WINUSER.H can be used by adding an include to the RC file: **#include** "WINUSER.H")

#### **Static control:**

**staticClass** *controlText, id*

*staticClass* {LTEXT | RTEXT | CTEXT}

##### *controlText*

Specifies the window text for the control. For more information, see "Common Statement Parameters".

##### *id*

Specifies the control identifier. For more information, see "Common Statement Parameters".

#### **Button control:**

**buttonClass** *controlText, id*

*buttonClass* {AUTO3STATE | AUTOCHECKBOX | AUTORADIOBUTTON | CHECKBOX | PUSHBOX | PUSHBUTTON | RADIOBUTTON | STATE3 | USERBUTTON}

##### *controlText*

Specifies the window text for the control. For more information, see "Common Statement Parameters".

##### *id*

Specifies the control identifier. For more information, see "Common Statement Parameters".

#### **Edit control:**

**editClass** *id*

*editClass* {EDITTEXT | BEDIT | HEDIT | IEDIT}

##### *id*

Specifies the control identifier. For more information, see "Common Statement Parameters".

#### **Arithmetic and Boolean Operations**

Valid operations that may be contained in any of the numeric expressions in the statements of **DIALOGEX** are:

- Add ('+')
- Subtract ('-')
- Unary minus ('-')
- Unary NOT ('~')
- AND ('&')
- OR ('|')

**See Also**

[CONTROL](#), [CreateDialog](#), [CreateWindow](#), [DialogBox](#), [GetDialogBaseUnits](#), [Multiline Statements](#), [ACCELERATORS](#), [CHARACTERISTICS](#), [LANGUAGE](#), [MENU](#), [RCDATA](#), [STRINGTABLE](#), [VERSION](#)



## EDITTEXT Control

**EDITTEXT** *text, id, x, y, width, height* [, *style* [, *extended-style*]]

The **EDITTEXT** statement defines an EDIT control belonging to the EDIT class. It creates a rectangular region in which the user can type and edit text. The control displays a cursor when the user clicks the mouse in it. The user can then use the keyboard to enter text or edit the existing text. Editing keys include the BACKSPACE and DELETE keys. The user can also use the mouse to select characters to be deleted or to select the place to insert new characters.

### Parameters

#### *style*

Specifies the control styles. This value can be a combination of the edit class styles and the following styles: WS\_TABSTOP, WS\_GROUP, WS\_VSCROLL, WS\_HSCROLL, and WS\_DISABLED.

If you do not specify a style, the default style is ES\_LEFT, WS\_BORDER, and WS\_TABSTOP.

For more information on the *text, id, x, y, width, height, style, and extended-style* parameters, see "[Common Statement Parameters](#)".

### Example

The following example demonstrates the use of the **EDITTEXT** statement:

```
EDITTEXT 3, 10, 10, 100, 10
```



## EXSTYLE Statement

**EXSTYLE** *extended-style*

The EXSTYLE command allows you to designate a dialog box with the *WS\_EX\_style* styles. In a resource definition, the **EXSTYLE** statement is placed with the optional statements before the **BEGIN** keyword. It can also be placed with the *load-mem* parameters in a **DIALOG** statement as follows:

*name* **DIALOG** [*load-mem*] **EXSTYLE=***extended-style* *x*, *y*, ...

For controls, extended styles are specified after the *style* option in any control definition, as follows:

*control text*, *id*, *x*, *y*, *width*, *height*, [*style*[, *extended-style*]]

### Parameters

*extended-style*

The *WS\_EX\_style* style for the dialog box or control.

### See also

[ACCELERATORS](#), [CONTROL](#), [DIALOG](#), [MENU](#), [POPUP](#), [RCDATA](#), [STRINGTABLE](#), [User-Defined Resource](#)



## FONT Resource

*nameID* **FONT** [*load-mem*] *filename*

The **FONT** resource-definition statement specifies a file that contains a font.

For a font resource, *nameID* must be a number; it cannot be a name.

### Parameters

*nameID*

Specifies either a unique name or a 16-bit unsigned integer value identifying the resource.

*load-mem*

Specifies loading and memory attributes for the resource. For more information, see "[Common Resource Attributes](#)".

*filename*

Specifies the name of the file that contains the resource. The name must be a valid filename; it must be a full path if the file is not in the current working directory. The path can either be a quoted or non-quoted string.

### Example

The following example specifies a single font resource:

```
5 FONT CMROMAN.FNT
```

### See also

[FONT Statement](#)



## **FONT Statement**

**FONT** *pointsize*, *typeface*

The **FONT** statement defines the font with which Windows will draw text in the dialog box. The font must have been previously loaded, either from the WIN.INI file or by calling the **LoadResource** function.

### **Parameters**

*pointsize*

Specifies the size, in points, of the font.

*typeface*

Specifies the name of the typeface. This name must be identical to the name defined in the [fonts] section of WIN.INI. This parameter must be enclosed in double quotes.

### **Example**

The following example demonstrates the use of the **FONT** statement:

```
FONT 12, "MS Sans Serif"
```

### **See Also**

**DIALOG**, FONT Resource, **LoadResource**



## GROUPBOX Control

**GROUPBOX** *text, id, x, y, width, height* [, *style* [, *extended-style*]]

The **GROUPBOX** statement creates a group box control. The control is a rectangle that groups other controls together. The controls are grouped by drawing a border around them and displaying the given text in the upper-left corner. The **GROUPBOX** statement, which you can use only in a **DIALOG** statement, defines the text, identifier, dimensions, and attributes of a control window.

When the style contains WS\_TABSTOP or the text specifies an accelerator, tabbing or pressing the accelerator key moves the focus to the first control within the group.

### Parameters

*style*

Specifies the control styles. This value can be a combination of the button class style BS\_GROUPBOX and the WS\_TABSTOP and WS\_DISABLED styles.

If you do not specify a style, the default style is BS\_GROUPBOX.

For more information on the *text, id, x, y, width, height, style, and extended-style* parameters, see "Common Statement Parameters".

### Example

This example creates a group-box control that is labeled Options:

```
GROUPBOX "Options", 101, 10, 10, 100, 100
```

### See Also

DIALOG



## ICON Resource

*nameID* **ICON** [*load-mem*] *filename*

The **ICON** resource-definition statement specifies a bitmap that defines the shape of the icon to be used for a given application.

### Parameters

*nameID*

Specifies either a unique name or a 16-bit unsigned integer value identifying the resource.

*load-mem*

Specifies loading and memory attributes for the resource. For more information, see "[Common Resource Attributes](#)".

*filename*

Specifies the name of the file that contains the resource. The name must be a valid filename; it must be a full path if the file is not in the current working directory. The path can either be a quoted or non-quoted string.

### Comments

Icon and cursor resources can contain more than one image. If the resource is marked as **PRELOAD**, Windows loads all images in the resource when the application executes.

### Example

The following example specifies two icon resources:

```
desk1    ICON desk.ico
11       ICON DISCARDABLE custom.ico
```



## ICON Control

**ICON** *text*, *id*, *x*, *y*, [*width*, *height*, *style* [, *extended-style*]]

The **ICON** statement creates an icon control. This control is an icon displayed in a dialog box. The **ICON** control statement, which you can use only in a **DIALOG** statement, defines the icon-resource identifier, icon-control identifier, position, and attributes of a control.

### Parameters

#### *text*

Specifies the name of an icon (not a filename) defined elsewhere in the resource file.

#### *width*

This value is ignored and should be set to zero.

#### *height*

This value is ignored and should be set to zero.

#### *style*

Specifies the control style. This parameter is optional. The only value that can be specified is the `SS_ICON` style. This is the default style whether this parameter is specified or not.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### Example

This example creates an icon control whose icon identifier is 901 and whose name is "myicon":

```
ICON "myicon" 901, 30, 30
```

### See Also

[DIALOG](#), [ICON Resource](#)



## **LANGUAGE Statement**

**LANGUAGE** *language, sublanguage*

The **LANGUAGE** statement sets the language for all resources up to the next **LANGUAGE** statement or to the end of the file. When the **LANGUAGE** statement appears before the **BEGIN** in an **ACCELERATORS**, **DIALOG**, **MENU**, **RCDATA**, or **STRINGTABLE** resource definition, the specified language applies only to that resource.

### **Parameters**

*language*

Language identifier. Must be one of the constants from WINNLS.H

*sublanguage*

Sublanguage identifier. Must be one of the constants from WINNLS.H

### **See Also**

Multiline Statements

**CHARACTERISTICS**, **LANGUAGE**, **VERSION**  
**ACCELERATORS**, **DIALOG**, **MENU**, **RCDATA**, **STRINGTABLE**



## LISTBOX Control

**LISTBOX** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]

The **LISTBOX** statement creates commonly used controls for a dialog box or window. The control is a rectangle containing a list of strings (such as filenames) from which the user can select. The **LISTBOX** statement, which can only be used in a **DIALOG** or **WINDOW** statement, defines the identifier, dimensions, and attributes of a control window.

### Parameters

#### *style*

Specifies the control styles. This value can be a combination of the list-box class styles and any of the following styles: WS\_BORDER and WS\_VSCROLL.

If you do not specify a style, the default style is LBS\_NOTIFY and WS\_BORDER.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "Common Statement Parameters".

### Example

This example creates a list-box control whose identifier is 101:

```
LISTBOX 101, 10, 10, 100, 100
```

### See Also

COMBOBOX, DIALOG



## LTEXT Control

**LTEXT** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]]

The **LTEXT** statement creates a left-aligned text control. The control is a simple rectangle displaying the given text left-aligned in the rectangle. The text is formatted before it is displayed. Words that would extend past the end of a line are automatically wrapped to the beginning of the next line. The **LTEXT** statement, which can be used only in a **DIALOG** statement, defines the text, identifier, dimensions, and attributes of the control.

### Parameters

#### *style*

Specifies the control styles. This value can be any combination of the BS\_RADIOBUTTON style and the following styles: SS\_LEFT, WS\_TABSTOP, and WS\_GROUP.

If you do not specify a style, the default style is SS\_LEFT and WS\_GROUP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "Common Statement Parameters".

### Example

This example creates a left-aligned text control that is labeled "Filename":

```
LTEXT "Filename", 101, 10, 10, 100, 100
```

See Also

**CONTROL**, **DIALOG**, **CTEXT**, **RTEXT**



## MENU Resource

```
menuID MENU [load-mem]  
[optional-statements]  
BEGIN  
    item-definitions  
    . . .  
END
```

The **MENU** statement defines the contents of a menu resource. A menu resource is a collection of information that defines the appearance and function of an application menu. A menu is a special input tool that lets a user select commands from a list of command names.

### Parameters

#### *menuID*

Identifies the menu. This value is either a unique string or a unique 16-bit unsigned integer value in the range of 1 to 65,535.

#### *load-mem*

Specifies loading and memory attributes for the resource. For more information, see "[Common Resource Attributes](#)".

#### *optional-statements*

Zero or more of the following statements:

Statement	Description
<u><b>CHARACTERISTICS</b></u> <i>dword</i>	User-defined information about a resource that can be used by tools that read and write resource files.
<u><b>LANGUAGE</b></u> <i>language.</i> <i>sublanguage</i>	Specifies the language for the resource. The parameters are constants from WINNLS.H.
<u><b>VERSION</b></u> <i>dword</i>	User-defined version number for the resource that can be used by tools that read and write resource files.

### Example

Following is an example of a complete **MENU** statement:

```
sample MENU
BEGIN
    MENUITEM "&Soup", 100
    MENUITEM "S&alad", 101
    POPUP "&Entree"
    BEGIN
        MENUITEM "&Fish", 200
        MENUITEM "&Chicken", 201, CHECKED
        POPUP "&Beef"
        BEGIN
            MENUITEM "&Steak", 301
            MENUITEM "&Prime Rib", 302
        END
    END
END
MENUITEM "&Dessert", 103
END
```

### **See Also**

**MENUITEM, POPUP**

**Multiline Statements**

**CHARACTERISTICS, LANGUAGE, VERSION**

**ACCELERATORS, DIALOG, MENU, RCDATA, STRINGTABLE**



## **MENU Statement**

**MENU** *menuname*

The **MENU** statement defines the dialog box's menu. If no statement is given, the dialog box has no menu.

### **Parameter**

*menuname*

Specifies the menu to use. This value is either the name of the menu or the integer identifier of the menu.

### **Example**

The following example demonstrates the use of the **MENU** dialog statement:

```
MENU errmenu
```



## MENUEX Resource

The **MENUEX** resource is an extension of the **MENU** resource. In addition to the functionality offered by **MENU**, **MENUEX** allows for the following:

- Help IDs on popup menus.
- IDs on popup menus.
- Use of the menu type and state flags created for Windows 95 (MFT\_\* type flags and MFS\_\* state flags).

### Syntax

```
menuID MENUEX
BEGIN
  [[MENUITEM itemText [, [id] [, [type] [, state]]]] |
  [POPUP itemText [, [id] [, [type] [, [state] [, helpID]]]]
  BEGIN
    popupBody
  END}] ...]
END
```

### Parameters

#### **MENUITEM** statement

Defines a normal menu item

*itemText*

Specifies the string containing the text for the menu item. For more information, see [MENUITEM](#).

*id*

Specifies a numeric expression indicating the ID of the menu item.

*type*

Specifies a numeric expression indicating the type of the menu item (explicit MFT\_\* type values defined in WINUSER.H can be used by adding an include to the RC file: **#include** "WINUSER.H")

*state*

Specifies a numeric expression indicating the state of the menu item (explicit MFS\_\* state values defined in WINUSER.H can be used by adding an include to the RC file: **#include** "WINUSER.H")

#### **POPUP** statement

Defines a menu item which has another menu (a submenu) associated with it.

*itemText*

Specifies a string containing the text for the menu item.

*id*

Specifies a numeric expression indicating the ID of the menu item.

*type*

Specifies a numeric expression indicating the type of the menu item (explicit MFT\_\* type values defined in WINUSER.H can be used by adding an include to the RC file: **#include** "WINUSER.H").

*state*

Specifies a numeric expression indicating the state of the menu item (explicit MFS\_\* state values defined in WINUSER.H can be used by adding an include to the RC file: **#include** "WINUSER.H").

*helpID*

Specifies a numeric expression indicating the ID used to identify the menu during WM\_HELP

processing.

*popupBody*

Contain any combination of the MENUITEM and POPUP statements described above.

### **Remarks**

Valid arithmetic and Boolean operations that may be contained in any of the numeric expressions in the statements of **MENUEX** are:

- Add ('+')
- Subtract ('-')
- Unary minus ('-')
- Unary NOT ('~')
- AND ('&')
- OR ('|')

### **See Also**

MENU, MENUITEM, POPUP

Multiline Statements

ACCELERATORS, CHARACTERISTICS, DIALOG, LANGUAGE, RCDATA,  
STRINGTABLE, VERSION



## MENUITEM Statement

**MENUITEM** *text*, *result*, [*optionlist*]  
**MENUITEM SEPARATOR**

The **MENUITEM** statement defines a menu item.

### Parameters

#### *text*

Specifies the name of the menu item.

The string can contain the escape characters **\t** and **\a**. The **\t** character inserts a tab in the string and is used to align text in columns. Tab characters should be used only in pop-up menus, not in menu bars. (For information on pop-up menus, see the **POPUP** statement.) The **\a** character aligns all text that follows it flush right to the menu bar or pop-up menu.

#### *result*

Specifies the result generated when the user selects the menu item. This parameter takes an integer value. Menu-item results are always integers; when the user clicks the menu-item name, the result is sent to the window that owns the menu.

#### *optionlist*

Specifies the appearance of the menu item. This optional parameter takes one or more redefined menu options, separated by commas or spaces. The menu options are as follows:

#### **CHECKED**

Item has a check mark next to it.

#### **GRAYED**

Item name is initially inactive and appears on the menu in gray or a lightened shade of the menu-text color.

#### **HELP**

Identifies a help item.

#### **INACTIVE**

Item name is displayed but it cannot be selected.

#### **MENUBARBREAK**

Same as MF\_MENUBREAK except that for pop-up menus, it separates the new column from the old column with a vertical line.

#### **MENUBREAK**

Places the menu item on a new line for static menu-bar items. For pop-up menus, it places the menu item in a new column with no dividing line between the columns.

The **INACTIVE** and **GRAYED** options cannot be used together.

### SEPARATOR

The **MENUITEM SEPARATOR** form of the **MENUITEM** statement creates an inactive menu item that serves as a dividing bar between two active menu items in a pop-up menu.

### Example

The following example demonstrates the use of the **MENUITEM** and **MENUITEM SEPARATOR** statements:

```
MENUITEM "&Roman", 206, CHECKED, GRAYED
MENUITEM SEPARATOR
MENUITEM "&Blackletter", 301
```

**See Also**

**MENU, POPUP**



## **MESSAGETABLE Resource**

*nameID* **MESSAGETABLE** *filename*

The **MESSAGETABLE** resource-definition statement defines the ID and file of an application's message table resource. Message tables are special string resources used in [event logging](#) and with the [FormatMessage](#) API. The file contains a binary message table generated by the [Message Compiler](#). The Message Compiler also generates a resource script file that contains the **MESSAGETABLE** statements you need to include the message table resources in the compiled resource file. Use the **#include** directive to include this resource script into your main resource script.

### **Parameters**

*nameID*

Specifies either a unique name or a 16-bit unsigned integer value identifying the resource.

*filename*

Specifies the name of the file that contains the resource. The name must be a valid filename; it must be a full path if the file is not in the current working directory. The path can either be a quoted or non-quoted string.

### **See Also**

[STRINGTABLE Resource](#), [Message Compiler](#)



## POPUP Resource

**POPUP** *text*, [*optionlist*]

**BEGIN**

*item-definitions*

.  
.  
.

**END**

The **POPUP** statement marks the beginning of the definition of a pop-up menu. A pop-up menu (which is also known as a drop-down menu) is a special menu item that displays a sublist of menu items when it is selected.

### Parameters

*text*

Specifies the name of the pop-up menu. This string must be enclosed in double quotation marks.

*optionlist*

Specifies one or more redefined menu options that specify the appearance of the menu item. The menu options follow:

#### **CHECKED**

Item has a check mark next to it. This option is not valid for a top-level pop-up menu.

#### **GRAYED**

Item name is initially inactive and appears on the menu in gray or a lightened shade of the menu-text color.

#### **INACTIVE**

Item name is displayed but it cannot be selected.

#### **MENUBARBREAK**

Same as MF\_MENUBREAK except that for pop-up menus, it separates the new column from the old column with a vertical line.

#### **MENUBREAK**

Places the menu item on a new line for static menu-bar items. For pop-up menus, it places the menu item in a new column with no dividing line between the columns.

The **INACTIVE** and **GRAYED** options cannot be used together.

### Example

The following example demonstrates the use of the **POPUP** statement:

```
chem MENU
BEGIN
  POPUP "&Elements"
  BEGIN
    MENUITEM "&Oxygen", 200
    MENUITEM "&Carbon", 201, CHECKED
    MENUITEM "&Hydrogen", 202
    MENUITEM SEPARATOR
    MENUITEM "&Sulfur", 203
    MENUITEM "Ch&lorine", 204
  END
  POPUP "&Compounds"
  BEGIN
    POPUP "&Sugars"
    BEGIN
      MENUITEM "&Glucose", 301
      MENUITEM "&Sucrose", 302, CHECKED
      MENUITEM "&Lactose", 303, MENUBREAK
      MENUITEM "&Fructose", 304
    END
    POPUP "&Acids"
    BEGIN
      "&Hydrochloric", 401
      "&Sulfuric", 402
    END
  END
END
END
```

### **See Also**

**MENU, MENUITEM**



## **PUSHBOX Control**

**PUSHBOX** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]

The **PUSHBOX** statement creates a push-box control. Identical to a **PUSHBUTTON**, except that it does not display a button face or frame; only the text appears.

### **Parameters**

*style*

Specifies styles for the pushbox, which can be a combination of the BS\_PUSHBOX style and the following styles: WS\_TABSTOP, WS\_DISABLED, and WS\_GROUP.

The default style is BS\_PUSHBOX and WS\_TABSTOP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### **See Also**

**PUSHBUTTON**



## **PUSHBUTTON Control**

**PUSHBUTTON** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]]

The **PUSHBUTTON** statement creates a push-button control. The control is a round-cornered rectangle containing the given text. The text is centered in the control. The control sends a message to its parent whenever the user chooses the control.

### **Parameters**

#### *style*

Specifies styles for the pushbutton, which can be a combination of the BS\_PUSHBUTTON style and the following styles: WS\_TABSTOP, WS\_DISABLED, and WS\_GROUP.

The default style is BS\_PUSHBUTTON and WS\_TABSTOP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### **Example**

The following example demonstrates the use of the **PUSHBUTTON** statement:

```
PUSHBUTTON "ON", 7, 10, 10, 20, 10
```

### **See Also**

[\*\*GetDialogBaseUnits\*\*](#)



## RADIOBUTTON Control

**RADIOBUTTON** *text*, *id*, *x*, *y*, *width*, *height* [, *style* [, *extended-style*]

The **RADIOBUTTON** statement creates a radio-button control. The control is a small circle that has the given text displayed next to it, typically to its right. The control highlights the circle and sends a message to its parent window when the user selects the button. The control removes the highlight and sends a message when the button is next selected.

### Parameters

#### *style*

Specifies styles for the radio button, which can be a combination of BUTTON-class styles and the following styles: WS\_TABSTOP, WS\_DISABLED, and WS\_GROUP.

The default style for **RADIOBUTTON** is BS\_RADIOBUTTON and WS\_TABSTOP.

For more information on the *text*, *id*, *x*, *y*, *width*, *height*, *style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### Example

The following example demonstrates the use of the **RADIOBUTTON** statement:

```
RADIOBUTTON "Italic", 100, 10, 10, 40, 10
```

### See Also

[GetDialogBaseUnits](#)



## RCDATA Resource

*nameID* **RCDATA** [*load-mem*]

[*optional-statements*]

**BEGIN**

*raw-data*

...

**END**

The **RCDATA** statement defines a raw data resource for an application. Raw data resources permit the inclusion of binary data directly in the executable file.

### Parameters

*nameID*

Specifies either a unique name or a 16-bit unsigned integer value that identifies the resource.

*load-mem*

Specifies loading and memory attributes for the resource. For more information, see "[Common Resource Attributes](#)".

*optional-statements*

Zero or more of the following statements:

<b>Statement</b>	<b>Description</b>
<b><u>CHARACTERISTICS</u></b> <i>dword</i>	User-defined information about a resource that can be used by tools that read and write resource files.
<b><u>LANGUAGE</u></b> <i>language</i> , <i>sublanguage</i>	Specifies the language for the resource. The parameters are constants from WINNLS.H.
<b><u>VERSION</u></b> <i>dword</i>	User-defined version number for the resource that can be used by tools that read and write resource files.

*raw-data*

Specifies raw data consisting of one or more integers or strings of characters. Integers can be specified in decimal, octal, or hexadecimal format. RC does not automatically append a terminating null character to a string. The string is a sequence of the specified ANSI (byte) characters unless explicitly qualified as a wide-character string with the L prefix. Strings in all resources other than RCDATA and user-defined resources are Unicode strings.

The block of data begins on a DWORD boundary and RC performs no padding or alignment of data within the *raw-data* block. It is the programmer's responsibility to ensure the proper alignment of data within the block.

### Example

The following example demonstrates the use of the **RCDATA** statement:

```
resname RCDATA
BEGIN
    L"Here is a Unicode string\0", /* A Unicode string. Note: explicitly
                                   null-terminated */
    1024,                          /* int      */
    0x029a,                         /* hex int  */
    0o733,                          /* octal int */
    "\07"                           /* octal byte */
END
```

### **See Also**

[Multiline Statements](#)

[CHARACTERISTICS](#), [LANGUAGE](#), [VERSION](#)

[ACCELERATORS](#), [DIALOG](#), [MENU](#), [RCDATA](#), [STRINGTABLE](#)



## **RTEXT Control**

**RTEXT** *text, id, x, y, width, height* [, *style* [, *extended-style*]]

The **RTEXT** statement creates a right-aligned text control. The control is a simple rectangle displaying the given text right-aligned in the rectangle. The text is formatted before it is displayed. Words that would extend past the end of a line are automatically wrapped to the beginning of the next line.

### **Parameters**

*style*

Specifies styles for the text control, which can be any combination of the following: WS\_TABSTOP and WS\_GROUP.

The default style for **RTEXT** is SS\_RIGHT and WS\_GROUP.

For more information on the *text, id, x, y, width, height, style*, and *extended-style* parameters, see "[Common Statement Parameters](#)".

### **Example**

The following example demonstrates the use of the **RTEXT** statement:

```
RTEXT "Number of Messages", 4, 30, 50, 100, 10
```

### **See Also**

**CONTROL**, **CTEXT**, **DIALOG**, **LTEXT**



## SCROLLBAR Control

**SCROLLBAR** *text, id, x, y, width, height* [, *style* [, *extended-style*]]

The **SCROLLBAR** statement creates a scroll-bar control. The control is a rectangle that contains a scroll box and has direction arrows at both ends. The scroll-bar control sends a notification message to its parent whenever the user clicks the mouse in the control. The parent is responsible for updating the scroll-box position. Scroll-bar controls can be positioned anywhere in a window and used whenever needed to provide scrolling input.

### Parameters

#### *style*

Specifies a combination (or none) of the following styles: WS\_TABSTOP, WS\_GROUP, and WS\_DISABLED.

In addition to these styles, the *style* parameter may contain a combination (or none) of the SCROLLBAR-class styles. The default style for **SCROLLBAR** is SBS\_HORZ.

For more information on the *text, id, x, y, width, height, style, and extended-style* parameters, see "[Common Statement Parameters](#)".

### Example

The following example demonstrates the use of the **SCROLLBAR** statement:

```
SCROLLBAR 999, 25, 30, 10, 100
```



## STATE3 Control

**STATE3** *text, id, x, y, width, height* [, *style* [, *extended-style*]

The STATE3 statement defines a 3-state check box control. The control is identical to a CHECKBOX, except that it has three states: checked, unchecked, and disabled (grayed).

### Parameters

#### *text*

Specifies text that is displayed to the right of the control.

#### *style*

Specifies the control styles. This value can be a combination of the button class style BS\_3STATE and the WS\_TABSTOP and WS\_GROUP styles.

If you do not specify a style, the default style is BS\_3STATE and WS\_TABSTOP.

For more information on the *text, id, x, y, width, height, style,* and *extended-style* parameters, see "[Common Statement Parameters](#)".

### See Also

[AUTOCHECKBOX](#), [CHECKBOX](#), [CONTROL](#)



## STRINGTABLE Resource

**STRINGTABLE** [*load-mem*]

[*optional-statements*]

**BEGIN**

*stringID string*

...

**END**

The **STRINGTABLE** statement defines one or more string resources for an application. String resources are simply null-terminated Unicode strings that can be loaded when needed from the executable file, using the LoadString function.

### Parameter

*load-mem*

Specifies loading and memory attributes for the resource. For more information, see "Common Resource Attributes".

*optional-statements*

Zero or more of the following statements:

**Statement**

**Decription**

**CHARACTERISTICS** *dword*

User-defined information about a resource that can be used by tools that read and write resource files.

**LANGUAGE** *language*,  
*sublanguage*

Specifies the language for the resource. The parameters are constants from WINNLS.H.

**VERSION** *dword*

User-defined version number for the resource that can be used by tools that read and write resource files.

*stringID*

Specifies an unsigned 16-bit integer that identifies the resource.

*string*

Specifies one or more strings, enclosed in double quotation marks. The string must be no longer than 255 characters and must occupy a single line in the source file. To add a carriage return to the string, use this character sequence: \012. For example, "Line one\012Line two" would define a string that would be displayed as follows:

```
Line one
Line two
```

### Comments

Grouping strings in separate sections allows all related strings to be read in at one time and discarded together. When possible, an application should make the table movable and discardable. RC allocates 16 strings per section and uses the identifier value to determine which section is to contain the string. Strings with the same upper-12 bits in their identifiers are placed in the same section.

### Example

The following example demonstrates the use of the **STRINGTABLE** statement:

```
#define IDS_HELLO    1
#define IDS_GOODBYE  2

STRINGTABLE
BEGIN
    IDS_HELLO,    "Hello"
    IDS_GOODBYE,  "Goodbye"
END
```

### **See Also**

Multiline Statements

CHARACTERISTICS, LANGUAGE, VERSION

ACCELERATORS, DIALOG, MENU, RCDATA, STRINGTABLE



## STYLE Statement

### STYLE *style*

The **STYLE** statement defines the window style of the dialog box. The window style specifies whether the box is a pop-up or a child window. The default style has the following attributes: WS\_POPUP, WS\_BORDER, and WS\_SYSMENU.

### Parameter

#### *style*

Specifies the window style. This parameter takes an integer value or redefined name. The following lists the redefined styles:

#### **DS\_LOCALEDIT**

Specifies that edit controls in the dialog box will use memory in the application's data section. By default, all edit controls in dialog boxes use memory outside the application's data section. This feature can be suppressed by adding the DS\_LOCALEDIT flag to the STYLE command for the dialog box. If this flag is not used, EM\_GETHANDLE and EM\_SETHANDLE messages must not be used since the storage for the control is not in the application's data section. This feature does not affect edit controls created outside of dialog boxes.

#### **DS\_MODALFRAME**

Creates a dialog box with a modal dialog box frame that can be combined with a title bar and System menu by specifying the WS\_CAPTION and WS\_SYSMENU styles.

#### **DS\_NOIDLEMSG**

Suppresses WM\_ENTERIDLE messages that Windows would otherwise send to the owner of the dialog box while the dialog box is displayed.

#### **DS\_SYSMODAL**

Creates a system-modal dialog box.

#### **WS\_BORDER**

Creates a window that has a border.

#### **WS\_CAPTION**

Creates a window that has a title bar (implies the WS\_BORDER style).

#### **WS\_CHILD**

Creates a child window. It cannot be used with the WS\_POPUP style.

#### **WS\_CHILDWINDOW**

Creates a child window that has the WS\_CHILD style.

#### **WS\_CLIPCHILDREN**

Excludes the area occupied by child windows when drawing within the parent window. Used when creating the parent window.

#### **WS\_CLIPSIBLINGS**

Clips child windows relative to each other; that is, when a particular child window receives a WM\_PAINT message, this style clips all other top-level child windows out of the region of the child window to be updated. (If the WS\_CLIPSIBLINGS style is not given and child windows overlap, it is possible, when drawing in the client area of a child window, to draw in the client area of a neighboring child window.) For use with the WS\_CHILD style only.

#### **WS\_DISABLED**

Creates a window that is initially disabled.

#### **WS\_DLGFRAME**

Creates a window with a modal dialog box frame but no title.

#### **WS\_GROUP**

Specifies the first control of a group of controls in which the user can move from one control to the

next by using the arrow keys. All controls defined with the WS\_GROUP style after the first control belong to the same group. The next control with the WS\_GROUP style ends the style group and starts the next group (that is, one group ends where the next begins). This style is valid only for controls.

**WS\_HSCROLL**

Creates a window that has a horizontal scroll bar.

**WS\_ICONIC**

Creates a window that is initially iconic. For use with the WS\_OVERLAPPED style only.

**WS\_MAXIMIZE**

Creates a window of maximum size.

**WS\_MAXIMIZEBOX**

Creates a window that has a Maximize box.

**WS\_MINIMIZE**

Creates a window of minimum size.

**WS\_MINIMIZEBOX**

Creates a window that has a Minimize box.

**WS\_OVERLAPPED**

Creates an overlapped window. An overlapped window has a caption and a border.

**WS\_OVERLAPPEDWINDOW**

Creates an overlapped window having the WS\_OVERLAPPED, WS\_CAPTION, WS\_SYSMENU, WS\_THICKFRAME, WS\_MINIMIZEBOX, and WS\_MAXIMIZEBOX styles.

**WS\_POPUP**

Creates a pop-up window. It cannot be used with the WS\_CHILD style.

**WS\_POPUPWINDOW**

Creates a pop-up window that has the WS\_POPUP, WS\_BORDER, and WS\_SYSMENU styles. The WS\_CAPTION style must be combined with the WS\_POPUPWINDOW style to make the System menu visible.

**WS\_SIZEBOX**

Creates a window that has a size box. Used only for windows with a title bar or with vertical and horizontal scroll bars.

**WS\_SYSMENU**

Creates a window that has a System-menu box in its title bar. Used only for windows with title bars. If used with a child window, this style creates a Close box instead of a System-menu box.

**WS\_TABSTOP**

Specifies one of any number of controls through which the user can move by using the TAB key. The TAB key moves the user to the next control specified by the WS\_TABSTOP style. This style is valid only for controls.

**WS\_THICKFRAME**

Creates a window with a thick frame that can be used to size the window.

**WS\_VISIBLE**

Creates a window that is initially visible. This applies to overlapping and pop-up windows. For overlapping windows, the y parameter is used as a parameter for the [ShowWindow](#) function.

**WS\_VSCROLL**

Creates a window that has a vertical scroll bar.

**Comments**

If the redefined names are used, you must include WINDOWS.H.



## User-Defined Resource

*nameID typeID [load-mem] filename*

The *filename* specifies the name of a file containing the binary data of the resource. The contents of the file are included as the resource. RC does not interpret the binary data in any way. It is the programmer's responsibility to ensure that the data is properly aligned for the target machine architecture.

A user-defined resource can also be defined completely in the resource script using the syntax:

*nameID typeID [load-mem]*

**BEGIN**

*raw-data*

**END**

A user-defined resource statement specifies a resource that contains application-specific data. The data can have any format and can be defined either as the content of a given file (if the *filename* parameter is given) or as a series of numbers and strings (if the *raw-data* block is given).

### Parameters

*nameID*

Specifies either a unique name or a 16-bit unsigned integer that identifies the resource.

*typeID*

Specifies either a unique name or a 16-bit unsigned integer that identifies the resource type. If a number is given, it must be greater than 255. The numbers 1 through 255 are reserved for existing and future redefined resource types.

*load-mem*

Specifies loading and memory attributes for the resource. For more information, see "[Common Resource Attributes](#)".

*filename*

Specifies the name of the file that contains the resource data. The parameter must be a valid filename; it must be a full path if the file is not in the current working directory.

*raw-data*

Specifies raw data consisting of one or more integers or strings of characters. Integers can be specified in decimal, octal, or hexadecimal format. RC does not automatically append a terminating null character to a string. The string is a sequence of the specified ANSI (byte) characters unless explicitly qualified as a wide-character string with the L prefix. Strings in all resources other than RCDATA and user-defined resources are Unicode strings.

The block of data begins on a DWORD boundary and RC performs no padding or alignment of data within the *raw-data* block. It is the programmer's responsibility to ensure the proper alignment of data within the block.

### Example

The following example shows several user-defined statements:

```
array MYRES data.res
14 300 custom.res
18 MYRES2
BEGIN
  "Here is a data string\0", /* A string. Note: explicitly
                             null-terminated */
  1024, /* int */
  0x029a, /* hex int */
  0o733, /* octal int */
  "\07" /* octal byte */
END
```



## **VERSION Statement**

**VERSION** *dword*

The **VERSION** statement allows the developer to specify version information about a resource that can be used by tools that read and write resource files. The specified *dword* value appears with the resource in the compiled .RES file. However, the value is not stored in the executable file and has no significance to Windows.

The **VERSION** statement appears before the **BEGIN** in an **ACCELERATORS**, **DIALOG**, **MENU**, **RCDATA**, or **STRINGTABLE** resource definition. The specified value applies only to that resource.

### **Parameter**

*dword*

A user-defined doubleword value.

### **See Also**

Multiline Statements

**CHARACTERISTICS**, **LANGUAGE**, **VERSION**,  
**ACCELERATORS**, **DIALOG**, **MENU**, **RCDATA**, **STRINGTABLE**



## VERSIONINFO Resource

*versionID* **VERSIONINFO** *fixed-info*

**BEGIN**

*block-statement*

...

**END**

The **VERSIONINFO** statement creates a version-information resource. The resource contains such information about the file as its version number, its intended operating system, and its original filename. The resource is intended to be used with the File Installation library functions.

### Parameters

*versionID*

Specifies the version-information resource identifier. This value must be 1.

*fixed-info*

Specifies the version information, such as the file version and the intended operating system. This parameter consists of the following statements:

**FILEVERSION** *version*

Specifies the binary version number for the file. The *version* consists of two 32-bit integers, defined by four 16-bit integers. For example, FILEVERSION 3,10,0,61 is translated into two doublewords: 0x0003000a and 0x0000003d, in that order. Therefore, if *version* is defined by the doublewords dw1 and dw2, they need to appear in the **FILEVERSION** statement as follows: HIWORD(dw1), LOWORD(dw1), HIWORD(dw2), LOWORD(dw2).

**PRODUCTVERSION** *version*

Specifies the binary version number for the product with which the file is distributed. The *version* parameter is two 32-bit integers, defined by four 16-bit integers. For more information about *version*, see the **FILEVERSION** description.

**FILEFLAGSMASK** *fileflagsmask*

Specifies which bits in the **FILEFLAGS** statement are valid. If a bit is set, the corresponding bit in **FILEFLAGS** is valid.

**FILEFLAGS** *fileflags*

Specifies the Boolean attributes of the file. The *fileflags* parameter must be the combination of all the file flags that are valid at compile time. For Windows 3.1, this value is 0x3f.

**FILEOS** *fileos*

Specifies the operating system for which this file was designed. The *fileos* parameter can be one of the operating system values given in the Comments section.

**FILETYPE** *filetype*

Specifies the general type of file. The *filetype* parameter can be one of the file type values listed in the Comments section.

**FILESUBTYPE** *subtype*

Specifies the function of the file. The *subtype* parameter is zero unless the *type* parameter in the **FILETYPE** statement is **VFT\_DRV**, **VFT\_FONT**, or **VFT\_VXD**. For a list of file subtype values, see the Comments section.

*block-statement*

Specifies one or more version-information blocks. A block can contain string information or variable information.

### Comments

To use the constants specified with the **VERSIONINFO** statement, the WINVER.H file (included in

WINDOWS.H) must be included in the resource-definition file.

The following list describes the parameters used in the **VERSIONINFO** statement:

### Parameter

#### *fileflags*

Specifies a combination of the following values:

#### **VS\_FF\_DEBUG**

File contains debugging information or is compiled with debugging features enabled.

#### **VS\_FF\_INFOINFERRED**

File contains a dynamically created version-information resource. Some of the blocks for the resource may be empty or incorrect. This value is not intended to be used in version-information resources created by using the **VERSIONINFO** statement.

#### **VS\_FF\_PATCHED**

File has been modified and is not identical to the original shipping file of the same version number.

#### **VS\_FF\_PRERELEASE**

File is a development version, not a commercially released product.

#### **VS\_FF\_PRIVATEBUILD**

File was not built using standard release procedures. If this value is given, the **StringFileInfo** block must contain a **PrivateBuild** string.

#### **VS\_FF\_SPECIALBUILD**

File was built by the original company using standard release procedures but is a variation of the standard file of the same version number. If this value is given, the **StringFileInfo** block must contain a **SpecialBuild** string.

#### *fileos*

Specifies one of the following values:

<b>Value</b>	<b>Description</b>
<b>VOS_UNKNOWN</b>	Operating system for which the file was designed is unknown to Windows.
<b>VOS_DOS</b>	File was designed for MS-DOS.
<b>VOS_NT</b>	File was designed for Windows NT.
<b>VOS_WINDOWS16</b>	File was designed for Windows version 3.0 or later.
<b>VOS_WINDOWS32</b>	File was designed for 32-bit Windows.
<b>VOS_DOS_WINDOWS16</b>	File was designed for Windows version 3.0 or later running with MS-DOS.
<b>VOS_DOS_WINDOWS32</b>	File was designed for 32-bit Windows running with MS-DOS.
<b>VOS_NT_WINDOWS32</b>	File was designed for 32-bit Windows running with Windows NT.

The values 0x00002L, 0x00003L, 0x20000L and 0x30000L are reserved.

#### *filetype*

Specifies one of the following values:

<b>Value</b>	<b>Description</b>
<b>VFT_UNKNOWN</b>	File type is unknown to Windows.
<b>VFT_APP</b>	File contains an application.
<b>VFT_DLL</b>	File contains a dynamic-link library (DLL).
<b>VFT_DRV</b>	File contains a device driver. If the <b>dwFileType</b>

	member is <b>VFT_DRV</b> , the <b>dwFileSubtype</b> member contains a more specific description of the driver.
<b>VFT_FONT</b>	File contains a font. If the <b>dwFileType</b> member is <b>VFT_FONT</b> , the <b>dwFileSubtype</b> member contains a more specific description of the font.
<b>VFT_VXD</b>	File contains a virtual device.
<b>VFT_STATIC_LIB</b>	File contains a static-link library.

All other values are reserved for use by Microsoft.

#### *subtype*

Specifies additional information about the file type.

If the **FILETYPE** statement specifies **VFT\_DRV**, this parameter can be one of the following values:

<b>Value</b>	<b>Description</b>
<b>VFT2_UNKNOWN</b>	Driver type is unknown to Windows.
<b>VFT2_DRV_COMM</b>	File contains a communications driver.
<b>VFT2_DRV_PRINTER</b>	File contains a printer driver.
<b>VFT2_DRV_KEYBOARD</b>	File contains a keyboard driver.
<b>VFT2_DRV_LANGUAGE</b>	File contains a language driver.
<b>VFT2_DRV_DISPLAY</b>	File contains a display driver.
<b>VFT2_DRV_MOUSE</b>	File contains a mouse driver.
<b>VFT2_DRV_NETWORK</b>	File contains a network driver.
<b>VFT2_DRV_SYSTEM</b>	File contains a system driver.
<b>VFT2_DRV_INSTALLABLE</b>	File contains an installable driver.
<b>VFT2_DRV_SOUND</b>	File contains a sound driver.

If the **FILETYPE** statement specifies **VFT\_FONT**, this parameter can be one of the following values:

<b>Value</b>	<b>Description</b>
<b>VFT2_UNKNOWN</b>	Font type is unknown to Windows.
<b>VFT2_FONT_RASTER</b>	File contains a raster font.
<b>VFT2_FONT_VECTOR</b>	File contains a vector font.
<b>VFT2_FONT_TRUETYPE</b>	File contains a TrueType font.

If the **FILETYPE** statement specifies **VFT\_VXD**, this parameter must be the virtual-device identifier included in the virtual-device control block.

All *subtype* values not listed here are reserved for use by Microsoft.

#### *langID*

Specifies one of the following language codes:

<b>Code</b>	<b>Language</b>	<b>Code</b>	<b>Language</b>
0x0401	Arabic	0x0417	Rhaeto-Romanic
0x0402	Bulgarian	0x0418	Romanian
0x0403	Catalan	0x0419	Russian
0x0404	Traditional Chinese	0x041A	Croato-Serbian (Latin)
0x0405	Czech	0x041B	Slovak
0x0406	Danish	0x041C	Albanian
0x0407	German	0x041D	Swedish
0x0408	Greek	0x041E	Thai
0x0409	U.S. English	0x041F	Turkish

0x040A	Castilian Spanish	0x0420	Urdu
0x040B	Finnish	0x0421	Bahasa
0x040C	French	0x0804	Simplified Chinese
0x040D	Hebrew	0x0807	Swiss German
0x040E	Hungarian	0x0809	U.K. English
0x040F	Icelandic	0x080A	Mexican Spanish
0x0410	Italian	0x080C	Belgian French
0x0411	Japanese	0x0810	Swiss Italian
0x0412	Korean	0x0813	Belgian Dutch
0x0413	Dutch	0x0814	Norwegian - Nynorsk
0x0414	Norwegian - Bokml	0x0816	Portuguese
0x0415	Polish	0x081A	Serbo-Croatian (Cyrillic)
0x0416	Brazilian Portuguese	0x0C0C	Canadian French
0x0417	Rhaeto-Romanic	0x100C	Swiss French

*charsetID*

Specifies one of the following character-set identifiers:

<b>Identifier</b>	<b>Character Set</b>
0	7-bit ASCII
932	Windows, Japan (Shift - JIS X-0208)
949	Windows, Korea (Shift - KSC 5601)
950	Windows, Taiwan (GB5)
1200	Unicode
1250	Windows, Latin-2 (Eastern European)
1251	Windows, Cyrillic
1252	Windows, Multilingual
1253	Windows, Greek
1254	Windows, Turkish
1255	Windows, Hebrew
1256	Windows, Arabic

*string-name*

Specifies one of the following redefined names:

**Comments**

Specifies additional information that should be displayed for diagnostic purposes.

**CompanyName**

Specifies the company that produced the file—for example, "Microsoft Corporation" or "Standard Microsystems Corporation, Inc.". This string is required.

**FileDescription**

Specifies a file description to be presented to users. This string may be displayed in a list box when the user is choosing files to install—for example, "Keyboard Driver for AT-Style Keyboards" or "Microsoft Word for Windows". This string is required.

**FileVersion**

Specifies the version number of the file—for example, "3.10" or "5.00.RC2". This string is required.

**InternalName**

Specifies the internal name of the file, if one exists—for example, a module name if the file is a dynamic-link library. If the file has no internal name, this string should be the original filename,

without extension. This string is required.

#### **LegalCopyright**

Specifies all copyright notices that apply to the file. This should include the full text of all notices, legal symbols, copyright dates, and so on—for example, "Copyright© Microsoft Corporation 1990-1992". This string is optional.

#### **LegalTrademarks**

Specifies all trademarks and registered trademarks that apply to the file. This should include the full text of all notices, legal symbols, trademark numbers, and so on—for example, "Windows™ is a trademark of Microsoft® Corporation". This string is optional.

#### **OriginalFilename**

Specifies the original name of the file, not including a path. This information enables an application to determine whether a file has been renamed by a user. The format of the name depends on the file system for which the file was created. This string is required.

#### **PrivateBuild**

Specifies information about a private version of the file—for example, "Built by TESTER1 on \TESTBED". This string should be present only if the **VS\_FF\_PRIVATEBUILD** flag is set in the **dwFileFlags** member of the **VS\_FIXEDFILEINFO** structure of the root block.

#### **ProductName**

Specifies the name of the product with which the file is distributed—for example, "Microsoft Windows". This string is required.

#### **ProductVersion**

Specifies the version of the product with which the file is distributed—for example, "3.10" or "5.00.RC2". This string is required.

#### **SpecialBuild**

Specifies how this version of the file differs from the standard version—for example, "Private build for TESTER1 solving mouse problems on M250 and M250E computers". This string should be present only if the **VS\_FF\_SPECIALBUILD** flag is set in the **dwFileFlags** member of the **VS\_FIXEDFILEINFO** structure in the root block.

A string information block has the following form:

```
BLOCK "StringFileInfo"  
BEGIN  
    BLOCK "lang-charset"  
    BEGIN  
        VALUE "string-name", "value"  
        . . .  
    END  
END
```

Following are the parameters in the **StringFileInfo** block:

#### *lang-charset*

Specifies a language and character-set identifier pair. It is a hexadecimal string consisting of the concatenation of the language and character-set identifiers listed earlier in this section.

#### *string-name*

Specifies the name of a value in the block and can be one of the redefined names listed earlier in this section.

#### *value*

Specifies, as a character string, the value of the corresponding string name. More than one **VALUE** statement can be given.

A variable information block has the following form:

```
BLOCK "VarFileInfo"
```

```
BEGIN  
  VALUE "Translation",  
    langID, charsetID
```

```
END
```

Following are the parameters in the variable information block:

*langID*

Specifies one of the language identifiers listed earlier in this section.

*charsetID*

Specifies one of the character-set identifiers listed earlier in this section. More than one identifier pair can be given, but each pair must be separated from the preceding pair with a comma.



## Preprocessing Reference

The syntax and semantics for the RC preprocessor is the same as for the preprocessor in a C compiler. Single-line comments begin with two forward slashes (`//`) and run to the end of the line. Block comments begin with an opening delimiter (`/*`) and run to a closing delimiter (`*/`). Comments do not nest.

You use the **#define** directive to define symbols for your resource identifiers in a header file. You include this header both in the resource script and your application source code. Similarly, the values for attributes and styles are defined by including the C header files for Windows.

You can also define macros. The standard C preprocessing operators (**#**, **##**) can be used in a macro definition. For detailed information on preprocessing and defining macros, see your C compiler documentation.

<b>Directive</b>	<b>Description</b>
<b><u>#define</u></b>	Defines a specified name by assigning it a given value.
<b><u>#elif</u></b>	Marks an optional clause of a conditional-compilation block.
<b><u>#else</u></b>	Marks the last optional clause of a conditional-compilation block.
<b><u>#endif</u></b>	Marks the end of a conditional-compilation block.
<b><u>#if</u></b>	Conditionally compiles the script if a specified expression is true.
<b><u>#ifdef</u></b>	Conditionally compiles the script if a specified name is defined.
<b><u>#ifndef</u></b>	Conditionally compiles the script if a specified name is not defined.
<b><u>#include</u></b>	Copies the contents of a file into the resource-definition file.
<b><u>#undef</u></b>	Removes the definition of the specified name.



## **#define**

**#define** *name value*

The **#define** directive assigns the given value to the specified name. All subsequent occurrences of the name are replaced by the value.

### **Parameters**

*name*

Specifies the name to be defined. This value is any combination of letters, digits, and punctuation.

*value*

Specifies any integer, character string, or line of text.

### **Example**

This example assigns values to the names "NONZERO" and "USERCLASS":

```
#define      NONZERO      1
#define      USERCLASS    "MyControlClass"
```

### **See Also**

**#ifdef**, **#ifndef**, **#undef**



## **#elif**

### **#elif** *constant-expression*

The **#elif** directive marks an optional clause of a conditional-compilation block defined by a **#ifdef**, **#ifndef**, or **#if** directive. The directive controls conditional compilation of the resource file by checking the specified constant expression. If the constant expression is nonzero, **#elif** directs the compiler to continue processing statements up to the next **#endif**, **#else**, or **#elif** directive and then skip to the statement after **#endif**. If the constant expression is zero, **#elif** directs the compiler to skip to the next **#endif**, **#else**, or **#elif** directive. You can use any number of **#elif** directives in a conditional block.

### **Parameter**

#### *constant-expression*

Specifies the expression to be checked. This value is a defined name, an integer constant, or an expression consisting of names, integers, and arithmetic and relational operators.

### **Example**

In this example, **#elif** directs the compiler to process the second **BITMAP** statement only if the value assigned to the name "Version" is less than 7. The **#elif** directive itself is processed only if Version is greater than or equal to 3.

```
#if Version < 3
BITMAP 1 errbox.bmp
#elif Version < 7
BITMAP 1 userbox.bmp
#endif
```

### **See Also**

**[#else](#)**, **[#endif](#)**, **[#if](#)**, **[#ifdef](#)**, **[#ifndef](#)**



## **#else**

### **#else**

The **#else** directive marks an optional clause of a conditional-compilation block defined by a **#ifdef**, **#ifndef**, or **#if** directive. The **#else** directive must be the last directive before the **#endif** directive.

This directive has no arguments.

### **Example**

This example compiles the second **BITMAP** statement only if the name "DEBUG" is not defined:

```
#ifdef DEBUG
    BITMAP 1 errbox.bmp
#else
    BITMAP 1 userbox.bmp
#endif
```

### **See Also**

**[#elif](#)**, **[#endif](#)**, **[#if](#)**, **[#ifdef](#)**, **[#ifndef](#)**



## **#endif**

### **#endif**

The **#endif** directive marks the end of a conditional-compilation block defined by a **#ifdef** directive. One **#endif** is required for each **#if**, **#ifdef**, or **#ifndef** directive.

This directive has no arguments.

### **See Also**

**[#elif](#)**, **[#else](#)**, **[#if](#)**, **[#ifdef](#)**, **[#ifndef](#)**



## **#if**

### **#if** *constant-expression*

The **#if** directive controls conditional compilation of the resource file by checking the specified constant expression. If the constant expression is nonzero, **#if** directs the compiler to continue processing statements up to the next **#endif**, **#else**, or **#elif** directive and then skip to the statement after the **#endif** directive. If the constant expression is zero, **#if** directs the compiler to skip to the next **#endif**, **#else**, or **#elif** directive.

### **Parameter**

#### *constant-expression*

Specifies the expression to be checked. This value is a defined name, an integer constant, or an expression consisting of names, integers, and arithmetic and relational operators.

### **Example**

This example compiles the **BITMAP** statement only if the value assigned to the name "Version" is less than 3:

```
#if Version < 3
BITMAP 1 errbox.bmp
#endif
```

### **See Also**

**[#elif](#)**, **[#else](#)**, **[#endif](#)**, **[#ifdef](#)**, **[#ifndef](#)**



## **#ifdef**

### **#ifdef** *name*

The **#ifdef** directive controls conditional compilation of the resource file by checking the specified name. If the name has been defined by using a **#define** directive or by using the **-d** command-line option with the Resource Compiler, **#ifdef** directs the compiler to continue with the statement immediately after the **#ifdef** directive. If the name has not been defined, **#ifdef** directs the compiler to skip all statements up to the next **#endif** directive.

### **Parameter**

*name*

Specifies the name to be checked by the directive.

### **Example**

This example compiles the **BITMAP** statement only if the name "Debug" is defined:

```
#ifdef Debug
BITMAP 1 errbox.bmp
#endif
```

### **See Also**

**#define**, **#endif**, **#if**, **#ifndef**, **#undef**



## **#ifndef**

**#ifndef** *name*

The **#ifndef** directive controls conditional compilation of the resource file by checking the specified name. If the name has not been defined or if its definition has been removed by using the **#undef** directive, **#ifndef** directs the compiler to continue processing statements up to the next **#endif**, **#else**, or **#elif** directive and then skip to the statement after the **#endif** directive. If the name is defined, **#ifndef** directs the compiler to skip to the next **#endif**, **#else**, or **#elif** directive.

### **Parameter**

*name*

Specifies the name to be checked by the directive.

### **Example**

This example compiles the **BITMAP** statement only if the name "Optimize" is not defined:

```
#ifndef Optimize
BITMAP 1 errbox.bmp
#endif
```

### **See Also**

**[#elif](#)**, **[#else](#)**, **[#endif](#)**, **[#if](#)**, **[#ifdef](#)**, **[#undef](#)**



## **#include**

### **#include** (*filename*)

The **#include** directive causes Resource Compiler to process the file specified in the *filename* parameter. This file should be a header file that defines the constants used in the resource-definition file.

### **Parameter**

#### *filename*

Specifies the name of the file to be included. If the file is in the current directory, the string must be enclosed in double quotation marks; if the file is in the directory specified by the INCLUDE environment variable, the string must be enclosed in less-than and greater-than characters (<>). You must give a full path enclosed in double quotation marks if the file is not in the current directory or in the directory specified by the INCLUDE environment variable.

### **Example**

This example processes the header files WINDOWS.H and HEADERS\MYDEFS.H while compiling the resource-definition file:

```
#include <windows.h>
#include "headers\mydefs.h"
```

### **See Also**

#### **#define**



## **#undef**

### **#undef** *name*

The **#undef** directive removes the current definition of the specified name. All subsequent occurrences of the name are processed without replacement.

### **Parameter**

#### *name*

Specifies the name to be removed. This value is any combination of letters, digits, and punctuation.

### **Example**

This example removes the definitions for the names "nonzero" and "USERCLASS":

```
#undef    nonzero
#undef    USERCLASS
```

### **See Also**

#### **#define**



## RC Diagnostic Messages



The Help topics available under the alphabetic buttons at the top of the Help window contain descriptions of diagnostic messages produced by Microsoft Resource Compiler (RC) for Windows NT. Many of these messages appear when RC is not able to compile resources properly. The descriptions clarify the cause of each message.

A capital V in parentheses (V) at the beginning of a message description indicates that the message is displayed only if RC is run with the **V** (verbose) option. These messages are generally informative and do not necessarily indicate errors.



## RC Diagnostic Messages



- A -

### Accelerator Type required (ASCII or VIRTKEY)

The *type* parameter in the **ACCELERATORS** statement must contain either the **ASCII** or **VIRTKEY** value.



## RC Diagnostic Messages



- B -

### **BEGIN expected in Accelerator Table**

An **ACCELERATORS** statement was not followed by the **BEGIN** keyword.

### **BEGIN expected in Dialog**

A **DIALOG** statement was not followed by the **BEGIN** keyword.

### **BEGIN expected in menu**

A **MENU** statement was not followed by the **BEGIN** keyword.

### **BEGIN expected in RCData**

An **RCDATA** statement was not followed by the **BEGIN** keyword.

### **BEGIN expected in String Table**

A **STRINGTABLE** statement was not followed by the **BEGIN** keyword.

### **BEGIN expected in VERSIONINFO resource**

A **VERSIONINFO** statement was not followed by the **BEGIN** keyword.

### **Bitmap file *resource-file* is not in *version-number* format.**

Use Microsoft Image Editor (IMAGEDIT.EXE) to convert old resource files to the current format.



## RC Diagnostic Messages



- C -

### **Cannot Re-use String Constants**

You are using the same value twice in a **STRINGTABLE** statement. Make sure that you have not mixed overlapping decimal and hexadecimal values.

### **Control Character out of range [A - Z]**

A control character in the **ACCELERATORS** statement is invalid. The character following the caret (^) must be in the range A through Z.

### **Could not open *in-file-name***

Microsoft Windows Resource Compiler (RC) could not open the specified file. Make sure that the file exists and that you typed the filename correctly.

### **Couldn't open *resource-name***

Microsoft Windows Resource Compiler (RC) could not open the specified file. Make sure that the file exists and that you typed the filename correctly.

### **Creating *resource-name***

(V) Microsoft Windows Resource Compiler (RC) is creating a new binary resource (.RES) file.



## RC Diagnostic Messages



- E -

### Empty menus not allowed

An **END** keyword appears before any menu items are defined in the **MENU** statement. Empty menus are not permitted by Microsoft Windows Resource Compiler (RC). Make sure that you do not have any opening quotation marks within the **MENU** statement.

### END expected in Dialog

The **END** keyword must appear at the end of a **DIALOG** statement. Make sure that there are no opening quotation marks left from the preceding statement.

### END expected in menu

The **END** keyword must appear at the end of a **MENU** statement. Make sure that there are no mismatched **BEGIN** and **END** statements.

### Error Creating *resource-name*

Microsoft Windows Resource Compiler (RC) could not create the specified binary resource (.RES) file. Make sure that it is not being created on a read-only drive. Use the **-V** option to find out whether the file is being created.

### Expected Comma in Accelerator Table

Microsoft Windows Resource Compiler (RC) requires a comma between the *event* and *idvalue* parameters in the **ACCELERATORS** statement.

### Expected control class name

The *class* parameter of a **CONTROL** statement in the **DIALOG** statement must be one of the following

control types: **BUTTON**, **COMBOBOX**, **EDIT**, **LISTBOX**, **SCROLLBAR**, **STATIC**, or user-defined. Make sure that the class is spelled correctly.

#### **Expected font face name**

The *typeface* parameter of the **FONT** statement in the **DIALOG** statement must be a character string enclosed in double quotation marks. This parameter specifies the name of a font.

#### **Expected ID value for Menuitem**

The **MENU** statement must contain a **MENUITEM** statement, which has either an integer or a symbolic constant in the *MenuID* parameter.

#### **Expected Menu String**

Each **MENUITEM** and **POPUP** statement must contain a *text* parameter. This parameter is a string enclosed in double quotation marks that specifies the name of the menu item or pop-up menu. A **MENUITEM SEPARATOR** statement requires no quoted string.

#### **Expected numeric command value**

Microsoft Windows Resource Compiler (RC) was expecting a numeric *idvalue* parameter in the **ACCELERATORS** statement. Make sure that you have used a **#define** constant to specify the value and that the constant used is spelled correctly.

#### **Expected numeric constant in string table**

A numeric constant, defined in a **#define** statement, must immediately follow the **BEGIN** keyword in a **STRINGTABLE** statement.

#### **Expected numeric point size**

The *pointsize* parameter of the **FONT** statement in the **DIALOG** statement must be an integer point-size value.

#### **Expected Numerical Dialog constant**

A **DIALOG** statement requires integer values for the *x*, *y*, *width*, and *height* parameters. Make sure that these values, which are included after the **DIALOG** keyword, are not negative.

#### **Expected String in STRINGTABLE**

A string is expected after each numeric *stringid* parameter in a **STRINGTABLE** statement.

#### **Expected String or Constant Accelerator command**

Microsoft Windows Resource Compiler (RC) was not able to determine which key was being set up for the accelerator. The *event* parameter in the **ACCELERATORS** statement might be invalid.

#### **Expected VALUE, BLOCK, or END keyword.**

The **VERSIONINFO** structure requires a **VALUE**, **BLOCK**, or **END** keyword.

#### **Expecting number for ID**

A number is expected for the *id* parameter of a **CONTROL** statement in the **DIALOG** statement. Make sure that you have a number or a **#define** statement for the control identifier.

#### **Expecting quoted string for key**

The key string following the **BLOCK** or **VALUE** keyword should be enclosed in double quotation marks.

#### **Expecting quoted string in dialog class**

The *class* parameter of the **CLASS** statement in the **DIALOG** statement must be an integer or a string enclosed in double quotation marks.

#### **Expecting quoted string in dialog title**

The *captiontext* parameter of the **CAPTION** statement in the **DIALOG** statement must be a character string, enclosed in double quotation marks.



## RC Diagnostic Messages



- F -

### **File not found:** *filename*

The file specified in the **rc** command was not found. Make sure that the file has not been moved to another directory and that the filename or path is typed correctly.

### **Font names must be ordinals**

The *pointsize* parameter in the **FONT** statement must be an integer, not a string.



## RC Diagnostic Messages



- | -

### Invalid Accelerator

An *event* parameter in the **ACCELERATORS** statement was not recognized or was more than two characters long.

### Invalid Accelerator Type (ASCII or VIRTKEY)

The *type* parameter in the **ACCELERATORS** statement must contain either the **ASCII** or **VIRTKEY** value.

### Invalid control character

A control character in the **ACCELERATORS** statement is invalid. A valid control character consists of a caret (^) followed by a single letter.

### Invalid Control type

The **CONTROL** statement in a **DIALOG** statement must be one of the following: **AUTO3STATE**, **AUTOCHECKBOX**, **AUTORADIOBUTTON**, **CHECKBOX**, **COMBOBOX**, **CONTROL**, **CTEXT**, **DEFPUSHBUTTON**, **EDITTEXT**, **GROUPBOX**, **ICON**, **LISTBOX**, **LTEXT**, **PUSHBOX**, **PUSHBUTTON**, **RADIOBUTTON**, **RTEXT**, **SCROLLBAR**, **STATE3**.

### Invalid directive in preprocessed RC file

The specified filename has an embedded newline character.

### Invalid .EXE file

The executable (.EXE) file is invalid. Make sure that the linker created it correctly and that the file exists.

**Invalid switch, option**

An option used was invalid. For a list of the command-line options, use the **RC /?** command.

**Invalid switch, too many -D switches**

Too many /D options were specified. To define a large number of symbols, use the **#include** directive to include a file of definitions.

**Invalid type**

The resource type was not among the types defined in the include file.

**Invalid usage. Use RC -? for Help**

Make sure that you have at least one filename to work with. For a list of the command-line options, use the **RC /?** command.

**I/O error reading file.**

Read failed. Since this is a generic routine, no specific filename is supplied.

**I/O error seeking in file**

Seeking in file failed. Since this is a generic routine, no specific filename is supplied.

**I/O error writing file.**

Write failed. Since this is a generic routine, no specific filename is supplied.



**RC Diagnostic Messages**



**- N -**

**No resource binary filename specified.**  
The /FO option was used, but no binary resource (.RES) file was specified.



## RC Diagnostic Messages



- O -

**Old DIB in *resource-name*. Pass it through IMAGEDIT.**

The resource file specified is not compatible with Win32. Make sure you have read and saved this file using the latest version of Microsoft Image Editor (IMAGEDIT.EXE).

**Out of heap memory**

There was not enough memory.

**Out of memory, needed *n* bytes**

Microsoft Windows Resource Compiler (RC) was not able to allocate the specified amount of memory.



## RC Diagnostic Messages



- R -

### **Redefinition of Button Type**

The specified button styles conflict with or modify the style specified by the control keyword. This is a warning only and may be ignored.

The following common method of declaring an automatic radio button generates this warning:

```
RADIOBUTTON "&Italic", MYRB_ITALIC, 10, 10, 30, 12, BS_AUTORADIOBUTTON
```

To avoid the warning, use the control statement appropriate for the type of button that you want to define. In this example, the corrected statement is:

```
AUTORADIOBUTTON "&Italic", MYRB_ITALIC, 10, 10, 30, 12
```

### **RC: Invalid switch: *option***

An option used was invalid. For a list of the command-line options, use the **RC /?** command.

### **RC terminated by user**

A CTRL+C key combination was pressed, exiting Microsoft Windows Resource Compiler (RC).

### **RC terminating after preprocessor errors**

For information about preprocessor errors, see the documentation for the preprocessor.

### **Resource file *resource-name* is not in *version-number* format.**

Make sure your icons and cursors have been read and saved using the latest version of Microsoft

Image Editor (IMAGEDIT.EXE).



## RC Diagnostic Messages



- T -

### Text string or ordinal expected in Control

The *text* parameter of a **CONTROL** statement in the **DIALOG** statement must be either a text string or an ordinal reference to the type of control that is expected. If using an ordinal, make sure that you have a **#define** statement for the control.



## RC Diagnostic Messages



- U -

### Unable to create *destination*

Microsoft Windows Resource Compiler (RC) was not able to create the destination file. Make sure that there is enough disk space.

### Unbalanced Parentheses

Make sure that you have closed every opening parenthesis in the **DIALOG** statement.

### Unexpected value in RCData

The values for the *raw-data* parameter in the **RCDATA** statement must be integers or strings, separated by commas. Make sure that you did not leave out a comma or a quotation mark around a string.

### Unexpected value in value data

A statement contained information with a format or size different from the expected value for that parameter.

### Unknown DIB header format

The device-independent bitmap (DIB) header is not a **BITMAPCOREHEADER** or **BITMAPINFOHEADER** structure.

### Unknown Menu SubType

The *item-definitions* parameter of the **MENU** statement can contain only **MENUITEM** and **POPUP** statements.

**Unrecognized VERSIONINFO field; BEGIN or comma expected**  
The format of the information following a **VERSIONINFO** statement is incorrect.



### RC Diagnostic Messages



- V -

#### Version WORDs separated by commas expected

Values in an information block for a **VERSIONINFO** statement should be separated by commas.



## RC Diagnostic Messages



- W -

### **Warning: ASCII character not equivalent to virtual key code**

An invalid virtual-key code exists in the **ACCELERATORS** statement. The ASCII values for some characters such as \*, ^, or & are not equivalent to the virtual-key codes for the corresponding keys. In the case of the asterisk [\*], the virtual-key code is equivalent to the ASCII value for 8, the numeric character on the same key. Therefore, the statement **VIRTKEY '\* '** is invalid.

### **Warning: SHIFT or CONTROL used without VIRTKEY**

The **ALT**, **SHIFT**, and **CONTROL** options apply only to virtual keys in the **ACCELERATORS** statement. Make sure that the **VIRTKEY** option is used with one of these other options.

### **Writing resource *type image lang:language size:size***

(V) Microsoft Windows Resource Compiler (RC) is writing the specified resource. The *type* is the resource type. It may be a number or a string. The *image* can be a number or a string. The *language* is the national language of the resource. The *size* is the decimal size of the resource in bytes.



## **Resource Compiler Outline**

Resource Compiler

Including Resources in an Application

Creating a Resource-Definition File

Preprocessing Directives

Single-Line Statements

Multiline Statements

Sample Resource-Definition File

Using RC (The RC Command Line)

Defining Names for the Preprocessor

Renaming the Compiled Resource File

Searching for Files

Displaying Progress Messages

Resource-Definition Statements

Common Statement Parameters

Common Resource Attributes

Statement Reference

Preprocessing Reference

RC Diagnostic Messages



## **Resource Compiler Statements**

[Common Statement Parameters](#)  
[Common Resource Attributes](#)  
[ACCELERATORS Resource](#)  
[AUTO3STATE Control](#)  
[AUTOCHECKBOX Control](#)  
[AUTORADIOBUTTON Control](#)  
[BITMAP Resource](#)  
[CAPTION Statement](#)  
[CHARACTERISTICS Statement](#)  
[CHECKBOX Control](#)  
[CLASS Statement](#)  
[COMBOBOX Control](#)  
[CONTROL: General Control](#)  
[CTEXT Control](#)  
[CURSOR Resource](#)  
[DEFPUSHBUTTON Control](#)  
[DIALOG Resource](#)  
[DIALOGEX Resource](#)  
[EDITTEXT Control](#)  
[EXSTYLE Statement](#)  
[FONT Resource](#)  
[FONT Statement](#)  
[GROUPBOX Control](#)  
[ICON Resource](#)  
[ICON Control](#)  
[LANGUAGE Statement](#)  
[LISTBOX Control](#)  
[LTEXT Control](#)  
[MENU Resource](#)  
[MENU Statement](#)  
[MENUEX Resource](#)  
[MENUITEM Statement](#)  
[MESSAGETABLE Resource](#)  
[POPUP Resource](#)  
[PUSHBOX Control](#)  
[PUSHBUTTON Control](#)  
[RADIOBUTTON Control](#)  
[RCDATA](#)  
[RTEXT Control](#)  
[SCROLLBAR Control](#)  
[STATE3 Control](#)  
[STRINGTABLE Resource](#)  
[STYLE Statement](#)  
[User-Defined Resource](#)  
[VERSION Statement](#)  
[VERSIONINFO Resource](#)

