

## Introduction to Borland SQL Links for Windows (32-bit version)

Borland SQL Links for Windows is a set of BDE-hosted driver connections to database servers. By creating queries, SQL Links emulates full navigation capabilities, enabling users to access and manipulate data in SQL databases by using convenient features in Borland applications.

Any Borland application based upon the Borland Database Engine (BDE) can use Borland SQL Links, including your custom applications built using the BDE API. Borland SQL Links is included with some Borland client/server application development tools such as the Enterprise editions of Delphi and C++Builder.

The SQL Links product package includes database drivers for InterBase, DB2, Informix, ORACLE, Sybase, and Microsoft SQL Server databases. These drivers require the installation of the appropriate vendor's server connectivity API or interface software. Borland Database Engine includes built-in drivers for Borland standard databases.

---

{button ,AL('intro')} Other topics in this Introduction to SQL Links

{button ,JI('','additionalinformation')} Additional information

{button ,AL('bdedocs')} Other BDE online documentation

### **Where to find additional information**

This Online User's Guide describes how Borland SQL Links for Windows works, how to install one or more SQL Links drivers, and how to set up your supported Borland application to access SQL data. See [Configuring and connecting to an SQL Server](#) for driver-specific information on required workstation software, configuration parameters, troubleshooting, and data translation.

Depending on how you plan to work with SQL data, you might need the following documentation:

- your BDE application user documentation, which describes how to use your product to access both local (workstation-based) and SQL server data
- your BDE application programming documentation, which describes how to write custom applications to use with both local and SQL server data
- your database server connectivity software documentation
- your SQL database server documentation
- the Borland SQL Links README file, if any (BDEREADME.TXT)
- the BDE Online Reference (BDE32.HLP) and its Contents file (BDE32.CNT)
- the BDE Administrator Online Guide and Help (BDEADMIN.HLP) and its Contents file (BDEADMIN.CNT)

## Vendor's server connectivity API

<b>Vendor</b>	<b>API/Connectivity software</b>
InterBase	Win32 Client
DB2	IBM CAE version 2.1.2*, DB2v5
Informix	Informix ESQL/C 7.2 or 9.12
Microsoft	DB-Lib 6.x, 7
ODBC Socket	ODBC vendors' drivers
Oracle	OCI 7.x, 8.x
Sybase	DB-Lib for Sybase SQL Server version 4.x
Sybase	CT-Lib for Sybase Open Client version 10 and later

\* Though we provide a driver for IBM CAE version 2.1.2, IBM no longer supports that product. Thus, we recommend upgrading to DB2v5.

**Note:** If a vendor DLL is not found in the vendor's directory, check the WINDOWS\SYSTEM directory.

## The database server

A local area network (LAN) enables workstation users to share files, software, and printer resources stored on dedicated machines called servers. Workstations connect to network servers through a system of cabling, communications hardware, and software. In large user populations, two or more LANs can connect through gateways to form wide area networks, or WANs.

In a network environment, your workstation uses the network server in much the same way as it uses its own hard disk. If your workstation needs access to data stored on the server's hard disk it requests that data from the server. The server sends the requested data over the network and back to your workstation where it is processed locally. However, the network server differs from the workstation in that server data can be accessed by more than one user at the same time.

A database server is a network server that processes high-level database requests. Although other types of network servers let most processing occur on the user's workstation, database servers are active, with most processing occurring on the database server itself. If your workstation needs access to data stored in a database server, you query the server directly. The database server processes the query itself and sends only the answer over the network and back to your workstation.

Since the processing is performed at the server and not at the workstation that originated the request, the workstation becomes a client of the database server. In a client/server system, multiple clients (users) request the services of the database server through the use of client applications created with Delphi, Borland C++Builder, IntraBuilder, Visual dBASE, Borland C++, or Paradox for Windows.

Thus, the client and the server share the work of maintaining the database: the server dictates the kind of interactions the client can have with the data, but the client chooses how to display and use the results of those interactions.

---

{button ,AL('intro')} Other topics in this Introduction to SQL Links

## SQL

SQL is a descendant of SEQUEL (or Structured English QUery Language), which was originally designed at IBM. SQL was created as a language for constructing relational database management systems (RDBMS) on any hardware platform. The first commercial RDBMS using SQL appeared in 1981, and SQL is now the standard language for network queries across different hardware and software platforms.

SQL is actually a sublanguage designed to be embedded in an application programming language. It is so flexible that it can be used for both data manipulation and data definition.

SQL database servers handle requests in logical units of work called transactions. A transaction is a group of related operations that must all be performed successfully before the RDBMS will finalize any changes to the database. Transaction processing on database servers ensures that your processing requests are appropriate to the current state of your data.

In SQL, all transactions can be explicitly ended with a statement (command) to either accept or discard the changes. Once you are satisfied that no errors occurred during the transaction, you can end that transaction with a COMMIT statement. The database then changes to reflect the operations you have just performed. If an error occurs, you can abandon the changes with a ROLLBACK statement.

---

{button ,AL('intro')} [Other topics in this Introduction to SQL Links](#)


## How SQL Links works

Borland SQL Links for Windows is designed for BDE application users who need to access SQL databases. You begin with the BDE application installed at your workstation, along with any other client software needed to access the SQL server. Once you install the SQL Links driver and create an SQL driver alias, you can use your BDE application to access SQL data the same way you use it to access a local Paradox or dBASE database:

- through your application's user interface
- through custom applications that may include embedded SQL statements
- by passing SQL statements directly to the server

**Note:** BDE applications also support the use of SQL statements on local data. For information on how to use local SQL in your BDE application, see your application's user documentation.

With an SQL Links driver installed, you can access SQL data without needing to learn SQL. The driver enables the connection to the SQL server, translates queries into the appropriate SQL dialect, and passes them to the SQL database. When processing is complete, the SQL database returns the answer to the client in a format that the desktop application can display. This picture shows how it works.



1. BDE client queries an SQL database.
2. SQL Links driver, using the workstation's client software, connects to the SQL server and sends the query in that server's SQL dialect.
3. SQL server performs error and syntax checking on the SQL statements, processes the query, and returns the answer to the BDE client.
4. SQL Links driver translates the answer from SQL to client syntax. The client then formats and displays the data to the user.

---

{button ,AL('intro')} [Other topics in this Introduction to SQL Links](#)

## SQL Links features

Using your BDE application with an SQL Links driver actually extends what you can do with your application, lending it some of the advantages inherent in using SQL databases:

- the ability to query the SQL server directly
- support for SQL-style transactions
- improved record caching
- data locking behavior

Accessing an SQL server through an SQL Links driver and your BDE application also lends traditional SQL database users some of the advantages inherent in workstation databases, enabling you to

- open a table and clone a cursor
- move in both forward and backward directions through a result set or answer table
- order data using an available index
- set a "bookmark" on a database location in the current session, and reuse the bookmark in a later session
- work dynamically with the SQL data itself through "live" access to data sources

---

{button ,AL('intro')} Other topics in this Introduction to SQL Links

## Requirements

This section lists software that should already be installed and running at the client workstation. It also lists related files and parameters and database access requirements.

<b>Category</b>	<b>Description</b>
BDE application(s)	Supported BDE application, installed as required by the product documentation.
System requirements	1.5 MB of free disk space and operating system that meets the requirements of your BDE application.
Access rights	If your BDE application is installed on the shared disk of a network file server, make sure your network user account has Read and Write access rights to the application's BDE installation directory. This directory is modified during SQL Links installation. (For applications installed on the network server only.)
Network protocol software	Network protocol software compatible with both the server network protocol and the client workstation database communication driver.

For information on the software required at your SQL server and other server-related software requirements, see your driver-specific section.

### **Database access requirements**

To access the SQL database, you need a valid user identification and password on the SQL server. You also need at least Read (SELECT) access privileges for the SQL database.

To obtain these privileges, see your database administrator.

---

{button ,AL('intro')} [Other topics in this Introduction to SQL Links](#)

## Installing the software

**Before you begin:** Be sure your workstation already meets the client workstation requirements for installing Borland SQL Links for Windows. See [Requirements](#)

Also, be sure you have already installed your BDE application.

### What happens during installation?

During installation, the SQL Links SETUP program always:

- Installs an SQL Links driver that enables your application to access your SQL database.
- Adds new options to the BDE configuration file so you can configure the driver default parameters and create an alias to an SQL database. (See the appropriate driver page in the BDE Administrator, BDEADMIN.EXE)
- Installs an online Help file you can use when configuring the driver.

Depending on which driver(s) you install, the installation program will ask you for information about the SQL server to which you plan to connect. For further information see the "Installation Changes" section of your driver-specific section.

---

{button ,AL('intro')} [Other topics in this Introduction to SQL Links](#)

## Configuring the SQL environment: Overview

Installed with your BDE application is the BDE Administrator (BDEADMIN.EXE), which enables users to modify their application configuration. The configuration parameters are stored in the BDE configuration file IDAPI.CFG and in the Windows Registry:

HKEY\_LOCAL\_MACHINE | SOFTWARE | BORLAND | DATABASE ENGINE | SETTINGS

This section describes how to use the BDE Administrator to set up your application's SQL environment. Once your BDE application is configured, you are ready to connect to the network and access the SQL server, as described at the end of this chapter.

For instructions on how to use the BDE Administrator, see the *BDE Administrator Online Help*.

---

{button ,AL('config')} [Other SQL Links configuration topics](#)

{button ,AL('bdedocs')} [Other BDE online documentation](#)

## Before you begin

Be sure you have already installed the SQL Links software.

1. Exit all Borland applications and other applications that use BDE.
2. Open your application program group.
3. Click the BDE Administrator icon. The BDE Administrator window appears, open to the Configuration page.

---

{button ,AL(`config`)} Other SQL Links configuration topics

## Specifying default SQL Links driver settings

An alias is a name and a set of parameters that describe a network resource. BDE applications use aliases to connect with shared databases. An alias is not required to access a local database, but it is required to access an SQL database.

The SQL Links settings for your driver serve as a prototype for each new alias you create. Although you can customize an alias after you create it, it is easier to specify default driver settings that match your installation before you create any aliases for SQL databases. Then every alias you create will inherit these settings.

To specify default driver settings,

1. Start the BDE Administrator by clicking its icon in the BDE directory.
2. On the Configuration page, highlight the entry for your driver. The right pane displays all the configuration parameters for that driver.
3. If necessary, use the scroll bars at the side of the Parameters list to examine the complete list of driver configuration parameters.
4. If desired, edit the driver's default configuration. If you leave any categories blank, the BDE Administrator assumes you want to use the driver default.
5. When you are finished, choose Object|Apply to save changes into the default configuration file. To save the changes into a new file, choose Object|Save As Configuration.

Your changes take effect the next time BDE is restarted.

---

{button ,AL('config')} [Other SQL Links configuration topics](#)

## Common SQL Links driver settings

SQL driver settings determine the way the Borland Database Engine connects to a target SQL server, and how SQL databases are opened. Borland SQL Links drivers must be installed before configuring.

You configure all settings for each SQL Links driver by using the BDE Administrator, Configuration page. For each selected driver a list of parameter settings is displayed in the right pane. Each driver includes a subset of configuration parameters common to all SQL Links drivers, along with a few special settings specific to that driver.

### Common SQL Links driver configuration parameters

The following configuration parameters are common to all SQL Links drivers:

- VERSION
- TYPE
- DLL
- DLL32
- DRIVER FLAGS
- TRACE MODE
- SERVER NAME
- USER NAME
- OPEN MODE
- SCHEMA CACHE SIZE
- LANGDRIVER
- SQLQRYMODE
- SQLPASSTHRU MODE
- SCHEMA CACHE TIME
- MAX ROWS
- BATCH COUNT
- ENABLE SCHEMA CACHE
- SCHEMA CACHE DIR
- ENABLE BCD
- BLOBS TO CACHE
- BLOB SIZE

### Special SQL Links driver configuration parameters

For information on configuration parameters that are unique to a specific SQL driver, see the driver-specific sections listed below. If you have installed the specific driver, these special parameters appear along with the common parameters when the specific driver is selected in the Configuration page of the BDE Administrator:

- Special SQL Links driver settings for Informix
- Special SQL Links driver settings for ORACLE
- Special SQL Links driver settings for Sybase
- Special SQL Links driver settings for Microsoft SQL Server
- Special SQL Links driver settings for DB2 Server
- Connecting to InterBase (No special settings)

Alternatively, in the BDE Administrator, you can highlight the specific driver name and click the Help button to display the same topics available here.

---

{button ,AL('config')} Other SQL Links configuration topics

**VERSION**

Internal Borland version number of the SQL Links driver. Do not modify.

**TYPE**

Type of server to which this driver helps you connect. Do not modify.

SERVER represents an SQL server.

FILE represents a standard driver, file-based server, such as local Paradox and dBASE tables.

**DLL**

SQL Links dynamic link library name for the selected 16-bit driver.

For internal use only. Do not modify.

**DLL32**

SQL Links dynamic link library name for the selected 32-bit driver.

In the case of Informix or Sybase drivers, you might need to specify a particular DLL to support a specific server interface.

For Oracle 8, this will be SQLORA8.DLL. For Oracle 7, this will be SQLORA32.DLL.

For Informix 9, this will be SQLINF9.DLL. For Informix 7, this will be SQLINF32.DLL.

**DRIVER FLAGS**

Internal product-specific flag. Do not modify unless directed to do so by Borland support personnel.

**Setting Interbase driver flags**

Specifying a Read Committed transaction isolation level can result in incompatibility with applications using earlier versions of SQL Links for InterBase.

Earlier versions of SQL Links supported Repeatable Read only. To maintain transaction support compatibility with earlier versions of SQL Links, use the BDE Administrator to set the DRIVER FLAGS option to 512.

**Default:**

NULL.

## TRACE MODE

A numeric value (bit mask) specifying how much trace information to log. The Windows OutputDebugString call is used to output the requested information to the debug window. The following table shows which information is logged based on bit settings:

<b>Bit Settings</b>	<b>Logged Information</b>
0x0001	prepared query statement
0x0002	executed query statements
0x0004	vendor errors
0x0008	statement options (that is: allocate, free)
0x0010	connect / disconnect
0x0020	transaction
0x0040	BLOB I/O
0x0080	miscellaneous
0x0100	vendor calls

**SERVER NAME**

Name of the target SQL server. Use format appropriate for your server. When specified for InterBase servers, includes the full path to the database file, that is:

```
servername:servername:/usr/gds/directoryname/databasename.gdb
```

**USER NAME**

Default user name for accessing the target SQL server.

**OPEN MODE**

Mode in which SQL Links opens the SQL database. Possible values are READ/WRITE and READ ONLY.

**Note:** Setting OPEN MODE to READ ONLY affects operations from the application's user interface, but has no effect on passthrough SQL.

**Default:**

READ/WRITE

**SCHEMA CACHE SIZE**

Number of SQL tables whose schema information will be cached.

**Possible values:**

0 – 32

**Default:**

8

## LANGDRIVER

Language driver used to manipulate all data that originates from the SQL server. When the cursor is in the LANGDRIVER field, a scroll bar appears at the right side of the text box; use the scroll bar to display a list of language driver long names that work with your driver. The default value is blank.

When a specific language driver is associated with a server alias, your application uses this driver to manipulate all data that originates from the server. This includes all tables you view and all answer tables that result from a query. Servers running on different systems use conventions called character sets (or code pages) to determine how to encode alphabetic data. If you operate in a non-English language environment, your BDE application may use a different character set than the one used by the SQL server. When the character set at your desktop does not match the character set at the SQL server, passing alphabetic data between the two may cause either (or both) of the following:

- Data displays incorrectly on your desktop.
- The wrong characters are recorded in the SQL database.

To prevent this from happening, SQL Links provides language drivers to convert character data between your application character set and the SQL server character set. This ensures that the characters from your server display correctly on your desktop, and that data you enter in the SQL server database is transmitted reliably.

### Extended character sets

If your SQL database uses extended character sets, make sure the alias you use to access the SQL server specifies the correct SQL Links language driver. Choose a language driver that uses the same character set in which the server passes data to your BDE application, and a collation sequence that matches your server's collation sequence. If you cannot find an appropriate SQL Links language driver, you may want to modify your alias SQLQRYMODE entry to prevent processing of queries under local database rules.

### Default

If no language driver is specified, the data will be processed in codepoint order, and in the DOS character set.

## SQLQRYMODE

SQLQRYMODE specifies the mode for handling queries to SQL data. Possible modes and their meanings are listed here.

Setting	Mode	Meaning
NULL	Server-local	In server-local query mode, the query goes first to the SQL server. If the server is unable to perform the query, the query is performed locally. For a discussion of how Borland language drivers affect the processing of SQL queries, see "Blocking local processing of queries," below.
SERVER	Server-only	In server-only query mode, the query is sent to the SQL server. If the server is unable to perform the query, no local processing is performed.
LOCAL	Local-only	In local-only query mode, the query is always performed locally.

**Default:** NULL (blank setting)

For an explanation of SQL query modes, including passthrough, see [Default and passthrough SQL query modes](#)

### How language drivers affect SQL server query processing

Language drivers include information on sort order and uppercasing conventions used by your SQL server. Whenever a query to an SQL database is processed under the rules of the local (non-SQL) database, the application language driver is used in evaluating character ranges for sorting. If the sort order and uppercasing conventions at your desktop do not match the conventions used at the SQL server, your application may display inconsistent results. (A different sort order can cause the selection of a different set of records.)

To ensure consistent results you may want to set SQLQRYMODE to block local processing of queries, as described in the following section.

### Blocking local processing of queries

Normally queries to SQL databases are processed on the SQL server. However, in some cases, the result of a query executed completely on an SQL server will differ from that of a query executed locally. For example, say you use your BDE application's query function to perform a case-sensitive search on character fields. If the server does not support case-sensitive searches on a character field, then selecting on criteria such as ">A" will produce a different answer set depending on where the query is processed.

If you want to make sure that all queries originating from the BDE application are processed according to the rules of the SQL server, you can configure the SQL Links driver to block local processing of queries.

To do so, use the BDE Administrator to modify the SQL database alias, setting SQLQRYMODE to SERVER. (See [Modifying an existing SQL alias](#).)

The new SQLQRYMODE value takes effect the next time BDE is restarted.

**Note:** Types of SQL database queries that are always processed locally will return an error message when SQLQRYMODE is set to SERVER. These include:

- Heterogenous queries (queries made across more than one type of database)
- Queries that cannot be expressed as a single SQL statement
- Queries that the SQL server does not support

## SQLPASSTHRU MODE

Specifies whether or not the application will be able to access the SQL server via both desktop commands and passthrough SQL in the same alias connection. Possible modes and their meanings are listed in this table.

<b>Setting</b>	<b>Meaning</b>
SHARED AUTOCOMMIT	Passthrough SQL and non-passthrough SQL share the same connection, and passthrough SQL behaves in a similar fashion to non-passthrough. This means that, as long as the user is not in an explicit client transaction or batch mode, passthrough SQL statements are automatically committed.
SHARED NOAUTOCOMMIT	Passthrough SQL and non-passthrough SQL share the same connection, but the SQL driver does not automatically commit passthrough statements. In this mode, passthrough behavior is server-dependent.
NOT SHARED	Passthrough SQL and non-passthrough SQL do NOT share the same connection. Updateable SQL queries are not supported with aliases that have the SQLPASSTHRU MODE parameter set to NOT SHARED. (Default)

### **Default:**

The default value is NOT SHARED (or blank setting) for all SQL Links drivers.

SHARED AUTOCOMMIT and SHARED NOAUTOCOMMIT modes do not support all passthrough SQL statements. When SHARED AUTOCOMMIT or SHARED NOAUTOCOMMIT mode is set, do not execute transaction control statements in passthrough SQL; use your BDE API to begin, commit, or roll back the transaction.

When passthrough SQL and non-passthrough queries share a single connection, the record cache does not immediately reflect updates performed in passthrough SQL.

For a discussion of how the application processes passthrough SQL queries, and information about using passthrough SQL with your Borland application, see your application product documentation.

For an explanation of SQL query modes, including passthrough, see [Default and passthrough SQL query modes](#).

## **SCHEMA CACHE TIME**

Specifies how long table list information will be cached. (In BDE table information is cached when you call either `DbiOpenTableList` or `DbiOpenFileList`.)

Setting this value can increase performance for table and file list retrieval.

Possible modes and their meanings are listed here.

<b>Setting</b>	<b>Meaning</b>
-1	The table list is cached until you close the database. (Default)
0	No table lists are cached.
1 through 2147483647	The table list is cached for the number of seconds specified in the setting.

### **Default:**

-1

## MAX ROWS

Specifies maximum number of rows that the SQL driver will attempt to fetch for every SQL statement sent to the server. This includes schema inquiry queries that the driver sends to the server during a table open to retrieve column, index, and valcheck information.

If a request is made for more than MAX ROWS, then an error is returned (DBIERR\_ROWFETCHLIMIT). A return of DBIERR\_ROWFETCHLIMIT is similar to DBIERR\_EOF, except that it indicates a client-forced EOF when there actually may be more rows available on the server.

You can use the MAX ROWS option as a system governor to prevent users from unintentionally tying up valuable system resources. For example, a database administrator may set up users' configuration files to prevent them from tying up server and network resources if they happen to do a "SELECT \* ..." on a huge table. You can set the MAX ROWS option to make it impossible for a user to generate a million record query by mistake.

Be aware that if you set MAX ROWS too small, you may not be able to open a table under that database because it cannot get sufficient schema information. If MAX ROWS is not set to a large enough value to retrieve all the required metadata information during table open, then an error is returned and the table cannot be opened. MAX ROWS does not affect non-updateable queries in this way because a DESCRIBE (instead of a schema query) is used to get query column information.

### Default:

-1 (No limit on fetching rows.)

### WARNING!

A MAX ROW limitation could break existing BDE applications that fetch until receiving DBIERR\_EOF. Such applications must be modified to handle a return of DBIERR\_ROWFETCHLIMIT as well as DBIERR\_EOF. Users should be able to "see" all rows that have already been fetched, but they should be notified that there may be additional rows on the server.

**BATCH COUNT**

Specifies the number of modified records to be included in a batch before auto-committing. In this way you can adjust the size of a batch to accommodate server transaction logs that are not big enough to handle the whole batch.

In BDE you can override this value by setting the database property, dbBATCHCOUNT. See [Borland Database Engine Online Reference](#).

**Default:**

The number of records that can fit into 32 KB

## **ENABLE SCHEMA CACHE**

Specifies whether the BDE caches table schema locally for tables residing on SQL servers. This enhances performance for table opens. Set SCHEMA CACHE DIR to the directory in which the local cache is stored.

The schema cache is designed for static databases. Changes to the tables within the database can cause errors. If you frequently add columns to a table, add or drop indexes from a table, or change validity checks on fields (such as adding or removing "not null"), set ENABLE SCHEMA CACHE to FALSE.

Another good sign that a database is not static enough to use schema cache is if "Unknown SQL Errors" are returned whose error context refers to

- "Unknown Column"

- "Invalid Bind Type"

- "Invalid Type"

- "Invalid Type Conversion"

- "Column Not a Blob"

### **Default:**

FALSE (No local schema caching)

### **Oracle8**

For Oracle8, ENABLE SCHEMA CACHE must be set to FALSE since SCHEMA CACHE mode is not supported.

**SCHEMA CACHE DIR**

Specifies the directory in which the local schema cache is stored. Used when ENABLE SCHEMA CACHE is TRUE to cache schema locally when tables reside on an SQL server.

**BLOBS TO CACHE**

Determines how many BLOBs will be cached on the client. Applications that deal with fetching dead BLOBs using dead table opens or queries can set a limit on the number of BLOBs to cache depending on the resource available on the client.

Setting a value 100 means the application can work with a maximum of 100 BLOB records cached. Fetching more than 100, then scrolling back 100 records results in an "Invalid Blob handle in record buffer" error message.

This parameter does not apply to live table opens.

Default Value: 64

Range : >64 and < 65536

**BLOB SIZE**

Determines the fetch buffer size for dead BLOBs. Applications that deal with dead BLOBs using dead table opens or queries or batchmoves can set a maximum limit on the size of BLOBs to fetch. Setting this parameter to 64 means your application can fetch BLOBs of up to 64K.

This parameter does not apply to live table opens.

Default Value: 32

Range : >32 and <1000

## ENABLE BCD

Specifies whether BDE translates numeric and decimal fields into floating point values or binary coded decimal (BCD) values. BCD values eliminate the rounding errors associated with floating point math (such as a  $3 * (2/3)$  resulting in 2.00000000001). The following table lists field types converted to BCD when ENABLE BCD is set to TRUE:

<b>Driver</b>	<b>Field types</b>
DB2	DECIMAL and NUMERIC
dBASE	All NUMBER and FLOAT fields
Informix	DECIMAL, NUMERIC, and MONEY
InterBase	DECIMAL and NUMERIC
MS SQL	MONEY, SMALLMONEY, DECIMAL, and NUMERIC
ODBC	DECIMAL and NUMERIC
Oracle	NUMBER and FLOAT
Paradox	BCD
Sybase	MONEY, SMALLMONEY, DECIMAL, and NUMERIC

**Note:** A field is translated to BCD only if the target driver supports BCD fields.

With SQL drivers (all non-local drivers), the ENABLE BCD property must be set in the driver area of the configuration. The driver setting can be overridden by setting it in the alias; however, if it is blank in the driver area, setting it in the alias has no effect.

With local drivers, you can only set ENABLE BCD in an alias that is of type STANDARD. This is because a STANDARD alias can be either of dBASE or Paradox type.

**Default:**

FALSE (Convert to floating point values)

## Default and passthrough SQL query modes

There are two SQL Links driver options that influence how your application behaves when querying SQL data:

- Default SQL Query Mode
- Default Passthrough SQL Mode

For information on how to use your application to query SQL data, or how to query Paradox or dBASE data by using SQL statements, see [Borland Local SQL Online Guide](#). For information on how to adapt custom BDE applications for use with SQL data, see your product-specific online help for SQL and upsizing issues.

### Default SQL query mode

Under most circumstances, queries to SQL databases are processed on the SQL server. However, in cases where the SQL server cannot (or should not) process a query, the BDE application processes the query locally.

Types of SQL database queries that are processed locally include

- Heterogenous queries (queries made across more than one type of database)
- Queries that cannot be expressed as a single SQL statement
- Queries that the SQL server does not support

If you want to make sure that all queries originating from your BDE application are processed according to the rules of the SQL server, you can configure the SQL Links driver to block workstation processing of queries. For example, you may want to force remote processing if you are using a non-English language driver that does not properly mimic the SQL server's conventions for sorting and uppercasing.

To do so, use the BDE Administrator to modify the default SQL database alias, setting default SQLQRYMODE to SERVER. (See [Creating and managing SQL aliases](#))

### Default passthrough SQL mode

Usually the BDE application enables you to choose whether you want to query the SQL database through the user interface or pass SQL statements directly to the server. Through the BDE Administrator, you can also specify whether or not SQL statements passed directly to the server should be automatically committed.

For a discussion of SQL passthrough options, see [SQLPASSTHRU MODE](#). Also see the parameter, [SQLQRYMODE](#).

For information about using passthrough SQL with your BDE application, see your application's user documentation.

---

{button ,AL('config')} [Other SQL Links configuration topics](#)

## Creating and managing SQL aliases: Overview

Your SQL alias includes your user name on the target SQL server, and is required to access any SQL data through your BDE application. A generic SQL alias is automatically created the first time you modify the default SQL Links driver parameters after installation.

To set up a standard alias, use the BDE Administrator to assign a name to, and specify the path name for, a directory containing Paradox or dBASE files.

To set up an alias for an SQL database, use the BDE Administrator to assign a name to, and customize the access parameters for, an SQL server and database.

---

{button ,AL(`alias`)} [SQL alias topics](#)

## Adding a new SQL alias

To add a new alias,

1. Start the BDE Administrator (BDEADMIN.EXE).
2. Click the Databases page and choose Object|New. The New Database Alias dialog box appears.
3. Enter the new alias name and select the SQL-specific alias type. Then choose OK to begin the setup process. The right pane of the Databases page displays all the configuration parameters you can change to customize the new alias.

The parameters are the same as those listed in the Configuration page for your driver type. For a description of each setting you can change, see [Specifying default SQL Links driver settings](#)

4. If desired, edit the settings for the category you selected. If you leave any categories blank, the Databases page assumes you want to use the default for that driver type.
5. When you are finished, choose Object|Apply to save the new alias.

---

{button ,AL(`alias`)} [SQL alias topics](#)

## Modifying an existing SQL alias

To change a default parameter type for all aliases of that driver type, follow the procedure described in [Specifying default SQL Links driver settings](#). When you modify a driver parameter, all aliases that use the default setting for that parameter inherit the new setting.

To modify an existing alias,

1. Start the BDE Administrator and click the Databases page.
2. Scan the list of available database aliases.
3. Highlight the name of the alias you wish to modify. The configuration for that alias appears in the right pane of the Databases page. The parameters are the same as those listed in the Configuration page.
4. Highlight the configuration parameter you wish to change, and enter the desired value. If you leave any categories blank, the Databases page uses the driver's default value.
5. When you are finished, click Object|Apply to save the new alias.

---

{button ,AL(`alias`)} [SQL alias topics](#)

## Deleting an SQL alias

To delete an alias:

1. Start the BDE Administrator and click the Databases page.
2. Scan the list of available database aliases.
3. Highlight the name of the alias to delete, and choose Object|Delete.
4. Respond OK to the confirmation prompt and the alias is deleted.

---

{button ,AL(`alias`)} [SQL alias topics](#)

## Configuring and connecting to an SQL server

Whenever you attempt an operation against an SQL database for the first time in a session (like opening a table or running a query), you trigger an automatic connection process. The object of this process is to ensure that you have the right to access the database.

If your BDE files and your SQL Links driver are configured properly, you should be able to use your application's File menu to select a table in your SQL database using the appropriate alias. See [Creating and managing SQL aliases](#)

If you have trouble connecting, see the troubleshooting procedures in your driver-specific section and your BDE application documentation.

**Note:** If you saved your new (or modified) alias in a configuration file with a different name, be sure to activate that configuration file in the Windows Registry before you start your BDE application. One way to do this is to update the BDE section of Registry directly, changing the CONFIGFILE01= statement to reflect the desired configuration file. Another way to do this is to open and save the file by using the BDE Administrator. If directed at Save time, the BDE Administrator automatically updates the Registry.

For complete information on installing, configuring, using, and troubleshooting Borland SQL Links drivers, see these topics:

- [Connecting to InterBase](#)
- [Connecting to DB2](#)
- [Connecting to Informix](#)
- [Connecting to Oracle](#)
- [Connecting to Sybase](#)
- [Connecting to Microsoft SQL Server](#)

## Connecting to InterBase

This section contains topics about using Borland SQL Links that are unique to InterBase. These settings are applicable only if you have purchased and installed the Borland SQL Links Driver for InterBase.

- [InterBase requirements](#)
- [InterBase installation changes](#)
- [Working with InterBase servers](#)
- [Troubleshooting InterBase connection problems](#)
- [InterBase data type translations](#)
- [InterBase field-naming rules](#)

## InterBase requirements

Here is a list of software that should already be installed and running at the InterBase server before you install Borland SQL Links for Windows.

<b>Server requirements</b>	<b>Description</b>
Database server software	InterBase version 4.0 or later
Network protocol software	Network protocol software compatible with both the database server and the client workstation network protocol

For information on network protocol software and network access rights, see your system administrator.

Here is a list of requirements for the client workstation.

<b>Client requirements</b>	<b>Description</b>
BDE application(s)	Supported BDE application, installed as required by the product documentation.
Requirements	1.5 MB of free disk space. Hardware and operating system that meets the requirements of your Borland desktop product.
Access rights	(For desktop products installed on the network server only) If your Borland desktop product is installed on a network file server, make sure your network user account has Read and Write access rights to the product's BDE files (including BDEADMIN.EXE and the BDE configuration file). This directory is modified during SQL Links installation.
Network protocol software	Network protocol software compatible with both the server network protocol and the client workstation client database communication driver. InterBase supports the Windows 95 Winsock API.
HOSTS file	HOSTS file containing the name and IP address of each server to which you plan to attach. This file must contain the name and IP address of at least one host. For example: 128.127.50.12 mis_server If your server is running Domain Name Service (DNS), this information may be configured for you.
SERVICES file	A SERVICES file containing the protocol for InterBase server access. During SQL Links installation, this file is updated to include the line: gds_db 3050/tcp Note: If you prefer, you can add the line to your SERVICES file manually, after SQL Links installation.

---

{button ,AL('connectingtointerbase')} [Connecting to InterBase topics](#)

## InterBase installation changes

When you install the InterBase SQL Links driver, the following items are installed in your workstation system:

<b>Item added</b>	<b>Description</b>
SQLINT32.DLL	Dynamic Link Library comprising the new InterBase driver and its supporting files.
INTRBASE driver type	Added to BDE Administrator Configuration page to enable basic configuration of Borland InterBase SQL Links driver.

---

{button ,AL(`connectingtointerbase`)} [Connecting to InterBase topics](#)

## Working with InterBase servers

This section provides information about InterBase servers and their implementation of SQL. The topics discussed in this section cover aspects of InterBase that differ from other SQL database products.

Here is a list of the general items that you might find helpful in working with InterBase.

<b>Item</b>	<b>Description</b>
Dynamic Link Library (DLL) name	SQLINT32.DLL
Case-sensitive for data?	Yes (including pattern matching)
Case-sensitive for objects (tables, columns, indexes)?	No
Does the server require an explicit request to begin a transaction for multistatement transaction processing?	Yes
Does the server require that you explicitly start a transaction for multi-statement transaction processing in passthrough SQL?	No
Implicit row IDs	No
BLOB handles	InterBase BLOBs have handles. However, InterBase CHAR and VARCHAR columns that are more than 255 characters long are treated as non-handle BLOBs.
Maximum size of single BLOBs read (if BLOB handles are not supported)	32K
Language drivers?	InterBase transliterates data from its current language driver to the language driver BDE is using.

---

{button ,AL('connectingtointerbase')}} [Connecting to InterBase topics](#)

## Troubleshooting InterBase connection problems

If you have problems establishing an InterBase connection with SQL Links, try to isolate the problem the following way:

Check whether your BDE application InterBase alias is set up properly.

If you can connect directly from your workstation but not from within your BDE application, there is probably a problem with your IDAPI.CFG alias setup. Run the BDE Administrator and examine your InterBase alias.

---

{button ,AL('connectingtointerbase')} [Connecting to InterBase topics](#)

## InterBase data type translations

Certain database operations cause SQL Links to convert data from Paradox or dBASE format to InterBase format. For example, a BDE application that copies or appends data from a local table to an InterBase table causes SQL Links to convert the local data to InterBase format before performing the copy or append operation.

Other database operations cause a conversion in the opposite direction, from InterBase format to Paradox or dBASE format. For example, suppose you run a local query against one or more SQL tables. During the query, SQL Links converts any data originating in an SQL database to Paradox or dBASE format (depending on the answer format requested) before placing the data in the local answer table.

The following topics list InterBase, Paradox, and dBASE data types and show how SQL Links translates between them:

- [From InterBase data types](#)
- [From Paradox data types](#)
- [From dBASE data types](#)
- [From Paradox physical types](#)
- [From dBASE physical types](#)
- [From InterBase physical types](#)
- [InterBase equivalents to standard SQL data types](#)
- [InterBase field-naming rules](#)

---

{button ,AL('connectingtointerbase')} [Connecting to InterBase topics](#)

## From InterBase data types (to Paradox, dBASE)

FROM InterBase	TO Paradox	TO dBASE
SHORT	Short	Number {6.0}
LONG	Number	Number {11.0}
FLOAT	Number	Float {20.4}
DOUBLE	Number	Float {20.4}
NUMERIC	Number	Float {20.4}
DECIMAL	Number	Float {20.4}
DATE	DateTime	Date
BLOB	Binary	Binary
BLOB/1	Memo	Memo
CHAR(1-255)	Alphanumeric(n)	Character(n)
CHAR(greater than 255)	Memo	Memo
VARYING(1-255)	Alphanumeric(n)	Character(n)
VARYING(greater than 255)	Memo	Memo
ARRAY	Binary	Memo

---

{button ,AL('interbasetranslations')} InterBase data translations

## From Paradox data types (to InterBase, dBASE)

<b>FROM Paradox</b>	<b>TO InterBase</b>	<b>TO dBASE</b>
Alphanumeric(n)	VARYING(n)	Character(n)
Number	DOUBLE	Float {20.4}
Money	DOUBLE	Float {20.4}
Date	DATE	Date
Short	SHORT	Number {6.0}
Memo	BLOB/1 (Text)	Memo
Formatted memo	BLOB (Binary)	Memo
Binary	BLOB (Binary)	Binary
Graphic	BLOB (Binary)	Binary
OLE	BLOB (Binary)	OLE
Long	Long	Number {11.0}
Time	Character {>8}	TimeStamp
DateTime	Date	TimeStamp
Bool	Character {1}	Logical
AutoInc	Long	Number {11.0}
Bytes	BLOB	Binary
BCD	N/A	N/A

---

{button ,AL('interbasetranslations')} InterBase data translations

## From dBASE data types (to InterBase, Paradox)

<b>FROM dBASE</b>	<b>TO InterBase</b>	<b>TO Paradox</b>
Character(n)	VARYING(n)	Alphanumeric(n)
Number	Float	SHORT, DOUBLED DOUBLEShort number, NumberNumber
Date	DATE	Date
TimeStamp	DATE	TimeStamp
Lock	Character {24}	Alpha {24}
Logical	Character {1}	Bool
Memo	BLOB/1	Memo in append, copy, and local query operations.
Binary	BLOB	Raw binary data in append, copy, and local query operations.

---

{button ,AL(`interbasetranslations`)} InterBase data translations

## From Paradox physical types (to BDE, dBASE)

<b>Paradox physical</b>	<b>BDE logical</b>	<b>dBASE</b>
fldPDXCHAR	fldZSTRING	fldDBCHAR
fldPDXNUM	fldFLOAT	fldDBFLOAT {20.4}
fldPDXMONEY	fldFLOAT/fldstMONEY	fldDBFLOAT {20.4}
fldPDXDATE	fldDATE	fldDATE
fldPDXSHORT	fldINT16	fldDBNUM {6.0}
fldPDXMEMO	fldBLOB/fldstMEMO	fldDBMEMO
fldPDXBINARYBLOB	fldBLOB/fldstBINARY	fldDBMEMO
fldPDXFMTMEMO	fldBLOB/fldstFMTMEMO	fldDBMEMO
fldPDXOLEBLOB	fldBLOB/fldstOLEOBJ	fldDBMEMO
fldPDXGRAPHIC	fldBLOB/fldstGRAPHIC	fldDBMEMO
fldPDXBLOB	fldPDXMEMO	fldDBMEMO
fldPDXLONG	fldINT32	fldDBNUM {11.0}
fldPDXTIME	fldTIME	fldDBCHAR {>8}
fldPDXDATETIME	fldTIMESTAMP	fldDBCHAR {30}
fldPDXBOOL	fldBOOL	fldDBBOOL
fldPDXAUTOINC	fldINT32	fldDBNUM {11.0}
fldPDXBYTES	fldBYTES	fldDBBYTES
fldPDXBCD	fldBCD	fldDBCHAR

---

{button ,AL('interbasetranslations')} InterBase data translations

## From dBASE physical types (to BDE, Paradox)

<b>dBASE physical</b>	<b>BDE logical</b>	<b>Paradox</b>
fldDBCHAR	fldZSTRING	fldPDXCHAR
fldDBNUM	if( iUnits2=0 && iUnits1<5 )	fldINT16 else fldFLOAT fldPDXSHORT fldPDXNUM
fldDBMEMO	fldBLOB	fldPDXMEMO
fldDBBOOL	fldBOOL	fldPDXBOOL
fldDBDATE	fldDATE	fldPDXDATE
fldDBFLOAT	fldFLOAT	fldPDXNUM
fldDBLOCK	fldLOCKINFO	fldPDXCHAR {24}
fldDBBINARY	fldBLOB/fldstTYPEDBINARY	fldPDXBINARYBLOB
fldDBOLEBLOB	fldBLOB/fldstDBSOLEOBJ	fldPDXOLEBLOB

---

{button ,AL('interbasetranslations')} InterBase data translations

## From InterBase physical types (to BDE, Paradox, dBASE)

<b>InterBase physical</b>	<b>BDE logical</b>	<b>Paradox physical</b>	<b>dBASE physical</b>
fldIBSHORT	fldINT16	fldPDXSHORT	fldDBNUM {6.0}
fldIBLONG	fldINT32	fldPDXLONG	fldDBNUM {11.0}
fldIBFLOAT	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldIBDOUBLE	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldIBCHAR < 255	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR
fldIBCHAR > 255	fldBLOB	fldSTMEMO	fldDBCHAR
fldIBVARYING < 255	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR
fldIBVARYING > 255	fldBLOB	fldSTMEMO	fldDBCHAR
fldIBDATE	fldTIMESTAMP	fldPDXDATETIME	fldDBDATE
fldIBBLOB	fldBLOB	fldPDXBINARYBLOB	fldDBMEMO
fldIBTEXTBLOB	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO

---

{button ,AL('interbasetranslations')} InterBase data translations

## InterBase equivalents to standard SQL data types

When you use passthrough SQL commands to create or alter an InterBase table, you must use standard SQL data types. Here is a list of standard SQL data types and their corresponding InterBase data types.

<b>FROM SQL</b>	<b>TO InterBase</b>
SMALLINT	SHORT
INTEGER	LONG
DATE	DATE
CHAR(n)	CHAR(n)
VARCHAR(n)	VARYING
DECIMAL	LONG
FLOAT	FLOAT
LONG FLOAT	DOUBLE
BLOB	BLOB

Note: SQL does not support the InterBase ARRAY data type.

---

{button ,AL(`interbasetranslations`)} [InterBase data translations](#)

## InterBase field-naming rules

Here is a list of field-naming rules for Paradox, dBASE, and InterBase.

<b>Database</b>	<b>Naming rule</b>
Paradox	Maximum 25 characters; valid characters are all characters valid; must begin with any valid character except a space.
dBASE	Maximum 31 characters; valid characters are all alphanumeric characters except punctuation marks, blank spaces, and other special characters; must begin with a letter.
InterBase	Maximum 31 characters; valid characters are letters (A-Z, a-z), digits (0-9), \$, or _; must begin with a letter.

**Note:** You may not use InterBase reserved words for table names. See the *InterBase Language Reference* for a list of reserved words.

---

{button ,AL('connectingtointerbase')} [Connecting to InterBase topics](#)

{button ,AL('interbasetranslations')} [InterBase data translations](#)

## Connecting to Informix

This section describes how to troubleshoot common Borland Informix SQL Link connection problems, and discusses various topics about using Borland SQL Links that are unique to Informix.

- [INFORMIX-SQL requirements](#)
- [Informix installation changes](#)
- [Working with Informix servers](#)
- [Special SQL Links driver settings for Informix](#)
- [Troubleshooting Informix connection problems](#)
- [Borland language drivers for Informix](#)
- [Informix data type translations](#)

## INFORMIX-SQL requirements

Here is a list of software that should already be installed and running at the INFORMIX-SQL server before you install the Borland Informix SQL Links driver:

<b>Server requirements</b>	<b>Description</b>
Database server software	Informix version 7 or 9
Network protocol software	TCP/IP or SPX network protocol software compatible with both the database server and the client workstation network protocol.

Here is a list of software and related files that should already be installed and running at the client workstation.

<b>Client requirements</b>	<b>Description</b>
BDE application(s)	Supported BDE application, installed as required by the product documentation.
Informix PC client software	Informix ESQL/C 7.2 or 9.12 for Windows 95 and NT
Requirements	1.5 MB of free disk space. Hardware and operating system that meets the requirements of your Borland desktop product.
Access rights	(For desktop products installed on the network server only.) If your Borland desktop product is installed on a network file server, make sure your network user account has Read and Write access rights to the product's BDE files, including the BDE Administrator (ADMIN.EXE) and the BDE configuration file (IDAPI.CFG). This directory is modified during SQL Links installation.
Network protocol software	TCP or SPX network protocol software compatible with both the server network protocol and the client workstation communication driver.

### Informix database access requirements

Accessing the INFORMIX-SQL database requires a valid user identification and password on the Informix server, and at least Read (SELECT) access privileges. If you are a Netware user, you should also belong to the Network group "Informix" on the server where the Informix database resides.

To obtain these privileges, see your database administrator.

---

{button ,AL('connectingtoinformix')} [Connecting to Informix topics](#)

## Informix installation changes

When you install the Borland Informix SQL Link driver, the following changes take place in your workstation system:

<b>Item added</b>	<b>Description</b>
INFORMIX driver type	Added to BDE Administrator to enable basic configuration of Borland INFORMIX SQL Link driver.
BDEREADME.TXT	Borland SQL Links for Windows README file.
SQLINF32.DLL	Dynamic Link Library comprising the INFORMIX SQL Link driver and its supporting files. (SQLINF9.DLL for version 9.)

---

{button ,AL(`connectingtoinformix`)} [Connecting to Informix topics](#)

## Working with Informix servers

This section provides information about Informix servers and their implementation of SQL. The topics discussed in this section cover aspects of Informix that differ from other SQL database products.

**Note:** To improve query retrieval time, you may want to use the Informix UPDATE STATISTICS statement.

- [Informix data type translations](#)
- [Informix transaction isolation levels](#)
- [Informix field-naming rules](#)

This table lists the general items that you might find helpful in working with Informix.

Item	Description
Dynamic Link Library (DLL) name	SQLINF32.DLL (SQLINF9.DLL for version 9)
Case-sensitive for data?	Yes (including pattern matching)
Case-sensitive for objects (such as tables, columns, indexes)?	No (ANSI-compliant databases are case-sensitive on owner name only)
Does the server require an explicit request to begin a transaction for multi-statement transaction processing?	Yes, if your database is set up for transactions.
Does the server require that you explicitly start a transaction for multi-statement transaction processing in passthrough SQL?	Depends on how the Informix database was set up: ANSI-compliant--NO Logging database--YES Non-logging database--NOT APPLICABLE
Implicit row IDs	Yes
Blob handles	No
Maximum size of single blob read	64K
Multiple client connections?	Yes
Run-time specification of server information, such as Server Name, User Name, and Password?	Yes
Stored procedures?	Yes. See <i>BDE Online Reference</i>

---

{button ,AL('connectingtoinformix')} [Connecting to Informix topics](#)

## Informix transaction isolation levels

Informix supports four levels of isolation among processes attempting to access data. A database's default isolation level is established according to database type, at the time the database is created:

### Dirty read

Default isolation level for non-logging databases. Provides no isolation.

### Committed read

Default isolation level for logging/non-ANSI databases. Guarantees that every retrieved row is committed in the table at the time that the row is retrieved, but does not prevent other processes from acquiring an exclusive lock on that same row. This makes it possible for another process to acquire an exclusive lock on that row, and modify or delete it, before you commit your transaction.

### Cursor stability

Not applicable to BDE applications.

### Repeatable read

Default isolation level for ANSI-compliant databases. Acquires a shared lock on every row selected during the transaction. This does not prevent another process from acquiring a shared lock on a selected row, but it does prevent another process from modifying any selected row during your transaction.

In some cases, when connecting with your Informix database, your BDE application overrides the current Informix transaction isolation settings. The following table shows under which circumstances these overrides occur.

Database	Default isolation level:	Default isolation level:
	Informix	SQL Link
ANSI	RepeatableRead	CommittedRead
Logged	CommittedRead	CommittedRead
Non-logged	DirtyRead	DirtyRead

---

{button ,AL('connectingtoinformix')} [Connecting to Informix topics](#)

## Special SQL Links driver settings for Informix

These BDE Administrator parameters are unique to Informix:

### COLLCHAR

Used with DBNLS to specify whether you can access NLS databases. This lets CHAR/VARCHAR database requests from an application be interpreted as NCHAR/NVARCHAR requests. If DBNLS is '2' and COLLCHAR '1', you can access an NLS database.

### DATABASE NAME

Name of the target SQL database.

### DATE MODE

The format in which the driver sends dates to the SQL server. Valid settings are 0 (MDY) and 1 (DMY).

**Note:** This setting must match the DBDATE environment variable on the Informix server.

### DATE SEPARATOR

The character used to separate day, month, and year for DATE MODE information. Valid characters are the forward slash (/), the period (.), and the dash (-).

The default character is the forward slash.

**Note:** This setting must match the DBDATE environment variable on the Informix server.

### DBNLS

Used with COLLCHAR to specify whether you can access NLS databases. If DBNLS is NULL, you can't create or access an NLS database. If DBNLS is '2' and COLLCHAR is '1', you can access or create an NLS database.

### LOCK MODE

Defines how the server handles a process that tries to access a locked row or table. This table lists possible values and their meanings. The default value is 5 (blank setting).

Setting	SQL statement represented	Meaning
-1	SET LOCK MODE TO WAIT	Suspends the process until the lock is released.
0	SET LOCK MODE TO NOT WAIT	Ends the operation immediately and returns an error code. This is the Informix default, which the Borland Informix driver now overrides.
1-32766	SET LOCK MODE TO WAIT n	Suspends the process until the lock is released, or until the end of the specified number of seconds. Default: 5

**Note:** Lock mode has no effect on exclusive locks. If a process attempts to access a row, table, or database that is locked in exclusive mode, the operation ends and an error code is returned.

---

{button ,AL('connectingtoinformix')} [Connecting to Informix topics](#)

## Troubleshooting Informix connection problems

If you have problems connecting to the Informix database from within your BDE application, Check whether your BDE application's Informix alias is set up properly.

If you can connect directly from your workstation but not from within your BDE application, there is probably a problem with your IDAPI.CFG alias setup. Run the BDE Administrator and examine your Informix alias.

For further information about Informix troubleshooting utilities, see your Informix documentation.

---

{button ,AL(`connectingtoinformix`)} [Connecting to Informix topics](#)

## Borland language drivers for Informix

The following table lists language drivers available for use with Informix, their corresponding character sets, and Borland collation sequences. Choose the language driver that uses the same collation sequence as your server, and the same character set as the one your server uses to pass data to your BDE application.

Long driver name	Short driver name	Character set	Collation sequence
Borland ENU Latin-1	BLLT1US0	ISO8859.1(ANSI)	Binary
dBASE FRA cp437	DB437FR0	DOS CODE PAGE 437	dBASE French
dBASE FIN cp437	DB437FI0	DOS CODE PAGE 437	dBASE Finnish
dBASE ENU cp437	DB437US0	DOS CODE PAGE 437	dBASE English/US
dBASE NOR cp865	DB865NO0	DOS CODE PAGE 865	dBASE Norwegian
dBASE SVE cp437	DB437SV0	DOS CODE PAGE 437	dBASE Swedish
dBASE SVE cp850	DB850SV1	DOS CODE PAGE 850	dBASE Swedish850
dBASE ESP cp437	DB437ES1	DOS CODE PAGE 437	dBASE Spanish
dBASE NLD cp437	DB437NL0	DOS CODE PAGE 437	dBASE Dutch
dBASE ESP cp850	DB850ES1	DOS CODE PAGE 850	dBASE Spanish850
dBASE ENG cp437	DB437UK0	DOS CODE PAGE 437	dBASE English/UK
dBASE ENU cp850	DB850US0	DOS CODE PAGE 850	dBASE English/US
dBASE FRC cp863	DB863CF1	DOS CODE PAGE 863	dBASE French Canadian
dBASE ENG cp850	DB850UK0	DOS CODE PAGE 850	dBASE English850/UK
dBASE ITA cp850	DB850IT1	DOS CODE PAGE 850	dBASE Italian850
dBASE DEU cp850	BD850DE0	DOS CODE PAGE 850	dBASE German850
dBASE FRA cp850	DB850FR0	DOS CODE PAGE 850	dBASE French850
dBASE ITA cp437	DB437IT0	DOS CODE PAGE 437	dBASE Italian
dBASE NLD cp850	DB850NL0	DOS CODE PAGE 850	dBASE Dutch
dBASE FRC cp850	DB850CF0	DOS CODE PAGE 850	dBASE French Canadian850
dBASE DAN cp865	DB865DA0	DOS CODE PAGE 865	dBASE Danish
dBASE DEU cp437	DB437DE0	DOS CODE PAGE 437	dBASE German
DB2 SQL ANSI	db2andeu	1252 (ANSI)	Dictionary
Paradox 'ascii'	ascii	DOS CODE PAGE 437	Binary
Paradox 'intl'	intl	DOS CODE PAGE 437	Paradox 'intl'
Paradox 'intl' 850	intl850	DOS CODE PAGE 850	Paradox 'intl' 850
Paradox 'nordan'	nordan	DOS CODE PAGE 865	Paradox 'nordan'
Paradox 'nordan40'	nordan40	DOS CODE PAGE 865	Paradox 'nordan40'
Paradox 'swedfin'	swedfin	DOS CODE PAGE 437	Paradox 'swedfin'
Paradox ANSI INTL	ANSIINTL	ISO8859.1 (ANSI)	Paradox 'intl'
Paradox ESP 437	SPANISH	DOS CODE PAGE 437	Paradox ESP 437
Paradox ISL 861	iceland	DOS CODE PAGE 861	Paradox ISL 861
Pdcox ANSI INTL850	ANSII850	ISO8859.1 (ANSI)	Paradox 'intl' 850
Pdcox ANSI NORDAN4	ANSINOR4	ISO8859.1 (ANSI)	Paradox 'nordan40'
Pdcox ANSI SWEDFIN	ANSISWFN	ISO8859.1 (ANSI)	Paradox 'swedfin'
Pdcox ESP ANSI	ANSISPAN	ISO8859.1 (ANSI)	Paradox ESP437
SQL Link ROMAN8	BLROM800	ROMAN8	Binary

---

{button ,AL(`connectingtoinformix`)} Connecting to Informix topics

## Informix data type translations

Certain database operations cause SQL Links to convert data from Paradox or dBASE format to Informix format. For example, a BDE application that copies or appends data from a local table to an Informix table causes SQL Links to convert the local data to Informix format before performing the copy or append operation.

Other database operations cause a conversion in the opposite direction, from Informix format to Paradox or dBASE format. For example, suppose you run a local query against one or more SQL tables. During the query, SQL Links converts any data originating in an SQL database to Paradox or dBASE format (depending on the answer format requested) before placing the data in the local answer table.

The following topics contain tables showing Informix, Paradox, and dBASE data types and show how SQL Links translates between them in append, copy, and local query operations:

- [From Informix data types](#)
- [From Paradox data types](#)
- [From dBASE data types](#)
- [From Paradox physical types](#)
- [From dBASE physical types](#)
- [From Informix physical types](#)
- [Using the Informix Interval data type](#)

---

{button ,AL('connectingtoinformix')} [Connecting to Informix topics](#)

## From Informix data types (to Paradox, dBASE)

<b>From Informix</b>	<b>To Paradox</b>	<b>To dBASE</b>
Char <255	Alpha	Character
Char >255	Memo	Memo
Smallint	Short	Number {6.0}
Integer	Number	Number {11.0}
Smallfloat	Number	Float {20.4}
Float	Number	Float {20.4}
Money	Money	Float
Decimal	Number	Float
Date	Date	Date
DateTime	DateTime	Date
Interval	Alpha {25}	Character
Serial	Number	Number {11.0}
Byte	Binary	Memo
Text	Memo	Memo
Varchar	Alpha	Character

The following data types are added when using Informix 5 or later

<b>From Informix 5</b>	<b>To Paradox</b>	<b>To dBASE</b>
NChar <255	Alpha	Character
NChar >255	Memo	Memo
NVarchar	Alpha	Character

---

{button ,AL('informixdatatranslations')} [Informix data translations](#)

## From Paradox data types (to dBASE, Informix)

From Paradox	To dBASE	To Informix
Alpha	Character	VarChar
Number	Float {20.4}	Float
Money	Float {20.4}	Money {16.2}
Date	Date	Date
Short	Number {6.0}	Smallint
Memo	Memo	Text
Binary	Memo	Byte
Formatted Memo	Memo	Byte
OLE	Memo	Byte
Graphic	Memo	Byte
Long	Number {11.0}	Integer
Time	Character {>8}	Character {>8}
DateTime	Character {>8}	DateTime
Bool	Bool	Character
AutoInc	Number {11.0}	Integer
Bytes	Bytes	Byte
BCD	N/A	N/A

---

{button ,AL('informixdatatranslations')} [Informix data translations](#)

## From dBASE data types (to Paradox, Informix)

From dBASE	To Paradox	To Informix
Character	Alpha	VarChar
Number	Short, Number	Smallint, Float
Float	Number	Float
Date	Date	Date
Memo	Memo	Text
Bool	Bool	Char
Bytes	Bytes	Byte
Lock	Alpha {24}	Char

**Note:** The dBASE Number data type translates to different Informix and Paradox data types depending on the WIDTH and DEC specification. A dBASE Number with a WIDTH less than 5 and a DEC equal to 0 translates to the Informix Smallint data type or the Paradox Short data type. dBASE Numbers with a WIDTH greater than 5 or a DEC greater than 0 translate into the Informix Float data type or the Paradox Number data type.

---

{button ,AL('informixdatatranslations')} [Informix data translations](#)

## From Paradox physical types (to BDE, dBASE)

<b>Paradox physical</b>	<b>BDE logical</b>	<b>dBASE physical</b>
fldPDXAUTOINC	fldINT32	fldDBNUM {11.0}
fldPDXBCD	fldBCD	fldDBCHAR
fldPDXBINARYBLOB	fldBLOB/fldstBINARY	fldDBMEMO
fldPDXBLOB	fldPDXMEMO	fldDBMEMO
fldPDXBOOL	fldBOOL	fldDBBOOL
fldPDXBYTES	fldBYTES	fldDBBYTES
fldPDXCHAR	fldZSTRING	fldDBCHAR
fldPDXDATE	fldDATE	fldDATE
fldPDXDATETIME	fldTIMESTAMP	fldDBCHAR {30}
fldPDXFMTMEMO	fldBLOB/fldstFMTMEMO	fldDBMEMO
fldPDXGRAPHIC	fldBLOB/fldstGRAPHIC	fldDBMEMO
fldPDXLONG	fldINT32	fldDBNUM {11.0}
fldPDXMEMO	fldBLOB/fldstMEMO	fldDBMEMO
fldPDXMONEY	fldFLOAT/fldstMONEY	fldDBFLOAT {20.4}
fldPDXNUM	fldFLOAT	fldDBFLOAT {20.4}
fldPDXOLEBLOB	fldBLOB/fldstOLEOBJ	fldDBMEMO
fldPDXSHORT	fldINT16	fldDBNUM {6.0}
fldPDXTIME	fldTIME	fldDBCHAR {>8}

---

{button ,AL('informixdatatranslations')} Informix data translations

## From dBASE physical types (to BDE, Paradox)

<b>dBASE physical</b>	<b>BDE logical</b>	<b>Paradox physical</b>
fldDBCHAR	fldZSTRING	fldPDXCHAR
fldDBNUM	if( iUnits2=0 && iUnits1<5 )	fldINT16 else fldFLOAT fldPDXSHORT fldPDXNUM
fldDBMEMO	fldBLOB	fldPDXMEMO
fldDBBOOL	fldBOOL	fldPDXBOOL
fldDBDATE	fldDATE	fldPDXDATE
fldDBFLOAT	fldFLOAT	fldPDXNUM
fldDBLOCK	fldLOCKINFO	N/A
fldDBBINARY	fldBLOB/fldstTYPEDBINARY	fldPDXBINARYBLOB
fldDBOLEBLOB	fldBLOB/fldstDBSOLEOBJ	fldPDXOLEBLOB

---

{button ,AL('informixdatatranslations')} [Informix data translations](#)

## From Informix physical types (to BDE, Paradox, dBASE)

Informix physical	BDE logical	Paradox physical	dBASE physical
fldINFCHAR < 255	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR
fldINFCHAR > 255	fldBLOB	fldstMEMO	fldDBMEMO
fldINFSMALLINT	fldINT16	fldPDXSHORT	fldDBNUM {6.0}
fldINFINTEGER	fldINT32	fldPDXLONG	fldDBNUM {11.0}
fldINFSMALLFLOAT	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldINFFLOAT	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldINFMONEY	fldFLOAT/fldstMONEY	fldPDXMONEY	fldDBFLOAT {20.4}
fldINFDECIMAL	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldINFDATE	fldDATE	fldPDXDATE	fldDBDATE
fldINFDATETIME	fldTIMESTAMP	fldPDXDATETIME	fldDBDATE
fldINFINTERVAL	fldZSTRING	fldPDXCHAR	fldDBCHAR
fldINFSERIAL	fldINT32	fldPDXLONG	fldDBNUM {11.0}
fldINFBYTE	fldBLOB/fldstBINARY	fldPDXBINARYBLOB	fldDBMEMO
fldINFTEXT	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO
fldINFVARCHAR	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR

---

{button ,AL('informixdatatranslations')} Informix data translations

## Using the Informix Interval data type

BDE applications have no data type that is directly equivalent to the Informix Interval data type.

Developers can create Interval fields with the Year-to-month qualifier on Informix servers. However, when you manipulate Informix Interval data with any range qualifiers through your BDE application, the SQL Link driver translates it into a character string.

For more information on the Informix Interval data type, see the *Informix Guide to SQL: Reference*.

---

{button ,AL('informixdatatranslations')} [Informix data translations](#)

## Informix field-naming rules

This table lists field-naming rules for Paradox, dBASE, and Informix.

Naming rule	Paradox	dBASE	Informix
Max length (characters)	25	31	18
Valid characters	All	All except punctuation marks, blank spaces, and other special characters	Integers from 0 to 9, upper or lowercase letters, and underscore ( _ ) character
Must begin with . . .	Any valid character	A letter	A letter except space

**Note:** Paradox field names should not contain:

- square brackets []
- curly braces {}
- pipes |
- parentheses ()
- the combination ->
- or the hash symbol # by itself.

---

{button ,AL('connectingtoinformix')} [Connecting to Informix topics](#)

{button ,AL('informixdatatranslations')} [Informix data translations](#)

## Connecting to ORACLE

This section contains topics about using Borland SQL Links that are unique to ORACLE. These settings are applicable only if you have purchased and installed the Borland SQL Links Driver for ORACLE.

- [ORACLE requirements](#)
- [ORACLE installation changes](#)
- [Working with ORACLE servers](#)
- [Special SQL Links driver settings for ORACLE](#)
- [Troubleshooting ORACLE connection problems](#)
- [Borland language drivers for ORACLE](#)
- [ORACLE data type translations](#)
- [ORACLE field-naming rules](#)

## ORACLE requirements

This table lists software that should already be installed and running at the ORACLE server before you install the Borland ORACLE SQL Links driver.

<b>Server requirements</b>	<b>ORACLE 7</b>	<b>ORACLE 8</b>
Database server software	ORACLE version 7.3 or later	ORACLE version 8.04 or later
Network protocol software	ORACLE SQL*NET version 2 or later	ORACLE NET80 version 8.0.4 or later

For information on network protocol software and network access rights, see your system administrator.

This table lists software that should already be installed and running at the client workstation. It also lists related files and parameters.

<b>Client requirements</b>	<b>Description</b>
Network protocol software	Network protocol software compatible with both the server network protocol and the client workstation client database communication driver.

---

{button ,AL('connectingtooracle')} [Connecting to ORACLE topics](#)

## ORACLE installation changes

When you install the Borland ORACLE SQL Links driver, the following changes take place in your workstation system:

Item added	Description
ORACLE 7: SQLORA32.DLL	Dynamic Link Library comprising the ORACLE SQL Links driver and its supporting files.
ORACLE 8: SQLORA8.DLL	
ORACLE driver type	Added to BDE Administrator Configuration page to enable basic configuration of Borland ORACLE SQL Links driver.

---

{button ,AL('connectingtooracle')} [Connecting to ORACLE topics](#)

## Special SQL Links driver settings for ORACLE

The following topics describe driver configuration parameters that are unique to ORACLE:

### ENABLE INTEGERS

Specifies whether the BDE translates NUMERIC fields with no scale into logical integers.

**Note:** If this setting and ENABLE BCD are both TRUE, ENABLE INTEGERS takes precedence.

#### Default:

FALSE (don't convert NUMERIC fields into logical integers)

### NET PROTOCOL

Network transport is used to communicate with the SQL server. This table describes NET PROTOCOL options.

### ENABLE SCHEMA CACHE

For Oracle8, ENABLE SCHEMA CACHE should be set to FALSE since SCHEMA CACHE mode is not supported.

Value	Description
3270	IBM 3270 protocol
APPC	IBM APPC LU 6.2 protocol
ASYNCR	Asynchronous (dial-up) access protocol
DECNET	Digital Equipment Corporation DECnet protocol
NAMED PIPES	Named Pipes protocol, as used by OS/2
NETBIOS	NetBios protocol, as used by LAN Manager and other PC LANs
SPX/IPX	SPX/IPX protocol, as used by Novell NetWare
TCP/IP	Transport Control Protocol/Internet Protocol, as used by UNIX and VAX workstations
VINES	Banyan VINES protocol
TNS	Transparent Network Substrate, Oracle high-level communications protocol

### OBJECT MODE

OBJECT MODE should be set to TRUE when connecting to ORACLE8 and accessing object types such as ADT, VARRAY, REF, NESTED TABLE, etc. OBJECT MODE should be set to FALSE when using Oracle servers prior to ORACLE8. Setting OBJECT MODE to TRUE initializes the OCI object cache on the client. Applications that work only with scalar data types should have OBJECT MODE set to FALSE and the OCI object cache will not be initialized.

#### Default:

TRUE (applies only to Oracle 8).

### Vendor Init

Enter the vendor DLL filename. For ORACLE 7, use ORA73.DLL (unless you require MTS services, in which case you must choose MTXOCI.DLL). For ORACLE8, choose OCI.DLL.

### Oracle synonyms

Synonyms are alternate names for other objects, such as tables or views. The special SQL Links Driver setting for ORACLE, called LIST SYNONYMS, determines whether or not to include synonyms in the schema table returned from BDE API functions DbiOpenTableList and DbiOpenFileList, as shown in the following table.

Value	Meaning
NONE	Do not include any synonyms (default)

PRIVATE            Only include private synonyms  
ALL                Include both private and public synonyms

Synonyms are supported by a field in the BDE TBLBaseDesc structure called *bSynonym*. The field *bSynonym* is a BOOL16, which is set to TRUE if the object is a synonym.

#### **Cross database and cross server table access**

You can access Oracle synonyms by using DbiOpenTable. You can access tables on different databases or servers in the same way. For example, you can open "SCOTT"."CUSTOMER"@ "DBLINK" on Oracle and pubs.dbo.authors on Sybase.

#### **Public synonyms**

Oracle has PUBLIC synonyms that appear in the table list when the value of LIST SYNONYMS = ALL. However, to open a PUBLIC synonym, the user must also have SELECT privileges on the base object of the synonym. If the user does not have SELECT privileges and tries to open the PUBLIC SYNONYM, Oracle returns the error "Table or view does not exist".

Oracle has PUBLIC synonyms to a set of dynamic performance tables. Even though these are PUBLIC synonyms, they are accessible only to the DBA user SYS, by default (other users can be granted privileges). These synonym names are in the format, V\$... (that is, V\$DATABASE, V\$ACCESS, and so on).

---

{button ,AL(`connectingtooracle`)} [Connecting to ORACLE topics](#)

## Working with ORACLE servers

This table lists the general items that you might find helpful in working with ORACLE servers.

<b>Item</b>	<b>Description</b>
Dynamic Link Library (DLL) name	SQLORA32.DLL (ORACLE 7.3 or later) SQLORA8.DLL (ORACLE 8.04 or later)
Case-sensitive for data?	Yes
Case-sensitive for objects (such as tables, columns and indexes)?	Yes
Does the server require an explicit request to begin a transaction for multistatement transaction processing?	Yes
Does the server require that you explicitly start a transaction for multistatement transaction processing in passthrough SQL?	No
Implicit row IDs	Yes
Blob handles	No

---

{button ,AL('connectingtooracle')} [Connecting to ORACLE topics](#)

## Troubleshooting ORACLE connection problems

If you have problems establishing an ORACLE connection with SQL Links, Check whether your BDE application ORACLE alias is set up properly.

If you can connect directly from your workstation but not from within your BDE application, there is probably a problem with your BDEADMIN.EXE alias setup. Run the BDE Administrator and examine your ORACLE alias.

For more information on ORACLE diagnostic tools, see your ORACLE documentation.

---

{button ,AL(`connectingtooracle`)} [Connecting to ORACLE topics](#)

## Borland language drivers for ORACLE

The following table lists language drivers available for use with ORACLE, their corresponding character sets, and Borland collation sequences. Choose the language driver that uses the same collation sequence as your server, and the same character set as the one your server uses to pass data to your BDE application.

**Note:** If you need to use a language driver that does not properly mimic the ORACLE server collation sequence, be sure to set SQLQRYMODE to SERVER in your ORACLE database alias.

Long name	Short name	Character set	Collation sequence
Borland ENU Latin-1	BLLT1US0	ISO8859.1(ANSI)	Binary
dBASE FRA cp437	DB437FR0	DOS CODE PAGE 437	dBASE French
dBASE FIN cp437	DB437FI0	DOS CODE PAGE 437	dBASE Finnish
dBASE ENU cp437	DB437US0	DOS CODE PAGE 437	dBASE English/US
dBASE NOR cp865	DB865NO 0	DOS CODE PAGE 865	dBASE Norwegian
dBASE SVE cp437	DB437SV0	DOS CODE PAGE 437	dBASE Swedish
dBASE SVE cp850	DB850SV1	DOS CODE PAGE 850	dBASE Swedish850
dBASE ESP cp437	DB437ES1	DOS CODE PAGE 437	dBASE Spanish
dBASE NLD cp437	DB437NL0	DOS CODE PAGE 437	dBASE Dutch
dBASE ESP cp850	DB850ES1	DOS CODE PAGE 850	dBASE Spanish850
dBASE ENG cp437	DB437UK0	DOS CODE PAGE 437	dBASE English/UK
dBASE ENU cp850	DB850US0	DOS CODE PAGE 850	dBASE English/US
dBASE FRC cp863	DB863CF1	DOS CODE PAGE 863	dBASE French Canadian
dBASE ENG cp850	DB850UK0	DOS CODE PAGE 850	dBASE English850/UK
dBASE ITA cp850	DB850IT1	DOS CODE PAGE 850	dBASE Italian850
dBASE DEU cp850	BD850DE0	DOS CODE PAGE 850	dBASE German850
dBASE FRA cp850	DB850FR0	DOS CODE PAGE 850	dBASE French850
dBASE ITA cp437	DB437IT0	DOS CODE PAGE 437	dBASE Italian
dBASE NLD cp850	DB850NL0	DOS CODE PAGE 850	dBASE Dutch
dBASE FRC cp850	DB850CF0	DOS CODE PAGE 850	dBASE French Canadian850
dBASE DAN cp865	DB865DA0	DOS CODE PAGE 865	dBASE Danish
dBASE DEU cp437	DB437DE0	DOS CODE PAGE 437	dBASE German
DB2 SQL ANSI	db2andeu	1252 (ANSI)	Dictionary
Oracle SQL WE850	ORAWE850 0	DOS CODE PAGE 850	ORACLE multi-lingual Western European sort order
Paradox 'ascii'	ascii	DOS CODE PAGE 437	Binary
Paradox 'intl'	intl	DOS CODE PAGE 437	Paradox 'intl'
Paradox 'intl' 850	intl850	DOS CODE PAGE 850	Paradox 'intl' 850
Paradox 'nordan'	nordan	DOS CODE PAGE 865	Paradox 'nordan'
Paradox 'nordan40'	nordan40	DOS CODE PAGE 865	Paradox 'nordan40'
Paradox 'swedfin'	swedfin	DOS CODE PAGE 437	Paradox 'swedfin'
Paradox ANSI INTL	ANSIINTL	ISO8859.1 (ANSI)	Paradox 'intl'
Paradox ESP 437	SPANISH	DOS CODE PAGE 437	Paradox ESP 437

Paradox ISL 861	iceland	DOS CODE PAGE 861	Paradox ISL 861
Pdox ANSI INTL850	ANSII850	ISO8859.1 (ANSI)	Paradox 'intl' 850
Pdox ANSI NORDAN4	ANSINOR 4	ISO8859.1 (ANSI)	Paradox 'nordan40'
Pdox ANSI SWEDFIN	ANSISWF N	ISO8859.1 (ANSI)	Paradox 'swedfin'
Pdox ESP ANSI	ANSISPAN	ISO8859.1 (ANSI)	Paradox ESP437
SQL Links ROMAN8	BLROM80 0	ROMAN8	Binary

---

{button ,AL(`connectingtooracle`)} Connecting to ORACLE topics

## ORACLE data type translations

Certain database operations cause SQL Links to convert data from Paradox or dBASE format to ORACLE format. For example, a BDE application that copies or appends data from a local table to an ORACLE table causes SQL Links to convert the local data to ORACLE format before performing the copy or append operation.

Other database operations cause a conversion in the opposite direction, from ORACLE format to Paradox or dBASE format. For example, suppose you run a local query against one or more SQL tables. During the query, SQL Links converts any data originating in an SQL database to Paradox or dBASE format (depending on the answer format requested) before placing the data in the local answer table.

The following topics contain tables that list ORACLE, Paradox, and dBASE data types and show how SQL Links translates between these data types:

- [From ORACLE data types](#)
- [From Paradox data types](#)
- [From dBASE data types](#)
- [From Paradox physical types](#)
- [From dBASE physical types](#)
- [From ORACLE physical types](#)

---

{button ,AL('connectingtooracle')} [Connecting to ORACLE topics](#)

## From ORACLE data types (to Paradox, dBASE)

<b>FROM: ORACLE</b>	<b>TO: Paradox</b>	<b>TO: dBASE</b>
CHAR(n)	VARCHAR(n)	Alphanumeric(n)Character(n)
DATE {date/time}	DateTime	Character {date/time}
FLOAT	Number	Number {20.4}
LONG	Memo	Memo
LONG RAW	Binary	Memo
NUMBER	Number	Float {20.4}
RAW	Binary	Memo
VARCHAR2 (CHAR <255)	Alphanumeric(n)	Character(n)1
VARCHAR2 (CHAR >255)	Memo	Memo

---

{button ,AL('oracletranslations')} [ORACLE data translations](#)

## From Paradox data types (to ORACLE, dBASE)

<b>FROM: Paradox</b>	<b>TO: ORACLE</b>	<b>TO: dBASE</b>
Alphanumeric(n)	VARCHAR2(n)	Character(n)
Number	NUMBER	Float {20.4}
Money	NUMBER	Float {20.4}
Date	DATE {date/time}	Character {date/time}
Short	NUMBER	Number {6.0}
Memo	LONG	Memo
Formatted memo	LONG RAW	Memo
Binary	LONG RAW	Memo
Graphic	LONG RAW	Memo
OLE	LONG RAW	Memo
Long	NUMBER	Number {11.0}
Time	CHARACTER {>8}	Character {>8}
Datetime	DATE	Character {>8}
Logical	CHARACTER {1}	Bool
AutoInc	NUMBER	Number {11.0}
Bytes	LONG RAW	BYTES
BCD	N/A	N/A

---

{button ,AL('oracletranslations')} ORACLE data translations

## From dBASE data types (to ORACLE, Paradox)

<b>FROM: dBASE</b>	<b>TO: ORACLE</b>	<b>TO: Paradox</b>
Character	VARCHAR2(n)	Alphanumeric(n)
Number1	NUMBER	Short, Number
Float	NUMBER	Short, Number
Date	DATE {date/time}	Date
Logical	CHAR(1)	Bool
Memo	LONG	Memo
Bytes	LONG RAW	Bytes
Lock	CHAR(24)	Alphanumeric {24}.

---

{button ,AL(`oracletranslations`)} ORACLE data translations

## From Paradox physical types (to BDE, dBASE)

<b>Paradox physical</b>	<b>BDE logical</b>	<b>dBASE physical</b>
fldPDXCHAR	fldZSTRING	fldDBCHAR
fldPDXNUM	fldFLOAT	fldDBFLOAT {20.4}
fldPDXMONEY	fldFLOAT/fldstMONEY	fldDBFLOAT {20.4}
fldPDXDATE	fldDATE	fldDATE
fldPDXSHORT	fldINT16	fldDBNUM {6.0}
fldPDXMEMO	fldBLOB/fldstMEMO	fldDBMEMO
fldPDXBINARYBLOB	fldBLOB/fldstBINARY	fldDBMEMO
fldPDXFMTMEMO	fldBLOB/fldstFMTMEMO	fldDBMEMO
fldPDXOLEBLOB	fldBLOB/fldstOLEOBJ	fldDBMEMO
fldPDXGRAPHIC	fldBLOB/fldstGRAPHIC	fldDBMEMO
fldPDXBLOB	fldPDXMEMO	fldDBMEMO
fldPDXLONG	fldINT32	fldDBNUM {11.0}
fldPDXTIME	fldTIME	fldDBCHAR {>8}
fldPDXDATETIME	fldTIMESTAMP	fldDBCHAR {30}
fldPDXBOOL	fldBOOL	fldDBBOOL
fldPDXAUTOINC	fldINT32	fldDBNUM {11.0}
fldPDXBYTES	fldBYTES	fldDBBYTES
fldPDXBCD	fldBCD	fldDBCHAR

---

{button ,AL(^oracletranslations')} ORACLE data translations

## From dBASE physical types (to BDE, Paradox)

<b>dBASE physical</b>	<b>BDE logical</b>	<b>Paradox physical</b>
fldDBCHAR	fldZSTRING	fldPDXCHAR
fldDBNUM	if( iUnits2=0 && iUnits1<5 )	fldINT16 else fldFLOAT fldPDXSHORT fldPDXNUM
fldDBMEMO	fldBLOB	fldPDXMEMO
fldDBBOOL	fldBOOL	fldPDXBOOL
fldDBDATE	fldDATE	fldPDXDATE
fldDBFLOAT	fldFLOAT	fldPDXNUM
fldDBLOCK	fldLOCKINFO	fldPDXCHAR {24}
fldDBBINARY	fldBLOB/fldstTYPEDBINARY	fldPDXBINARYBLOB
fldDBOLEBLOB	fldBLOB/fldstDBSOLEOBJ	fldPDXOLEBLOB

---

{button ,AL(`oracletranslations`)} ORACLE data translations

## From ORACLE physical types (to BDE, Paradox, dBASE)

<b>ORACLE physical</b>	<b>BDE logical</b>	<b>Paradox physical</b>	<b>dBASE physical</b>
fldORACHAR	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR
fldORARAW	fldVARBYTES	fldPDXBINARYBLOB	fldDBMEMO
fldORADATE	fldTIMESTAMP	fldPDXDATETIME	fldDBCHAR
fldORANUMBER	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldORALONG	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO
fldORALONGRAW	fldBLOB/fldstBINARY	fldPDXBINARYBLOB	fldDBMEMO
fldORAVARCHAR	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR
fldORAVARCHAR2 <255	fldZSTRING	fldPDXCHAR	fldDBCHAR
fldORA VARCHAR2 >255	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO
fldORAFLOAT	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}

---

{button ,AL(`oracletranslations`)} ORACLE data translations

## ORACLE field-naming rules

Here is a list of field-naming rules for Paradox, dBASE, and ORACLE.

Naming rule	Paradox	dBASE	ORACLE
Max length (characters)	25	31	30
Valid characters	All	All except punctuation marks, blank spaces, and other special characters	A-Z, 0-9, -, \$, #
Must begin with. . .	Any valid character except space	A letter	A letter

**Note:** You may not use ORACLE reserved words for remote table names, quoted table names, or quoted index names. For a list of reserved words and other naming restrictions, see the *ORACLE Programmer's Reference*.

---

{button ,AL('connectingtooracle')} [Connecting to ORACLE topics](#)

{button ,AL('oracletranslations')} [ORACLE data translations](#)

## Connecting to Sybase

This section contains topics about using Borland SQL Links that are unique to Sybase. These settings are applicable only if you have purchased and installed the Borland SQL Links Driver for Sybase.

- [Sybase requirements](#)
- [Sybase installation changes](#)
- [Working with Sybase servers](#)
- [Special SQL Links driver settings for Sybase](#)
- [Troubleshooting Sybase connection problems](#)
- [Borland language drivers for Sybase](#)
- [Sybase data type translations](#)
- [Sybase field-naming rules](#)

## Sybase requirements

Here is a list of software that should already be installed and running at the Sybase server before you install the Borland Sybase SQL Links driver.

<b>Server requirements</b>	<b>Description</b>
Database server software	Version 4.x and earlier with DB-Lib interface OR: System 10 and later with CT-Lib interface
Network protocol software	Supporting the Sybase Net libraries

For information on network protocol software and network access rights, see your system administrator.

Here is a list of software that should already be installed and running at the client workstation:

<b>Client requirements</b>	<b>Description</b>
BDE application(s)	Supported BDE application, installed as required by the product documentation.
Requirements	1.5 MB of free disk space. Hardware and operating system that meets the requirements of your BDE application.
Access rights	(For applications installed on the network server only.) If your BDE application is installed on the shared disk of a network file server, make sure your network user account has Read and Write access rights to the application's BDE files (including BDEADMIN.EXE and IDAPI.CFG). This directory is modified during SQL Links installation.
Network protocol software	Network protocol software compatible with both the server network protocol and the client workstation client database communication driver.

---

{button ,AL(`connectingtosybase`)} [Connecting to Sybase topics](#)

## Sybase installation changes

When you install a Borland Sybase SQL Links driver the following changes take place in your workstation system:

<b>Item added</b>	<b>Description</b>
SQLSYB32.DLL	Dynamic Link Library comprising the Sybase driver and its supporting files (for DB-Lib/Version 4.x).
SQLSSC32.DLL	Dynamic Link Library comprising the Sybase driver and its supporting files (for CT-Lib/System 10 and later).
Sybase driver type	Added to BDE Administrator Configuration page to enable basic configuration of Borland Sybase SQL Links driver.

---

{button ,AL(`connectingtosybase`)} [Connecting to Sybase topics](#)

## Working with Sybase servers

This section provides information about Sybase and its implementation of SQL. The topics discussed in this section cover aspects of Sybase that differ from other SQL database products.

Here is a list of general items that you might find helpful in working with Sybase:

Item	Description
Product name	Sybase SQL Server Version 4.x OR: Sybase SQL Server System 10 and later
SQL dialect	Sybase TRANSACT-SQL
Dynamic Link Library (DLL) name	SQLSYB32.DLL (for DB-Lib/Version 4.x) SQLSSC32.DLL (for CT-Lib/System 10 and later)
Case-sensitive for data?	As installed
Case-sensitive for objects (such as tables, columns, and indexes)?	As installed
Does the server require an explicit request to begin a transaction for multi-statement transaction processing?	Yes
Does the server require that you explicitly start a transaction for multi-statement transaction processing in passthrough SQL?	Yes
Implicit row IDs	No
Blob handles	No
Maximum size of single BLOB read (if BLOB handles are not supported)	32K

---

{button ,AL(`connectingtosybase`)} [Connecting to Sybase topics](#)

## Special SQL Links driver settings for Sybase

The following topics describe driver configuration parameters that are unique to Sybase:

### APPLICATION NAME

Specifies an application name used in the sysprocesses table of the master database to help the server identify your process.

### BLOB EDIT LOGGING

Enables or disables the logging of any edits to blob (Binary Large Object) fields. Possible values are TRUE (the default) or FALSE. When set to FALSE, this option helps minimize log space requirements and increase performance.

**Note:** If you set blob EDIT LOGGING to FALSE, you must also set BULKCOPY to ON at the server. For more information, see your SQL Server documentation.

### CONNECT TIMEOUT

Specifies the amount of time the workstation will retry when attempting to attach to the SQL server. The default is 60 seconds.

### DATABASE NAME

Name of the target SQL database.

### DATE MODE

The format in which the driver sends dates to the SQL server. Valid settings are 0 (MDY), 1 (DMY), and 2 (YMD).

### HOST NAME

Specifies a workstation name used in the sysprocesses table of the master database to help the server identify your process. Also appears when sp\_who is executed on the server.

### NATIONAL LANG NAME

Specifies the language to use when displaying error messages. If blank, the default SQL server language is used. Only applies to servers with language support installed.

### TDS PACKET SIZE

Specifies the size of tabular data stream (TDS) packets exchanged by the client and server. TDS PACKET SIZE can be a value from 0 to 65535. Larger packet sizes can improve performance by reducing the number of packet requests, especially when working with BLOBs. A packet size between 4096 and 8192 is recommended for optimal performance.

To determine the TDS PACKET SIZE settings supported by your server, send the SQL command sp\_configure to your Sybase or MS SQL server, then note the settings returned for MAX NETWORK PACKET SIZE and ADDITIONAL NETMEM. If TDS PACKET SIZE is set to a higher value than the maximum network packet size, or ADDITIONAL NETMEM is not set, the following errors can occur:

Error : unknown user name or password

Server error

4002 Login failed

20014 Login incorrect

TDS 5 or later is required to modify the packet size. See the Sybase System Administrator's Guide for more information.

### Default:

512

**TIMEOUT**

Specifies the maximum amount of time that the workstation waits for results to return from the server. The default is 500 seconds.

You may want to change the TIMEOUT value to minimize conflicts between operations. For best performance, determine how much time a complex query would take to complete successfully on your network, then set TIMEOUT to a slightly larger number than that. For example, if you often run complex queries that can take up to 120 seconds to complete, be sure to set the TIMEOUT value to more than 120 seconds.

**MAX QUERY TIME**

Specifies the maximum amount of time that SQL Links will wait for query execution to complete before canceling the operation. The default is 3,600 seconds.

**Note:** Applications using earlier versions of SQL Links for Sybase may generate an error message if a transaction isolation level other than Repeatable Read has been specified. In such cases, specify an isolation level of Read Committed when starting a transaction or use the BDE Administrator to set the Driver Flags parameter to 512.

Although the beginTrans (dBASE) or beginTransaction (Paradox) methods indicate that the isolation level is optional, when using SQL Links for Sybase, specify the Read Committed isolation level.

---

{button ,AL('connectingtosybase')} [Connecting to Sybase topics](#)

## Troubleshooting Sybase connection problems

If you have problems establishing a Sybase connection with SQL Links, Check whether your BDE application Sybase alias is set up properly.

If you can connect directly from your workstation but not from within your BDE application, there is probably a problem with your BDEADMIN.EXE alias setup. Run the BDE Administrator and examine your Sybase alias.

For more information on your vendor-supplied diagnostic tools, see your Sybase documentation.

---

{button ,AL('connectingtosybase')} Connecting to Sybase topics

## Borland language drivers for Sybase

The following table lists language drivers available for use with Sybase, their corresponding character sets, and Borland collation sequences. The language driver you choose must use the same collation sequence as your server, and the same character set as the one your server uses to pass data to your BDE application.

Long name	Short name	Character set	Collation sequence
Borland ENU Latin-1	BLLT1US0	ISO8859.1(ANSI)	Binary
dBASE FRA cp437	DB437FR0	DOS CODE PAGE 437	dBASE French
dBASE FIN cp437	DB437FI0	DOS CODE PAGE 437	dBASE Finnish
dBASE ENU cp437	DB437US0	DOS CODE PAGE 437	dBASE English/US
dBASE NOR cp865	DB865NO0	DOS CODE PAGE 865	dBASE Norwegian
dBASE SVE cp437	DB437SV0	DOS CODE PAGE 437	dBASE Swedish
dBASE SVE cp850	DB850SV1	DOS CODE PAGE 850	dBASE Swedish850
dBASE ESP cp437	DB437ES1	DOS CODE PAGE 437	dBASE Spanish
dBASE NLD cp437	DB437NL0	DOS CODE PAGE 437	dBASE Dutch
dBASE ESP cp850	DB850ES1	DOS CODE PAGE 850	dBASE Spanish850
dBASE ENG cp437	DB437UK0	DOS CODE PAGE 437	dBASE English/UK
dBASE ENU cp850	DB850US0	DOS CODE PAGE 850	dBASE English/US
dBASE FRC cp863	DB863CF1	DOS CODE PAGE 863	dBASE French Canadian
dBASE ENG cp850	DB850UK0	DOS CODE PAGE 850	dBASE English850/UK
dBASE ITA cp850	DB850IT1	DOS CODE PAGE 850	dBASE Italian850
dBASE DEU cp850	BD850DE0	DOS CODE PAGE 850	dBASE German850
dBASE FRA cp850	DB850FR0	DOS CODE PAGE 850	dBASE French850
dBASE ITA cp437	DB437IT0	DOS CODE PAGE 437	dBASE Italian
dBASE NLD cp850	DB850NL0	DOS CODE PAGE 850	dBASE Dutch
dBASE FRC cp850	DB850CF0	DOS CODE PAGE 850	dBASE French Canadian850
dBASE DAN cp865	DB865DA0	DOS CODE PAGE 865	dBASE Danish
dBASE DEU cp437	DB437DE0	DOS CODE PAGE 437	dBASE German
DB2 SQL ANSI	db2andeu	1252 (ANSI)	Dictionary
Paradox 'ascii'	ascii	DOS CODE PAGE 437	Binary
Paradox 'intl'	intl	DOS CODE PAGE 437	Paradox 'intl'
Paradox 'intl' 850	intl850	DOS CODE PAGE 850	Paradox 'intl' 850
Paradox 'nordan'	nordan	DOS CODE PAGE 865	Paradox 'nordan'
Paradox 'nordan40'	nordan40	DOS CODE PAGE 865	Paradox 'nordan40'
Paradox 'swedfin'	swedfin	DOS CODE PAGE 437	Paradox 'swedfin'
Paradox ANSI INTL	ANSIINTL	ISO8859.1 (ANSI)	Paradox 'intl'
Paradox ESP 437	SPANISH	DOS CODE PAGE 437	Paradox ESP 437
Paradox ISL 861	iceland	DOS CODE PAGE 861	Paradox ISL 861
Pdcox ANSI INTL850	ANSII850	ISO8859.1 (ANSI)	Paradox 'intl' 850
Pdcox ANSI NORDAN4	ANSINOR4	ISO8859.1 (ANSI)	Paradox 'nordan40'
Pdcox ANSI SWEDFIN	ANSISWFN	ISO8859.1 (ANSI)	Paradox 'swedfin'
Pdcox ESP ANSI	ANSISPAN	ISO8859.1 (ANSI)	Paradox ESP437
SQL Links ROMAN8	BLROM800	ROMAN8	Binary

Sybase SQL Dic437	SYDC437	DOS CODE PAGE 437	Sybase dict. with case-sensitivity
Sybase SQL Dic850	SYDC850	DOS CODE PAGE850	Sybase dict. with case-sensitivity

---

{button ,AL(`connectingtosybase`)} [Connecting to Sybase topics](#)

## Sybase data type translations

Certain database operations cause SQL Links to convert data from Paradox or dBASE format to Sybase format. For example, a BDE application that copies or appends local data to a Sybase table causes SQL Links to convert the local data to Sybase format before performing the copy or append operation.

Other database operations cause a conversion in the opposite direction, from Sybase format to Paradox or dBASE format. For example, suppose you run a local query against one or more remote tables. During the query, SQL Links converts any data originating in an SQL database to Paradox or dBASE format (depending on the type of answer required) before placing the data in the local answer table.

The following topics contain lists of Sybase, Paradox, and dBASE data types and show how SQL Links translates between these data types:

- [From Sybase data types](#)
- [From Paradox data types](#)
- [From dBASE data types](#)
- [From Paradox physical types](#)
- [From dBASE physical types](#)
- [From Sybase physical types](#)

---

{button ,AL('connectingtosybase')} [Connecting to Sybase topics](#)

## From Sybase data types (to Paradox, dBASE)

<b>FROM: Sybase</b>	<b>TO: Paradox</b>	<b>TO: dBASE</b>
Char(n)	Alphanumeric(n)	Character(n)
Binary(n)	Binary	Memo
Bit	Alphanumeric(1)	Bool
DateTime	DateTime	Date
Float	Number	Float {20.4}
Float4	Number	Float {20.4}
Money4	Money	Float {20.4}
DateTime4	DateTime	Date
Image	Binary	Memo
Int	Number	Number {11.0}
Money	Money	Number {20.4}
SmallDateTime	DateTime	Date
SmallFloat	Number	Number
SmallInt	Short	Number {6.0}
SmallMoney	Money	Number {20.4}
Text	Memo	Memo
TimeStamp	Binary	Memo
TinyInt	Short	Number {6.0}
VarBinary(n)	Binary	Memo
VarChar(n)	Alphanumeric(n)	Character(n)

If you are using the SQLSSC32.DLL (for CT-Lib/System 10 and later), the following additional data types are available:

<b>FROM: Sybase</b>	<b>TO: Paradox</b>	<b>TO: dBASE</b>
Numeric	Number	Float {20.4}
Decimal (8,5)	Number	Float {20.4}
Double Precision	Number	Float {20.4}

---

{button ,AL(`sybasetranslations`)} Sybase data translations

## From Paradox data types (to Sybase, dBASE)

<b>FROM: Paradox</b>	<b>TO: Sybase</b>	<b>TO: dBASE</b>
Alphanumeric(n)	varchar(n)	Character(n)
Number	float	Float {20.4}
Money	money	Float {20.4}
Date	datetime	Date
Short	smallint	Number {6.0}
Memo	text	Memo
Formatted memo	image	Memo
Binary	image	Memo
Graphic	image	Memo
OLE	image	Memo
Long	Int	Number {11.0}
Time	Character {>8}	Character {>8}
DateTime	DateTime	Character {>8}
Bool	Bit	Bool
AutoInc	Int	Number {11.0}
Bytes	Image	Bytes
BCD	N/A	N/A

---

{button ,AL(`sybasetranslations')} [Sybase data translations](#)

## From dBASE data types (to Sybase, Paradox)

<b>FROM: dBASE</b>	<b>TO: Sybase</b>	<b>TO: Paradox</b>
Character(n)	varchar(n)	Alphanumeric(n)
Number	int, float	Number
Float number1	int, float	Number
Date	datetime	Date
Bool	bit	Bool
Lock	character {24.0}	Alphanumeric {24.0}
Bytes	image	Bytes
Memo	text	Memo

---

{button ,AL(`sybasetranslations`)} Sybase data translations

## From Paradox physical types (to BDE, dBASE)

<b>Paradox physical</b>	<b>BDE logical</b>	<b>dBASE physical</b>
fldPDXCHAR	fldZSTRING	fldDBCHAR
fldPDXNUM	fldFLOAT	fldDBFLOAT {20.4}
fldPDXMONEY	fldFLOAT/fldstMONEY	fldDBFLOAT {20.4}
fldPDXDATE	fldDATE	fldDATE
fldPDXSHORT	fldINT16	fldDBNUM {6.0}
fldPDXMEMO	fldBLOB/fldstMEMO	fldDBMEMO
fldPDXBINARYBLOB	fldBLOB/fldstBINARY	fldDBMEMO
fldPDXFMTMEMO	fldBLOB/fldstFMTMEMO	fldDBMEMO
fldPDXOLEBLOB	fldBLOB/fldstOLEOBJ	fldDBMEMO
fldPDXGRAPHIC	fldBLOB/fldstGRAPHIC	fldDBMEMO
fldPDXBLOB	fldPDXMEMO	fldDBMEMO
fldPDXLONG	fldINT32	fldDBNUM {11.0}
fldPDXTIME	fldTIME	fldDBCHAR {>8}
fldPDXDATETIME	fldTIMESTAMP	fldDBCHAR {30}
fldPDXBOOL	fldBOOL	fldDBBOOL
fldPDXAUTOINC	fldINT32	fldDBNUM {11.0}
fldPDXBYTES	fldBYTES	fldDBBYTES
fldPDXBCD	fldBCD	fldDBCHAR

---

{button ,AL('sybasetranslations')} Sybase data translations

## From dBASE physical types (to BDE, Paradox)

<b>dBASE physical</b>	<b>BDE logical</b>	<b>Paradox physical</b>
fldDBCHAR	fldZSTRING	fldPDXCHAR
fldDBNUM	if( iUnits2=0 && iUnits1<5 )	fldINT16 else fldFLOAT fldPDXSHORT fldPDXNUM
fldDBMEMO	fldBLOB	fldPDXMEMO
fldDBBOOL	fldBOOL	fldPDXBOOL
fldDBDATE	fldDATE	fldPDXDATE
fldDBFLOAT	fldFLOAT	fldPDXNUM
fldDBLOCK	fldLOCKINFO	fldPDXCHAR {24}
fldDBBINARY	fldBLOB/fldstTYPEDBINARY	fldPDXBINARYBLOB
fldDBOLEBLOB	fldBLOB/fldstDBSOLEOBJ	fldPDXOLEBLOB

---

{button ,AL(`sybasetranslations`)} Sybase data translations

## From Sybase physical types (to BDE, Paradox, dBASE)

From Sybase physical type	To BDE logical type	To Paradox physical type	To dBASE physical type
fldSYBBINARY	fldBYTES	fldPDXBYTES	fldDBMEMO
fldSYBBIT	fldBOOL	fldPDXBOOL	fldDBBOOL
fldSYBCHAR	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR
fldSYBDATETIME	fldTIMESTAMP	fldPDXDATETIME	fldDBDATE
fldSYBDATETIME4	fldTIMESTAMP	fldPDXDATETIME	fldDBDBDATE
fldSYBFLOAT	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldSYBFLOAT4	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldSYBIMAGE	fldBLOB/fldstBINARY	fldPDXBINARYBLOB	fldDBMEMO
fldSYBINT	fldINT32	fldPDXLONG	fldDBNUM {11.0}
fldSYBMONEY	fldFLOAT/fldstMONEY	fldPDXMONEY	fldDBNUM {20.4}
fldSYBMONEY4	fldFLOAT/fldstMONEY	fldPDXMONEY	fldDBNUM {20.4}
fldSYBSMALLINT	fldINT16	fldPDXSHORT	fldDBNUM {6.0}
fldSYBTEXT	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO
fldSYBTIMESTAMP	fldVARBYTES	fldPDXBINARYBLOB	fldDBMEMO
fldSYBTINYINT	fldINT16	fldPDXSHORT	fldDBNUM {6.0}
fldSYBVARBINARY	fldVARBYTES	fldPDXBINARYBLOB	fldDBMEMO
fldSYBVARCHAR	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR

If you are using Sybase System 10, the following additional physical types are available:

From Sybase physical type	To BDE logical type	To Paradox physical type	To dBASE physical type
fldSYBDECIMAL	fldFLOAT	fldPDXNUM	fldDBFLOAT(20,4)
fldSYBNUMERIC	fldFLOAT	fldPDXNUM	fldDBFLOAT(20,4)

---

{button ,AL(`sybasetranslations`)} [Sybase data translations](#)

## Sybase field-naming rules

Here is a list of field-naming rules for Paradox, dBASE, and CT-LIB.

<b>Naming rule</b>	<b>Paradox</b>	<b>dBASE</b>	<b>Sybase</b>
Max length (chars)	25	31	30
Valid characters	All	All alphanumeric except punctuation marks, blank spaces, and other special characters.	All except spaces and hyphen.
Must begin with . . .	Any valid character except space	A letter	A letter

**Note:** You may not use Sybase reserved words for remote table and column names.

---

{button ,AL(`connectingtosybase`)} [Connecting to Sybase topics](#)

{button ,AL(`sybasetranslations`)} [Sybase data translations](#)

## Connecting to Microsoft SQL Server

This section contains topics about using Borland SQL Links that are unique to Microsoft SQL Server. These settings are applicable only if you have purchased and installed the Borland SQL Links Driver for Microsoft SQL Server.

### **NUMERIC and DECIMAL types**

BDE supports the Microsoft SQL Driver 6.0 NUMERIC and DECIMAL data types. These types are translated to logical fldFLOAT, but they are retrieved from the server in the native NUMERIC format so that a user is guaranteed no data loss when working with the physical data (xltNONE).

- [Microsoft SQL Server requirements](#)
- [Microsoft SQL Server installation changes](#)
- [Working with Microsoft SQL servers](#)
- [Special SQL Links driver settings for Microsoft SQL Server](#)
- [Troubleshooting Microsoft SQL Server connection problems](#)
- [Borland language drivers for Microsoft SQL Server](#)
- [Microsoft SQL Server data type translations](#)
- [Microsoft SQL Server field-naming rules](#)

## Microsoft SQL Server requirements

Here is a list of software that should already be installed and running at the Microsoft SQL Server before you install the Borland SQL Links driver for Microsoft SQL Server.

<b>Server requirements</b>	<b>Description</b>
Database server software	Version 4.x and 6.x
Network protocol software	Supporting SPX/IPX, TCP/IP, or Named Pipes protocol (Microsoft LAN Manager, 3Com 3+Open, or Novell NetWare Requestor for OS/2)

For information on network protocol software and network access rights, see your system administrator.

Here are the requirements for the client workstation, including a list of software that should already be installed and running at the client workstation.

<b>Client requirements</b>	<b>Description</b>
BDE application(s)	Supported BDE application, installed as required by the product documentation.
Requirements	1.5 MB of free disk space. Hardware and operating system that meets the requirements of your BDE application.
Access rights	(For applications installed on the network server only.) If your BDE application is installed on the shared disk of a network file server, make sure your network user account has Read and Write access rights to the application's BDE files (including BDEADMIN.EXE and the IDAPI.CFG). This directory is modified during SQL Links installation.
Network protocol software	Network protocol software compatible with both the server network protocol and the client workstation client database communication driver.

---

{button ,AL('connectingtoms')} [Connecting to Microsoft SQL Server](#)

## Microsoft SQL Server installation changes

When you install the Borland Microsoft SQL Server SQL Links driver (called MSSQL in the BDE Administrator), the following changes take place in your workstation system:

<b>Item added</b>	<b>Description</b>
SQLMSS32.DLL	Dynamic Link Library comprising the Microsoft SQL driver and its supporting files.
Driver type	Added to BDE Administrator Configuration page to enable basic configuration of Borland Microsoft SQL Server SQL Links driver.

---

{button ,AL(`connectingtoms`)} Connecting to Microsoft SQL Server

## Working with Microsoft SQL servers

This section provides information about Microsoft SQL Server and its implementation of SQL. The topics discussed in this section cover aspects of Microsoft SQL Server that differ from other SQL database products.

Here is a list of general items that you might find helpful in working with Microsoft SQL Server:

<b>Item</b>	<b>Description</b>
Product name	Microsoft SQL Server
SQL dialect	Microsoft TRANSACT-SQL
Dynamic Link Library (DLL) name	SQLMSS32.DLL
Case-sensitive for data?	As installed
Case-sensitive for objects (such as tables, columns, and indexes)?	As installed
Does the server require an explicit request to begin a transaction for multi-statement transaction processing?	Yes
Does the server require that you explicitly start a transaction for multi-statement transaction processing in passthrough SQL?	Yes
Implicit row IDs	No
Blob handles	No
Maximum size of single BLOB read (if BLOB handles are not supported)	32K

---

{button ,AL('connectingtoms')} [Connecting to Microsoft SQL Server](#)

## Special SQL Links driver settings for Microsoft SQL Server

The following topics describe driver configuration parameters that are unique to Microsoft SQL Server:

### APPLICATION NAME

Specifies an application name used in the sysprocesses table of the master database to help the server identify your process.

### CONNECT TIMEOUT

Specifies the amount of time the workstation will retry when attempting to attach to the SQL server. The default is 60 seconds.

### HOST NAME

Specifies a workstation name used in the sysprocesses table of the master database to help the server identify your process. Also appears when sp\_who is executed on the server.

### NATIONAL LANG NAME

Specifies the language to use when displaying error messages. If blank, the default SQL server language is used. Only applies to servers with language support installed.

### TDS PACKET SIZE

Specifies the size of tabular data stream (TDS) packets exchanged by the client and server. TDS PACKET SIZE can be a value from 0 to 65535. Larger packet sizes can improve performance by reducing the number of packet requests, especially when working with BLOBs. A packet size between 4096 and 8192 is recommended for optimal performance.

To determine the TDS PACKET SIZE settings supported by your server, send the SQL command sp\_configure to your Sybase or MS SQL server, then note the settings returned for MAX NETWORK PACKET SIZE and ADDITIONAL NETMEM. If TDS PACKET SIZE is set to a higher value than the maximum network packet size, or ADDITIONAL NETMEM is not set, the following errors can occur:

Error : unknown user name or password

Server error

4002 Login failed

20014 Login incorrect

TDS 5 or later is required to modify the packet size. See your System Administrator's Guide for more information.

### Default:

4096

### TIMEOUT

Specifies the maximum amount of time that the workstation waits for results to return from the server. The default is 500 seconds.

You may want to change the TIMEOUT value to minimize conflicts between operations. For best performance, determine how much time a complex query would take to complete successfully on your network, then set TIMEOUT to a slightly larger number than that. For example, if you often run complex queries that can take up to 120 seconds to complete, be sure to set the TIMEOUT value to more than 120 seconds.

### DATABASE NAME

Name of the target SQL database.

### BLOB EDIT LOGGING

Enables or disables the logging of any edits to blob (Binary Large Object) fields. Possible values are TRUE (the default) or FALSE. When set to FALSE, this option helps minimize blob space requirements

and increase performance.

**Note:** If you set blob EDIT LOGGING to FALSE, you must also set BULKCOPY to ON at the server. For more information, see your SQL Server documentation.

**DATE MODE**

The format in which the driver sends dates to the SQL server. Valid settings are 0 (MDY), 1 (DMY), and 2 (YMD).

**MAX QUERY TIME**

Specifies the maximum amount of time that SQL Links will wait for query execution to complete before canceling the operation. The default is 3,600 seconds.

---

{button ,AL(`connectingtoms`)} Connecting to Microsoft SQL Server

## Troubleshooting Microsoft SQL Server connection problems

If you have problems establishing a Microsoft SQL Server connection with SQL Links, Check whether your BDE application alias is set up properly.

If you can connect directly from your workstation but not from within your BDE application, there is probably a problem with your BDEADMIN.EXE alias setup. Run the BDE Administrator and examine the alias.

For more information on your vendor-supplied diagnostic tools, see your Microsoft SQL Server documentation.

---

{button ,AL('connectingtoms')} Connecting to Microsoft SQL Server

## Borland language drivers for Microsoft SQL Server

The following table lists language drivers available for use with SQL servers, their corresponding character sets, and Borland collation sequences. The language driver you choose must use the same collation sequence as your server, and the same character set as the one your server uses to pass data to your BDE application.

Long name	Short name	Character set	Collation sequence
Borland ENU Latin-1	BLLT1US0	ISO8859.1(ANSI)	Binary
dBASE FRA cp437	DB437FR0	DOS CODE PAGE 437	dBASE French
dBASE FIN cp437	DB437FI0	DOS CODE PAGE 437	dBASE Finnish
dBASE ENU cp437	DB437US0	DOS CODE PAGE 437	dBASE English/US
dBASE NOR cp865	DB865NO0	DOS CODE PAGE 865	dBASE Norwegian
dBASE SVE cp437	DB437SV0	DOS CODE PAGE 437	dBASE Swedish
dBASE SVE cp850	DB850SV1	DOS CODE PAGE 850	dBASE Swedish850
dBASE ESP cp437	DB437ES1	DOS CODE PAGE 437	dBASE Spanish
dBASE NLD cp437	DB437NL0	DOS CODE PAGE 437	dBASE Dutch
dBASE ESP cp850	DB850ES1	DOS CODE PAGE 850	dBASE Spanish850
dBASE ENG cp437	DB437UK0	DOS CODE PAGE 437	dBASE English/UK
dBASE ENU cp850	DB850US0	DOS CODE PAGE 850	dBASE English/US
dBASE FRC cp863	DB863CF1	DOS CODE PAGE 863	dBASE French Canadian
dBASE ENG cp850	DB850UK0	DOS CODE PAGE 850	dBASE English850/UK
dBASE ITA cp850	DB850IT1	DOS CODE PAGE 850	dBASE Italian850
dBASE DEU cp850	BD850DE0	DOS CODE PAGE 850	dBASE German850
dBASE FRA cp850	DB850FR0	DOS CODE PAGE 850	dBASE French850
dBASE ITA cp437	DB437IT0	DOS CODE PAGE 437	dBASE Italian
dBASE NLD cp850	DB850NL0	DOS CODE PAGE 850	dBASE Dutch
dBASE FRC cp850	DB850CF0	DOS CODE PAGE 850	dBASE French Canadian850
dBASE DAN cp865	DB865DA0	DOS CODE PAGE 865	dBASE Danish
dBASE DEU cp437	DB437DE0	DOS CODE PAGE 437	dBASE German
DB2 SQL ANSI	db2andeu	1252 (ANSI)	Dictionary
Paradox 'ascii'	ascii	DOS CODE PAGE 437	Binary
Paradox 'intl'	intl	DOS CODE PAGE 437	Paradox 'intl'
Paradox 'intl' 850	intl850	DOS CODE PAGE 850	Paradox 'intl' 850
Paradox 'nordan'	nordan	DOS CODE PAGE 865	Paradox 'nordan'
Paradox 'nordan40'	nordan40	DOS CODE PAGE 865	Paradox 'nordan40'
Paradox 'swedfin'	swedfin	DOS CODE PAGE 437	Paradox 'swedfin'
Paradox ANSI INTL	ANSIINTL	ISO8859.1 (ANSI)	Paradox 'intl'
Paradox ESP 437	SPANISH	DOS CODE PAGE 437	Paradox ESP 437
Paradox ISL 861	iceland	DOS CODE PAGE 861	Paradox ISL 861
Pdcox ANSI INTL850	ANSII850	ISO8859.1 (ANSI)	Paradox 'intl' 850
Pdcox ANSI NORDAN4	ANSINOR4	ISO8859.1 (ANSI)	Paradox 'nordan40'
Pdcox ANSI SWEDFIN	ANSISWFN	ISO8859.1 (ANSI)	Paradox 'swedfin'
Pdcox ESP ANSI	ANSISPAN	ISO8859.1 (ANSI)	Paradox ESP437
SQL Links ROMAN8	BLROM800	ROMAN8	Binary
Sybase SQL Dic437	SYDC437	DOS CODE PAGE 437	Sybase dict. with case-

Sybase SQL Dic850

SYDC850

DOS CODE PAGE850

sensitivity

Sybase dict. with case-  
sensitivity

---

{button ,AL(`connectingtoms`)} Connecting to Microsoft SQL Server

## Microsoft SQL Server data type translations

Certain database operations cause SQL Links to convert data from Paradox or dBASE format to SQL Server format. For example, a BDE application that copies or appends local data to an SQL Server table causes SQL Links to convert the local data to Microsoft SQL Server format before performing the copy or append operation.

Other database operations cause a conversion in the opposite direction, from SQL Server format to Paradox or dBASE format. For example, suppose you run a local query against one or more remote tables. During the query, SQL Links converts any data originating in an SQL database to Paradox or dBASE format (depending on the type of answer required) before placing the data in the local answer table.

The following topics contain lists of SQL Server, Paradox, and dBASE data types and show how SQL Links translates between these data types:

- [From Microsoft SQL server data types](#)
- [From Paradox data types](#)
- [From dBASE data types](#)
- [From Paradox physical types](#)
- [From dBASE physical types](#)
- [From Microsoft SQL Server physical types](#)

---

{button ,AL('connectingtoms')} [Connecting to Microsoft SQL Server](#)

## From Microsoft SQL Server data types (to Paradox, dBASE)

<b>FROM: SQL Server</b>	<b>TO: Paradox</b>	<b>TO: dBASE</b>
Char(n)	Alphanumeric(n)	Character(n)
Binary(n)	Binary	Memo
Bit	Alphanumeric(1)	Bool
DateTime	DateTime	Date
Float	Number	Float {20.4}
Float4	Number	Float {20.4}
Money4	Money	Float {20.4}
DateTime4	DateTime	Date
Image	Binary	Memo
Int	Number	Number {11.0}
Money	Money	Number {20.4}
SmallDateTime	DateTime	Date
SmallFloat	Number	Number
SmallInt	Short	Number {6.0}
SmallMoney	Money	Number {20.4}
Text	Memo	Memo
TimeStamp	Binary	Memo
TinyInt	Short	Number {6.0}
VarBinary(n)	Binary	Memo
VarChar(n)	Alphanumeric(n)	Character(n)

---

{button ,AL(`mstranslations`)} Microsoft SQL Server data translations

## From Paradox data types (to SQL Server, dBASE)

<b>FROM: Paradox</b>	<b>TO: SQL Server</b>	<b>TO: dBASE</b>
Alphanumeric(n)	varchar(n)	Character(n)
Number	float	Float {20.4}
Money	money	Float {20.4}
Date	datetime	Date
Short	smallint	Number {6.0}
Memo	text	Memo
Formatted memo	image	Memo
Binary	image	Memo
Graphic	image	Memo
OLE	image	Memo
Long	Int	Number {11.0}
Time	Character {>8}	Character {>8}
DateTime	DateTime	Character {>8}
Bool	Bit	Bool
AutoInc	Int	Number {11.0}
Bytes	Image	Bytes
BCD	N/A	N/A

---

{button ,AL('mstranslations')} Microsoft SQL Server data translations

## From dBASE data types (to SQL Server, Paradox)

<b>FROM: dBASE</b>	<b>TO: SQL Server</b>	<b>TO: Paradox</b>
Character(n)	varchar(n)	Alphanumeric(n)
Number	int, float	Number
Float number1	int, float	Number
Date	datetime	Date
Bool	bit	Bool
Lock	character {24.0}	Alphanumeric {24.0}
Bytes	image	Bytes
Memo	text	Memo

---

{button ,AL(`mstranslations')} [Microsoft SQL Server data translations](#)

## From Paradox physical types (to BDE, dBASE)

<b>Paradox physical</b>	<b>BDE logical</b>	<b>dBASE physical</b>
fldPDXCHAR	fldZSTRING	fldDBCHAR
fldPDXNUM	fldFLOAT	fldDBFLOAT {20.4}
fldPDXMONEY	fldFLOAT/fldstMONEY	fldDBFLOAT {20.4}
fldPDXDATE	fldDATE	fldDATE
fldPDXSHORT	fldINT16	fldDBNUM {6.0}
fldPDXMEMO	fldBLOB/fldstMEMO	fldDBMEMO
fldPDXBINARYBLOB	fldBLOB/fldstBINARY	fldDBMEMO
fldPDXFMTMEMO	fldBLOB/fldstFMTMEMO	fldDBMEMO
fldPDXOLEBLOB	fldBLOB/fldstOLEOBJ	fldDBMEMO
fldPDXGRAPHIC	fldBLOB/fldstGRAPHIC	fldDBMEMO
fldPDXBLOB	fldPDXMEMO	fldDBMEMO
fldPDXLONG	fldINT32	fldDBNUM {11.0}
fldPDXTIME	fldTIME	fldDBCHAR {>8}
fldPDXDATETIME	fldTIMESTAMP	fldDBCHAR {30}
fldPDXBOOL	fldBOOL	fldDBBOOL
fldPDXAUTOINC	fldINT32	fldDBNUM {11.0}
fldPDXBYTES	fldBYTES	fldDBBYTES
fldPDXBCD	fldBCD	fldDBCHAR

---

{button ,AL('mstranslations')} [Microsoft SQL Server data translations](#)

## From dBASE physical types (to BDE, Paradox)

<b>dBASE physical</b>	<b>BDE logical</b>	<b>Paradox physical</b>
fldDBCHAR	fldZSTRING	fldPDXCHAR
fldDBNUM	if( iUnits2=0 && iUnits1<5 )	fldINT16 else fldFLOAT fldPDXSHORT fldPDXNUM
fldDBMEMO	fldBLOB	fldPDXMEMO
fldDBBOOL	fldBOOL	fldPDXBOOL
fldDBDATE	fldDATE	fldPDXDATE
fldDBFLOAT	fldFLOAT	fldPDXNUM
fldDBLOCK	fldLOCKINFO	fldPDXCHAR {24}
fldDBBINARY	fldBLOB/fldstTYPEDBINARY	fldPDXBINARYBLOB
fldDBOLEBLOB	fldBLOB/fldstDBSOLEOBJ	fldPDXOLEBLOB

---

{button ,AL(`mstranslations`)} Microsoft SQL Server data translations

## From Microsoft SQL Server physical types (to BDE, Paradox, dBASE)

From MS SQL physical type	To BDE logical type	To Paradox physical type	To dBASE physical type
fldMSSBINARY	fldBYTES	fldPDXBYTES	fldDBMEMO
fldMSSBIT	fldBOOL	fldPDXBOOL	fldDBBOOL
fldMSSCHAR	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR
fldMSSDATETIME	fldTIMESTAMP	fldPDXDATETIME	fldDBDATE
fldMSSDATETIME4	fldTIMESTAMP	fldPDXDATETIME	fldDBDBDATE
fldMSSDECIMAL	fldFLOAT	fldPDXNUM	fldDBFLOAT(20,4)
fldMSSFLOAT	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldMSSFLOAT4	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldMSSIMAGE	fldBLOB/fldstBINARY	fldPDXBINARYBLOB	fldDBMEMO
fldMSSINT	fldINT32	fldPDXLONG	fldDBNUM {11.0}
fldMSSMONEY	fldFLOAT/fldstMONEY	fldPDXMONEY	fldDBNUM {20.4}
fldMSSMONEY4	fldFLOAT/fldstMONEY	fldPDXMONEY	fldDBNUM {20.4}
fldMSSNUMERIC	fldFLOAT	fldPDXNUM	fldDBFLOAT(20,4)
fldMSSSMALLINT	fldINT16	fldPDXSHORT	fldDBNUM {6.0}
fldMSSTEXT	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO
fldMSSTIMESTAMP	fldVARBYTES	fldPDXBINARYBLOB	fldDBMEMO
fldMSSTINYINT	fldINT16	fldPDXSHORT	fldDBNUM {6.0}
fldMSSVARBINARY	fldVARBYTES	fldPDXBINARYBLOB	fldDBMEMO
fldMSSVARCHAR	fldZSTRING/fldstFIXED	fldPDXCHAR	fldDBCHAR

---

{button ,AL('mstranslations')} [Microsoft SQL Server data translations](#)

## Microsoft SQL Server field-naming rules

Here is a list of field-naming rules for Paradox, dBASE, and Microsoft SQL Server.

Naming rule	Paradox	dBASE	SQL Server
Max length (chars)	25	31	30
Valid characters	All	All alphanumeric except punctuation marks, blank spaces, and other special characters.	All except spaces and hyphen.
Must begin with . . .	Any valid character except space	A letter	A letter

**Note:** You may not use Microsoft SQL Server reserved words for remote table and column names. See the *Microsoft SQL Server Programmer's Reference* for a list of reserved words.

---

{button ,AL(`mstranslations`)} [Microsoft SQL Server data translations](#)

{button ,AL(`connectingtoms`)} [Connecting to Microsoft SQL Server](#)

## InterBase driver configuration parameters

Click on the following parameter names for pop-up help configuring the InterBase driver with the BDE Administrator.

- VERSION
- TYPE
- DLL
- DLL32
- DRIVER FLAGS
- TRACE MODE
- SERVER NAME
- USER NAME
- OPEN MODE
- SCHEMA CACHE SIZE
- LANGDRIVER
- SQLQRYMODE
- SQLPASSTHRU MODE
- SCHEMA CACHE TIME
- MAX ROWS
- BATCH COUNT
- ENABLE SCHEMA CACHE
- SCHEMA CACHE DIR
- ENABLE BCD
- BLOBS TO CACHE
- BLOB SIZE
- ROLE NAME
- WAIT ON LOCKS
- COMMIT RETAIN

---

{button ,AL('connectingtointerbase')} Connecting to InterBase topics

## Informix driver configuration parameters

Click on the following parameter names for pop-up help configuring the Informix driver with the BDE Administrator.

- [VERSION](#)
- [TYPE](#)
- [DLL](#)
- [DLL32](#)
- [DRIVER FLAGS](#)
- [TRACE MODE](#)
- [SERVER NAME](#)
- [DATABASE NAME](#)
- [USER NAME](#)
- [OPEN MODE](#)
- [SCHEMA CACHE SIZE](#)
- [LANGDRIVER](#)
- [SQLQRYMODE](#)
- [SQLPASSTHRU MODE](#)
- [LOCK MODE](#)
- [DATE MODE](#)
- [DATE SEPARATOR](#)
- [SCHEMA CACHE TIME](#)
- [MAX ROWS](#)
- [BATCH COUNT](#)
- [ENABLE SCHEMA CACHE](#)
- [SCHEMA CACHE DIR](#)
- [ENABLE BCD](#)
- [LIST SYNONYMS](#)
- [COLLCHAR](#)
- [DBNLS](#)
- [BLOBS TO CACHE](#)
- [BLOB SIZE](#)

---

{button ,AL('connectingtoinformix')}} [Connecting to Informix topics](#)

## DB2 driver configuration parameters

Click on the following parameter names for pop-up help configuring the DB2 driver with the BDE Administrator.

- [VERSION](#)
- [TYPE](#)
- [DLL](#)
- [DLL32](#)
- [DRIVER](#)
- [DRIVER FLAGS](#)
- [TRACE MODE](#)
- [USER NAME](#)
- [DB2 DSN](#)
- [OPEN MODE](#)
- [SCHEMA CACHE SIZE](#)
- [LANGDRIVER](#)
- [SQLQRYMODE](#)
- [SQLPASSTHRU MODE](#)
- [SCHEMA CACHE TIME](#)
- [MAX ROWS](#)
- [BATCH COUNT](#)
- [ENABLE SCHEMA CACHE](#)
- [SCHEMA CACHE DIR](#)
- [ENABLE BCD](#)
- [ROWSET SIZE](#)
- [BLOBS TO CACHE](#)
- [BLOB SIZE](#)

---

{button ,AL('connectingtoDB2')} [Connecting to DB2 topics](#)

## ORACLE driver configuration parameters

Click on the following parameter names for pop-up help configuring the ORACLE driver with the BDE Administrator.

- [VERSION](#)
- [TYPE](#)
- [DLL](#)
- [DLL32](#)
- [VENDOR INIT](#)
- [DRIVER FLAGS](#)
- [TRACE MODE](#)
- [SERVER NAME](#)
- [USER NAME](#)
- [NET PROTOCOL](#)
- [OBJECT MODE](#)
- [OPEN MODE](#)
- [SCHEMA CACHE SIZE](#)
- [LANGDRIVER](#)
- [SQLQRYMODE](#)
- [SQLPASSTHRU MODE](#)
- [SCHEMA CACHE TIME](#)
- [MAX ROWS](#)
- [BATCH COUNT](#)
- [ENABLE SCHEMA CACHE](#)
- [SCHEMA CACHE DIR](#)
- [ENABLE BCD](#)
- [ENABLE INTEGERS](#)
- [LIST SYNONYMS](#)
- [ROWSET SIZE](#)
- [BLOBS TO CACHE](#)
- [BLOB SIZE](#)

---

{button ,AL('connectingtooracle')} [Connecting to ORACLE topics](#)

**ROLE NAME**

InterBase allows users to login by specifying a role. ROLE NAME is a BDE configuration entry that allows BDE clients to pass the role name. ROLE NAME can also be passed as an optional parameter in Database components (such as USER NAME).

**WAIT ON LOCKS**

The default behavior of earlier versions of InterBase SQL Links was to use NOWAIT when resolving lock conflicts in order to return an error immediately in the case of a resource conflict. Setting either the BDE configuration entry WAIT ON LOCKS or the read/write database property dbWAITONLOCK to TRUE allows SQL Links to use WAIT on InterBase transactions.

**COMMIT RETAIN**

The read/write database property dbCOMMITRETAIN or the BDE configuration entry COMMIT RETAIN allows explicit transactions to use soft commit. This affects only explicit transactions. Existing driver flags are still valid for implicit transactions.

Parameters:

**TRUE** calls `isc_commit_retaining()`

**FALSE** calls `isc_commit_transaction()`

**ROWSET SIZE**

Specifies the number of rows to retrieve from the server in a single fetch, and the number of records to insert at a time when using DbiWriteBlock.

**Default:**

The default value is 20 (20 records per server fetch, 20 records inserted at a time).

**Vendor Init**

Enter the vendor DLL filename. For ORACLE 7, use ORA73.DLL or higher (unless you require MTS services, in which case you must choose MTXOCI.DLL). For ORACLE8, use OCI.DLL.

**OBJECT MODE**

OBJECT MODE should be set to TRUE when connecting to ORACLE8 and accessing object types such as ADT, VARRAY, REF, NESTED TABLE, etc. OBJECT MODE should be set to FALSE when using Oracle servers prior to ORACLE8.

## NET PROTOCOL

Network transport is used to communicate with the SQL server. This table describes NET PROTOCOL options.

<b>Value</b>	<b>Description</b>
3270	IBM 3270 protocol
APPC	IBM APPC LU 6.2 protocol
ASYNC	Asynchronous (dial-up) access protocol
DECNET	Digital Equipment Corporation DECnet protocol
NAMED PIPES	Named Pipes protocol, as used by OS/2
NETBIOS	NetBios protocol, as used by LAN Manager and other PC LANs
SPX/IPX	SPX/IPX protocol, as used by Novell NetWare
TCP/IP	Transport Control Protocol/Internet Protocol, as used by UNIX and VAX workstations
VINES	Banyan VINES protocol
TNS	Transparent Network Substrate, Oracle high-level communications protocol

### **LIST SYNONYMS (Oracle)**

Synonyms are alternate names for other objects, such as tables or views. The special SQL Links Driver setting for ORACLE, called LIST SYNONYMS, determines whether or not to include synonyms in the schema table returned from BDE API functions DbiOpenTableList and DbiOpenFileList, as shown in the following table.

<b>Value</b>	<b>Meaning</b>
NONE	Do not include any synonyms (default)
PRIVATE	Only include private synonyms
ALL	Include both private and public synonyms

Synonyms are supported by a field in the BDE TBLBaseDesc structure called *bSynonym*. The field *bSynonym* is a BOOL16, which is set to TRUE if the object is a synonym.

### **Cross database and cross server table access**

You can access Oracle synonyms by using DbiOpenTable. You can access tables on different databases or servers in the same way. For example, you can open "SCOTT"."CUSTOMER"@ "DBLINK" on Oracle and pubs.dbo.authors on Sybase.

### **Public synonyms**

Oracle has PUBLIC synonyms which will show up in the table list when the value of LIST SYNONYMS = ALL. However, to open a PUBLIC synonym, the user must also have SELECT privileges on the base object of the synonym. If the user does not have SELECT privileges and tries to open the PUBLIC SYNONYM, Oracle returns the error "Table or view does not exist".

Oracle has PUBLIC synonyms to a set of dynamic performance tables. Even though these are PUBLIC synonyms, they are accessible only to the DBA user SYS, by default (other users can be granted privileges). These synonym names are in the format, V\$... (that is, V\$DATABASE, V\$ACCESS, and so on).

**LIST SYNONYMS (Informix)**

Synonyms are alternate names for other objects, such as tables or views. The special SQL Links Driver setting for Informix, called LIST SYNONYMS, determines whether or not to include synonyms in the schema table returned from BDE API functions DbiOpenTableList and DbiOpenFileList, as shown in the following table.

<b>Value</b>	<b>Meaning</b>
NONE	Do not include any synonyms (default)
PRIVATE	Only include private synonyms
ALL	Include both private and public synonyms

## Sybase driver configuration parameters

Click on the following parameter names for pop-up help configuring the Sybase driver with the BDE Administrator.

- [VERSION](#)
- [TYPE](#)
- [DLL](#)
- [DLL32](#)
- [VENDOR INIT](#)
- [CONNECT TIMEOUT](#)
- [TIMEOUT](#)
- [DRIVER FLAGS](#)
- [TRACE MODE](#)
- [MAX DBPROCESSES](#)
- [DATABASE NAME](#)
- [SERVER NAME](#)
- [USER NAME](#)
- [OPEN MODE](#)
- [SCHEMA CACHE SIZE](#)
- [BLOB EDIT LOGGING](#)
- [LANGDRIVER](#)
- [SQLQRYMODE](#)
- [SQLPASSTHRU MODE](#)
- [DATE MODE](#)
- [SCHEMA CACHE TIME](#)
- [MAX QUERY TIME](#)
- [MAX ROWS](#)
- [BATCH COUNT](#)
- [ENABLE SCHEMA CACHE](#)
- [SCHEMA CACHE DIR](#)
- [HOST NAME](#)
- [APPLICATION NAME](#)
- [NATIONAL LANG NAME](#)
- [ENABLE BCD](#)
- [TDS PACKET SIZE](#)
- [BLOBS TO CACHE](#)
- [BLOB SIZE](#)
- [CS CURSOR ROWS](#)

**VENDOR INIT**  
(No longer applicable.)

**MAX DBPROCESSES**

The maximum number of concurrent open Sybase DBLIB client DBPROCESSes (connections) to the server.

The default setting for this parameter is 31. If additional DBPROCESSes are needed for your application, this setting can be changed to reflect the expected maximum.

**BLOB EDIT LOGGING**

Enables or disables the logging of any edits to blob (Binary Large Object) fields. Possible values are TRUE (the default) or FALSE. When set to FALSE, this option helps minimize blob space requirements and increase performance.

**Note:** If you set blob EDIT LOGGING to FALSE, you must also set BULKCOPY to ON at the server. For more information, see your SQL Server documentation.

**CONNECT TIMEOUT**

Specifies the amount of time the workstation will retry when attempting to attach to the SQL server. The default is 60 seconds.

**DATABASE NAME**

Name of the target SQL database.

**DATE MODE**

The format in which the driver sends dates to the SQL server.

Valid settings are 0 (MDY), 1 (DMY), and 2 (YMD).

**TIMEOUT**

Specifies the maximum amount of time that the workstation waits for results to return from the server.

Default: 300 seconds.

You may want to change the TIMEOUT value to minimize conflicts between operations. For best performance, determine how much time a complex query would take to complete successfully on your network, then set TIMEOUT to a slightly larger number than that. For example, if you often run complex queries that can take up to 120 seconds to complete, be sure to set the TIMEOUT value to more than 120 seconds.

**MAX QUERY TIME**

Specifies the maximum amount of time that SQL Links will wait for query execution to complete before canceling the operation. The default is 3,600 seconds.

**Note:** Applications using earlier versions of SQL Links for Sybase may generate an error message if a transaction isolation level other than Repeatable Read has been specified. In such cases, specify an isolation level of Read Committed when starting a transaction or use the BDE Administrator to set the Driver Flags parameter to 512.

Although the beginTrans (dBASE) or beginTransaction (Paradox) methods indicate that the isolation level is optional, when using SQL Links for Sybase, specify the Read Committed isolation level.

**CS CURSOR ROWS**

Specifies the number of rows that the server returns to Client-Library per internal fetch request. The default setting is 1. If CS CURSOR ROWS is set to 5, Client-Library makes an internal fetch request when an application calls fetch the first time, the sixth time, and so on.

In general, a higher CS CURSOR ROWS setting can benefit application performance when processing a read-only cursor. A higher CS CURSOR ROWS setting decreases the number of network round trips required to fetch rows. However, if CS CURSOR ROWS is set too high and Client-Library must buffer rows, the buffering overhead can outweigh the gains achieved by decreasing the number of round trips.

## Microsoft SQL Server driver configuration parameters

Click on the following parameter names for pop-up help configuring the Microsoft SQL Server driver with the BDE Administrator.

- VERSION
- TYPE
- DLL
- DLL32
- VENDOR INIT
- CONNECT TIMEOUT
- TIMEOUT
- DRIVER FLAGS
- TRACE MODE
- MAX DBPROCESSES
- DATABASE NAME
- SERVER NAME
- USER NAME
- OPEN MODE
- SCHEMA CACHE SIZE
- BLOB EDIT LOGGING
- LANGDRIVER
- SQLQRYMODE
- SQLPASSTHRU MODE
- DATE MODE
- SCHEMA CACHE TIME
- MAX QUERY TIME
- MAX ROWS
- BATCH COUNT
- ENABLE SCHEMA CACHE
- SCHEMA CACHE DIR
- HOST NAME
- APPLICATION NAME
- NATIONAL LANG NAME
- ENABLE BCD
- TDS PACKET SIZE
- BLOBS TO CACHE
- BLOB SIZE

**VENDOR INIT**  
(No longer applicable.)

**MAX DBPROCESSES**

The maximum number of concurrent open MSSQL DBLIB client DBPROCESSes (connections) to the server.

The default setting for this parameter is 31. If additional DBPROCESSes are needed for your application, this setting can be changed to reflect the expected maximum.

**CONNECT TIMEOUT**

Specifies the amount of time the workstation will retry when attempting to attach to the Microsoft SQL server.

Default: 60 seconds.

**TIMEOUT**

Specifies the maximum amount of time that the workstation waits for results to return from the server.

Default: 300 seconds.

You may want to change the TIMEOUT value to minimize conflicts between operations. For best performance, determine how much time a complex query would take to complete successfully on your network, then set TIMEOUT to a slightly larger number than that. For example, if you often run complex queries that can take up to 120 seconds to complete, be sure to set the TIMEOUT value to more than 120 seconds.

**DATABASE NAME**

Name of the target SQL database.

**BLOB EDIT LOGGING**

Enables or disables the logging of any edits to blob (Binary Large Object) fields.

Possible values are TRUE (the default) or FALSE.

When set to FALSE, this option helps minimize blob space requirements and increase performance.

**Note:** If you set blob EDIT LOGGING to FALSE, you must also set BULKCOPY to ON at the server. For more information, see your Microsoft SQL Server documentation.

**DATE MODE**

The format in which the driver sends dates to the Microsoft SQL server.

Valid settings are 0 (MDY), 1 (DMY), and 2 (YMD).

**MAX QUERY TIME**

Specifies the maximum amount of time that SQL Links will wait for query execution to complete before canceling the operation.

Default: 3,600 seconds.

## Connecting to DB2

The Borland SQL Links Driver for DB2 is a driver for DB2, IBM's next generation interface for its DATABASE 2 client/server product.

This section contains topics about using Borland SQL Links that are unique to the DB2 driver. This information is applicable only if you have installed the Borland SQL Links Driver for DB2.

- [DB2 requirements](#)
- [DB2 installation changes](#)
- [Working with DB2](#)
- [Creating a DB2 alias](#)
- [Special SQL Links driver settings for DB2](#)
- [Troubleshooting DB2 connection problems](#)
- [Borland language drivers for DB2](#)
- [DB2 data type translations](#)
- [DB2 field-naming rules](#)

## DB2 requirements

Here is a list of software that should already be installed and running at the DB2 server before you install the Borland SQL Links driver for DB2.

<b>Server requirements</b>	<b>Description</b>
Database server software	DB2 for NT, OS/2, IBM MVS, or AS/400.
Network protocol software	Supporting IPX/SPX, TCP/IP, or Named Pipes protocol (Microsoft LAN Manager, 3Com 3+Open, or Novell NetWare Requestor for OS/2)

For information on network protocol software and network access rights, see your system administrator. Here is a list of requirements for the client workstation.

<b>Client requirements</b>	<b>Description</b>
BDE application(s)	Supported BDE application, installed as required by the product documentation.
Requirements	1.5 MB of free disk space. Hardware and operating system that meets the requirements of your BDE application.
Access rights	(For applications installed on the network server only.) If your BDE application is installed on the shared disk of a network file server, make sure your network user account has Read and Write access rights to the application's BDE files (including BDEADMIN.EXE and the IDAPI.CFG). This directory is modified during SQL Links installation.
Network protocol software	Network protocol software compatible with both the server network protocol and the client workstation client database communication driver.
DB2 Client Application Enabler	DB2 Client Application Enabler version 2.1 must be installed. Perform the required binding by clicking the Client Setup icon. For details, see the IBM DB2 manual <i>Installing and Using DB2 Client for Windows</i> .

---

{button ,AL('connectingtodb2')} [Connecting to DB2 topics](#)

## DB2 installation changes

When you install the Borland DB2 SQL Links driver, the following changes take place in your workstation system:

<b>Item added</b>	<b>Description</b>
SQLDB232.DLL	The DB2 driver (Dynamic Link Library). (Or SQLDB2V5.DLL for DB2 V5 (UDB)).
DB2 driver type	Added to BDE Administrator Driver page to enable basic configuration of Borland DB2 SQL Links driver.
BDEREADME.TXT	Borland SQL Links for Windows README file.

---

{button ,AL('connectingodb2')} [Connecting to DB2 topics](#)

## Working with DB2

This section provides general information about DB2 and its implementation of SQL.

<b>Item</b>	<b>Description</b>
Product name	SQL Links driver for DB2
DLL name	SQLDB232.DLL (SQLDB2V5.DLL for DB/2 V5 (UDB))
SQL dialect	ANSI 92 standard
Case-sensitive for data?	Yes
Case-sensitive for objects?	Yes
Does the server require that you explicitly start a transaction for multi-statement transaction processing in passthrough SQL?	Yes
Implicit row IDs	No
Blob handles	Yes
Maximum size of single BLOB read (if BLOB handles are not supported)	64KB

---

[{button ,AL\('connectingtodb2'\)} Connecting to DB2 topics](#)

## Creating a DB2 alias

To create a DB2 alias, follow the steps in [Adding a new SQL alias](#).

---

{button ,AL('connectingodb2')} [Connecting to DB2 topics](#)

## Special SQL Links driver settings for DB2

The following topic describes driver configuration parameters unique to DB2. You set these parameters in the BDE Administrator.

### **DB2 DSN**

DB2 Data Source Name: the name of a connection to a DB2 database. This is a DB2 client alias for a database existing on the DB2 server. You create this alias by using the DB2 Client Setup utility.

Default: DB2\_SERVER

### **DRIVER**

The name of the DB2 driver.

Default: IBM DB2 DRIVER

---

{button ,AL('connectingtodb2')} Connecting to DB2 topics

## Troubleshooting DB2 connection problems

If you have problems establishing a DB2 connection with SQL Links, Check whether your BDE application alias is set up properly.

If you can connect directly from your workstation but not from within your BDE application, there is probably a problem with your BDEADMIN.EXE alias setup. Run the BDE Administrator and examine the alias.

For more information on your vendor-supplied diagnostic tools, see your DB2 documentation.

---

{button ,AL(`connectingtodb2`)} [Connecting to DB2 topics](#)

## Borland language drivers for DB2

The following table lists language drivers available for use with SQL servers, their corresponding character sets, and Borland collation sequences. The language driver you choose must use the same collation sequence as your server, and the same character set as the one your server uses to pass data to your BDE application.

Long name	Short name	Character set	Collation sequence
Borland ENU Latin-1	BLLT1US0	ISO8859.1(ANSI)	Binary
dBASE FRA cp437	DB437FR0	DOS CODE PAGE 437	dBASE French
dBASE FIN cp437	DB437FI0	DOS CODE PAGE 437	dBASE Finnish
dBASE ENU cp437	DB437US0	DOS CODE PAGE 437	dBASE English/US
dBASE NOR cp865	DB865NO0	DOS CODE PAGE 865	dBASE Norwegian
dBASE SVE cp437	DB437SV0	DOS CODE PAGE 437	dBASE Swedish
dBASE SVE cp850	DB850SV1	DOS CODE PAGE 850	dBASE Swedish850
dBASE ESP cp437	DB437ES1	DOS CODE PAGE 437	dBASE Spanish
dBASE NLD cp437	DB437NL0	DOS CODE PAGE 437	dBASE Dutch
dBASE ESP cp850	DB850ES1	DOS CODE PAGE 850	dBASE Spanish850
dBASE ENG cp437	DB437UK0	DOS CODE PAGE 437	dBASE English/UK
dBASE ENU cp850	DB850US0	DOS CODE PAGE 850	dBASE English/US
dBASE FRC cp863	DB863CF1	DOS CODE PAGE 863	dBASE French Canadian
dBASE ENG cp850	DB850UK0	DOS CODE PAGE 850	dBASE English850/UK
dBASE ITA cp850	DB850IT1	DOS CODE PAGE 850	dBASE Italian850
dBASE DEU cp850	BD850DE0	DOS CODE PAGE 850	dBASE German850
dBASE FRA cp850	DB850FR0	DOS CODE PAGE 850	dBASE French850
dBASE ITA cp437	DB437IT0	DOS CODE PAGE 437	dBASE Italian
dBASE NLD cp850	DB850NL0	DOS CODE PAGE 850	dBASE Dutch
dBASE FRC cp850	DB850CF0	DOS CODE PAGE 850	dBASE French Canadian850
dBASE DAN	DB865DA0	DOS CODE PAGE	dBASE Danish

cp865		865	
dBASE DEU cp437	DB437DE0	DOS CODE PAGE 437	dBASE German
DB2 SQL ANSI	db2andeu	1252 (ANSI)	Dictionary
Paradox 'ascii'	ascii	DOS CODE PAGE 437	Binary
Paradox 'intl'	intl	DOS CODE PAGE 437	Paradox 'intl'
Paradox 'intl' 850	intl850	DOS CODE PAGE 850	Paradox 'intl' 850
Paradox 'nordan'	nordan	DOS CODE PAGE 865	Paradox 'nordan'
Paradox 'nordan40'	nordan40	DOS CODE PAGE 865	Paradox 'nordan40'
Paradox 'swedfin'	swedfin	DOS CODE PAGE 437	Paradox 'swedfin'
Paradox ANSI INTL	ANSIINTL	ISO8859.1 (ANSI)	Paradox 'intl'
Paradox ESP 437	SPANISH	DOS CODE PAGE 437	Paradox ESP 437
Paradox ISL 861	iceland	DOS CODE PAGE 861	Paradox ISL 861
Pdox ANSI INTL850	ANSII850	ISO8859.1 (ANSI)	Paradox 'intl' 850
Pdox ANSI NORDAN4	ANSINOR4	ISO8859.1 (ANSI)	Paradox 'nordan40'
Pdox ANSI SWEDFIN	ANSISWFN	ISO8859.1 (ANSI)	Paradox 'swedfin'
Pdox ESP ANSI	ANSISPAN	ISO8859.1 (ANSI)	Paradox ESP437
SQL Links ROMAN8	BLROM800	ROMAN8	Binary
Sybase SQL Dic437	SYDC437	DOS CODE PAGE 437	Sybase dict. with case- sensitivity
Sybase SQL Dic850	SYDC850	DOS CODE PAGE850	Sybase dict. with case- sensitivity

---

{button ,AL('connectingtodb2')} Connecting to DB2 topics

## DB2 data type translations

Certain database operations cause SQL Links to convert data from Paradox or dBASE format to DB2 format. For example, a BDE application that copies or appends local data to a DB2 table causes SQL Links to convert the local data to DB2 format before performing the copy or append operation.

Other database operations cause a conversion in the opposite direction, from DB2 format to Paradox or dBASE format. For example, suppose you run a local query against one or more remote tables. During the query, SQL Links converts any data originating in an SQL database to Paradox or dBASE format (depending on the type of answer required) before placing the data in the local answer table.

The following topics contain lists of DB2, Paradox, and dBASE data types and show how SQL Links translates between them:

- [From DB2 data types](#)
- [From Paradox data types](#)
- [From dBASE data types](#)
- [From DB2 physical types](#)

---

{button ,AL(`connectingtodb2`)} [Connecting to DB2 topics](#)

## From DB2 data types (to Paradox, dBASE)

FROM: DB2	TO: Paradox	TO: dBASE
BLOB	Binary	Memo
Char(n)	Alphanumeric(n)	Character(n)
Char(n) for bit data	Bytes	Memo
CLOB	Memo	Memo
Date	Date	Date
Decimal	Number	Number
DBCLOB	NOT SUPPORTED	
Double	Number	Double
Float	Number	Number {20.4}
Graphic	Binary	Binary
Integer	Long	Long
Long VarChar	Memo	Memo
Long VarChar(n)		
Long VarGraphic		
for bit data	Binary	Binary
Numeric	Number	Number
SmallInt	Short	Number {6.0}
Time	Time	Character
TimeStamp	TimeStamp	Datetime
VarChar(n), n <=255	Alphanumeric(n)	Character(n)
VarChar(n), n >255	Memo	Memo
VarChar(n) for bit data	Binary	Binary
VarGraphic	Binary	Binary

**Note:** Although BDE supports NUMERIC and DECIMAL data types, inserting data for these types into a database on the DB2 server is not supported, pending a software update from IBM.

**Note:** The DB2 field types Graphic, VarGraphic, Long VarGraphic, and DBCLOB are not supported by the BDE. If encountered, they would either be interpreted as simple BLOB fields or an error occurs indicating an unsupported field type.

## From Paradox data types (to DB2, dBASE)

FROM: Paradox	TO: DB2	TO: dBASE
Alphanumeric(n)	VarChar(n)	Character(n)
AutoInc	Integer	Number {11.0}
BCD	Double	Number {20.4}
Binary	long VarChar(n) for bit data	Memo
Bool	Char(1)	Bool
Bytes	Char(n) for bit data	Memo
Date	Date	Date
DateTime	TimeStamp	Character {>8}
Formatted memo	BLOB	Memo
Graphic	BLOB	Binary
Long	Integer	Number {11.0}
Memo	CLOB	Memo
Money	Double	Number {20.4}
Number	Double	Number {20.4}
OLE	BLOB	OLE
Short	Small int	Number {6.0}
Time	Time	Character {>8}

**Note:** Although BDE supports NUMERIC and DECIMAL data types, inserting data for these types into a database on the DB2 server is not supported, pending a software update from IBM. Char(n) for bit data is binary. VarChar(n) for bit data is varbinary. long VarChar(n) for bit data is longvarbinary.

**Note:** The DB2 field types Graphic, VarGraphic, Long VarGraphic, and DBCLOB are not supported by the BDE. If encountered, they would either be interpreted as simple BLOB fields or an error occurs indicating an unsupported field type.

---

{button ,AL('db2translations')} DB2 data translations

## From dBASE data types (to DB2, Paradox)

FROM: dBASE	TO: DB2	TO: Paradox
Bool	Char(1)	Bool
Bytes	Char(n) for bit data	Bytes
Character(n)	VarChar(n)	Alphanumeric(n)
Date	Date	Date
Float	Double	Number
Lock	Char(24)	Alphanumeric {24.0}
Memo	CLOB	Memo
Number	Double	Number
OLE	BLOB	OLE
Binary	BLOB	Graphic

**Note:** Although BDE supports NUMERIC and DECIMAL data types, inserting data for these types into a database on the DB2 server is not supported, pending a software update from IBM. Bytes in the dBASE driver is for temporary tables only.

**Note:** The DB2 field types Graphic, VarGraphic, Long VarGraphic, and DBCLOB are not supported by the BDE. If encountered, they would either be interpreted as simple BLOB fields or an error occurs indicating an unsupported field type.

---

{button ,AL('db2translations')} DB2 data translations

## From DB2 physical types (to BDE, Paradox, dBASE)

DB2 physical	BDE logical	Paradox physical	dBASE physical
fldDB2BINARY	fldBYTES	fldPDXBYTES	fldDBMEMO
fldDB2BLOB	fldBLOB/fldstBINARY	fldPDXBINARYBLOB	fldDBMEMO
fldDB2CHAR	fldZSTRING/fldstFIXED		fldPDXCHAR fldDBCHAR
fldDB2CLOB	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO
fldDB2DATE	fldDATE	fldPDXDATE	fldDBDATE
fldDB2DBCLOB	NOT SUPPORTED		
fldDB2DECIMAL	fldFLOAT	fldPDXNUM	fldDBFLOAT {20.4}
fldDB2DOUBLE	fldFLOAT	fldPDXNUM	fldDBNUM {20.4}
fldDB2FLOAT	fldFLOAT	fldPDXNUM	fldDBNUM {20.4}
fldDB2INT	fldINT32	fldPDXLONG	fldDBNUM {11.0}
fldDB2LONGVARCHAR	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO
fldDB2LONGVARBINARY	fldBLOB/fldstBINARY	fldPDXBINARYBLOB	fldDBMEMO
fldDB2NUMERIC	fldFLOAT	fldPDXNUM	fldDBFLOAT
fldDB2SMALLINT	fldINT16	fldPDXSHORT	fldDBNUM {6.0}
fldDB2TIME	fldTIME	fldPDXTIME	fldDBCHAR
fldDB2TIMESTAMP	fldTIMESTAMP	fldPDXDATETIME	fldDBCHAR
fldDB2VARBINARY	fldVARBYTES	fldPDXBINARYBLOB	fldDBMEMO
fldDB2VARCHAR, n <= 255	fldZSTRING	fldCHAR/fldstFIXED	fldPDXCHAR
fldDB2VARCHAR, n > 255	fldBLOB/fldstMEMO	fldPDXMEMO	fldDBMEMO

**Note:** Although BDE supports NUMERIC and DECIMAL data types, inserting data for these types into a database on the DB2 server is not supported, pending a software update from IBM.

**Note:** The DB2 field types Graphic, VarGraphic, Long VarGraphic, and DBCLOB are not supported by the BDE. If encountered, they would either be interpreted as simple BLOB fields or an error occurs indicating an unsupported field type.

---

{button ,AL('db2translations')} [DB2 data translations](#)

## DB2 field-naming rules

Here is a list of field-naming rules for Paradox, dBASE, and DB2.

Naming rule	Paradox	dBASE	DB2
Max length (chars)	25	31	18
Valid characters	All	All alphanumeric except punctuation marks, blank spaces, and other special characters.	All alphanumeric except punctuation marks, blank spaces, and other special characters.
Must begin with . . .	Any valid character except space	A letter	A letter

**Note:** You may not use DB2-reserved words for remote table and column names. See the IBM *DATABASE 2 Client/Server SQL Reference*, Chapter 3 “Characters” and “Tokens” for reserved words.

---

{button ,AL(`connectingtodb2`)} [Connecting to DB2 topics](#)

{button ,AL(`db2translations`)} [DB2 data translations](#)

## Tips for using SQL Links

### Using aliases without specifying a language driver

If no language driver is specified, the default language driver is ASCII. Language-specific processes like character translation, sorting and table name validation will default to English rules. For further information, see [Common SQL Links driver settings](#) and your driver's "Connecting to..." section, listed in [Configuring and connecting to the SQL server](#).

### Working with large tables

If you create data entry forms on large tables you might find some performance degradation, particularly if the user is allowed to view unrestricted record sets. To help cut down the load on your server and optimize server performance try to write applications that access relatively few records at a time. One way to do this within a form-based application is to create forms that order the data by index and set range criteria to limit the record set. (For example, instead of creating a form that displays all orders for all customers, write your application to limit the user's working selection by criteria such as customer name, state, and area code.)

### Working with "snapshots" (tables without a unique index or row ID)

It is always better to use a table with a unique index if possible. This allows for better control and performance. If you insert records into a "snapshot" table, you might need to close and reopen the table to see your additions.

When working with a table that does not have a unique index or row ID, keep the following in mind:

- SQL Links does not support record modifications and deletions on "snapshots" within an explicit client transaction. Emptying tables is supported within an explicit client transaction, but rolling back such an operation does not update the internal record cache.
- To update the record cache, close the table and then open it again.

### Synonym and cross-database/cross-server table access

Oracle and Informix synonyms can now be accessed using DbiOpenTable and Live Queries. Tables on different databases or servers can also be accessed in the same way. For example, you can now open "SCOTT"."CUSTOMER"@ "DBLINK" on Oracle and pubs.dbo.authors on Sybase.

---

{button ,AL('sqlnotes')} [SQL Links hints, problems, and notes](#)

## **Known problems with this version of SQL Links**

For a discussion of known problems and issues with this version of SQL Links, see the following topics, then check BDEREADME.TXT in the same directory where your SQL Links are installed:

[General problems](#)

[Problems with dBASE indexes on Windows NT 3.51](#)

[Informix problems and notes](#)

[Sybase CT-Lib problems and notes](#)

[Sybase DB-Lib problems and notes](#)

[DB2 problems and notes](#)

[InterBase notes](#)

[Oracle notes](#)

[Microsoft SQL Server notes](#)

## DB2 problems and notes

### Transaction isolation level support

All BDE transaction isolation levels are supported by the DB2 driver. Any DB2 isolation levels not supported by the BDE are treated as Read Committed.

### Problems with DB2 on Windows 95

In Windows 95, you should catalog DB2 nodes using TCP/IP on the client, such as

```
CATALOG TCP/IP NODE MYNODE . . .
```

If you use the Microsoft IPX/SPX protocol, the protocol will hang when metadata is retrieved. IBM reports that this is a Microsoft problem.

The DB2 SQL Links driver can only access servers in the Windows 95 environment that are connected using TCP/IP.

### Connecting to AS/400 servers

Due to a problem with IBM server software, remote connections to DB2 on the AS/400 platform do not work properly when version 2.1.0 or earlier of the DB2 client/server library is used. Version 2.1.1 of the client/server library corrects the problem.

### Creating schema objects on IBM MVS

There is an optional entry within the alias settings of the BDE configuration called REMOTE DBN. This entry can be used for setting the user's preferred database on IBM MVS. For creating Schema objects using APIs like DbiCreateTable() this entry should be set to the user's preferred database name. This entry is only used for IBM MVS.

For example; REMOTE DBN = BORLAND will create objects in database BORLAND and the query generated by BDE will be "CREATE TABLE TABNAME ( . . . ) IN DATABASE BORLAND".

Ignoring this entry creates objects in the user's default database.

---

{button ,AL(`connectingtodb2`)} [Connecting to DB2 topics](#)

{button ,AL(`sqlnotes`)} [SQL Links hints, problems, and notes](#)

## Informix problems and notes

### Software requirements

The Informix 7 SQL Links driver requires this client software from Informix:

INFORMIX-ESQL/C for Win32 7.20. TC1 (or higher)

The Informix 9 SQL Links driver requires this client software from Informix:

INFORMIX-ESQL/C for Win32 9.12.

### Rollbacks and Informix Logging tables

Rolling back a transaction on an Informix Logging database invalidates the cursor. To avoid this, use ANSI databases or close the cursor after rolling back the transaction and reopen it.

### DECIMAL and MONEY precision in Informix

DECIMAL and MONEY data types are rounded to two decimal places when getting data from the server. For example, DECIMAL 123.4567 is rounded to 123.45. This is a vendor issue. To prevent this, set ENABLE BCD to TRUE in the BDE Administrator.

### DECIMAL and MONEY filters in Informix

Applying a filter on DECIMAL and MONEY fields in Informix fails because the data types are all mapped to the BDE logical type fldFLOAT. To avoid this, use passthrough SQL.

### Using Informix version 7.2 with BLOB fields

If you open a BLOB field on an Informix 7.2 server, trying to move to another record causes the server to crash. This is caused by an Informix problem corrected in version 7.21 of their server. You can also revert to version 7.14 to avoid the problem. Reference case number 55155 when contacting Informix for an update.

### Limitations on opening tables

This edition of the Informix SQL Link driver does not support opening a table with a column name that is an Informix keyword or function name. Some examples include MONTH, DAY, YEAR, AVG, COUNT, ALL, and UNIQUE.

For a complete list of keywords and function names, see your Informix documentation.

### Copying Informix tables with interval columns

When an Informix table with an interval column is copied, the destination table is created with an interval that has a qualifier of year-to-month. If this qualifier does not match the source table's interval qualifier, you will receive an error during the copy.

To work around this problem, use passthrough SQL to create the destination table with the correct interval qualifier. Then append the contents of the source table to the destination table.

### System table storage of object names

Before storing object names in the system tables (such as table names, index names, field names, and so on) the Informix driver converts them to lowercase.

---

{button ,AL('connectingtoinformix')} [Connecting to Informix topics](#)

{button ,AL('sqlnotes')} [SQL Links hints, problems, and notes](#)

## Sybase CT-Lib problems and notes

### Problems with Sybase CT-Lib stored procedures

When ENABLE BCD is TRUE, stored procedures with MONEY fields fail to retrieve MONEY output parameters.

### Supporting older Sybase SQL Server versions

The Sybase CT-Lib driver does not support older versions of the Sybase SQL Server. If you intend to use Sybase SQL Server versions 4.x and below, you must use the BDE Administrator (on the Sybase Driver page) to change the name of the DLL32 parameter from SQLSSC32.DLL (the default) to SQLSYB32.DLL. If you cannot find the SQLSYB32.DLL file then you will need to run the Install program and select the Sybase DBLIB driver to install. You will also need to set the environment variables PATH, SYBASE, INCLUDE and LIB so that they do not refer to the CT-Lib directory.

---

{button ,AL(`connectingtosybase`)} [Connecting to Sybase topics](#)

{button ,AL(`sqlnotes`)} [SQL Links hints, problems, and notes](#)

## General problems

### Updatable SQL queries

Tables owned by another user must be qualified by owner name. Use quotation marks around the entire qualified name, for example "OWNER" . "TABLE".

---

{button ,AL(`sqlnotes`)} [SQL Links hints, problems, and notes](#)

## Problems with dBASE indexes on Windows NT 3.51

When you add an index using DbiAddIndex or DbiCreateTable to a dBASE table under Windows NT version 3.51, you must close any cursors referencing the table and reopen them before using the table. This problem only occurs with tables located on a Novell NetWare server being accessed by Microsoft's NetWare client for NT. A workaround is to use Novell's NetWare client for NT.

---

{button ,AL('sqlnotes')} [SQL Links hints, problems, and notes](#)

## InterBase notes

### Stored procedures and parameter binding

Trying to bind parameters to a SQL statement after a stored procedure has been run results in a "Column Unknown" error when DbiQPrepare is called.

### InterBase installation changes

Before installing 5.1.1, it imperative that you uninstall any previous version (such as 4.x or 5.0).

---

{button ,AL(`connectingtointerbase`)} [Connecting to InterBase topics](#)

{button ,AL(`sqlnotes`)} [SQL Links hints, problems, and notes](#)

## Oracle notes

### Oracle updatable queries

All names, both column and table, are case sensitive (as if they were quoted explicitly).

### Configuring BDE for use with Oracle SQL\*NET v2.0 or greater

Use the BDE Administrator (to set the "Net Protocol" parameter for Oracle aliases to TNS).

### Oracle stored procedures

Oracle stored procedures do not accept boolean parameters, since OCI does not support the PL/SQL Boolean data type. Workarounds are:

1. Change the parameter type to integer and set the boolean value inside the procedure.
2. Write a wrapper procedure which does the above.

### FOR UPDATE in Oracle8

To use the keywords "FOR UPDATE" in a passthru SELECT statement to pessimistically lock a result set you need to do one of the following steps, but not both:

1. SQLPASSTHRU MODE must be set to SHARED NOAUTOCOMMIT
2. An explicit transaction must be started before executing the statement

### Live Queries

Live queries using Oracle8 ADT member fields in a WHERE clause are not supported.

### Additional Oracle notes

See these topics for additional notes on SQL Links and Oracle connectivity:

[Quoted names in Oracle](#)

[DRIVER FLAGS settings and Oracle compatibility](#)

---

{button ,AL('connectingtooracle')} [Connecting to Oracle topics](#)

{button ,AL('sqlnotes')} [SQL Links hints, problems, and notes](#)

## Quoted names in Oracle

### Support for quoted object names

This release of SQL Links supports the creation of Oracle tables with quoted object names. Object names enclosed in double quotation marks may contain spaces, special characters, reserved words, or mixed case. When querying a table with special object names, be sure to enclose the name in double quotation marks. For example:

```
SELECT * FROM "Customer"
```

For more information on object naming rules, see your Oracle server documentation.

### Using live queries with quoted field names

Live queries for Oracle tables require a table qualifier or an alias name if the field names are quoted. For example :

```
SELECT * FROM someTable WHERE "fieldname" = someValue
```

will not work, the workaround will be to use either

```
SELECT * FROM someTable T1 WHERE T1."fieldname" = someValue
```

or

```
SELECT * FROM someTable WHERE "someTable"."fieldname" = someValue
```

---

{button ,AL(`connectingtooracle`)} [Connecting to Oracle topics](#)

{button ,AL(`sqlnotes`)} [SQL Links hints, problems, and notes](#)

## DRIVER FLAGS settings and Oracle compatibility

### Mixed-case object names and compatibility

Using mixed-case object names can result in incompatibility with earlier versions of SQL Links for Oracle. Earlier versions of SQL Links used uppercase object names only. To use uppercase object names only, set the DRIVER FLAGS option to 1 using the BDE Administrator.

### Repeatable Read and compatibility

Specifying a Repeatable Read transaction isolation level can result in incompatibility with applications using earlier versions of SQL Links for Oracle. Earlier versions of SQL Links supported Read Committed only. To maintain transaction support compatibility with earlier versions of SQL Links, use the BDE Administrator to set the DRIVER FLAGS option to 512.

**Note:** To use uppercase object names only AND maintain transaction support compatibility with earlier versions of SQL Links, use the BDE Administrator to set the DRIVER FLAGS option to 513 (representing 512+1).

---

{button ,AL('connectingtooracle')} [Connecting to Oracle topics](#)

{button ,AL('sqlnotes')} [SQL Links hints, problems, and notes](#)

## Sybase DB-Lib problems and notes

### Transaction isolation level support

An error (DBIERR\_NOTSUPPORTED) is returned if Repeatable Read is specified.

### Multiple result sets

The Sybase SQL Links driver does not support the use of stored procedures that return multiple answer sets. A single returned cursor is supported.

### Sybase index hint for updatable queries

This release of SQL Link has added support for Sybase's forceindex hint for query optimization when performing updatable queries. For example, the following query is now a valid updatable query:

```
SELECT * FROM CUSTOMER (2)
```

In order to use this feature, the Sybase driver flags setting must contain 2.

**Note:** This is not a Sybase supported feature. It is not guaranteed to be trouble free.

### UPDATE/DELETE queries and DBIGETRELATIVERECORD

Running the SQL statements UPDATE or DELETE on a table with a unique index, closing and reopening the table, switching to an existing index, then calling DbiGetRelativeRecord results in the server error "Attempt to initiate a new SQL operation with results pending."

### Stored procedures and DBIQSETPROCPARAMS

If a stored procedure with a result set and either an output parameter or a return value is executed and then rebound using a call to DbiQSetProcParams, the output parameter or return value will not work correctly.

### Additional Sybase DB-Lib notes

See these topics for additional notes on SQL Links and Sybase DB-Lib connectivity:

[DRIVER FLAGS settings and Sybase DB-Lib BLOB handling](#)

[Sybase DB-Lib URGENT parameter and performance](#)

---

{button ,AL(`connectingtosybase`)} [Connecting to Sybase topics](#)

{button ,AL(`sqlnotes`)} [SQL Links hints, problems, and notes](#)

## **DRIVER FLAGS settings and Sybase DB-Lib BLOB handling**

For Sybase SQL Servers prior to System 10, if your SQL Server faults while executing BLOB reads or BLOB writes, check the SQL Link driver's DRIVER FLAGS parameter. If DRIVER FLAGS is set to 0 (the Sybase default):

1. Call Sybase Customer Support and describe the problem, referencing Case #125046.
2. Set the DRIVER FLAGS parameter to 1. Use this DRIVER FLAGS setting until you receive the necessary software fix from Sybase.

Setting DRIVER FLAGS to 1 will enable you to execute BLOB reads and BLOB writes without causing a server fault. This may cause the client to receive SQL Server timeouts during BLOB writes.

---

{button ,AL(`connectingtosybase`)} [Connecting to Sybase topics](#)

{button ,AL(`sqlnotes`)} [SQL Links hints, problems, and notes](#)

## Sybase DB-Lib URGENT parameter and performance

The use of the URGENT parameter is supported by the named pipes driver, the Novell NetWare networking software (SPX/IPX) as well as many TCP/IP networking packages (the DLLs specified in the following examples are network and network transport specific):

```
myNLMSrvr=C:\SQL\BIN\WDBNOVSP,04200020,1,83BD,URGENT
myUNIXsrvr=C:\SQL\BIN\WDBNOVTC,128.0.168.245,1425,URGENT
myNamedPipesrvr=C:\SQL\BIN\DLL_NAME,\\MY_SRV\ROOT,URGENT
```

The Sybase Open Client documentation erroneously notes that Novell's LanWorkPlace does not support the URGENT parameter. You actually need a LanWorkPlace version later than 4.0, Lan WorkPlace for OS/2 is compatible only with version 3.0.

URGENT requires Out of Band Data (OOBD) support and is necessary for Sybase's dbcancel() to work effectively. Dbcancel() is called to cancel the retrieval of un-read result sets.

In order to properly support OOBD, your Solaris-based server may need a call to ndd to set its tcp\_rexmit\_interval\_max parm. The call is:

```
/usr/sbin/ndd -set /dev/tcp tcp_rexmit_interval_max nnnn
```

where *nnnn* is a number of milliseconds.

You might see a delay when clicking on the master grid of a master-detail form—the query to retrieve the data for the detail might not return for several minutes.

By default, the TCP protocol will wait until a packet is full before sending it. This generally helps packet transmission over large networks because it cuts down on the number of packets sent. This can often slow the performance of client applications. If the server needs to send 750 bytes to an application and is using 512-byte packets, the client will see a delay while the server waits on 274 bytes of additional data.

It might be possible to disable this on the SQL Server itself. This can be done by adding a trace flag to the RUN\_SERVER file, -T1610.

---

{button ,AL('connectingtosybase')} [Connecting to Sybase topics](#)

{button ,AL('sqlnotes')} [SQL Links hints, problems, and notes](#)

## Microsoft SQL Server notes

### **DRIVER FLAGS setting and BLOB handling**

If your Microsoft SQL Server faults while executing BLOB reads or BLOB writes, check the SQL Link driver's DRIVER FLAGS parameter. If DRIVER FLAGS is set to 0 (the Microsoft SQL default) set the DRIVER FLAGS parameter to 1. Setting DRIVER FLAGS to 1 will enable you to execute BLOB reads and BLOB writes without causing a server fault. This may cause the client to receive SQL Server timeouts during BLOB writes.

---

{button ,AL(`connectingtoms`)} [Connecting to Microsoft SQL Server](#)

{button ,AL(`sqlnotes`)} [SQL Links hints, problems, and notes](#)

