

Libraries

COLLABORATORS

	<i>TITLE :</i> Libraries		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		July 23, 2024	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	Libraries	1
1.1	Amiga® RKM Libraries: B Boopsi Class Reference	1
1.2	B Boopsi Class Reference / Introduction	1
1.3	B Boopsi Class Reference / rootclass	3
1.4	B / rootclass / New Methods: OM_NEW	4
1.5	B / rootclass / New Methods: OM_DISPOSE	5
1.6	B / rootclass / New Methods: OM_ADDTAIL	6
1.7	B / rootclass / New Methods: OM_REMOVE	6
1.8	B / rootclass / New Methods: OM_ADDMEMBER	6
1.9	B / rootclass / New Methods: OM_REMMEMBER	7
1.10	B / rootclass / New Methods: OM_GET	7
1.11	B / rootclass / New Methods: OM_SET	7
1.12	B / rootclass / New Methods: OM_UPDATE	8
1.13	B / rootclass / New Methods: OM_NOTIFY	9
1.14	B Boopsi Class Reference / icclass	9
1.15	B / icclass / Changed Methods: OM_SET	10
1.16	B / icclass / Changed Methods: OM_UPDATE/OM_NOTIFY	10
1.17	B / icclass / Attributes: ICA_TARGET (IS)	10
1.18	B / icclass / Attributes: ICA_MAP (IS)	10
1.19	B / icclass / Attributes: ICSPECIAL_CODE (*)	11
1.20	B Boopsi Class Reference / modelclass	11
1.21	B / modelclass / Changed Methods: OM_ADDMEMBER	11
1.22	B / modelclass / Changed Methods: OM_REMMEMBER	11
1.23	B / modelclass / Changed Methods: OM_DISPOSE	12
1.24	B / modelclass / Changed Methods: OM_NOTIFY/OM_UPDATE	12
1.25	B Boopsi Class Reference / imageclass	12
1.26	B / imageclass / New Methods: IM_DRAW	12
1.27	B / imageclass / New Methods: IM_HITTEST	14
1.28	B / imageclass / New Methods: IM_ERASE	14
1.29	B / imageclass / New Methods: IM_DRAWFRAME	15

1.30	B / imageclass / New Methods: IM_HITFRAME	16
1.31	B / imageclass / New Methods: IM_ERASEFRAME	16
1.32	B / imageclass / New Methods: IM_FRAMEBOX	17
1.33	B / imageclass / Changed Methods: OM_NEW	18
1.34	B / imageclass / Changed Methods: OM_SET	18
1.35	B / imageclass / Attributes: IA_Left, IA_Top, IA_Width, IA_Height (ISG)	18
1.36	B / imageclass / Attributes: IA_FGPen, IA_BGPen (ISG)	18
1.37	B / imageclass / Attributes: IA_Data (ISG)	18
1.38	B / imageclass / Attributes: IA_Pens ()	18
1.39	B Boopsi Class Reference / frameiclass	18
1.40	B / frameiclass / Changed Methods: IM_DRAW	19
1.41	B / frameiclass / IDS_NORMAL, IDS_INACTIVENORMAL, IDS_DISABLED	19
1.42	B / frameiclass / Changed Methods: IDS_SELECTED, IDS_INACTIVeselected	19
1.43	B / frameiclass / Changed Methods: IM_DRAWFRAME	19
1.44	B / frameiclass / Changed Methods: IM_FRAMEBOX	20
1.45	B / frameiclass / Attributes: IA_Recessed (IS)	20
1.46	B / frameiclass / Attributes: IA_EdgesOnly (IS)	20
1.47	B Boopsi Class Reference / sysiclass	20
1.48	B / sysiclass / Attributes: SYSIA_DrawInfo (I)	21
1.49	B / sysiclass / Attributes: SYSIA_Which (I)	21
1.50	B / sysiclass / Attributes: SYSIA_Size (I)	21
1.51	B Boopsi Class Reference / fillrectclass	22
1.52	B / fillrectclass / Changed Methods: IM_DRAW	22
1.53	B / fillrectclass / Changed Methods: IM_DRAWFRAME	22
1.54	B / fillrectclass / Attributes: IA_APattern, IA_APatSize (IS)	22
1.55	B / fillrectclass / Attributes: IA_Mode (IS)	23
1.56	B Boopsi Class Reference / itexticlass	23
1.57	B / itexticlass / New Methods: IM_DRAW/IM_DRAWFRAME	23
1.58	B Boopsi Class Reference / gadgetclass	23
1.59	B / gadgetclass / New Methods: GM_HITTEST	25
1.60	B / gadgetclass / New Methods: GM_RENDER	25
1.61	B / gadgetclass / New Methods: GM_GOACTIVE	26
1.62	B / gadgetclass / New Methods: GM_HANDLEINPUT	27
1.63	B / gadgetclass / New Methods: GM_GOINACTIVE	28
1.64	B / gadgetclass / Changed Methods: OM_NEW	29
1.65	B / gadgetclass / Changed Methods: OM_NOTIFY	29
1.66	B / gadgetclass / Attributes: GA_Previous (I)	29
1.67	B / gadgetclass / Attributes: ICA_TARGET (IS)	29
1.68	B / gadgetclass / Attributes: ICA_MAP (IS)	30

1.69	B / gadgetclass / Attributes:GA_Left, GA_Top, GA_Width, GA_Height (IS)	30
1.70	B // GA_RelRight, GA_RelBottom, GA_RelWidth, GA_RelHeight (IS)	30
1.71	B / gadgetclass / Attributes:GA_IntuiText, GA_Text, GA_LabelImage (IS)	30
1.72	B / gadgetclass / Attributes: GA_Image (IS)	31
1.73	B / gadgetclass / Attributes: GA_Border - GA_SpecialInfo (IS)	31
1.74	B / gadgetclass / Attributes: GA_GZZGadget, GA_SysGadget (IS)	31
1.75	B / gadgetclass / Attributes: GA_Disabled, GA_Selected (IS)	31
1.76	B / gadgetclass / Attributes: GA_EndGadget - GA_TabCycle (IS)	31
1.77	B / gadgetclass / Attributes: GA_Highlight (IS)	32
1.78	B / gadgetclass / Attributes: GA_SysGType (IS)	32
1.79	B Boopsi Class Reference / propgclass	32
1.80	B / propgclass / Changed Methods: GM_HANDLEINPUT	33
1.81	B / propgclass / Attributes: GA_Image (I)	33
1.82	B / propgclass / Attributes: GA_Border (I)	33
1.83	B / propgclass / Attributes: GA_Highlight (I)	33
1.84	B / propgclass / Attributes: PGA_Freedom (IG)	34
1.85	B / propgclass / Attributes: PGA_NewLook (I)	34
1.86	B / propgclass / Attributes: PGA_Borderless (I)	34
1.87	B / propgclass / PGA_Top (ISGNU), PGA_Visible, PGA_Total (ISU)	34
1.88	B Boopsi Class Reference / strgclass	35
1.89	B / strgclass / Changed Methods: OM_NEW	35
1.90	B / strgclass / Attributes: STRINGA_LongVal (ISGNU)	35
1.91	B / strgclass / Attributes: STRINGA_TextVal (ISGNU)	36
1.92	B / strgclass / Attributes: STRINGA_MaxChars - STRINGA_WorkBuffer (I)	36
1.93	B / strgclass / Attributes: STRINGA_BufferPos, STRINGA_DispPos (ISU)	36
1.94	B / strgclass / Attributes: STRINGA_AltKeyMap (IS)	36
1.95	B / strgclass / Attributes: STRINGA_Font (IS)	36
1.96	B / strgclass / Attributes: STRINGA_Pens (IS)	36
1.97	B / strgclass / Attributes: STRINGA_ActivePens (IS)	37
1.98	B / strgclass / Attributes: STRINGA_EditHook (I)	37
1.99	B / strgclass / Attributes: STRINGA_EditModes (IS)	37
1.100B	/ strgclass / STRINGA_ReplaceMode - STRINGA_NoFilterMode (IS)	37
1.101B	/ strgclass / Attributes: STRINGA_Justification (IS)	37
1.102B	/ strgclass / Attributes: STRINGA_ExitHelp (IS)	37
1.103B	Boopsi Class Reference / buttongclass	37
1.104B	/ buttongclass / Changed Methods: GM_HITTEST	38
1.105B	/ buttongclass / Changed Methods: GM_HANDLEINPUT	38
1.106B	/ buttongclass / Changed Methods: GM_RENDER	38
1.107B	/ buttongclass / Attributes: GA_Image (IS)	38

1.108B Boopsi Class Reference / frbuttonclass	38
1.109B / frbuttonclass / Changed Methods: OM_NEW	39
1.110B / frbuttonclass / Changed Methods: GM_HITTEST	39
1.111B / frbuttonclass / Changed Methods: GM_RENDER	39
1.112B / frbuttonclass / Attributes: GA_Width, GA_Height (S)	40
1.113B / frbuttonclass / Attributes: GA_DrawInfo (I)	40
1.114B / frbuttonclass / Attributes:GA_Text,GA_IntuiText,GA_LabelImage (IS)	40
1.115B Boopsi Class Reference / groupgclass	40
1.116B / groupgclass / Changed Methods: OM_SET	41
1.117B / groupgclass / Changed Methods: OM_ADDMEMBER	41
1.118B / groupgclass / Changed Methods: OM_REMMEMBER	41
1.119B / groupgclass / Changed Methods: OM_DISPOSE	41
1.120B / groupgclass / Changed Methods: GM_HITTEST	41
1.121B / groupgclass / Changed Methods: GM_RENDER	41
1.122B / groupgclass / Changed: GM_GOACTIVE/GM_GOINACTIVE/GM_HANDLEINPUT	41
1.123B / groupgclass / Attributes: GA_Left, GA_Top (IS)	42

Chapter 1

Libraries

1.1 Amiga® RKM Libraries: B Boopsi Class Reference

The Boopsi Class Reference documents all of the classes built into Intuition. Each class entry in the reference starts off with:

```

Class:           The class's name (for example, gadgetclass)
Superclass:     The class's superclass (for example, rootclass)
Include File:   The class's include file (for example,
                <intuition/gadgetclass.h>)

```

The include file contains the class's message structures, attribute IDs, and method IDs. This is followed by a short description of the class.


The rest of a class entry is broken up into three sections:


- * New Methods Describes each new method that the class defines.
- * Changed Methods Describes each method to which this class makes significant changes.
- * Attributes Describes the attributes that this class defines as well as inherited ones that this class alters.

Introduction	imageclass	itexticlass	buttonclass
rootclass	frameiclass	gadgetclass	frbuttonclass
icclass	sysiclass	propgclass	groupgclass
modelclass	fillrectclass	strgclass	

1.2 B Boopsi Class Reference / Introduction

There are 14 public classes built into the Release 2.04 ROM:





This appendix documents all the standard Boopsi classes, including their methods and attributes.

Each class entry in this document can have two sets of methods: new methods that the class defines and inherited methods that the class has modified significantly. Similarly, each class entry can have two sets of attributes: those that the class defines and those that the class inherited and modified. Unless documented otherwise, all classes inherit all of its superclass's methods and attributes.

Each method has a Boopsi message associated with it. These messages are in the form of C structures. Many methods use the default message structure:

```

typedef struct
{
    ULONG MethodID;
} *Msg;
  
```

Some methods require a customized message so they can pass other parameters besides the Method ID. If a method requires a custom message, its custom message structure is documented along with the method.

All methods have to return some sort of return value. The meaning of the return value depends on the class and method. Normally a return value of zero indicates that either the method failed or it is not supported by the class. A method can use the return value to return a pointer to an object. If a class does not directly support a particular method, the class's dispatcher should pass the method on to its superclass for processing. The class dispatcher should record the return value it gets from its superclass and use that as its return value. Methods that assign no meaning to their return value can return 1L to indicate that the method is implemented.

The description of each attribute contains a code which lists the rootclass methods that apply to that attribute:

I	OM_NEW	Attribute can be set at initialization
S	OM_SET	Attribute can be set with OM_SET method
G	OM_GET	Attribute can be read with OM_GET method
N	OM_NOTIFY	Changing the attribute triggers object to send notifications

U OM_UPDATE Attribute can be set with OM_UPDATE method

For example, the itexticlass attribute IA_Left has the code (ISG) after it. This means an application can set IA_Left when it creates an instance of itexticlass (OM_NEW) and when it uses the OM_SET method. The application can also ask an itexticlass object what the IA_Left value is, using the OM_GET method.

The OM_NEW, OM_SET, OM_NOTIFY, and OM_UPDATE messages all contain a pointer to a tag list. This tag list contains the attributes and corresponding values that the method affects. Each TagItem in this list makes up an attribute/value pair. The ti_Tag portion of the TagItem contains the attribute's ID while the ti_Data field contains the attribute's value. Note that these tag lists can also contain utility.library Global System control tags (like TAG_SKIP and TAG_DONE), so dispatchers should use the tag functions from utility.library to process these lists. See documentation on the Utility library for more information.

All methods are called via a class dispatcher:

```
classDispatcher(Class *class, Object *object, Msg msg);
```

The first argument, class, is a pointer to the dispatcher's Class structure (defined in <intuition/classes.h>). The second parameter, object, is a pointer to the Boopsi object to which the Boopsi message (the third argument, msg) refers. Both Object and Msg are defined in <intuition/classusr.h>.

1.3 B Boopsi Class Reference / rootclass

```
Class:                rootclass
Superclass:           None
Include File:         <intuition/classusr.h>
```

This is the universal base class for all other classes.

New Methods:

```
-----
OM_NEW                OM_ADDTAIL
OM_DISPOSE            OM_REMOVE
```

The following methods are described at the rootclass level although its up to the subclasses to actually implement them. If a class does not implement these methods, it should either return zero, indicating that this class does not support the method, or defer processing on to its superclass.

```
OM_ADDMEMBER          OM_GET          OM_UPDATE
OM_REMMEMBER          OM_SET          OM_NOTIFY
```

Changed Methods:

```
-----
Not applicable.
```

Attributes:

None.

1.4 B / rootclass / New Methods: OM_NEW

This method tells a class to create a new instance of itself. If OM_NEW is successful, it returns a pointer to the new object, otherwise it returns NULL.

For programmers who are only creating Boopsi objects rather than creating custom classes, use the intuition.library function NewObject():

```
APTR NewObject(struct IClass *privateclass,
              UBYTE *publicclassname,
              ULONG firsttag,
              ...)
```

The OM_NEW method receives the following arguments (defined in <intuition/classusr.h>):

```
struct opSet /* The OM_NEW method uses the same structure as OM_SET */
{
    ULONG MethodID; /* OM_NEW */
    struct TagItem *ops_AttrList; /* tag attributes to initialize */
    struct GadgetInfo *ops_GInfo; /* Always NULL for OM_NEW */
};
```

The ops_AttrList field contains a pointer to a tag list of attribute/value pairs. Each pair contains an attribute ID and the initial value of the corresponding attribute.

The ops_GInfo field is always NULL for the OM_NEW method.

Unlike other methods, when the dispatcher gets an OM_NEW message, the object pointer (newobject from the dispatchRKMMModel() prototype above) does not point to an object, since the idea is to create a new object. The pointer normally used to pass a Boopsi object is instead used to pass the address of the object's "true class" (the class of which the object is an instance).

The first thing the dispatcher does when it processes an OM_NEW message is pass the OM_NEW message on to its superclass's dispatcher. It does this using the amiga.lib function DoSuperMethodA():

```
ULONG DoSuperMethodA(Class *cl, Object *trueclass, Msg msg);
```

Each superclass's dispatcher does this until the message gets to the rootclass dispatcher.

Each class keeps a record of how much memory its local instance data requires. The rootclass dispatcher's OM_NEW method looks at the object's true class (newobject from the prototype) to find out how much memory to allocate for the object's instance data. The rootclass dispatcher allocates enough memory for the true class's local instance data, plus

enough memory for the local instance data of each of the true class's superclasses. If all goes well, the rootclass dispatcher increments the true class's internal count of instances of true class, and returns a pointer to the newly created object. It passes control back to the subclass dispatcher that called it. If there was a problem, the rootclass dispatcher passes back a NULL.

When the rootclass dispatcher returns, the subclass dispatcher regains control from `DoSuperMethodA()`. `DoSuperMethodA()` will return either a pointer to the new object or NULL if there was an error. Although the rootclass dispatcher allocated all the memory the object needs, it did not set up any of that memory. Now it's the subclass dispatcher's turn to do some work. It has to initialize the instance data that is local to its class. A dispatcher finds its local instance data by using the `INST_DATA()` macro (defined in `<intuition/classes.h>`).

After initializing its local instance data, the subclass dispatcher passes control down to its subclass dispatcher, which in turn, initializes its local instance data. Control passes down from class to subclass until the true class dispatcher regains control.

Now the true class dispatcher has to initialize its local instance data. It has to scan through the tag list of attribute/value pairs passed in the `OM_NEW` message (`opSet.ops_AttrList`). If the dispatcher finds any attributes that the true class recognizes, it has to initialize them to the value passed in the attribute/value pair.

At this point, the new object can allocate other resources it needs that it did not allocate as part of its instance data. For example, the new Boopsi object might need a frame image around itself, so it can create a new one using a Boopsi frame image. If the object allocates any resources in this step, it must deallocate these resources later when it is disposed in the `OM_DISPOSE` method.

Finally, the dispatcher can return. When the dispatcher returns from an `OM_NEW` method, it returns a pointer to the new object.

1.5 B / rootclass / New Methods: OM_DISPOSE

This method instructs an object to delete itself. The rootclass dispatcher's `OM_DISPOSE` method decrements the true class's internal count of instances of true class. The return value for this method is not explicitly defined.

This method uses the default Boopsi message.

Applications should not call this method directly. Instead they should use the `intuition.library` function `DisposeObject()`.

For the `OM_DISPOSE` method, an object should do the following:

Free any additional resources the object explicitly allocated itself in the `OM_NEW` method (this does not include the instance data).

Pass the message up to the superclass, which will eventually reach

rootclass, which will free the instance data allocated for the object.

If a class does not allocate any extra resources when it creates an object, it can defer all OM_DISPOSE processing to its superclass.

1.6 B / rootclass / New Methods: OM_ADDTAIL

This method tells an object to add itself to the end of a specified Exec list. Boopsi objects contain a MinNode structure used for this purpose. The return value for this method is not explicitly defined.

The method uses a custom message (defined in <intuition/classusr.h>):

```
struct opAddTail {
    ULONG      MethodID;    /* OM_ADDTAIL */
    struct List *opat_List; /* The exec list to add the object to */
};
```

The opat_List can be any Exec list. Use the Intuition function NextObject() to step through this list.

1.7 B / rootclass / New Methods: OM_REMOVE

Remove an object from an Exec list. The return value for this method is not explicitly defined. This method uses the default Boopsi message.

1.8 B / rootclass / New Methods: OM_ADDMEMBER

Tells an object to add another object to its personal Exec list. What the list is for depends on the class. The return value for this method is not explicitly defined.

One class that uses this method is modelclass. A modelclass object maintains a broadcast list. When a modelclass object gets an OM_NOTIFY message, it broadcasts an OM_UPDATE message about the OM_NOTIFY to every object in its broadcast list.

This method uses a custom message (defined in <intuition/classusr.h>):

```
#define opAddMember opMember
struct opMember {
    ULONG      MethodID;    /* OM_ADDMEMBER (or OM_REMEMBER) */
    Object *opam_Object; /* add (or remove) this object */
};                      /* to (from) personal list. */
```

opam_Object is the object to add to the list. A dispatcher typically implements OM_ADDMEMBER by sending the OM_ADDTAIL message to the opam_Object object.

1.9 B / rootclass / New Methods: OM_REMMEMBER

Tells an object to remove a member object from its personal list. The member object should have already been added with OM_ADDMEMBER. This method uses the same custom message as OM_ADDMEMBER. Normally a dispatcher implements OM_REMMEMBER by sending the OM_REMOVE message to the opam_Object object. The return value for this method is not explicitly defined.

1.10 B / rootclass / New Methods: OM_GET

Tells an object to report an attribute's value. Applications should not call this method directly. Instead, use the intuition.library function GetAttr(). The return value for this method is not explicitly defined.

This method uses a custom message (defined in <intuition/classusr.h>):

```
struct opGet {
    ULONG MethodID;      /* OM_GET */
    ULONG opg_AttrID;    /* ID of attribute to get */
    ULONG *opg_Storage; /* place to put attribute value */
};
```

If the object's dispatcher recognizes opg_AttrID as one of the attributes defined by this class, the dispatcher should copy the value of that attribute to where opg_Storage points:

```
struct opGet *myopget;
...
*(myopget->opg_Storage) = my_attribute_value;
...
```

If the dispatcher does not recognize opg_AttrID, it should pass the message on to the superclass.

1.11 B / rootclass / New Methods: OM_SET

This method tells an object to set one or more of its attributes. Applications should not call this method directly. Instead, use the intuition.library functions SetAttrs() and SetGadgetAttrs() to call this method. The return value for this method is not explicitly defined.

The return value for this method is not explicitly defined. However, in general, when implementing the OM_SET method, if setting an object attribute causes some sort of visual state change, the OM_SET method should return a value greater than zero. If changing an attribute does not affect the visual state, OM_SET should return zero.

This method uses a custom message (defined in <intuition/classusr.h>):

```
struct opSet {
    ULONG          MethodID;      /* OM_SET */
```

```

    struct TagItem    *ops_AttrList; /* tag list of attributes to set*/
    struct GadgetInfo *ops_GInfo;
};

```

The `ops_AttrList` field contains a pointer to a tag list of attribute/value pairs. These pairs contain the IDs and the new values of the attributes to set. The dispatcher has to look through this list (see docs for the `utility.library NextTagItem()` function) for attributes its class recognizes and set the attribute's value accordingly. The dispatcher should let its superclass handle any attributes it does not recognize.

If the object is a gadget, the `ops_GInfo` field contains a pointer to a `GadgetInfo` structure. Otherwise, the value in `ops_GInfo` is undefined. Intuition use the `GadgetInfo` structure to pass display information to gadgets. See the `gadgetclass` methods for more details.

1.12 B / rootclass / New Methods: OM_UPDATE

This method tells an object to update one or more of its attributes. No application should call this method. Only Boopsi objects send `OM_UPDATE` messages. The return value for this method is not explicitly defined.

A Boopsi object uses an `OM_UPDATE` message to notify another Boopsi object about transitory changes to one or more attributes.

From the point of view of most objects, an `OM_UPDATE` message is almost identical to `OM_SET`. Because the methods are so similar, When a typical dispatcher receives an `OM_UPDATE` message, it processes the `OM_UPDATE` the same way it would process an `OM_SET` message, usually using the same code.

There are actually two kinds of `OM_UPDATE`, an interim and final one. While a Boopsi object's attribute is in a transient state, it can send out interim `OM_UPDATE` messages to its target(s). For example, while the user is sliding a Boopsi prop gadget, the prop gadget sends interim `OM_UPDATE` message about changes to its `PGA_Top` value (the integer value of the prop gadget is the `PGA_Top` attribute) to some target object. When the user lets go of the prop gadget, the gadget is no longer in a transient state, so the gadget sends out a final `OM_UPDATE` about its `PGA_Top` attribute. The target object can choose to change one of its attributes based on the `OM_UPDATE` messages it receives.

The layout of the `OM_UPDATE` message is almost identical to the `OM_SET` message:

```

    struct opUpdate { /* the OM_NOTIFY method also uses this structure */
        ULONG          MethodID;          /* OM_UPDATE */
        struct TagItem *opu_AttrList;     /* tag list of attributes */
        struct GadgetInfo *opu_GInfo;     /* that changed. */
        ULONG          opu_Flags;        /* The extra field */
    };

    #define OPUF_INTERIM    (1<<0)

```

Some dispatchers need to know the difference between an interim and final `OM_UPDATE`. A dispatcher can tell the difference between an interim and

final OM_UPDATE message because the OM_UPDATE message has an extra field for flags. If the low order bit (the OPUF_INTERIM bit) is set, this is an interim OM_UPDATE message. The interim flag is useful to a class that wants to ignore any interim messages, processing only final attribute values.

1.13 B / rootclass / New Methods: OM_NOTIFY

This method tells an object to broadcast an attribute change to a set of target objects using OM_UPDATE messages. The return value for this method is not explicitly defined.

The OM_NOTIFY method uses the same message structure as OM_UPDATE.

Most dispatchers do not handle the OM_NOTIFY message directly. Normally they inherit this method from a superclass, so they pass the OM_NOTIFY message on to the superclass dispatcher.

Although most dispatchers don't have to process OM_NOTIFY messages, most do have to send them. Whenever an object receives an OM_SET or OM_UPDATE about one of its attributes, it may need to notify other objects of the change. For example, when a prop gadget's PGA_Top value changes, its target object(s) need to hear about it.

If an object needs to notify other objects about a change to one or more of its attributes, it sends itself an OM_NOTIFY message. The OM_NOTIFY message will eventually end up in the hands of a superclass that understands OM_NOTIFY and it will send OM_UPDATE messages to the target objects.

1.14 B Boopsi Class Reference / icclass

```
Class:                icclass (interconnection class)
Superclass:          rootclass
Include File:        <intuition/icclass.h>
```

Base class of simple OM_UPDATE forwarding objects. When an icclass object gets an OM_UPDATE message, it maps the attributes in the OM_UPDATE message according to its mapping list (its ICA_MAP attribute) and forwards the OM_UPDATE to its target (its ICA_TARGET attribute).

New Methods:

None.

Changed Methods:

OM_SET OM_UPDATE/OM_NOTIFY

Attributes:

ICA_TARGET (IS) ICA_MAP (IS) ICSPECIAL_CODE (*)

1.15 B / icclass / Changed Methods: OM_SET

This method sets its attributes and returns 0.

1.16 B / icclass / Changed Methods: OM_UPDATE/OM_NOTIFY

These methods tell the object to notify its ICA_TARGET of attribute changes by sending the target an OM_UPDATE message. If the object has an ICA_MAP, it maps the attribute IDs it finds to new attribute IDs. See the rootclass descriptions of OM_NOTIFY and OM_UPDATE for more information. The return value for this method is not explicitly defined.

1.17 B / icclass / Attributes: ICA_TARGET (IS)

This attribute stores the address of the icclass object's target object. Whenever the icclass object receives an OM_NOTIFY or OM_UPDATE message, it forwards that message to its target in the form of an OM_UPDATE message. If the icclass object has an attribute mapping list (see the ICA_MAP attribute below), it also maps the OM_NOTIFY/OM_UPDATE message's attribute IDs to new ones before forwarding the message.

If the value of ICA_TARGET is ICTARGET_IDCMP, the icclass object sends an IDCMP_IDCMPUPDATE IntuiMessage to its window instead of forwarding an OM_UPDATE message. See the rootclass description of OM_UPDATE for more information.

1.18 B / icclass / Attributes: ICA_MAP (IS)

This attribute points to a tag list of attribute mappings which the icclass object uses to change the attribute IDs of an OM_UPDATE's attribute/value pairs. For example, if an icclass object had the following ICA_MAP:

```
struct TagItem map[] =
{
    {PGA_Top, STRINGA_LongVal},
    {MYATTR, MYNEWATTR},
    {TAG_END, }
};
```

before sending an OM_UPDATE to its ICA_TARGET, the icclass object scans through the OM_UPDATE message's attribute/value pairs looking for the PGA_Top and MYATTR attributes. If it finds the PGA_Top attribute, it changes PGA_Top to STRINGA_LongVal. Likewise, if the icclass object finds the MYATTR attribute, it changes MYATTR to MYNEWATTR. The icclass object does not disturb the attribute's value.

1.19 B / icclass / Attributes: ICSPECIAL_CODE (*)

This is a dummy attribute for the ICA_MAP. If any attribute maps to ICSPECIAL_CODE and ICA_TARGET is ICTARGET_IDCMP, then the value of the mapped attribute will be copied into the IntuiMessage.Code field of the IDCMP_IDCMPUPDATE message (just the lower sixteen bits of the attribute value will fit).

1.20 B Boopsi Class Reference / modelclass

```
Class:                modelclass
Superclass:          icclass
Include File:        <intuition/icclass.h>
```

A class of OM_UPDATE forwarding objects that have multiple targets. In addition to the features the modelclass object inherits from icclass, when a modelclass object gets an OM_UPDATE message, it forwards that OM_UPDATE message to all of the objects in its broadcast list.

New Methods:

None.

Changed Methods:

OM_ADDMEMBER OM_REMEMBER OM_DISPOSE OM_NOTIFY/OM_UPDATE

Attributes:

None.

1.21 B / modelclass / Changed Methods: OM_ADDMEMBER

This method tells a model to add an object to its broadcast list. When the object disposes of itself, it will also dispose of any objects remaining on its broadcast list. The return value for this method is not explicitly defined. See the rootclass description of OM_ADDMEMBER for more information.

1.22 B / modelclass / Changed Methods: OM_REMEMBER

This method tells a model to remove an object from its broadcast list. The return value for this method is not explicitly defined. See the rootclass description of OM_REMEMBER for more information.

1.23 B / modelclass / Changed Methods: OM_DISPOSE

This method tells a model to dispose of itself plus the objects remaining on its broadcast list. The return value for this method is not explicitly defined.

1.24 B / modelclass / Changed Methods: OM_NOTIFY/OM_UPDATE

This method tells an object to forward the message in the form of an OM_UPDATE message to all the objects in its broadcast list. The modelclass does not map the attributes in these OM_UPDATE messages. Because modelclass inherits behavior from icclass, if the model has an ICA_TARGET and ICA_MAP, it will also send a mapped OM_UPDATE message to its ICA_TARGET. The return values for these methods are not explicitly defined. See the rootclass OM_NOTIFY/OM_UPDATE and icclass OM_NOTIFY/OM_UPDATE descriptions for more information.

1.25 B Boopsi Class Reference / imageclass

```
Class:                imageclass
Superclass:          rootclass
Include File:        <intuition/imageclass.h>
```

This class is the base class for Boopsi Images. These images are backwards compatible with the conventional Intuition Images. Every Boopsi image has an Intuition Image structure embedded in it so Intuition can access the Boopsi image as a conventional Image structure when necessary. Normally there are no direct instances of this class, only instances of subclasses of imageclass.

New Methods:

```
-----
IM_DRAW          IM_ERASE          IM_HITFRAME      IM_FRAMEBOX
IM_HITTEST       IM_DRAWFRAME      IM_ERASEFRAME
```

Changed Methods:

```
-----
OM_NEW          OM_SET
```

Attributes:

```
-----
IA_Left, IA_Top, IA_Width, IA_Height (ISG)
IA_FGPen, IA_BGPen (ISG)
IA_Data (ISG)
IA_Pens ()
```

1.26 B / imageclass / New Methods: IM_DRAW

This method tells an image object to draw itself. Applications should not call this method directly, instead use the intuition.library function DrawImageState(). The return value for this method is not explicitly defined.

The IM_DRAW method uses a custom message structure:

```

struct impDraw
{
    ULONG          MethodID;    /* IM_DRAW          */
    struct RastPort *imp_RPort; /* RastPort to render into */
    struct
    {
        /* X and Y offset relative to */
        WORD X;                /* the image's IA_Left and */
        WORD Y;                /* IA_Top attributes      */
    } imp_Offset;
    ULONG          imp_State;    /* Visual state of image    */
    struct DrawInfo *imp_DrInfo; /* describing rendering area */
};
n

```

The imp_State field contains the visual state to render the image. The visual states (defined in <intuition/imageclass.h>) are:

IDS_NORMAL	Render using normal imagery. This is the only kind of imagery available to non-Boopsi images.
IDS_SELECTED	Render using "selected" imagery. "Selected" refers to the state of a gadget's imagery when it is the selected gadget.
IDS_DISABLED	Render using "disabled" imagery. "Disabled" refers to the state of a gadget's imagery when it is disabled. Typically, a disabled image has a ghosting pattern on top of it.
IDS_INACTIVENORMAL	This is a special version of IDS_NORMAL for a "normal" image that is in the border of an inactive window.
IDS_INACTIVeselected	This is a special version of IDS_SELECTED for a "selected" image that is in the border of an inactive window.
IDS_INACTIVEDISABLED	This is a special version of IDS_DISABLED for a "disabled" image that is in the border of an inactive window.
IDS_BUSY	Render using "busy" imagery as if the object was the image of a gadget in a busy state. The busy gadget state is not yet supported by Intuition.
IDS_INDETERMINATE	Render using "indeterminate" imagery as if the object was the image of a gadget in an

indeterminate state. The indeterminate gadget state is not yet supported by Intuition.

Most image objects do not have different visual states for each possible `imp_State`. See the `imageclass` entries in this index for more details.

When setting the pens to render an image, use the values from the `imp_DrInfo->dri_Pens` pen array (Note that it is possible for `imp_DrInfo` to be `NULL`). The possible pen values are defined in `<intuition/screens.h>`. See the "Intuition Screens" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information on the pen array.

1.27 B / imageclass / New Methods: IM_HITTEST

This method returns `TRUE` if a point is within the old Image structure box defined by the Image structure's `LeftEdge`, `TopEdge`, `Width`, and `Height` fields. Subclasses of `imageclass` can redefine this method if they need to change the criteria for deciding if a point is within an image. Application programs should not call this method directly, instead use the Intuition function `PointInImage()`. The `IM_HITTEST` method uses a custom message structure:

```
struct impHitTest
{
    ULONG MethodID; /* IM_HITTEST */
    struct
    {
        WORD X;      /* Coordinates of point to test for hit */
        WORD Y;
    } imp_Point;
};
```

If an image object doesn't need to make any changes to how its superclass handles `IM_HITTEST`, it can blindly pass this method on to its superclass.

1.28 B / imageclass / New Methods: IM_ERASE

The `IM_ERASE` method tells an image to erase itself. Applications should not call this method directly, instead they should call the Intuition function `EraseImage()`. The return value for this method is not explicitly defined.

The `IM_ERASE` method uses a custom message structure:

```
struct impErase
{
    ULONG          MethodID; /* IM_ERASE */
    struct RastPort *imp_RPort; /* The image's RastPort */
    struct
    {
        WORD X;          /* X and Y offset relative */
        WORD Y;          /* to the image's IA_Left */
    }
};
```

```

    } imp_Offset;          /* and IA_Top attributes. */
};

```

The imageclass dispatcher calls the graphics.library function EraseRect() to erase the image. The imageclass dispatcher gets the position of the image using the offsets from the IM_ERASE message and the dimensions it finds in the object's Image structure. The imageclass dispatcher does not do any bounds checking before calling EraseRect().

1.29 B / imageclass / New Methods: IM_DRAWFRAME

The IM_DRAWFRAME method instructs an image object to render itself within the confines of a given rectangle. The return value for this method is not explicitly defined.

This method uses a custom message structure that is basically an extension of the IM_DRAW message: struct impDraw

```

{
    ULONG          MethodID;    /* IM_DRAWFRAME */
    struct RastPort *imp_RPort; /* RastPort to render into */
    struct
    {
        WORD X;                /* X and Y offset relative to the */
        WORD Y;                /* image's IA_Left and IA_Top attributes */
    } imp_Offset;
    ULONG          imp_State; /* Visual state of image (see defines below)*/
    struct DrawInfo *imp_DrInfo;
                          /* DrawInfo describing target RastPort (can be NULL) */
    struct
    {
        WORD Width; /* scale, clip, restrict, etc. to these bounds */
        WORD Height;
    } imp_Dimensions;
};

```

The Width and Height fields provide the object's rectangular bounds. How the image object deals with the frame is implementation specific. If the imageclass dispatcher sees this message, it will convert it to an IM_DRAW message and send it back to the image's true class. An image subclass which assigns proper meaning to this method (i.e., frameiclass) should handle this method itself.

This method is useful to classes of images that can scale or clip themselves to arbitrary dimensions. Typically, an instance of a class that truly supports this method will massage its imagery as best it can to fit into the rectangle.

In general, applications that use this method to draw an object should use the IM_ERASEFRAME method to erase it (see below). This will ensure that the image erases itself at the proper scale.

1.30 B / imageclass / New Methods: IM_HITFRAME

This method is a special version of IM_HITTEST for images that support IM_DRAWFRAME. It asks an image if a point would be inside it if the image was confined (scaled, clipped, etc.) to a rectangular bounds. The return value for this method is not explicitly defined.

This method uses a custom message structure:

```
struct impHitTest
{
    ULONG MethodID;    /* IM_HITFRAME */
    struct
    {
        WORD X;        /* Coordinates of point to test for hit */
        WORD Y;
    } imp_Point;

    struct
    {
        WORD Width; /* scale, clip, restrict, etc. to these bounds */
        WORD Height;
    } imp_Dimensions;
};
```

The imageclass dispatcher treats IM_HITFRAME just like IM_HITTEST, ignoring the restricting dimensions.

1.31 B / imageclass / New Methods: IM_ERASEFRAME

This method is a special version of IM_ERASE for images that support IM_DRAWFRAME. It asks an image to erase itself as if it were confined (scaled, clipped, etc.) to a rectangular bounds. The return value for this method is not explicitly defined.

This method uses a custom message structure:

```
struct impErase /* NOTE: This is a subset of impDraw */
{
    ULONG MethodID; /* IM_ERASEFRAME */
    struct RastPort *imp_RPort; /* The image's RastPort */
    struct
    {
        WORD X; /* X and Y offset relative to the */
        WORD Y; /* image's IA_Left and IA_Top attributes */
    } imp_Offset;

    struct
    {
        WORD Width; /* scale, clip, restrict, etc. to these bounds */
        WORD Height;
    } imp_Dimensions;
};
```

The imageclass dispatcher handles an `IM_ERASEFRAME` message as if it was an `IM_ERASE` message, ignoring the bounds. See the imageclass description for `IM_ERASE` for more details.

1.32 B / imageclass / New Methods: `IM_FRAMEBOX`

This method applies to image classes that are used to put a frame centered around some other objects. This method asks a framing image what its dimensions should be if it had to frame some object or set of objects that fit into a rectangular bounds. For example, to draw an image around a group of gadgets that fit into a specific rectangle, you first send the image object an `IM_FRAMEBOX` message describing the dimensions and position of that rectangle. The frame reports what its position and dimensions would have to be to surround those gadgets. Use these results to draw the image. The return value for this method is not explicitly defined.

`IM_FRAMEBOX` uses a custom message structure:

```
struct impFrameBox
{
    ULONG          MethodID;          /* IM_FRAMEBOX */
    struct IBox    *imp_ContentsBox; /* The object fills in this */
                                          /* structure with the */
                                          /* dimensions of a rectangle */
                                          /* big enough to frame... */
    struct IBox    *imp_FrameBox;    /* <----- this rectangle. */
    struct DrawInfo *imp_DrInfo;    /* imp_DrInfo can be NULL. */
    ULONG          imp_FrameFlags;
};
#define FRAMEF_SPECIFY (1<<0) /* Make do with the dimensions */
                               /* passed in FrameBox. */
```

The `imp_FrameBox` field points to an `IBox` structure (defined in `<intuition/intuition.h>`) describing the dimensions and position of the rectangle to frame. After the framing image determines the position and size it should be in order to properly frame `imp_FrameBox`, it stores the result in the `imp_ContentsBox` `IBox`. This method allows an application to use a framing image without having to worry about image specific details such as the thickness of the frame or centering the frame around the object.

The `imp_FrameFlags` field is a bit field used to specify certain options for the `IM_FRAMEBOX` method. Currently, there is only one defined for it, `FRAMEF_SPECIFY`. If this bit is set, the `imp_FrameBox` contains a width and height that the frame image has to use as its width and height, even if the `imp_FrameBox` is smaller than `imp_ContentsBox`. The frame is free to adjust its position, but it is stuck with the `imp_FrameBox` dimensions. This allows an application to set the size of the frame image and still allow the frame image to position itself so it is centered on a rectangle.

The imageclass dispatcher does not support this method. It returns zero.

1.33 B / imageclass / Changed Methods: OM_NEW

The instance data for imageclass contains an Image structure, and its Depth field is initialized to CUSTOMIMAGEDEPTH, which identifies such images to Intuition. The Image's Width and Height fields default to arbitrary positive numbers for safety, but an imageclass subclass or an application should set these attributes to something meaningful.

1.34 B / imageclass / Changed Methods: OM_SET

This method applies to all imageclass attributes. OM_SET returns 1.

1.35 B / imageclass / Attributes: IA_Left, IA_Top, IA_Width, IA_Height (ISG)

These attributes correspond to similarly named fields in the Intuition Image structure. The imageclass dispatcher stores these attributes in their corresponding fields in the image object's embedded Image structure.

1.36 B / imageclass / Attributes: IA_FGPen, IA_BGPen (ISG)

These attributes are copied into the Image structure's PlanePick and PlaneOnOff fields, respectively.

1.37 B / imageclass / Attributes: IA_Data (ISG)

A pointer to general image data. This value is stored in the ImageData field of the Image structure.

1.38 B / imageclass / Attributes: IA_Pens ()

This attribute points to an alternative pen array for the image. Imageclass does not support this attribute, it is described here for subclasses to use. See the "Intuition Screens" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information on the pen array.

1.39 B Boopsi Class Reference / frameiclass

```
Class:                frameiclass
Superclass:          imageclass
Include File:        <intuition/imageclass.h>
```

This is a class of framing image, which can optionally fill itself. Its

purpose is to frame other display elements using an embossed or recessed rectangular frame. The frame renders itself using the appropriate DrawInfo pens (SHINEPEN, SHADOWPEN, etc.). This class is intelligent enough to bound or center its contents.

New Methods:

None.

Changed Methods:

IM_DRAW
IDS_NORMAL, IDS_INACTIVENORMAL, IDS_DISABLED
IDS_SELECTED, IDS_INACTIVELYSELECTED
IM_DRAWFRAME
IM_FRAMEBOX

Attributes:

IA_Recessed (IS) IA_EdgesOnly (IS)

1.40 B / frameiclass / Changed Methods: IM_DRAW

This method tells a frameiclass object to render itself using the position and dimensions of its Image structure. It supports two sets of drawing states (passes in the impDraw.imp_State field):

1.41 B / frameiclass / IDS_NORMAL, IDS_INACTIVENORMAL, IDS_DISABLED

In these states, the frame renders its edges using SHADOWPEN and SHINEPEN. If it is a filled frame the frame uses the BACKGROUNDPEN for its interior. Note that the frame renders the same imagery for all three of these states.

1.42 B / frameiclass / Changed Methods: IDS_SELECTED, IDS_INACTIVELYSELECTED

In these states, the frame renders its edges using SHADOWPEN and SHINEPEN. If it is a filled frame the frame uses the FILLPEN for its interior.

See the imageclass description for IM_DRAW for more details.

1.43 B / frameiclass / Changed Methods: IM_DRAWFRAME

This method is almost the same as the frameiclass IM_DRAW method, except this method accepts a width and height that overrides the width and height stored in the object's Image structure. It uses the same drawing states as the frameiclass's IM_DRAW method. See the imageclass description for IM_DRAWFRAME for more information.

1.44 B / frameiclass / Changed Methods: IM_FRAMEBOX

This method asks a frameiclass image what its dimensions would be if it has to frame a specific rectangular area. See the imageclass description for IM_FRAMEBOX for more information.

1.45 B / frameiclass / Attributes: IA_Recessed (IS)

If this attribute is TRUE, a frameiclass object will appear recessed into the drawing surface. It does this by swapping its use of the SHADOWPEN and SHINEPEN. By default, the frame appears to be raised from the surface.

1.46 B / frameiclass / Attributes: IA_EdgesOnly (IS)

If this attribute is TRUE, the frame does not fill itself, it just draws its edges.

1.47 B Boopsi Class Reference / sysiclass

```
Class:                sysiclass
Superclass:           imageclass
Include File:         <intuition/imageclass.h>
```

This is a class of system images and standard application images. As of Intuition version 37, there are 11 possible sysiclass image glyphs to choose from:

```
DEPTHIMAGE    Window depth arrangement image.
ZOOMIMAGE     Window Zoom image.
SIZEIMAGE     Window Sizing image.
CLOSEIMAGE    Window close image.
SDEPTHIMAGE   Screen depth arrangement image.
LEFTIMAGE     Left arrow image.
RIGHTIMAGE    Right arrow image.
UPIMAGE       Up arrow image.
DOWNIMAGE     Down arrow image.
CHECKIMAGE    Checkmark image.
MXIMAGE       Radio button image.
```

The class caches the image's bitmap to improve rendering speed.

New Methods:

None.

Changed Methods:

None.

Attributes:

SYSIA_DrawInfo (I) SYSIA_Which (I) SYSIA_Size (I)

1.48 B / sysiclass / Attributes: SYSIA_DrawInfo (I)

This attribute contains a pointer to a DrawInfo structure (defined in <intuition/screens.h>) describing the target screen. The class requires this attribute in order to generate the image into a bitmap cache.

1.49 B / sysiclass / Attributes: SYSIA_Which (I)

This attribute identifies which of the system image glyphs the sysiclass object uses. It can be one of the 11 glyphs described above.

1.50 B / sysiclass / Attributes: SYSIA_Size (I)

This attribute identifies which image size to use for the object. This generalizes Intuition's older concept of two different system image dimensions. There are three possible values for this attribute:

SYSISIZE_MEDRES Meant for Hires, non-interlaced 640x200/256 display.
 SYSISIZE_HIRES Meant for Hires, interlaced 640x400/512 display.
 SYSISIZE_LOWRRES Meant for Lores 320x200/256 display.

These sizes do not apply to all of the glyphs consistently. See the chart below for image dimensions (width x height) according to the SYSIA_Size and the glyph type. An 'H' for the height means the glyph allows its height to be specified with IA_Height.

SYSISIZE	LOWRES	SYSISIZE_MEDRES	SYSISIZE_HIRES
-----	-----	-----	-----
DEPTHIMAGE	18 x H	24 x H	24 x H
ZOOMIMAGE	18 x H	24 x H	24 x H
SIZEIMAGE	13 x 11	18 x 10	18 x 10
CLOSEIMAGE	15 x H	20 x H	20 x H
SDEPTHIMAGE	17 x H	23 x H	23 x H
LEFTIMAGE	16 x 11	16 x 10	23 x 22
RIGHTIMAGE	16 x 11	16 x 10	23 x 22
UPIMAGE	13 x 11	18 x 11	23 x 22
DOWNIMAGE	13 x 11	18 x 11	23 x 22
CHECKIMAGE	26 x 11	26 x 11	26 x 11
MXIMAGE	17 x 9	17 x 9	17 x 9

1.51 B Boopsi Class Reference / fillrectclass

```
Class:                fillrectclass
Superclass:          imageclass
Include File:        <intuition/imageclass.h>
```

This is a class of filled rectangles. The fillrectclass object can use a pattern to fill in its interior.

New Methods:

None.

Changed Methods:

IM_DRAW IM_DRAW

Attributes:

IA_APattern, IA_APatSize (IS) IA_Mode (IS)

1.52 B / fillrectclass / Changed Methods: IM_DRAW

This method asks a fillrectclass object to render itself relative to the position (LeftEdge and TopEdge) and dimensions (Width and Height) in its embedded Image structure. See the imageclass description of IM_DRAW for more details.

1.53 B / fillrectclass / Changed Methods: IM_DRAWFRAME

This method asks a fillrectclass object to render itself relative to the position in its embedded Image structure, but using the width and height passed in the message's Dimensions.Width and Dimensions.Height fields. See the imageclass description of IM_DRAWFRAME for more details.

1.54 B / fillrectclass / Attributes: IA_APattern, IA_APatSize (IS)

These attributes supply the fillrectclass object with an area fill pattern. The IA_APattern attribute points to the area fill pattern for the object. The IA_APatSize attribute is the depth of the area fill pattern. These attribute values are similar to the parameters passed to the SetAfPt() macro (defined in <graphics/gfxmacros.h>) and indirectly correspond to fields in a RastPort structure. For more information on these patterns, see the section on patterns in the "Graphics Primitives" chapter of the Amiga ROM Kernel Reference Manual: Libraries.

1.55 B / fillrectclass / Attributes: IA_Mode (IS)

This attribute contains the drawing mode for the pattern (JAM1, JAM2, etc.)

1.56 B Boopsi Class Reference / itexticlass

```
Class:          itexticlass
Superclass:    imageclass
Include File:  <intuition/imageclass.h>
```

This is a class of image objects that render an IntuiText structure. Using some of the imageclass attributes, the object can override some of the parameters in the IntuiText structure. This class makes it easy to share an IntuiText structure between objects.

New Methods:

None.

Changed Methods:

IM_DRAW/IM_DRAWFRAME

1.57 B / itexticlass / New Methods: IM_DRAW/IM_DRAWFRAME

These methods ask an itexticlass object to render its IntuiText structure, which it gets from the imageclass IA_Data attribute. An itexticlass object renders its IntuiText relative to the IA_Left and IA_Top attributes it inherits from imageclass. This method uses the JAM1 drawing mode and the IA_FGPen to render the text. See the imageclass description of IM_DRAW/IM_DRAWFRAME for more details.

1.58 B Boopsi Class Reference / gadgetclass

```
Class:          gadgetclass
Superclass:    rootclass
Include File:  <intuition/gadgetclass.h>
```

This is a base class for Intuition compatible gadget objects. The dispatcher for this class takes care of creating an Intuition Gadget structure as part of its local instance data. All of the standard Boopsi gadget classes build on this class. Normally there are no direct instances of this class, only instances of subclasses of gadgetclass.

The behavior of a Boopsi gadget depends on how it handles the five Boopsi gadget methods: GM_HITTEST, GM_RENDER, GM_GOACTIVE, GM_HANDLEINPUT, and GM_GOINACTIVE. Intuition controls a Boopsi gadget by sending it these types of messages. The structures that these methods use for their messages begin with the method's ID followed by a pointer to a GadgetInfo

structure (defined in <intuition/cghooks.h>). The GadgetInfo structure is a read-only structure that contains information about the gadget's rendering environment. The gadget uses this to find things like its window, screen, or pen array. Although this structure does contain a pointer to a RastPort for the gadget, the gadget must not use this RastPort for rendering. The gadget can obtain a RastPort for rendering by calling the Intuition function ObtainGIRPort() using the GadgetInfo structure. See the intuition.library Autodocs for more details on this function.

These methods are not defined directly by gadgetclass. It is up to subclasses of gadgetclass to implement them.

Like all Boopsi methods, these methods run on the context of the task that called the method. Normally, Intuition is the only entity that calls these methods, so these normally operate in the input.device's task. Because a gadget may have to process a large number of input events, poor implementations of gadget methods (especially the GM_HANDLEINPUT method) can degrade system performance.

New Methods:

```
-----
GM_HITTEST      GM_GOACTIVE      GM_GOINACTIVE
GM_RENDER       GM_HANDLEINPUT
```

Changed Methods:

```
-----
OM_NEW         OM_NOTIFY
```

Attributes:

```
-----
GA_Previous (I)
ICA_TARGET (IS)
ICA_MAP (IS)
GA_Left, GA_Top, GA_Width, GA_Height (IS)
GA_RelRight, GA_RelBottom, GA_RelWidth, GA_RelHeight (IS)
```

The remaining attributes defined by gadgetclass are used to set the fields in the Gadget structure of the Boopsi gadget. Some Boopsi gadgets do not pay attention to many of the fields in its Gadget structure, so most applications will not have to worry about the majority of these attributes. Some gadget classes assign special meanings to these attributes. See the documentation of the specific gadget classes for more details.

```
GA_IntuiText, GA_Text, GA_LabelImage (IS)
GA_Image (IS)
GA_Border, GA_SelectRender, GA_ID, GA_UserData, GA_SpecialInfo (IS)
GA_GZZGadget, GA_SysGadget (IS)
GA_Disabled, GA_Selected (IS)
GA_EndGadget, GA_Immediate, GA_RelVerify, GA_FollowMouse, (IS)
GA_RightBorder, GA_LeftBorder, GA_TopBorder, GA_BottomBorder, (IS)
GA_ToggleSelect, GA_TabCycle (IS)
GA_Highlight (IS)
GA_SysGType (IS)
```

1.59 B / gadgetclass / New Methods: GM_HITTEST

This method asks a gadget if a point is within its bounds. Usually the point corresponds to a mouse click. Intuition sends a gadget this message when the user clicks inside the rectangular bounds found in the object's Gadget structure (using its TopEdge, LeftEdge, Width, and Height fields). This method returns GMR_GADGETHIT if a point is within the gadget, otherwise it returns zero. Because the gadget decides if it was hit, the gadget can be almost any shape or pattern. Boopsi gadgets that default to using the bounds of their Gadget structure should always return GMR_GADGETHIT.

GM_HITTEST uses a custom message structure (defined in <intuition/gadgetclass.h>):

```
struct gpHitTest
{
    ULONG          MethodID;      /* GM_HITTEST */
    struct GadgetInfo *gpht_GInfo;
    struct
    {
        WORD X;                  /* Is this point inside */
        WORD Y;                  /* of the gadget? */
    } gpht_Mouse;
};
```

The gpht_Mouse.X and gpht_Mouse.Y fields make up the X and Y coordinates of the hit point. These coordinates are relative to the upper-left corner of the gadget (Gadget.LeftEdge, Gadget.TopEdge).

1.60 B / gadgetclass / New Methods: GM_RENDER

This method tells a gadget to render itself. The return value for this method is not explicitly defined.

GM_RENDER uses a custom message structure (defined in <intuition/gadgetclass.h>):

```
struct gpRender
{
    ULONG          MethodID;      /* GM_RENDER */
    struct GadgetInfo *gpr_GInfo;
    struct RastPort *gpr_RPort; /* all ready for use */
    LONG           gpr_Redraw; /* might be a "highlight pass" */
};
```

The GM_RENDER message contains a pointer to the Gadget's RastPort which it can use for rendering. The Gadget renders itself according to how much imagery it needs to replace. The gpr_Redraw field contains one of three values:

GREDRAW_REDRAW Redraw the entire gadget.

GREDRAW_UPDATE The user has manipulated the gadget changing the

imagery. Update only that part of the gadget's imagery that is effected by the user manipulating the gadget (for example, the knob and scrolling field of the prop gadget).

GREDRAW_TOGGLE If this gadget supports it, toggle to or from the highlighting imagery.

1.61 B / gadgetclass / New Methods: GM_GOACTIVE

This method asks a gadget if it is OK to make it the active gadget. The active gadget is the gadget that is currently receiving user input. Intuition sends this message after a gadget responds affirmatively to the GM_HITTEST method. A gadget becomes active because it needs to process input events (like a prop gadget or string gadget).

Some types of gadget do not need to become active. These gadgets do not have to process input from the user, they only have to deal with a single mouse click to toggle their state. Because that mouse click triggered this method, the button already has all of the user input it requires. Note that the behavior of the GadTools button differs from a Boopsi buttongclass gadget, which processes other input events besides a single mouse click. See the entry for buttongclass in this Appendix for more details.

GM_GOACTIVE uses a custom message structure (defined in <intuition/gadgetclass.h>):

```

struct gpInput
{
    ULONG          MethodID;      /* GM_GOACTIVE or GM_HANDLEINPUT */
    struct GadgetInfo *gpi_GInfo;
    struct InputEvent *gpi_IEvent; /* The input event that triggered */
                                   /* this method (can be NULL for */
                                   /* GM_GOACTIVE). */
    LONG          *gpi_Termination; /* For GADGETUP IntuiMessage.Code */
    struct
    {
        WORD X;                /* Mouse position relative to upper */
        WORD Y;                /* left corner of gadget (LeftEdge, */
    } gpi_Mouse;              /* TopEdge). */
};

```

The gpi_IEvent field points to the struct InputEvent that triggered the GM_GOACTIVE message. If gpi_IEvent is NULL, the GM_GOACTIVE message was triggered by a function like intuition.library's ActivateGadget() and not by the user clicking the gadget.

For gadgets that only want to become active as a direct result of a mouse click, this difference is important. For example, the prop gadget becomes active only when the user clicks on its knob. Because the only way the user can control the prop gadget is via the mouse, it would not make sense for it to be activated by anything besides the mouse. On the other hand, a string gadget gets input from the keyboard, so a string gadget doesn't care what activates it. Its input comes from the keyboard rather than the

mouse.

A gadget's `GM_GOACTIVE` method returns `GMR_MEACTIVE` (defined in `<intuition/gadgetclass.h>`) if it wants to be the active gadget. Otherwise it returns `GMR_NOREUSE`. For a description of what these values mean, See their description in the `gadgetclass`'s `GM_HANDLEINPUT` method, below.

If necessary, a gadget's `GM_GOACTIVE` method can precalculate and cache information before it becomes the active gadget. The gadget will use this information while it's processing user input with the `GM_HANDLEINPUT` method. When it is time for the active gadget to become inactive, Intuition will send the gadget a `GM_GOINACTIVE` message. The gadget can clean up its precalculations and cache in the `GM_GOINACTIVE` method. For more information on `GM_GOINACTIVE`, see its description below.

1.62 B / gadgetclass / New Methods: GM_HANDLEINPUT

This method asks an active gadget to handle an input event. After Intuition gets an OK to make this gadget object active (see the `GM_GOACTIVE` method above), Intuition starts sending input events to the gadget. Intuition sends them in the form of a `GM_HANDLEINPUT` message. This method uses the same custom message structure as `GM_GOACTIVE` (see the `gpInput` structure above).

The information in the `gpInput` structure is the same for `GM_HANDLEINPUT` as it is for `GM_GOACTIVE`. The only difference is that the `GM_HANDLEINPUT` message's `gpi_IEvent` can never be `NULL`. It always points to an `InputEvent` structure.

The gadget has to examine the incoming `InputEvents` to see how its state may have changed. For example, a string gadget processes key presses, inserting them into the gadgets string. When the string changes, the gadget has to update its visual state to reflect that change. Another example is the prop gadget. If the user picks up the prop gadget's knob, the prop gadget has to track the mouse to process changes to the gadget's internal values. It does this by processing `IECLASS_RAWMOUSE` events.

If the `GM_HANDLEINPUT` method needs to do some rendering, it must call `ObtainGIRPort()` on the `GM_HANDLEINPUT` message's `gpi_GInfo` to get a pointer to a `RastPort`. To relinquish this `RastPort`, the `GM_HANDLEINPUT` method must call `ReleaseGIRPort()`. The `GM_HANDLEINPUT` method has to allocate and release this `RastPort`, it cannot be cached in the `GM_GOACTIVE` method.

The return value from `GM_HANDLEINPUT` informs Intuition if the gadget wants to remain active. The return values for the `GM_HANDLEINPUT` are similar to `GM_GOACTIVE`. The gadget tells Intuition that it wants to remain active by returning `GMR_MEACTIVE`. A gadget tells Intuition it wants to become inactive by returning one of the "go inactive" return values:

`GMR_NOREUSE` Tells Intuition to throw away the `gpInput.gpi_IEvent` `InputEvent`.

`GMR_REUSE` Tells Intuition to reprocess the `gpInput.gpi_IEvent` `InputEvent` after deactivating the gadget.


```
};
```

The `gpgi_Abort` field contains either a 0 or 1. If it is 0, the gadget became inactive at its own request (because the `GM_HANDLEINPUT` method returned something besides `GMR_MEACTIVE`). If `gpgi_Abort` is 1, Intuition aborted this active gadget. Some cases where Intuition aborts a gadget include: the user clicked in another window or screen, an application removed the active gadget with `RemoveGLList()`, and an application called `ActivateWindow()` on a window other than the gadget's window.

If the gadget allocated any resources to cache or precalculate information in the `GM_GOACTIVE` method, it should deallocate those resources in this method.

1.64 B / gadgetclass / Changed Methods: OM_NEW

This method allocates space for an embedded struct `Gadget` (defined in `<intuition/intuition.h>`) and initializes some of the attributes defined by `gadgetclass`.

1.65 B / gadgetclass / Changed Methods: OM_NOTIFY

This method tells a gadget to send an `OM_UPDATE` message to its target object. Boopsi gadgets have a function similar to `icclass` objects--each gadget can have an `ICA_TARGET` and `ICA_MAP` in order to notify some target object of attribute changes. When a Boopsi gadget sends an `OM_NOTIFY` message, it always includes its `GA_ID`. This makes it easy for an application to tell which gadget initially sent the `OM_NOTIFY`. See the description of `icclass`'s `OM_NOTIFY` and `OM_UPDATE` and the `rootclass`'s `OM_NOTIFY` and `OM_UPDATE` methods for more details.

1.66 B / gadgetclass / Attributes: GA_Previous (I)

This attribute is used to insert a new gadget into a list of gadgets linked by their `Gadget.NextGadget` field. When the `OM_NEW` method creates the new gadget, it inserts the new gadget into the list following the `GA_Previous` gadget. This attribute is a pointer to the gadget (struct `Gadget *`) that the new gadget will follow. This attribute cannot be used to link new gadgets into the gadget list of an open window or requester, use `AddGLList()` instead.

1.67 B / gadgetclass / Attributes: ICA_TARGET (IS)

This attribute stores the address of the gadget's target object. Whenever the gadget receives an `OM_NOTIFY` message, it sends an `OM_UPDATE` message to its target. If the gadget has an attribute mapping list (see the `ICA_MAP` attribute below), it also maps the IDs from the `OM_NOTIFY` message.

If the value of ICA_TARGET is ICTARGET_IDCMP, the gadget sends an IDCMP_IDCMPUPDATE IntuiMessage to its window. See the rootclass description of OM_UPDATE for more information.

1.68 B / gadgetclass / Attributes: ICA_MAP (IS)

This attribute points to a tag list of attribute mappings which the gadget uses to change the attribute IDs of an OM_UPDATE's attribute/value pairs. For example, if a gadget had the following ICA_MAP:

```
struct TagItem map[] =
{
    {PGA_Top, STRINGA_LongVal},
    {MYATTR, MYNEWATTR},
    {TAG_END, }
};
```

before it sends an OM_UPDATE to its ICA_TARGET, the gadget scans through the OM_UPDATE message's attribute/value pairs looking for the PGA_Top and MYATTR attributes. If it finds the PGA_Top attribute, it changes PGA_Top to STRINGA_LongVal. Likewise, if the gadget finds the MYATTR attribute, it changes MYATTR to MYNEWATTR. The gadget does not disturb the attribute's value, only its ID.

1.69 B / gadgetclass / Attributes:GA_Left, GA_Top, GA_Width, GA_Height (IS)

These attributes correspond to the Gadget structure's LeftEdge, TopEdge, Width, and Height fields. Setting these clears the "gadget relative" flags (below).

1.70 B // GA_RelRight, GA_RelBottom, GA_RelWidth, GA_RelHeight (IS)

These attributes correspond to the Gadget structure's LeftEdge, TopEdge, Width, and Height fields. Setting any of these attributes also sets the corresponding "relative" flag in the Gadget structure's Flags field (respectively, GFLG_RELRIGHT, GFLG_RELBOTTOM, GFLG_RELWIDTH, and GFLG_RELHEIGHT). Note that the value passed in this attribute is normally a negative LONG. See the "Intuition Gadgets" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information on these flags.

1.71 B / gadgetclass / Attributes:GA_IntuiText, GA_Text, GA_LabelImage (IS)

These attributes correspond to one field in the object's embedded Gadget structure--the GadgetText field. Setting any of these attributes copies the attribute's value blindly into the GadgetText field. In addition, setting GA_Text also sets the GFLG_LABELSTRING flag in Gadget.Flags and

setting `GA_LabelImage` sets the `GFLG_LABELIMAGE` flag in `Gadget.Flags`. The `GA_IntuiText` attribute must be an `IntuiText` pointer, as with old-style gadgets. `GA_Text` takes a pointer to a NULL-terminated string (`UBYTE *`). `GA_LabelImage` takes a pointer to a (Boopsi) image. Note that most gadget classes do not support `GA_Text` and `GA_LabelImage`. See the description of specific gadget classes for more details.

1.72 B / gadgetclass / Attributes: `GA_Image` (IS)

This attribute is a pointer to either a Boopsi image or a Release 1.3-compatible Intuition image. This attribute corresponds to the Gadget's `GadgetRender` field. The gadgetclass dispatcher will not dispose of this image when it disposes of the gadget object.

1.73 B / gadgetclass / Attributes: `GA_Border` - `GA_SpecialInfo` (IS)

`GA_Border`, `GA_SelectRender`, `GA_ID`, `GA_UserData`, `GA_SpecialInfo` (IS) - These attributes correspond to the similarly named fields in the Gadget structure embedded in the gadget object.

1.74 B / gadgetclass / Attributes: `GA_GZZGadget`, `GA_SysGadget` (IS)

These are boolean attributes that correspond to the flags in the object's `Gadget.GadgetType` field. If the value passed with the attribute is `TRUE`, the corresponding flag in `Gadget.GadgetType` is set. If the value passed with the attribute is `FALSE`, the corresponding flag in `Gadget.GadgetType` is cleared. See the `<intuition/intuition.h>` include file or the "Intuition Gadgets" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information.

1.75 B / gadgetclass / Attributes: `GA_Disabled`, `GA_Selected` (IS)

These are boolean attributes that correspond to the similarly named flags in the object's `Gadget.Flags` field. If the value passed with the attribute is `TRUE`, the corresponding flag in `Gadget.Flags` is set. If the value passed with the attribute is `FALSE`, the corresponding flag in `Gadget.Flags` is cleared. See the `<intuition/intuition.h>` include file or the "Intuition Gadgets" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information.

1.76 B / gadgetclass / Attributes: `GA_EndGadget` - `GA_TabCycle` (IS)

GA_EndGadget, GA_Immediate, GA_RelVerify, GA_FollowMouse, (IS)
 GA_RightBorder, GA_LeftBorder, GA_TopBorder, GA_BottomBorder, (IS)
 GA_ToggleSelect, GA_TabCycle (IS) - These are boolean attributes that correspond to the flags in the object's Gadget.Activation field. If the value passed with the attribute is TRUE, the corresponding flag in Gadget.Activation is set. If the value passed with the attribute is FALSE, the corresponding flag in Gadget.Activation is cleared. See the <intuition/intuition.h> include file or the "Intuition Gadgets" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information.

1.77 B / gadgetclass / Attributes: GA_Highlight (IS)

This attribute corresponds to the GFLG_GADGHIGHBITS portion of the gadget's Gadget.Flags field. This attribute can be one of four values (from <intuition/intuition.h>):

GFLG_GADGHCOMP, GFLG_GADGHBOX, GFLG_GADGHIMAGE, GFLG_GADGHNONE

See the "Intuition Gadgets" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information.

1.78 B / gadgetclass / Attributes: GA_SysGType (IS)

This attribute corresponds to the system gadget type portion of the gadget's Gadget.GadgetType fields. This attribute is any one of the following flags (from <intuition/intuition.h>):

GTYP_SIZING, GTYP_WDRAGGING, GTYP_SDRAGGING, GTYP_WUPFRONT,
 GTYP_SUPFRONT, GTYP_WDOWNBACK, GTYP_SDOWNBACK, GTYP_CLOSE

See the "Intuition Gadgets" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information.

1.79 B Boopsi Class Reference / propgclass

Class: propgclass
 Superclass: gadgetclass
 Include File: <intuition/gadgetclass.h>

A Boopsi proportional ("prop") gadget. The Boopsi prop gadget is similar to the conventional prop gadget, but extends its function to make it easier to use. The Boopsi prop gadget keeps its current integer value in its PGA_Top attribute.

New Methods:

None.

Changed Methods:

```
-----
GM_HANDLEINPUT
```

```
Attributes:
```

```
-----
GA_Image (I)          PGA_Freedom (IG)      PGA_Top (ISGNU)
GA_Border (I)        PGA_NewLook (I)      PGA_Visible, PGA_Total (ISU)
GA_Highlight (I)     PGA_Borderless (I)
```

1.80 B / propgclass / Changed Methods: GM_HANDLEINPUT

If the knob position changes sufficiently to change a propgclass object's PGA_Top attribute, the gadget will send an OM_NOTIFY message to itself, which the propgclass dispatcher passes on to the gadgetclass dispatcher for processing (see the rootclass description of OM_NOTIFY and OM_UPDATE for more information).

The OM_NOTIFY message will contain two attribute/value pairs, PGA_Top and GA_ID. While the prop gadget's PGA_Top is in a transitory state (while it is active and the user is moving the prop gadget's knob), the gadget sends interim OM_NOTIFY messages. The interim OM_NOTIFY messages have the OPUF_INTERIM flag of the opUpdate.opu_Flags field set. When the user finishes manipulating the gadget (by letting go of the knob), the gadget sends a final OM_NOTIFY message, which has a cleared OPUF_INTERIM flag.

1.81 B / propgclass / Attributes: GA_Image (I)

Propgclass intercepts this gadgetclass attribute before passing it on to gadgetclass. This attribute passes an image for the prop gadget's knob, which gets stored in the propgclass object's Gadget.Image structure. If the propgclass does not get a GA_Image when it creates a prop gadget, the prop gadget's knob defaults to an AUTOKNOB. An AUTOKNOB automatically sizes itself according to how large the range of the gadget is compared to the visible range of the gadget. See the PGA_Visible and PGA_Total attributes for more details.

1.82 B / propgclass / Attributes: GA_Border (I)

Propgclass intercepts this gadgetclass attribute to prevent gadgetclass from setting up a border. If an application tries to set this attribute for a propgclass gadget, the prop gadget turns itself into an AUTOKNOB gadget.

1.83 B / propgclass / Attributes: GA_Highlight (I)

Propgclass intercepts this gadgetclass attribute before passing it on to gadgetclass. It does this to make sure the highlighting is not set to GADGHBOX. GADGHBOX will be converted to GADGHCOMP. See the "Intuition Gadgets" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information on the types of gadget highlighting.

Other gadgetclass attributes are passed along to the superclass.

1.84 B / propgclass / Attributes: PGA_Freedom (IG)

This attribute tells a propgclass object on which axis the gadget's knob is free to move, the horizontal or the vertical. It is either FREEHORIZ or FREEVERT. The default is FREEVERT.

1.85 B / propgclass / Attributes: PGA_NewLook (I)

This is a boolean attribute which corresponds to the PROPNEWLOOK flag PropInfo structure's Flags field (defined in <intuition/intuition.h>). If this attribute is TRUE, the new propgclass object will use Release 2 imagery rather than the Release 1.3 imagery.

1.86 B / propgclass / Attributes: PGA_Borderless (I)

This is a boolean attribute which corresponds to the PROPBORDERLESS flag of the PropInfo structure's Flags field (defined in <intuition/intuition.h>). If this attribute is TRUE, the new propgclass object will not have a border around it. In an AUTOKNOB propgclass gadget, if the PROPNEWLOOK flag is set as well (see the PGA_NewLook attribute), the knob will have a 3D appearance.

1.87 B / propgclass / PGA_Top (ISGNU), PGA_Visible, PGA_Total (ISU)

These attributes replace the Pot and Body variables of the Release 1.3 prop gadget. They are based on the use of proportional gadgets to control scrolling text. When scrolling 100 lines of text in a 25 line visible window, you would set PGA_Total to 100, PGA_Visible to 25, and watch PGA_Top run from 0 to 75 (the top line of the last page).

If the user clicks in the prop gadget but not on the knob, the entire knob jumps one "page" (the size of the visible area minus one, PGA_Visible-1). The page jump will leave an overlap of one line, unless the value PGA_Visible is 1, in which case the prop gadget acts as an integer numeric slider, sliding from 0 to PGA_Total - 1.

Note that when PGA_Top changes, the gadget sends itself an OM_NOTIFY message about this attribute change (see the propgclass description of GM_HANDLEINPUT for more information). All three of these attributes have OM_UPDATE access, so they can be controlled from other objects.

1.88 B Boopsi Class Reference / strgclass

Class: strgclass
 Superclass: gadgetclass
 Include File: <intuition/gadgetclass.h>

Intuition compatible string gadgets. The Boopsi string gadget can either be a plain string gadget or an integer string gadget. An integer gadget filters out all characters except those that make up integer values.

New Methods:

None.

Changed Methods:

OM_NEW

Attributes:

STRINGA_LongVal (ISGNU) STRINGA_TextVal (ISGNU)

The remaining strgclass attributes correspond to the flags and fields that the conventional Intuition string gadget uses. See the "STRING GADGET TYPE" section of the "Intuition Gadgets" chapter of the Amiga ROM Kernel Reference Manual: Libraries for more information.

STRINGA_MaxChars, STRINGA_Buffer, (I)
 STRINGA_UndoBuffer, STRINGA_WorkBuffer (I)
 STRINGA_BufferPos, STRINGA_DispPos (ISU)
 STRINGA_AltKeyMap (IS)
 STRINGA_Font (IS)
 STRINGA_Pens (IS)
 STRINGA_ActivePens (IS)
 STRINGA_EditHook (I)
 STRINGA_EditModes (IS)
 STRINGA_ReplaceMode, STRINGA_FixedFieldMode, STRINGA_NoFilterMode (IS)
 STRINGA_Justification (IS)
 STRINGA_ExitHelp (IS)

1.89 B / strgclass / Changed Methods: OM_NEW

This method sets up the string gadget's StringInfo and StringExtend structures. It allocates a buffer if needed and will use shared data buffers for UndoBuffer and WorkBuffer if the MaxChars is less than SG_DEFAULTMAXCHARS (128). Default text pens are: Foreground = 1, Background = 0. See the rootclass description of the OM_NEW method for more details.

1.90 B / strgclass / Attributes: STRINGA_LongVal (ISGNU)

This attribute tells strgclass that this gadget is an integer string gadget and the new value of the integer is this attribute's value.

1.91 B / strgclass / Attributes: STRINGA_TextVal (ISGNU)

This attribute tells strgclass that this gadget is a plain string gadget. The attribute points to a string which the object copies into the string gadget's current string value buffer.

When a strgclass gadget's internal STRINGA_LongVal or STRINGA_TextVal value changes (usually because the user manipulated the gadget), it sends itself an OM_NOTIFY message. The OM_NOTIFY message will contain two attribute/value pairs, GA_ID and either STRINGA_LongVal or STRINGA_TextVal (depending on what kind of strgclass gadget it is). Strgclass gadgets only send a final OM_NOTIFY message (one's with the OPUF_INTERIM flag of the opUpdate.opu_Flags field cleared).

1.92 B / strgclass / Attributes: STRINGA_MaxChars - STRINGA_WorkBuffer (I)

STRINGA_MaxChars, STRINGA_Buffer, STRINGA_UndoBuffer, STRINGA_WorkBuffer (I) - Specify various buffers defined for string gadgets and extended string gadgets. If your value of STRINGA_MaxChars is less than SG_DEFAULTMAXCHARS (128 for now), then this class can provide all these buffers for you. Note that UndoBuffer and WorkBuffer can be shared by many separate gadgets, providing they are as large as the largest MaxChars they will encounter.

1.93 B / strgclass / Attributes: STRINGA_BufferPos, STRINGA_DispPos (ISU)

The attributes tell the object its cursor and scroll position.

1.94 B / strgclass / Attributes: STRINGA_AltKeyMap (IS)

This attribute corresponds to the StringInfo.AltKeyMap field.

1.95 B / strgclass / Attributes: STRINGA_Font (IS)

This attribute points to an open TextFont structure that the string gadget uses for rendering its text.

1.96 B / strgclass / Attributes: STRINGA_Pens (IS)

Pen numbers, packed as two WORDs into a longword, for rendering gadget text.

1.97 B / strgclass / Attributes: STRINGA_ActivePens (IS)

Optional pen numbers, packed as two WORDs into a longword, for rendering gadget text when the gadget is active.

1.98 B / strgclass / Attributes: STRINGA_EditHook (I)

Custom string gadget edit hook.

1.99 B / strgclass / Attributes: STRINGA_EditModes (IS)

Value taken from flags defined in <intuition/cghooks.h> for initial editing modes.

1.100 B / strgclass / STRINGA_ReplaceMode - STRINGA_NoFilterMode (IS)

STRINGA_ReplaceMode, STRINGA_FixedFieldMode, STRINGA_NoFilterMode (IS) - These three are independent Boolean equivalents to the individual flags that you can set for STRINGA_EditModes.

1.101 B / strgclass / Attributes: STRINGA_Justification (IS)

Takes the values STRINGCENTER, STRINGRIGHT, and STRINGLEFT (which is 0).

1.102 B / strgclass / Attributes: STRINGA_ExitHelp (IS)

Set this if you want the gadget to exit when the "Help" key is pressed. Look for a code of 0x5F, the rawkey code for help.

1.103 B Boopsi Class Reference / buttongclass

```
Class:                buttongclass
Superclass:           gadgetclass
Include File:         <intuition/gadgetclass.h>
```

A class of button gadget that continually sends interim OM_UPDATE messages to its target while the user holds down the button. The button sends a final OM_UPDATE message when the user lets go of the button. The imagery for these objects is not built directly into the gadget. Instead, a buttongclass object uses a Boopsi image object, which it gets from its GA_Image attribute.

New Methods:

None.

Changed Methods:

GM_HITTEST GM_HANDLEINPUT GM_RENDER

Attributes:

GA_IMAGE (IS)

1.104 B / buttonclass / Changed Methods: GM_HITTEST

This method gets passed over to the button's image for processing. The button's IM_HITTEST checks for the hit.

1.105 B / buttonclass / Changed Methods: GM_HANDLEINPUT

This method continuously issues OM_NOTIFY messages for each IECLASS_TIMER event it gets. The OM_NOTIFY message's OPUF_INTERIM flag (from opUpdate.opu_Flags) is set for all but the final OM_NOTIFY.

The OM_NOTIFY message contains one attribute/value pair, GA_ID. If the pointer is currently over the gadget image, the value of this attribute/value pair is the gadget's actual GA_ID (from the Gadget.GadgetID field). If the pointer isn't over the image, the value is the negative of the gadget's actual GA_ID.

1.106 B / buttonclass / Changed Methods: GM_RENDER

All rendering is passed along to the GadgetRender.Image (the GA_Image attribute). This method can tell its image to render in any of four image states: IDS_INACTIVESELECTED, IDS_INACTIVENORMAL, IDS_SELECTED, or IDS_NORMAL.

1.107 B / buttonclass / Attributes: GA_Image (IS)

This attribute points to the gadget's Boopsi image. Changing this attribute will cause the gadget to refresh its imagery.

1.108 B Boopsi Class Reference / frbuttonclass

```

Class:          frbuttonclass
Superclass:    buttonclass
Include File:   <intuition/gadgetclass.h>

```

This is a special class of button gadget that puts a Boopsi framing image around some other display element. This display element can be one of three things: plain text from the GA_Text attribute, an IntuiText from the GA_IntuiText attribute, or an Image from the GA_LabelImage attribute.

The user activates the gadget by clicking within the bounds of the gadget's framing image, which it gets from the GA_Image attribute. Usually the framing image is an instance of an image class that supports the IM_FRAMEBOX method (like frameiclass). If the framing image supports the IM_FRAMEBOX method, the frbuttonclass object centers the frame image around the display element. See the imageclass description of IM_FRAMEBOX for more information.

New Methods:

None.

Changed Methods:

OM_NEW GM_HITTEST GM_RENDER

Attributes:

GA_Width, GA_Height (S)
 GA_DrawInfo (I)
 GA_Text, GA_IntuiText, GA_LabelImage (IS)

1.109 B / frbuttonclass / Changed Methods: OM_NEW

When this class creates an object, it sets the object's embedded Gadget.Width and Gadget.Height fields according to the frame image in GA_Image. If the GA_Image understands the IM_FRAMEBOX method, the gadget asks the GA_Image what its dimensions would be if it had to surround the display element. If the GA_Image does not support IM_FRAMEBOX, it just copies the GA_Image image's width and height into the Gadget structure.

1.110 B / frbuttonclass / Changed Methods: GM_HITTEST

The gadget delegates this method to the framing image's IM_HITFRAME method.

1.111 B / frbuttonclass / Changed Methods: GM_RENDER

For this method, the frbuttonclass object first draws the framing image by sending the image an IM_DRAWFRAME message. The object then draws its display element.

1.112 B / frbuttonclass / Attributes: GA_Width, GA_Height (S)

These attribute correspond to the gadget's Width and Height fields. If the framing image supports IM_FRAMEBOX, changing these resizes the framing image. The framing image re-centers itself around the display element as best it can, and the frbuttonclass gadget re-renders the whole itself.

1.113 B / frbuttonclass / Attributes: GA_DrawInfo (I)

This attribute passes a pointer to a valid DrawInfo structure. If the frbuttonclass gadget is going to frame plain text (passed to it in the GA_Text attribute), the frbuttonclass gadget requires a DrawInfo structure to properly calculate the dimensions of the text.

1.114 B / frbuttonclass / Attributes:GA_Text,GA_IntuiText,GA_LabelImage (IS)

These attributes tell the frbuttonclass object what kind of imagery to use as its display element. See their description in the gadgetclass entry for more information.

1.115 B Boopsi Class Reference / groupgclass

```
Class:                groupgclass
Superclass:           gadgetclass
Include File:         <intuition/gadgetclass.h>
```

This is a class of objects that maintains an internal list of gadgets. Its purpose is to make it easier to layout a group of gadgets. Any gadgets that are a member of a groupgclass object are rendered relative to the groupgclass object's GA_Left and GA_Top attributes. As new gadgets are added to the groupgclass object, the groupgclass object's dimensions grow to enclose the new gadgets. When the groupgclass object receives an OM_DISPOSE message, it not only disposes of itself, it also disposes of all the gadgets in its list. Groupgclass does not support the gadget relative flags (GA_RelWidth, GA_RelHeight, GA_RelBottom, and GA_RelRight).

New Methods:

None.

Changed Methods:

```
OM_SET                GM_HITTEST
OM_ADDMEMBER          GM_RENDER
OM_REMEMBER           GM_GOACTIVE/GM_GOINACTIVE/GM_HANDLEINPUT
OM_DISPOSE
```

Attributes:

```
GA_Left, GA_Top (IS)
```

1.116 B / groupgclass / Changed Methods: OM_SET

This method passes most attributes to the superclass, but propagates changes in position to its members appropriately. Also, GA_Width and GA_Height are calculated from the position and dimension of the membership.

1.117 B / groupgclass / Changed Methods: OM_ADDMEMBER

This method adds a gadget to the group object's list. The group object will increase the size of its select box to include the new gadget's select box. The group object moves the new member to an absolute location (by changing the new member's GA_Left and GA_Top attributes) relative to the group object's upper-left corner. Note that all members of the groupgclass object will be deleted by OM_DISPOSE.

1.118 B / groupgclass / Changed Methods: OM_REMEMBER

This method removes a gadget added to the group object's list with OM_ADDMEMBER. Note that all members of the groupgclass object will be deleted by OM_DISPOSE.

1.119 B / groupgclass / Changed Methods: OM_DISPOSE

This method disposes of the groupgclass object and all its member gadgets.

1.120 B / groupgclass / Changed Methods: GM_HITTEST

This method works its way through the list of group members, sending each a GM_HITTEST message, looking for the first member in the list that says it has been hit. This member gadget becomes the active member.

1.121 B / groupgclass / Changed Methods: GM_RENDER

This method sends a GM_HITTEST message to each of its members.

1.122 B / groupgclass / Changed: GM_GOACTIVE/GM_GOINACTIVE/GM_HANDLEINPUT

This method passes the message to the active member's dispatcher for processing. For GM_GOINACTIVE and GM_HANDLEINPUT, the coordinates passed to the member's dispatcher in the message's gpi_Mouse.X and gpi_Mouse.Y fields are translated so that they are relative to the gadget's upper-left corner.

1.123 B / groupgclass / Attributes: GA_Left, GA_Top (IS)

These attributes correspond to the embedded Gadget.LeftEdge and Gadget.TopEdge fields. Setting these attributes in groupgclass object causes it to change its position as well as the position of each of the gadgets that have been added to the group gadget.
