
# $T_EXdraw$

PostScript Drawings from T<sub>E</sub>X Edition 1.4a July 1992



## 1 Introduction

TEX is a powerful typesetting program written by D. Knuth. It allows for complex text layouts but by itself lacks a general graphics capability. However, when coupled with an appropriate printing program, external graphics files can be inserted into the printed document. In this mode, TEX is instructed to leave space for a drawing. The drawing is inserted at print time by the print program. The TEXdraw macros generate the external graphics file from within TEX and generate the instructions to the the print program to position the graphics at the appropriate position on the page. In this way, TEXdraw produces drawings from within TEX.

TEX draw consists of a set of TEX macros that create line drawings and other figures. The drawing primitives include solid lines, patterned lines, Bezier curves, circles and arrows. Other commands allow for the filling of a region with a gray level. The drawing commands generate PostScript code. This limits TEX draw to systems which use PostScript printers. TEX draw also provides commands to position TEX text, including mathematics, on the drawing. The final drawing, with text and graphics, can be positioned on the page like any other TEX box.

TEXdraw generates an intermediate PostScript file for the drawing commands. This file is included in the final printout by invoking the \special command provided by TEX. The present version of TEXdraw uses the \special syntax recognized by the program 'dvips' by Tom Rokicki. The program 'dvips' is used to process the device independent (dvi) output file produced by TEX. The program 'dvips' combines the PostScript drawing commands from the intermediate PostScript file and the text positioning information from the dvi file into a single PostScript file which can be printed on a PostScript printer. The program 'dvips' also automatically scales the PostScript figure to compensate for changes to the TEX magnification, so that TEX text and the PostScript graphics remain aligned. The structure of TEXdraw is such that only minor changes need be made to allow it to be used with other dvi to PostScript drivers that allow for the inclusion of PostScript files, at least at nominal magnification.

The basic TEXdraw macros provide only simple drawing commands. However, TEXdraw provides a drawing segment environment which allows parameter changes and coordinate scaling changes to be kept local to the drawing segment. This facility, together with TEX's macro capabilities allows one to modularize drawing units and extend TEXdraw by building more complex graphics entities from simpler elements. New user commands can be defined using the tools used to construct the basic TEXdraw commands.

## 1.1 History

The TEXdraw macros have evolved from the TEXgraph macros, written by Michael Ferguson at INRS-Telecommunications, University of Quebec. In its first incarnation, TEXgraph generated output for a QMS (QUIC graphics language) laser printer. A later version wrote PostScript output directly to the dvi file for subsequent printing by a modified version of the 'dvialw' dvi to PostScript driver.

The functional interface for TEXdraw is largely based on TEXgraph. However, TEXdraw writes PostScript commands to an intermediate file. This file is a PostScript file which can be printed on its own, although the position of the drawing may be offset with respect to the the printed page. The intermediate file is printed as part of the document, correctly positioned using the \special command mechanism.

## 1.2 Distribution information

The TEXdraw routines are provided free of charge without warranty of any kind. Note that the TEXdraw routines are copyrighted. They may be distributed freely provided that the recipients also acquire the right to distribute them freely. The notices to this effect must be preserved when the source files are distributed.

## 2 Using the T<sub>E</sub>Xdraw Commands

The TEXdraw macros (commands) are defined in file 'texdraw.tex'. These macros enable the TEXdraw environment within the TEX program. The following sections describe the basic commands for TEXdraw.

## 2.1 Accessing TeXdraw

From within a TFX file, the user must read in the TFXdraw macros from the file 'texdraw.tex'.

The form of the user command to run the program TEX depends on which version of TEX is being used, and which other macro packages are preloaded as format files. Typically, installations have at least two versions of TEX — plain TEX which includes basic typesetting macros (usually invoked as 'tex') and LaTEX which includes the LaTEX typesetting macros (usually invoked as 'latex'). The TEXdraw macros can be used with plain TEX or with LaTEX. Alternate forms of a few TEXdraw commands for use with LaTEX are introduced later (see Chapter 4 [Using TeXdraw with LaTeX], page 23). The TEX commands, including TEXdraw commands, are processed by TEX to produce a device independent (dvi) file. This file is passed to the program 'dvips' which produces output that can be printed on a PostScript printer. The output from 'dvips' combines the results of the regular TEX typesetting commands with the drawing produced by the TEXdraw commands.

As the T<sub>E</sub>Xdraw commands are processed by T<sub>E</sub>X, an intermediate PostScript file is generated. The intermediate PostScript has a name of the form 'name.ps1'. The name part is derived from the name of the main T<sub>E</sub>X file being processed. If more than one drawing is produced, the digit in the file name extension is incremented.<sup>1</sup>

<sup>&</sup>lt;sup>1</sup> After the ninth PostScript file, the name of the intermediate PostScript file takes the form 'name.p10', with the number increasing from 10 with each file.

The high-level user interface to TEXdraw consists of three TEX macros. The basic macros to invoke TEXdraw are the \btexdraw and \etexdraw commands. The TEXdraw commands to produce a drawing are inserted between the \btexdraw and \etexdraw macros. These macros create a TEX box of appropriate size containing the drawing generated by the TEXdraw commands. The TEXdraw box can be positioned in a document like any other TEX box.

The third macro is a convenience form which centers the box generated by TEXdraw. The vertical space taken up is equal to the vertical size of the drawing. It is invoked as \centertexdraw \lambda...\rangle. This macro is normally used in vertical mode (between paragraphs). A \par command (a blank line will do also) before a \centertexdraw command will terminate horizontal mode and return to vertical mode.

#### \btexdraw

Start a TFXdraw drawing. The drawing is terminated with an \etexdraw command.

### \etexdraw

End a TEXdraw drawing started with a **\btexdraw** command. The resulting TEXdraw drawing is placed in a box with height equal to the height of the drawing and width equal to the width of the drawing. The depth of the box is zero.

#### \centertexdraw { ... }

Center a TEXdraw box. The argument contains TEXdraw commands. The resulting box has the horizontal size \hsize and height equal to the height of the drawing.

## 2.2 Command syntax

Generally TEXdraw commands that take a single argument need a terminating blank or newline after the argument. Arguments that are self-delimiting, such as coordinates within parentheses and text within braces, do not need the terminating blank. However, even when not needed by the defining syntax of the command, blanks following command arguments are allowed and ignored within the TEXdraw environment.


On entering the T<sub>E</sub>Xdraw environment, T<sub>E</sub>X is in internal vertical mode (vertical mode inside a \vbox). In this mode, spaces can be placed freely between commands. However, any other extraneous input not specifically intended for a T<sub>E</sub>Xdraw command is disallowed.

Blank lines are interpreted as paragraph breaks, equivalent to a \par command. The TEXdraw macro \centertexdraw is defined with the \long attribute to allow \par commands and blank lines to be interspersed between TEXdraw commands. The \btexdraw and \etexdraw commands

also allow \par command and blank lines to be included. Note, however, that enclosing macros may not be declared to be \long and hence may not allow blank lines as part of their argument.

## 2.3 T<sub>E</sub>Xdraw coordinates

The TEX draw coordinate system has increasing x to the right and increasing y upward. The coordinates (without the unit) are floating point numbers. Integer values can be written without a decimal point. The size of the drawing is determined by the maximum excursions of the coordinates specified in TEX draw commands.



Consider the following example of TEXdraw commands to draw a simple figure.

```
\centertexdraw{
  \drawdim cm \linewd 0.02
  \move(2 2) \lvec(3 3) \lvec(2 4) \lvec(1 3) \lvec(2 2)
  \textref h:C v:C \htext(2 3){$\sum \rho_n$}
}
```



This drawing uses units of centimetres, with a line width of 0.02 cm. The x coordinate ranges between 1 and 3 while the y coordinate ranges between 2 and 4. When included into a document, the size of the drawing is 2 cm by 2 cm. The drawing is placed in a TEX box, with the lower lefthand corner of the box corresponding to TEXdraw coordinate (1 2) and the upper righthand corner at (3 4). The \centertexdraw command horizontally centers the drawing. The \textref command controls the centering of the text. The text in this drawing is centered (both horizontally and vertically) at the coordinate (2 3).

## 2.4 Coordinate specification

Coordinates are specified within parentheses, with blanks (but no comma) between the values. Leading blanks and trailing blanks are permitted within the parentheses. The coordinates refer to units, which are specified by the \drawdim command. The default is inches, but any valid TEX dimension unit can be specified. Symbolic specification of saved coordinate values will be discused later (see Section 3.3 [Saving positions], page 18).

#### \drawdim dim

Set the units to dim. The argument dim can be any valid T<sub>E</sub>X dimension unit. The units are used to interpret coordinate values. Examples of valid units: cm, mm, in, pt, and bp.

Examples of coordinate and scaling specifications:

### \drawdim {cm} \move(22)

Set the units to centimetres, move to a position 2 cm to the right and 2 cm up from the origin of the drawing coordinate system.

#### \drawdim bp

Set the units to big points.

Examples of acceptable coordinate specifications.

## 2.5 Line vectors

TEXdraw implements moves, line vectors and arrow vectors. There are both absolute and relative motion versions of these vector commands. TEXdraw maintains a current position. Lines are drawn from the current position to a new coordinate, with the new coordinate becoming the new current position. An explicit move can be used to establish an initial current position. The position (0 0) is used if there is no move to an initial current position.

The \move and \rmove commands establish a new current position without drawing a line. The \lvec and \rlvec commands draw a line from the current position to a new position, which then becomes the new current position. The \avec and \ravec commands draw a line with an arrowhead from the current position to a new coordinate, which then becomes the new current position. The tip of the arrow is at the new current position. The direction of the arrow follows the direction of the line. Since this direction is undefined for zero length vectors, these are not

allowed. Zero length arrow vectors will generate a PostScript print error: undefinedresult. For any non-zero length vector, the full size arrowhead is drawn, even if that arrowhead is longer than the line length.

The absolute motion versions of these commands specify the coordinate of the final position.

#### \move $(x \ y)$

Move to coordinate (x y). The new current position is (x y).

### $\label{eq:lvec} \exists x \ y$

Draw a line from the current position to coordinate (x y). The new current position is (x y).

### $\avec(x y)$

Draw a line with an arrowhead from the current position to  $(x \ y)$ . The new current position is  $(x \ y)$ . The arrowhead is aligned with the line, with the tip at  $(x \ y)$ .

The relative motion versions of these commands interpret the coordinates as displacements relative to the current position. Given the displacements (dx dy) as a parameter, each of the relative motion commands moves dx units in the x direction and dy units in the y direction.

### $\t$ \rmove $(dx \ dy)$

Move from the current position, dx units in the x direction and dy units in the y direction. The final position becomes the new current position.

### 

Draw a line from the current position, dx units in the x direction and dy units in the y direction. The final position becomes the new current position.

#### 

Draw a line with an arrowhead from the current position, dx units in the x direction and y units in the y direction. The final position becomes the new current position. The arrowhead is aligned with the line, with the tip at the new current position.

Lines can be customized with commands to change the line width, line pattern and line gray level rendition. In addition, commands for changing the type and size of the arrowhead are available.

#### \linewd width

Set the line width to width units. Initially width is 0.01 inches (corresponding to 3 pixels at 300 pixels to the inch).

## \lpatt (pattern)

Set lines to have the pattern (pattern). A pattern is a sequence of on/off lengths separated by blanks enclosed in parentheses. The lengths alternately specify the length of a dash and the length of a gap between dashes. Each length is interpreted using the current scaling and drawing units. The pattern is used cyclically. The empty pattern signifies a solid line. The initial line pattern is a solid line, corresponding to the empty pattern \lambdapatt ().

## \setgray level

Set the gray level of lines. Gray levels are real values from 0 (black) through intermediate values (gray) to 1 (white). The initial gray level is 0 corresponding to black.

## $\arrowheadtype t: type$

Set the arrowhead type to type, where type is one of F, T, W, V, or H. There are two kinds of arrowheads. The first kind is a triangle. There are 3 variants: type T is an empty triangle, type F is a filled triangle (using the current gray level), type W is a triangle filled with white. The second kind of arrowhead is an open ended Vee. There are 2 variants: type V has the stem continue to the tip, type H has the stem stop at the base of the arrowhead. The initial arrowhead type is T.


### \arrowheadsize 1: length w: width

Set the arrowhead size to be *length* units long and *width* units wide. The width is measured across the "base" of the arrowhead. The initial arrowhead size has a *length* of 0.16 inches and a *width* of 0.08 inches.

Note that the lines which outline the arrowhead will be drawn with the same line pattern used for the stem. Normally, arrow vectors are drawn with the line pattern set for a solid line. Note that the fill level used for the F variant of the arrowhead uses the same gray level as used for lines. The difference between the T variant and the W variant only shows up if the arrowhead is placed over non-white areas of the drawing. The W variant obliterates the area under the arrowhead.

Examples of line parameter and arrowhead settings are shown in the following code.

```
\centertexdraw{
  \drawdim in
  \linewd 0.03 \setgray 0.6 \arrowheadtype t:F \avec(0 0.5)
  \linewd 0.01 \setgray 0 \arrowheadtype t:V \avec(0.5 0.5)
  \linewd 0.015 \linewd 0.067 0.1) \livec (1 0)
  \linewd 0.02 \linewd (1 \arrowheadtype t:T \avec(1.5 0.5))
  \arrowheadtype t:H \avec(2.0 0.5)
  \setgray 0.4 \arrowheadtype t:W \avec(3.0 0)
}
```



## 2.6 TeX text

Text may be superimposed on the drawing. The text argument of the \htext command is in horizontal mode. This text can be ordinary text, math mode expressions, or even more complicated boxes consisting of tables and the like. The resulting TEX text is placed in a box. The reference point of the box can be chosen to be one of nine locations: horizontally left, center or right; vertically top, center or bottom. The \htext command takes one of two forms.

\htext (x y) {text}
\htext {text}

The first form of this command places the  $T_EX$  text text horizontally with the text reference point at the coordinate  $(x \ y)$ . The new current position is  $(x \ y)$ . The second form of this command places the  $T_EX$  text text horizontally with the text reference point at the current position. The text reference point is set with the \textref command.

Text can be placed vertically using the \vtext command. The text argument is in horizontal mode. The TEX text is placed in a box and then rotated counterclockwise. The reference point is the point in the box, before rotation of the text.

\vtext (x y){text}
\vtext {text}

The first form of this command places the TEX text text vertically with the text reference point at the coordinate (x y). The new current position is (x y). The second form of this command places the TEX text text vertically with the text reference point at the current position. In both cases, the TEX text is placed in a box and the box is rotated counterclockwise by 90 degrees about the text reference point. The text reference point is set with the \textref command.

Text can be placed at an arbitrary angle using the \rtext command. The text argument is in horizontal mode. The TEX text is placed in a box and then rotated counterclockwise. The reference point is the point in the box, before rotation of the text.

\rtext td:angle (x y){text}
\rtext td:angle {text}

The first form of this command places the  $T_EX$  text text at an angle with the text reference point at the coordinate  $(x \ y)$ . The new current position is  $(x \ y)$ . The


 $T_{\rm E}X{
m draw}$ 

second form of this command places the TEX text at an angle with the text reference point at the current position. In both cases, the TEX text is placed in a box and the box is rotated counterclockwise by angle degrees about the text reference point. The text reference point is set with the \textref command.

The reference point for subsequent TEX text in a \htext, \vtext or \rtext command is set with the \textref command.

## $\t h-ref v: v-ref$


Set the text reference point for subsequent text commands. The horizontal reference point h-ref is one of L, C or R (left, center or right). The vertical reference point v-ref is one of T, C or B (top, center or bottom). For rotated text, the reference point is determined before rotation. The initial text reference point corresponds to textref  $h:L\ v:B$ .



The font used to render the text is determined as for any other TEX text. Normally the font used outside of TEXdraw is in effect. If desired, other fonts can be specified as part of the text. Any font changes within a TeXdraw text command remain local to that command.

Only the coordinate of the text reference point in a \htext, \vtext or \rtext command is used in calculating the size of the drawing. This means that text itself can spill outside of the drawing area determined by TEXdraw. The area of the drawing can be increased to enclose the text by issuing additional \move commands.

Superimposed on this example is a shaded region showing the limits of the TEXdraw box as determined by the coordinates specified.



## 2.7 Circles, ellipses and arcs

TEXdraw supplies commands to generate circles, ellipses and arcs. There are two forms of the circle command. The \lcir draws a circle of given radius. The \fcir draws a filled circle. In the latter case, the circle is filled by a specified gray level. For the filled circle, the line defining the circumference of the circle is not drawn. Note that the gray level area filled in by the \fcir command is opaque, even if the fill is chosen to be white. For either form of the circle command, the drawing size is increased if necessary to contain the circle.

The **\lellip** command generates an ellipse specified by the radius of the ellipse in the x direction and the radius of the ellipse in the y direction. The ellipse is symmetrical about horizontal and vertical lines drawn through the current point. The drawing size is increased if necessary to contain the ellipse.

The \larc command generates a counterclockwise arc specified by a start angle in degrees and an end angle in degrees. The center of the arc is the current position. Only the arc is drawn, not the line joining the center to the beginning of the arc. Note that the \larc command does not affect the size of the drawing.

#### \lcir r:radius

Draw a circle with center at the current position. The radius is specified by radius. This command draws a line along the circumference of the circle. The drawing size is increased if necessary to contain the circle.

### \fcir f:level r:radius

Draw a filled circle at the current position. The radius is specified by radius. The circle is painted with the gray level specified by level. A gray level of 1 corresponds to white, with decreasing values getting darker. The level 0 is full black. This command does not draw a line along the circumference. The drawing size is increased if necessary to contain the circle.

#### \lellip rx: x-radius ry: y-radius


Draw an ellipse. The center of the ellipse is at the current position. The radius in the x direction is specified by x-radius. The radius in the y direction is specified by y-radius. The drawing size is increased if necessary to contain the ellipse.

### \larc r:radius sd:start-angle ed:end-angle

Draw a counterclockwise arc. The center of the arc is at the current position. The radius is specified by radius. The start and end angles (in degrees) are specified by start-angle and end-angle. This command does not affect the limits (size) of the drawing.

As an example, the following commands draw a filled circle, and superimpose an arc.

```
\centertexdraw{
  \linewd 0.02
  \fcir f:0.7 r:1
  \larc r:1 sd:45 ed:135
  \lvec (+0.707 +0.707) \move (0 0) \lvec (-0.707 +0.707)
}
```



Note that for the arc command, the resulting figure can spill outside of the TEXdraw box as determined by the maximum excursions of the coordinates. Extra moves can be used to compensate for the size of the figure.

## 2.8 Bezier curves

Bezier curves in TEXdraw use 4 reference coordinates, two as the end points and two others to control the shape of the curve. Let the 4 points be  $(x0\ y0)$ ,  $(x1\ y1)$ ,  $(x2\ y2)$  and  $(x3\ y3)$ . The curve starts out tangent to the line joining the first two points and ends up tangent to the line joining the second two points. The control points "pull" at the curve to control the curvature. The amount of pull increases with the distance of the control point from the endpoint.

As the parameter  $\mu$  varies from 0 to 1, the coordinates of the Bezier curve are given by a pair of parametric cubic equations,

$$x(\mu) = (1 - \mu)^3 x 0 + 3\mu (1 - \mu)^2 x 1 + 3\mu^2 (1 - \mu) x 2 + \mu^3 x 3$$
  
$$y(\mu) = (1 - \mu)^3 y 0 + 3\mu (1 - \mu)^2 y 1 + 3\mu^2 (1 - \mu) y 2 + \mu^3 y 3.$$

\clvec  $(x1 \ y1)(x2 \ y2)(x3 \ y3)$ 


Draw a Bezier curve from the current position to the coordinate  $(x3 \ y3)$  which becomes the new current position. The coordinates  $(x1 \ y1)$  and  $(x2 \ y2)$  serve as control points for the curve. Only the last coordinate given is used to update the size of the drawing.

Note that only 3 coordinate pairs are specified. The other point is the current position before the \clvec command is executed. Only the last coordinate specified in the \clvec command is used to determine the extent of the drawing. While the Bezier curve passes through the old current position and the new current position, in general the curve will not reach the intermediate control points. The curve is always entirely enclosed by the convex quadrilateral defined by the two end points and the two control points. Note that the curve may pass outside the limits of the drawing as determined by the end point of the curve.

A simple Bezier curve is produced by the following example.

```
\btexdraw
\move (0 0)
\clvec (0 1)(1 0)(1 1)
\etexdraw
```

This example is the rightmost of the following Bezier curves. The drawings also show the end points and the control points for each curve.



## 2.9 Fill commands

PostScript deals with paths consisting of line segments. The paths can be closed and the interior of the closed region filled. From TEXdraw, paths start with a \move or \rmove command and continue with \lvec, \rlvec or \clvec commands. The TEXdraw fill commands close the path and fill the interior of the closed region. Closing the path means that effectively another \lvec line is drawn from the last point specified to the initial point. TEXdraw provides two forms of the fill command. The \ifill fills the interior of the region with the given gray level. The lines defining the path are not drawn. The \lfill command fills the region defined by the closed path and draws a line along the enclosing path. Note for both forms of the fill command, the gray level used for filling is opaque, even if the gray level is chosen to be white.

#### \lfill f: level


Close the current path, draw the line around the path using the current grey level for lines and paint the interior of the region with specified gray level level. Gray levels are real values from 0 (black) through intermediate values (grays) to 1 (white).

#### \ifill f: level

Close the current path and paint the interior of the region with gray level level. The line around the path is not drawn. Gray levels are real values from 0 (black) through intermediate values (grays) to 1 (white).

The following example draws a "flag" with the interior filled in. The path around the boundary is given in a clockwise order to define a closed path. We could take advantage of the fact that the fill command will close an open path to eliminate one of the \luescript vec commands.

```
\centertexdraw{
\move (0.5 0)
\lvec (0 0.5) \clvec (0.5 0.85)(1 0.65)(1.5 1)
\lvec (2 0.5) \clvec (1.5 0.15)(1 0.35)(0.5 0)
\lfill f:0.8
}
```



In TEXdraw, the \move command always terminates any previous paths and starts a new path. Commands that change line parameters (e.g. \setgray or \lpatt) also terminate paths and start new paths. The circle, ellipse and arc commands do not affect the definition of the current path. The \avec command is not appropriate for defining a path to be filled. It ends a subpath at its tail and begins a new subpath at its tip. Filling a region defined by a path with subpaths is more complicated in that each subpath is closed before filling.

 $T_{\rm E} X draw$ 

## 3 Drawing Segments and Scaling

TEXdraw provides individually scaled segments which can be used to create relocatable drawing modules.

## 3.1 Drawing segments

A TEXdraw drawing segment allows for local modifications of parameters and relative positioning. A TEXdraw segment is delimited by a \bsegment command and an \esegment command. Inside the segment, the initial current position is (0 0). Any changes to parameters such as the gray level and the line width, remain local to the segment. Segments are implemented in TEX using a \begingroup and \endgroup. Segments can be nested.

### \bsegment

Start a drawing segment. The coordinate system is shifted such that the current position corresponds to the coordinate (0 0). Changes to scaling, position and line parameters stay local to the drawing segment.

#### \esegment

End a drawing segment. The current position in effect before the corresponding \bsegment command is restored. The scaling and line parameter values revert to those in effect before the corresponding \bsegment command was invoked.

## 3.2 Drawing paths

Certain subtle interactions occur between drawing segments and fill operations. In PostScript, lines are drawn by first defining a path, then later stroking the path to draw the line. In TEXdraw, this stroking occurs when the line is terminated, say by a \move command. PostScript paths are interrupted by, but continue after a drawing segment. This means that a path started before a segment may not be stroked (drawn) until after the segment ends. Consider the following example.

```
\move (0 0)
\lvec (1 1)
\bsegment
  \move (-0.25 -0.25)
  \fcir f:0.8 r:0.5
\esegment
\move (0 0)
```

A PostScript path is started at (0 0) and continues with a line to (1 1). This path is interrupted by the segment. The filled circle is drawn next. After the segment, the path continues and is not stroked until the \move (0 0) command after the end of the segment. This means that the line appears on top of the filled region.

If the fill operation is to cover the line, the path must be stroked before the fill operation. From TEXdraw, the move commands \move and \rmove, and the end TEXdraw command \etexdraw terminate a path and cause it to be stroked. Within a segment, the end segment command \esegment also terminates and strokes a path. In the example above, the line can be stroked by inserting a move command (such as a \rmove (0 0) which does not affect the position), before the start of the segment.

## 3.3 Saving positions

The \savecurrpos command saves the current position. The saved position is an absolute position, not one relative to a segment. The position saving mechanism is global; the position can be saved within a nested segment and then used outside of the segment. The x and y coordinates of the position are saved separately as named coordinates. The names are of the form \*name, with the leading \* being obligatory. A companion command, \savepos, saves a given coordinate (relative to the current segment) as an absolute symbolic position.

```
\savecurrpos (*px *py)

Save the current position as the absolute position referenced by (*px *py).

\savepos (x y)(*px *py)
```

Save the coordinate position  $(x \ y)$  as the absolute position referenced by (\*px \*py). The coordinate  $(x \ y)$  is interpreted in the normal fashion as a coordinate relative to the current segment, using the current scaling factors and drawing unit.

The symbolic names used to specify a saved position can consist of any characters that are not special to T<sub>E</sub>X, but must start with a \* character. The symbolic names can be used as the

x and/or y coordinate in any command that needs a coordinate. Symbolic coordinates are not normally used with relative motion commands such as \rlvec or \rmove. If used with relative motion, the corresponding displacement is equal to the symbolic coordinate value.

On exit from a segment, the position and graphics state on entry is restored. Any changes to line types, scaling and position are discarded. However, it is sometimes useful alter the position on exit from a segment. The \savepos command allows for the saving of a position within the segment. This position can be restored after the \esegment with a \move command using the saved symbolic position. This approach can be used to build modules which operate in a manner analogous to the basic relative motion line vector commands.

The following example defines a macro which draws a box 0.75 inches wide by 0.5 inches high containing centered text. On leaving the macro the position will be set at a point on the righthand side of the box.

```
\def\tbox #1{\bsegment
      \lvec (0 +0.25) \lvec (0.75 +0.25)
      \lvec (0.75 -0.25) \lvec (0 -0.25) \lvec (0 0)
      \textref h:C v:C \htext (0.375 0){#1}
      \savepos (0.75 0)(*ex *ey)
      \esegment
      \move (*ex *ey)}
```

With this definition, we can treat \tbox in the same way as the basic vector commands, stringing them together to form a block diagram as in this example.

```
\label{eq:local_equation} $$\operatorname{Tavec}(1\ 0) \to \{H(z)\} \rightarrow H(z)$$
```

## 3.4 Scaling coordinates

There are two scale factors available, the unit scale factor and the segment scale factor. The overall scale factor is the product of these two. There are absolute and relative versions of commands to change these scale factors.

 $T_{\rm F}X{
m draw}$ 

The unit scale factor is normally used to affect global scale changes. Changes to the unit scale factor remains local to a segment, but propagate to inferior segments. The default value is unity.

The segment scale factor is used for local scale changes. It remains local to a segment. The segment scale factor is reset to unity on entry into each segment. This means that changes to the segment scale factor do not propagate to inferior segments.

#### \setunitscale scale

Set the unit scaling to *scale*. The argument *scale* is a real number which is used to scale coordinate values. The overall scaling factor is the product of the unit scale factor and the segment scale factor.

#### \relunitscale value

Adjust the unit scale factor by multiplying by *value*. This has the effect of multiplying the overall scale factor by the same factor. The overall scaling factor is the product of the unit scale factor and the segment scale factor.

### \setsegscale scale

Set the segment scale factor. The argument *scale* is a real number which is used to scale coordinate values. The overall scale factor is the product of the unit scale factor and the segment scale factor.

#### \relsegscale value

Adjust the segment scale factor by multiplying by value. This has the effect of multiplying the current overall scale factor by the same factor. The overall scaling factor is the product of the unit scale factor and the segment scale factor.

In addition to the unit scale factor and the segment scale factor, the scaling can be controlled by the choice of drawing units with the command \drawdim (see Section 2.4 [Coordinate specification], page 6).

### \drawdim cm \setunitscale 2.54

Set the units to centimetres scaled by 2.54. Together these commands are effectively the same as \drawdim in.

The segment scale can be used to allow scale changes in segments so that values are in more convenient units. For example suppose dimensions in a segment are multiples of one third of an inch. The segment scale can be set once to make 1 drawing unit equal 0.3333 inches. From that point on, coordinates can be specified with integer values.

The following example defines a macro to draw a rectangular box which is twice as wide as it is high. The width is specified as an argument.

```
\def\mybox #1{\bsegment
     \setsegscale #1
     \lvec (0 +0.25) \lvec (1 +0.25) \lvec (1 -0.25)
     \lvec (0 -0.25) \lvec (0 0)
     \esegment}
```

## 3.5 Drawing size

The effective size of the drawing is determined by the maximum excursions of the coordinates supplied to TEXdraw commands. The minimum and maximum scaled x and y coordinates are tallied. Note that \move commands contribute to the determination of the calculated size of the drawing, even though they do not generate visible lines. The circle and ellipse commands add a compensation for the radii of circles and ellipses. The final TEXdraw drawing is placed in a TEX box with lower lefthand corner corresponding to (x-min y-min) and upper righthand corner at (x-max y-max).

Text generated by \htext, \vtext or \rtext can spill outside the box as determined above. Only the text reference point is guaranteed to be in the drawing box. Arcs can also spill outside the drawing box. Note also that the widths of lines, and the sizes of arrowheads do not affect the size of the drawing. The calculated size of the drawing will never be larger than the actual size of the drawing. In extreme cases in which text or lines extend far outside the drawing, extra \move commands should be used to establish the size of the drawing so that the TeXdraw box includes all of the drawing.

TEXdraw provides the \drawbb command to draw a box which indicates the effective size of the drawing. Whenever \drawbb is invoked, a ruled box is drawn around the drawing as it has been sized up to that point. Normally \drawbb is invoked just before the end of a drawing to indicate the effective size of the final drawing.

\drawbb Draw a ruled box around the effective size of a drawing produced by TEXdraw commands.

## 3.6 Initial current position

The first operation in a drawing should be a move to establish the current position. The current position can be established explicitly through a \move command or a text positioning command such as \htext with a coordinate. However, if an attempt is made to use a drawing command which needs a current position and none has been established, TeXdraw implicitly sets the initial current position to (0 0). The size of the TeXdraw figure is normally determined from the sequence of coordinates specified, but will include the implicit initial position in case another initial position has not been explicitly specified.

## 4 Using T<sub>E</sub>Xdraw with LaT<sub>E</sub>X

The LaTEX typesetting system uses a structured approach to declaring typesetting environments. An interface to TEXdraw which follows these structuring conventions is provided on top of the basic TEXdraw commands. Using this interface, TEXdraw is enabled as a document-style option, then invoked as a typesetting environment. The TEXdraw environment is started with a \begin{texdraw} command and terminated with an \end{texdraw} command. As an example, a LaTEX document to be typeset using the article style with the 12pt option invokes TEXdraw as follows.

```
\documentstyle [12pt,texdraw]{article}
...
\begin{document}
...
\begin{texdraw}
...
% TeXdraw commands to generate a drawing
\end{texdraw}
...
\end{document}
```

## 4.1 Alternate command forms for LaTeX

All of the basic TEXdraw commands can be used with LaTEX. However, there are alternate forms for the commands used to invoke TEXdraw for use with LaTEX. The \begin{texdraw} and \end{texdraw} commands.

### \begin{texdraw}

Start a TEXdraw drawing. The drawing is terminated with an \end{texdraw} command. This command is for use with LaTeX.

#### \end{texdraw}

End a TeXdraw drawing started with a \begin{texdraw} command. The resulting TeXdraw drawing is placed in a box with height equal to the height of the drawing and width equal to the width of the drawing. The depth of the box is zero. This command is for use with LaTeX.

A LaT<sub>F</sub>X specific variant of an earlier example can be constructed as follows.

 $T_{\rm E}X{
m draw}$ 

```
\newcommand{\tbox}[1]{%
  \bsegment
  \lvec (0 +0.25) \lvec (0.75 +0.25)
  \lvec (0.75 -0.25) \lvec (0 -0.25) \lvec (0 0)
  \textref h:C v:C \htext (0.375 0){#1}
  \savepos (0.75 0)(*ex *ey)
  \esegment
  \move (*ex *ey)}
\begin{center}
\begin{center}
\begin{texdraw}
  \ravec (1 0) \tbox{$H(z)$} \ravec (1 0)
\end{texdraw}
\end{center}
```

This example illustrates the use of the LaT<sub>E</sub>X command \newcommand as an alternative to the plain T<sub>E</sub>X command \def. Instead of the basic T<sub>E</sub>Xdraw command \centertexdraw, a nested combination of the LaT<sub>E</sub>X centering environment and the T<sub>E</sub>Xdraw environment is used.

## 5 More Details

The first part of this chapter offers some suggestions for strategies to isolate errors in TEX and TEXdraw input. The second part of this chapter discusses implementational issues. An awareness of these issues is useful if the TEXdraw package is to be extended.

## 5.1 Common problems

TEX input is notoriously difficult to debug. If TEX reports errors, so much the better. If the cause is not immediately obvious, consider using a a binary search strategy, removing sections of code with the premature insertion of the \bye command (with the appropriate closing of any open groups and the like). Other strategies include the insertion of \message{I am here} at appropriate places. Try using \tracingmacros=1. Many problems turn out to be due to incorrect numbers of macro arguments or incorrectly delimited macro arguments. The \tracingmacros=1 option writes the macro arguments and macro expansions to the TEX log file.

Certain errors may not manifest themselves until well after the offending command. For instance, if a closing parenthesis is missing from a T<sub>E</sub>Xdraw coordinate, T<sub>E</sub>X continues searching for the parenthesis. If one is found, perhaps many lines later, the T<sub>E</sub>Xdraw error message invalid coordinate will be printed at this later point.

All input in the TEXdraw environment should be intended for interpretation by TEXdraw commands. TEXdraw places text inside a zero size box (the text itself extends outside the box). Extraneous input manifests itself as a non-zero size TEXdraw text box. This causes the TEXdraw text and the PostScript graphics to be displaced from one another. An error message is issued if a non-zero width TEXdraw text box is detected. If this error message appears, look for unintended character sequences amongst the commands to TEXdraw.

Several TEXdraw commands pass their arguments "raw" to the PostScript file. That means that invalid arguments can generate PostScript errors when the document is printed. For instance the argument of the \setgray command is passed straight through to the PostScript file. If this argument is non-numeric, a PostScript error results. Not all PostScript printers report errors back to the user. The print may just stop prematurely. One approach to debugging is to use a PostScript previewer on a workstation. That way, one can determine at which point in the drawing the PostScript error occurs.

 $T_{
m EXdraw}$ 

## 5.2 Extending TeXdraw

TEXdraw is implemented using a combination of TEX commands and PostScript code. This section discusses some of the implementational issues as they relate to extending TEXdraw.

TEXdraw as implemented, offers a basic set of drawing features. These are adequate for certain tasks such as producing block diagrams. There are different approaches to extending TEXdraw to include other functions. In some cases, the desired functionality can be achieved by writing a TEX macro which builds on top of the existing TEXdraw commands. As these extensions become more complex, the limitations of TEX for computations become increasingly evident. In other cases, access to different features of PostScript is desired. The appropriate approach would be to write new PostScript procedures which can be accessed by TEX macros.

Included with T<sub>E</sub>Xdraw are a set of macros for directly accessing PostScript functions. These are described in an appendix (see Appendix A [PostScript Commands], page 29).

TEXdraw also comes with a toolbox of routines for handling much of the user interface, converting between different coordinate representations and the like. The macros for coordinate decoding and for computations involving coordinates are described in an appendix (see Appendix B [TeXdraw Toolbox], page 33).

## 5.2.1 Scaling

The scaling commands provided in TEXdraw are designed to affect only the coordinate values specified in commands. For instance, changing the \setunitscale value changes the interpretation of the coordinate in an \avec (x y) command, but does not change the line width or arrowhead sizes in effect. None of the TEXdraw scaling commands affect the size of TEX text produced by, for instance, the \htext command. Scale changes will however affect the positioning of text for subsequent commands.

The line parameters are changed only if the corresponding commands to change them are issued. If the \linewd command is given, the current coordinate scaling is used to determine the line width. To achieve a behaviour more like a global scaling, whenever the scale factor is changed, the line parameters must be set again.

### 5.2.2 Resolution

TEXdraw scales coordinates before passing them to PostScript. Keeping track of the coordinate scaling is necessary, in any event, to allow TEXdraw to compute the maximum excursions of the coordinates. TEXdraw uses pixel units in its PostScript code. These units correspond to 1/300 of an inch. TEXdraw issues PostScript commands which use integer numbers of pixel units. This sets the positioning resolution for TEXdraw. The passing of integer valued coefficients which correspond to the device resolution keeps lines aligned with the device grid. Parallel lines of the same width will be rendered with the same width.

The position saving mechanism in TeXdraw (see Section 3.3 [Saving positions], page 18) associates the pixel coordinates of a position with the specified name.

TEXdraw uses the limited real number representations provided by TEX. These operations are based on the representation of dimensions as real-valued numbers of points. Internally in TEX, dimensions are stored 32-bit values, normalized so that 1 pt corresponds to the scaled point (sp) value of 65536. Dimensions with magnitudes between 0.000015 pt and 32767 pt can be represented. This is also the dynamic range of the TEXdraw pixel coordinates passed to PostScript. TEXdraw must convert from user supplied coordinates using the scaling factor (which itself consists of two components, the unit scale and the segment scale) and a pixel conversion factor. The use of limited precision real numbers in these computations can cause accumulation of error when relative scaling is used repeatedly.

## 5.2.3 Text placement

While in the TEXdraw environment, TEX text is placed directly in a TEX box while PostScript code is being written to the intermediate file. On leaving the TEXdraw environment, the size of the drawing is determined. A TEX \vbox of this size is created. The TEX \special mechanism is used to tell the dvi to PostScript driver to position the PostScript drawing information from the intermediate file in this area. Next, the text generated by TEXdraw is positioned and placed in the box. To adapt most of TEXdraw to another dvi to PostScript driver, only the \special command to position the PostScript include file need be modified.

Note that when the document is printed, the PostScript drawing is placed on the page before the TEX text, independently of the relative order of the text and drawing commands. Generating TEX text after the PostScript plot places text on top of filled areas.

Rotated text is treated in a different manner. The rotation is carried out with in-line PostScript code which does not appear in the intermediate PostScript file. This code is sent to the dvi to PostScript driver with a \special command. In effect this PostScript code is part of the dvi file. To adapt this part of TeXdraw to another dvi to PostScript driver, a \special syntax for in-line PostScript compatible with the driver must be used.

## 5.2.4 The output PostScript file

The intermediate PostScript file consists of a header, a body and a trailer following Encapsulated PostScript File (EPSF) standards. The header sets up PostScript definitions and default parameter values. The trailer includes BoundingBox information which gives the coordinates in default PostScript units (72 per inch) for the lower lefthand corner and the upper righthand corner of the drawing. The body of the intermediate PostScript file contains the PostScript commands generated by TEXdraw.

Many moves in TeXdraw serve only to position text or to reset saved positions. TeXdraw buffers move commands in order to be able to collapse runs of moves. Only the last move of a run of moves is actually written to the PostScript file. However the intermediate moves still affect the size of the drawing. The expunging of moves means that the PostScript file BoundingBox information may indicate a drawing size larger than the PostScript commands themselves would warrant.

Drawing segments in TEXdraw show up in the PostScript file as saves and restores of the PostScript graphics state. Segment starts are also buffered and only written out if necessary. This way "empty" segments do not generate output to the PostScript file. These empty segments arise if a segment contains only moves and text commands. The moves inside the segment are not needed since they are local to the segment, and the text commands do not generate output to the PostScript file.

If TFXdraw is used only for moves and text, no intermediate PostScript file will be created.

The PostScript file produced by TEXdraw can be saved and used as an EPSF file to be included in documents. As noted above, such a file does not contain the commands to create the TEX text. Note that some procedures for including EPSF files will only look for the BoundingBox information in the header. In that case, the BoundingBox statement must be moved from the trailer to the header of the EPSF file, replacing the %%BoundingBox: (at end) line in the header.

## Appendix A PostScript Commands

This appendix describes a set of macros for accessing some of the PostScript builtin functions. Each of these macros issues a single PostScript command. The extra services provided by TEXdraw are the interpretation of coordinates in user units relative to the current drawing segment and the writing of a pending TEXdraw move to the PostScript file. This last operation establishes the current point in PostScript. The user of these commands should be familiar with the concepts of path construction and filling in PostScript. Further details on the PostScript functions used can found in the PostScript Language Reference Manual, Second Edition, Adobe Systems, Addison-Wesley, 1990.

These macros are distributed in file 'txdps.tex'.

The \PSsetlinecap and \PSsetlinejoin commands control the way line ends and line joins are rendered. The default values set by TEXdraw (round caps and round join) are appropriate for most drawings. Changes to these parameters apply to the current and subsequent paths.

### $\P$

Set the line cap parameter. The value 0 gives a butt cap; 1 gives a round cap; and 2 gives a projecting square cap. The initial value is corresponds to a round cap.

### $\P$

Set the line join parameter. The value O gives a miter join; 1 gives a round join; and 2 gives a bevel join. The initial value corresponds to a round join.

PostScript paths and fill operations can be controlled by a number of functions. By design, TEXdraw always maintains a defined PostScript current point. Some of the following macros cause the PostScript current point to become undefined. The PostScript current point must be set again (say with a \PSmoveto command) before invoking basic TEXdraw commands.

### \PSstroke

Stroke a PostScript path. The current path is stroked with the current gray level (set with \setgray) and the current line pattern (set with \lpatt). The PostScript current point becomes undefined.

### \PSnewpath

Establish a new path. The PostScript current point becomes undefined.

#### \PSclosepath

Close a subpath. A new subpath is started.

 $T_{
m EXdraw}$ 

\PSfill Fill a region defined by a path. Each subpath is closed and the enclosed regions painted with the current gray level. The PostScript current point becomes undefined. The gray level can be set with the T<sub>F</sub>Xdraw command \setgray.

The following line commands interpret coordinates relative to the current TEXdraw scaling and drawing segment. The specified coordinate affects the drawing size as determined by TEXdraw.

### $\P$ \PSlineto $(x \ y)$

Add a line segment to the current path. This command is identical to the TEXdraw command \luec. The PostScript current point must be defined before this command is issued.

### $\PSmoveto(x y)$

Move to the coordinate specified by (x y). The PostScript current point becomes defined.

The following macros provide access to the general arc commands in PostScript. The coordinates are interpreted relative to the current TEXdraw scaling and drawing segment. The specified coordinate affects the drawing size as determined by TEXdraw.

#### \PSarc r: radius sd: start-angle ed: end-angle $(x \ y)$

Draw a counterclockwise arc. The center of the arc is at the given position. The radius is specified by radius. The start and end angles (in degrees) are specified by start-angle and end-angle. If the PostScript current point is defined, this command also draws the line from the current point to the beginning of the arc. The line and arc become part of the current path. The current point becomes defined.

#### \PSarcn r:radius sd:start-angle ed:end-angle (x y)

Draw a clockwise arc. The center of the arc is at the given position. The radius is specified by radius. The start and end angles (in degrees) are specified by start-angle and end-angle. If the PostScript current point is defined, this command also draws the line from the current point to the beginning of the arc. The line and arc become part of the current path. The current point becomes defined.

The macro \writeps provides the general facility to write arbitrary PostScript commands to the PostScript file. This macro is used by the preceding commands and by the TEXdraw commands themselves. This facility has to be used with care since any changes in position or scaling resulting from the PostScript commands are not known to TEXdraw.

## \writeps {<ps-commands>}

Write PostScript commands to the intermediate PostScript file. Before the commands are inserted, any pending TeXdraw move is written to the PostScript file. The PostScript scaling gives 300 units/inch.

TeXdraw

## Appendix B TEXdraw Toolbox

This appendix describes some of the macros supplied with TEXdraw which can be used to define additional commands for creating drawings. The macros described here work in the user specified coordinate system. Some of these toolbox macros are used by the TEXdraw commands themselves, others are supplied in an auxiliary file 'txdtools.tex'.

## **B.1** Coordinate parsing

The coordinate parsing macro \getpos is useful for creating new commands. This macro takes care of stripping leading and trailing blanks from coordinates specified between parentheses. In addition, symbolic coordinates are translated to the corresponding relative coordinate using the segment offset and scaling in effect.

The macro \currentpos returns the relative coordinates of the current position. The returned values are relative to the current segment and the current scaling. The macro \cossin returns the real-valued cosine and sine of the direction of the line joining two points. The macro \vectlen returns the length of a vector. The results appear as the value of user supplied macro names.

## \getpos (x y) mx my

Decode coordinate values. The coordinates specified by  $(x \ y)$  are decoded. Symbolic coordinates are translated to the corresponding relative coordinate using the current segment offset and scaling. The resulting character strings representing the real-valued coordinates are assigned to the macros specified by  $\mbox{$\backslash$mx$}$  and  $\mbox{$\backslash$my$}$ .

### \currentpos $\mbox{\mbox{}mx\mbox{}my}$

Return the coordinates of the current position. The coordinates are relative to the current segment offset and scaling. The resulting character strings representing the real-valued coordinates are assigned to the macros specified by  $\mbox{$\backslash$mx$}$  and  $\mbox{$\backslash$my$}$ .

## $\cossin (x1 y1)(x2 y2)\cosa\sina$

Return the cosine and sine of the direction of a vector joining two points. The cosine and sine of the angle of the vector which goes from  $(x1 \ y1)$  to  $(x2 \ y2)$ . The character strings representing these real-valued quantities are assigned to the macros specified by  $\cos a$  and  $\sin a$ .

### \vectlen $(x1 \ y1)(x2 \ y2) \setminus len$

Return the length of a vector joining two points. The length of the vector is relative to the current scaling. The character string representing the real-valued length is assigned to the macro specified by  $\lambda len$ .

 $T_{\rm E}X{
m draw}$ 

## B.2 Real arithmetic

The T<sub>E</sub>Xdraw toolbox supplies macros to perform real arithmetic on coordinate values. The result appears as the value of a user supplied macro name.

### \realadd {value1} {value2} \sum

Add two real quantities, assigning the resultant character string representing the sum to the macro  $\lambda sum$ .

### \realmult {value1} {value2} \prod


Multiply two real quantities, assigning the resultant character string representing the product to the macro  $\prod$ .

#### \realdiv {value1} {value2} \result

Divide two real quantities, assigning the resultant character string representing the result of value1/value2 to the macro  $\$ 

## B.3 Arrow curve

This example illustrates the use of the TEXdraw toolbox routines to do computations with the coordinates. The problem will be tackled in two parts. First, we will produce a macro to place an arrowhead on a Bezier curve. Then given this macro, we will produce a macro which can draw a "wiggly" line from the current position to a given coordinate.



The first macro, \cavec, uses the \cossin command to determine the the cosine and sine of the angle of the line joining the second control point to the end point of the Bezier curve. Recall that the Bezier curve is tangent to this line at the end point. After drawing the Bezier curve, the scaling is set locally to absolute units of 0.05 inches. We go back down the line from the end point by 0.05 inches and draw an arrow vector to the end point from there. This arrow vector is mostly arrowhead, with little or no tail.

```
\def\cavec (#1 #2)(#3 #4)(#5 #6){
  \clvec (#1 #2)(#3 #4)(#5 #6)
  \cossin (#3 #4)(#5 #6)\cosa\sina
  \rmove (0 0)
  \bsegment
   \drawdim in \setsegscale 0.05
   \move ({-\cosa} -\sina) \avec (0 0)
  \esegment}
```

Note the use of macros as arguments to a \move command. Minus signs are put in front of the macros. However, the value of the macro \cosa or \sina could be negative. Fortunately, TEX accepts two minus signs in a row and interprets the result as positive. Note the \rmove (0 0) before the beginning of the segment ensures that the Bezier curve is stroked before the arrowhead is drawn.

The second macro \caw builds on \cavec. The goal is to produce a wiggly vector that can be used as a pointer in a drawing. Consider the following normalized Bezier curve.

```
\contertexdraw{ (0 0) \cavec (1.4 0.1)(-0.4 -0.1)(1 0) }
```

This curve has the appropriate wiggle. Now we want to be able to draw this curve, appropriately scaled and rotated. The macro \caw needs to do computations on the coordinates. First, \caw uses the macros \getpos and \currentpos to get the positions of the end and start of the curve. Next, the length of the vector is calculated using the macro \vectlen. A local macro \rotatecoord is used to rotate a coordinate pair about the origin, using the cosine and sine of the rotation angle. The vector length is used to scale the normalized curve. The remaining code draws the rotated, normalized curve.

```
\def\caw (#1 #2){
  \currentpos \xa\ya
  \cossin ({\xa} \ya)(#1 #2)\cosa\sina
%
% calculate the length of the vector, and the x and y displacements
  \vectlen ({\xa} \ya)(#1 #2)\len
  \getpos (#1 #2)\xb\yb
  \realadd \xb {-\xa} \dx \realadd \yb {-\ya} \dy
%
% calculate the offsets
  \rotatecoord (0.4 0.1)\cosa\sina \du\dv
%
% draw the curve in normalized units
  \bsegment
  \setsegscale {\len}
```

 $_{
m TEXdraw}$ 

```
\realadd \cosa \du \tmpa \realadd \sina \dv \tmpb
  \cavec ({\tmpa} \tmpb)({-\du} -\dv)({\cosa} \sina)
  \esegment
  \move (#1 #2)}

\def\rotatecoord (#1 #2)#3#4#5#6{
  \getpos (#1 #2)\xarg\yarg
  \realmult \xarg {#3} \tmpa \realmult \yarg {#4} \tmpb
  \realadd \tmpa {-\tmpb} #5
  \realmult \xarg {#4} \tmpa \realmult \yarg {#3} \tmpb
  \realadd \tmpa \tmpb #6}
```

Finally, the new macro can be used as follows.

```
\centertexdraw{
  \arrowheadtype t:W
  \move (0 0)
  \cavec (1.4 0.1)(-0.4 -0.1)(1 0)
  \move (1 0) \caw (1 1) \htext{tip at \tt (1 1)}
  \move (1 0) \caw (2 1) \htext{tip at \tt (2 1)}
  \move (1 0) \caw (2 0) \htext{tip at \tt (2 0)}
}
```


Note that the Bezier curve in the macro \cavec lies below the arrowhead. The example then draws an arrowhead of type W to erase the part of the line below the arrowhead.

## Appendix C Examples

This appendix shows examples of the use of TEXdraw.

## C.1 Block diagram of a lattice filter

The block diagram of a lattice filter uses a library of extended commands built from the basic T<sub>F</sub>Xdraw commands.



The block diagram uses a "delay" block. This is defined as a segment which leaves the current position at the end of this block. A second macro, \bdot, draws a "big" dot which is used to mark junctions of lines. The \Ttext command centers text above a given point. The offset to position the text is local to a segment, resulting in no change to the current point. Similar macros to position text below a point (\Btext), to the left of a point (\Ltext) and to the right of a point (\Rtext) are used in the final drawing.

```
\def\delay {\bsegment
          \setsegscale 0.3
          \lvec (0 +0.5) \lvec (1 +0.5) \lvec (1 -0.5)
          \lvec (0 -0.5) \lvec (0 0)
          \textref h:C v:C \htext (0.5 0){$z^{-1}$}
          \savepos (1 0)(*ex *ey)
          \esegment
          \move (*ex *ey)}
\def\bdot {\fcir f:0 r:0.02 }
\def\Ttext #1{\bsegment
          \textref h:C v:B \htext (0 +0.06){#1}
          \esegment}
```

Several of the block diagram elements scale with the size of the summing nodes. The radius of the circles for the summing nodes is defined as the macro \cradius. The summing nodes will

 $T_{\rm E}X{
m draw}$ 

have enclosed plus signs, appropriately scaled. The plus sign is drawn by the macro \pluss. The macro \pcir draws both the circle and the plus sign. The incoming lines to a summing node will be labelled with plus or minus signs (characters this time), placed at the appropriate position with respect to the center of the summing node. These positions are given in terms of compass directions. The macro \putwnw places text west by north-west relative to the center of the summing node.

The block diagram has vectors arriving and departing from the summing nodes (circles). One could calculate the points of intersection of the lines with the circles, and then enter the values into the TeXdraw code. However, in this example, we implement an automated procedure. Two macros are needed, an arrow vector to a circle (\avectoc) and an arrow vector leaving from a circle (\avectoc). The macros will calculate the point of intersection with the circle and start or end the vector at the intersection point.

The arrow macros use scaling and relative positioning inside of a drawing segment. In the case of the macro \avectoc, a move is made to the final point (center of the circle), then within a drawing segment, a scaled move is made back towards the start to find the intersection point with the circle.

```
\bsegment
  \setsegscale {\cradius}
  \move ({\cosa} \sina)
  \savecurrpos (*ex *ey)
\esegment
\move (*ex *ey)
\avec (#1 #2)}
```

Using these macros, we are ready to draw the block diagram. The first and last sections of the lattice filter are very similar, differing mainly in the text labels. With more effort, code could be shared between the commands used to draw these blocks.

```
\centertexdraw{
\drawdim in
\arrowheadtype t:F \arrowheadsize 1:0.08 w:0.04
\def\pl {{\sevenrm \char43}} \def\mn {{\sevensy \char0}}
\move (0 +0.63) \move (0 -0.60) \move (0 0) % compensate for the text size
% Input to the first stage
\bsegment
      \text{Ltext}\{x(n)\}
      \lvec (0.3 0) \bdot \lvec <math>(0.3 +0.4) \mbox{move } (0.3 0) \lvec (0.3 -0.4)
      \space{1.5} \spa
\esegment
\move (*ex *ey)
% first lattice stage
\bsegment
      \move (0 + 0.4) \avectoc (1.7 + 0.4)
      \pcir \putwnw{\pl} \puts{\mn}
      \avecfrc (2.1 + 0.4)
      \move (0 - 0.4) \avec (0.4 - 0.4) \delay \avectoc (1.7 - 0.4)
      \pcir \putwsw{\pl} \putn{\mn}
      \avecfrc (2.1 - 0.4)
      \move (0.9 + 0.4) \bdot \avectoc (1.7 - 0.4)
      \move (0.9 - 0.4) \bdot \avectoc (1.7 + 0.4)
      \move (0.1 + 0.42) \text{Ttext } \{f_0(n)\}
      \move (2.0 +0.42) \text{Ttext } \{f_1(n)\}
      \move (0.1 - 0.4) \Btext \{b_0(n)\}
      \move (2.0 - 0.4) \Btext \{b_1(n)\}
      \textref h:L v:B \htext (1.15 +0.2){$K_1$}
      \textref h:L v:T \htext (1.15 -0.2){$K_1$}
      \space{2.1.0}(*ex *ey)
\esegment
\move (*ex *ey)
% center section
```


 $T_{\rm E}X{
m draw}$ 

```
\bsegment
  \textref h:C v:C \htext (0.3 +0.4){$\cdots$}
  \begin{array}{cccc} \text{htext } (0.3 - 0.4) & \cdots \end{array}
  \space{-0.60}(0.60)(*ex *ey)
\esegment
\move (*ex *ey)
% last lattice stage
\bsegment
  \move (0 + 0.4) \avectoc (1.7 + 0.4)
  \pcir \putwnw{\pl} \puts{\mn}
  \avecfrc (2.3 +0.4) \text{Rtext}\{\$e(n)\$\}
  \move (0 - 0.4) \avec (0.4 - 0.4) \delay \avectoc (1.7 - 0.4)
  \pcir \putwsw{\pl} \putn{\mn}
  \avecfrc (2.1 - 0.4)
  \move (0.9 + 0.4)
                     \bdot \avectoc (1.7 -0.4)
  \move (0.9 -0.4)
                      \bdot \avectoc (1.7 +0.4)
  \move (0.1 + 0.42) \text{Ttext } \{f_{P-1}(n)\}
  \move (2.0 +0.42) \text{Ttext } \{f_P(n)\}
  \move (0.1 -0.4)
                     \Btext \{b_{P-1}(n)\}
  \move (2.0 - 0.4)
                      Btext {$b_P(n)$}
  \textref h:L v:B \htext (1.15 +0.2){$K_P$}
  \textref h:L v:T \htext (1.15 -0.2){$K_P$}
\esegment
}
```

The macros used in this example are similar to the block diagram macros defined in the file 'blockdiagram.tex'.

## C.2 Filter response graph

This example shows the response of a canonical filter. TEXdraw is not well suited for general purpose graphing — it has no coordinate translation facility nor does it have separate x and y scaling. However, for certain simple graphs, TEXdraw is adequate.



In this example, macro \ticklab places a labelled axis tick at a given position. The data is specified in a straightforward manner, having been scaled beforehand to give the desired aspect ratio for the graph.


```
\centertexdraw{
\arrowheadtype t:F \arrowheadsize 1:0.08 w:0.04
\def\ds {\displaystyle}
\def\ticklab (#1 #2)#3{\move(#1 #2)
                        \bsegment
                          \label{lvec} \ (0\ 0.05)
                          \textref h:C v:T \htext (0 -0.05){#3}
                        \esegment}
\def\Rtext #1{\bsegment
                 \textref h:L v:C \htext (+0.08 0){#1}
               \esegment}
\move (2.4 - 0.3)
                    % move to set the size
\move (0 0)
% Axes
\avec (0 + 1.4)
\move (0 0) \avec (2.2 0) \Rtext{$\omega$}
\ticklab (0 0)
                {0}
\ticklab (0.8 0) {$\ds {\pi \over 2N} $}
\ticklab (1.2 0) {\square\conga_s\}
\ticklab (1.6 0) {$\ds {\pi \over N} $}
\linewd 0.025
\move (0 1)
\label{lvec} (0.41)
\lvec (0.44 0.998)
\lvec (0.48 0.988)
\lvec (0.52 0.973)
\lvec (0.56 0.951)
\lvec (1.08 0.233)
\lvec (1.12 0.156)
\lvec (1.16 0.078)
\lvec (1.20 0)
\lvec (1.9 0)
```

## C.3 Geometric construction

This example shows a geometric construction which places an ellipse tangent to an enclosing circle. The size of the ellipse is determined from geometric considerations. Macros are used to

42 T<sub>F</sub>Xdraw

modularize the code. The example alters the unit scale factor. This allows the drawing to be carried out in units normalized to the radius of the circle.



```
\centertexdraw{
\arrowheadtype t:V \arrowheadsize 1:0.08 w:0.04
\linewd 0.01
\setunitscale 1.5
                              % circle will have radius 1.5 inches
\def\Btext #1{\bsegment
                \textref h:C v:T \htext (0 -0.04){#1}
              \esegment}
\def\Ttext #1{\bsegment
                \textref h:C v:B \htext (0 +0.04){#1}
              \esegment}
\def\Ltext #1{\bsegment
                \textref h:R v:C \htext (-0.04 \ 0){#1}
               \esegment}
\def\bdot {\fcir f:0 r:0.0133 }
\def\vtick {\bsegment
               \move (0 -0.05) \setminus 1 \text{vec} (0 +0.05)
            \esegment}
\def\htick {\bsegment
               \move (-0.05\ 0)\ \ (+0.05\ 0)
            \esegment}
\def\Hlen (#1 #2)(#3 #4){\move (#1 #2) \vtick}
                          \move (#3 #4) \vtick
                          \avec (#1 #2) \avec (#3 #4)}
\def\Vlen (#1 #2)(#3 #4){\move (#1 #2) \htick}
                          \move (#3 #4) \htick
                          \avec (#1 #2) \avec (#3 #4)}
```

```
\lcir r:1
                          % circle
\move (-1.05 0) \lvec ( 1.05 0)
                          % axes
\move (0 -1.05) \ \ (0 1.05)
\text{textref } h:R \ v:T \ \text{htext}(-0.02 \ -0.02)\{0\}
\textref h:L v:B \htext(0.725 0.725){X}
\move (0 0) \lvec (0.707 0.707)
\move (0.5 0)
                          % center of ellipse
\bsegment
 \lellip rx:0.435 ry:0.804
 \bdot \Btext {$\beta_2$}
 \Hlen (0 0.15)(0.435 0.15) \move (0.218 0.15) \Ttext{\{|\beta_1\}}
 \esegment
}
```

 $T_{\rm E}X{
m draw}$ 

# Appendix D Alphabetic listing of commands

## \arrowheadsize 1: length w: width

Set the arrowhead size to be *length* units long and *width* units wide. The width is measured across the "base" of the arrowhead. The initial arrowhead size has a *length* of 0.16 inches and a *width* of 0.08 inches.

#### \arrowheadtype t: type

Set the arrowhead type to type, where type is one of F, T, W, V, or H. There are two kinds of arrowheads. The first kind is a triangle. There are 3 variants: type T is an empty triangle, type F is a filled triangle (using the current gray level), type W is a triangle filled with white. The second kind of arrowhead is an open ended Vee. There are 2 variants: type V has the stem continue to the tip, type H has the stem stop at the base of the arrowhead. The initial arrowhead type is T.

## $\avec(x y)$

Draw a line with an arrowhead from the current position to  $(x \ y)$ . The new current position is  $(x \ y)$ . The arrowhead is aligned with the line, with the tip at  $(x \ y)$ .

## \begin{texdraw}

Start a TEXdraw drawing. The drawing is terminated with an \end{texdraw} command. This command is for use with LaTeX.

## \bsegment

Start a drawing segment. The coordinate system is shifted such that the current position corresponds to the coordinate (0 0). Changes to scaling, position and line parameters stay local to the drawing segment.

#### \btexdraw

Start a TFXdraw drawing. The drawing is terminated with an \etexdraw command.

#### \centertexdraw { ... }

Center a TEXdraw box. The argument contains TEXdraw commands. The resulting box has the horizontal size \hsize and height equal to the height of the drawing.

#### \clvec $(x1 \ v1)(x2 \ v2)(x3 \ v3)$

Draw a Bezier curve from the current position to the coordinate  $(x3 \ y3)$  which becomes the new current position. The coordinates  $(x1 \ y1)$  and  $(x2 \ y2)$  serve as control points for the curve. Only the last coordinate given is used to update the size of the drawing.

\drawbb Draw a ruled box around the effective size of a drawing produced by TEXdraw commands.

 $T_{\rm E}X{
m draw}$ 

#### \drawdim dim

Set the units to dim. The argument dim can be any valid TEX dimension unit. The units are used to interpret coordinate values. Examples of valid units: cm, mm, in, pt, and bp.

#### \end{texdraw}

End a TEXdraw drawing started with a \begin{texdraw} command. The resulting TEXdraw drawing is placed in a box with height equal to the height of the drawing and width equal to the width of the drawing. The depth of the box is zero. This command is for use with LaTeX.

## \esegment

End a drawing segment. The current position in effect before the corresponding \bsegment command is restored. The scaling and line parameter values revert to those in effect before the corresponding \bsegment was invoked.

#### \etexdraw

End a TEXdraw drawing started with a \btexdraw command. The resulting TEXdraw drawing is placed in a box with height equal to the height of the drawing and width equal to the width of the drawing. The depth of the box is zero.

#### \fcir f:level r:radius

Draw a filled circle at the current position. The radius is specified by radius. The circle is painted with the gray level specified by level. A gray level of 1 corresponds to white, with decreasing values getting darker. The level 0 is full black. This command does not draw a line along the circumference. The drawing size is increased if necessary to contain the circle.

# $\begin{array}{c} \text{htext } (x \ y) \{ text \} \end{array}$

\htext { text}

The first form of this command places the  $T_EX$  text text horizontally with the text reference point at the coordinate  $(x\ y)$ . The new current position is  $(x\ y)$ . The second form of this command places the  $T_EX$  text text horizontally with the text reference point at the current position. The text reference point is set with the \textref command.

## \ifill f: level

Close the current path and paint the interior of the region with gray level level. The line around the path is not drawn. Gray levels are real values from 0 (black) through intermediate values (grays) to 1 (white).

## \larc r:radius sd:start-angle ed:end-angle

Draw a counterclockwise arc. The center of the arc is at the current position. The radius is specified by radius. The start and end angles (in degrees) are specified by start-angle and end-angle. This command does not affect the limits (size) of the drawing.

#### \lcir r:radius

Draw a circle with center at the current position. The radius is specified by radius. This command draws a line along the circumference of the circle. The drawing size is increased if necessary to contain the circle.

## \lellip rx: x-radius ry: y-radius

Draw an ellipse. The center of the ellipse is at the current position. The radius in the x direction is specified by x-radius. The radius in the y direction is specified by y-radius. The drawing size is increased if necessary to contain the ellipse.

#### \lfill f: level

Close the current path, draw the line around the path using the current grey level for lines and paint the interior of the region with specified gray level *level*. Gray levels are real values from 0 (black) through intermediate values (grays) to 1 (white).

#### \linewd width

Set the line width to width units. Initially width is 0.01 inches (corresponding to 3 pixels at 300 pixels to the inch).

## \lpatt (pattern)

Set lines to have the pattern (pattern). A pattern is a sequence of on/off lengths separated by blanks enclosed in parentheses. The lengths alternately specify the length of a dash and the length of a gap between dashes. Each length is interpreted using the current scaling and drawing units. The pattern is used cyclically. The empty pattern signifies a solid line. The initial line pattern is a solid line, corresponding to the empty pattern \lnablapattern \lnablapatte

## $\label{lvec} (x y)$

Draw a line from the current position to coordinate (x y). The new current position is (x y).

#### \move $(x \ y)$

Move to coordinate (x y). The new current position is (x y).

## 

Draw a line with an arrowhead from the current position, dx units in the x direction and y units in the y direction. The final position becomes the new current position. The arrowhead is aligned with the line, with the tip at the new current position.

## \relsegscale value

Adjust the segment scale factor by multiplying by value. This has the effect of multiplying the current overall scale factor by the same factor. The overall scaling factor is the product of the unit scale factor and the segment scale factor.

48 T<sub>F</sub>Xdraw

#### \relunitscale value

Adjust the unit scale factor by multiplying by *value*. This has the effect of multiplying the overall scale factor by the same factor. The overall scaling factor is the product of the unit scale factor and the segment scale factor.

## 

Draw a line from the current position, dx units in the x direction and dy units in the y direction. The final position becomes the new current position.

## $\mbox{rmove} (dx dy)$

Move from the current position, dx units in the x direction and dy units in the y direction. The final position becomes the new current position.

\rtext td:angle (x y){text}
\rtext td:angle {text}

The first form of this command places the  $T_EX$  text text at an angle with the text reference point at the coordinate (x y). The new current position is (x y). The second form of this command places the  $T_EX$  text text at an angle with the text reference point at the current position. In both cases, the  $T_EX$  text is placed in a box and the box is rotated counterclockwise by angle degrees about the text reference point. The text reference point is set with the \textref command.

## \savecurrpos (\*px \*py)

Save the current position as the absolute position referenced by (\*px \*py).

\savepos  $(x \ y)(*px *py)$ 

Save the coordinate position  $(x \ y)$  as the absolute position referenced by (\*px \*py). The coordinate  $(x \ y)$  is interpreted in the normal fashion as a coordinate relative to the current segment, using the current scaling factors and drawing unit.

## \setgray level

Set the gray level of lines. Gray levels are real values from 0 (black) through intermediate values (gray) to 1 (white). The initial gray level is 0 corresponding to black.

## \setsegscale scale

Set the segment scale factor. The argument *scale* is a real number which is used to scale coordinate values. The overall scale factor is the product of the unit scale factor and the segment scale factor.

#### \setunitscale scale

Set the unit scaling to scale. The argument scale is a real number which is used to scale coordinate values. The overall scaling factor is the product of the unit scale factor and the segment scale factor.

## \texdrawbox { ... }

Create a TEXdraw box. The argument contains TEXdraw commands. This macro returns a TEX box with height equal to the height of the drawing and width equal to the width of the drawing. The depth of the box is zero.

## \textref h: h-ref v: v-ref

Set the text reference point for subsequent text commands. The horizontal reference point h-ref is one of L, C or R (left, center or right). The vertical reference point v-ref is one of T, C or B (top, center or bottom). For rotated text, the reference point is determined before rotation. The initial text reference point corresponds to textref h:L v:B.

\vtext (x y){text}
\vtext {text}

The first form of this command places the TEX text text vertically with the text reference point at the coordinate (x y). The new current position is (x y). The second form of this command places the TEX text text vertically with the text reference point at the current position. In both cases, the TEX text is placed in a box and the box is rotated counterclockwise by 90 degrees about the text reference point. The text reference point is set with the \textref command.

 $_{
m TEXdraw}$ 

Command Index 51

# Command Index

\	\realmult	34
\arc11	\relsegscale	20
\arrowheadsize 7	\relunitscale	20
\arrowheadtype 7	\rlvec	. 7
\avec 7	\rmove	. 7
\begin{texdraw}	\rtext	. 9
\bsegment	\savecurrpos	18
\btexdraw 4	\savepos	18
\centertexdraw 4	\setgray	. 7
\clwec	\setsegscale	20
\cossin	\setunitscale	20
\currentpos	\textref	10
\drawbb	\vectlen	33
\drawdim6	\vtext	. 9
\end{texdraw}	\writeps	30
\esegment		
\etexdraw 4	$\mathbf{A}$	
\fcir 11	arc	30
\getpos 33	arcn	30
\htext9	~	
\ifill 14	$\mathbf{C}$	
\lcir 11	closepath	29
\lfill 14	_	
\linewd 7	${f F}$	
\lvec	fill	29
\move 7	_	
\PSarc 30	${f L}$	
\PSarcn	lineto	30
\PSclosepath		
\PSfill	$\mathbf{M}$	
\PSlineto 30	moveto	30
\PSmoveto		
\PSnewpath29	N	
\PSsetlinecap	newpath	29
\PSsetlinejoin		
\PSstroke	$\mathbf{S}$	
\ravec 7	setlinecap	29
\realadd34	setlinejoin	29
\realdiv 34	stroke	29

TeXdraw

Concept Index 53

# Concept Index

$\mathbf{A}$	${f F}$	
accessing TEXdraw	fill operations, interaction with drawing segments 17	
angle of a vector	filled circles	
arcs	filling regions	
arrowhead parameters 7		
arrows	G	
	gray levels for lines	
В	TT	
Bezier curves	Н	
	history of TEXdraw	
C	I	
circles	implementation	
command syntax 4	initial current position 22	
coordinate parsing	invoking TEXdraw	
coordinate specification 6	-	
coordinate, symbolic	${f L}$	
coordinates 5	LaTEX forms for TEXdraw commands 23	
cosine of a vector direction	length of a vector	
current position 6, 22, 33	line cap	
current position in PostScript	line join	
curves	line width 7	
	lines	
D	listing of commands	
dashed lines	$\mathbf{M}$	
direction of a line	moves	
distribution	,	
dotted lines 7	P	
drawing segments	painting regions	
T.	paths	
$\mathbf{E}$	position specification 6	
ellipses	positions, saving	
Encapsulated PostScript File	PostScript commands	
errors, common	predecessors to TEXdraw	
example, arrow curve	problems	
example, block diagram	D	
example, circle and ellipse	R	
example, graph	relative positioning 7	

 $_{
m TEXdraw}$ 

relative scaling	syntax of commands 4	
resolution       27         rotated text       9	${f T}$	
S	text commands	
saving positions	$\mathbf{U}$	
scaling	unit scale	
scaling coordinates		
segment scale	V	
segments	vectors	
sine of a vector direction	vertical text 9	
size of the drawing		
stroking lines	$\mathbf{W}$	
symbolic coordinate	width of lines 7	

# **Table of Contents**

1	Intro	$oduction \dots 1$
	1.1	History
	1.2	Distribution information
2	Usin	${ m ag\ the\ T_EXdraw\ Commands}\dots 3$
	2.1	Accessing TEXdraw
	2.2	Command syntax4
	2.3	TEXdraw coordinates5
	2.4	Coordinate specification
	2.5	Line vectors6
	2.6	T <sub>E</sub> X text9
	2.7	Circles, ellipses and arcs
	2.8	Bezier curves
	2.9	Fill commands
3	Drav	wing Segments and Scaling17
	3.1	Drawing segments
	3.2	Drawing paths
	3.3	Saving positions
	3.4	Scaling coordinates
	3.5	Drawing size
	3.6	Initial current position
4	Usin	ng T <sub>E</sub> Xdraw with LaT <sub>E</sub> X
	4.1	Alternate command forms for LaTeX
5	Mor	e Details 25
	5.1	Common problems
	5.2	Extending TeXdraw
		5.2.1 Scaling
		5.2.2 Resolution
		5.2.3 Text placement
		5.2.4 The output PostScript file
$\mathbf{A}_{\mathbf{I}}$	pend	ix A PostScript Commands 29

 $_{
m TE}$ Xdraw

Append	$egin{array}{lll}  ext{lix B} &  ext{T}_{ ext{E}}  ext{X}  ext{draw Toolbox} \dots & \dots $	33
B.1	Coordinate parsing	
B.2	zeour univillitette	
B.3	Arrow curve	34
$\mathbf{Append}$	lix C Examples	
C.1	Block diagram of a lattice filter	37
C.2	Filter response graph	40
C.3	Geometric construction	41
Append	lix D Alphabetic listing of comma	${ m nds}\ldots\ldots 45$
Comma	$\mathbf{nd}  \mathbf{Index} \dots \dots \dots \dots \dots$	51
Concept	$ ext{t Index} \dots \dots$	53