

**PhxAss**

**COLLABORATORS**

	<i>TITLE :</i> PhxAss		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		July 1, 2022	

**REVISION HISTORY**

NUMBER	DATE	DESCRIPTION	NAME

# Contents

<b>1</b>	<b>PhxAss</b>	<b>1</b>
1.1	PhxAss V4.26 Documentation (28-Dec-95)	1
1.2	Preface	2
1.3	Modifications since PhxAss V2.xx	4
1.4	Modifications since PhxAss V3.00	6
1.5	Modifications since PhxAss V4.00	9
1.6	Bug fixes since V2.11	11
1.7	Bug fixes since V3.00	12
1.8	Bug fixes since V4.00	14
1.9	Starting PhxAss	16
1.10	Command line arguments	17
1.11	Programmer Information	21
1.12	Comments	22
1.13	Labels	22
1.14	Executable M68000 instructions	23
1.15	General Format	23
1.16	M68000 Standard Addressing Modes	23
1.17	68020+ Extended Addressing Modes	24
1.18	68020+ Suppressed Registers	26
1.19	M68000 Instructions supported by PhxAss	26
1.20	Integer Instructions (68000,68010,68020,68030,68040,68060)	27
1.21	Integer Instructions (68010,68020,68030,68040,68060)	29
1.22	Integer Instructions (68020,68030,68040,68060)	29
1.23	Integer Instructions (68040,68060)	30
1.24	Integer Instructions (68060)	30
1.25	MOVEC Control Registers (Rc)	30
1.26	Floating Point Instructions (68881,68882,68040,68060)	30
1.27	Floating Point Instructions (68040,68060)	32
1.28	PMMU Instructions (68851)	33
1.29	PMMU Instructions (68030)	33

---

1.30	PMMU Instructions (68040,68060)	34
1.31	Expressions	34
1.32	Assembler Directives	35
1.33	EQU	40
1.34	EQU.x	40
1.35	EQR	41
1.36	REG	41
1.37	FREG	41
1.38	SET	41
1.39	SET.x	42
1.40	INT	42
1.41	RSRESET	42
1.42	RSSET	42
1.43	RS	42
1.44	IDNT	43
1.45	SUBTTL	43
1.46	COMMENT	43
1.47	LIST	43
1.48	NOLIST	43
1.49	OPT	44
1.50	MACRO, ENDM	44
1.51	MEXIT	44
1.52	END	45
1.53	FAIL	45
1.54	ECHO	45
1.55	MACHINE	45
1.56	FPU	45
1.57	PMMU	46
1.58	SECTION	46
1.59	CODE, CSEG	46
1.60	DATA, DSEG	46
1.61	CODE_C, CODE_F, DATA_C, DATA_F, BSS_C, BSS_F	47
1.62	BSS	47
1.63	BSS	47
1.64	GLOBAL	47
1.65	OFFSET	47
1.66	RORG	48
1.67	INCDIR	48
1.68	INCLUDE	48

---

---

1.69	INCBIN	49
1.70	XREF	49
1.71	NREF	49
1.72	XDEF	49
1.73	PUBLIC	49
1.74	ORG	50
1.75	LOAD	50
1.76	FILE	50
1.77	SFORM	51
1.78	TRACKDISK	51
1.79	NEAR	51
1.80	FAR	52
1.81	INITNEAR	52
1.82	DC	52
1.83	DCB, BLK	53
1.84	DS, DX	53
1.85	CNOP	53
1.86	EVEN	53
1.87	IFcond, ELSEIF, ELSE, ENDIF, ENDC	53
1.88	PROCSTART,PROCEND	54
1.89	REPT/ENDR	54
1.90	SAVE	54
1.91	RESTORE	55
1.92	DEBUG	55
1.93	DSOURCE	55
1.94	Compiler Compatibility	55
1.95	PhxOpts	56
1.96	Environment Variables	56
1.97	Linker	56
1.98	Assembler Errors	57
1.99	History / Literature	62
1.100	Acknowledgements	63
1.101	Known bugs in version V4.26	64
1.102	My Address	65

---



The Author's Address

## 1.2 Preface

PhxAss V4.xx is a highly optimizing macro assembler for Motorola's 680x0 CPUs, 6888x FPUs and 68851 MMU (of course, the 030, 040 and 060 MMUs are also supported).

PhxAss V4.xx requires OS2.04 (V37) as a minimum and does no longer support older operating systems! (Kick 1.x owners: Get PhxAss V3.97, it's the last version running under Kick 1.x). 1 MB of RAM recommended.

PhxAss V4.xx is SHAREWARE and © copyright 1994,1995 by Frank Wille (Phoenix of Phantasm). Commercial usage of this program, without a written permission of the author, is strictly forbidden!

Most important features:

- o Fast: 15000-30000 lines per minute with standard Amigas, 50000-350000 with A4000/040.
- o Resident.
- o Symbolic and Source Level Debugging. Possibility to enable Source Level Debugging for high level languages too.
- o Automatic generation of executables (if possible).
- o Creates relocatable Amiga-DOS objects or absolute code (written into a file (raw or Motorola S-Format), into memory or directly onto disk).
- o Small Code and Small Data support (also support for \_\_MERGED sections).
- o Listing file, Cross Reference Listing, Equates file.
- o Complete floating point support: You can use complex floating point expressions, including float functions (sine, logarithm, square root, power, etc.), everywhere in your source, e.g. defining float EQUates or SETs.
- o Switches for nine different optimizations.
- o Locale symbols (xxx\$ and .xxx type).
- o Up to 36 macro parameters.
- o Support for Motorola's old and new operand style (even in 68000 mode).
- o locale.library usage (english, german, swedish, italian, danish, dutch, hungarian and french).
- o Nearly all directives of the most popular assemblers like Seka, DevPac or AS (Aztec) are supported. Example: INCBIN, INCDIR, CODE\_C, REPT, RS, RSRESET, EQU, REG, OFFSET, XDEF, XREF, PUBLIC, ...
- o Further development and support is guaranteed for years, because I'll \*never\* change my system.
- o Finally: Although Shareware, there are no disabled functions in PhxAss!

You will find four different versions of PhxAss in this distribution:

1. PhxAss: The standard 680x0,FPU,MMU macro assembler.
  2. SmallPhxAss: This is a 68000 only version without floating point support. As a result the program is much smaller.
  3. FreePhxAss: This program is FREEWARE! It is intended for developers of PD-Compilers, who want to include PhxAss in their compiler package.
-





```

_d" LEGAL__E# __\ensuremath{\lnot}\textdegree{}#ÑmJØ EQ$\mathrm{\mu}$_\$ \leftarrow
  \mathrm{\mu}$ØP , #P , $\mathrm{\mu}$*$@@@*ÑØ E@" _æE\textdegree{} ¶\$ \leftarrow
  \mathrm{\mu}$
_P æØ@#ØP JØ#æ_ \ensuremath{\lnot}\textdegree{}#Ø ØØMÑØ" $\mathrm{\mu}$Ø \leftarrow
0 ØF _æØF __æ*"OTHER nET\ensuremath{\lnot}Ø
_P \ensuremath{\lnot}g_\ensuremath{\lnot} *P\textdegree{}"-__æ# ØMw_ \leftarrow
çÑØP l OE ØM^- æ@" &FULL aMinET\ensuremath{\lnot}Ø
E æØ\textdegree{}" _ *EØØZØF JØØP _$\mathrm{\mu}$_\ensuremath{\lnot}' \leftarrow
JK \ensuremath{\lnot}#K \ensuremath{\lnot}# #W_ mIRROr \ensuremath{\lnot} \leftarrow
lnot)K
J' 4nODES \ensuremath{\lnot}qæ J#æ$\mathrm{\mu}$_\ensuremath{\lnot}\textdegree \leftarrow
{}ÑØP ÍØK $\mathrm{\mu}$$_\ensuremath{\lnot}¶qç Øm \ensuremath{\lnot}#m_ JØ _ \leftarrow
\textdegree{}#m_ ¶
Ø sYSTEM _áØ ØØ#P\textdegree{} __E EL_dØØØ#mJ# Ø@#_ ¶ÑwØF JØ*_ \textdegree \leftarrow
{}#m_ oNLINE L
# _EØÑ$^2$ __$\mathrm{\mu}$$_\mathrm{\mu}$æ@"" ---- __EP#_ 2Q_\leftarrow
ensuremath{\lnot}q_\ensuremath{\lnot}¶Ø EF \ensuremath{\lnot}*_ \textdegree{}# \leftarrow
m_ sINCE `88 l
Q ¶E__$\mathrm{\mu}$m@P"^-æØØMÑæ æ@çççç¶¶P _æ#MØØÑ#mEÑ#mæ" _æØm*_ ã# \leftarrow
F
¶ \ensuremath{\lnot}¶\textdegree{}^- \ensuremath{\lnot}¶L \ensuremath{\lnot} \leftarrow
lnot}¶#ØQ_ _æEØP"^- \textdegree{}# OE_æØ\textdegree{} 2@ \ensuremath{\lnot} \leftarrow
lnot}¶" JF
\ensuremath{\lnot}L lOcal rAtes __JØ _ \ensuremath{\lnot}¶ÑÑm_æØP"__æ*M\ \leftarrow
\textdegree{}ØL JL JØØ\textdegree{} aE" Ø
¶_fRom hAmburg aEÑØØ# Ø#m_ \ensuremath{\lnot}\textdegree{}#ØP ,ØP^- _ØP J& P \leftarrow
_E" a3000/1.5giga J'
#_ \ensuremath{\lnot}#_ \ensuremath{\lnot}' J#P\textdegree{}" __aK \$ \leftarrow
\mathrm{\mu}$# _Ø@_ØØ E" mULTIFACECARD ,K
¶_ E@\textdegree{} +æMØØ# ØP _æØF _ØP _ OK IsdN-mASTER $ \leftarrow
\mathrm{\mu}$F
¶m_ \ensuremath{\lnot}*\mathrm{\mu}$r #m__ \ensuremath{\lnot}¶Ñ# \leftarrow
0#__æØ@'_dP _Ø#L J# _Ø'
\ensuremath{\lnot}¶w_ _ØP áØØ#P^ _Øh_ ¶#Ø\textdegree{} _æ@"_Ø \leftarrow
\textdegree{} J& OK _æP
\ensuremath{\lnot}¶w_ _æØØÑ " __$\mathrm{\mu}$$_\mathrm{\mu}$*$@\ \leftarrow
\textdegree{} \ensuremath{\lnot}q_ _æ#_Ø\textdegree{} ¶L J# \leftarrow
_ØP
\ensuremath{\lnot}¶æw_ ¶#^-__$\mathrm{\mu}$m@P"^- \ensuremath{\lnot} \leftarrow
}¶P" \ensuremath{\lnot}\textdegree{} \ensuremath{\lnot}¶" \leftarrow
_æ#\textdegree{}
\ensuremath{\lnot}¶æw2¶M\textdegree{}^-LINK tO tHE oNLY lIVING wITNESS! \leftarrow
__$\mathrm{\mu}$$_\textdegree{}^-
\ensuremath{\lnot}\textdegree{}¶æw_____ \leftarrow
__$\mathrm{\mu}$$_æ#P"
\ensuremath{\lnot}\textdegree{}¶Ñæm$\mathrm{\mu}$ F-E-A-R E- \leftarrow
H-Q $\mathrm{\mu}$$_\mathrm{\mu}$*$@¶\textdegree{}^- [/\] \leftarrow
CliTroMax D-SigN
-----

```

### 1.3 Modifications since PhxAss V2.xx

Register symbols ( EQUr ) must be defined before they are used. This enables

a faster addressing mode recognition.

There are some new optimizations possible. The optimize-flags which can be specified after `-n` (since V4.00: OPT) or after the `OPT` directive have completely changed (see Command line parameters).

If you have enabled the `near-code` model, all jumps which are referencing external symbols are converted to PC-relative instead of long branch.

The `'*'`-symbol contains the current address. For example a `'bra *+10'` would branch to the location 12 bytes behind the `'bra'`-opcode.

New directives:

```
FPU
,
PMMU
,
CODE_C
,
CODE_F
,
DATA_C
,
DATA_F
,
BSS_C
,
BSS_F
and
INCDIR
.
```

The

```
instructions
and
addressing modes
of 68020-68060, 68851(PMMU)
```

and 6888x(FPCP) are completely supported. You can use Motorola's new addressing mode style even in the 68000 mode (e.g. `MOVE (4,A5),D0`).

The new addressing mode recognition has no difficulties with parentheses `'()'` instead of brackets `'[]'` to indicate a term. An operand like

```
-( [x|y]*z)+6([addr+2,A4,regxy*QSIZE],[outdisp+$10<<(1+3)]),((abc-xyz)+2,A3)
```

would cause no problems.

PhxAss enables floating-point numbers to be used with the 6888x (FPCP) instructions. For example: `fmove.d #3.1415926536,fp7`

moves the double-precision number pi to the FPCP register seven.

## 1.4 Modifications since PhxAss V3.00

V3.10:

- o PhxAss is able to optimize forward-branches, which are coming into their 8/16-bit range by optimization of the subsequent code. As a result, other forward-branches could come into range and are also optimized, and so on.

V3.30:

- o Symbols which are preceded by a '.' will be regarded as local symbols too.
- o A special version of PhxAss is available, which is not limited to the maximum number of 65535 lines.

V3.40:

- o Macro parameters may contain 63 characters now.
- o The extended addressing mode recognition accepts the register symbols ZD0-ZD7 and ZA0-ZA7 to specify a suppressed register.
- o Two new escape codes available:  
 \e = escape (\$1b) and \c = control sequence introducer (\$9b).

V3.42:

- o Float constants may be replaced by hex-constants now.
- o When branch-optimization is activated, no extension-checking takes place. The best-possible code will be generated.

V3.47

- o New optimization flag: 'I' forces PhxAss to ignore a 'Too large distance' error.

V3.50

- o '@' is allowed to be the first character of a symbol name, providing the second character is non-numeric.
- o The RORG directive is implemented.
- o Two Devpac-specific directives are also supported now:

RSRESET  
and  
RS.x  
for faster reading of (Devpac) include files.

- o The new option  
'-c' (V4:CASE)  
can be used to switch off the case-  
sensitivity.

### V3.51

- o  
RSSET  
was forgotten in V3.50
- o New directives:  
IDNT  
, COMMENT,  
SUBTTL  
V3.55
- o From now on  
near-data  
symbols can be accessed not only by Absolute  
Addressing but also by Address Register Indirect mode ( (An) must be the  
correct near-data base register). This will make the assembling of your  
source much faster, because PhxAss has to do less optimizations. As a  
side effect  
XREFs  
will be interpreted correctly and must not be re-  
placed by  
NREFs  
.
- o If no unit name is given (by  
TTL or IDNT  
) , PhxAss will use the name  
of the source code without extension as the default unit name.
- o The  
OFFSET  
directive is supported.

### V3.60

- o PhxAss V3.60 is pure! You can use the CLI-command RESIDENT to add it to  
the resident list.

### V3.70

- o '.W' and '.L' displacement-extensions for explicitly activating the 68020  
base-displacement mode.

### V3.71

- o  
PROCSTART/PROCEND  
directives for compatibility with DICE-C.

### V3.75

- o Immediate values are checked for their correct size. For example a  
MOVE.B #\$1234,D0 will lead to an error now.

### V3.80

---

- o New option
  - '-w' (V4:ERRORS)
  - to determine the maximum number of errors
  - which will be displayed before a request.
- o The addressing mode syntax is checked much sharper (e.g. former versions accepted "(SP)-").

## V3.81

- o
  - DC.W / DC.L
  - strings must no longer be aligned (e.g. DC.L "x" -> \$00000078).

## V3.90

- o PhxAss was completely localized using the "locale.library". Available languages (August '94): english, german, polish.
- o Documentation converted to AmigaGuide format.

## V3.92

- o New option
  - '-v' (V4:VERBOSE)
  - for displaying the names of all include files and macros, which are accessed during assembly.
- o New directive
  - ELSEIF
  - for DevPac compatibility.
- o Protection flags for created files will be "rw-d" now.

## V3.94

- o The immediate value of BTST, BSET, BCLR and BCHG is checked for valid range (0..7 or 0..31).
- o You will need to enable (s)pecial optimization, to remove a ZRn-index. I think, if somebody explicitly writes 'ZRn', he doesn't want it to be removed by (n)ormal optimization.

## V3.95

- o From now on, it is possible to shift distances! Example:
 

```
move.w    #(label2-label1)>>1,d0
```

 Although this is the same as "(label2-label1)/2", division and multiplication is not allowed on distances, use right- or left shift instead. You might find it useful to use e.g. "((label2-label1)>>1)-1" to initialize the counter for a DB<cc>-loop - but be careful! Addition and subtraction after a distance-shift is not really supported, although it seems to work in this special case, if the distance between label1 and label2 is even.
 

The reason is, that the shift is always executed last, which means that the "-1" doesn't affect the result of the shifting but the result of the distance directly.

## V4.00:

- o Conversion to OS 2. New command line parsing, using ReadArgs(), and new argument names.
- o Automatic generation of executable load files. You no longer need to start the linker, if your code doesn't make use of external references. This feature can be disabled by using the CLI parameter
  - NOEXE
  - .

- o Source Level Debugging support! By using the CLI parameter  
LINEDEBUG  
,  
PhxAss creates a Line Debug block for each section, which contains the addresses of each source code line.
- o Extended operand buffer from 80 to 128 characters.
- o Floating point symbols and constants can be used in expressions of any complexity (like integers) now. PhxAss supports five binary operators, +(plus), -(minus), \*(mult.), /(division), ^(power), and six unary operators: SIN(sine), COS(cosine), TAN(tangent), EXP(exponent), LOG(nat. logarithm), SQR(square root).
- o New directive  
SET.x  
for alterable floating point symbols.
- o New directive  
INT  
for assigning a float expression to an integer  
SET-symbol.
- o  
REPT ... ENDR  
directives, like with DevPac.
- o Floating point symbols in a listing file are displayed as floats instead of hexadecimals.
- o Float symbols do appear in an equates file.
- o Two new standard optimizations (which I must have forgotten in former versions):  
1. move.l #0,An -> suba.l An,An      2. move.l #x,An -> move.w #x,An
- o New Small Data Mode: By writing  
NEAR A4,-2  
only the sections which are named "\_\_MERGED", will be regarded as small data sections (similar to SAS/C).
- o 68060 instructions implemented! (except PLPA, because it was impossible for me to get its code).

## 1.5 Modifications since PhxAss V4.00

### V4.01:

- o The INCLUDE directive does no longer ignore a label in the same line.
- o Implemented abbreviations 'I' for 'INCPATH' and 'H' for 'HEADINC'.

### V4.05:

- o Code Sections are padded with \$4E71 (NOP) instead with \$0000.
- o PhxAss accepts the DevPac options 'C', 'D', 'L' and 'O'.
- o "DS.L 0" corresponds to "CNOP 0,4", "DS.Q 0" corresponds to "CNOP 0,8", etc.. Previously it works only with "DS.W 0".

### V4.10:

- o Operand may contain blanks. Example: 'DC.B 1, 2, 3, 4'
  - o Operators may have the same priorities! Examples: '\*' and '/' or '<<' and '>>'.
  - o INCDIR "" is allowed for compatibility reasons.
-

- o Operands may contain up to 511 characters (127 before V4.10).
- o New parsing routines accelerate PhxAss by 5% - 25% !
- o Swedish catalog.

## V4.12:

- o New directive for compatibility:  
DX  
. Behaves the same like DS.
- o The 68060 instructions  
PLPAR and PLPAW  
are implemented!
- o When assembly fails, PhxAss quits with a return code of 20 instead 1.

## V4.14:

- o Implemented the  
\_\_RS  
symbol.
- o PhxAss checks for conflicts between macro names and directive or instruction names.
- o "" and '' within a string are recognized as a single ' or " character.
- o If a code section ends with a minimum of eight zero-bytes, no NOP-padding will be performed.
- o Italian catalog.

## V4.15:

- o Improved the compatibility with old Seka-sources. The '=' (EQU) directives and labels, terminated by a ':', must no longer be separated from the rest of the line with blanks or TABs.
- o Because of numerous requests, symbol names are allowed to contain dots ('.'). But beware of terminating your symbols with ".w" or ".l"!
- o The new directive  
SFORM  
enables the output of Motorola S-Records  
in absolute mode.
- o Danish catalog.

## V4.16:

- o Increased the number of possible macro parameters to 15. Parameter 10 to 15 can be accessed by '\a' to '\f'.
- o New CLI-Parameter "RC=ERRCODE/K/N" for defining the return code in case of an error.

## V4.18:

- o MOVEQ #x,Dn with 128<x<255 will force PhxAss to display a warning, which can be disabled by the new NOWARN/S option.
- o Increased the number of possible macro parameters again. Now there are 36 parameters possible! (\0 - \9 and \a - \z)
- o Increased the buffer sizes from 512 to 1024 bytes.
- o French catalog.

## V4.19

- o Relocatable symbols will be suffixed by a ' in the listing file.
- o SECTION allows a numerical third parameter to select the type of the section (should be \$40000000 or \$80000000, of course!).
- o Freeware-PhxAss assembles 68030-060, FPU and MMU code too.

## V4.20

- o Dutch catalog.
- o
  - EQR
    - works with register symbols.
- o New directive
  - FREG
    - . It's like
    - REG
      - , but for the FPU registers.
  - So FMOVEMs without any registers, which could be generated by a compiler, can be removed by optimization.
- o Support for PHXOPTIONS option files, which are created by PhxOpts from Johan Johanssen. PhxOpts offers a GUI for presetting the options of PhxAss. But of course, the command line options have still priority.
- o PHXASSINC has moved to ENV:PhxAss/ like the global PHXOPTIONS.
- o New directives
  - SAVE
    - and
    - RESTORE
      - to save name and type of the
  - current section. Useful in macros.

#### V4.21

- o When an error occurs inside a macro, PhxAss will additionally display the line number and source text name from where the macro was invoked.

#### V4.23

- o Implemented the special 68060 debugging instructions HALT and PULSE (for completeness only ;)

#### V4.25

- o New directive IF, as an alias for IFNE.

#### V4.26

- o Two new directives,
  - DEBUG
    - and
    - DSOURCE
      - , enable the generation
  - of source level debugging information for high level languages too.
- o With
  - Branch Optimization
    - enabled, PhxAss can convert a B<cc>.w instruction, which is out of range (in 68000 or 68010 mode), into a B<!cc>.b/JMP combination.

## 1.6 Bug fixes since V2.11

- o Some instructions had generated a wrong error, e.g. TRAP and STOP generated 'Assembly aborted' instead of 'Out of range'.
- o 'move.l #xxxx, -(a0)' produced an illegal opcode.
- o If someone writes a program without first opening a section with CODE/ CSEG, SECTION or an initial label, all labels got wrong values.
- o In some cases the equates file let PhxAss crash.



- o A XDEF for a symbol which was already defined in another section would add this symbol to the external-hunk of the section currently active.
- o Jump to Branch optimization did not check the addressing mode of the JMP/JSR instruction. It simply optimized all modes.
- o A long branch to the next instruction was incorrectly optimized to \$6x00.
- o B<cc>.B was not recognized as a short branch. PhxAss accepted only B<cc>.S.
- o The CNOP directive had disabled all optimizing in its section.
- o The 'Word at odd address'-error crashed PhxAss sometimes.
- o INITNEAR was useless in the absolute mode.

## 1.7 Bug fixes since V3.00

V3.01 (03.03.93)

- o The 68020 addressing-mode ([Rn]) was assembled with a wrong size in pass one.

V3.02 (20.04.93)

- o TRACKDISK now really works.

V3.05 (30.05.93)

- o The near-data range was incorrectly limited to 32k in object files.
- o The formatted text-output should also work on OS2.xx/3.xx now.
- o MOVE USP,An , MOVES and MOVEP produced incorrect code.
- o GLOBAL and BSS destroyed the MSW-bits of the BSS-hunk type (\$000003eb).

V3.10 (04.06.93)

- o PhxAss didn't accept octal numbers (@xxx).

V3.11 (06.06.93)

- o CNOP definitely bug-free (I hope).
- o CMPI #x,(PC) (>=68020)

V3.12 (08.06.93)

- o Width 32 was impossible for bit fields.

V3.15 (12.06.93)

- o Fixed bug with MOVEM-optimization.

V3.20 (03.07.93)

- o References on "\@"-labels behind another macro nesting were impossible.

V3.21 (05.07.93)

- o "\@" only allowed 999 macro calls (now it's unlimited).

V3.22 (06.07.93)

- o Some extended addressing modes had made some problems:  
([..],Rn.s|\*x,od) and ([PC.. got a wrong size in pass one,  
([BaseDisp]) generated an error and (bd,An/PC,Xn) (where bd is outside  
of the normal 8-bit range) crashed PhxAss.

V3.25 (17.07.93)

- o Fixed bug with MOVES.
  - o FETOXM1 was forgotten (in my Reference Manual too).
-

V3.26 (18.07.93)

- o TAB-Codes within strings could not be expanded.

V3.30 (25.07.93)

- o Fixed bug with extended addressing modes (`[..],Rn.x/*y,od`), (`[pc],..`) and (`[pc,Rn],..`).

V3.31 (28.07.93)

- o INITNEAR was useless in small-data mode.

V3.40 (07.08.93)

- o Include paths which are suffixed by a ':' (volume names) were not recognized.
- o FMOVE.M L Dn,FPcr got four bytes more in pass one than in pass two.
- o Starting with page 100 the listing file became unreadable.
- o The 'Out of memory' error was useless, because PhxAss crashed in most cases.
- o CPUSHL,CINVL,CPUSHP,CINVP didn't work.
- o BTST Dn,#x was missing.

V3.42 (24.08.93)

- o The new forward-branch optimization destroyed the CNOP-alignments, which are located between the branch-instruction and the branch-destination.

V3.46 (02.09.93)

- o PhxAss tried to optimize "MOVEP (d16,An)" with d16=0 into "MOVEP (An)". This was a bug!

V3.50 (15.09.93)

- o Fixed bug with the '\*'-symbol, containing the address of the current line.
- o ".local" was impossible with float symbols.

V3.57 (22.09.93)

- o PTESTR/PTESTW (68030) ignored the fourth operand.

V3.58 (23.09.93)

- o NARG was not zero for a macro call without arguments.
- o INCLUDE/INCBIN without quotes caused an error.

V3.61 (02.10.93)

- o IFC '\1','' only behaved reliable if \1 was not used before.

V3.64 (24.11.93)

- o The 16/32-bit displacements in the PC Indirect with Index addressing mode were wrong (+2 Bytes).

V3.65 (10.12.93)

- o Fixed bugs in AbsLong->AbsShort and Logical Shifts optimization.

V3.70 (15.12.93)

- o Fixed bug with (d16,An,ZRn) and (bd,PC).
- o PhxAss tried to optimize CMPI #x,AbsLong always to PC-relative, which caused an 'Illegal Addressing Mode' error in 68000/010 mode.

V3.76 (07.04.94)

- o Another bug in forward-branch optimizing (T-flag) made a mess with the object file in some specific cases.
-

- o An illegal Bcc.B \*+2 was converted into Bcc.W \*+2 instead of Bcc.W \*+4.

V3.77 (21.04.94)

- o More than 13 sections in a file had lead to a crash or an infinite loop.

V3.78 (27.04.94)

- o When PhxAss discovered an error in a line  $\geq 32768$  it didn't show neither the line-counter nor the incorrect line itself (now it works until 65000).

V3.79 (01.05.94)

- o Absolute addressing with parentheses caused a Syntax Error.  
E.g.: "move.w label+(x+y)\*z", but "move.w (x+y)\*z+label" works.

V3.90 (16.09.94)

- o Macro arguments which contained a comma (e.g. (d,An)) were unusable.

V3.93 (25.09.94)

- o An explicit B<cc>.L was calculated 2 bytes too short in 020+ mode and 2 bytes too far in normal mode.

V3.94 (09.10.94)

- o The code generated by MOVE.B #-1,d0 (also: cmp, and, or, eor, etc.) was \$103C \$FFFF, but the bits 8-15 of the first extension word are reserved, for a byte-instruction! Now PhxAss politely generates: \$103C \$00FF.
- o PhxAss changed (d,PC,ZRn) into (d,ZPC,ZRn).

V3.96 (23.10.94)

- o PhxAss crashed when the macro nesting depth exceeded 8.

V3.97 (01.11.94)

- o Distances, which are calculated by using a label directly behind a CNOP, were sometimes wrong.
- o Because of some speed-improvements in V3.96, macro-arguments in opcode could lead to an error.

V4.00 (26.12.94)

- o PhxAss crashed when a fixed number of include files were open.
- o There were still some problems with removing empty sections.
- o ELSEIF was documented, but not supported (forgotten).

## 1.8 Bug fixes since V4.00

V4.01 (07.01.95)

- o Multiplication now has a lower priority than Division/Modulo to prevent situations like:  $12/4*3 = 1$   
I know, '\*', '/' and '//' should have the same priorities, but currently my expression evaluation routines don't allow multiple operations at the same priority. Maybe I will completely rewrite them, in the future.

V4.05 (25.01.95)

- o FreePhxAss didn't create an object file!!! :((( (very ugly bug)
- o The NOT operation (~) didn't pay attention to the operation size of the current instruction. So "move.b #~\$80,d0" generated an error 97.
- o An empty section, which was automatically removed during creation of

- o an object file, deleted all XREFs of the subsequent sections.
- o \" and \" made still some problems within strings.
- o Macro parameters in the opcode field only worked, when using capital letters.

V4.10 (09.02.95)

- o INCLUDE and INCBIN didn't work, if the file name contains blanks.

V4.11 (21.02.95)

- o A numerical value within the command line, e.g. with "SMALLDATA x,y" crashes the system. It resulted from the massive changes in V4.10! :(

V4.14 (19.03.95)

- o Beginning with error-message 89, the locale catalogs generated the wrong message.

V4.15 (30.04.95)

- o If your source contains not a single byte, PhxAss sometimes crashed.

V4.16 (13.05.95)

- o As a result of improvements in V4.15, the
  - OPT
  - parameter didn't
 work. :(

V4.17 (18.05.95)

- o MOVE16 didn't work with absolute addresses less than \$8000.

V4.18 (07.06.95)

- o #'"' and #'"' failed since V4.15.

V4.19 (27.06.95)

- o Long range branches, which were explicitly defined as Byte branches, were made to Word instead Long. This caused an error in the following branch optimization.
- o Distance shifts didn't work with equates (EQU).
- o Distance shifts didn't get the correct value in the listing file.
- o Forgot to close two math-libraries during clean-up.

V4.20 (12.08.95)

- o Usage of scaling in 68000 mode will generate an error message now.
- o ASL will be optimized to ADD by
  - (n)ormal optimization
  - (if
  - possible).
- o
  - \@
  - generates '\_000' labels instead '000'. So you will be no longer forced to change you exec/types.i include file.
- o It is possible again, to create an object file which contains only absolute
  - XDEFs
  - . It was already possible before v4.00, I think. ;)
- o Now you will get an error message, when a symbol inside a macro was defined twice.
- o When both Data and Bss sections were empty in small data mode, PhxAss generated an object file with 65535 size fields in the hunk header.

## V4.21 (20.09.95)

- o The expression X in d(X) or (d,X) was ignored, if not a register. Now it generates a Syntax Error.
- o Missing Byte/Word range check in DC, DCB and BLK implemented.
- o In a situation where the system runs out of memory the error message 'Shift error' was displayed instead 'Out of memory'.

## V4.22 (22.09.95)

- o Since v4.20 an expression may be preceded by a '+'. Unfortunately, that was not the case with float expressions.

## V4.23 (03.10.95)

- o Operation size ist checked much stricter. It was possible to write MOVE.P for example, and PhxAss generated wrong code without a warning. Additionally, things like SWAP Dn,Dm are no longer supported... ;)
- o Because of the stricter expression checking in V4.21, operands like ea{x:y} did no longer work.

## V4.24 (08.10.95)

- o The domino-effect in fwd-branch optimization leads to wrong branch destinations in some specific cases.

## V4.25 (15.11.95)

- o Symbols which are terminated by .W or .L created an "Undefined Symbol" error since v4.21.
- o Negative RORG offsets are forbidden.
- o S-optimization MOVE.x #0,An -> CLR.x An disabled.
- o Bug in S-optimization PEA 0.L -> CLR.L -(SP) shifted the following symbols by two bytes.
- o OPT N has absolute priority against OPT P. Thereby MOVE.L #0,An can be optimized to SUBA.L An,An instead LEA 0.w,An, in spite of activated P-optimization.
- o PhxAss crashed on encountering a not terminated string, as e.g. MOVE #"abc,<ea>.
- o The bitfield instructions BF??? (d,An){x:y} didn't work since v4.21.
- o FMOVEM.x label,<freglist> created a "Bad register list" error.
- o DC.? "xxx" is treated as expression instead as a string, if "xxx" fits into the given data size. Thereby DC.L "DOS"<<8 for example, is allowed again.
- o DC.? ("xxx") generated a syntax error in pass 1.
- o FILE, TTL and SFORM enable arguments without " or ', as with INCLUDE or INCBIN.

## 1.9 Starting PhxAss

PhxAss can be used from CLI only. You should copy it to "C:" or ↵  
set a path

or link to its directory. If you know, you will need PhxAss very often, I recommend to make it resident by typing "Resident C:PhxAss".

Format: PhxAss [FROM] <source file> [TO <output file>] [OPT <opt flags>]  
[EQU <equ file>] [LIST <list file>] [INCPATH {<include paths>}]

```
[HEADINC {<include files>}] [PAGE=<n>] [ERRORS=<n>]
[ERRCODE=<n>] [SMALLDATA <basReg>,[<sec>]] [SMALLCODE] [LARGE]
[VERBOSE] [SYMDEBUG] [LINEDEBUG] [ALIGN] [case] [XREFS] [QUIET]
[NOWARN] [SET "<symbol>[=<n>][,<symbol>...]" ] [NOEXE]
```

Template: FROM/A, TO/K, OPT/K, EQU/K, LIST/K, I=INCPATH/K, H=HEADINC/K, PAGE/K/N, ERRORS/K/N, RC=ERRCODE/K/N, SD=SMALLDATA/K, SC=SMALLCODE/S, LARGE/S, VERBOSE/S, DS=SYMDEBUG/S, DL=LINEDEBUG/S, A=ALIGN/S, C=CASE/S, XREFS/S, Q=QUIET/S, NOWARN/S, SET/K, NOEXE/S

Starting PhxAss with no argument or with a single '?' will display a short description. For a more precise description of all arguments, refer to

Command line arguments

.

When PhxAss is running, it can be stopped at any time by holding CTRL-C.

## 1.10 Command line arguments

The standard version of PhxAss understands the following arguments ←  
:

FROM/A [FROM] <source file>	The only parameter, which is always required, is the name of your source code file. If this name has no extension, PhxAss automatically assumes ".asm" for being the extension. The source code must be an ASCII text file, where each line is terminated by a line feed (\$0a) character (the format, which all Amiga editors should generate). TAB-codes (\$09) are allowed and completely supported.
TO/K TO <output file>	Defines the name of the output file. If not specified, PhxAss takes the source code's filename and replaces its extension by ".o" . If PhxAss is able to create an executable file instead of an object module, the ".o"-extension will be removed.
EQU/K EQU <file name>	Generates an equates file. If the <file name> is "*", the name of the source code with extension ".equ" will be used. Since V4.00 equates files can also contain floating point equates.
LIST/K LIST <file name>	Generates a listing file. If the <file name> is "*", the name of the source code with extension ".lst" will be used.
PAGE/K/N PAGE=<lines>	Determines the page length for equates and listing files. If <lines> equals zero, no form feed (\$0c) characters will be generated. The default value is 60 lines.

XREFS/S  
XREFS                   Appends a reference list with all global symbols in the listing file. If no listing file was opened, this switch will cause an error.

I=INCPATH/K  
I <path1>[,<path2>,...] by the INCLUDE and INCBIN directives. The paths, specified by INCPATH/K, are used directly after the path, specified by the environment-variable PHXASSINC, has failed. Important: If the path- or file names after INCPATH or HEADINC contain blanks, you should embrace \*all\* names with quotation marks and not only the one, which contains blanks. Example:  
INCPATH "include:,dh1:inc dir" ←

H=HEADINC/K  
H <incl>[,<inc2>,...]   Creates one or more INCLUDE directives at the top of your source code. See also: INCPATH.

DS=SYMDEBUG/S  
DS                       The names of all global labels of each section are stored to symbol data blocks. A debugger can use these names instead of addresses.

DL=LINEDEBUG/S  
DL                       PhxAss creates a linedebug block, which can tell a Source Level Debugger the right line in your source code for any address. The location of your source is stored in this block with a complete path, e.g. "Work:Programs/Assembler/Tools/Source/Test.asm" (this is, for example, not the case with SAS's ASM :-).  
Compilers should use the directives  
DEBUG  
and  
DSOURCE  
instead this option.  
A useful PD-Debugger with source level debugging capabilities is for example "PowerVisor v1.42", which can be found on Aminet dev/debug/pv142.lha or on the GoldFish-CD.

SD=SMALLDATA/K  
SD <basReg>[,<sec>]   Forces all sections to use the small data model. <basReg> (default: 4 ) specifies the number of the address register which will be used as pointer to the small data section. Only the registers A2-A6 can be used. <sec> is the number of the section which will be your small data section (defaults to -2). If <sec> is -1, all Data and Bss sections will be treated as a whole small data section. If <sec> is -2, only the sections which are named "\_\_MERGED", will be added to small data.

SC=SMALLCODE/S           Forces PhxAss to use the small code model. All JSR

---

---

SC and JMP instructions which are referencing external (XREF) symbols are converted to PC-relative 16-bit jumps.

LARGE/S Forces PhxAss to use the large code and large data model in all sections.  
LARGE

NEAR directives within the source code will be ignored.

SET/K Predefines a symbol by  
SET directive.

SET "<symbol>[=<val>]" Definition of multiple symbols must be separated by commas. <val> default to 1, when missing. Don't forget the to embed the whole term, which follows SET, in quotes (because of some problems with ReadArgs()) !

A=ALIGN/S Enable auto-align for  
DC.x directives. All DC.W,  
A DC.L, etc. directives in the code will be automatically aligned to word-boundaries.

C=CASE/S Case-sensitivity off. All symbol names will be converted to upper case. This will slow down PhxAss by 5%.  
C

NOWARN/S Disables the output of warning messages.

ERRORS/K/N Determines the maximum number of error-messages to be displayed before a "continue?"-request. If  
ERRORS=<max errors> <max errors> is zero, PhxAss will never stop to perform a request.

RC=ERRCODE/K/N Defines the Shell return code in case of an error.  
RC=<rc> <rc> defaults to 20.

VERBOSE/S Displays the names of all include files and macros, which are accessed during assembly. This can be helpful to locate errors with macros.  
VERBOSE

Q=QUIET/S Quiet mode. PhxAss makes no outputs until an error occurs.  
Q

NOEXE/S PhxAss always tries to create an executable load file, instead of an object module, which requires the additional use of a linker. NOEXE forces PhxAss to create object modules in any case.  
NOEXE

OPT/K Sets the optimize flags. The following characters, without embedded blanks, can be specified after 'OPT':  
OPT <flags>

0 (None)  
No optimizing allowed. This flag should always

---



stand alone.

#### N (Normal)

Standard optimizations:

```

clr.l Dn          -> moveq #0,Dn
move.l #x,Dn      -> moveq #x,Dn
move.l #0,An      -> suba.l An,An
move.l #xxxx,An   -> move.w #xx,An
link.l(68020)     -> link.w
adda/suba        -> lea
($xxxx).L        -> ($xx).W
(0,An)           -> (An)
asl #1,Dn        -> add Dn,Dn
asl.w/b #2,Dn    -> add Dn,Dn  add Dn,Dn

```

#### R (Relative)

```
($xxxx) -> (xx,PC)
```

#### Q (Quick)

Conversions into addq/subq

#### B (Branches)

```

Bcc.l(020) -> Bcc.w -> Bcc.b, jmp/jsr -> bra/bsr
Bcc.w(000/010) -> B!cc.b, jmp

```

Example:

```

                beq.w  label
will be converted into ->
                bne.b  *+8
                jmp    label

```

if the distance until label is greater than 32766 bytes.

#### T (Total branch optimization)

```

Bcc.l(020) -> Bcc.w -> Bcc.b (forward branches)
Only active if 'B' is also selected.

```

WARNING! If you use this option together with a listing file, then you can't rely on the line-addresses in it.

#### L (Logical Shifts)

```

lsl #1,Dn -> add Dn,Dn
lsl.w/b #2,Dn -> add Dn,Dn + add Dn,Dn

```

#### P (PEA/LEA conversion)

```

move.l #x,An -> lea x,An
                -> lea (x,PC),An / lea x.w,An
move.l #x,-(SP) -> pea x -> pea (x,PC) / pea x.w

```

#### S (Special optimizations)

```

pea 0 -> clr.l -(SP)
add/sub #0,An / lea (0,An),An -> (removed)
(d,An,ZRn) -> (d,An) -> (An)
(d,PC,ZRn) -> (d,PC)

```

The following are not recommendable for a MC68000 accessing hardware registers:

```

move #0,<ea> -> clr <ea>
move.b #-1,<ea> -> st <ea>

```

M (MOVEM/FMOVEM)  
movem Rn,<ea> -> move Rn,<ea>  
movem ,<ea> -> (removed)  
fmovem ,<ea> -> (removed)

I (Ignore too large distances)  
Distances, which are currently out of range will not cause an error. This is sometimes useful for assembling reassembler-outputs or when you're sure that all distances will come into range again, by optimization of the subsequent code. BE CAUTIOUS!!! If a distance has not come into range, PhxAss creates faulty code!

There are two short cuts, which usually stand alone:

\* Selects all standard optimizations & T  
(OPT nrqbt).

! Enables all optimizations possible  
(OPT nrqbtlpsm).

If OPT is not specified the assembler uses standard optimization (OPT nrqb).

The Freeware version of PhxAss does not support the following arguments:

EQU, LIST, XREFS, PAGE, INCPATH, HEADINC, VERBOSE, CASE

## 1.11 Programmer Information

Comments

Labels

M68000 Instructions

Expressions

Assembler Directives

Compiler Compatibility

PhxOpts

Environment Variables

---

## 1.12 Comments

Comments start with a ';' or with an '\*'.

Example:

```
; Comment text
    moveq    #0,d0
** This is a comment too **
    nop                                ; comment
    add.l   d0,d0                       * another comment
```

If no operand field is given, e.g. after the NOP instruction, the comment must be preceded by a ';'. Examples:

```
    nop    * comment                -> Error!
    nop    comment                   -> Error!
```

## 1.13 Labels

Labels must start in the first column of a line. The colon after a label is optional. You must insert a blank or TAB between label and opcode, if you decide to omit the colon.

Example:

```
Label:  moveq    #0,d0
```

Local labels have a '\$' suffixed or are preceded by a '.' (since V3.30). They are only valid between two global labels.

Example:

```
Global1: add.w    d0,d1
        beq.s    local1$
        bpl.s    .local2
        rts
local1$: moveq    #-1,d0
.local2: rts
Global2:
```

The length for global and local labels is unlimited. Valid characters for the labels are: 'a'-'z', 'A'-'Z', '0'-'9', '\_' and '.' (since V4.15). The first character may be an '@' (providing the second character is non-numeric). Global labels cannot start with a digit.

The special '\*'-symbol always contains the address of the current source code line. This enables instructions like: bra \*+4

CAUTION! Forward references with '\*' will be corrected by PhxAss, but backward references won't! I recommend to use labels, if you want to be really safe.

## 1.14 Executable M68000 instructions

General Format

Standard Addressing Modes

Extended Addressing Modes

Suppressed Registers (020+)

M68000 Instruction Overview

## 1.15 General Format

A line of an assembler source text has the general format:

```
<label>      <opcode>      <operands>
```

PhxAss recognizes all operations found in Motorola's M68000PM/AD Programmer's Reference Manual and all of the common additions and short forms like BHS instead of BCC, BLO instead of BCS, MOVE instead of MOVEA, ADD instead of ADDI, etc. . In the current version all MC68000, 68010, 68020, 68030, 68040, 68060, 68851, 68881 and 68882 instructions are completely supported.

Labels must start at the first column. Opcodes (M68000 instructions or assembler directives) and operands must have at least one preceding blank.

The operand field consists of one, two, three or four (68851) operands, separated by a comma. Embedded blanks are allowed since V4.10.

## 1.16 M68000 Standard Addressing Modes

The notational conventions used in this section are:

EA	- Effective address
An	- Address register n
Dn	- Data register n
Xn.SIZE	- Denotes index register n (data or address) and index size (W for Word or L for Longword)
PC	- Program counter
dn	- Displacement value, n bits wide
( )	- Identify an indirect address in a register

Data Register Direct

```
Syntax:      Dn
Generation:  EA = Dn
Extension Words:  0
```

Address Register Direct

```
Syntax:      An
Generation:  EA = An
```

Extension Words: 0

Address Register Indirect

Syntax: (An)

Generation: EA = (An)

Extension Words: 0

Address Register Indirect with Postincrement

Syntax: (An)+

Generation: EA = (An), An = An + SIZE

Extension Words: 0

Address Register Indirect with Predecrement

Syntax: -(An)

Generation: An = An - SIZE, EA = (An)

Extension Words: 0

Address Register Indirect with Displacement (16-Bit)

Syntax: (d16,An) or d16(An)

Generation: EA = (An) + d16

Extension Words: 1

Address Register Indirect with Index (8-Bit Displacement)

Syntax: (d8,An,Xn.SIZE) or d8(An,Xn.SIZE)

Generation: EA = (An) + (Xn) + d8

Extension Words: 1

Program Counter Indirect with Displacement (16-Bit)

Syntax: (d16,PC) or d16(PC)

Generation: EA = (PC) + d16

Extension Words: 1

Program Counter Indirect with Index (8-Bit Displacement)

Syntax: (d8,PC,Xn.SIZE) or d8(PC,Xn.SIZE)

Generation: EA = (PC) + (Xn) + d8

Extension Words: 1

Absolute Short Addressing

Syntax: (xxx).W or xxx.W

Generation: EA given

Extension Words: 1

Absolute Long Addressing

Syntax: (xxx).L or xxx.L

Generation: EA given

Extension Words: 2

Immediate Data

Syntax: #xxx

Generation: Operand given

Extension Words: 1 or 2

## 1.17 68020+ Extended Addressing Modes

The notational conventions used in this section are:

EA	- Effective address
An	- Address register n
Dn	- Data register n
Xn.SIZE*SCALE	- Denotes index register n (data or address), the index size (W or L), and a scale factor (1, 2, 4 or 8)
PC	- Program counter
dn	- Displacement value, n bits wide
bd	- Base displacement
od	- Outer displacement
( )	- Identify an indirect address in a register
[ ]	- Identify an indirect address in memory

Address Register Indirect with Index (extension of standard format)

Syntax: (d8,An,Xn.SIZE\*SCALE)  
 Generation:  $EA = (An) + (Xn)*SCALE + d8$   
 Extension Words: 1

Address Register Indirect with Index and Base Displacement

Syntax: (bd,An,Xn.SIZE\*SCALE)  
 Generation:  $EA = (An) + (Xn)*SCALE + bd$   
 Extension Words: 1, 2 or 3

Memory Indirect Postindexed

Syntax: ([bd,An],Xn.SIZE\*SCALE,od)  
 Generation:  $EA = (bd + An) + Xn.SIZE*SCALE + od$   
 Extension Words: 1, 2, 3, 4 or 5

Memory Indirect Preindexed

Syntax: ([bd,An,Xn.SIZE\*SCALE],od)  
 Generation:  $EA = (bd + An + Xn.SIZE*SCALE) + od$   
 Extension Words: 1, 2, 3, 4 or 5

Program Counter Indirect with Index (extension of standard format)

Syntax: (d8,PC,Xn.SIZE\*SCALE)  
 Generation:  $EA = (PC) + (Xn)*SCALE + d8$   
 Extension Words: 1

Program Counter Indirect with Index and Base Displacement

Syntax: (bd,PC,Xn.SIZE\*SCALE)  
 Generation:  $EA = (PC) + (Xn)*SCALE + bd$   
 Extension Words: 1, 2 or 3

Program Counter Memory Indirect Postindexed

Syntax: ([bd,PC],Xn.SIZE\*SCALE,od)  
 Generation:  $EA = (bd + PC) + Xn.SIZE*SCALE + od$   
 Extension Words: 1, 2, 3, 4 or 5

Program Counter Memory Indirect Preindexed

Syntax: ([bd,PC,Xn.SIZE\*SCALE],od)  
 Generation:  $EA = (bd + An + Xn.SIZE*SCALE) + od$   
 Extension Words: 1, 2, 3, 4 or 5

The extended addressing modes have some ambiguities:

E.g. (0,A0) would be optimized to (A0) (one word), but maybe you want the

zero to be a 32-bit base displacement and you also want a suppressed D7 register. This instruction would have the same effect when executing, but it consists of eight words instead of one.

Since PhxAss V3.70 you only have to write: (0.L,A0,ZD7)

## 1.18 68020+ Suppressed Registers

The Memory Indirect Post/Preindexed addressing modes allow the programmer to suppress really everything. This means you may for example change the standard format ([bd,An,Xn.SIZE\*SCALE],od) into the following formats:

- o ([bd,An,Xn.SIZE\*SCALE])
  - o ([An,Xn.SIZE\*SCALE],od)
  - o ([bd],od)
  - o ([An])
  - o ([Xn.SIZE\*SCALE])
  - o ([An],od)
- etc...

If you want to specify the number of a suppressed register you can use the Zero-register symbols (ZRn, ZPC). By utilizing Zero-register symbols and the displacement extensions .W and .L you should be able to generate any 68020 instruction bit-pattern you want (maybe helpful for reassemblers).

A .W/.L extension after the first displacement will tell PhxAss to switch to base displacement mode and to disable optimizing for the current instruction.

The suppressed registers are represented by the following symbols:

- o suppressed data register D0-D7: ZD0-ZD7
- o suppressed address register A0-A7: ZA0-ZA7
- o suppressed PC: ZPC

It is impossible to EQUER suppressed registers!

## 1.19 M68000 Instructions supported by PhxAss

Integer Instructions for all processors

Integer Instructions 010,020,030,040,060 only

Integer Instructions 020,030,040,060 only

Integer Instructions 040,060 only

Integer Instructions 68060 only

MOVEC Control Registers

Floating Point Instructions 881,882,040,060

Floating Point Instructions 040,060 only

68851 PMMU Instructions

68030 PMMU Instructions

68040/060 PMMU Instructions

## 1.20 Integer Instructions (68000,68010,68020,68030,68040,68060)

ABCD	Dy, Dx	Add Decimal with Extend
ABCD	-(Ay), -(Ax)	
ADD.x	<ea>, Dn	Add
ADD.x	Dn, <ea>	
ADDA.x	<ea>, An	Add Address
ADDI.x	#<data>, <ea>	Add Immediate
ADDQ.x	#<data>, <ea>	Add Quick
ADDX.x	Dy, Dx	Add Extended
ADDX.x	-(Ay), -(Ax)	
AND.x	<ea>, Dn	And Logical
AND.x	Dn, <ea>	
ANDI.x	#<data>, <ea>	And Immediate
ANDI.x	#<data>, CCR	And Immediate to Condition Codes
ANDI.x	#<data>, SR	And Immediate to the Status Register
ASL/ASR.x	Dx, Dy	Arithmetic Shift Left/Right
ASL/ASR.x	#<data>, Dy	
ASL/ASR	<ea>	
B<cc>.x	<label>	Branch Conditionally
BCHG	Dn, <ea>	Test a Bit and Change
BCHG	#<data>, <ea>	
BCLR	Dn, <ea>	Test a Bit and Clear
BCLR	#<data>, <ea>	
BRA.x	<label>	Branch Always
BSET	Dn, <ea>	Test a Bit and Set
BSET	#<data>, <ea>	
BSR.x	<label>	Branch to Subroutine
BTST.x	Dn, <ea>	Test a Bit
BTST.x	#<data>, <ea>	
CHK.x	<ea>, Dn	Check Register Against Bounds
CLR.x	<ea>	Clear an Operand
CMP.x	<ea>, Dn	Compare
CMPA.x	<ea>, An	Compare Address
CMPI.x	#<data>, <ea>	Compare Immediate
CMPM.x	(Ay)+, (Ax)+	Compare Memory
DB<cc>	Dn, <label>	Test Condition, Decrement, and Branch
DIVS	<ea>, Dn	Signed Divide
DIVU	<ea>, Dn	Unsigned Divide
EOR.x	Dn, <ea>	Exclusive-OR Logical
EORI.x	#<data>, <ea>	Exclusive-OR Immediate
EORI.x	#<data>, CCR	Exclusive-OR Immediate to Cond. Codes
EORI.x	#<data>, SR	Exclusive-OR Immediate to Status Reg.
EXG	Rn, Rm	Exchange Registers
EXT.x	Dn	Sign Extend
ILLEGAL		Take Illegal Instruction Trap
JMP	<ea>	Jump
JSR	<ea>	Jump to Subroutine
LEA	<ea>, An	Load Effective Address



LINK	An, #<displacement>	Link and Allocate
LSL/LSR.x	Dx, Dy	Logical Shift Left/Right
LSL/LSR.x	#<data>, Dy	
LSL/LSR	<ea>	
MOVE.x	<ea>, <ea>	Move Data from Source to Destination
MOVEA.x	<ea>, An	Move Address
MOVE	<ea>, CCR	Move to Condition Codes
MOVE	<ea>, SR	Move to the Status Register
MOVE	SR, <ea>	Move from Status Register
MOVE	USP, An	Move User Stack Pointer
MOVE	An, USP	
MOVEM.x	<register list>, <ea>	Move Multiple Registers
MOVEM.x	<ea>, <register list>	
MOVEP.x	Dx, (d, Ay)	Move Peripheral Data (not 68060!)
MOVEP.x	(d, Ay), Dx	
MOVEQ	#<data>, Dn	Move Quick
MULS	<ea>, Dn	Signed Multiply
MULU	<ea>, Dn	Unsigned Multiply
NBCD	<ea>	Negate Decimal with Extend
NEG.x	<ea>	Negate
NEGX.x	<ea>	Negate with Extend
NOP		No Operation
NOT.x	<ea>	Logical Complement
OR.x	<ea>, Dn	Inclusive-OR Logical
OR.x	Dn, <ea>	
ORI.x	#<data>, <ea>	Inclusive-OR Immediate
ORI.x	#<data>, CCR	Inclusive-OR Immediate to Cond. Codes
PEA	<ea>	Push Effective Address
RESET		Reset External Devices
ROL/ROR.x	Dx, Dy	Rotate (without Extend) Left/Right
ROL/ROR.x	#<data>, Dy	
ROL/ROR	<ea>	
ROXL/ROXR.x	Dx, Dy	Rotate Left/Right with Extend
ROXL/ROXR.x	#<data>, Dy	
ROXL/ROXR	<ea>	
RTE		Return from Exception
RTR		Return and Restore Condition Codes
RTS		Return from Subroutine
SBCD	Dx, Dy	Subtract Decimal with Extend
SBCD	-(Ax), -(Ay)	
S<cc>	<ea>	Set According to Condition
STOP	#<data>	Load Status Register and Stop
SUB.x	<ea>, Dn	Subtract
SUB.x	Dn, <ea>	
SUBA.x	<ea>, An	Subtract Address
SUBI.x	#<data>, <ea>	Subtract Immediate
SUBQ.x	#<data>, <ea>	Subtract Quick
SUBX.x	Dx, Dy	Subtract with Extend
SWAP	Dn	Swap Register Halves
TAS	<ea>	Test and Set an Operand
TRAP	#<vector>	Take Trap Exception
TRAPV		Trap on Overflow
TST.x	<ea>	Test an Operand
UNLK	An	Unlink

Integer Condition Codes <cc>:

CC (HS) carry clear (higher or same) CS (LO) carry set (lower)

EQ	equal	F	never true
GE	greater or equal	GT	greater than
HI	higher	LE	less or equal
LS	less or same	LT	less than
MI	negative	NE	not equal
PL	positive	T	always true
VC	overflow clear	VS	overflow set

## 1.21 Integer Instructions (68010,68020,68030,68040,68060)

BKPT	#<data>	Breakpoint
MOVE	CCR,<ea>	Move from the Condition Code Register
MOVEC	Rc,Rn	Move Control Registers
MOVEC	Rn,Rc	
MOVES	Rn,<ea>	Move Address Space
MOVES	<ea>,Rn	
RTD	#<displacement>	Return and Deallocate

## 1.22 Integer Instructions (68020,68030,68040,68060)

BFCHG	<ea>{offset:width}	Test Bit Field and Change
BFCLR	<ea>{offset:width}	Test Bit Field and Clear
BFEXTS	<ea>{offset:width},Dn	Extract Bit Field Signed
BFEXTU	<ea>{offset:width},Dn	Extract Bit Field Unsigned
BFFFO	<ea>{offset:width},Dn	Find First One in Bit Field
BFINS	Dn,<ea>{offset:width}	Insert Bit Field
BFSET	<ea>{offset:width}	Test Bit Field and Set
BFTST	<ea>{offset:width}	Test Bit Field
CALLM	#<data>,<ea>	Call Module (68020 ONLY!)
CAS.x	Dc,Du,<ea>	Compare and Swap with Operand
CAS2.x	Dc1:Dc2,Du1:Du2,(Rn1):(Rn2) (020-040 only!)	
CHK2.x	<ea>,Rn (020-040 only!)	Check Register Against Bounds
CMP2.x	<ea>,Rn (020-040 only!)	Compare Register Against Bounds
DIVS.L	<ea>,Dq	Signed Divide
DIVS.L	<ea>,Dr:Dq	
DIVSL.L	<ea>,Dr:Dq (020-040 only!)	
DIVU.L	<ea>,Dq	Unsigned Divide
DIVU.L	<ea>,Dr:Dq	
DIVUL.L	<ea>,Dr:Dq (020-040 only!)	
EXTB.L	Dn	Sign Extend
LINK.L	An,#<displacement>	Link and Allocate
MULS.L	<ea>,Dl	Signed Multiply
MULS.L	<ea>,Dh:Dl	
MULU.L	<ea>,Dl	Unsigned Multiply
MULU.L	<ea>,Dh:Dl	
PACK	-(Ax),-(Ay),#<adjustment>	Pack BCD
PACK	Dx,Dy,#<adjustment>	
RTM	Rn	Return from Module (68020 ONLY!)
TRAP<cc>		Trap on Condition
TRAP<cc>.x	#<data>	
UNPK	-(Ax),-(Ay),#<adjustment>	Unpack BCD
UNPK	Dx,Dy,#<adjustment>	

### 1.23 Integer Instructions (68040,68060)

CINVL	<cache>, (An)	Invalidate Cache Lines
CINVP	<cache>, (An)	(<cache> = DC, IC, BC or NC)
CINVA	<cache>	
CPUSHL	<cache>, (An)	Push and Invalidate Cache Lines
CPUSHP	<cache>, (An)	
CPUSHA	<cache>	
MOVE16	(Ax)+, (Ay)+	Move 16 Bytes Block
MOVE16	xxx.L, (An)	
MOVE16	xxx.L, (An)+	
MOVE16	(An), xxx.L	
MOVE16	(An)+, xxx.L	

### 1.24 Integer Instructions (68060)

LPSTOP	#<data>	Low-Power Stop
HALT		Processor halted
PULSE		Send \$14 pulse on PSTx

Instructions that are not directly supported by the 68060, like DIVUL, DIVSL, CAS2, CHK2, CMP2, MOVEP, will be assembled without warning, because they are emulated by the "68060.library" (I hope... :-).

### 1.25 MOVEC Control Registers (Rc)

		68010	68020	68030	68040	68060
SFC	Source Function Code	x	x	x	x	x
DFC	Destination Function Code	x	x	x	x	x
USP	User Stack Pointer	x	x	x	x	x
VBR	Vector Base Register	x	x	x	x	x
CACR	Cache Control Register		x	x	x	x
CAAR	Cache Address Register		x	x		
MSP	Master Stack Pointer		x	x	x	x
ISP	Interrupt Stack Pointer		x	x	x	x
TC	MMU Translation Control Register				x	x
ITT0	Instr. Transparent Translation Reg. 0				x	x
ITT1	Instr. Transparent Translation Reg. 1				x	x
DTT0	Data Transparent Translation Reg. 0				x	x
DTT1	Data Transparent Translation Reg. 1				x	x
MMUSR	MMU Status Register				x	x
URP	User Root Pointer				x	x
SRP	Supervisor Root Pointer				x	x
BUSCR	Bus Control Register					x
PCR	Processor Control Register					x

### 1.26 Floating Point Instructions (68881,68882,68040,68060)

Many of these instructions must be emulated for a 68040 or 68060, but PhxAss will assemble them without any warnings.

68040 emulated instructions:

FACOS, FASIN, FATAN, FCOS, FCOSH, FETOX, FETOXM1, FGETEXP, FGETMAN, FINT, FINTRZ, FLOG10, FLOG2, FLOGN, FLOGNP1, FMOD, FREM, FSGLDIV, FSGLMUL, FSIN, FSINCOS, FSINH, FTAN, FTANH, FTENTOX, FTWOTOX

68060 emulated instructions:

FACOS, FASIN, FATAN, FCOS, FCOSH, FDB<cc>, FETOX, FETOXM1, FGETEXP, FGETMAN, FLOG10, FLOG2, FLOGN, FLOGNP1, FMOD, FREM, FSGLDIV, FSGLMUL, FS<cc>, FSIN, FSINCOS, FSINH, FTAN, FTANH, FTENTOX, FTWOTOX

Monadic operations:

Fxxxx <ea>,FPn  
 Fxxxx Fm,FPn  
 Fxxxx FPn

FABS Floating-Point Absolute value  
 FACOS Arc Cosine  
 FASIN Arc Sine  
 FATAN Arc Tangent  
 FATANH Hyperbolic Arc Tangent  
 FCOS Cosine  
 FCOSH Hyperbolic Cosine  
 FETOX e to x  
 FETOXM1 e to x minus one  
 FGETEXP Get Exponent  
 FGETMAN Get Mantissa  
 FINT Integer Part  
 FINTRZ Integer Part, Round to Zero  
 FLOG10 log10  
 FLOG2 log2  
 FLOGN loge  
 FLOGNP1 loge (x+1)  
 FNEG Floating-Point Negate  
 FSIN Sine  
 FSINH Hyperbolic Sine  
 FSQRT Floating-Point Square Root  
 FTAN Tangent  
 FTANH Hyperbolic Tangent  
 FTENTOX 10 to x  
 FTWOTOX 2 to x

Dyadic operations:

Fxxxx <ea>,FPn  
 Fxxxx Fm,FPn

FADD Floating-Point Add  
 FCMP Floating-Point Compare  
 FDIV Floating-Point Divide  
 FMOD Modulo Remainder  
 FMUL Floating-Point Multiply  
 FREM IEEE Remainder  
 FSCALE Scale Exponent

FSGLDIV      Single Precision Divide  
 FSGLMUL     Single Precision Multiply  
 FSUB         Floating-Point Subtract

Special operations:

FB<cc>.x	<label>	Floating-Point Branch Conditionally
FDB<cc>	Dn,<label>	FP Test Cond., Decr., and Branch
FMOVE.x	<ea>,FPn	Move Floating-Point Data Register
FMOVE.x	FPm,<ea>	
FMOVE.P	FPm,<ea>{Dn}	
FMOVE.P	FPm,<ea>{#k}	
FMOVE.L	<ea>,FPcr	Move F.-Point System Control Register
FMOVE.L	FPcr,<ea>	(FPcr = FPCR, FPSR or FPIAR)
FMOVECR	#ccc,FPn	Move Constant ROM
FMOVEM	<list>,<ea>	Move Multiple F.-Point Data Registers
FMOVEM	Dn,<ea>	
FMOVEM	<ea>,<list>	
FMOVEM	<ea>,Dn	
FMOVEM.L	<list>,<ea>	Move Multiple F.-Point Control Regs.
FMOVEM.L	<ea>,<list>	(<list> = combin. of FPCR,FPSR,FPIAR)
FNOP		No Operation
FRESTORE	<ea>	Restore Internal Floating-Point State
FSAVE	<ea>	Save Internal Floating-Point State
FS<cc>	<ea>	Set According to Flt.-Point Condition
FSINCOS.x	<ea>,FPc:FPs	Simultaneous Sine and Cosine
FSINCOS	FPm,FPc:FPs	
FTRAP<cc>		Trap on Floating-Point Condition
FTRAP<cc>.x	#<data>	
FTST.x	<ea>	Test Floating-Point Operand
FTST	FPm	

Floating-Point Condition Codes <cc>:

F	false	EQ	equal
OGT	ordered greater than	OGE	ordered gt. than or equal
OLT	ordered less than	OLE	ordered less than or equal
OGL	ordered greater or less than	OR	ordered
UN	unordered	UNE	unordered or equal
UGT	unordered or greater than	UGE	unord. or gt. than or equal
ULT	unordered or less than	ULE	unord. or less than or equal
NE	not equal	T	true
SF	signaling false	SEQ	signaling equal
GT	greater than	GE	greater than or equal
LT	less than	LE	less than or equal
GL	greater than or less than	GLE	gt. or less than or equal
NGLE	not (gt. or less or equal)	NGL	not (greater or less than)
NLE	not (less than or equal)	NLT	not (less than)
NGE	not (greater than or equal)	NGT	not (greater than)
SNE	signaling not equal	ST	signaling true

## 1.27 Floating Point Instructions (68040,68060)

FSADD        Add Single Precision  
 FDADD        Add Double Precision  
 FSDIV        Single Precision Divide  
 FDDIV        Double Precision Divide

FSMOVE	Single Precision Move
FDMOVE	Double Precision Move
FSMUL	Single Precision Multiply
FDMUL	Double Precision Multiply
FSNEG	Single Precision Negate
FDNEG	Double Precision Negate
FSSQRT	Single Precision Square Root
FDSQRT	Double Precision Square Root
FSSUB	Subtract Single Precision
FDSUB	Subtract Double Precision

## 1.28 PMMU Instructions (68851)

PB<cc>.x	<label>	Branch on PMMU Condition
PDB<cc>	Dn, <label>	Test, Decr., and Branch on PMMU Cond.
PFLUSHA		Invalidate Entries in the ATC
PFLUSH	<fc>, #<mask>	
PFLUSHS	<fc>, #<mask>	
PFLUSH	<fc>, #<mask>, <ea>	
PFLUSHS	<fc>, #<mask>, <ea>	
PFLUSHR	<ea>	Invalidate ATC and RPT Entries
PLOADR	<fc>, <ea>	Load an Entry into the ATC
PLOADW	<fc>, <ea>	
PMOVE	<PMMU Register>, <ea>	Move PMMU Register
PMOVE	<ea>, <PMMU Register>	
PRESTORE	<ea>	PMMU Restore Function
PSAVE	<ea>	PMMU Save Function
PS<cc>	<ea>	Set on PMMU Condition
PTESTR	<fc>, <ea>, #<level>	Get Information About Logical Address
PTESTR	<fc>, <ea>, #<level>, An	
PTESTW	<fc>, <ea>, #<level>	
PTESTW	<fc>, <ea>, #<level>, An	
PTRAP<cc>		Trap on PMMU Condition
PTRAP<cc>.x	#<data>	

PMMU Condition Codes <cc>:

BS, BC	Bus Error
LS, LC	Limit Violation
SS, SC	Supervisor Only
AS, AC	Access Level Violation
WS, WC	Write Protected
IS, IC	Invalid Descriptor
GS, GC	Gate
CS, CC	Globally Sharable

PMMU Registers:

CRP, SRP, DRP, TC, BACx, BADx, AC, PSR, PCSR, CAL, VAL, SCC

## 1.29 PMMU Instructions (68030)

PFLUSHA		Flush Entry in the ATC
PFLUSH	<fc>, #<mask>	

PFLUSH	<fc>, #<mask>, <ea>	
PLOADR	<fc>, <ea>	Load an Entry into the ATC
PLOADW	<fc>, <ea>	
PMOVE	MRn, <ea>	Move to/from MMU Registers
PMOVE	<ea>, MRn	
PMOVEFD	<ea>, MRn	
PTESTR	<fc>, <ea>, #<level>	Test a Logical Address
PTESTR	<fc>, <ea>, #<level>, An	
PTESTW	<fc>, <ea>, #<level>	
PTESTW	<fc>, <ea>, #<level>, An	

PMMU Registers (MRn):

SRP, CRP, TC, MMUSR(PSR), TT0, TT1

### 1.30 PMMU Instructions (68040,68060)

PFLUSH	(An)	Flush ATC Entries
PFLUSHN	(An)	
PFLUSHA		
PFLUSHAN		
PTESTR	(An)	Test a Logical Address
PTESTW	(An)	
PLPAR	(An)	Translate Logical to Physical
PLPAW	(An)	(68060 only!)

### 1.31 Expressions

Expressions consist of symbols and constants. Symbols can be absolute, relocatable or external. The arithmetic operations for INTEGER expressions, supported by PhxAss, are (from highest to lowest precedence) :

1. ~ not (unary)                      - negation (unary)
2. << shift left                      >> shift right
3. \* multiplication                    / division                      // modulo
4. & and                                | or ('!' also allowed)        ^ exclusive or
5. - subtraction                      + addition
6. ( ) parentheses                    or [ ] brackets

For absolute symbols and constants (which are absolute too), all arithmetic operations are allowed.

If relocatables or externals occur in the expression, only subtraction and addition is possible with some restrictions:

reloc - abs	extern - abs	reloc - reloc	
reloc + abs	extern + abs	abs + reloc	abs + extern
(reloc-reloc)<<abs	(reloc-reloc)>>abs	(V3.95 feature)	

are defined, the others are illegal.

FLOAT expressions consist of floating point constants, absolute integer

constants and symbols. The following operations and functions are valid for float expressions (V4.00 feature):

Binary:

+	plus	-	minus	*	multiplication
/	division	^	power		

Unary:

-	negation	sqr	square root	exp	e^x
log	nat. logarithm	sin	sine	cos	cosine
tan	tangent				

SQR, EXP, LOG, SIN, COS and TAN are functions and not case sensitive. They are usually introducing a term, e.g. "sin(3.14159)". But if, as in the last example, the term only consists of a single constant, it is also allowed to write "sin:3.14159". The ':' is required to separate the function name from a possible symbol name.

There are six types of constants:

Hexadecimal, preceded by a '\$', consists of '0'-'9' and 'A'-'F' (or 'a'-'f')

Decimal, consists of '0'-'9'

Float, has the format [+/-][integer][.fraction][E[+/-]exponent]

Octal, preceded by a '@', consists of '0'-'7'

Binary, preceded by a '%', consists of '0' and '1'

String, embedded by ' or ", consists of one to four characters.

The character '\ ' is an escape-symbol, which can generate the following codes:

\\	the '\ '-character itself
\'	character #39 (single quote)
\"	character #34 (quote)
\0	character #0 (string terminator)
\n	character #10 (line feed)
\f	character #12 (form feed)
\b	character #8 (backspace)
\t	character #9 (tabulator)
\r	character #13 (carriage return)
\e	character #27 (escape)
\c	character #155 (control sequence introducer)

"" and '' within a string will be replaced by " and ' (V4.14).

## 1.32 Assembler Directives

The following paragraphs describe all directives that are ← supported by

PhxAss. Important note! Directives must \*not\* start at the first column of a line or they will be treated as labels! (note for Seka users :-)

Directives supported by PhxAss:

BLK  
Define Constant Block



---

BSS  
Bss section

BSS  
Allocate storage for Bss symbol

BSS\_C  
Chip-RAM Bss section

BSS\_F  
Fast-RAM Bss section

CNOP  
Align the following code

CODE  
Code section

CODE\_C  
Chip-RAM Code section

CODE\_F  
Fast-RAM Code section

COMMENT  
Comment line

CSEG  
Code section

DATA  
Data section

DATA\_C  
Chip-RAM Data section

DATA\_F  
Fast-RAM Data section

DC  
Define Constant

DCB  
Define Constant Block

DEBUG  
Store current address in Line Debug block

DS  
Define Storage

DSEG  
Data section

DSOURCE  
Set complete source path for Line Debug block

---

---

DX  
Define Storage

ECHO  
Print string

ELSE  
Define ELSE-part for conditional assembly

ELSEIF  
Define ELSE-part for conditional assembly

EQU  
Assign expression to symbol

EQU.x  
Assign floating point expression to symbol

EQR  
Assign register to symbol

END  
End of source text

ENDC  
End of conditional assembly

ENDIF  
End of conditional assembly

ENDM  
End of Macro definition

ENDR  
End of REPT loop

EVEN  
Align the following code to an even address

FAIL  
Abort assembly

FAR  
Enter Far mode

FILE  
Destination file for absolute code

FPU  
Enable FPU code generation

FREG  
Assign FPU register list to symbol

GLOBAL  
Allocate storage for global Bss symbol

---

---

IDNT  
Set unit name

IFC  
Cond.Ass.: Compares two strings for equality

IFD  
Cond.Ass.: Test if a symbol is defined

IFEQ  
Cond.Ass.: Test if expression is zero

IFGT  
Cond.Ass.: Test if expression is greater than zero

IFGE  
Cond.Ass.: Test if exp. is greater or equal to zero

IFLT  
Cond.Ass.: Test is exp. is less than zero

IFLE  
Cond.Ass.: Test if exp. is less or equal to zero

IFNC  
Cond.Ass.: Compares two strings for difference

IFND  
Cond.Ass.: Test if a symbol is undefined

IFNE  
Cond.Ass.: Test if expression is not zero

IF  
Cond.Ass.: Test if expression is not zero

INCBIN  
Include binary file

INCDIR  
Set Include directory path

INCLUDE  
Include another source file

INITNEAR  
Initialize near mode base register

INT  
Assign value of float expression to an integer SET-symbol

LIST  
Next lines to listing file

LOAD  
Destination address for absolute code

---

---

MACHINE  
Set CPU type

MACRO  
Macro definition

MEXIT  
Exit Macro

NEAR  
Enter Near mode

NOLIST  
Next lines are invisible in listing file

NREF  
Import Near-symbol

OFFSET  
Start Offset section

OPT  
Change optimization mode

ORG  
Set absolute code origin

PMMU  
Enable 68851 code generation

PROCSTART  
Start of C-function for DICE-Compiler

PROCEND  
End of C-function for DICE-Compiler

PUBLIC  
Import/Export symbol

REG  
Assign register list to symbol

REPT  
Repeat lines between REPT and ENDR

RESTORE  
Reactivate the last saved section

RORG  
Set offset to start of section

RS  
Assign value of RS-counter to symbol

RSRESET  
Reset RS-counter

---

```

    RSSET
    Set RS-counter

    SAVE
    Saves the state of the current section

    SECTION
    Set section for following code

    SET
    Change value of SET-symbol

    SET.x
    Change value of floating point SET-symbol

    SFORM
    Creates Motorola S-Record format

    SUBTTL
    (no function)

    TTL
    Set unit name

    TRACKDISK
    Absolute code directly to disk

    XDEF
    Export symbol

    XREF
    Import symbol

```

The following directives are *\*not\** supported by the Freeware version:  
 RSRESET, RSSET, RS, ECHO, LIST, NOLIST, INCDIR, INCLUDE, INCBIN, MACRO, ENDM, MEXIT,  
 RORG, OFFSET, ORG, FILE, LOAD, TRACKDISK, SFORM, COMMENT, SUBTTL, IF<cc>, ELSE,  
 ELSEIF, ENDC, ENDIF, REPT, ENDR, INT

### 1.33 EQU

```

symbol    equ    <expression>
symbol    =      <expression>

```

The expression will be assigned to the symbol.

### 1.34 EQU.x

```

symbol    equ.x  <float expression>
symbol    =.x    <float expression>

```

An equate with extension *.d*, *.f*, *.p*, *.s*, *.x* will assign the value of a

floating point expression to the symbol. If you want to know more about float expressions, refer to

Expressions

.

This is a special PhxAss directive.

### 1.35 EQU

```
symbol    equ    <register>
```

This directive assigns a register (D0-D7,A0-A7 or SP) or (since v4.20) a register symbol to the specified symbol. Since V3.00 a register symbol must be defined before it is used.

### 1.36 REG

```
symbol    reg    <register list>
```

This directive assigns the value of the register list to the symbol. Valid register lists contain several register names (see

```
EQU
)
```

separated by the '/' character. The '-' character defines a range of registers. The following are valid register lists:

```
a1/a3-a5/d0/d2/d4
d0-d7/a2-a6
d1-3/d5-7/a0-1/a3-6 (since V3.56)
```

### 1.37 FREG

```
symbol    freg   <register list>
```

The directive assign a FPU register list to the specified symbol. Valid register lists contain the FPU registers FP0-FP7 separated by the '/' character. The '-' character defines a range of FPU registers. The following are valid FPU register lists:

```
fp1/fp3-fp5/fp0
fp0-fp7
```

### 1.38 SET

```
symbol    set    <absolute expression>
```

This directive assigns the value of the expression to the symbol. No relocatables or externals are allowed within the expression. A symbol defined by a SET directive may change its value by another SET.

There are some set-symbols which are defined by PhxAss:

---

```
_PHXASS_    set      1
_VERSION_   set      version<<16+revision
```

According to the connected processor and co-processor PhxAss will set `_MC68000_`, `_MC68010_`, `_MC68020_`, `_MC68030_`, `_MC68040_`, `_MC68060_`, `_MC68881_` and `_MC68882_`.

NARG is zero outside a macro. Within a macro NARG is set to the number of specified arguments.

```
__RS always reflects the current
      RS-counter
      value.
```

### 1.39 SET.x

```
symbol  set.x  <float expression>
```

A SET with extension `.d`, `.f`, `.p`, `.s`, `.x` will assign the value of a floating point expression to the symbol. You may change its value by another SET, later in the source, provided that you don't change its type (e.g. "symbol SET.S" followed by "symbol SET.D"). This is a special PhxAss directive.

### 1.40 INT

```
symbol  int    <float expression>
```

The float expression will be evaluated and the result, without the fractional part, will be assigned to an integer symbol.

### 1.41 RSRESET

This directive resets the internal RS-counter.

### 1.42 RSSET

```
rsset   [<count>]
```

This directive sets the internal RS-counter to the `<count>` expression.

### 1.43 RS

```
[symbol] rs.x    [<count>]
```

RS assigns the value of the internal RS-counter to the symbol, then it increases the counter by the extension size multiplied with <count>. If <count> is missing, it defaults to zero. For valid extensions refer to the

DC

directive.

The current RS-counter value is reflected by the `__RS` symbol also.

## 1.44 IDNT

```
idnt    <name>
ttl     <name>
```

These directives set the name of the object file unit which the assembler will generate. By default, it will be the name of the source file without the extension.

## 1.45 SUBTTL

Source texts containing `subttl` will cause no error with PhxAss, but for now it does completely nothing. (To be honest, I've no idea what it should do! Please write me, if somebody knows it.)

## 1.46 COMMENT

```
comment text
```

You may write any text you like behind this directive.

## 1.47 LIST

The following source code will be written to the listing file.

## 1.48 NOLIST

The following source code will not be written to the listing file.

---



## 1.49 OPT

```
opt      <optimize flags>
```

Changes optimization level. For a listing of all optimize flags, see

```
Command line parameters
```

This is a special PhxAss directive.

## 1.50 MACRO, ENDM

```
symbol  macro
        ...text...
        endm

macro   symbol
        ...text...
        endm
```

This directive assigns a macro to the specified symbol. The symbol may appear on the left or right side of the directive. The text between the MACRO and ENDM directives will be inserted into the source code when the assembler discovers this symbol. When invoking the macro, up to 35 arguments, separated by a commas, can be specified in the operand field. They are referenced in the macro text as '\1' through '\9' and (since V4.18) as '\a' through '\z' for the last 26.

'\0' is reserved for the extension of the macro symbol. Example:

```
bhs     macro
        bcc.\0  \1
        endm
```

This macro can be called by: `bhs.s label`  
 ".s" will be assigned to \0 and "label" will be assigned to \1.  
 A "\@" within the macro is replaced by text of the form "nnn",  
 where nnn is a unique three-digit number for each macro call.

Labels within a macro should consist of "\@", because defining labels twice is illegal.

There is a limitation for using macro parameters in string constants. Only \1 through \9 are allowed to avoid problems with escape symbols.

## 1.51 MEXIT

```

        Upon encountering this directive within a macro, the ↵
        assembler scans
for the
        ENDM
```

directive and leaves the macro.

## 1.52 END

In pass one the assembler ignores the rest of the source code and starts pass two. In pass two the assembler closes all files and terminates. By default the assembler terminates at end of file.

## 1.53 FAIL

The assembler displays the error "69 Assembly aborted !" and terminates.

## 1.54 ECHO

```
echo <string>
```

The assembler echoes the string. If <string> isn't specified, only a newline is echoed.

This is a special PhxAss directive.

## 1.55 MACHINE

```
machine <processor-type>
```

This directive sets the processor-type for which the code will be generated. Valid processor-types are:

68000, 68010, 68020, 68030, 68040, 68060

The implementation of this directive may be different in other assemblers.

## 1.56 FPU

```
fpu [<cpID>]
```

This directive enables code generation for a MC68881/68882 coprocessor. By default the <cpID> is set to one, which should be the correct ID for most systems using a floating point coprocessor.

Never set <cpID> to zero, because this is the constant ID for a PMMU. If you have set the processor-type to 68040 or 68060 you should not use this directive.

This is a special PhxAss directive.

---

## 1.57 PMMU

This directive enables code generation for a MC68851 Paged Memory Management Unit. PMMU only makes sense if you have set the processor-type to '68020'.

This is a special PhxAss directive.

## 1.58 SECTION

```
section <name>[,<type>[,<memflag>]]
```

The subsequent code will be placed in the section named <name>. There are three section types: CODE, DATA and BSS. CODE contains the executable M68000 instructions, DATA contains initialized data and BSS contains uninitialized data (set to zero before the program is started). By default <type> is set to CODE. The section will be loaded to the memory indicated by the <memflag> argument. This can be FAST or CHIP. By default the section will be loaded to the memory with the highest priority.

For compatibility reasons CODE\_C, DATA\_C and BSS\_C are also recognized as section type since V3.56.

Creating a section lets the assembler change into relocatable mode. In this mode the following directives are illegal:

```
org
,
load
,
file
,
trackdisk
.
```

## 1.59 CODE, CSEG

```
These directives correspond to:
section
"CODE",code
```

## 1.60 DATA, DSEG

```
These directives correspond to:
section
"DATA",data
```

---

## 1.61 CODE\_C, CODE\_F, DATA\_C, DATA\_F, BSS\_C, BSS\_F

```

                See
CODE
,
DATA
  or
BSS
. In addition a memflag will be set, which
causes the section to be loaded to FAST (xxx_F) or to CHIP (xxx_C).

```

## 1.62 BSS

```

                This directive corresponds to:
section
  "BSS",bss

```

## 1.63 BSS

```

                bss      symbol,<size>

```

BSS with arguments does not start a section. It defines a symbol to be in the

```

                BSS
                -section, reserves <size> bytes in this section and assigns
the address of the first byte to the symbol.
This directive is for Aztec-C compatibility only.

```

## 1.64 GLOBAL

```

                global  symbol,<size>

```

This directive does the same as

```

                BSS
                symbol,<size>. In addition GLOBAL
will declare the symbol as
                XDEF
                (ext_def).

```

It is for Aztec-C compatibility only.

## 1.65 OFFSET

```

                offset  [<start offset>]

```

This directive indicates the beginning of a special offset-section. All the labels, which are declared in this section, will be treated as absolute offsets instead of addresses. <start offset> defaults to

zero. This might be useful for declaring structure offsets with the

```

        DS.x
        directive. While writing programs for PhxAss you should
prefer the faster
        RSRESET
        ,
        RSSET
        and
        RS.x
        directives.

```

OFFSET was mainly implemented for compatibility reasons.

## 1.66 RORG

```
rorg    <section offset>
```

This directive defines the offset of the subsequent code relative to the start of the current section. <section offset> must be positive.

## 1.67 INCDIR

```
incdir  <path1>[,<path2>,...]
```

This directive does the same like the INCPATH argument (see

```

        Command line arguments
        ). Note that other assemblers don't accept
multiple paths.

```

## 1.68 INCLUDE

```
include <filename>
```

This directive causes PhxAss to suspend the assembling of the current file and to assemble the file named <filename>. When done, the assembler continues assembling the original file.

If PhxAss can't find the include file, it first searches in the include directory defined by the environment variable PHXASSINC. Then it searches in the include directories defined by INCPATH parameters (see

```

        Command line arguments
        ). At last, the
directories defined by
        INCDIR
        are searched.

```

## 1.69 INCBIN

```
incbin <filename>
```

This directive causes the assembler to include a binary file into the current section (e.g. graphics, samples or trigonometrical tables).

The assembler searches in the same include directories like

```
INCLUDE
```

```
.
```

## 1.70 XREF

```
xref symbol1[,symbol2,...]
```

This directive tells the assembler that the specified symbols are externally defined and will be inserted by the linker.

Note that other assemblers may not support multiple symbols.

## 1.71 NREF

```
nref symbol1[,symbol2,...]
```

This directive does the same like

```
XREF
```

```
, but the assembler is forced to
```

use these symbols as near-data relocatables.

This is a special PhxAss directive.

## 1.72 XDEF

```
xdef symbol1[,symbol2,...]
```

This directive causes the assembler to add the names and values of the specified symbols to the external-block of the object file. The linker can read the values of these symbols and insert them into other object files.

Note that other assemblers may not support multiple symbols.

## 1.73 PUBLIC

```
public symbol1[,symbol2,...]
```

When the specified symbols are defined in the current code, PUBLIC will do the same like

```
XDEF
```

```
. When the symbols are unknown, PUBLIC
```

will do the same like

---

```
XREF
```

```
.
```

This directive is for Aztec-C compatibility only.

## 1.74 ORG

```
org      address
```

Defines the origin of the subsequent code and lets the assembler change into absolute mode. Since V1.8 several ORG directives are allowed and each one can be seen as a new section. The following directives are illegal in absolute mode:

```
t11
/
code
/
cseg
/
section
/
offset
/
xref
/
nref
/
xdef
/
public
/
idnt
.
```

## 1.75 LOAD

```
load    address
```

After assembling is done, the absolute code will be loaded to this address. By default the code will be loaded to the address which was specified as origin. Be cautious with this directive, because the destination memory will neither be checked nor allocated. This is a special PhxAss directive (also known from SEKA).

## 1.76 FILE

```
file    <filename>
```

After assembling is done, the absolute code will be written into the

---

file named <filename>.  
This is a special PhxAss directive.

## 1.77 SFORM

```
sform    <filename>
```

After assembling is done, the absolute code will be written as a Motorola S-Record with the name <filename>.  
You should always consider, that the S-Format supports only 24-Bit addresses.  
This is a special PhxAss directive.

## 1.78 TRACKDISK

```
trackdisk <drive>,<startblock>[,<offset>]
```

After assembling is done, the absolute code will be written directly to floppy disk using the 'trackdisk.device'. <drive> is valid from 0 to 3. <startblock> is valid from 0 to 1759 (or 3519, if you have a HD drive). <offset>, which is zero by default, specifies the byte-offset within a block and is valid from 0 to 511.  
This is a special PhxAss directive.

## 1.79 NEAR

```
near    [An[,<secnum>]]
```

This directive initializes the parameters used by the near-data model. NEAR with arguments may appear only once in your whole source code. You shouldn't use 'NEAR An,0' before the first SECTION, CODE, DATA, etc. directive.

After initializing the small-data model, it can be switched on and off by NEAR and

```
FAR
```

without arguments. In this mode you are allowed to access near-symbols via 'NearSymbol(An)'. Absolute references will be automatically converted to Address Register Indirect, if possible. The first argument, the address-register, is valid from A2 to A6 and will be A4 by default. <secnum>, which defaults to -2, specifies the number of the section which will be accessed by Address Register Indirect mode.

If <secnum> is -1, all Data and Bss sections will be added to one large small data section. Either PhxAss will do this job immediately, when creating an executable file, or you must invoke your Linker with the correct small data option.

If <secnum> is -2, only the Data or Bss sections which were named "\_\_MERGED", will be added to the small data section.



```
near code
```

If the argument equals to the string "CODE" the assembler activates the near-code model. This will force all absolute

```
XREF
jumps
into PC-relative mode.
```

Note that other assemblers don't accept parameters for NEAR.

## 1.80 FAR

This directive deactivates the near-code/data model when active.

## 1.81 INITNEAR

This directive inserts two M68000 instructions into the code ↔ which will initialize the small-data model depending on the parameters set by the

```
NEAR
directive. The assembler will generate this code
(10 bytes):
    lea    SmallDataBase,An
    lea    32766(An),An
```

This is a special PhxAss directive.

## 1.82 DC

```
label dc.? <value>[,<value>,...]
label dc.b/w/l "string"[,...]
```

The DC (Define Constant) directive causes one or more fields of memory to be allocated and initialized. Each field has the same size, specified by the extension of the directive. Each byte, word or longword <value> can be an expression and may contain forward references.

The following extensions are valid:

.B	(1 byte)	Byte	.W	(2 bytes)	Word
.L	(4 bytes)	Longword	.F	(4 bytes)	Fast Flt. Point
.S	(4 bytes)	Single Precision	.D	(8 bytes)	Double Precision
.Q	(8 bytes)	Quadword(V3.42)	.X	(12 bytes)	Ext. Precision
.P	(12 bytes)	Packed BCD			

Note that other assemblers may not support the floating-point and quadword types.

### 1.83 DCB, BLK

```

                label    dcb.x    <num>[,<fill>]
label    blk.x    <num>[,<fill>]

```

These directives allocate a block of memory having <num> entries. The available entry sizes are the same like with

```

DC
. The block will be
initialized with <fill>, which is zero when missing. For valid exten-
sions, refer to
DC
.

```

### 1.84 DS, DX

```

                label    ds.x    <num>
label    dx.x    <num>

```

This directive allocates a block of memory having <num> entries and initializes each field with zero. See

```

DCB
,
BLK
.

```

### 1.85 CNOP

```

cnop    <offset>,<align>

```

This directive aligns the address of the following code to <align>. Then the <offset> is added. Example: `cnop 2,4`. This example would align the next address two bytes behind the next longword boundary. Note that an <align> larger than 8 makes no sense, if you're creating relocatable code (see `AllocMem()`, `exec.library`).

### 1.86 EVEN

```

                This directive corresponds to
cnop
    0,2 which will make the
address word-aligned.

```

### 1.87 IFcond, ELSEIF, ELSE, ENDIF, ENDC

These directives support conditional assembling. The general form of the IF directive is:

```

    if<cond>    <expression> or symbol
    ...
    [else (or elseif)
    ...]
    endc (or endif)

```

PhxAss supports the following conditions:

IFC "string1", "string2"	compares two strings. This is useful within macros, when the strings contain macro-arguments '\x' .
IFD/IFND symbol	tests if the symbol is defined (undefined).
IFEQ/IFNE <exp>	tests if <exp> is zero (not zero).
IFGT/IFLT <exp>	tests if <exp> is greater (less) than zero.
IFGE/IFLE <exp>	tests if <exp> is greater (less) than or equal to zero.
IF <exp>	is an alias for IFNE.

## 1.88 PROCSTART,PROCEND

These directives are for compatibility with the DICE-C sytem. But currently they do nothing. For the future it should be possible to remove LINK A5,#0 / UNLK A5 when A5 is not referenced between PROCSTART and PROCEND.

## 1.89 REPT/ENDR

```

    rept    <count>
    ...
    endr

```

The part of source code, embedded by REPT/ENDR, will be assembled <count> times. A negative <count> is illegal.

## 1.90 SAVE

```

    save

```

Saves the name and type of the current section, so that it can be reactivated by

```

    RESTORE
    later. Very useful in

```

macros. Example:

```

    print    macro
            save
            section strings,data
    \@      dc.b    \1,0
            restore

```

```

lea    \@,a0
bsr    printstring
endm

```

## 1.91 RESTORE

```
restore
```

Reactivates the section which was last saved by the `SAVE` directive.

## 1.92 DEBUG

```
debug    <line number>
```

Links the line <line number> of a high level source (full path must be defined by

```

DSOURCE
) with the current address and

```

appends this information to the Line Debug block. Very useful for compilers, which want to offer source level debugging.

Don't set

```

LINEDEBUG/S
when using this directive!

```

## 1.93 DSOURCE

```
dsource    <source path>
```

Defines the full path of your high level source. E.g.:  
`"Work:Programs/C/Test/Source/HelloWorld.c"`.

See

```

DEBUG
for additional information.

```

## 1.94 Compiler Compatibility

A major reason for writing PhxAss was to create a program which  $\leftrightarrow$   
can replace

the very slow AS-assembler of Aztec-C. There are many directives for Aztec-compatibility, but since V3.30, where symbols preceded by a '.' are regarded as local symbols, it is nearly impossible to assemble Aztec compiler outputs. The only solution is to write a program which translates all '.nnn' symbols into '\_nnn', for example.

Since introducing the new directives

```

PROCSTART
and
PROCEND
in V3.71,

```

DICE-C sources are completely supported.

## 1.95 PhxOpts

PhxOpts from Johan Johanssen offers a GUI to predefine most options for

PhxAss and save them either as a global or local options file. So any of your projects can get a local PHXOPTIONS file, which contains all options you don't want to specify with every invocation of PhxAss. If no local options file is present in your current directory, PhxAss will look for the global one in

```
ENV:PhxAss
```

PhxOpts requires the triton.library to work.

## 1.96 Environment Variables

PhxAss searches in ENV:PhxAss/ for environment variables. Currently there

are two:

**PHXASSINC** Specifies the path where to look for include files, if they are not located in the current directory. Note, that the location of PHXASSINC has changed in v4.20! Before it was ENV:PHXASSINC.

**PHXOPTIONS** Contains several global predefined options, which will be passed to PhxAss when no local PHXOPTIONS in the current directory was found. PHXOPTIONS can be edited manually, but will be normally created by the PhxOpts GUI from Johan Johansson, which should be in your PhxAss archive. The options, which are passed to PhxAss via the command line, have priority and will overwrite those predefined ones.

## 1.97 Linker

You may use any linker which supports the standard Amiga DOS object file format. For example BLink, DLink, etc. - but I recommend that you use PhxLnk, of course :-).

Since V4.00, you only need a linker when you have more than a single module. PhxAss automatically generates an executable, if no external references are present.

Two features of PhxLnk are not implemented in PhxAss:

1. Generation of HUNK\_RELOC32SHORT blocks (16-bit offsets)
2. Removing zero-bytes at the end of a Code or Data section (so called Code-Bss or Data-Bss sections)

If you want to use one of these features (which require OS2.04 to run your program), you should set the

NOEXE  
switch and invoke PhxLnk.

## 1.98 Assembler Errors

In the current version of PhxAss the following errors could occur:

- 01 Out of memory
  - 02 Unable to open utility.library
  - 03 Can't open timer.device
  - 04 DREL16 out of range  
Your Small Data area is too large. 64k is the limit for all data and bss sections together.
  - 07 HEADINC: file name expected  
Example: PhxAss HEADINC "dh0:file1,dh1:xdir/file2,"
  - 08 IncDir path name expected  
Example: incdir "dir1","dir2",  
Caused also by INCPATH.
  - 10 SMALLDATA: Illegal base register  
Allowed are 2-6 for A2-A6. A4 is standard.
  - 11 MACHINE not supported  
The current version of PhxAss supports 68000, 68010, 68020, 68030, 68040 and 68060.
  - 12 File doesn't exist  
Unable to open your source code.
  - 13 Missing include file name
  - 14 Read error
  - 15 String buffer overflow  
The length of a label, opcode or operand is limited to a length of 128 characters.
  - 16 Too many sections  
Maximum is 250 sections.
  - 17 Symbol can't be made external  
XDEF can only be used on absolute or relocatable symbols.
-

- 
- 18 Symbol was declared twice  
Only SET symbols can be declared more than once.
- 19 Unable to make XREF symbol  
A symbol, which is already defined in the current source code, can't be an XREF at the same time. Or: A symbol which is already declared as XREF can't be defined.
- 20 Illegal opcode extension  
Legal: .b .w .l .s .f .d .x .p .q
- 21 Illegal macro parameter  
Possible parameters are: \0 (opcode extension), \1 - \9, \a - \z and \@
- 22 Illegal characters in label  
Refer to  
    Labels  
    in Programmer Information.
- 23 Unknown directive  
The opcode is neither a 680x0-mnemonic nor an assembler directive or macro.
- 24 Too many parameters for a macro  
35 parameters ( \1 through \9 and \a through \z ) are possible.
- 25 Can't open trackdisk.device
- 26 Argument buffer overflow  
Arguments are in most cases limited to 128 characters.
- 27 Bad register list  
Valid register lists: d0-d3 d3-d4/a2 d2/d3/a4-a6 d7 a0/d2 d2-6/a0-4
- 28 Missing label  
The directive requires a label.  
Example: EQU <exp> -> Error 28
- 29 Illegal separator for a register list  
Valid separators are '-' and '/'.
- 30 SET, MACRO, XDEF, XREF and PUBLIC are illegal for a local symbol
- 31 Not a register (try d0-d7 or a0-a7 or sp)
- 32 Too many ')'
- 33 Unknown addressing mode  
See  
    Standard Addressing Modes  
    and  
    Extended Addressing Modes  
    for a complete description of all addressing modes.
- 34 Addressing mode not supported  
Example: move.b d0,a1 / move usp,d2 / clr.w (d3)+ -> Error 34
-

- 35 Can't use macro in operand  
Macros must be used as opcodes.
- 36 Undefined symbol
- 37 Missing register  
Example: `mulu d0,` -> Error 37
- 38 Need data-register
- 39 Need address-register
- 40 Word at odd address  
Example: `dc.b "Hallo"`  
`dc.w 0` -> Error 40  
Insert CNOP 0,2 or EVEN after string-constants.
- 41 Syntax error in operand
- 42 Relocatability error  
Example: `move.l label(pc),d0` , where label is not a reloc. and/or  
label is not defined in the current section -> Error 42
- 43 Too large distance  
Example: `move.w 50000(a0),d0` -> Error 43  
Too large distance for a displacement by indirect addressing or branch.  
Short branches have a range of +126/-128 bytes. Long branches have a  
range of +32766/-32768 bytes.
- 44 Displacement expected  
Example: `label: move.l label(a2),d1` -> Error 44
- 45 Valid address expected  
A program address was expected.
- 46 Missing argument
- 47 Need numeric symbol
- 48 Displacement outside of section  
Example: `bra label` , where label is not defined in the current  
section -> Error 48
- 49 Only one distance allowed  
Expression can't contain several distances.  
Example: `move.l #(label1-label2)+(label3-label4),d0` -> Error 49
- 50 Missing bracket/parenthesis
- 51 Expression stack overflow  
A maximum of 128 arguments are allowed in one expression.
- 52 Unable to negate an address
- 53 Can't use distance and reloc in the same expression  
Example: `move.l #(label1-label2)+label3,d0` -> Error 53
-



- 
- 54 Shift error (wrong type or negative count)  
Example: `l<<-1`                    -> Error 54  
          `label<<1`               -> Error 54
- 55 Can't multiply an address  
56 Overflow during multiplication  
57 Can't divide an address  
58 Division by zero  
59 No logical operation allowed on addresses  
60 Need two addresses to make a distance  
61 Unable to sum addresses
- 62 Write error
- 63 Not a byte-, word- or long-string  
Example: `dc.d "XYZ"`   -> Error 63
- 64 Can't subtract a XREF  
Valid operations with externals: `ext + abs` , `abs + ext` and `ext - abs`
- 65 Impossible in absolute mode  
These directive can't be used in absolute mode:  
`t1, code, cseg, data, dseg, bss, section, xref, nref, xdef, public`
- 66 Unknown error (fatal program failure)  
The assembler or its memory was corrupted by a faulty program running at the same time.
- 67 No externals in absolute mode  
See 65.
- 68 Out of range  
Example: `addq.l #9,d1`   -> Error 68
- 69 Assembly aborted  
Generated by the FAIL directive.
- 70 Missing ENDC/ENDIF
- 71 Missing macro name
- 72 Missing ENDM
- 73 Can't define macro within a macro
- 74 Unexpected ENDM
- 75 Unexpected ENDC/ENDIF
- 76 Impossible in relative mode  
These directive can't be used in relative mode: `org, file, load, track-disk`.
- 77 Parameter buffer overflow  
Macro parameters are limited to 63 characters.
-

- 78 Illegal REPT count  
The initial count for REPT should not be negative.
- 79 Unable to create file  
Maybe the destination disk is write-protected.
- 80 No reference list without a listing file  
XREFS switch was specified without the LIST switch.
- 81 No address allowed here  
Example: ds.l label -> Error 81
- 82 Illegal characters in symbol  
See error 22.
- 83 Source code too large (max. 65535 lines)
- 84 No floating point without the appropriate math-libraries  
To use floating point symbols, you must have the following libraries  
in your LIBS: directory:  
mathtrans.library, mathieeedoubbas.library, mathieeedoubtrans.library
- 85 Overflow during float calculation  
This happens usually when converting the result of a float expression  
into a float type with lower precision, e.g. FFP or Single Precision.
- 86 Illegal symbol type in float expression  
Don't use relocatable symbols in float expressions.
- 89 Type of SET can't be changed  
Example: symbol set.d 3.14159265  
symbol set.x -0.1 -> Error 89  
The value of SET is changeable, but not its type!
- 90 Can't mix LOAD, FILE and TRACKDISK  
Example: load \$70000  
file "mycode" -> Error 90
- 91 Near mode not activated  
The near mode must be activated first, before using the INITNEAR  
directive.
- 92 Instruction not implemented in your machine  
The instruction exists for another processor, but not for your one. Use  
MACHINE to change processor type.
- 93 Illegal scale factor  
Example: move.w (a1,d2\*3) -> Error 93  
Valid scale factors are: 1, 2, 4 and 8
- 94 Missing operand  
Example: move.l (a0)+ -> Error 94
- 95 Section doesn't exist  
This error is caused by specifying an illegal section number in the NEAR  
directive.
-

- 96 Illegal RORG offset  
The relative offset must not specify an address before the actual PC.
- 97 Immediate operand size error  
Example:    move.b    #\$1234,d0   -> Error 97
- 98 Missing ENDR  
Open repeat loop, when leaving the source code, an include file or macro.
- 99 Unexpected ENDR  
No matching REPT discovered.
- 100 REPT nesting depth exceeded  
The maximum nesting depth is 255.
- 101 Already a directive name  
You tried to define a macro, whose name is already used by a built-in directive or instruction.
- 102 SAVE nesting depth exceeded  
The maximum nesting depth is 8.
- 103 Unexpected RESTORE  
No matching SAVE discovered.
- 104 Missing RESTORE  
Missing a RESTORE when reaching the last line.

## 1.99 History / Literature

After six years of working with assemblers like SEKA, AS (Aztec-C) and A68k, I decided in December 1991 that I need a new, powerful assembler. First, I had the idea to buy O.M.A. or Devpac, but I don't like these modern assemblers with an integrated editor. Other reasons for starting the development of PhxAss were the chronic lack of money (I'm student) and the possibility to create an assembler which will satisfy all of my demands.

I completed the first version V1.00 at the 28th of January in 1992. From now on I used PhxAss to assemble itself (first I used A68k). It took me more than a year and 23 versions to reach V3.00 and nearly another two years and 52 versions for V4.00 (of course PhxAss was not my only project in this period).

Here is a list of my hardware and literature that made the development of PhxAss possible:

Hardware:    My good old A1000 (first version from '85) with 68010 CPU,  
              2 MB Fast-RAM and a 33 MB Harddisk.  
              (since December '93 also:) A4000, 68040, 18 MB RAM, 600 MB  
              Harddisk.

Literature: Motorola MC68000/68008/68010/68HC000 8-/16-/32-Bit Micro-  
              processor User's Manual (Prentice Hall)

---

Motorola MC68020 32-Bit Microprocessor User's Manual (Prentice Hall)

Motorola MC68040/68EC040/68LC040 Microprocessor User's Manual (Motorola)

Motorola MC68881/882 Floating-Point Coprocessor User's Manual (Prentice Hall)

Motorola MC68851 Paged Memory Management Unit User's Manual (Prentice Hall)

Motorola M68000, MC68020, MC68030, MC68040, MC68851, MC68881/882 Programmer's Reference Manual (Motorola)

Amiga ROM Kernel Reference Manual: Libraries & Devices (Addison-Wesley)

Amiga ROM Kernel Reference Manual: Includes & Autodocs (Addison-Wesley)

Amiga Intern (Data Becker)

Amiga Intern Band 2 (Data Becker)

The Amiga Guru Book (Taunusstein)

## 1.100 Acknowledgements

Thanks to the following persons, who intensively tested PhxAss and accelerated its development by constructive bug-reports:

Fabien Campagne (F)	
Tim Rühsen	SiliconSurfer@Blackbox.shnet.org
Wojciech Czyz (PL)	
Thomas Hagen Johansen (DK)	tjohansen@thj.adsp.sub.org
Matthias Bock	starfox@cow.mayn.de
Christian Bauer	cebix@ng-box.wwbnet.de
Dave Dustin (NZ)	dave@eclipsnz.manawatu.gen.nz
Richard Körber	r.koerber@tfh.dssd.sub.org
Christian Wasner	Crisi@Blackbox.shnet.org
Mark Knibbs (USA)	markk@msmail01.liffe.com
David Neale (GB)	david@reeve.demon.co.uk
Andy Church (USA)	achurch@binx.mbhs.edu
Rainer Koschnick	r.koschnick@r-m-b.gun.de
Volker Barthelmann	volker@vb.franken.de
Jorma Oksanen (SF)	tenu@sci.fi
Joop van de Wege (NL)	joop.vandewege@medew.ento.wau.nl

The swedish catalogs were made by:

Marcus Geelnard (S)	e4geeln@etek.chalmers.se
---------------------	--------------------------

The italian catalogs were made by:

Simone Tellini (I) Simone.Tellini@f502.n332.z2.fidonet.org

The danish catalogs were made by:

Morten Holm (DK) mortenh@viking.roskildees.dk

The french catalogs were made by:

Georges Goncalves (F) kersten\_emmrich@ramses.telesys-innov.fr

The dutch catalogs were made by:

Leon Woestenberg (NL) leon@stack.urc.tue.nl

The hungarian catalogs were made by:

Attila Tajti (H) tajtia@info.pmmf.hu

Author of PhxOpts:

Johan Johanssen (S) d95-jjo@nada.kth.se

Another acknowledgement, although gone bankrupt, is going to Commodore:

Thanks, for the only computer of the present time, which really makes fun to work with :-)

## 1.101 Known bugs in version V4.26

- o When instruction xxxx is completely removed by optimization, PhxAss will generate an illegal short branch with zero displacement:
 

```

B<cc>.B label
xxxx
label:
This will only happen when you've set the optimize flag 'M', and xxxx is a MOVEM without registers, or when you have set the 'S'-flag, and xxxx is a 'ADDA/SUBA #0,An' or 'LEA 0(An),An'.

```
- o The Forward-Branch optimization (T-flag) doesn't correct the line-addresses in the listing file.
- o Don't define labels directly before a CNOP directive!
 

```

label1:
    CNOP    0,4
label2:
Unfortunately, PhxAss can only differentiate between label1 and label2 in Pass 1. In Pass 2, it may happen that label1 is shifted too!
Sorry, I see no solution... :(

```

If any bugs or questions occur, please write to :


My Address

---

## 1.102 My Address

SMail: Frank Wille  
Auf dem Dreische 45  
32049 Herford  
GERMANY

EMail: frank@phoenix.owl.de



A M I G A F O R E V E R !