## **VBStak®**

## **TCP/IP Custom Control**

## © Copyright 1995 Christopher C. Smith

<u>Concepts</u> <u>Properties</u> <u>Events</u> <u>Troubleshooting</u> <u>Copyright and Registration</u>

## **Description**

The VBStak custom control provides a TCP/IP interface for Visual Basic and Visual C++ programs, opening Unix and Internet connectivity to Windows applications. VBStak handles the low level access to the Winsock dynamic link library, presenting a set of properties to the program.

The VBStak icon looks like the following when added to the Visual Basic tool box:



#### **File Name**

VBStak.vbx

### **Object Type**

**VBStak** 

#### Remarks

#### **Constants**

Data constants for VBStak are defined in VBSTAK.TXT.

**Distribution Notes:** When you create and distribute applications that use VBStak you should install VBSTAK.VBX in windows\system directory.

# **Properties**

 Action
 LocalPort

 Debug
 Output

 Family
 Protocol

 Host
 ProtocolName

 HostAddress
 RemotePort

 InBufferCount
 Service

 Input
 Socket

 InputLen
 Status

 LocalAddress
 Type

MasterSocket

## **Action Property**

## **Description**

Initiate a socket action. Write only at run time.

#### **Visual Basic**

[form.]VbStakControl . **Action** [= ActionConstant% ]

#### Remarks

Initiate the asynchronous action/request contained in *ActionValue* Upon completion of the action or request VBStak fires the <u>Message</u> event with the message parameter set to indicate source of the event. If an error occurred in the processing of the action/request the <u>Error</u> property will be set to the last error that occurred.

#### Action values are:

- <u>STAK\_ACTION\_CONNECT</u> Connect to the <u>host</u> on the <u>service</u> using the family and protocols. The <u>Family</u>, <u>Protocol</u>, <u>HostAddress</u>, <u>Type</u> and <u>RemotePort</u> properties must be set prior to this action. Upon completion of the request VBStak fires the Message event with <u>FD\_CONNECT</u> as the parameter.
- STAK\_ACTION\_CLOSE Close the socket. If the VBStak is in STAK\_STATE\_ACCEPTED state, the secondary socket is closed and the master socket is restored to a listening state (STAK\_STATE\_LISTENING). To close the master socket issue the STAK\_ACTION\_CLOSE again.
- <u>STAK\_ACTION\_GET\_SERVICE</u> Lookup the service name using the text in the <u>Service</u>property. Upon return VBStak fires the <u>Message</u>event with <u>STAK\_EVENT\_SERVICE</u> as the parameter. If the service is found the <u>RemotePort</u> property is set to the port number of the service.
- STAK\_ACTION\_GET\_HOST Lookup the IP address of the host entered in the Host property. Upon return VBstak fires the Message event with STAK\_EVENT\_HOST as a parameter. If the host has been found the HostAddress property is set to the dotted IP address of the host.
- STAK\_ACTION\_GET\_PROTOCOL Find the protocol number for the text in the <u>ProtocolName</u> property. Upon completion of the request VBStak fires the Message event with <u>STAK\_EVENT\_PROTOCOL</u> as the parameter. If the search was successful set the <u>Protocol</u> property to the integer value of the protocol.
- STAK\_ACTION\_LISTEN Prepare the socket as a server. Prior to this action the LocalPort should be set to a value above IPPORT\_RESERVED. Upon receiving a request for a connection the Message event STAK\_EVENT\_ACCEPT will occur. At this point two sockets will be open: the master socket (MasterSocket) and the secondary socket (Socket). The secondary socket will be available for data transactions and the master socket will be idle. Issuing a STAK\_ACTION\_CLOSE closes the secondary socket and reactivates the master socket.

<u>STAK\_ACTION SEND</u> Send the <u>datagram</u> to the socket. Upon completion of the request (assuming a response is pending) VBStak fires the the Message event with <u>FD\_READ</u> as the parameter. The <u>Output</u>property should be set prior to setting this action.

Note: The constants are contained in VBStak.txt file.

## Concepts

#### Introduction

VBStak is a Visual Basic Control (DLL) which provides a programming interface to the Winsock services through properties and events. VBStak is accessed through VBSTAK.VBX in conjunction with the constants file VBSTAK.TXT which are added to your project file.

## Setup

The recommended platform for VBStak development is the Windows for Workgroups (WFW) version 3.11 with the Microsoft WFWT32 driver set. This package is distributed free and can be downloaded from Compuserve and other BBS's. A handy Telnet program included in the package allows you to connect to the <a href="https://example.com/host\_and-monitor">host\_and-monitor</a> the connections and activity on the host at the same time as you debug your VBStak application.

Install the WFWT32 driver set into its own directory then install the driver using the WFW network setup utility. Make sure that your local <u>IP address</u> and local host name (your workstation) are assigned properly.

Create/edit the \windows\hosts file to include your host. The format for each host entry is:

hostipAddress

hostName

## **Asynchronous Interface**

VBStak utilizes asynchronous processing provided by Winsock to build a well behaved Windows program. The programming technique required to take advantage of this is presented in <u>Asynchronous Interface</u> topic. Detailed examples are provided in the VBMail and StakMan program samples.

## **Basic Steps (Client)**

TCP\IP client connectivity involves the four basic steps.

- 1. Configure local communication port (can be set at design time)
  - set the Family, Type properties
  - set the <u>Protocol</u> property.
  - set the LocalPort property
- 2. Connect to remote host.
  - set the HostAddress of the remote host.
  - set the RemotePort property.
  - connect.
- 3. Transmit and receive data.
  - load the <u>Output</u> property
  - send the data using the Action property with STAK\_ACTION\_SEND.
  - respond to the receipt of data in the Message event.
  - receive the data using the **Input** property.
- 4. Close the connection.
  - close the socket using the <u>Action</u> property and STAK ACTION CLOSE.

## **Basic Steps (Server)**

TCP\IP server connectivity involves the four basic steps.

- 1. Configure local communication port (can be set at design time)
  - set the Family, Type properties
  - set the <u>Protocol</u> property.
  - set the <u>LocalPort</u> property.
- 2. Listen for connection requests.
  - set the Action property to STAK ACTION LISTEN.
  - wait for the Message event with FD\_ACCEPT to indicate an accepted connection.
- 3. Transmit and receive data.
  - load the Output property
  - send the data using the Action property with STAK ACTION SEND.
  - respond to the receipt of data in the Message event.
  - receive the data using the **Input** property.
- 4. Close the connection.
  - close the socket using the <u>Action</u> property and STAK\_ACTION\_CLOSE. This restores the VBStak to the STAK STATUS LISTENING state.

#### **Database functions**

VBStak provides two interface methods for Winsock services, the direct access and the indirect database lookup method.

- 1. The direct access method requires that you specify the host address, protocol and host port using the numeric values such as the dotted host address format 192.23.3.1. This requires that you know, prior to running the program, the absolute value of these properties.
- 2. The second (and preferred) method uses the Unix database facilities to provide a translation between text based names and the socket parameters. The host name is entered in the familiar *user@company.com* format. The address of the host is resolved by the network name resolution functions. Protocol names and services are entered as their 'well know names' (eg. tcp and telnet). This interface allows greater flexibility in addressing and user defined services.

Three files installed in your \windows directory define the databases provided. Alternately if your network has Domain Name System installed the files exist on the name server in the /etc/ directory. The file are:

hosts a list of the hosts on the network, including your local workstation. services a list of the network services, port numbers and protocols. protocol a list of the available protocols

## Copyright and Shareware Licence

© Copyright 1995 Christopher C. Smith, All rights reserved.

Thank you for considering VBStak for your TCP/IP development project. Our objective is to provide communication solutions that are accessable and reasonably priced. We do this by concentrating our resources on development and customer support, not advertising and marketing. If your project can benefit from this control please jump to <a href="Registration"><u>Registration</u></a> to view the benefits of registering this product.

Distribution of the Shareware version is permitted under the following terms:

#### **DEFINITION OF SHAREWARE**

Shareware distribution gives users a chance to try software before buying it. If you try a Shareware program and continue—using it, you are expected to register. Individual programs—differ on details -- some request <u>registration</u>while others require it, some specify a maximum trial period. With—registration, you get anything from the simple right to continue using the software to an updated program with printed manual.

Copyright laws apply to both Shareware and commercial software, and the copyright holder retains all rights, with a few specific exceptions as stated below. Shareware authors are accomplished programmers, just like commercial authors, and the programs are of comparable quality. (In both cases, there are good programs and bad ones!) The main difference is in the method of distribution. The author specifically grants the right to copy and distribute the software, either to all and sundry or to a specific group. For example, some authors require written permission before a commercial disk vendor may copy their Shareware.

Shareware is a distribution method, not a type of software. You should find software that suits your needs and pocketbook, whether it's commercial or Shareware. The Shareware system makes fitting your needs easier, because you can try before you buy. And because the overhead is low, prices are low also. Shareware has the ultimate money-back guarantee -- if you don't use the product, you don't pay for it.

#### **DISCLAIMER - AGREEMENT**

Users of VBStak must accept this disclaimer of warranty:

"VBStakis supplied as is. The author disclaims all warranties, expressed or implied, including, without limitation, the warranties of merchantability and of fitness for any purpose. The author assumes no liability for damages, direct or consequential, which may result from the use of VBStak."

VBStak is a "shareware program" and is provided at no charge to the user for evaluation. Feel free to share it with your friends, but please do not give it away altered or as part of another system. The essence of "user-supported" software is to provide personal computer users with quality software without high prices, and yet to provide incentive for programmers to continue to develop new products. If you find this program useful and find that you are using VBStak and continue to use VBStak after a reasonable trial period, you must make a registration payment of \$49.00 US to Third Stone. The \$49.00 US registration fee will license one copy for use on any one computer at any one time. You must treat this software just like a book. An example is that this software may be used by any number of people and may be freely moved from one computer location to another, so long as there is no possibility of it being used at one location while it's being used at another. Just as a book cannot be read by two different persons at the same time.

Commercial users of VBStak must register and pay for their copies of VBStak within 30 days of first use or their license is withdrawn. Site-License arrangements may be made by contacting Third Stone.

Anyone distributing VBStak for any kind of remuneration must first contact Third Stone at the address below for authorization. This authorization will be automatically granted to distributors recognized by the (ASP) as adhering to its guidelines for shareware distributors, and such distributors may begin offering VBStak immediately (However Third Stone must still be advised so that the distributor can be kept up-to-date with the latest version of VBStak .).

You are encouraged to pass a copy of VBStak along to your friends for evaluation. Please encourage them to register their copy if they find that they can use it. All registered users will receive a copy of the latest version of the VBStak system.

## Registration

## What do I get for registering?

- 1. Royalty free licence with distribution VBStak.vbx.
- 2. Free updates for 6 months.
- 3. 1 Year of TIP's Electronic newsletter with TCP/IP connectivity examples, programming tips and configuration details.

### How do I register?

#### **Credit Card Orders:**

(NorthStar Solutions credit card order processing - not tech support)

Phone: 1-800-699-6395 (10:00 a.m. to 10:00 p.m., Eastern Standard Time)

Fax 1-803-699-5465 (24 hours) E-mail 71561.2751@compuserve.com

or

Compuserve registration: GO SWREG use Registration #: 5222

or

## **Check/Money orders:**

Fill in VBStak.reg and send \$49.00 to:

Third Stone Engineering, Inc. 5215 Sepulveda Blvd. Suite 6A Culver City, CA 90230

Regardless of how you register, please have the following information ready:

- 1. The program and version number ([NAME] version [x.x]) you are registering.
- 2. Where the latest version should be mailed.
- 3. Your Visa or MasterCard # and its expiration date (if using Visa/MC).
- 4. Your drive types, 5.25 inch or 3.5 inch.

NOTES: 1) NorthStar processes registrations only, please contact Third Stone for any product/technical support.

2) E-mailed or faxed registrations are encouraged due to their low cost & high efficiency, but any registration is appreciated!

\_\_\_\_\_\_

## **VBStak Registration**

Product: VBSTAK.VBX Version 1.2

Name: Company: Address: City:

x \$US 49:

## **Host Property**

## **Description**

Sets and returns the name of the remote computer. Read/write.

#### **Visual Basic**

```
[form.]VbStakControl . Host [= hostName$]
```

#### Remarks

The <u>host</u> property is the name of the host computer in the user@entity.type form. This is used with the <u>STAK\_ACTION\_GET\_HOST</u> action parameter to look up the host address. The Winsock dll uses the **hosts** file in the windows directory to search for a host/address association in the absence of a Domain Name System (DNS) server.

To locate a host:

- 1. Set the Host property to the name of the host eg. "haddock@tse.com"
- Set the <u>Action</u> property to <u>STAK\_ACTION\_GET\_HOST</u>.

Response:

- 1. VBStak sets the <u>HostAddress</u> property with the <u>IP address</u> (nnn.nnn.nnnn format) of the host if located. The <u>Error</u> property is set if an error occurred.
- 2. VBStak fires the Message event with STAK EVENT HOST.

## Data Type String

## **Example:**

Define a form with a button called CheckHost and a VBStak control called VBStak.

```
Sub CheckHost_Click()

VBStak.Service = "haddock@tse.com"
```

VBStak.Action = STAK ACTION GET HOST

**End Sub** 

Sub VBStak Message(message as Integer)

```
' Check the return response
Select Case message
Case STAK_EVENT_HOST
' .....
If VBStak.Error = 0 then
```

```
HostAddressBox.Text = VBStak.HostAddress
Else

MsgBox("Host " & VBStak.Host & " not found - Error: " &

Str(VBStak.Error))

End If

....
End Select
End Sub
```

## Input Property

## Description

Receive the number of bytes set by the <u>InputLen</u> property. Read only at run time.

#### **Visual Basic**

[form.]VbStakControl . Input

#### Remarks

If there are more bytes in the input buffer than defined in InputLen VBStak will retrieve the InputLen number of bytes and then post another FD\_READ message event indicating that there is more data available.

If there are less then InputLen bytes available VBStak will retrieve an empty string and set the Error property to <a href="mailto:STAK\_ERROR\_DATA\_NOT\_AVAILABLE">STAK\_ERROR\_DATA\_NOT\_AVAILABLE</a>.

**Note:** If you use <u>InputLen</u> to set the input size, it is important to check the InBufferCount value prior to accessing the <u>Input</u> property. Winsock only sends the <u>FD\_READ</u> message when data is first available or after an Input access with an InputLen which is less than the InBufferCount. This means that if you attempt to input more than the buffer count you will not get subsequent <u>FD\_READ</u> messages. To prevent this deadlock you must clear the buffer with the Input property.

Prior to receiving data the socket must be connected to a <u>host</u>. This is accomplished by setting the <u>Action</u> property to <u>STAK\_ACTION\_CONNECT</u>. The connect action enables data reception on the socket and directs the Winsock messages to the control event Message.

Data Type String

## **Error Property**

#### Description

Sets and returns the error result of the last socket operation. Read only at run time.

#### **Visual Basic**

[form.]VbStakControl . Error

#### Remarks

VBStak errors are defined below and in VBStak.txt. The text string associated with an error are defined in VBStak.txt as the error name with a "S" suffix eg. WSANOTINITIALISED S. These can be loaded into an array at startup time.

WSANOTINITIALISED = "A successful WSAStartup() must occur before using this API."

WSAENETDOWN = "The Windows Sockets implementation has detected that the network subsystem has failed."

WSAEADDRINUSE = "The specified address is already in use. (See the SO REUSEADDR socket option under setsockopt().)"

WSAEFAULT = "The namelen argument is too small (less than the size of a struct sockaddr)."

WSAEINTR = "The (blocking) call was canceled via WSACancelBlockingCall()"

WSAEINPROGRESS = "A blocking Windows Sockets call is in progress."

WSAEAFNOSUPPORT = "The specified address family is not supported by this protocol."

WSAEINVAL = "The socket is already bound to an address."

WSAENOBUFS = " Not enough buffers available, too many connections." WSAENOTSOCK = "The descriptor is not a socket."

WSAEADDRNOTAVAIL = "The specified address is not available from the local machine."

WSAECONNREFUSED = "The attempt to connect was forcefully rejected."

WSAEDESTADDREQ = "A destination address is required."

WSAEISCONN = "The socket is already connected."

WSAEMFILE = "No more file descriptors are available."

WSAENETUNREACH = "The network can't be reached from this host at this time."

WSAETIMEDOUT = "Attempt to connect timed out without establishing a connection"

WSAEWOULDBLOCK = "The socket is marked as non-blocking and the connection cannot be completed immediately. It is possible to select() the socket while it is connecting by select()ing it for writing."

- WSAHOST\_NOT\_FOUND = "Authoritative Answer Host not found."
  WSATRY\_AGAIN = "Non-Authoritative Host not found, or SERVERFAIL."
  WSANO\_RECOVERY = "Non recoverable errors, FORMERR, REFUSED,
  NOTIMP."
- WSANO\_DATA = "Valid name, no data record of requested type."
  WSAENOPROTOOPT = "The option is unknown or unsupported. In particular."
- WSAEACCES = "The requested address is a broadcast address, but the appropriate flag was not set."
- WSAENETRESET = "The connection must be reset because the Windows Sockets implementation dropped it."
- WSAENOTCONN = "The socket is not connected."
- WSAEOPNOTSUPP = "MSG\_OOB was specified, but the socket is not of type SOCKTREAM."
- WSAESHUTDOWN = "The socket has been shutdown; it is not possible to send() on a socket after shutdown() has been invoked with how set to 1 or 2."
- WSAEMSGSIZE = "The socket is of type SOCK\_DGRAM, and the <u>datagram</u> is larger than the maximum supported by the Windows Sockets implementation."
- WSAECONNABORTED = "The virtual circuit was aborted due to timeout or other failure."
- WSAECONNRESET = "The virtual circuit was reset by the remote side."

## Service Property

#### Description

Sets and returns the name of the <u>service</u> to use on the remote <u>host</u>. Read and write design and run time.

#### **Visual Basic**

[form.]VbStakControl . Service [= serviceName\$]

#### Remarks

The service property sets the service to connect to on the host. Use the Service property to verify that the service exists on the host and to define the <u>RemotePort</u> property. A list of the services is maintained in the **/etc/services** file on the host and in the **services** file in the local Windows directory.

To define a custom service, add the definition to the **services** file in your Windows directory. Each service is defined on one lin in the form:

serviceName portNumber/protocolName comment

eg.

echo 7/tcp return all data

To locate the host port number:

- 1. Set the Service property to the service name.
- 2. Set the ProtocolName property to the desired protocol (tcp/udp)
- 3. Set the Action property to STAK ACTION GET SERVICE.

Upon completion of the request VBStak sets the RemotePort property to the port number and fires the <u>Message</u> event with <u>STAK EVENT SERVICE</u>.

## Data Type String

See Also: <u>Host</u> property, <u>Action</u> property

#### **Example:**

Define a form with a button called CheckService and a VBStak control called VBStak.

Sub CheckService\_Click()

```
VBStak.Service = "echo"
VBStak.ProtocolName = "tcp"
VBStak.Action = STAK_ACTION_GET_SERVICE
```

## **End Sub**

```
Sub VBStak_Message(message as Integer)
```

```
'Check the return response
Select Case message
Case STAK_EVENT_SERVICE
'....

If VBStak.Error = 0 then
RemotePortBox.Text = VBStak.RemotePort
Else
MsgBox("Service Request Failed")
End If
'....
End Select
End Sub
```

# RemotePort Property

## **Description**

Sets and returns the numeric value of the port on the remote <u>host</u>. Read/Write.

#### Visual Basic

[form.]VbStakControl . RemotePort [= portNumber%]

#### Remarks

The RemotePort property can be set directly to define the port number of the host <u>service</u>. The preferred method of defining the RemotePort value is to set the <u>Service</u> property to the symbolic name for the service then set the <u>Action</u> property to STAK\_ACTION\_GET\_SERVICE.

## HostAddress Property

## **Description**

Sets and returns the <u>IP address</u> of the remote computer.

#### **Visual Basic**

[form.]VbStakControl . **HostAddress** [= ipAddress\$]

#### Remarks

The HostAddress property is the string representation of the 32 bit address assigned to the <u>host</u>. This is used by VBStak to reach the remote computer.

The HostAddress property can be set directly to quickly test a host response or if the host address will not change in the furture. However the recommended method of defining the HostAddress property is to set the <u>Host</u> property to the symbolic address of the host then setting the <u>Action</u> property to <u>STAK\_ACTION\_GET\_HOST</u>.

## Data Type String

# Family Property

## **Description**

Sets and returns the family of protocols to use on the socket connection.

#### Visual Basic

[form.]VbStakControl . **Family** [= familyConstant%]

### **Remarks**

The family values are defined in VBSTAK.TXT. The usual value for Family property is set AF\_INET for remote <u>host</u> to host communication.

# **Protocol Property**

## **Description**

Sets and returns the protocol of the local socket. Read/Write.

#### **Visual Basic**

[form.]VbStakControl . Protocol [= protocolValue%]

### **Remarks**

The Protocol value may be set directly or may be defined by setting the <a href="ProtocolName">ProtocolName</a> property then setting the <a href="Action">Action</a> property to <a href="STAK\_ACTION\_GET\_PROTOCOL">STAK\_ACTION\_GET\_PROTOCOL</a>. This will tell VBStak to look up the protocol value.

Protocol values are stored in the windows\system\protocols file distributed with Winsock.dll.

# Type Property

## **Description**

Sets and returns the type of the local socket. Read/Write.

#### **Visual Basic**

[form.]VbStakControl . **Type** [= ipAddress\$]

#### Remarks

The type values are:

```
SOCK_STREAM - Stream socket (use with TCP protocol)
SOCK_DGRAM - Datagram socket (use with UDP protocol)
SOCK_RAW - Raw protocol interface
SOCK_RDM - Reliably delivered message
SOCK_SEQPACKET - Sequenced packet stream
```

Common values for type are SOCK\_STREAM or SOCK\_DGRAM. Type values may be set at design time using the drop down list provided with VBStak.

# **Output Property**

## **Description**

Load the output buffer with a string. Run time write only.

#### **Visual Basic**

[form.]VbStakControl . **Output** [= sendString\$]

### Remarks

Setting this property makes the strng available for transmission. To actually send the data the <u>Action</u> property must be set to <u>STAK\_ACTION\_SEN</u>.

The string may contain byte values between 0 and 255.

## Data Type String

# Message Service Example

This example is a template for the asynchronous serviceing of the Winsock requests initiated by setting the <u>Action</u> property. To run this example setup a form with a VBStak control named VBStak. Add controls:

```
StatusBox - (TextBox) The status of the socket connection. Make this a multi-
   line control.
   InputBox - (TextBox) - User input.
   ActionButton (Button) - Start the action
   Sub VBStak Message (message As Integer)
     Service the message event
   If VBStak.Error = 0 then
        Select Case message
        Case FD CONNECT
             ' The socket has connected to the <u>host</u>
             StatusBox.Text = "Connected to " & VBStak.HostAddress & "/"
        Case FD READ
              ' Copy to the output text box.
             InputBuffer.Text = InputBuffer.Text & VBStak.Input & Chr(13) &
   Chr(10)
                Case FD CLOSE
             VBStak.Action = STAK ACTION CLOSE
                          StatusBox.text = "Closed"
        Case STAK EVENT SERVICE
             'The remote port has been loaded
             StatusBox.Text = "Host Port: " & VBStak.RemotePort
        Case STAK_EVENT_PROTOCOL
             'The protocol has been loaded
             StatusBox.Text = "Protocol Number: " & VBStak.Protocol
        Case STAK EVENT HOST
             'The host address has been loaded
             StatusBox.Text = "Remote Host Address: " & VBStak.HostAddress
                          ConnectButton.Enabled = true
        End Select
   Else
        StatusBox.Text = "Error: " & VBStak.Error
   End If
End Sub
```

# Asynchronous Interface

VBStak utilizes the asynchronous request facilities of the Winsock dll. This approach provides a well behaved Windows interface because other processes are able to execute while waiting for a request to complete. This fits Visual basic's event driven architecture very well as long as we utilize it properly.

The effective utilization of VBStak involves separating the action initiation from the request result. In a single user / process environment the following code is permissible:

```
Sub WeHaveAllDay()
    Call InitiateAction()
    While not Responded() and not TimedOut()
    ' Wait here
    Loop
    If TimedOut() then
        Call ProcessTimeOutError()
    End If
End Sub
```

In a multi-processing environment (especially Windows without any preemption) this code would prevent any other program from getting access to the processor or at least waste a lot of processor time. Event driven programs separate the initiation / result portions of the program as follows:

```
' Initiating procedure
Sub StartThingsOff()
    RequestTimer.Interval = THE MAXIMUM TOLERABLE WAIT
    RequestTimer.Enabled = True
    VBStak.Output = "Echo this string" & Chr(0)
    VBStak.Action = STAK_ACTION_SEND
End Sub
'Receiving procedure - VBStak messages are processed here.
Sub VBStak message(message as integer)
    Select Case message
    Case FD READ
         ' Service the request
         Text1.text = VBStak.Input
          ' Initiate the next transmission
    End Select
End Sub
'To prevent an indefinite wait a timer is used:
Sub RequestTimer Time
```

' Alert user and/or retry MsgBox("Request Timed Out") End Sub

This trilog of procedures seems more complicated than the direct send/wait loop. However in fact the programming steps are the same, they have just been separated into independent, asynchronous modules which allows other processes to run while your program waits for input.

The control of sequential operations is implemented by building a state machine in the Message event. As each step in the sequence is completed (the appropriate resonse from the <u>host</u>) the state of the machine is set to the next step in the sequence. If an error occurs the state machine is reset to an idle state. A working example of this technique is contained in the VBMail sample program.

# **LocalPort Property**

### **Description**

Sets and returns the port number to use on the local socket. Read/write.

#### Visual Basic

[form.]VbStakControl . LocalPort [= portNumber%]

#### Remarks

The local port value may be set to 0 to allow the socket to pick the next available port. The LocalPort property must be set prior to connecting to the remote <u>host</u>. If VBStak is to be used as a server the LocalPort property must be set to the value that will be used by the remote computer to connect to the server.

Standard port values are defined in the Services file distributed with Winsock. A user defined port may be used if it is in above the <a href="IPPORT\_RESERVED">IPPORT\_RESERVED</a> (1024) range.

Data Type Integer

# **Debug Property**

## **Description**

Sets and returns the socket debug setting. Read/write.

### **Visual Basic**

[form.]VbStakControl . Debug [= debugSetting%]

### **Remarks**

VBStak debug mode displays messages indicating the phases of the Action property actions.

## Data Type Integer (Boolean)

# **Status Property**

### **Description**

Returns a value indicating the state of the VBStak control. Read only at run time.

#### **Visual Basic**

[form.]VbStakControl . Status

#### Remarks

The integer constants are defined in VBStak.txt

STAK STATUS IDLE - Control has been loaded but not initialized.

STAK\_STATUS\_INITIALIZED - VBStak has been initialized.

STAK STATUS OPENED - Socket is opened.

STAK STATUS BOUND - Socket bound to protocol.

STAK\_STATUS\_CONNECTED - Socket has conected to a <a href="https://example.com/html/>host.">host.</a>.

STAK STATUS SENDING - Sending to host.

**STAK\_STATUS\_WAITING** - Waiting for response.

STAK\_STATUS\_REC\_READY - Input available.

#### Data Type Integer

# Socket Property

# **Description**

Returns the handle of the local socket. Run time read/write.

### **Visual Basic**

[form.]VbStakControl . Socket

### **Remarks**

The number of the socket assigned by the Winsock dll.

## Data Type Integer

# ProtocolName Property

## **Description**

Sets and returns the name of the TCP/IP protocol to use. Read/write.

#### Visual Basic

[form.]VbStakControl . **ProtocoName** [= protocolString\$]

#### Remarks

The Protocol property defines the symbolic value for the protocol to use in TSP/IP communication. The common values are TCP and UDP.

The symbolic protocol name is used to retrieve the numeric <u>Protocol</u> property through an Action property setting with the STAK ACTION GET PROTCOL value.

## Data Type String

# Message Event

### **Description**

Notifies the application that an event has occured which may require servicing.

#### **Visual Basic**

Sub VBStakControl Message (messageNumber as integer)

#### Remarks

This is the entry point for Winsock message postings. Asynchronous calls to the Winsock dll are routed back the VBStak control upon completion. The VBStak fires the message event to notify your program of the message. The messages are:

- **FD\_ACCEPT** A connection has been requested by a client on a VBSTAK which has been enabled for listening. See <u>Action</u> property STAK ACTION LISTEN.
- **FD\_CLOSE** The socket has been closed at the <u>host</u> end. This occurs with services such as Daytime which respond with a single <u>datagram</u>.
- **FD CONNECT** Socket has completed a connect to a host.
- FD OOB Out of band data has arrived on the socket.
- **FD\_READ** Socket data is available for reading. Data can be accessed through the <u>Input tproperty</u>.
- FD WRITE Socket has completed the last write operation.
- **STAK EVENT HOST** The STAK ACTION GET HOST action has completed.
- **STAK\_EVENT\_SERVICE** The STAK\_ACTION\_GET\_SERVICE action has completed. If an error occurred the <u>Error</u> property will contain the error value.
- **STAK\_MESSAGE\_PROTOCOL** The STAK\_ACTION\_GET\_PROTOCOL has completed.

**See Also:** Action Property, Errors, Error Property, Input Property

# **Troubleshooting**

The following list is a quick troubleshooting guide.

## Cannot locate host

```
Check:
```

The existence of \windows\hosts file.

Host name entry in the form:

ipAddress(nnn.nnn.nnn form) hostName

Correct host name.

## Cannot locate service/port number

#### Check:

The existence of \windows\services file.

Entry of the <u>service</u> you are trying to connect to such as:

echo 7/tcp

Host - /etc/services file.

### Cannot locate the protocolName

#### Check:

The existence of \windows\protocol file.

The entry of the protocol you want such as:

tcp 6 TCP # Transmission control protocol

Host - /etc/protocol file.

## Cannot find Winsock library.

#### Check:

Installed Winsock library. The TCP/IP WFWT32.EXE library can be downloaded from Compuserve and other services.

Installed protocol - see network setup for WFW.

### Cannot connect to host

#### Check:

Network and host availability - use the Telnet function built into the TCP/IP library to connect to the host.

Host services, inetd running.

Host address correct - check \windows\hosts file.

# InputLen Property

### **Description**

Define the number of bytes to receive using the <u>Input</u> property. Read/write.

### **Visual Basic**

[form.]VbStakControl . InputLen [= inputLength%]

#### **Remarks**

To receive the complete buffer set InputLen to 0. To check the number of bytes available in the input buffer use the <u>InBufferCount</u> property prior to using the Input property.

## Data Type String

# InBufferCount Property

# **Description**

Returns the number of bytes of data in the input buffer.

#### **Visual Basic**

[form.]VbStakControl . InBufferCount

#### Remarks

InBufferCount can be used to check for a complete fixed-length string. If you use the InputLen property to set the size of the input string you should always check the value of the InBufferCount prior to accessing the Input property.

## Data Type Integer

# **LocalAddress Property**

## **Description**

Sets and returns the <u>IP address</u> of the local socket.

#### Visual Basic

[form.]VbStakControl . LocalAddress [= ipAddress\$]

#### Remarks

The primary use of the LocalAddress Property is with multi-homed servers such as Compuserve. The IP address assigned to the local socket changes on each connection. This information is valid only after a successful <a href="STAK\_ACTION\_CONNECT">STAK\_ACTION\_CONNECT</a>.

## Data Type String

Helpfile generated by VB HelpWriter.

# MasterSocket Property

## **Description**

Returns/sets the handle of the master server socket associated with the socket. Run time read only.

#### **Visual Basic**

[form.]VbStakControl . MasterSocket

#### **Remarks**

The number of the master socket used to create the secondary data socket. This property is used by VBStak to restore the server socket to the listening state after a data transaction is complete. The main use of this property for the VB programmer is in debugging server applications.

### Data Type Integer

Helpfile generated by VB HelpWriter.

# Glossary

Α	В	C	D	E	F	G	Н	П	J	K	L	М
N	0	Р	Q	R	S	I	U	٧	W	X	Y	Z

**D** datagram

<u>**H**</u> host

<u>I</u> <u>IP address</u>

<u>**S**</u> service

**W** well known service

# host

A TCP/IP <u>service</u> provider (server).

# service

A program function made available to outside computers. The services are typically defined in the host's /etc/services database.

**datagram**A single TCP/IP transmission chunk containing the source, destination, port, and data information.

**well known service**A predefined list of services provided by typical Unix systems.

# **IP** address

The unique numeric address assigned to a computer using the TCP/IP protocol. The VBstak text representation of the IP address is the dotted address form: 123.456.789.012.