

asl.library (basename: _AslBase) V36

AllocAslRequest(type,tagList)(d0/a0)
 - Also stack-based amiga.lib stub
 AllocAslRequestTags() alloc an ASL requester, with TagItem modifiers (V36)
 AllocFileRequest()
 AslRequest(request,tagList)(a0/a1)
 - Allocates a FileRequester structure (V36)
 - lso stack-based amiga.lib stub
 AslRequestTags(). Get input from user for an ASL requester (V36)
 FreeAslRequest(request)(a0)
 - Frees requester obtained from AllocAslRequest (V36)
 FreeFileRequest(fileReq)(a0)
 - Frees requester allocated by AllocFileRequest (V36)
 RequestFile(fileReq)(a0)
 - request user to select file(s) (V36)

battclock.resource (basename: _BattClockBase)

ReadBattClock()
 - Read time from clock chip. (V36)
 ResetBattClock()
 - Reset the clock chip. (V36)
 WriteBattClock(time)(d0)
 - Set the time on the clock chip. (V36)

battmem.resource (basename: _BattMemBase)

ObtainBattSemaphore()
 - Obtain access to nonvolatile ram. (V36)
 ReadBattMem(buffer,offset,length)(a0,d0/d1)
 - Read a bitstring from nonvolatile ram. (V36)
 ReleaseBattSemaphore()
 - Allow nonvolatile ram to others. (V36)
 WriteBattMem(buffer,offset,length)(a0,d0/d1)
 - Write a bitstring to nonvolatile ram. (V36)

clipboard.device (device commands)

CBD_CHANGEHOOK - Add or remove a clip change hook.

commodities.library (basename: _CxBase) V36

ActivateCxObj(co,true)(a0,d0)
 - Change the activation state of a commodity object.
 AddIEvents(events)(a0)
 - Add input events to commodities' input stream. (V36)
 AttachCxObj(headobj,co)(a0/a1)
 - Attach a commodity object to the end of an existing
 ClearCxObjError(co)(a0)
 - Clear the accumulated error value of a commodity
 CreateCxObj(type,arg1,arg2)(d0/a0/a1)
 - Create a new commodity object. (V36)
 CxBroker(nb,error)(a0,d0)
 - Create a commodity broker. (V36)
 CxMsgData(cxm)(a0)
 - Obtain a pointer to a commodity message's data area. (V36)
 CxMsgID(cxm)(a0)
 - Obtain the ID of a commodity message. (V36)
 CxMsgType(cxm)(a0)
 - Obtain the type of a commodity message. (V36)
 CxObjError(co)(a0)
 - Obtain a commodity object's accumulated error. (V36)

CxObjType(co)(a0)
 - Obtain the type of a commodity object. (V36)
 DeleteCxObj(co)(a0)
 - Delete a commodity object. (V36)
 DeleteCxObjAll(co)(a0)
 - Recursively delete a tree of commodity objects.
 DisposeCxMsg(cxm)(a0)
 - Delete a commodity message. (V36)
 DivertCxMsg(cxm,headobj,ret)(a0/a1/a2)
 - Send a commodity message down an object list. (V36)
 EnqueueCxObj(headobj,co)(a0/a1)
 - Insert a commodity object within a list of objects
 InsertCxObj(headobj,co,pred)(a0/a1/a2)
 - Insert a commodity object in a list after a given
 InvertKeyMap(ansicode,event,km)(d0/a0/a1)
 - Generate an input event from an ANSI code. (V36)
 ParseIX(description,ix)(a0/a1)
 - Initialize an input expression given a description string.
 RemoveCxObj(co)(a0)
 - Remove a commodity object from a list. (V36)
 RouteCxMsg(cxm,co)(a0/a1)
 - Set the next destination of a commodity message. (V36)
 SetCxObjPri(co,pri)(a0,d0)
 - Set the priority of a commodity object. (V36)
 SetFilter(filter,text)(a0/a1)
 - Change the matching condition of a commodity filter.
 SetFilterIX(filter,ix)(a0/a1)
 - Change the matching condition of a commodity filter.
 SetTranslate(translator,events)(a0/a1)
 - Replace a translator object's translation list. (V36)

disk.resource (basename: _DiskBase)

ReadUnitID(unitNum)(d0)
 - Reread and return the type of drive (V37)

diskfont.library (basename: _DiskfontBase)

NewScaledDiskFont(sourceFont,destTextAttr)(a0/a1)
 - Create a DiskFont scaled from another. (V36)

dos.library (basename: _DOSBase)

AbortPkt(port,pkt)(d1/d2)
 - Aborts an asynchronous packet, if possible. (V36)
 AddBuffers(name,number)(d1/d2)
 - Changes the number of buffers for a filesystem (V36)
 AddDosEntry(dlist)(d1)
 - Add a Dos List entry to the lists (V36)
 AddPart(dirname,filename,size)(d1/d2/d3)
 - Appends a file/dir to the end of a path (V36)
 AddSegment(name,seg,system)(d1/d2/d3)
 - Adds a resident segment to the resident list (V36)
 AllocDosObject(type,tags)(d1/d2)
 - Creates a dos object (V36)
 AssignAdd(name,lock)(d1/d2)
 - Adds a lock to an assign for multi-directory assigns (V36)
 AssignLate(name,path)(d1/d2)
 - Creates an assignment to a specified path later (V36)
 AssignLock(name,lock)(d1/d2)
 - Creates an assignment to a locked object (V36)

AssignPath(name,path)(d1/d2) - Creates an assignment to a specified path (V36)

AttemptLockDosList(flags)(d1) - Attempt to lock the Dos Lists for use (V36)

ChangeMode(type,fh,newmode)(d1/d2/d3)- Change the current mode of a lock or filehandle (V36)

CheckSignal(mask)(d1) - Checks for break signals (V36)

Cli()() - Returns a pointer to the CLI structure of the process (V36)

CliInitNewCli(dp)(a0) - Set up a process as a shell according to the initial packet.

CliInitRun(dp)(a0) - Set up a process as a shell according to the initial packet.

CompareDates(date1,date2)(d1/d2) - Compares two timestamps (V36)

CreateNewProc(tags)(d1) - Create a new process (V36)

DateToStr(datetime)(d1) - Converts a DateStamp to a string (V36)

DeleteVar(name,flags)(d1/d2) - Deletes a local or environment variable (V36)

DoPkt(port,action,arg1,arg2,arg3,arg4,arg5)(d1/d2/d3/d4/d5/d6/d7) - Send a dos packet and wait for reply (V36)

DupLockFromFH(fh)(d1) - Gets a lock on an open file (V36)

EndNotify(notify)(d1) - Ends a notification request (V36)

ErrorReport(code,type,arg1,device)(d1/d2/d3/d4) - Displays a Retry/Cancel requester for an error (V36)

ExAll(lock,buffer,size,data,control)(d1/d2/d3/d4/d5) - Examine an entire directory (V36)

ExamineFH(fh,fib)(d1/d2) - Gets information on an open file (V36)

Fault(code,header,buffer,len)(d1/d2/d3/d4) - Returns the text associated with a DOS error code (V36)

FGetC(fh)(d1) - Read a character from the specified input (buffered) (V36)

FGets(fh,buf,buflen)(d1/d2/d3) - Reads a line from the specified input (buffered) (V36)

FilePart(path)(d1) - Returns the last component of a path (V36)

FindArg(keyword,template)(d1/d2) - Find a keyword in a template (V36)

FindCliProc(num)(d1) - Returns a pointer to the requested CLI process (V36)

FindDosEntry(dlist,name,flags)(d1/d2/d3) - Finds a specific Dos List entry (V36)

FindSegment(name,seg,system)(d1/d2/d3) - Finds a segment on the resident list (V36)

FindVar(name,type)(d1/d2) - Finds a local variable (V36)

Flush(fh)(d1) - Flushes buffers for a buffered filehandle (V36)

Format(filesystem,volumename,dostype)(d1/d2/d3) - Causes a filesystem to initialize itself (V36)

FPutC(fh,ch)(d1/d2) - Write a character to the specified output (buffered) (V36)

Fputs(fh,str)(d1/d2) - Writes a string the the specified output (buffered) (V36)

FRead(fh,block,blocklen,number)(d1/d2/d3/d4) - Reads a number of blocks from an input (buffered) (V36)

FreeArgs(args)(d1) - Free allocated memory after ReadArgs() (V36)

FreeDeviceProc(dp)(d1) - Releases port returned by GetDeviceProc() (V36)

FreeDosEntry(dlist)(d1) - Frees an entry created by MakeDosEntry (V36)

FreeDosObject(type,ptr)(d1/d2) - Frees an object allocated by AllocDosObject() (V36)

FWrite(fh,block,blocklen,number)(d1/d2/d3/d4) - Writes a number of blocks to an output (buffered) (V36)

GetArgStr()() - Returns the arguments for the process (V36)

GetConsoleTask()() - Returns the default console for the process (V36)

GetCurrentDirName(buf,len)(d1/d2) - Returns the current directory name (V36)

GetDeviceProc(name,dp)(d1/d2) - Finds a handler to send a message to (V36)

GetFileSysTask()() - Returns the default filesystem for the process (V36)

GetProgramDir()() - Returns a lock on the directory the program was loaded

GetProgramName(buf,len)(d1/d2) - Returns the current program name (V36)

GetPrompt(buf,len)(d1/d2) - Returns the prompt for the current process (V36)

GetVar(name,buffer,size,flags)(d1/d2/d3/d4) - Returns the value of a local or global variable (V36)

Inhibit(name,onoff)(d1/d2) - Inhibits access to a filesystem (V36)

InternalLoadSeg(fh,table,funcarray,stack)(d0/a0/a1/a2) - Low-level load routine (V36)

InternalUnLoadSeg(seglist,freefunc)(d1/a1) - Unloads a seglist loaded with InternalLoadSeg() (V36)

IsFileSystem(name)(d1) - Returns whether a Dos handler is a filesystem (V36)

LockDosList(flags)(d1) - Locks the specified Dos Lists for use (V36)

LockRecord(fh,offset,length,mode,timeout)(d1/d2/d3/d4/d5) - Locks a portion of a file (V36)

LockRecords(recArray,timeout)(d1/d2) - Lock a series of records (V36)

MakeDosEntry(name,type)(d1/d2) - Creates a DosList structure (V36)

MakeLink(name,dest,soft)(d1/d2/d3) - Creates a filesystem link (V36)

MatchEnd(anchor)(d1) - Free storage allocated for MatchFirst()/MatchNext() (V36)

MatchFirst(pat,anchor)(d1/d2) - Finds file that matches pattern (V36)

MatchNext(anchor)(d1) - Finds the next file or directory that matches pattern (V36)

MatchPattern(pat,str)(d1/d2) - Checks for a pattern match with a string (V36)

MatchPatternNoCase(pat,str)(d1/d2) - Checks for a pattern match with a string (V37)

MaxCli()() - Returns the highest CLI process number possibly in use (V36)

NameFromFH(fh,buffer,len)(d1/d2/d3) - Get the name of an open filehandle (V36)

NameFromLock(lock,buffer,len)(d1/d2/d3) - Returns the name of a locked object (V36)

NewLoadSeg(file,tags)(d1/d2) - Improved version of LoadSeg for stack sizes (V36)

NextDosEntry(dlist,flags)(d1/d2) - Get the next Dos List entry (V36)

OpenFromLock(lock)(d1) - Opens a file you have a lock on (V36)

ParentOfFH(fh)(d1) - Returns a lock on the parent directory of a file (V36)

ParsePattern(pat,buf,buflen)(d1/d2/d3) - Create a tokenized string for MatchPattern() (V36)

ParsePatternNoCase(pat,buf,buflen)(d1/d2/d3) - Create a tokenized string for MatchPattern() (V36)

PathPart(path)(d1) - Returns a pointer to the end of the next-to-last (V36)

PrintFault(code,header)(d1/d2) - Returns the text associated with a DOS error code (V36)

PutStr(str)(d1) - Writes a string the the default output (buffered) (V36)

ReadArgs(template,array,args)(d1/d2/d3) - Parse the command line input (V36)

ReadItem(name,maxchars,cSource)(d1/d2/d3)
- Reads a single argument/name from command line (V36)

ReadLink(port,lock,path,buffer,size)(d1/d2/d3/d4/d5)
- Reads the path for a soft filesystem link (V36)

Relabel(drive,newname)(d1/d2)
- Change the volume name of a volume (V36)

RemAssignList(name,lock)(d1/d2)
- Remove an entry from a multi-dir assign (V36)

RemDosEntry(dlist)(d1)
- Removes a Dos List entry from it's list (V36)

RemSegment(seg)(d1)
- Removes a resident segment from the resident list (V36)

ReplyPkt(dp,res1,res2)(d1/d2/d3)
- Replies a packet to the person who sent it to you (V36)

RunCommand(seg,stack,paramptr,paramlen)(d1/d2/d3/d4)
- Runs a program using the current process (V36)

SameDevice(lock1,lock2)(d1/d2)
- Are two locks are on partitions of the device? (V37)

SameLock(lock1,lock2)(d1/d2)
- Returns whether two locks are on the same object (V36)

SelectInput(fh)(d1)
- Select a filehandle as the default input channel (V36)

SelectOutput(fh)(d1)
- Select a filehandle as the default input channel (V36)

SendPkt(dp,port,replyport)(d1/d2/d3)
- Sends a packet to a handler (V36)

SetArgStr(string)(d1)
- Sets the arguments for the current process (V36)

SetConsoleTask(task)(d1)
- Sets the default console for the process (V36)

SetCurrentDirName(name)(d1)
- Sets the directory name for the process (V36)

SetFileDate(name,date)(d1/d2)
- Sets the modification date for a file or dir (V36)

SetFileSize(fh,pos,mode)(d1/d2/d3)
- Sets the size of a file (V36)

SetFileSysTask(task)(d1)
- Sets the default filesystem for the process (V36)

SetIoErr(result)(d1)
- Sets the value returned by IoErr() (V36)

SetMode(fh,mode)(d1/d2)
- Set the current behavior of a handler (V36)

SetProgramDir(lock)(d1)
- Sets the directory returned by GetProgramDir (V36)

SetProgramName(name)(d1)
- Sets the name of the program being run (V36)

SetPrompt(name)(d1)
- Sets the CLI/shell prompt for the current process (V36)

SetVar(name,buffer,size,flags)(d1/d2/d3/d4)
- Sets a local or environment variable (V36)

SetVBuf(fh,buff,type,size)(d1/d2/d3/d4)
- Set buffering modes and size (V36)

SplitName(name,separator,buf,oldpos,size)(d1/d2/d3/d4/d5)
- Splits out a component of a pathname into a buffer (V36)

StartNotify(notify)(d1)
- Starts notification on a file or directory (V36)

StrToDate(datetime)(d1)
- Converts a string to a DateStamp (V36)

StrToLong(string,value)(d1/d2)
- String to long value (decimal) (V36)

SystemTagList(command,tags)(d1/d2)
- Have a shell execute a command line (V36)

UnGetC(fh,character)(d1/d2)
- Makes a char available for reading again. (buffered) (V36)

UnLockDosList(flags)(d1)
- Unlocks the Dos List (V36)

UnLockRecord(fh,offset,length)(d1/d2/d3)
- Unlock a record (V36)

UnLockRecords(recArray)(d1)
- Unlock a list of records (V36)

VFPrintf(fh,format,argv)(d1/d2/d3)
- Format and print a string to a file (buffered) (V36)

VFWritef(fh,format,argv)(d1/d2/d3)
- Write a BCPL formatted string to a file (buffered) (V36)

VPrintf(format,argv)(d1/d2)
- Format and print string (buffered) (V36)

WaitPkt()
- Waits for a packet to arrive at your pr_MsgPort (V36)

WriteChars(buf,buflen)(d1/d2)
- Writes bytes to the the default output (buffered) (V36)

exec.library (basename: _SysBase)

AllocVec(byteSize,requirements)(d0/d1)
- Allocate memory and keep track of the size (V36)

CacheClearE(address,length,caches)(a0,d0/d1)
- Cache clearing with extended control (V37)

CacheClearU()
- User callable simple cache clearing (V37)

CacheControl(cacheBits,cacheMask)(d0/d1)
- Instruction & data cache control

CachePostDMA(address,length,flags)(a0/a1,d1)
- Take actions after to hardware DMA (V37)

CachePreDMA(address,length,flags)(a0/a1,d1)
- Take actions prior to hardware DMA (V37)

ColdReboot()
- Reboot the Amiga (V36)

CreateIORequest(port,size)(a0,d0)
- Create an IORequest structure (V36)

CreateMsgPort()
- Allocate and initialize a new message port (V36)

DeleteIORequest(iorequest)(a0)
- Free a request made by CreateIORequest() (V36)

DeleteMsgPort(port)(a0)
- Free a message port created by CreateMsgPort (V36)

FreeVec(memoryBlock)(a1)
- Return AllocVec() memory to the system (V36)

ObtainSemaphoreShared(sigSem)(a0)
- Gain shared access to a semaphore (V36)

StackSwap(newSize,newSP,newStack)(d0/d1/a0)
- Exec supported method of replacing a task's stack.

expansion.library (basename: _ExpansionBase)

AddBootNode(bootPri,flags,deviceNode,configDev)(d0/d1/a0/a1)
- Add a BOOTNODE to the system (V36)

gadtools.library (basename: _GadToolsBase) V36

CreateContext(glistptr)(a0)
- Create a place for GadTools context data. (V36)

CreateGadgetA(kind,gad,ng,taglist)(d0/a0/a1/a2)
- Allocate and initialize a gadtools gadget. (V36)

CreateMenusA(newmenu,taglist)(a0/a1)
- Allocate and fill out a menu structure. (V36)

DrawBevelBoxA(rport,left,top,width,height,taglist)(a0,d0/d1/d2/d3/a1)
- Draws a bevelled box. (V36)

FreeGadgets(gad)(a0)
- Free a linked list of gadgets. (V36)

FreeMenus(menu)(a0)
- Frees memory allocated by CreateMenusA(). (V36)

FreeVisualInfo(vi)(a0) - Return any resources taken by GetVisualInfo. (V36)

GetVisualInfoA(screen,taglist)(a0/a1) - Get information GadTools needs for visuals. (V36)

GT_BeginRefresh(win)(a0) - Begin refreshing friendly to GadTools. (V36)

GT_EndRefresh(win,complete)(a0,d0) - End refreshing friendly to GadTools. (V36)

GT_FilterIMsg(msg)(a1) - Filter an IntuiMessage through GadTools. (V36)

GT_GetIMsg(iport)(a0) - Get an IntuiMessage, with GadTools processing. (V36)

GT_PostFilterIMsg(msg)(a1) - Return the unfiltered message after GT_RefreshWindow(win,req)(a0/a1) - Refresh all the GadTools gadgets. (V36)

GT_ReplyIMsg(msg)(a1) - Reply a message obtained with GT_GetIMsg(). (V36)

GT_SetGadgetAttrs(gad,win,req,taglist)(a0/a1/a2/a3) - Change the attributes of a GadTools gadget. (V36)

LayoutMenuItemsA(firstitem,vi,taglist)(a0/a1/a2) - Position all the menu items. (V36)

LayoutMenusA(firstmenu,vi,taglist)(a0/a1/a2) - Position all the menus and menu items. (V36)

graphics.library (basename: _GfxBase)

BitMapScale(bitScaleArgs)(a0) - Perform raster scaling on a bit map. (V36)

CloseMonitor(monitorSpec)(a0) - Close a MonitorSpec (V36)

EraseRect(rp,xMin,yMin,xMax,yMax)(a1,d0/d1/d2/d3) - Fill a defined rectangular area using the current BackFill hook. (V36)

ExtendFont(font,fontTags)(a0/a1) - Ensure tf_Extension has been built for a font (V36)

FindDisplayInfo(displayID)(d0) - Search for a record identified by a specific key (V36)

FontExtent(font,fontExtent)(a0/a1) - Get the font attributes of the current font (V36)

GetDisplayInfoData(handle,buf,size,tagID,displayID)(a0/a1,d0/d1/d2) - Query DisplayInfo Record parameters (V36)

GetVPMODEID(vp)(a0) - Get the 32 bit DisplayID from a ViewPort. (V36)

GfxAssociate(associateNode,gfxNodePtr)(a0/a1) - Associate a graphics extended node with a given pointer

GfxFree(gfxNodePtr)(a0) - Free a graphics extended data structure (V36)

GfxLookUp(associateNode)(a0) - Find a graphics extended node associated with a given pointer (V36)

GfxNew(gfxNodeType)(d0) - Allocate a graphics extended data structure (V36)

ModeNotAvailable(modeID)(d0) - Check to see if a DisplayID isn't available. (V36)

NextDisplayInfo(displayID)(d0) - Iterate current displayinfo identifiers (V36)

OpenMonitor(monitorName,displayID)(a1,d0) - Open a named MonitorSpec (V36)

ReadPixelArray8(rp,xstart,ystart,xstop,ystop,array,tempRP)(a0,d0/d1/d2/d3/a2,a1) - Read the pen number value of a rectangular array

ReadPixelLine8(rp,xstart,ystart,width,array,tempRP)(a0,d0/d1/d2/a2,a1) - Read the pen number value of a horizontal line

ScalerDiv(factor,numerator,denominator)(d0/d1/d2) - Get the scaling result that BitMapScale would. (V36)

StripFont(font)(a0) - Remove the tf_Extension from a font (V36)

TextExtent(rp,string,count,textExtent)(a1,a0,d0/a2) - Determine raster extent of text data. (V36)

TextFit(rp,string,strLen,textExtent,constrainingExtent, strDirection, constrainingBitWidth, constrainingBitHeight)(a1,a0,d0/a2/a3,d1/d2/d3) - Count characters that will fit in a given extent (V36)

VideoControl(colorMap,tagarray)(a0/a1) - Modify the operation of a ViewPort's ColorMap (V36)

WeighTAMatch(reqTextAttr,targetTextAttr,targetTags)(a0/a1/a2) - Get a measure of how well two fonts match. (V36)

WritePixelArray8(rp,xstart,ystart,xstop,ystop,array,tempRP)(a0,d0/d1/d2/d3/a2,a1) - Write the pen number value of a rectangular array

WritePixelLine8(rp,xstart,ystart,width,array,tempRP)(a0,d0/d1/d2/a2,a1) - Write the pen number value of a horizontal line

icon.library (basename: _IconBase)

DeleteDiskObject(name)(a0) - Delete a Workbench disk object from disk.

GetDefDiskObject(type)(d0) - Read default wb disk object from disk. (V36)

GetDiskObjectNew(name)(a0) - Read in a Workbench disk object from disk.

PutDefDiskObject(diskObject)(a0) - Write disk object as the default for its type. (V36)

iffparse.library (basename: _IFFParseBase) V36

AllocIFF()() - Create a new IFFHandle structure.

AllocLocalItem(type,id,ident,dataSize)(d0/d1/d2/d3) - Create a local context item structure.

CloseClipboard(clipboard)(a0) - Close and free an open ClipboardHandle.

CloseIFF(iff)(a0) - Close an IFF context.

CollectionChunk(iff,type,id)(a0,d0/d1) - Declare a chunk type for collection.

CollectionChunks(iff,propArray,nProps)(a0/a1,d0) - Declare many collection chunks at once.

CurrentChunk(iff)(a0) - Get context node for current chunk.

EntryHandler(iff,type,id,position,handler,object)(a0,d0/d1/d2/a1/a2) - Add an entry handler to the IFFHandle context.

ExitHandler(iff,type,id,position,handler,object)(a0,d0/d1/d2/a1/a2) - Add an exit handler to the IFFHandle context.

FindCollection(iff,type,id)(a0,d0/d1) - Get a pointer to the current list of collection

FindLocalItem(iff,type,id,ident)(a0,d0/d1/d2) - Return a local context item from the context stack.

FindProp(iff,type,id)(a0,d0/d1) - Search for a stored property chunk.

FindPropContext(iff)(a0) - Get the property context for the current state.

FreeIFF(iff)(a0) - Deallocate an IFFHandle struct.
FreeLocalItem(localItem)(a0) - Deallocate a local context item structure.
GoodID(id)(d0) - Test if an identifier follows the IFF 85 specification.
GoodType(type)(d0) - Test if a type follows the IFF 85 specification.
IDtoStr(id,buf)(d0/a0) - Convert a longword identifier to a null-terminated string.
InitIFF(iff,flags,streamHook)(a0,d0/a1) - Initialize an IFFHandle struct as a user stream.
InitIFFasClip(iff)(a0) - Initialize an IFFHandle as a clipboard stream.
InitIFFasDOS(iff)(a0) - Initialize an IFFHandle as a DOS stream.
LocalItemData(localItem)(a0) - Get pointer to user data for local context item.
OpenClipboard(unitNum)(d0) - Create a handle on a clipboard unit.
OpenIFF(iff,rwMode)(a0,d0) - Prepare an IFFHandle to read or write a new IFF stream.
ParentChunk(contextNode)(a0) - Get the nesting context node for the given chunk.
ParseIFF(iff,control)(a0,d0) - Parse an IFF file from an IFFHandle struct stream.
PopChunk(iff)(a0) - Pop top context node off context stack.
PropChunk(iff,type,id)(a0,d0/d1) - Specify a property chunk to store.
PropChunks(iff,propArray,nProps)(a0/a1,d0) - Declare many property chunks at once.
PushChunk(iff,type,id,size)(a0,d0/d1/d2) - Push a new context node on the context stack.
ReadChunkBytes(iff,buf,size)(a0/a1,d0) - Read bytes from the current chunk into a buffer.
ReadChunkRecords(iff,buf,bytesPerRecord,nRecords)(a0/a1,d0/d1) - Read record elements from the current chunk into
SetLocalItemPurge(localItem,purgeHook)(a0/a1) - Set purge vector for a local context item.
StopChunk(iff,type,id)(a0,d0/d1) - Declare a chunk which should cause ParseIFF to return.
StopChunks(iff,propArray,nProps)(a0/a1,d0) - Declare many stop chunks at once.
StopOnExit(iff,type,id)(a0,d0/d1) - Declare a stop condition for exiting a chunk.
StoreItemInContext(iff,localItem,contextNode)(a0/a1/a2) - Store local context item in given context node.
StoreLocalItem(iff,localItem,position)(a0/a1,d0) - Insert a local context item into the context stack.
WriteChunkBytes(iff,buf,size)(a0/a1,d0) - Write data from a buffer into the current chunk.
WriteChunkRecords(iff,buf,bytesPerRecord,nRecords)(a0/a1,d0/d1) - Write records from a buffer to the current

input.device (basename: InputBase)

PeekQualifier()() - Get the input device's current qualifiers (V36)

intuition.library (basename: IntuitionBase)

AddClass(class)(a0) - Make a public class available (V36)
BuildEasyRequestArgs(window,easyStruct,idcmp,args)(a0/a1,d0/a3) - Simple creation of system request. (V36)
ChangeWindowBox(window,left,top,width,height)(a0,d0/d1/d2/d3) - Change window position and dimensions. (V36)
DisposeObject(object)(a0) - Deletes a 'boopsi' object. (V36)
DrawImageState(rp,image,leftOffset,topOffset,state,drawInfo)(a0/a1,d0/d1/d2/a2) - Draw an (extended) Intuition Image with EasyRequestArgs(window,easyStruct,idcmpPtr,args)(a0/a1/a2/a3) - Easy alternative to AutoRequest(). (V36)
EraseImage(rp,image,leftOffset,topOffset)(a0/a1,d0/d1) - Erases an Image. (V36)
FreeClass(classPtr)(a0) - Frees a boopsi class created by MakeClass(). (V36)
FreeScreenDrawInfo(screen,drawInfo)(a0/a1) - Finish using a DrawInfo structure. (V36)
GadgetMouse(gadget,gInfo,mousePoint)(a0/a1/a2) - Calculate gadget-relative mouse position. (V36)
GetAttr(attrID,object,storagePtr)(d0/a0/a1) - Inquire the value of some attribute of an object. (V36)
GetDefaultPubScreen(nameBuffer)(a0) - Get name of default public screen. (V36)
GetScreenDrawInfo(screen)(a0) - Get pointer to rendering information. (V36)
LockPubScreen(name)(a0) - Prevent a public screen from closing. (V36)
LockPubScreenList()() - Prevent changes to the system list. (V36)
MakeClass(classID,superClassID,superClassPtr,instanceSize,flags)(a0/a1/a2,d0/d1) - Create and initialize a boopsi class. (V36)
MoveWindowInFrontOf(window,behindWindow)(a0/a1) - Arrange the relative depth of a window. (V36)
NewObjectA(class,classID>tagList)(a0/a1/a2) - Create an object from a class. (V36)
NextObject(objectPtrPtr)(a0) - Iterate through the object on an Exec list. (V36)
NextPubScreen(screen,namebuf)(a0/a1) - Identify next public screen in the cycle. (V36)
ObtainGIRPort(gInfo)(a0) - Set up a RastPort for a custom gadget. (V36)
OpenScreenTagList(newScreen>tagList)(a0/a1) - Also stack-based amiga.lib stub OpenScreenTags(). OpenScreen() with TagItem extension array. (V36)
OpenWindowTagList(newWindow>tagList)(a0/a1) - Also stack-based amiga.lib stub OpenWindowTags(). OpenWindow() with TagItem extension. (V36)
PointInImage(point,image)(d0/a0) - Tests whether an image "contains" a point. (V36)
PubScreenStatus(screen,statusFlags)(a0,d0) - Change status flags for a public screen. (V36)
QueryOverscan(displayID,rect,oScanType)(a0/a1,d0) - Inquire about a standard overscan region. (V36)
ReleaseGIRPort(rp)(a0) - Release a custom gadget RastPort. (V36)
RemoveClass(classPtr)(a0) - Make a public boopsi class unavailable. (V36)

ResetMenuStrip(window,menu)(a0/a1) - Re-attach a menu strip to a window. (V36)

SetAttrA(object,tagList)(a0/a1) - Specify attribute values for an object. (V36)

SetDefaultPubScreen(name)(a0) - Choose a new default public screen. (V36)

SetEditHook(hook)(a0) - Set global processing for string gadgets. (V36)

SetGadgetAttrA(gadget,window,requester,tagList)(a0/a1/a2/a3) - Specify attribute values for a boopsi gadget. (V36)

SetMouseQueue(window,queueLength)(a0,d0) - Change limit on pending mouse messages. (V36)

SetPubScreenModes(modes)(d0) - Establish global public screen behavior. (V36)

SysReqHandler(window,idcmpPtr,waitInput)(a0/a1,d0) - Handle system requester input. (V36)

UnlockPubScreen(name,screen)(a0/a1) - Release lock on a public screen. (V36)

UnlockPubScreenList()() - Release public screen list semaphore. (V36)

ZipWindow(window)(a0) - Change window to "alternate" position and

keymap.library (basename: _KeymapBase)

AskKeyMapDefault()() - Ask for a pointer to the current default keyMap. (a0,d0/a1,d1/a2)

MapANSI(string,count,buffer,length,keyMap)(a0,d0/a1,d1/a2) - Encode an ANSI string into keycodes. (V36)

MapRawKey(event,buffer,length,keyMap)(a0/a1,d1/a2) - Decode single raw key input event to an ANSI

SetKeyMapDefault(keyMap)(a0) - Set the current default keymap. (V36)

layers.library (basename: _LayersBase)

CreateBehindHookLayer(li,bm,x0,y0,x1,y1,flags,hook,bm2)(a0/a1,d0/d1/d2/d3/d4/a3,a2) - Create a new layer behind all existing layers,

CreateUpfrontHookLayer(li,bm,x0,y0,x1,y1,flags,hook,bm2)(a0/a1,d0/d1/d2/d3/d4/a3,a2) - Create a new layer on top of existing layers,

InstallLayerHook(layer,hook)(a0/a1) - Safely install a new Layer->BackFill hook.

MoveSizeLayer(layer,dx,dy,dw,dh)(a0,d0/d1/d2/d3) - Position/Size layer

**mathieeesingbas.library
(basename: _MathIeeeSingBasBase) V36**

IEEESPAbs(parm)(d0) - Compute absolute value of IEEE single precision argument

IEEESPAdd(leftParm,rightParm)(d0/d1) - Add one single precision IEEE number to another

IEEESPCeil(parm)(d0) - Compute Ceil function of IEEE single precision number

IEEESPCmp(leftParm,rightParm)(d0/d1) - Compare two single precision floating point numbers

IEEESPDIV(dividend,divisor)(d0/d1) - Divide one single precision IEEE by another

IEEESPFix(parm)(d0) - Convert IEEE single float to integer

IEEESPFloor(parm)(d0) - Compute Floor function of IEEE single precision number

IEEESPFlt(integer)(d0) - Convert integer to IEEE single precision number

IEEESPMul(leftParm,rightParm)(d0/d1) - Multiply one double precision IEEE number by another

IEEESPNeg(parm)(d0) - Compute negative value of IEEE single precision number

IEEESPSub(leftParm,rightParm)(d0/d1) - Subtract one single precision IEEE number from another

IEEESPTst(parm)(d0) - Compare IEEE single precision value to 0.0

**mathieeesingtrans.library
(basename: _MathIeeeSingTransBase) V36**

IEEESPAcos(parm)(d0) - Compute the arc cosine of a number

IEEESPAsin(parm)(d0) - Compute the arcsine of a number

IEEESPAtan(parm)(d0) - Compute the arc tangent of number

IEEESPCos(parm)(d0) - Compute the cosine of a floating point number

IEEESPCosh(parm)(d0) - Compute the hyperbolic cosine of a floating point number

IEEESPExp(parm)(d0) - Compute the exponential of e

IEEESPFieee(parm)(d0) - Convert IEEE single to IEEE single

IEEESPLog(parm)(d0) - Compute the natural logarithm of a floating point number

IEEESPLog10(parm)(d0) - Compute logarithm base 10 of a number

IEEESPPow(exp,arg)(d1,d0) - Raise a number to another number power

IEEESPSin(parm)(d0) - Compute the sine of a floating point number

IEEESPSincos(cosptr,parm)(a0,d0) - Compute the arc tangent of a floating point number

IEEESPSinh(parm)(d0) - Compute the hyperbolic sine of a floating point number

IEEESPSqrt(parm)(d0) - Compute the square root of a number

IEEESPTan(parm)(d0) - Compute the tangent of a floating point number

IEEESPTanh(parm)(d0) - Compute the hyperbolic tangent of a floating point number

IEEESPTieee(parm)(d0) - Convert IEEE single to IEEE single

ramdrive.device (basename: _RamdriveDevice)

KillRAD(unit)(d0) - Kill ramdrive.device unit

KillRAD()() - Kill ramdrive.device unit 0

rexxsyslib.library (basename: _RexxSysBase) V36

ClearRexxMsg(msgptr,count)(a0,d0) - Releases and clears the argument array in a RexxMsg

CreateArgstring(string,length)(a0,d0) - Create an argument string structure

CreateRexxMsg(port,extension,host)(a0/a1,d0) - Create an ARexx message structure

DeleteArgstring(argstring)(a0) - Releases an Argstring created by CreateArgstring()

DeleteRexxMsg(packet)(a0) - Releases a RexxMsg structure created by CreateRexxMsg()

FillRexxMsg(msgptr,count,mask)(a0,d0/d1)
 - Fill the argument strings as needed
 IsRexxMsg(msgptr)(a0)
 - Function to determine if a message came from ARexx
 LengthArgstring(argstring)(a0)
 - Returns the length value stored in the argstring
 LockRexxBASE(resource)(d0)
 - Obtain a semaphore lock on the REXXBase structure
 UnlockRexxBASE(resource)(d0)
 - Release a semaphore lock on the REXXBase structure

Timer.Device (basename: _TimerBase)

GetSysTime(dest)(a0)
 - Get the system time. (V36)
 ReadEClock(dest)(a0)
 - Get the current value of the E-Clock. (V36)

trackdisk.device (device commands)

TD_GETGEOMETRY
 - Gets the disk geometry table.
 TD_EJECT
 - For those drives that support it.

utility.library (basename: _UtilityBase) V36

AllocateTagItems(numItems)(d0)
 - Allocate a TagItem array (or chain). (V36)
 Amiga2Date(amigaTime,date)(d0/a0)
 - Calculate the date from a timestamp. (V36)
 CallHookPkt(hook,object,paramPacket)(a0/a2,a1)
 - Invoke a Hook function callback. (V36)
 CheckDate(date)(a0)
 - Checks ClockData struct for legal date. (V36)
 CloneTagItems(tagList)(a0)
 - Copies a TagItem list. (V36)
 Date2Amiga(date)(a0)
 - Calculate seconds from 01-Jan-1978. (V36)
 FilterTagChanges(newTagList,oldTagList,apply)(a0/a1,d0)
 - Eliminate TagItems which specify no change. (V36)
 FilterTagItems(tagList,filterArray,logic)(a0/a1,d0)
 - Remove selected items from a TagItem list. (V36)
 FindTagItem(tagVal,tagList)(d0/a0)
 - Scans TagItem list for a Tag. (V36)
 FreeTagItems(tagList)(a0)
 - Frees allocated TagItem lists. (V36)
 GetTagData(tagVal,defaultVal,tagList)(d0/d1/a0)
 - Obtain data corresponding to Tag. (V36)
 MapTags(tagList,mapList,includeMiss)(a0/a1,d0)
 - Convert ti_Tag values in a list via map pairing. (V36)
 NextTagItem(tagListPtr)(a0)
 - Iterate TagItem lists. (V36)
 PackBoolTags(initialFlags,tagList,boolMap)(d0/a0/a1)
 - Builds a "Flag" word from a TagList. (V36)
 RefreshTagItemClones(cloneList,origList)(a0/a1)
 - Rejuvenates a clone from the original. (V36)
 SDivMod32(dividend,divisor)(d0/d1)
 - Signed 32 by 32 bit division and modulus. (V36)
 SMult32(factor1,factor2)(d0/d1)
 - Signed 32 by 32 bit multiply with 32 bit result. (V36)
 Stricmp(string1,string2)(a0/a1)
 - Case-insensitive string compare. (V37)

Strnicmp(string1,string2,length)(a0/a1,d0)
 - Case-insensitive string compare, length-limited. (V37)
 TagInArray(tagVal,tagArray)(d0/a0)
 - Check if a Tag value appears in a Tag array. (V36)
 ToLower(character)(d0)
 - Convert a character to lowercase. (V37)
 ToUpper(character)(d0)
 - Convert a character to uppercase. (V37)
 UDivMod32(dividend,divisor)(d0/d1)
 - Unsigned 32 by 32 bit division and modulus. (V36)
 UMult32(factor1,factor2)(d0/d1)
 - Unsigned 32 by 32 bit multiply with 32 bit result. (V36)

workbench.library (basename: _WorkbenchBase)

AddAppIconA(id,userdata,text,msgport,lock,diskobj,taglist)(d0/d1/a0/a1/a2/a3/a4)
 - Also stack-based amiga.lib stub
 AddAppIcon(). Add an icon to workbench's list of appicons. (V36)
 AddAppMenuItemA(id,userdata,text,msgport,taglist)(d0/d1/a0/a1/a2)
 - Also stack-based amiga.lib stub
 AddAppMenuItem(). Add a menuitem to workbench's list of appmenuitems (V36)
 AddAppWindowA(id,userdata>window,msgport,taglist)(d0/d1/a0/a1/a2)
 - Also stack-based amiga.lib stub
 AddAppWindow(). Add a window to workbench's list of appwindows. (V36)
 RemoveAppIcon(appIcon)(a0)
 - Remove an icon from workbench's list (V36)
 RemoveAppMenuItem(appMenuItem)(a0)
 - Remove a menuitem from workbench's list (V36)
 RemoveAppWindow(appWindow)(a0)
 - Remove a window from workbench's list (V36)

