



VTSocket (Windows Sockets) Control

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

The VT SOCKET control provides network communications for your application by allowing transmission and reception of TCP/IP data via the Windows Sockets (winsock) standard.

Object Type

WinSock

Remarks

The windows socket control provides the TCP/IP functionality for communicating as either a server process or a client process or both. Event driven and polled communications are supported. BSD style streaming sockets are fully supported; out of band data, broadcasting, and UDP type sockets are not supported.

Client communications allow applications written in Visual Basic or Visual C++ to communicate with server processes. A client process may be established with VTSocket using as few as 6 lines of procedural code (even less if host names and ports are assigned at design time).

For example:

```
Sub Form_Load ( )
    Client1.IPName = "remote.host"
    Client1.Port = 1234
    Client1.Open = True
    Client1.Send = "This is a test message"
    answer$ = Client1.Recv
    Client1.Open = False
```

A receive event may also be defined to accept input from remote hosts on an event-driven basis.

Server communications allow applications written in Visual Basic or Visual C++ to communicate with several client processes at the same time. A server process relies on event procedures for notification when a client process connects or disconnects. A control array is used to differentiate multiple client connections from one another.

For example:

```
Sub Form_Load ( )
    Server1(0).Port = 1234
    Server1(0).Open = True
Sub Server1_Connect (Index As Integer, ID As Integer)
    Load Server1(ID)
Sub Server1_Recv(Index As Integer)
    indata$ = Server1(Index).Recv
Sub Server1_Disconnect(Index As Integer)
    Unload Server1(Index)
```

Each client control corresponds to one connection to a remote host based on the host name and port number. If you need to access more than one host at the same time multiple client controls should be used. Multiple client controls may exist as separate controls, or as elements of a single control array.

Each server control corresponds to one port number at which multiple connections may be accepted. A server control **MUST** be defined as element zero of a control array. Connections received by this

control are then serviced by establishing a new (non-zero) control array element for each connection. The Visual Basic *Load* and *Unload* commands are used for this purpose.

Distribution Note When you create and distribute applications that use the VTSocket control, you should install the file VT SOCKET.VBX in the customer's Microsoft Window's \SYSTEM sub directory. Applications developed using the VTSocket control will cease to properly function after 30 days unless a VT PROD.LIC module is present on the development system. A VT PROD.LIC module may be obtained by licensing the VT Socket control from Visual Technology Products.



About the VTSocket Control

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

The VT Socket control was developed by Visual Technology Products. For additional information, they may be contacted at:

Visual Technology Products

4317 Olley Lane

Fairfax, VA 22032

Fax: (703) 978-7389

Internet mail: vtprod@access.digex.com



VTSocket Control Properties

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

| Properties | Description |
|----------------------------------|---|
| Client_or_Server | Sets and returns the operating mode of this connection (design time only access) |
| Description | Returns the description information provided by the winsock.dll in response to a WSStartup() function call. This is usually the vendor name and version number of the windows sockets DLL that is in use. |
| Interval | Sets and returns the timeout interval for linger during close (effective only if Linger is set to true) |
| IPName | Sets and returns the remote host domain name or IP number |
| Linger | Sets and returns an option to wait for data transmission completion during close processing |
| MyIP | Returns your local IP number as an unsigned long integer value. |
| Open | Sets and returns the connection status of this control. This event immediately initiates connection processing when set to True, and immediately terminates an active connection when set to False. |
| Port | Sets and returns the port number for a remote connection |
| Recv | Returns and removes data received from a remote host (read only) |
| RecvBufSize | Sets and returns the size of buffers used during data reception |
| Send | Receives a string of characters to be transmitted to a remote host (write only) |
| SendBufSize | Sets and returns the size of buffers used during data transmission |



VTSocket Control Events

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

| Events | Description |
|-----------------------------------|--|
| <u>Connect</u> | The connect event is invoked in response to a successful open (WinSock.Open = True) for the local host, or when the VTSocket control receives a request for connection from a remote host. |
| <u>Disconnect</u> | The disconnect event is invoked in response to a successful close (WinSock.Open = False) for the local host, or when the VTSocket control detects a disconnect notification from a previously connected remote host. |
| <u>Recv</u> | The receive event is invoked when the VTSocket control detects the availability of data sent by a currently connected remote host. This event is active for both client and server operating modes. |



Client_or_Server Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

Sets and returns the socket communications mode for this control. A setting of Client (0) causes the control to establish active communications with a remote host when connection is requested via the Open property. A setting of Server (1) causes the control to listen for a connection request initiated by a remote host.

Usage

setting % = [form.]Winsock.Client_or_Server

Remarks

Control is read-only at run time. The following table lists the Client_or_Server property settings for the VTSocket control:

| Setting | Description |
|---------|---------------------------------------|
| 0 | (Default) Control is a client socket. |
| 1 | Control is a server socket. |

Data Type

Integer (Enumerated)



Description Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

Returns the description information provided by winsock.dll in response to a WSAStartup() function call. This is usually the vendor name and version number of the windows sockets DLL that is in use.

Usage

description \$ = [form.]Winsock.**Description**

Remarks

Control is read-only at both design-time and run-time.

Data Type

String



Interval

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

Sets and returns the timeout interval for linger during close (effective only if Linger is set to true). Interval is the number of seconds to wait for a graceful close. If the interval property is set to zero and the linger property is true, a hard close will be forced.

Usage

```
[form.]Winsock.Interval = interval %  
interval % = [form.]Winsock.Interval
```

Data Type

Integer



IPName Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

The IPName property sets and returns the name or IP number of a remote host to be contacted when the open property is set true.

Usage

```
[form.]Winsock.IPName = ipname $  
ipname $ = [form.]Winsock.IPName
```

Remarks

IPName may be set and returned for both client and server connections, but is ignored when a server connection is specified.

Data Type

String



Linger Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

When the Client_or_Server property is set to Client (0), this property sets and returns the port number of a remote host to be contacted when open processing is initiated. When the Client_or_Server property is set to Server (1), this property sets and returns the port number at which the control should listen for remote host connection requests.

Usage

```
[form.]Winsock.Linger = { True | False }  
linger % = [form.]Winsock.Linger
```

Remarks

The following table lists the Linger property settings for the VTSocket control:

| Setting | Description |
|---------|-------------|
|---------|-------------|

| | |
|--------------|---|
| False | (Default) Do not wait for data to quiesce during close. |
|--------------|---|

| | |
|-------------|---|
| True | Wait "Interval" seconds for data to quiesce during close. |
|-------------|---|

Data Type

Integer (Boolean)



MyIP Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

The MyIP property returns the local IP address.

Usage

myipnumber % = [form.]Winsock.MyIP

Remarks

The MyIP property is read only, and is available at run-time only. It provides a valid local IP number only while a client or server connection is open (the Open property is set to True).

Data Type

Long



Open Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

When the Client_or_Server property is set to Client (0), this property initiates a connection (or terminates a connection) with the remote host identified by the IPName and Port property settings. When the Client_or_Server property is set to Server (1), this property causes the control to listen (or terminate listening) for connection requests from remote hosts using the port identified by the Port property.

Usage

```
[form.]Winsock.Open = { True | False }  
connection_status % = [form.]Winsock.Open
```

Remarks

The Open property is available at run-time only. The following table lists the Open property settings for the VTSocket control:

| Setting | Description |
|---------|-------------|
|---------|-------------|

| | |
|--------------|--|
| False | Terminate a currently connected TCP/IP socket. |
|--------------|--|

| | |
|-------------|---|
| True | Attempt to connect a currently disconnected TCP/IP socket.. |
|-------------|---|

Data Type

Integer (Boolean)



Port Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

When the Client_or_Server property is set to Client (0), this property sets and returns the port number of a remote host to be contacted when open processing is initiated. When the Client_or_Server property is set to Server (1), this property sets and returns the port number at which the control should listen for remote host connection requests.

Usage

```
[form.]Winsock.Port = port_number %  
port_number % = [form.]Winsock.Port
```

Data Type

Integer



Recv Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

The Recv property receives and removes data from a currently connected remote host. This property may be used to poll for pending data by repeatedly reading the property, or may be used within the Recv event procedure to read pending data.

Usage

```
received_data $ = [form.]Winsock.Recv
```

Remarks

The Recv property is a read-only property, and is available only at run-time.

Data Type

String



RecvBufSize Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

The RecvBufSize property sets and returns the size in bytes of the buffer used by windows sockets to receive inbound data from a remote host.

Usage

```
[form.]Winsock.RecvBufSize = buffer_size %  
buffer_size % = [form.]Winsock.RecvBufSize
```

Data Type

Integer



Send Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

The Send property is used to transmit data to a currently connected remote host.

Usage

```
[form.]Winsock.Send = send_data $
```

Remarks

The Send property is a write-only property, and is available only at run-time.

Data Type

String



SendBufSize Property

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

The SendBufSize property sets and returns the size in bytes of the buffer used by windows sockets to transmit outbound data to a remote host.

Usage

```
[form.]Winsock.SendBufSize = buffer_size %  
buffer_size % = [form.]Winsock.SendBufSize
```

Data Type

Integer



Connect Event

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

Occurs when a remote host attempts to connect to a VT Socket control for which the Client_or_Server property is set to Server, and the Open property is True. Also occurs in response to a successful connection by the local host when the Open property is set True.

Syntax

Sub Winsock_Connect (Index **As Integer**, ID **As Integer**)

Remarks

When the Client_or_Server property is set to Server, the index value for a Connect event should always be zero, indicating that the connection is for the listening control entry in a control array. ID contains an index value to be used in communicating with the newly connected remote host. A new instance of the control should be created to handle communications with the remote host. For example:

```
Sub Winsock_Connect (Index As Integer, ID As Integer)  
    Load Winsock(ID)
```



Disconnect Event

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

Occurs when a remote host terminates a connection to a VT Socket control for which the Client_or_Server property is set to Server, and the Open property is True. Also occurs in response to a successful disconnection by the local host when the Open property is set False.

Syntax

Sub Winsock_Disconnect (Index As Integer)

Remarks

When the Client_or_Server property is set to Server, the Index value for a Disconnect event should always be non-zero, indicating that the disconnect has been received from an instance of the control that was previously created during Connect event processing. The instance of the control that was previously created to handle communications with the remote host should be removed.

For example:

```
Sub Winsock_Disconnect (Index As Integer)
    Unload Winsock(Index)
```



Recv Event

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Description

Occurs when a remote host sends data to a VT Socket control.

Syntax

Sub Winsock_Recv ()

Remarks

The Recv event provides a convenient way for an application to recognize that new data is available from a remote host. The pending data may be immediately fetched using the Recv property, or may be deferred to a later time. However, no further Recv events will be posted until the currently pending data is fetched.

For example:

```
Sub Winsock_Recv ( )  
    recvdata$ = Winsock.Recv
```



Error Codes and Messages

[Properties](#)

[Events](#)

[Error Codes](#)

[About](#)

Remarks

All errors returned by VTSocket are, in fact, errors that originate with the Windows Sockets DLL (winsock.dll). These errors are defined in the following table. Error codes and tags are also defined in the file named VTSOCKET.INC, in a format suitable for inclusion Visual Basic applications. (The error codes are already defined in winsock.h for inclusion in Visual C++ applications.)

| Err | Message | Err | Message | Err | Message |
|-------|----------------|-------|----------------|-------|--------------|
| 10004 | INTR | 10009 | BADF | 10013 | ACCESS |
| 10014 | FAULT | 10022 | INVAL | 10024 | MFILE |
| 10035 | WOULDBLOCK | 10036 | INPROGRESS | 10037 | ALREADY |
| 10038 | NOTSOCK | 10039 | DESTADDRREQ | 10040 | MSGSIZE |
| 10041 | PROTOTYPE | 10042 | NOPROTOOPT | 10043 | PROTONOSPT |
| 10044 | SOCKTNOSPT | 10045 | OPNOTSUPP | 10046 | PFNOSUPPORT |
| 10047 | AFNOSUPPORT | 10048 | ADDRINUSE | 10049 | ADDRNOTAVAIL |
| 10050 | NETDOWN | 10051 | NETUNREACH | 10052 | NETRESET |
| 10053 | CONNABORTED | 10054 | CONNRESET | 10055 | NOBUFS |
| 10056 | ISCONN | 10057 | NOTCONN | 10058 | SHUTDOWN |
| 10059 | TOOMANYREFS | 10060 | TIMEDOUT | 10061 | CONNREFUSED |
| 10062 | LOOP | 10063 | NAMETOOLONG | 10064 | HOSTDOWN |
| 10065 | HOSTUNREACH | 10066 | NOTEMPTY | 10067 | PROCLIM |
| 10068 | USERS | 10069 | DQUOT | 10070 | STALE |
| 10071 | REMOTE | 10091 | SYSNOTREADY | 10092 | VERNOTSPT |
| 10093 | NOTINITIALISED | 11001 | HOST_NOT_FOUND | 11002 | TRY_AGAIN |
| 11003 | NO_RECOVERY | 11004 | NO_DATA | | |

