

AutoCLI V1.84 21st Aug 1990 by Nic Wilson

BUG FIXES & CHANGES SINCE THE VERSION ON MEGADISC 17

THE FOLLOWING BUGS AND CHANGES CAN ONLY BE GUARANTEED ON VERSIONS
1.82 AND HIGHER.

BUGS

1. FUNCTION KEY SCRIPT FILES WOULD OFTEN CAUSE A SYSTEM HANG OR
GURU.

Now Fixed. Caused by priority inheritance problem.

2. IF AutoCLI WAS LAUNCHED IN MIXED CASE, REMOVAL WAS NOT
POSSIBLE.

Now Fixed. Any case mixture is acceptable

3. MOUSE BLANKING (-b) SOMETIMES GAVE A VERTICAL BAR ON THE
SCREEN.

Now Fixed. Now manipulates copper list instead of Sprite DMA.

4. MOUSE BLANKING (-b) SOMETIMES CAUSED CERTAIN PROGRAMS TO HANG.

Now Fixed. DMA problem. Same bug as above.

5. CUSTOM CLI WINDOWS DID NOT WORK IF TIME BLANKING OPTION USED.

Now Fixed. Programming bug.

6. (-w) OPTION SOMETIMES DID NOT WORK.

Now Fixed. Intuition problem, now using Layers instead.

7. SCREEN BLANKING HUNG THE SYSTEM IF DRIVE WAS BEING ACCESSED.

Now Fixed. DMA problem, fixed by manipulating copper lists.

8. ON 68020 OR 68030 AMIGA, FUNCTION KEYS WOULD OFTEN CRASH

Fixed in 1.83. Needed slight delay before changing priority.

9. MOUSE BLANKING IMPROVED FURTHER.

Done in 1.84

CHANGES

Addition of options window that allows, changes to your options
without having to remove and relaunch. See main docs below for
instructions on its use.

KNOWN BUGS OR CONFLICTS

Problems have been encountered with non standard versions of the 'RUN' command. This command is called by dos.library's 'execute' command. If you have problems with the Amiga crashing when a CLI is popped up then make sure the 'run' command is standard. The one I use came from an original 1.3.2 workbench and has a filesize of 2568 bytes. It is also recommended that ARP Library commands are not used, as they are not very compatible and can cause various problems.

SUGGESTIONS

If AutoCLI does not have your favourite function, or you can think of any improvements, then write and tell me. The best suggestions will receive a full version of NoVirus free of charge.

This program has been placed on the Public Domain for your enjoyment. Permission is hereby given to distribute this program in any way you see fit, as long as this doc file accompanies it. Please send any bug reports or ideas (and spare money) to the address at the bottom of this file.

Commercial companies may also distribute the program, as long as the program is free of charge and this file accompanies it.

We at Nic Wilson Software not only write commercial programs, but as you see we write non-commercial too. If you like this program and you use it, then help us by sending a donation to the address below.

PROGRAM SUMMARY

This program was written because of problems with the similar program I have been using called 'popcli'. Popcli crashes if used under WorkBench/KickStart 2.0, and also if used on a PAL Amiga to open a CLI window with a vertical size greater than 200 lines, it will not

open if
your Amiga decides to start in NTSC mode as they sometimes do.
Popcli also
seems to waste CPU time when waiting and doesn't allow you to
remove it
from memory without crashing or a reboot. AutoCLI overcomes all
of the
above problems and has many added features equivalent to other
programs
around, but uses less CPU time. In fact while waiting it uses
0.0% (as seen
in 'Xoper').
AutoCLI was written in 100% Assembler using Devpac Amiga V2.14.

Hand coded assembler is definately the best way to program. The
code is
small and executes very quickly as compared to coding in 'C' or
other
language, as the code generated would be much larger and slower.
This can
be noticed by running a program like 'xoper' that shows a
percentage of CPU
time that each task is using. The only time AutoCLI uses time is
if an
event sends it a signal to do something. A lot of programmers
that do not
use assembler, code the event handler in C:, which is against
good
programming practise, as stated in the Amiga Rom Kernal Reference
Manual,
Libraries and Devices Revised and Updated.

FEATURES

- * Kickstart / Workbench 1.2, 1.3, 2.0 compatible
- * Compatible with A500, A1000, A2000, A2500, A3000

- * Default or custom CLI / Shell windows
- * Default windows open to 1 pixel less than current screen
- * Function key scripts option
- * Options window allows modification while running
- * Active window to front option
- * Screen shuffle option
- * Window shuffle option
- * Screen blanking after time period option
- * Mouse blanking on key press or time option
- * Mouse acceleration option
- * No CPU time wastage
- * 100% machine code
- * Freely distributable

PROGRAM USAGE FOR INSTALLING AutoCLI

AutoCLI [<optional switches>] [<optional seconds>] [<optional command>]

DO NOT USE RUN or RUNBACK as it will return the command line and allow the window it was launched from to close, when an ENDCLI command is given. Yet it still retains the directory it was launched from and does not lose the current path or stack as some programs do. This means that when a CLI is popped up it will default to the directory that was current, when AutoCLI was launched. The path and stack that was set, will still be valid.

The program is mainly designed to be used in your startup-sequence so you will always have a CLI window available very easily. For best results, AutoCLI should reside in your C: directory.

OPTIONAL SWITCHES

The following switches do not have to be given in any particular order, but must all be before the optional seconds and command parameters.

All options default to OFF and must be enabled with a switch.

Any of these options can be modified after launch, by using the Option Window provided. (see OPTIONS WINDOW below)

- f This switch enables function key trapping. When your qualifier (see below) is held down and a function key pressed, the program will execute a script file in the assigned S: directory with a filename of autocli.f1 to autocli.f10. This file must be a normal script (eg. startup-sequence).
- w This switch enables the window to front option. To use this function, select the window you want at the front by clicking

the left mouse inside the window and then hold your
qualifier key (see below) and press the Left ALT key.

-n This switch enables the screen shuffle option. To
use this function, hold down your qualifier key and use the
cursor up or down keys. These keys rotate all screens in
opposite directions to each other.

These This is different to the standard LEFT AMIGA N & M.
most standard keys only swap between the front and rear
screens.

-m This switch enables the window shuffle option. To
use this function, hold down your qualifier key and use the
cursor left or right keys. This will move the front most
window to the back or the back most window to the front
respectively.

at The window shuffle always occurs on the screen that is
windows the front. This allows you to easily move between
keys and screens by using the qualifier and all the cursor

-q This switch enables mouse acceleration, If you find
that it is too fast, slow it down in preferences. The
amount it speeds the mouse up by depends on the speed the mouse
is being moved. As it moves quicker the acceleration
rate increases and as it slows down the acceleration rate
also decreases.

-b This switch enables mouse blanking. When any key is
pressed the mouse pointer will be immediately blanked, or if

no mouse movement is detected within 30 seconds the mouse pointer will be blanked. As soon as the mouse is moved at all the pointer will be returned immediately. This overcomes the annoying habit of the pointer always being in the way while typing.

-s -c -a The default qualifier key is the LEFT AMIGA but this can be changed with a switch. The -s switch changes the qualifier key to the SHIFT key. The -c switch changes it to the CONTROL key, and the -a switch changes it to the ALT key. To use the default key (LEFT AMIGA) then don't use any of these three switches. Note that this qualifier key is also the same for the autocli function as well.

-r The above qualifier is, by default, the key on the LEFT side of the keyboard. To change this to the RIGHT side, use this switch.

? If the switch is a single question mark, then AutoCLI will display a USAGE string on the current CLI window. It will not install or remove itself.

remove This switch should be used on its own. It will signal the current version of AutoCLI to shut down and remove itself. Whenever it attempts this removal, a success or failure message will be displayed on the CLI window.

OPTIONS WINDOW

This function is always available, even if function key scripts (-f)

is turned off. It is accessed by holding the qualifier key and pressing

HELP. A window will open on the front most screen with gadgets set with

your current options.

Click on the gadgets to turn functions on or off. Screen blanking time

can be changed by clicking in the gadget and changing it accordingly.

If you turn screen blanking on, but give no time, then a default time

of 300 seconds will be set.

At the bottom of the window are two gadgets, 'OK' and 'REMOVE'.

The

remove gadget will remove AutoCLI from memory completely. The ok gadget

will set the new options you have made.

OPTIONAL SECONDS

This is an optional time (in seconds) to blank the screen when no user

input is detected. The default is off, so if blanking is not wanted then

do not give a time at all. When the screen has been blanked, it can be

turned on again by touching any key or moving the mouse. Because it only

requires a single rawmouse event, we have found that giving your computer

table a nudge is sufficient to turn the display on again.

OPTIONAL COMMAND

If no optional command is given then AutoCLI will use a default command.

AutoCLI will launch and wait for your qualifier key and ESCAPE to be

pressed. When this event occurs AutoCLI will open a CLI window 1 pixel

less than the size of the WorkBench Screen at the time it is opened. So

if resolution mode is changed AutoCLI will notice the change. If NEWCON:

is available, a Shell window will open instead of a CLI window.

If an optional command is given, AutoCLI will execute that command

in preference to the default CLI/SHELL window when your qualifier key

and ESCAPE is pressed (see EXAMPLES). This allows custom commands or

custom size CLI/Shell windows to be used. Note that if AutoCLI is already

in memory it will display an error message on the current CLI window.

EXAMPLES-----

```
AutoCLI -f -w -n -m -r -s 600 newshell  
newcon:0/10/640/150/MyShell
```

(opens a Shell window with a title of 'MyShell', enables function

keys, selects the RIGHT SHIFT as your qualifier, enables the

window

to front option ,enables the screen shuffle option, enables the window shuffle and will blank the screen after 10 mins of non use).

AutoCLI -f -w YourProg
(runs a file called YourProg. When LEFT AMIGA/ESCAPE is pressed enables function keys and window to front and will disable the screen blanking ie. no time given).

AutoCLI remove
(attempts to remove the currently running version from memory and displays a success or failure message).

REQUIREMENTS

The following commands MUST be available in the current C: directory :-

run	; c directory (called by the DOS Execute function)
newcli	; c directory (called by AutoCLI if NEWCON not available)
newshell	; c directory (called by AutoCLI if NEWCON is available)
shell-seg	; l directory (needed if newcon: is mounted)
AutoCLI	; c directory

The following commands, devices, files are optional :-

cli-startup	; s directory (script executed by Newcli)
shell-startup	; s directory (script executed by NewShell)
NEWCON:	; (must be mounted to enable Shell instead of CLI)
AutoCLI.F1	; s directory (script file for qualifier/F1)
AutoCLI.F2	; s directory (script file for qualifier/F2)
...etc.	

NOTE: 'Amiga' is a Trademark of Commodore Amiga Inc.

Nic Wilson Software
138d South Street
TOOWOOMBA Queensland 4350
Australia
Phone (076) 358539 Home, (076) 358522 Work or Fax

