

 $\sim$  Expand

Introduction

General Information

Programming Information

External Commands

Eunction Reference





- Introduction
   The WOIO package
- General Information
- Distributing External Commands
- WOIO Library Compatibility
- Programming Information
- Entry function main()
- Exit function exit() and Errorlevels
- Stdin, Stdout and Stderr
- External Commands
- Display arg...() function results (ARGS)
- Function Reference
- Categories

- Introduction
   The WOIO package
- General Information
- Programming Information
- External Commands
- Function Reference

Introduction
--------------

- General Information
- Distributing External Commands
- WOIO Library Compatibility
- Programming Information
- External Commands
- Function Reference

- Introduction
- General Information
- Programming Information
- Entry function main()
- Exit function exit() and Errorlevels
- Stdin, Stdout and Stderr
- External Commands
- <u>Function Reference</u>

- Introduction
- General Information
- Programming Information
- External Commands
- Display arg...() function results (ARGS)
- Function Reference

- Introduction
- General Information
- Programming Information
- External Commands
- Function Reference
- Categories

# **Function Reference Categories**

### **Control Functions**

- screen enable/disable buffered screen output
- <u>yield</u> allow other tasks to multitask.

### **Screen Output Functions**

- printf formatted output
- <u>puts</u> display a string
- <u>putchar</u> display a character
- <u>putch</u> display a character (direct video)
- <u>textcolor</u> change foreground colours
- <u>perror</u> display an error message
- <u>errcnt</u> global variable
- clrscr clear the screen
- clear till the end of the line
- gotoxy set the caret screen position
- wherex get the horizontal caret position
- <u>wherey</u> get the vertical caret position
- scroll a number of line up or down
- insline insert a line
- delline delete a line
- scrflush update the screen
- scrwidth get the screen width
- = <u>scrheight</u> get the screen height

<u>atoc</u> delimit a number with comma's

### **Input Functions**

- <u>scanf</u> formatted input
- gets get a string
- getchar get a character
- getch get a character (direct keyboard)

### **Command Line Functions**

- <u>argc</u> get the number of command line arguments
- argv retrieve a command line argument
- □ <u>arg\_c</u> global variable
- arg\_v global variable
- argpath retrieve a command line path
- argabs retrieve an absolute command line path
- argtail retrieve the actual command line tail
- argn get the number of command line switches
- args retrieve all the command line switches

### **Status Bar Functions**

- limit set the status bar target value
- inc update the status bar by a value
- empty clear the status bar percent indicator

### **File Manipulation Functions**

- 🗖 <u>filesize</u> get the size of a file
- 📟 <u>istextfile</u> check for a text file
- filecpy
  filencpy copy a file
- copy part of a file
- concatenate a file
- <u>filecat</u> <u>filencat</u> concatenate part of a file

### **File Name Functions**

- create a file table of all files in a given path 📟 <u>fillfile</u>
- 📟 <u>getfile</u> retrieve a file control block from the file table
- getfilepath retrieve a file path from the file table
- getfilename retrieve a file name from the file table
- padfilename pad a file name suitable for displaying

### **Path Name Functions**

- 📟 <u>fillpath</u> create a path table of all directories
- 📟 <u>fillpathall</u> create a path table of all directories for all drives
- freepaths free the path table
- 📟 <u>getpath</u> retrieve a path from the path table

#### **Unix Functions**

- 🗖 <u>todos</u> convert a Unix command to a DOS command
- 📟 <u>tounix</u> convert a DOS command to a Unix command
- 🗖 <u>isunix</u> determine if Unix mode is on or off

#### **File Description Functions**

- 🗖 getdesc get a file description
- 📟 <u>setdesc</u> set a file description
- deldesc delete a file description

### **Environment Functions**

- getenvironment get a WinOne environment variable
- putenvironment set a WinOne environment variable

## The WOIO package

WOIO is a library that allows programs to interact (ie. preform I/O functions) with the main WinOne window. WOIO is essentially an abstract layer that sits on top of a normal windows program and provides a number of functions, that covers up just what is necessary to write a windows program. In fact a program written using WOIO, will look more like a DOS program then a Windows program. For example, WOIO programs use main() as the entry point, just like DOS programs do, and printf() will write to the main WinOne window (ie. a virtual screen), just like DOS programs write to the screen.

WOIO greatly simplifies the writing of programs intended for execution by WinOne. Those of you familiar with Windows programming would known just how much code is needed to displaying something as simple as "*hello, world*" inside a window. It takes about 2 pages of code to do this properly, registering a class, set-up up an event loop to handle events like WM\_PAINT, creating a font, etc. Using the WOIO library the same can be accomplish with 5 lines of code :-

```
#include "woio.h"
int main(void)
{
    printf("Hello, World\n");
    return 0;
}
```

There are some additional things that need to be set-up correctly before the above program will work, for example, the project file, renaming the .EXE to a .EXC, etc. Apart from these extra things that are needed, some programs will only need to be modified to include this library to compile. However this will NOT generally be the case.

## **Distributing External Commands**

Users of WinOne (either registered or un-registered) may freely use the WOIO Library package to program External Commands and can distribute them in any way, shape or form. The authors of External Commands are solely responsible for the quality of the commands they program and distribute.

## Library Compatibility

External Commands written with the WOIO Library package are all compatible upwards, that is, External Commands will still run with newer and updated versions of WinOne. However, the reverse does not apply. For example, an External Command that is written for a newer version of WinOne will not run on an older version of WinOne.

## The entry function main()

WOIO programs have an entry function main(), which is similar to DOS programs, but with one important difference, main() does not include the argc and argv arguments, but instead these arguments are implemented as functions calls. The arg... family of functions provide a high level of functionality that the standard argc and argv arguments do not and greatly simplifies the processing of command line arguments. It is not uncommon to see programs that devote whole modules purely for handling command line arguments and this is clearly not necessary when using the WOIO library. It may be interesting to note that these functions are similar to that used internally by WinOne itself. There are 10 arg... functions available, which include :-

<u>argc</u>	<u>argn</u>	<u>argpath</u>
<u>argv</u>	args	<u>argabs</u>
argtail		

## The exit function exit() and Errorlevels

The standard library exit() may be used to exit a program at any time during it execution and the value past to it will set the errorlevel after the program exits. However, the following errorlevel values are reserved by WinOne and should not be used :-

- 3 Abnormal termination (ie. ^C pressed).
- 255 Incompatible WOIO library version. (ie. the External Command is meant for a newer version of WinOne).

When a program exits it should return 0 to signal a normal termination and a value greater then 0 (ie. excluding 3 and 255) to signal an error :-

```
#include "woio.h"
int main(void)
{
    printf("Hello, World\n");
    return 0; /* normal termination */
}
```

## **Command ARGS**

Function:

Displays in a tabular form the values returned by all the arg...() functions.

#### Syntax:

### ARGS [anything]

anything Sequence of characters. This may include strings, arguments and switches.

See Also

<u>argc</u>	<u>argn</u>	<u>argpath</u>	<u>arg_c</u>
<u>argv</u>	<u>args</u>	<u>argabs</u>	<u>arg v</u>
<u>argtail</u>			

## **Borland or Turbo C/C++ Compilers for Windows**

The WOIO package is compiled using Borland C/C++ for windows. Therefore, to use the WOIO package you will need to use either the Borland or Turbo C/C++ compilers for Windows 3.0 and above.

## Stdin, Stdout and Stderr

The standard I/O streams stdin, stdout and stderr are not supported by the WOIO library. Instead WOIO provides a number of functions that attempt to simulate these streams. Functions that requires stdin, stdout or stderr to be past as a parameter will NOT work, and should NOT be used. For example, fputc(c, stdout), putc(c, stdout), fgetc(stdin) or getc(stdin) should not be used. When a program uses these functions, the program will still compile and run, but will not produce the expected result. You may very well be wondering what happens when a program uses these functions, well, the output will most likely end up writing over the desktop window. WOIO supports the following functions, which attempt to mimic the standard I/O functions of the same name as closely as is possible :-

<u>printf</u>	<u>textcolor</u>	<u>scrwidth</u>	<u>scanf</u>
<u>puts</u>	<u>clrscr</u>	<u>scrheight</u>	<u>gets</u>
<u>putchar</u>		<u>clreol</u>	<u>getchar</u>
<u>putch</u>		<u>gotoxy</u>	<u>getch</u>
<u>perror</u>		<u>wherex</u>	
		<u>wherey</u>	

# **Control Functions**

## void screen(flag)

int flag /\* BUFFERED or UNBUFFERED value \*/

Enable or disable buffered screen output. When writing to the screen the text will not appear until enough lines have been written to fill one complete screen.

Parameter	Description
flag	When this value is BUFFERED, then the screen will only update
	after each screen full. When this value is UNBUFFERED, then the
	screen is updated to show any lines not yet displayed.

### Returns

There is no return value.

#### Comments

```
When screen() is set to BUFFERED it should be set to UNBUFFERED before the program terminates. When screen() is not used then the screen is updated as it is written to.
```

The values BUFFERED and UNBUFFERED are #defined in the WOIO.H file.

### Example

```
#include "woio.h"
int main(void)
{
    int ret;
    screen(BUFFERED); /* enable buffered output */
    ret = dofunction();
    screen(UNBUFFERED); /* flush any lines not displayed */
    return ret; /* error level */
}
```

## void yield(void)

Allows other tasks that are running to multitask.

### Returns

There is no return value.

### Comments

Since Windows is a co-operative multitasking operating system, yield() should be called when a long period of time elapses without calling any of the WOIO library functions.

### Example

```
#include "woio.h"
int main(void)
{
    printf("press ^C to quit: \n");
    while (1)
        yield(); /* allow other tasks to multitask */
}
```

# **Screen Output Functions**

## int printf(fmt, ...)

 $\tt printf()$  provides formatted output and functions similar to the standard run time library  $\tt printf()$  .

#### Comments

For a full description of printf() consult your standard run time library reference manual.

printf() will only display printable characters.

The following #define values can be past as character arguments to change the colour of the text displayed by printf():-

```
/*
       all external commands should use the following system
       colours instead of the fix colours
 * /
#define COL FILENAME
                                                   (char )144
                                                                               /* system text colours */
#define COL_HIGHFNAME (char )145
#define COL_HIGHFNAME (char )145
#define COL_NUMBER (char )146
#define COL_TEXT (char )147
#define COL_HIGHTEXT (char )148
#define COL_BOLDTEXT (char )149
#define COL_ENVNAME (char )150
#define COL_ENVSTR (char )151
#define COL_ERROR (char )152
#define COL_LHS (char )153
#define COL_HIGHLHS (char )154
#define COL_FILEDATE (char )156
#define COL_FILETIME (char )157
#define COL_FILEATTRIB (char )158
#define COL FILEATTRIB (char )158
#define COL FILEDESC (char )159
#define BLACK (char )128 /* text colours */
#define RED (char )129
#define GREEN (char )130
#define BLUE (char )131
#define YELLOW (char )132
#define MAGENTA (char )133
#define CYAN (char )134
#define WHITE (char )135
#define LIGHTGRAY (char )136
#define LIGHTRED (char )137
#define LIGHTREP (char )138
#define LIGHTGREEN (char )138
#define LIGHTBLUE (char )139
                                                     (char )140
#define BROWN
#define LIGHTMAGENTA (char )140
#define LIGHTCYAN (char )142
#define DARKGRAY
                                                    (char )143
```

#### See Also

<u>puts</u> <u>putch</u> <u>putchar</u> <u>textcolor</u> <u>scanf</u> gets

### Example

Consider the following :-

will display the following :-

Hello, world How are you?

## void puts(s)

char \*s /\* character string \*/

Display a character string along with a CR-LF character combination.

# ParameterDescriptionsAddress of aNULL terminated character string.

### Returns

There is no return value.

### Comments

Function puts() is streamable, that is, when stdout is redirected on the command line to a file, the character string will be written to the file.

Tab characters are padded with space characters.

### See Also

<u>printf</u> <u>putchar</u> <u>putch</u> <u>gets</u>

## void putch(c)

**char** c /\* character \*/

Display a character directly to the screen.

Parameter	Description
с	Character value.

**Returns** There is no return value.

### Comments

Function putch() writes directly to the screen, and as a result is not streamable.

Tab characters are padded with space characters.

#### See Also

<u>printf</u> <u>puts</u> <u>putchar</u> <u>getch</u>

### Example

```
void myerror(char *msg)
{
   textcolor(COL_ERROR); /* display message in COL_ERROR */
   while (*msg) /* display message */
      putch(*msg++);
   putch('\n');
}
```

## void putchar(c)

**char** c /\* character \*/

Display a character.

Parameter	Description
С	Character value.

**Returns** There is no return value.

### Comments

Function <code>putchar()</code> is streamable, that is, when <code>stdout</code> is redirected on the command line to a file, the character will be written to the file.

Tab characters are padded with space characters.

### See Also

<u>printf</u> <u>puts</u> <u>putch</u> <u>getchar</u>

### Example

```
void charmsg(char *msg)
{
    while (*msg) /* display message */
    putchar(*msg++);
    putchar('\n');
}
```

# int errcnt

Global variables that is incremented by one each time  $\underline{\texttt{perror}()}$  is called to display an error message.

## void perror(msg)

char \*msg /\* character string \*/

Display an error message.

Parameter	Description
msg	Address of a NULL terminated character string that contains the
	message to display.

#### Returns

There is no return value.

#### Comments

The message along with two CR-LF character combinations is written to stderr. Stderr is not streamable, that is, when stdout is redirected on the command line to a file, stderr will still write to the screen.

RED is used for the foreground colour.

#### See Also

<u>errcnt</u> <u>printf</u> <u>puts</u> <u>putchar</u>

### void textcolor(col)

char col /\* colour value \*/

Set the current text colour.

Parameter	Description
col	Range value, that specifies the colour to set.

#### Returns

There is no return value.

#### Comments

The following colours are #defined in the WOIO.H header file :-

```
/*
      all external commands should use the following system
      colours instead of the fix colours
 */
#define COL FILENAME (char )144
                                                                       /* system text colours */
#define COL_HIGHFNAME (char )145
#define COL_HIGHFNAME (char )145
#define COL_NUMBER (char )146
#define COL_TEXT (char )147
#define COL_HIGHTEXT (char )148
#define COL_BOLDTEXT (char )149
#define COL_ENVNAME (char )150
#define COL_ENVSTR (char )151
#define COL_ERROR (char )152
#define COL_LHS (char )153
#define COL_HIGHLHS (char )154
#define COL_RHS (char )155
#define COL_FILEDATE (char )156
#define COL_FILETIME (char )157
#define COL_FILEATTEIB (char )158
#define COL FILEATTRIB (char )158
#define COL FILEDESC (char )159
#define BLACK (char )128 /* text colours */
#define RED (char )129
#define GREEN (char )130
#define BLUE (char )131
#define YELLOW (cha
#define YELLOW (char )132
#define MAGENTA (char )133
#define CYAN(char )133#define WHITE(char )135#define LIGHTGRAY(char )136
#define LIGHTRED
                                                (char )137
#define LIGHTGREEN (char )138
#defineLIGHTBLUE(char )139#defineBROWN(char )140#defineLIGHTMAGENTA(char )141#defineLIGHTCYAN(char )142#defineDARKGRAY(char )143
#define DARKGRAY
                                              (char )143
```

There are no blinking or bold characters.

See Also

<u>printf</u>

# void clrscr(void)

Clear the screen.

### Returns

There is no return value

### Comments

When the screen is cleared, the contains of the screen are NOT moved to the scroll back buffer.

# void clreol(void)

Clear till the end of the current line.

### Returns

There is no return value

## void gotoxy(x, y)

int x	/* co-ordinate */
<b>int</b> y	/* co-ordinate */

Position the caret on the screen.

Parameter	Description
х	Co-ordinate on the horizontal x-axis.
У	Co-ordinate on the vertical y-axis.

**Returns** There is no return value

**Comments** The first character on the screen is at co-ordinate 1, 1.

### See Also

wherex wherey

### Example

```
#include "woio.h"
#include <string.h>
/*
  Display the string "Hello, World"
  centred on the screen
*/
int main(void)
{
   char *s;
   s = "Hello, World"; /* string to display */
   clrscr();
   gotoxy((scrwidth() - strlen(s)) / 2, scrheight() / 2);
   printf("%c%s", COL_HIGHTEXT, s);
   gotoxy(0, scrheight());
   return 0; /* error level */
}
```

# int wherex(void)

Determine the horizontal location of the caret.

### Returns

Co-ordinate of the caret on the horizontal x-axis.

### Comments

Co-ordinates start from 1.

#### See Also

<u>wherey</u> gotoxy

# int wherey(void)

Determine the vertical location of the caret.

### Returns

Co-ordinate of the caret on the vertical y-axis.

### Comments

Co-ordinate start from 1.

#### See Also

<u>wherex</u> gotoxy

## void scroll(start, end, num)

int start/\* position of line \*/int end/\* position of line \*/int num/\* number of places to scroll \*/

Scroll a range of line, a specified number of places, up or down on the screen.

#### Returns

There is no return value

#### Comments

The first line on the screen is at position 0.

A positive value for num, scrolls the range of lines downward and a negative value for num, scrolls the range of lines upward.

# void insline(at)

int at /\* position of line \*/

Insert a blank line at the specified position.

## Returns

There is no return value

## Comments

The first line on the screen is at position 0.

# void delline(at)

int at /\* position of line \*/

Delete a line at the specified position.

**Returns** There is no return value

## Comments

The first line on the screen is at position 0.

# void scrflush(void)

Force updating of the screen.

## Returns

There is no return value

# int scrwidth(void)

Determine the screen width in characters.

## Returns

The screen width in characters.

See Also <u>scrheight</u>

# int scrheight(void)

Determine the screen height in characters.

## Returns

The screen height in characters.

See Also <u>scrwidth</u>

## char \*atoc(number)

**char** \*number /\* character string \*/

Delimit a character string containing a number with comma's, every thousand.

Parameter	Description
number	Address of a the character string containing the number to convert.

#### Returns

The address of the original character string number.

## Comments

The character string number must be large enough to hold the comma's inserted into it.

# **Input Functions**

# int scanf(fmt, ...)

 ${\tt scanf}$  () provides formatted input and functions the same as the standard run time library  ${\tt scanf}$  ().

## Comments

For a full description of scanf() consult your standard run time library reference manual.

See Also

<u>gets</u> <u>getch</u> <u>getchar</u> <u>printf</u>

## char \*gets(s)

char \*s /\* character string \*/

Get a character string without the CR-LF character combination.

Parameter	Description
S	Address of a character array to store the string. This array must be at
	least 80 characters in size.

#### Returns

On success, it returns the address of the character array, where the NULL terminated character string is stored. On end of file (ie. EOF) or on error, NULL is returned.

#### Comments

Function gets() is streamable, that is, when stdin is redirected on the command line from a file, the character string will be read from the file and will not be echoed to the screen.

Tab characters are converted to a single space character, unless stdin has been redirected on the command line.

#### See Also

<u>scanf</u> <u>getch</u> <u>getchar</u> <u>puts</u>

### Example

```
#include "woio.h"
#include <dos.h>
/* Determine whether a file exists */
int prompt_open(void)
{
   char buf[80];
   int handle;
   printf("%cEnter filename:%c ", COL_HIGHTEXT, COL_TEXT);
                             /* get a filename */
   if (gets(buf))
       if ( dos open(buf, 0, &handle)
                                    /* opened file */
           return handle;
                 /* failed to open file */
   return 0;
}
int main(void)
{
   int handle;
   if ((handle = prompt_open()) != 0) {
       printf("File exists\n");
       _dos_close(handle); /* close the file */
       return 1;
```

}
return 0;
}

# int getchar(void)

Get a character .

### Returns

On success, a character value is returned, on error or end of file, a value of EOF (ie. -1) is returned.

### Comments

Function getchar() is streamable, that is, when stdin is redirected on the command line from a file, the characters will be read from the file and will not be echoed to the screen.

When stdin has NOT been redirected on the command line then the following applies :-

1. Characters are echoed to the screen.

2. Tab characters are converted to single space characters,

3. Carriage return characters are converted to new line characters (ie. '\r' mapped to '\n').

4. All non-printable characters are ignored.

#### See Also

<u>scanf</u> <u>getch</u> <u>putch</u> putchar

# int getch(void)

Get a character from the keyboard

## Returns

A character value.

## Comments

Function getch() read characters from the keyboard, and as a result is not streamable.

Characters read are not echoed to the screen.

There is no character mapping. (ie. '\r' is NOT mapped to '\n');

## See Also

<u>scanf</u> <u>putch</u> <u>getchar</u> <u>putchar</u>

# **Command Line Functions**

# int arg\_c

# char \*arg\_v[]

Global variables that contains the number of command line arguments (ie.  $arg_c$ ) and the actual command line arguments (ie.  $arg_v$ ).

#### Comments

 $arg_c$  and  $arg_v$  is provided for compatibility with the standard library argc and argv, which is past to a normal C or C++ main(), and has the following format :-

```
#include "stdio.h"
int main(int argc, char *argv[])
{
}
```

and a WinOne external command main (), has the following format :-

```
#include "woio.h"
int main(void)
{
    /* arg_c is used instead of argc */
    /* arg_v is used instead of argv */
}
```

When using  $arg_c$  and  $arg_v$ , avoid using the arg... () family of functions, since  $arg_c$  and  $arg_v$  do not separate command line arguments and command line switches.

#### See Also

argc argv argn args

# int argc(void)

Determines the number of command line arguments.

## Returns

The number of command line arguments.

## Comments

Command line strings (eg. "This is a string") are considered as command line arguments. Command line switches are not considered as part of the command line arguments.

#### See Also

<u>argv</u> argn args

## char \*argv(index)

int index /\* command line argument \*/

Retrieve a command line argument.

Parameter	Description
index	Specifies which argument to retrieve. Specifying an index of 0 retrieves
	the programs name. Command line arguments start from an index of 1.

#### Returns

On success it returns the address of a NULL terminated string containing the argument. On error it returns a NULL.

#### Comments

The argument is stored in a static buffer and is over-written each time this function is called. This function cannot be used to retrieve command line switches.

#### See Also

<u>argc</u> argn args

#### Example

```
#include "woio.h"
#include <stdlib.h>
/* Sum all value on the command line */
int main(void)
{
   long total;
   int i, n;
   if ((n = argc()) == 0) {
       perror("nothing to sum");
       return 1;
   }
   for (i = 0; i < n; i++)
       total += atol(argv(i + 1));
   printf("%ctotal=%c%ld\n", COL HIGHTEXT, COL NUMBER, total);
   return 0; /* error level */
```

}

## char \*argpath(index)

int index /\* command line argument \*/

Retrieve a command line argument and convert it to a full path name.

Parameter	Description
index	Specifies which argument to retrieve. Specifying an index of 0 retrieves the current directory, as a full path name. Command line
	arguments start from an index of 1.

#### Returns

On success it returns a the address of a NULL terminated string containing the full path name. On error it returns a NULL.

#### Comments

The full path name is stored in a static buffer and is over-written each time this function is called.

Full path names are made up of the following components :-

drive:\directory\filename

#### **Component** When not Specified

drive	Current drive is used.
directory	Current directory is used. Also relative
	directories are converted to absolute
	directories.
filename	*.* is used. Wildcard characters are
	allowed in the filename.

#### See Also

<u>argc</u> <u>argv</u> <u>argabs</u>

## Examples

The following examples assume the current directory is C:\WINDOWS :-

Argument	
C:	C:\WINDOWS\*.*
C:\	C:\*.*
\DOS\	C:\DOS\*.*
NOTEPAD.EXE	C:\WINDOWS\NOTEPAD.EXE
*.EXE	C:\WINDOWS\*.EXE
WHAT	C:\WINDOWS\WHAT.
* *	C:\WINDOWS\*.*
	C:\WINDOWS\*.*
	C:\*.*

## char \*argabs(index)

int index /\* command line argument \*/

Retrieve a command line argument and convert it to an absolute path name.

Parameter	Description
index	Specifies which argument to retrieve. Specifying an index of 0 retrieves
	the current directory, as an absolute path name. Command line arguments start from an index of 1.

#### Returns

On success it returns the address of a NULL terminated string containing the absolute path name. On error it returns a NULL.

#### Comments

The absolute path name is stored in a static buffer and is over-written each time this function is called.

Absolute path names are made up of the following components :-

drive:\directory\filename

#### **Component** When not Specified

drive	Current drive is used.
directory	Current directory is used. Also relative
	directories are converted to absolute
	directories.
filename	The previous directory name becomes the
	filename. Wildcard characters are allowed
	in filename.

#### See Also

<u>argc</u> <u>argv</u> argpath

#### Example

The following examples assume the current directory is C:\WINDOWS :-

Argument C: C:\ \DOS\ NOTEPAD.EXE *.EXE WHAT *.*	Full path C:\WINDOWS. C:\. C:\DOS. C:\WINDOWS\NOTEPAD.EXE C:\WINDOWS\*.EXE C:\WINDOWS\WHAT. C:\WINDOWS\*.* C:\WINDOWS. C:\.
	C:\.

# char \*argtail(void)

Retrieve the actual command line tail.

## Returns

Address of a NULL terminated string containing the command line tail.

## Comments

The actual command line tail does not include any redirection arguments. Also, the tail is stored in a static buffer and is over-written each time this function is called.

#### See Also

argc argv argn args

# int argn(void)

Determines the number of command line switches.

## Returns

The number of switches.

See Also

<u>argc</u> <u>argv</u> <u>args</u>

# char \*args(void)

Retrieve the command line switches.

## Returns

Address of a NULL terminated string containing all the switches.

## Comments

Switches are stored in a static buffer and is over-written each time this function is called.

The string returned can be empty, when there are no command line switches.

### See Also

<u>argc</u> <u>argv</u> argn **Status Bar Functions** 

# void limit(upper)

## unsigned long upper/\* upper limit \*/

Set the Status Bar upper limit (ie. target value) to reach.

ParameterDescriptionupperSpecifies the upper limit to reach.

**Returns** There is no return value.

## Comments

This will display 0 in the Precent indicator, the next time the display is updated.

See Also

<u>inc</u> empty

## void inc(value)

unsigned long value /\* value to increment by \*/

Increment the current Status Bar total.

ParameterDescriptionvalueSpecifies a value to be added to the current Status Bar total.

## Returns

There is no return value.

#### Comments

Function inc() may be called many times before a percentage is calculated and displayed, since the Status Bar is updated once every second.

#### See Also

<u>limit</u> empty

# void empty(void)

Clear the Status Bar Percent indicator.

## Returns

There is no return value.

## Comments

The Status Bar Percent indicator is blanked unconditionally.

#### See Also

limit inc

# **File Manipulation Functions**

# long filesize(path)

char \*path /\* file name path \*/

Retrieve the size of a file.

Parameter	Description
path	Address of a NULL terminated character string containing the path of a filename. This path can be relative or absolute and can not contain wildcard characters.

#### Returns

The size (in bytes) of the specified file. When the file does not exist -1 is returned.

#### Comments

On error filesize() does NOT display an error message.

### See Also

filecpy filencpy filecat filencat

# int istextfile(path)

char \*path /\* file name path \*/

Determine whether the specified file contains text.

Parameter	Description
path	Address of a NULL terminated character string containing the
	path of a filename. This path can be relative or absolute and can
	not contain wildcard characters.

#### Returns

TRUE when the specified file is a text file, otherwise FALSE is returned. On error -1 is returned.

#### Comments

On error <code>istextfile()</code> does NOT display an error message.

Function <code>istextfile()</code> check's the first 100 bytes of the specified file to determine if it is a text file or not.

# long filecpy(dst, src, o\_flag, u\_flag)

char *dst	/* file name path */
<b>char</b> *src	/* file name path */
int o_flag	/* open file flags */
int u_flag	/* update status bar flags */

Copies the source file to the destination file.

path of the destination and can NOT contain w	inated character string containing the file. This path can be relative or absolute ildcard characters. inated character string containing the
path of the source file. This path can be relative or absolute and can NOT contain wildcard characters. Value which specifies how to open the destination file. These	
values are #defined in O_OPEN O_CREATE	the WOIO.H header file and include:- Open the destination file. Create the destination file. When the destination file already exists then it is truncated to 0 length.
Value which specifies h These values are #defi include:- INC_BYTE	be combined. ow to update the status bar percentage. ned in the WOIO.H header file and Increment by the size of the source file. Increment by a value of 1 only.
	Address of a NULL term path of the destination and can NOT contain w Address of a NULL term path of the source file. can NOT contain wildca Value which specifies h values are #defined in O_OPEN O_CREATE O_CREATE These values can NOT Value which specifies h These values are #defi include:-

#### Returns

On success, it returns the number of bytes copied to the destination file. On error a value of -1 is returned.

Do not update.

#### Comments

On error, filecpy() displays one of the following error messages:-

INC\_NONE

```
Out of memory
Invalid path or file name
Destination file already exists
Read error
Insufficient disk space
```

## See Also

<u>filesize</u> <u>filencpy</u> <u>filecat</u> filencat

# long filecat(dst, src, u\_flag)

<b>char</b> *dst	/* file name path */
<b>char</b> *src	/* file name path */
<b>int</b> u_flag	/* update status bar flags */

Appends the source file to the end of the destination file.

<b>Parameter</b> dst		ninated character string containing the n file. This path can be relative or absolute vildcard characters.	
src	Address of a NULL terminated character string containing the path of the source file. This path can be relative or absolute and can NOT contain wildcard characters.		
u_flag	Value which specifies how to update the status bar percentage. These values are #defined in the WOIO.H header file and include:-		
	INC_BYTE INC_ONE INC_NONE	Increment by the size of the source file. Increment by a value of 1 only. Do not update.	

#### Returns

On success, it returns the number of bytes appended to the destination file. On error a value of -1 is returned.

#### Comments

On error, filecat() displays one of the following error messages:-

```
Out of memory
Invalid path or file name
Destination file already exists
Seek error
Read error
Insufficient disk space
```

#### See Also

filesize filecpy filencpy filencat

## long filencpy(dst, src, num, offset, o\_flag, u\_flag)

<b>char</b> *dst	/* file name path */
<b>char</b> *src	/* file name path */
long num	/* number of bytes to copy */
long offset	/* starting offset */
int o_flag	/* open file flags */
int u_flag	/* update status bar flags */

Copy a part of the source file to the destination file.

<b>Parameter</b> dst src	path of the destination and can NOT contain w Address of a NULL term path of the source file.	ninated character string containing the This path can be relative or absolute and
num	should be copied to the	mber of bytes in the source file that e destination file. A value of -1 indicates bytes in the source file, taking into account
offset	Value specifying an offs	set into the source file, where characters irst byte in the source file is located at
o_flag	Value which specifies how to open the destination file. These values are #defined in the WOIO.H header file and include:-	
	O_OPEN O_CREATE	Open the destination file. Create the destination file. When the destination file already exists then it is truncated to 0 length.
	O_CREATNEW	5
u_flag	These values can NOT be combined. Value which specifies how to update the status bar percentage. These values are #defined in the WOIO.H header file and include:-	
	INC_BYTE INC_ONE INC_NONE	Increment by the size of the source file. Increment by a value of 1 only. Do not update.
Poturne		

#### Returns

On success, it returns the number of bytes copied to the destination file. On error a value of -1 is returned.

#### Comments

On error, filencpy() displays one of the following error messages:-

```
Out of memory
Invalid path or file name
Destination file already exists
Out of range
```

```
Seek error
Read error
Insufficient disk space
```

## See Also

<u>filesize</u> <u>filecpy</u> <u>filecat</u> filencat

## long filencat(dst, src, num, offset, u\_flag)

<b>char</b> *dst	/* file name path */
char *src	/* file name path */
long num	/* number of bytes to copy */
long offset	/* starting offset */
int u_flag	/* update status bar flags */

Appends a part of the source file to the end of the destination file.

<b>Parameter</b> dst	<b>Description</b> Address of a NULL terminated character string containing the path of the destination file. This path can be relative or absolute and can NOT contain wildcard characters.
SrC	Address of a NULL terminated character string containing the path of the source file. This path can be relative or absolute and can NOT contain wildcard characters.
num	Value specifying the number of bytes in the source file that should be appended to the destination file. A value of -1 indicates that all the remaining bytes in the source file, taking into account the starting offset, should be appended.
offset	Value specifying an offset into the source file, where characters will be read from, The first byte in the source file is located at offset zero.
u_flag	Value which specifies how to update the status bar percentage. These values are #defined in the WOIO.H header file and include:-
	INC PVTE Increment by the size of the source file

INC_BYTE	Increment by the size of the source file.
INC_ONE	Increment by a value of 1 only.
INC_NONE	Do not update.

#### Returns

On success, it returns the number of bytes appended to the destination file. On error a value of -1 is returned.

### Comments

On error, filecat() displays one of the following error messages:-

```
Out of memory
Invalid path or file name
Destination file already exists
Out of range
Seek error
Read error
Insufficient disk space
```

#### See Also

filesize filecpy filencpy filecat **File Name Functions** 

## int fillfile(path, attr)

<b>char</b> *path	/* directory path */
unsigned int attr	/* file attributes */

Create a File Table of all the files in a given path and with a given attribute.

Parameter	Description
path	Address of a NULL terminated character string containing a path.
	This path can be relative or absolute and can contain Wildcard
	characters any where in the filename part of the path.
attr	DOS File attribute (defined in DOS.H), include the following :-

FA RDONLY	Read-only
FA_HIDDEN	Hidden file
FA_SYSTEM	System file
FA_LABEL	Volume label
FA_DIREC	Directory
FA_ARCH	Archive

#### Returns

On success, it returns the number of files that match the path and attribute specified, otherwise, it returns a value of zero, when no files match.

#### Comments

Function fillfile() replaces findfirst(), findnext(), \_dos\_findfirst() and \_dos\_findnext(), since these functions do not support extended wildcard card characters.

WinOne allows wildcard characters to be placed anywhere inside a filename and be correctly interpreted.

All files that meet the specifies requirements are places inside a table (ie. File Table) which is over-written with each call to this function. Use the getfile... () functions to access the information stored in this table.

The table is sorted in alphabetical order.

See Also <u>getfile</u> <u>getfilepath</u> <u>getfilename</u>

## **BOOL** getfile(index, pff)

<b>int</b> index	/* index into File Table */
struct ffblk *pff	/* DOS file control block structure */

Retrieve a DOS file control block structure from the File Table.

Parameter index pff	<b>Description</b> Specifies which ffblk to retrieve from the File Table. Entries in the File Table start from an index of 0. Address of a DOS file control block structure (defined in WOIO.H) :-
	<pre>struct ffblk {     long ff_reserved; /* reserved */     long ff_fsize; /* file size */     unsigned long ff_attrib; /* file attribute */     unsigned short ff_ftime; /* file time */     unsigned short ff_fdate; /* file date */     char ff_name[256]; /* file name */</pre>

};

#### Returns

On success, it returns a non-zero value and the file control block structure is filled. On error zero is returned.

#### Comments

Use the fillfile() to fill the File Table before using getfile().

## See Also

<u>fillfile</u> <u>getfilepath</u> <u>getfilename</u>

### Example

```
#include "woio.h"
#include <dir.h>
/* Display a file listing */
int dir(char *path)
{
    int i, n;
    struct ffblk ffblk;
    printf("%cDirectory of %s\n\n", COL_HIGHTEXT, path);
    if ((n = fillfile(path, 0)) == 0) {
        perror("No files found");
        return 1;
    }
    for (i = 0;i < n;i++) {
        if (getfile(i, &ffblk) == FALSE) {
    }
}</pre>
```

```
perror("Bad index");
           return 1;
        }
       printf(" c^{-13s}c^{91d}n",
            COL FILENAME, ffblk.ff name,
            COL NUMBER, ffblk.ff fsize); /* display file names */
    }
   return 0; /* all done */
}
int main(void)
{
   char *path;
   int ret;
   if (argc() > 1) { /* check number of arguments */
       perror("Too many or few arguments");
       return 1;
    }
   screen(BUFFERED); /* buffered screen output */
   if ((path = argpath(argc())) == NULL) {
       perror("Path or file not found");
       return 1;
    }
   ret = dir(path);
   screen(UNBUFFERED); /* flush output */
   return ret; /* error level */
}
```

# char \*getfilepath(index)

int index /\* index into File Table \*/

Retrieve a file path from the File Table.

Parameter	Description
index	Specifies which file path to retrieve from the File Table. Entries in
	the File Table start from an index of 0.

### Returns

On success it returns the address of a NULL terminated string containing the path name. On error it returns a NULL.

### Comments

Use the fillfile() to fill the File Table before using getfilepath().

Path names are stored in a static buffer and is over-written each time this function is called.

The path returned may not contain a fully qualified path name.

### See Also

<u>fillfile</u> <u>getfile</u> getfilename

# char \*getfilename(index)

int index /\* index into File Table \*/

Retrieve a file name from the File Table.

Parameter	Description
index	Specifies which file name to retrieve from the File Table. Entries
	in the File Table start from an index of 0.

### Returns

On success it returns the address of a NULL terminated string containing the file name. On error it returns a NULL.

### Comments

Use the fillfile() to fill the File Table before using getfilename().

File names are stored in a static buffer and is over-written each time this function is called.

### See Also

<u>fillfile</u> <u>getfile</u> getfilepath

# char \*padfilename(path)

char \*path /\* character string \*/

Pad a file name so that it is suitable for displaying.

Parameter	Description
path	Address of a NULL terminated character string contain a path
	name.

### Returns

The address of a character string containing the padded file name.

### Comments

Only the file name is padded and returned, the rest of the path is discarded.

The padded file name is stored in a static buffer and is over-written each time this function is called.

**Path Name Functions** 

# int fillpath(path)

char \*path /\* directory path \*/

Create a Path Table containing all the directories and sub-directories starting from the specified path.

Parameter	Description
path	Address of a NULL terminated character string containing a path. This path can be relative or absolute. The file name part of the path is expected and ignored.

### Returns

On success, it returns the number of directories and sub-directories found, otherwise, it returns a value of zero, when no directories are found.

### Comments

The directories . and . . are not included in the table.

A new Path Table is allocated with each call to this function. Use freepaths() to release the memory allocated for the table, when it is no longer needed.

The table is sorted in alphabetical order

See Also

fillpathall freepaths getpath

# int fillpathall(void)

Create a Path Table containing all the directories and sub-directories for all drives that are non-removable.

### Returns

On success, it returns the number of directories and sub-directories found, otherwise, it returns a value of zero, when no directories are found.

### Comments

The directories . and . . are not included in the table.

A new Path Table is allocated with each call to this function. Use freepaths() to release the memory allocated for the table, when it is no longer needed.

The table is sorted in alphabetical order

See Also

<u>fillpath</u> <u>freepaths</u> <u>getpath</u>

# void freepaths(void)

Release the memory allocated to store the Path Table.

### Returns

There is no return value.

See Also

<u>fillpath</u> <u>fillpathall</u>

## char \*getpath(index)

int index /\* index into the Path Table \*/

Retrieve a path name from the Path Table.

Parameter	Description
index	Specifies which path to retrieve from the Path Table. Entries in
	the Path Table start from an index of 0.

### Returns

On success it returns the address of a NULL terminated string containing the path name. On error it returns a NULL.

### Comments

All the path names returned contains \*.\* for the file name part..

Use the fillpath() or fillpathall() to fill the Path Table before using getpath().

Path names are stored in a static buffer and is over-written each time this function is called.

### See Also

<u>fillpath</u> <u>fillpathall</u> <u>freepaths</u>

# **Unix Functions**

# char \*tounix(cmd)

char \*cmd /\* DOS command to convert \*/

Convert a DOS command line to a Unix command line, when Unix mode is enabled.

Parameter	Description
cmd	Address of a NULL terminated character string containing a DOS
	command line.

### Returns

The address of a NULL terminated string containing the Unix command line, when Unix mode is enabled, otherwise, the DOS command line is returned.

### Comments

Command lines are stored in a static buffer and is over-written each time this function is called.

This function is also used to convert DOS paths to Unix paths, suitable for displaying.

See Also

<u>isunix</u> todos

# int isunix(void)

Determines whether Unix mode is on or off.

### Returns

A value greater than zero when Unix is on and zero when Unix is off.

See Also

<u>tounix</u> <u>todos</u>

## char \*todos(cmd)

Convert a Unix command line to a DOS command line, when Unix mode is enabled.

Parameter	Description
cmd	Address of a NULL terminated character string containing a Unix
	command line.

### Returns

The address of a NULL terminated string containing the DOS command line, when Unix mode is enabled, otherwise, the Unix command line is returned.

### Comments

This function overwrites the cmd parameter.

When Unix mode is not enabled, then the Unix command line is simply copied into the static buffer and is not converted.

This function is also used to convert Unix paths to DOS paths.

### See Also

<u>tounix</u> isunix

# **File Description Functions**

# char \*getdesc(path)

char \*path /\* path of file \*/

Retrieve a file description for the specified file.

Parameter	Description
path	Address of a NULL terminated character string containing the full path of the decribed file.

### Returns

The address of a NULL terminated string containing the file description. On error an empty string is returned.

### Comments

The file description is stored in a static buffer and is over-written each time this function is called.

See Also

<u>setdesc</u> <u>deldesc</u>

# int setdesc(path, str)

char \*path/\* path of file \*/char \*str/\* character string \*/

Set a file description for the specified file.

<b>Parameter</b> path str	<b>Description</b> Address of a NULL terminated character string containing the full path of the file to describe. Address of a NULL terminated character string containing the file description. The description can contain a maximum of 60
	characters.

#### Returns

On success a value of zero is returned. On error -1 is returned.

See Also

<u>getdesc</u> <u>deldesc</u>

# int deldesc(path)

char \*path /\* path of file \*/

Delete a file description for the specified file.

Parameter	Description
path	Address of a NULL terminated character string containing the path of the described file.

### Returns

A value of zero on success. On error -1 is returned.

#### See Also

<u>getdesc</u> <u>setdesc</u>

# **Environment Functions**

## char \*getenvironment(name)

Retrieve an environment variable from the WinOne environment space.

Parameter	Description
name	Address of a NULL terminated character string that contains the
	name of the environment variable to retrieve.

### Returns

The address of a NULL terminated character string, where the environment variable is stored. On error a NULL value is returned.

### Comments

The environment variable is stored in a static buffer, that is over-written each time this function is called.

### See Also

<u>putenvironment</u>

### int putenvironment(name)

char \*name /\* environment string \*/

Place an environment string into the WinOne environment space.

Parameter	Description
name	Address of a NULL terminated character string that contains the
	environment string to place into the WinOne environment space.

### Returns

Value of zero. On error, a value of -1 is returned

### Comments

The parameter name is duplicated using malloc() by WinOne and therefore, does not need to be a static or malloced and not freed, which is the case with the standard library function putenv().

Environment strings have the form:-

VARNAME=ENVSTRING

To delete an environment variable, exclude the ENVSTRING. For example, to delete the environment variable AVAR :-

```
putenvironment("AVAR=");
```

See Also

getenvironment