Connection and Server Information

<u>EARTHLINK SUBSCRIBERS</u>

Subscribers logging into EarthLink must use the following format in the **Username** field:

- **Username**:   *username*@earthlink.net

The **POP** and **SMTP** Server settings are required in order to Send/Receive email through the EarthLink Servers.

- **POP Server**:   pop.earthlink.net
- **SMTP Server**:   smtp.earthlink.net

The **NNTP** (or **News**) Server setting is needed in order to gain access to EarthLink's News Server.

- **NNTP/News Server**: news.earthlink.net

Every EarthLink subscriber is provided with a FREE EarthLink webspace:

- **Webspace** address: http://home.earthlink.net/~*username*

The **FTP** and **Domain Server** settings are required to make changes to (or build) your webspace:

- **FTP Server**:   ftp-www.earthlink.net (6mb webspace only)
- **FTP Domain Server**: ftp-dom.earthlink.net (Domain hosting only)

In order for members to establish a connection with EarthLink, any two of the three DNS numbers below must be entered in the Network settings.

- **DNS Servers**:   207.217.77.82
                          207.217.120.83
                          207.217.126.81

<u>MINDSPRING SUBSCRIBERS</u>

Subscribers logging into MindSpring must use the following format in the **Username** field:

- **Username**: *username*@mindspring.com

The **POP** and **SMTP** Server settings are required in order to Send/Receive email through the MindSpring Servers.

- **POP Server**: pop.mindspring.com
- **SMTP Server**: smtp.mindspring.com

The **NNTP** (or **News**) Server setting is needed in order to gain access to MindSpring's News Server.

- **NNTP/News Server**: nntp.mindspring.com

Every EarthLink subscriber is provided with a FREE EarthLink webspace:

- **Webspace** address: http://*username*.home.mindspring.com

The **FTP** and **Domain Server** settings are required to make changes to (or build) your webspace:

- **FTP Server**: ftp.mindspring.com (6mb web space only)
- **FTP Domain Server**: ftp.business.earthlink.net (Domain hosting only)

In order for members to establish a connection with EarthLink, any two of the three DNS numbers below must be entered in the Network settings.

- **DNS Servers**: 207.69.188.187
  207.69.188.186
  207.69.188.185