

\$VER: ScreenTab v.1 (13.3.98)

COLLABORATORS

	TITLE : \$VER: ScreenTab v.1 (13.3.98)		
ACTION	NAME	DATE	SIGNATURE
WRITTEN BY		August 22, 2024	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	\$VER: ScreenTab v.1 (13.3.98)	1
1.1	ScreenTab V.10 Documentation.	1
1.2	Introduction	1
1.3	Features	2
1.4	Requirements	2
1.5	Installation	2
1.6	Information	3
1.7	Supported Tooltypes	3
1.8	Contact Address	3

Chapter 1

\$VER: ScreenTab v.1 (13.3.98)

1.1 ScreenTab V.10 Documentation.

```
"__"      ScreenTab
|O O|  Copyright © 1998 Denis Obriot
| V |    Les softs de la chouette
---
```

This software is Public Domain and can therefore be copied and distributed freely. The software is provided as is and the author accepts no responsibility for any damage or loss incurred from this programs use.

This program is Mailware
send me a message

Contact Address

Introduction
Features

Requirements
Installing

Information
Tooltypes

1.2 Introduction

This program allows you to surf from one screen to another
A Little window come in the frontscreen with a gadtool
list gadget. Click on the name of the screen, and this

screen go on the front.

This program is a commodity.

The normal HotKey is F4

The normal HotKey for quit is left alt f4

1.3 Features

Support all worbench screen mode

Supports Tooltypes

From the v 0.11 it is localized

1.4 Requirements

Minimum:

A Amiga with OS 3

68000

Recommended:

68020

1.5 Installation

Use the Install utility or

Just copy ScreenTab Anywere

For use clic on there Icon. A little window appear for few second and disappear.

For active this commodity hit the popkey
(f4 by default) choose the screen.

For quit this commodity hit quit popkey
(left alt f4 by default)

see Introduction

or Tooltypes

1.6 Information

This program was written with:

The Blitz Basic v 2.10

Is Copyright 1997, Denis Obriot

Les softs de la chouette

```

  "____"      ScreenTab
|O O|  Copyright © 1998 Denis Obriot
| V |      Les softs de la chouette
  ---
Version 0.1 B
```

1.7 Supported Tooltypes

CX_POPKEY=<key for activate the program>

CX_CLOSEKEY=<key for quit the program>

CX_CONFIGKEY=<key for config >

WBSCREEN=1 always on workbench
=0 on the first screen

PUBLIC=1 only publicscreen

1.8 Contact Address

All feedback, suggestions, bugs report to:

D OBRIOT
10 Rue de la libération
52600 Heuilley-Cotton
FRANCE

e-mail: sidne@club-internet.fr

Thank you for your message !!

If you are be interested in model. Visit my site
<http://www.mygale.org/07/sidne>
It is model by Amiga but not Virtual REAL