

## HERE 1.1



### DESCRIPTION

**Here** is a shareware program that allows you to easily post your ever-changing dynamic PPP Internet address to a finger or web account, thereby allowing others to look up your current Internet address and contact you.

**Here** also includes integrated finger and web clients to allow you to easily check the PPP address postings of other **Here** users.

Since other users will now be able to locate your current address, you will be able to use talk servers such as **WinTalk**; FTP servers such as **WinQV/Net**, **Serv-U**, and **WFTPD**; and HTTP servers such as **HTTPD** and **ZB Server**.

### MINIMUM HARDWARE AND SOFTWARE REQUIREMENTS

**Here** is available in two compilations, one for **Win16** and one for **Win32**. Both compilations require an IBM compatible PC with a **386+** microprocessor and **Winsock 1.1+**. The **Win16** version requires **Windows 3.1+** and the **Win32** version requires **Windows 95, NT, or 3.1** with **Win32s**.

### REGISTRATION

**Here** is shareware. You may try **Here** for thirty days for free. However, if you decide to continue to use **Here** after the initial trial period, you are required to register it. The registration fee is \$10 US.

You can register **Here** by mail by printing the accompanying registration form contained in the "register.txt" file and mailing it to the address on the form, together with your check or money order.

### INSTALLATION

After unzipping the archive, you will have the following files:

- here16.exe - 16 bit Program.
- here32.exe - 32 bit Program.
- here.hlp - Help.
- here.wri - Installation and Program Information.
- register.txt - Registration Form.
- file\_id.diz - Summary Program Description.
- ctl3dv2.dll - 16-bit 3-D Control Library.
- ctl3d32.dll - 32-bit 3-D Control Library.

First, there are two versions of **Here** included in the zip file. "here16.exe" is for Windows 3.1 and "here32.exe" is for Windows 95, Windows NT, and Windows 3.1 with Win32s.

If you use only "here16.exe", move the file "ctl3dv2.dll" into your \windows\system directory, if you do not already have a copy of it located there. You may then delete the "here32.exe" and "ctl3dv32.dll" files.

If you use only "here32.exe", move "ctl3d32.dll" into you \windows\system directory, if you do not already have a copy of it located there. You may then delete "here16.exe" and "ctl3dv2.dll".

If you use both "here16.exe" and "here32.exe", move both "ctl3dv2.dll" and "ctl3dv32.dll" into your \windows\system directory.

Second, create a new directory (for example, c:\here) and copy all of the remaining **Here** files into it.

Third, add a **Here** Program Item to one of your one of your **Program Manager** groups.

**IMPORTANT NOTE:** Before running **Here**, you **MUST** remove both of the "dll" files from the directory into which you installed **Here**, either by moving them to your \windows\system directory or by deleting them if you do not move them. If you leave them in the same directory as your **Here** "exe" files, you will get error messages and **Here** will not run!

## SETUP

To begin using **Here** to post messages, you must first enter your FTP login information in the **FTP Login** dialog box under the **Settings** menu.

You can choose two files to use for postings by using the **Upload Files** dialog box under the **Settings** menu. The default is to upload only your finger's ".project" file. You can add a second file to upload, and can choose any name for either of the two files so as to conform to the particular needs of your remote system (such as renaming ".project" to "project.txt" for VMS systems). The suggested name for the second file is "public\_html/here.txt" which would upload a web page on most web server setups.

## USE

To upload an ON message including your current PPP address, choose **On** from the **Post** menu. To upload an OFF message, choose **Off** from the **Post** menu. To automatically post ON and OFF messages when you start and when you exit **Here** choose the **Auto Post** toggle under the **Settings** menu.

You can check the address postings of other **Here** users by choosing **Finger** or **Web** under the **Query** menu.

**Here's** help file contains further detailed directions for using **Here**. If you would like to review

the help file before starting **Here**, just double-click on the file **here.hlp** from inside the Windows **File Manager**. You can browse through the help file sequentially from beginning to end by using the browse buttons (<< and >>).

## **VERSION AND DOWNLOAD INFORMATION**

The latest version can be downloaded from the **Here** Home Page:

<http://www.cris.com/~beers/here>

or from **TUCOWS** (The Ultimate Collection of Winsock Software):

<http://www.tucows.com>

## **COPYRIGHT AND LICENSE**

**Here** is copyrighted by its author, Everitt Beers. The author reserves and retains all rights to the program and its related files except as otherwise expressly licensed herein. The program is not in the public domain.

**Here** is a shareware program. It may be freely distributed to others as long as all of the original program, help, and documentation files remain together in unmodified form and as long as no fee is charged.

**Here** may be used by any individual for any non-commercial, non-profit, or educational use without paying any fee.

**Here** may be evaluated for thirty days for commercial use without paying a fee. However, each copy that is used for any commercial or profit-generating use after the initial thirty-day trial period must be registered. The commercial registration fee is \$10 US per copy.

To register **Here** for commercial use, you may use the Registration Form contained in the "register.txt" file that is included in the distribution, or you may instead simply mail your check, or credit card information, to:

Everitt Beers  
8928 Beverlywood Street  
Los Angeles, California 90034-2418  
United States

**Here** may not be resold or distributed as part of any commercial package without the express permission of the author.

## **DISCLAIMER**

**Here** is distributed "as is" without warranty of any kind, either express or implied, including without any implied warranties of merchantability and fitness for a particular purpose. The user

assumes all risks of using the program. The author shall not be liable for any damages whatsoever, including any direct, indirect, incidental, consequential, loss of profits, or special damages, arising out of the use, or the inability to use, the program, even if advised of the possibility of such damages in advance.

## **SUPPORT**

Support information on **Here** can be found at <http://www.cris.com/~beers/here>. You may also send bug reports, questions, or program revision suggestions to [beers@cris.com](mailto:beers@cris.com).

## **PROGRAM UPDATES**

The latest version of **Here** can be downloaded from <http://www.cris.com/~beers/here>.

Copyright (c) 1996 Everitt Beers  
All rights reserved.