

```

;PR;
;«PT1»«LM0»«RM78»«MDBO»Epson LQ 1500«MDNM» = «MDBO»Brother 2024L, DP mode + Hebr
; «MDRV»Augmentation for NL10-DRF.PRN«MDNM» April 14, 1990, Itamar Even-Zohar.
; «MDRV»must be loaded WITH the other printer table to work«MDNM»
;
; Contains fonts only for 4, 5, 6 & 8 pitches. Load as complementary
; printer table ('«MDRV»load NL10-DRF.PRN+&NL10DRF.PRN«MDNM»').
;
TF=1      Top margin set (0--by program 1--by user manually advancing paper)
DF NP     AP for autopause between sheets; NP for no pause
;        Monospace print types: 5, 6, 8
;
;«MDBO»Print-Type Tables«MDNM»«LD-»
;4 cpi«LD-»
; Quadruple-high, quadruple-wide characters
PT=4,214
MD NM+4
md 1+4
;;MD FL+4+NM
MD UL+4+UL
;;MD FU+4+UL
md 17+4+UL
MD BO+4+BO
md 129+4+BO
MD BU+4+UL+BO
md 124+4+UL+BO
MD RV+4
md 49+4
;MD BR+itl-4+BO
;md 177+itl-4+BO
MD SU+4+SU
md 64+4+SU
MD SD+4+SD
md 193+4+SD
MD FR+4+OVERSTRIKE
MD FN+4+FOOTNOTE
;4 Hebrew cpi«LD-»
;Hebrew 4Hp
md 6+4H+NM
md 22+4H+UL
md 134+4H+BO
md 140+4H+UL
md 44+4H+RV
md 70+4H+SU
md 198+4H+SD
;
;5 cpi«LD-»
PT=5,214
MD NM+5
md 1+5
;;MD FL+5+NM
MD UL+5+UL
;;MD FU+5+UL
md 17+5+UL
MD BO+5+BO
md 129+5+BO
MD BU+5+UL+BO
md 125+5+UL+BO
MD RV+5
md 49+5

```

;MD BR+itl-5+BO
;md 177+itl-5+BO
MD SU+5+SU
md 65+5+SU
MD SD+5+SD
md 193+5+SD
MD FR+5+OVERSTRIKE
MD FN+5+FOOTNOTE
;5 Hebrew cpi«LD-»
;Hebrew 5Hp
md 6+5H+NM
md 22+5H+UL
md 134+5H+BO
md 150+5H+UL
md 54+5H+RV
md 70+5H+SU
md 198+5H+SD
;6 cpi«LD-»
PT=6,212,
MD NM+6
md 1+6
;;MD FL+6+NM
MD UL+6+UL
;;MD FU+6+UL
md 17+6+UL
MD BO+6+BO
md 129+6+BO
MD BU+6+UL+BO
md 126+6+UL+BO
MD RV+6
md 49+6
;MD BR+itl-6+BO
;md 177+itl-6+BO
MD SU+6+SU
md 66+6+SU
MD SD+6+SD
md 193+6+SD
MD FR+6+OVERSTRIKE
MD FN+6+FOOTNOTE
;6 Hebrew cpi«LD-»
;Hebrew 6Hp
md 6+6H+NM
md 22+6H+UL
md 134+6H+BO
md 160+6H+UL
md 64+6H+RV
md 70+6H+SU
md 198+6H+SD
;8 cpi«LD-»
PT=8,17
MD NM+8
md 1+8
;;MD FL+8+NM
MD UL+8+UL
;;MD FU+8+UL
md 17+8+UL
MD BO+8+BO
md 129+8+BO
MD BU+8+UL+BO
md 128+8+UL+BO

MD RV+8
md 49+8
;MD BR+itl-8+BO
;md 177+itl-8+BO
MD SU+8+SU
md 88+8+SU
MD SD+8+SD
md 193+8+SD
MD FR+8+OVERSTRIKE
MD FN+8+FOOTNOTE
;8 Hebrew cpi«LD-»
;Hebrew 8Hp
md hn+8H+NM
md hu+8H+UL
md hb+8H+BO
;md hc+8H+UL
;md 84+8H+RV
md 70+8H+SU
md 198+8H+SD
;«MDBO»Attributes«MDRV»«MDNM»«LD-»
;Normal«LD-»
AT:NM
AT<
ET
;Insert«LD-»
AT:INSERT
AT<[
AT>]
ET
;Delete«LD-»
AT:DELETE
AT# 08\
ET
;Underline«LD-»
AT:UL
AT<⊙
AT> 00
ET
;Bold (Double-strike, not Emphasized)«LD-»
AT:BO
AT<G
AT>H
ET
;Bold Underlined«LD-»
;AT:BU
;AT<⊙G
;AT>H
;ET
;Reverse/Italics«LD-»
AT:RV
AT<⊙
AT> 00
ET
;Bold Reverse«LD-»
AT:Bold·Reverse/Forms
AT<
AT>
ET
;SU«LD-»
AT:SU

AT<S 00
AT>T
AT=2
ET
;Hebrew·SU«LD→»
;AT:SUH
;AT<S 00
;AT>T
;AT=32
;ET
;SD«LD→»
AT:SD
AT<S⊙
AT>T
AT=2
ET
;Flashing Reverse/Overstrike«LD→»
AT:Overstrike
AT<
AT>
ET
;Footnote Mode«LD→»
AT:Footnote
AT<
AT>
ET
;Micro Mode«LD→»
;AT:MICRO
;AT<P
;ET
;«MDBO»Font Tables«MDNM»«LD→»
;4cpi«LD→»
FO:4
FO<h⊙
FO>h 00
VL=10
UW:W4-Expanded
ET
;4cpiHebrew«LD→»
FO:4H
FO<p 00↑Ph⊙
FO>h 00
VL=10
UW:W4-Expanded
AT=32
ET
;5cpi«LD→»
FO:5
FO<p 00↑PW⊙
FO>W 00
VL=10
UW:W10-Expanded
ET
;5cpiHebrew«LD→»
FO:5H
FO<p 00↑PW⊙
FO>W 00
VL=10
UW:W10-Expanded
AT=32

ET
;6cpi«LD-»
FO:6
;FO:12-Expanded
FO<↑MW⊙
FO>W 00
VL=12
UW:W12-Expanded
ET
;6Hebrewcpi«LD-»
FO:6H
;FO:12H-Expanded
FO<↑MW⊙
FO>W 00
VL=12
UW:W12-Expanded
AT=32
ET
;8 cpi«LD-»
FO:8
;FO:15-Expanded
FO<PW⊙
~~FO>W200↑~~
UW:W15-Expanded
ET
;8 cpi Hebrew«LD-»
FO:8H
;FO:15-Expanded
FO<PW⊙
~~FO>W200↑~~
UW:W15-Expanded
AT=32
ET
;«MDBO»Width Tables«MDRV»«MDNM»«LD-»
;4cpi«LD-»
WD:W4-Expanded
DU=4
SW=4
=0
ET
;5cpi«LD-»
WD:W10-Expanded
DU=72
SW=72
=0
ET
;6cpi«LD-»
WD:W12-Expanded
DU=60
SW=60
=0
ET
;8cpi«LD-»
WD:W15-Expanded
DU=42
SW=42
=0
ET
;10cpi«LD-»
WD:W10

```
DU=36
SW=36
=0
ET
;12cpi«LD-»
WD:W12
DU=30
SW=30
=0
ET
;17cpi«LD-»
WD:W15
DU=21
SW=21
=0
ET
;«MDBO»Horizontal Spacing Table«MDNM»«LD-»
; Defined in the other printer table
; End of printer table
→
```