

Sheet1

PBRAND,C,25	PRESET,C,23	P12CPI,C,23	P10CPI,C,23	PCONDON,C,23	PCONDOFF,C
NONE, Generic 10 pitch					
Epson 9 pin (FX)	027+"@"	027+"M"	027+"P"	015	018
Epson 24 pin (LQ)	027+"@"	027+"M"	027+"P"	015	018
HP DeskJet	027+"E"	027+"(s12H"	027+"(s10H"	027+"(s16.67H"	027+"(s10H"
HP LaserJet+,500,II,III	027+"E"	027+"(s12H"	027+"(s10H"	027+"(s16.67H"	027+"(s10H"
HP LaserJet (original)	027+"E"	027+"(s12H"	027+"(s10H"	027+"(s16.67H"	027+"(s10H"
IBM Proprinter 9 pin		027+"M"	027+"P"	015	018
IBM Proprinter 24 pin		027+":"	018	015	018
Okidata 9 pin (Epson 9)	027+"@"	027+"M"	027+"P"	015	018
Okidata 24 pin (Epson24)	027+"@"	027+"M"	027+"P"	015	018
Okidata LED OL400/800	027+"E"	027+"(s12H"	027+"(s10H"	027+"(s16.67H"	027+"(s10H"
Panasonic 9 pin (Epson9)	027+"@"	027+"M"	027+"P"	015	018
Panasonic KX-P1124	027+"@"	027+"M"	027+"P"	015	018
Toshiba 24 pin	027/013/080	027+"E10"	027+"E12"	027+"["	

Sheet1

P8LPI,C,23 P6LPI,C,23 PBOLDON,CPBOLDOFF,(PEMPHON,CPEMPHOFF,PUNDRON,C,PUNDROFF,C

027+"0"	027+"2"	027+"G"	027+"H"	027+"E"	027+"F"
027+"0"	027+"2"	027+"G"	027+"H"	027+"E"	027+"F"
027+"&l8D"	027+"&l6D"	027+"(s3B"	027+"(s0B"	027+"(s4B"	027+"(s0B"
027+"&l8D"	027+"&l6D"	027+"(s3B"	027+"(s0B"	027+"(s4B"	027+"(s0B"
027+"&l8D"	027+"&l6D"	027+"(s3B"	027+"(s0B"	027+"(s4B"	027+"(s0B"
027+"0"	027+"2"	027+"G"	027+"H"	027+"E"	027+"F"
027+"0"	027+"2"	027+"G"	027+"H"	027+"E"	027+"F"
027+"0"	027+"2"	027+"G"	027+"H"	027+"E"	027+"F"
027+"0"	027+"2"	027+"G"	027+"H"	027+"E"	027+"F"
027+"&l8D"	027+"&l6D"	027+"(s3B"	027+"(s0B"	027+"(s4B"	027+"(s0B"
027+"0"	027+"2"	027+"G"	027+"H"	027+"E"	027+"F"
027+"0"	027+"2"	027+"G"	027+"H"	027+"E"	027+"F"
027+"L06"	027+"L08"	027+"K3"	027+"M"		

Sheet1

PLQON,C,23 PLQOFF,C,23PEXPDON,C,;PEXPDOFF,CPNUM,N,2,0

0  
1  
5  
12  
4  
21  
0  
8  
1  
5  
4  
1  
5  
6