

Sheet1

QPRNAME,C,40	QPQPRRESET,C,QPRFONT,C,90	QPR1COLF,C,90	QPRLPI,C,90
GENERIC DOT MATRIX	### CHR(24) CHR(15)	CHR(15)	CHR(27)+"0"
HP LASERJET II	### CHR(27)+"E" CHR(27)+"(s16.66H"		CHR(27)+"&I8D"
HP DESKJET 500	### CHR(27)+"E" CHR(27)+"(s16.66H"		CHR(27)+"&I8D"
ROLAND PR-1212A	### CHR(27)+"@" CHR(15)	CHR(27)+"!"+CHR(9)	CHR(27)+"0"
HP LASERJET III	### CHR(27)+"E" CHR(27)+"(s16.66H"		CHR(27)+"&I8D"

Sheet1

QPRPLEN,C,90	QPRLMAR,C,90	QPRRMAR,C,90	QPRTMAR,C,90	QPRORIENT,'QP
CHR(27)+"C"+CHR(88)	CHR(27)+"I"+CHR(4)	CHR(27)+"Q"+CHR(137)		###
CHR(27)+"&l88F"	CHR(27)+"&a4L"	CHR(27)+"&a137M"	CHR(27)+"&l4E"	###
CHR(27)+"&l88P"	CHR(27)+"&a2L"	CHR(27)+"&a137M"	CHR(27)+"&l3E"	###
CHR(27)+"C"+CHR(88)	CHR(27)+"I"+CHR(4)	CHR(27)+"Q"+CHR(137)		###
CHR(27)+"&l88F"	CHR(27)+"&a4L"	CHR(27)+"&a137M"	CHR(27)+"&l4E"	###

QPR2MMSG1,C,60

This print form is for a business-size (11" wide) envelope

Insert envelope under OUT tray wings according to manual

This print form is for a business-size envelope

Sheet1

QPR2MSG2,C,60

Adjust envelope so that print head at first line to print

QPRFONT2,C,90

CHR(18)

Then press printer UP and DOWN arrows simultaneously to load

Adjust envelope so that print head at first line to print

chr(27)+"(s1p12v4101t2Q"

CHR(27)+"n"

Sheet1

QPRLPI2,C,90	QPRPLEN2,C,90	QPRLMAR2,C,90	QPRRMAR2,C,90
CHR(27)+"2"	CHR(27)+"C" + CHR(8)	CHR(27) + "I" + CHR(20)	CHR(27) + "Q" + CHR(130)
chr(27) + "&l6D"	chr(27) + "&l24P"	chr(27) + "&a60L"	chr(27) + "&a130M"
CHR(27)+"2"	CHR(27)+"C" + CHR(8)	CHR(27) + "I" + CHR(20)	CHR(27) + "Q" + CHR(130)

QPRTMAR2,C,90 QPRORIENT2,C,90

chr(27) + "&l8E"