

ENVIRONLIB

Conversion program

COLLABORATORS

	<i>TITLE :</i> ENVIRONLIB	
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>
WRITTEN BY	Conversion program	October 9, 2022
<i>SIGNATURE</i>		

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1 ENVIRONLIB	1
1.1 Overview of ENVIRONLIB	1
1.2 ENVIRONLIB	1
1.3 ENVIRONLIB	1
1.4 ENVIRONLIB	2
1.5 ENVIRONLIB	2
1.6 ENVIRONLIB	2
1.7 ENVIRONLIB	2
1.8 ENVIRONLIB	3
1.9 ENVIRONLIB	3
1.10 ENVIRONLIB	3

Chapter 1

ENVIRONLIB

1.1 Overview of ENVIRONLIB

Overview

An Acid Software Library

Converted to AmigaGuide by

Red When Excited Ltd

Used with the permission of Acid Software

Edited, fixed and cleaned by Toby Zuidveld 26/20/1999.
mailto:hotcakes@abacus.net.au

1.2 ENVIRONLIB

Statement: WBWidth

Modes :

Syntax : WBWidth

The functions WBWidth, WBHeight, WBDepth & WBViewMode return the width, height, depth & viewmode of the current WorkBench screen as configured by preferences.

1.3 ENVIRONLIB

Statement: WBHeight

Modes :

Syntax : WBHeight

See Description of WBWidth.

1.4 ENVIRONLIB

Statement: WBDepth

Modes :

Syntax : WBDepth

See Description of WBWidth.

1.5 ENVIRONLIB

Statement: WBViewMode

Modes :

Syntax : WBViewMode

See Description of WBWidth.

1.6 ENVIRONLIB

Statement: Processor

Modes :

Syntax : Processor

The function Processor returns the type of processor in the computer on which the program is currently running.

0 = 68000

1 = 68010

2 = 68020

3 = 68030

4 = 68040

1.7 ENVIRONLIB

Statement: cr_vbr

Modes :

Syntax : cr_vbr

1.8 ENVIRONLIB

Statement: ExecVersion

Modes :

Syntax : ExecVersion

The function ExecVersion returns the relevant information about the system the program is running on.

33 = 1.2

34 = 1.3

36 = 2.0

1.9 ENVIRONLIB

Statement: WBExtViewMode

Modes :

Syntax : WBExtViewMode

See Description of WBWith.

1.10 ENVIRONLIB

ENVIRONLIB

Overview

Command Index

cr_vbr

ExecVersion

Processor

WBDepth

WBExtViewMode

WBHeight

WBViewMode

WBWidth
