

Sheet1

- \*---A macro to print only every other specified number of columns. The macro prompts the user for the number of columns to skip. Example: To print only every 4th column, answer 3 to the "How many columns to skip ? " prompt.
- \*---Use the /Range Name Label Right {End} {Down} <ENTER> to define the range names in this column (starts with the \Z macro name).
- \*---Hold the <ALT> key and press <Z> to activate the macro  
THIS MACRO AUTOMATICALLY DETECTS THE LOTUS 1-2-3 RELEASE  
IT WILL WORK IN LOTUS 2/2.01/2.2/2.3/3/3.1/3.1+/123W

```
\Z  
PRINTALT  
form206  
!  
!  
!  
!  
!  
!  
!  
!  
colshide206  
!  
prints206  
!  
!  
temp1206  
skip206  
counter1206  
counter2206  
copies206  
here1206  
key206  
err206  
!  
!  
rel206  
!  
loc206
```

```
{BREAKON}
{let rel206,@INFO("release")}~{recalc loc206}{recalc form206}

{WINDOWSOFF}{PANELOFF}/RNCRANGE TO PRINT?~/RNDRANGE TO PRINT?~/RNC{PANELON}{WINDOWSON}RAN
{panelon}{getlabel "How many columns to skip ? ",skip206}~
{LET TEMP1206,@STRING(@MOD(@COLS(RANGE TO PRINT?),(@VALUE(SKIP206)+1)),0)}~
{getnumber "No. of copies ? ",copies206}~{paneloff}{recalc colshide206}{recalc prints206}
{FOR COUNTER1206,1,(@COLS(RANGE TO PRINT?)-@MOD(@COLS(RANGE TO PRINT?),(@VALUE(SKIP206)+1)))/(@
{FOR COUNTER2206,1,COPIES206,1,PRINTS206}{ESC 10}
/WCDRANGE TO PRINT?~{GOTO}{HERE1206}~/RNDRANGE TO PRINT?~{esc 10}{CALC}
```

```
{ONERROR ERR206}{IF @MOD(@COLS(RANGE TO PRINT?),@VALUE(SKIP206)+1)>0}/PPCRRRANGE TO PRINT?~R{L
{IF @MOD(@COLS(RANGE TO PRINT?),@VALUE(SKIP206)+1)=0}/PPCRRRANGE TO PRINT?~R{LEFT}{RIGHT}~AGPQ
```

0  
3

\$B:\$A\$1

```
~
{if @LEFT(REL206,1)<>"@"}{beep}Turn on your printer and/or press any key to continue...{get key206}{ESC}/PRQ/wcda1..iv
{if @LEFT(REL206,1)="@"}{beep}Turn on your printer and/or press any key to continue...{get key206}{ESC}/wcda1..iv1~
```

3.00.00

coord

Sheet1