

EarthSun 2.5 - January 20th, 1994

What is EarthSun?

Installing EarthSun

Configuring EarthSun

Changing the icon's title

Current Date/Time window

EarthSun and Screen Savers

Troubleshooting

Acknowledgements

Calling all icon artists!

Author Information

Other related programs

Registering EarthSun

EarthSun is a MicroSoft Windows 3.x program that displays the current sunlit-side of the Earth in an icon. You can specify the icon's title to display the current time and/or date in **many** different formats, as well as changing the icon's background color and rotation direction. **EarthSun** even adjusts **automatically** for daylight savings/summer time for users in the United States, the UK, and Europe.

Simply use the Program Manager to create a New Program Icon in the group of your choice and set the *Working Directory* to the subdirectory where you installed the rest of the program files. You may place the files in the subdirectory of your choice, but the software **must** be able to find it's EARTHSUN.INI file there.

If it cannot find the .INI file, then the **About** box will be displayed *each and every time* you start **EarthSun**. See the section [Troubleshooting](#) for more information.

I also recommend placing the Program Icon in the **Startup** group so it loads every time you start Windows.

If you don't already have the file **BWCC.DLL**, make sure you copy it to your Windows system subdirectory and erase any other older copies of it. See the file BWCC.TXT for more information.

Before you can use **EarthSun**, you need to tell it where you live and how to adjust for daylight savings time. You can also select **many** different options as well. Select the following links for more information:

[Setting your Time Zone](#)

[Adjusting for Daylight Savings/Summer Time](#)

[Animating the EarthSun icon](#)

[Background Colors](#)

Once you have set all the above options, you will probably want to have a look at how you can [change the icon's title](#).

EarthSun must know the **time zone** in which you live to display the icon properly. The default is the Eastern Standard Time time zone, which is valid for cities in the United States such as New York City, Boston and Miami. If you live in another time zone, you must select it yourself.

When you first run **EarthSun**, the program's **About** box appears. Here you'll find a list box containing all of the world's time zones. Simply select the one in which you live.

There is a check box if you want the **Daylight Savings Time** (Summer Time) adjustment applied or not. Check this box if your area observes Daylight Savings Time. Just below this, there are four radio buttons to determine which set of summer-time dates you wish to use. If you select *Manual*, the daylight savings time adjustment will be applied **regardless** of today's date. This means you must change the above check box twice a year when the time changes. You may need to select this option if your region is not listed below. Tables that list the daylight savings time start/stop dates for the other radio buttons follow below. If you select one of these, the daylight savings time adjustment will be applied or not-applied **automatically** based on today's date. All daylight savings time adjustments subtract 1 hour from the current time.

United States:

1994 - Start: April 3rd	End: October 30th
1995 - Start: April 2nd	End: October 29th
1996 - Start: April 7th	End: October 27th
1997 - Start: April 6th	End: October 26th

UK:

1994 - Start: March 27th	End: October 23rd
1995 - Start: March 26th	End: October 22nd
1996 - Start: March 24th	End: October 27th
1997 - Start: March 23rd	End: October 26th

Europe:

1994 - Start: March 27th	End: September 25th
1995 - Start: March 26th	End: September 24th
1996 - Start: March 24th	End: September 22nd
1997 - Start: March 23rd	End: September 28th

If you live in one of these regions and the above dates are incorrect, OR if you live in another region not listed above, please contact me with the correct dates so I can update my software.

You can also select an **update interval** for the **EarthSun** icon. The default is *Real-Time*, which shows the current sunlit side of the Earth. Other values are available to **animate** the icon, displaying a new icon once every update interval. The values you may choose from are once every second, once every five seconds or once every ten seconds.

You can also have the icon **rotate** in the normal forward direction, or in reverse. Just click on the appropriate radio button.

You can change the **title** beneath the icon to whatever you like. More importantly, you can have the time and/or date displayed here as well.

The **About** box has the default icon title set to `~1~a ~w ~m ~d~o`, which is a special "code" to display the current time in 12-hour format, have either "am" or "pm" displayed after the time, show the day-of-the-week in 3 letters, show the month in 3 letters, and show the day-of-the-month followed by "st", "rd", etc. For example, "9:05pm Thu Jan 20th". Note how you can add spaces between the various options to cause them to "wrap" down to the next icon title line, if desired.

If you prefer, you can change the title to be just a simple word or two, like "Earth" or "Earth's Sunlit Side". This may be necessary to work with some screen savers.

All the available options are listed below:

- `~1` =12-hour format
- `~2` =24-hour format
- `~a` ="am" or "pm"
- `~A` = "AM" or "PM"
- `~p` = "a" or "p"
- `~P` = "A" or "P"
- `~w` = Weekday name as "Mon", "Tue", etc.
- `~W` = Weekday name as "Monday", "Tuesday", etc.
- `~m` = Month name as "Jan", "Feb", etc.
- `~M` = Month name as "January", "February", etc.
- `~h` = Month number (1-12)
- `~d` = Day of the month number (1-31)
- `~y` =Year as "94", etc. (Year without the century)
- `~Y` = Year as "1994", etc. (Year with the century)
- `~o` =Ordinal suffix of "Day of the month" as "st", "nd", "rd", "th", etc. (as in 1st, 2nd, 3rd, 4th, etc.)

Example icon titles:

Title:	Displays as:
<code>"~2 ~W ~m ~d~o"</code>	21:05 Thursday Jan 20th
<code>"~1~A"</code>	9:05PM
<code>"~W ~M ~d ~Y"</code>	Thursday January 20 1994
<code>"~y.~h.~d"</code>	94.01.20
<code>"Earth"</code>	Earth

Feel free to experiment with different combinations to suit your taste.

You can select one of many different **background colors**. The default is black, but you can select white or a shade of gray if you prefer. The "transparent" color is available, but is only partially supported in this version.

When you select the **Current Date/Time** window, the current date, time and icon are displayed in a small window and updated once a second.

Press the Minimize button in the upper right corner to shrink the window back to an icon.

In the default configuration, **EarthSun** displays a clock beneath the icon. Since this will automatically update the icon's title once per minute, this may cause some **screen savers**, which can sense such activity, to never activate. A simple solution is to change the *Icon Title* field in the **About** box to some simple word or words, such as "Earth" or "Earth's Sunlit Side". You will not be able to use **EarthSun**'s clock feature (although you could still display the date), but your screen savers should work again.

Look for GREDS_{Pxx}.ZIP, a Windows icon that shows the current position of Jupiter's Great Red Spot and the four Galilean Satellites, and MARSIC_{xx}.ZIP, a Windows icon that shows the current view of the planet Mars. Both are available at the Internet FTP site oak.oakland.edu and its mirrors, and at the Software Creations BBS (508) 365-2359 (2400,N,8,1), both in the USA. All users receive the shareware versions of these programs when they register. The current versions are **GREDS_{P35}.ZIP** and **MARSIC₂₅.ZIP**.

Print out the file ORDER.FRM to get a quick order form for registering **EarthSun**. This shareware version is not cripple-ware, nag-ware or free-ware, although it will remind you every 5 times to register until the evaluation period expires. When you do register, you will receive the latest executable version that allows **UNLIMITED** use of the program with no reminder box and no expiration.

All future versions/upgrades of this program are **FREE** to registered users. When a new shareware version becomes available, just download it and copy the new EARTHSUN.EXE file to the registered version's subdirectory. It's that simple!

The cost of the diskette and the mailing charges are all included in the **US \$10** registration fee. Personal checks, money orders and American Express traveler's checks are all accepted (sorry, I do not yet accept credit card orders). You also receive the full Borland C++ 3.1 source code and Windows resource files used to make this program as well. The source code for each future version will be available **free** for registered users.

If you find **EarthSun** useful, please upload it to other bulletin boards and/or Internet FTP sites so other people can see the sunny side of our planet!

If you have improved the existing **icons**, or have created any new icons to improve the animation, please send them to me and I might include them, along with your name and my thanks, in future versions. If I use your contributions, you will receive the latest registered version **free**.

If you get the **About** box each and every time you start the program, make **sure** you have the program icon's *Working Directory* set to the directory where you have the EARTHSUN.EXE file. This allows the program to properly find its .INI file. Make sure your EARTHSUN.INI file is in the same subdirectory as the EARTHSUN.EXE file; if it isn't, move it to that subdirectory. This is the recommended way to keep all of **EarthSun**'s files together.

If you prefer, you may also set the *Working Directory* to your Windows subdirectory explicitly, or just leave it blank to have it default to your Windows subdirectory.

Finally, make sure the .INI file is marked as read/write (this is the default); do **NOT** mark this file as read-only.

Many thanks go to **Peter Hayes** (peter.hayes@uk.cray.com) in England for the information he supplied to me on the daylight savings time issues in the UK and Europe.

Any suggestions, bugs, ideas, complaints? Let me know what you think of this program so I can improve it! Please include the version number you are using in all correspondence; this is version 2.5.

Mail Address:

W. Scott Thoman
41 Lee Road
Dryden, NY 13053
USA

Internet E-Mail Address:

thoman@law.mail.cornell.edu

Thank you for using EarthSun!
