

WINAPI Cross Reference and Window.h Constant values

Alphabetical lists of API by first letter:

A, B, C, D, E, F, G, H, I, K, L, M, N, O, P, Q, R, S, T, U, V, W, X, Y

Alphabetical lists of API by DLL:

KERNEL.EXE
SYSTEM.EXE
GDI.EXE
USER.EXE
COMM.DRV
SOUND.DRV
MOUSE.DRV
KEYBOARD.DRV

Alphabetical lists of Constants by first letter:

A, B, C, D, E, F, G, H, I, K, L, M, N, O, P, Q, R, S, T, V, W

KERNEL.EXE

Function Name	DLL Name
---------------	----------

ACCESSRESOURCE.....	KERNEL.EXE
ADDATOM.....	KERNEL.EXE
ALLOCALIAS.....	KERNEL.EXE
ALLOCCSTODSALIAS.....	KERNEL.EXE
ALLOCDSTOCSALIAS.....	KERNEL.EXE
ALLOCRESOURCE.....	KERNEL.EXE
ALLOCSELECTOR.....	KERNEL.EXE
ALLOCSELECTORARRAY.....	KERNEL.EXE
CALLPROCINSTANCE.....	KERNEL.EXE
CATCH.....	KERNEL.EXE
CVWBREAK.....	KERNEL.EXE
DEBUGBREAK.....	KERNEL.EXE
DEFINEHANDLETABLE.....	KERNEL.EXE
DELETEATOM.....	KERNEL.EXE
DELETEPATHNAME.....	KERNEL.EXE
DIRECTEDYIELD.....	KERNEL.EXE
DIRECTRESALLOC.....	KERNEL.EXE
DISABLEDOS.....	KERNEL.EXE
DISABLEKERNEL.....	KERNEL.EXE
DOS3CALL.....	KERNEL.EXE
DOSIGNAL.....	KERNEL.EXE
EMSCOPY.....	KERNEL.EXE
ENABLEDOS.....	KERNEL.EXE
ENABLEKERNEL.....	KERNEL.EXE
EXITKERNEL.....	KERNEL.EXE
FATALAPPEXIT.....	KERNEL.EXE
FATALEXIT.....	KERNEL.EXE
FILECDR.....	KERNEL.EXE
FINDATOM.....	KERNEL.EXE
FINDRESOURCE.....	KERNEL.EXE
FREELIBRARY.....	KERNEL.EXE
FREEMODULE.....	KERNEL.EXE
FREEPROCINSTANCE.....	KERNEL.EXE
FREERESOURCE.....	KERNEL.EXE
FREESELECTOR.....	KERNEL.EXE
GETATOMHANDLE.....	KERNEL.EXE
GETATOMNAME.....	KERNEL.EXE
GETCODEHANDLE.....	KERNEL.EXE
GETCODEINFO.....	KERNEL.EXE
GETCURPID.....	KERNEL.EXE
GETCURRENTPDB.....	KERNEL.EXE
GETCURRENTTASK.....	KERNEL.EXE
GETDOSENVIRONMENT.....	KERNEL.EXE
GETDRIVETYPE.....	KERNEL.EXE
GETEXEPTR.....	KERNEL.EXE
GETEXEVERSION.....	KERNEL.EXE
GETEXPWINVER.....	KERNEL.EXE
GETFREESPACE.....	KERNEL.EXE
GETHEAPSPACES.....	KERNEL.EXE
GETINSTANCEDATA.....	KERNEL.EXE
GETLASTDISKCHANGE.....	KERNEL.EXE
GETLPERRMODE.....	KERNEL.EXE
GETMODULEFILENAME.....	KERNEL.EXE

GETMODULEHANDLE.....KERNEL.EXE
GETMODULEUSAGE.....KERNEL.EXE
GETNUMTASKS.....KERNEL.EXE
GETPRIVATEPROFILEINT.....KERNEL.EXE
GETPRIVATEPROFILESTRING.....KERNEL.EXE
GETPROCADDRESS.....KERNEL.EXE
GETPROFILEINT.....KERNEL.EXE
GETPROFILESTRING.....KERNEL.EXE
GETSELECTORBASE.....KERNEL.EXE
GETSELECTORLIMIT.....KERNEL.EXE
GETSYSTEMDIRECTORY.....KERNEL.EXE
GETTASKDS.....KERNEL.EXE
GETTASKQUEUE.....KERNEL.EXE
GETTASKQUEUEEDS.....KERNEL.EXE
GETTASKQUEUEES.....KERNEL.EXE
GETTEMPDRIVE.....KERNEL.EXE
GETTEMPFILENAME.....KERNEL.EXE
GETVERSION.....KERNEL.EXE
GETWINDOWS DIRECTORY.....KERNEL.EXE
GETWINFLAGS.....KERNEL.EXE
GLOBALALLOC.....KERNEL.EXE
GLOBALCOMPACT.....KERNEL.EXE
GLOBALDOSALLOC.....KERNEL.EXE
GLOBALDOSFREE.....KERNEL.EXE
GLOBALFIX.....KERNEL.EXE
GLOBALFLAGS.....KERNEL.EXE
GLOBALFREE.....KERNEL.EXE
GLOBALFREEALL.....KERNEL.EXE
GLOBALHANDLE.....KERNEL.EXE
GLOBALHANDLENORIP.....KERNEL.EXE
GLOBALLOCK.....KERNEL.EXE
GLOBALLRUNEWEST.....KERNEL.EXE
GLOBALLRUOLDEST.....KERNEL.EXE
GLOBALMASTERHANDLE.....KERNEL.EXE
GLOBALNOTIFY.....KERNEL.EXE
GLOBALPAGELOCK.....KERNEL.EXE
GLOBALPAGEUNLOCK.....KERNEL.EXE
GLOBALREALLOC.....KERNEL.EXE
GLOBALSIZE.....KERNEL.EXE
GLOBALUNFIX.....KERNEL.EXE
GLOBALUNLOCK.....KERNEL.EXE
GLOBALUNWIRE.....KERNEL.EXE
GLOBALWIRE.....KERNEL.EXE
INITATOMTABLE.....KERNEL.EXE
INITLIB.....KERNEL.EXE
INITTASK.....KERNEL.EXE
INITTASK1.....KERNEL.EXE
ISTASKLOCKED.....KERNEL.EXE
ISWINOLDAPTASK.....KERNEL.EXE
LIMITEMSPAGES.....KERNEL.EXE
LOADLIBRARY.....KERNEL.EXE
LOADMODULE.....KERNEL.EXE
LOADRESOURCE.....KERNEL.EXE
LOCALALLOC.....KERNEL.EXE
LOCALCOMPACT.....KERNEL.EXE
LOCALCOUNTFREE.....KERNEL.EXE
LOCALFLAGS.....KERNEL.EXE

LOCALFREE.....KERNEL.EXE
LOCALHANDLE.....KERNEL.EXE
LOCALHEAPSIZE.....KERNEL.EXE
LOCALINIT.....KERNEL.EXE
LOCALLOCK.....KERNEL.EXE
LOCALNOTIFY.....KERNEL.EXE
LOCALREALLOC.....KERNEL.EXE
LOCALSHRINK.....KERNEL.EXE
LOCALSIZE.....KERNEL.EXE
LOCALUNLOCK.....KERNEL.EXE
LOCKCURRENTTASK.....KERNEL.EXE
LOCKRESOURCE.....KERNEL.EXE
LOCKSEGMENT.....KERNEL.EXE
LONGPTRADD.....KERNEL.EXE
LSTRCAT.....KERNEL.EXE
LSTRCPY.....KERNEL.EXE
LSTRLEN.....KERNEL.EXE
MAKEPROCINSTANCE.....KERNEL.EXE
MEMORYFREED.....KERNEL.EXE
NETBIOSCALL.....KERNEL.EXE
NOHOOKDOSCALL.....KERNEL.EXE
OLDYIELD.....KERNEL.EXE
OPENFILE.....KERNEL.EXE
OPENPATHNAME.....KERNEL.EXE
OUTPUTDEBUGSTRING.....KERNEL.EXE
PATCHCODEHANDLE.....KERNEL.EXE
POSTEVENT.....KERNEL.EXE
REGISTERPTRACE.....KERNEL.EXE
REPLACEINST.....KERNEL.EXE
SELECTORACCESSRIGHTS.....KERNEL.EXE
SETERRORMODE.....KERNEL.EXE
SETHANDLECOUNT.....KERNEL.EXE
SETPRIORITY.....KERNEL.EXE
SETRESOURCEHANDLER.....KERNEL.EXE
SETSELECTORBASE.....KERNEL.EXE
SETSELECTORLIMIT.....KERNEL.EXE
SETSIGHANDLER.....KERNEL.EXE
SETSWAPAREASIZE.....KERNEL.EXE
SETTASKQUEUE.....KERNEL.EXE
SETTASKSIGNALPROC.....KERNEL.EXE
SIZEOFRESOURCE.....KERNEL.EXE
SWAPRECORDING.....KERNEL.EXE
SWITCHSTACKBACK.....KERNEL.EXE
SWITCHSTACKTO.....KERNEL.EXE
THROW.....KERNEL.EXE
UNDEFDYNLINK.....KERNEL.EXE
UNLOCKSEGMENT.....KERNEL.EXE
VALIDATECODESEGMENTS.....KERNEL.EXE
VALIDATEFREESPACES.....KERNEL.EXE
WAITEVENT.....KERNEL.EXE
WINEXEC.....KERNEL.EXE
WINOLDAPCALL.....KERNEL.EXE
WRITEPRIVATEPROFILESTRING.....KERNEL.EXE
WRITEPROFILESTRING.....KERNEL.EXE
YIELD.....KERNEL.EXE

SYSTEM.EXE

Function Name	DLL Name
CREATESYSTEMTIMER.....	SYSTEM.EXE
DISABLESYSTEMTIMERS.....	SYSTEM.EXE
ENABLESYSTEMTIMERS.....	SYSTEM.EXE
GET80X87SAVESIZE.....	SYSTEM.EXE
GETSYSTEMMSECCOUNT.....	SYSTEM.EXE
INQUIRESYSTEM.....	SYSTEM.EXE
KILLSYSTEMTIMER.....	SYSTEM.EXE
RESTORE80X87STATE.....	SYSTEM.EXE
SAVE80X87STATE.....	SYSTEM.EXE

GDI.EXE

Function Name	DLL Name
---------------	----------

ADDFONTRESOURCE.....	GDI.EXE
ANIMATEPALETTE.....	GDI.EXE
ARC.....	GDI.EXE
BITBLT.....	GDI.EXE
BITMAPBITS.....	GDI.EXE
CHORD.....	GDI.EXE
CLOSEJOB.....	GDI.EXE
CLOSEMETAFILE.....	GDI.EXE
COMBINERGN.....	GDI.EXE
COMPATIBLEBITMAP.....	GDI.EXE
COPY.....	GDI.EXE
COPYMETAFILE.....	GDI.EXE
CREATEBITMAP.....	GDI.EXE
CREATEBITMAPINDIRECT.....	GDI.EXE
CREATEBRUSHINDIRECT.....	GDI.EXE
CREATECOMPATIBLEBITMAP.....	GDI.EXE
CREATECOMPATIBLEDC.....	GDI.EXE
CREATEDC.....	GDI.EXE
CREATEDIBITMAP.....	GDI.EXE
CREATEDIBPATTERNBRUSH.....	GDI.EXE
CREATEDISCARDABLEBITMAP.....	GDI.EXE
CREATEELLIPTICRGN.....	GDI.EXE
CREATEELLIPTICRGNINDIRECT.....	GDI.EXE
CREATEFONT.....	GDI.EXE
CREATEFONTINDIRECT.....	GDI.EXE
CREATEHATCHBRUSH.....	GDI.EXE
CREATEIC.....	GDI.EXE
CREATEMETAFILE.....	GDI.EXE
CREATEPALETTE.....	GDI.EXE
CREATEPATTERNBRUSH.....	GDI.EXE
CREATEPEN.....	GDI.EXE
CREATEPENINDIRECT.....	GDI.EXE
CREATEPOLYGONRGN.....	GDI.EXE
CREATEPOLYPOLYGONRGN.....	GDI.EXE
CREATEPQ.....	GDI.EXE
CREATEREALBITMAP.....	GDI.EXE
CREATEREALBITMAPINDIRECT.....	GDI.EXE
CREATERECTRGN.....	GDI.EXE
CREATERECTRGNINDIRECT.....	GDI.EXE
CREATEROUNDRECTRGN.....	GDI.EXE
CREATESOLIDBRUSH.....	GDI.EXE
CREATEUSERBITMAP.....	GDI.EXE
CREATEUSERDISCARDABLEBITMAP...	GDI.EXE
DELETEABOVELINEFONTS.....	GDI.EXE
DELETEDC.....	GDI.EXE
DELETEJOB.....	GDI.EXE
DELETMETAFILE.....	GDI.EXE
DELETEOBJECT.....	GDI.EXE
DELETEPQ.....	GDI.EXE
DEVICECOLORMATCH.....	GDI.EXE
DMBITBLT.....	GDI.EXE
DMCOLORINFO.....	GDI.EXE
DMENUMDFONTS.....	GDI.EXE

DMENUMOBJ.....GDI.EXE
DMOUTPUT.....GDI.EXE
DMPIXEL.....GDI.EXE
DMREALIZEOBJECT.....GDI.EXE
DMSCANLR.....GDI.EXE
DMSTRBLT.....GDI.EXE
DMTRANPOSE.....GDI.EXE
DPTOLP.....GDI.EXE
DPXLATE.....GDI.EXE
ELLIPSE.....GDI.EXE
ENDSPOOLPAGE.....GDI.EXE
ENUMCALLBACK.....GDI.EXE
ENUMFONTS.....GDI.EXE
ENUMMETAFILE.....GDI.EXE
ENUMOBJECTS.....GDI.EXE
EQUALRGN.....GDI.EXE
ESCAPE.....GDI.EXE
EXCLUDECLIPRECT.....GDI.EXE
EXCLUDEVISRECT.....GDI.EXE
EXTFLOODFILL.....GDI.EXE
EXTRACTPQ.....GDI.EXE
EXTTEXTOUT.....GDI.EXE
FASTWINDOWFRAME.....GDI.EXE
FILLRGN.....GDI.EXE
FINALGDIINIT.....GDI.EXE
FLOODFILL.....GDI.EXE
FRAMERGN.....GDI.EXE
GDIINIT2.....GDI.EXE
GDIMOVEBITMAP.....GDI.EXE
GDIREALIZEPALETTE.....GDI.EXE
GDISELECTPALETTE.....GDI.EXE
GETASPECTRATIOFILTER.....GDI.EXE
GETBITMAPBITS.....GDI.EXE
GETBITMAPDIMENSION.....GDI.EXE
GETBKCOLOR.....GDI.EXE
GETBKMODE.....GDI.EXE
GETBRUSHORG.....GDI.EXE
GETCHARWIDTH.....GDI.EXE
GETCLIPBOX.....GDI.EXE
GETCLIPRGN.....GDI.EXE
GETCURLOGFONT.....GDI.EXE
GETCURRENTPOSITION.....GDI.EXE
GETDCORG.....GDI.EXE
GETDCSTATE.....GDI.EXE
GETDEVICECAPS.....GDI.EXE
GETDIBITS.....GDI.EXE
GETENVIRONMENT.....GDI.EXE
GETMAPMODE.....GDI.EXE
GETMETAFILE.....GDI.EXE
GETMETAFILEBITS.....GDI.EXE
GETNEARESTCOLOR.....GDI.EXE
GETNEARESTPALETTEINDEX.....GDI.EXE
GETOBJECT.....GDI.EXE
GETPALETTEENTRIES.....GDI.EXE
GETPHYSICALFONTHANDLE.....GDI.EXE
GETPIXEL.....GDI.EXE
GETPOLYFILLMODE.....GDI.EXE

GETRELABS.....GDI.EXE
GETTRGNBOX.....GDI.EXE
GETROP2.....GDI.EXE
GETSPOOLJOB.....GDI.EXE
GETSTOCKOBJECT.....GDI.EXE
GETSTRETCHBLTMODE.....GDI.EXE
GETSYSTEMPALETTEENTRIES.....GDI.EXE
GETSYSTEMPALETTEUSE.....GDI.EXE
GETTEXTALIGN.....GDI.EXE
GETTEXTCHARACTEREXTRA.....GDI.EXE
GETTEXTCOLOR.....GDI.EXE
GETTEXTTEXTENT.....GDI.EXE
GETTEXTFACE.....GDI.EXE
GETTEXTMETRICS.....GDI.EXE
GETVIEWPORTEXT.....GDI.EXE
GETVIEWPORTORG.....GDI.EXE
GETWINDOWEXT.....GDI.EXE
GETWINDOWORG.....GDI.EXE
GSV.....GDI.EXE
INQUIREVISRGN.....GDI.EXE
INSERTPQ.....GDI.EXE
INTERNALCREATEDC.....GDI.EXE
INTERSECTCLIPRECT.....GDI.EXE
INTERSECTVISRECT.....GDI.EXE
INVERTRGN.....GDI.EXE
ISDCCURRENTPALETTE.....GDI.EXE
ISDCDIRTY.....GDI.EXE
ISVALIDMETAFILE.....GDI.EXE
LINEDDA.....GDI.EXE
LINETO.....GDI.EXE
LPTODP.....GDI.EXE
LVBUNION.....GDI.EXE
MFDRAWTEXT.....GDI.EXE
MINPQ.....GDI.EXE
MOVETO.....GDI.EXE
MULDIV.....GDI.EXE
OFFSETCLIPRGN.....GDI.EXE
OFFSETORG.....GDI.EXE
OFFSETRGN.....GDI.EXE
OFFSETVIEWPORTORG.....GDI.EXE
OFFSETVISRGN.....GDI.EXE
OFFSETWINDOWORG.....GDI.EXE
OPENJOB.....GDI.EXE
PAINTRGN.....GDI.EXE
PATBLT.....GDI.EXE
PIE.....GDI.EXE
PIXTOLINE.....GDI.EXE
PLAYMETAFILE.....GDI.EXE
PLAYMETAFILERECORD.....GDI.EXE
POLYGON.....GDI.EXE
POLYLINE.....GDI.EXE
POLYPOLYGON.....GDI.EXE
PTINREGION.....GDI.EXE
PTVISIBLE.....GDI.EXE
QUERYABORT.....GDI.EXE
QUERYJOB.....GDI.EXE
RCOS.....GDI.EXE

REALIZEDEFAULTPALETTE.....GDI.EXE
RECTANGLE.....GDI.EXE
RECTINREGION.....GDI.EXE
RECTSTUFF.....GDI.EXE
RECTVISIBLE.....GDI.EXE
REMOVEFONTRESOURCE.....GDI.EXE
RESIZEPALETTE.....GDI.EXE
RESTOREDC.....GDI.EXE
RESTOREVISRGN.....GDI.EXE
RESURRECTION.....GDI.EXE
ROUNDRECT.....GDI.EXE
RSIN.....GDI.EXE
SAVEDC.....GDI.EXE
SAVEVISRGN.....GDI.EXE
SCALEEXT.....GDI.EXE
SCALEVIEWPORTEXT.....GDI.EXE
SCALEWINDOWEXT.....GDI.EXE
SCANLR.....GDI.EXE
SELECTCLIPRGN.....GDI.EXE
SELECTOBJECT.....GDI.EXE
SELECTVISRGN.....GDI.EXE
SETBITMAPBITS.....GDI.EXE
SETBITMAPDIMENSION.....GDI.EXE
SETBKCOLOR.....GDI.EXE
SETBKMODE.....GDI.EXE
SETBRUSHORG.....GDI.EXE
SETDCORG.....GDI.EXE
SETDCSTATE.....GDI.EXE
SETDCSTATUS.....GDI.EXE
SETDIBITS.....GDI.EXE
SETDIBITSTODEVICE.....GDI.EXE
SETENVIRONMENT.....GDI.EXE
SETMAPMODE.....GDI.EXE
SETMAPPERFLAGS.....GDI.EXE
SETMETAFILEBITS.....GDI.EXE
SETPALETTEENTRIES.....GDI.EXE
SETPIXEL.....GDI.EXE
SETPOLYFILLMODE.....GDI.EXE
SETRECTRGN.....GDI.EXE
SETRELABS.....GDI.EXE
SETROP2.....GDI.EXE
SETSTRETCHBLTMODE.....GDI.EXE
SETSYSTEMPALETTEUSE.....GDI.EXE
SETTEXTALIGN.....GDI.EXE
SETTEXTCHARACTEREXTRA.....GDI.EXE
SETTEXTCOLOR.....GDI.EXE
SETTEXTJUSTIFICATION.....GDI.EXE
SETVIEWPORTEXT.....GDI.EXE
SETVIEWPORTORG.....GDI.EXE
SETWINDOWEXT.....GDI.EXE
SETWINDOWORG.....GDI.EXE
SETWINVIEWEXT.....GDI.EXE
SHRINKGDIHEAP.....GDI.EXE
SIZEPQ.....GDI.EXE
STARTSPOOLPAGE.....GDI.EXE
STRETCHBLT.....GDI.EXE
STRETCHDIBITS.....GDI.EXE

STUFFINREGION.....GDI.EXE
STUFFVISIBLE.....GDI.EXE
TEXTOUT.....GDI.EXE
UNREALIZEOBJECT.....GDI.EXE
UPDATECOLORS.....GDI.EXE
WORDSET.....GDI.EXE
WRITEDIALOG.....GDI.EXE
WRITESPOOL.....GDI.EXE

USER.EXE

Function Name	DLL Name
---------------	----------

ADJUSTWINDOWRECT.....	USER.EXE
ADJUSTWINDOWRECTEX.....	USER.EXE
ANSILOWER.....	USER.EXE
ANSILOWERBUFF.....	USER.EXE
ANSINEXT.....	USER.EXE
ANSIPREV.....	USER.EXE
ANSIUPPER.....	USER.EXE
ANSIUPPERBUFF.....	USER.EXE
ANYPOPUP.....	USER.EXE
APPENDMENU.....	USER.EXE
ARRANGEICONICWINDOWS.....	USER.EXE
BEGINDEFERWINDOWPOS.....	USER.EXE
BEGINPAINT.....	USER.EXE
BRINGWINDOWTOTOP.....	USER.EXE
BROADCASTMESSAGE.....	USER.EXE
BUILDCOMMDCB.....	USER.EXE
BUTTONWNDPROC.....	USER.EXE
CALCCHILDSCROLL.....	USER.EXE
CALLMSGFILTER.....	USER.EXE
CALLWINDOWPROC.....	USER.EXE
CARETBLINKPROC.....	USER.EXE
CASCADECHILDWINDOWS.....	USER.EXE
CHANGECLIPBOARDCHAIN.....	USER.EXE
CHANGEMENU.....	USER.EXE
CHECKDLGBUTTON.....	USER.EXE
CHECKMENUITEM.....	USER.EXE
CHECKRADIOBUTTON.....	USER.EXE
CHILDWINDOWFROMPOINT.....	USER.EXE
CLEARCOMMBREAK.....	USER.EXE
CLIENTTOSCREEN.....	USER.EXE
CLIPCURSOR.....	USER.EXE
CLOSECLIPBOARD.....	USER.EXE
CLOSECOMM.....	USER.EXE
CLOSEWINDOW.....	USER.EXE
COMBOBOXCTLWNDPROC.....	USER.EXE
COMPUPDATERECT.....	USER.EXE
COMPUPDATERGN.....	USER.EXE
CONTROLPANELINFO.....	USER.EXE
CONTSCROLL.....	USER.EXE
COPYRECT.....	USER.EXE
COUNTCLIPBOARDFORMATS.....	USER.EXE
CREATECARET.....	USER.EXE
CREATECURSOR.....	USER.EXE
CREATECURSORICONINDIRECT.....	USER.EXE
CREATEDIALOG.....	USER.EXE
CREATEDIALOGINDIRECT.....	USER.EXE
CREATEDIALOGINDIRECTPARAM.....	USER.EXE
CREATEDIALOGPARAM.....	USER.EXE
CREATEICON.....	USER.EXE
CREATEMENU.....	USER.EXE
CREATEPOPUPMENU.....	USER.EXE
CREATEWINDOW.....	USER.EXE
CREATEWINDOWEX.....	USER.EXE

DEFDLGPROC.....USER.EXE
DEFERWINDOWPOS.....USER.EXE
DEFFRAMEPROC.....USER.EXE
DEFHOOKPROC.....USER.EXE
DEFMDICHILDPROC.....USER.EXE
DEFWINDOWPROC.....USER.EXE
DELETEMENU.....USER.EXE
DESKTOPWNDPROC.....USER.EXE
DESTROYCARET.....USER.EXE
DESTROYCURSOR.....USER.EXE
DESTROYICON.....USER.EXE
DESTROYMENU.....USER.EXE
DESTROYWINDOW.....USER.EXE
DIALOGBOX.....USER.EXE
DIALOGBOXINDIRECT.....USER.EXE
DIALOGBOXINDIRECTPARAM.....USER.EXE
DIALOGBOXPARAM.....USER.EXE
DISABLEOEMLAYER.....USER.EXE
DISPATCHMESSAGE.....USER.EXE
DLGDIRLIST.....USER.EXE
DLGDIRLISTCOMBOBOX.....USER.EXE
DLGDIRSELECT.....USER.EXE
DLGDIRSELECTCOMBOBOX.....USER.EXE
DRAGDETECT.....USER.EXE
DRAGOBJECT.....USER.EXE
DRAWFOCUSRECT.....USER.EXE
DRAWICON.....USER.EXE
DRAWMENUBAR.....USER.EXE
DRAWTEXT.....USER.EXE
DUMPICON.....USER.EXE
EDITWNDPROC.....USER.EXE
EMPTYCLIPBOARD.....USER.EXE
ENABLEHARDWAREINPUT.....USER.EXE
ENABLEMENUITEM.....USER.EXE
ENABLEOEMLAYER.....USER.EXE
ENABLEWINDOW.....USER.EXE
ENDDEFERWINDOWPOS.....USER.EXE
ENDDIALOG.....USER.EXE
ENDMENU.....USER.EXE
ENDPAINT.....USER.EXE
ENUMCHILDWINDOWS.....USER.EXE
ENUMCLIPBOARDFORMATS.....USER.EXE
ENUMPROPS.....USER.EXE
ENUMTASKWINDOWS.....USER.EXE
ENUMWINDOWS.....USER.EXE
EQUALRECT.....USER.EXE
ESCAPECOMMFUNCTION.....USER.EXE
EXCLUDEUPDATERGN.....USER.EXE
EXITWINDOWS.....USER.EXE
FARCALLNETDRIVER.....USER.EXE
FILEPORTDLGPROC.....USER.EXE
FILLRECT.....USER.EXE
FILLWINDOW.....USER.EXE
FINALUSERINIT.....USER.EXE
FINDWINDOW.....USER.EXE
FLASHWINDOW.....USER.EXE
FLUSHCOMM.....USER.EXE

FRAMERECT.....USER.EXE
GETACTIVIEWINDOW.....USER.EXE
GETASYNCKEYSTATE.....USER.EXE
GETCAPTURE.....USER.EXE
GETCARETBLINKTIME.....USER.EXE
GETCARETPOS.....USER.EXE
GETCLASSINFO.....USER.EXE
GETCLASSLONG.....USER.EXE
GETCLASSNAME.....USER.EXE
GETCLASSWORD.....USER.EXE
GETCLIENTRECT.....USER.EXE
GETCLIPBOARDATA.....USER.EXE
GETCLIPBOARDFORMATNAME.....USER.EXE
GETCLIPBOARDOWNER.....USER.EXE
GETCLIPBOARDVIEWER.....USER.EXE
GETCOMMERROR.....USER.EXE
GETCOMMEVENTMASK.....USER.EXE
GETCOMMSTATE.....USER.EXE
GETCONTROLBRUSH.....USER.EXE
GETCURRENTTIME.....USER.EXE
GETCURSORPOS.....USER.EXE
GETDC.....USER.EXE
GETDESKTOPHWND.....USER.EXE
GETDESKTOPWINDOW.....USER.EXE
GETDIALOGBASEUNITS.....USER.EXE
GETDLGCTRLID.....USER.EXE
GETDLGITEM.....USER.EXE
GETDLGITEMINT.....USER.EXE
GETDLGITEMTEXT.....USER.EXE
GETDOUBLECLICKTIME.....USER.EXE
GETFILEPORTNAME.....USER.EXE
GETFOCUS.....USER.EXE
GETICONID.....USER.EXE
GETINPUTSTATE.....USER.EXE
GETINTERNALWINDOWPOS.....USER.EXE
GETKEYBOARDSTATE.....USER.EXE
GETKEYSTATE.....USER.EXE
GETLASTACTIVEPOPUP.....USER.EXE
GETMENU.....USER.EXE
GETMENUCHECKMARKDIMENSIONS...USER.EXE
GETMENUITEMCOUNT.....USER.EXE
GETMENUITEMID.....USER.EXE
GETMENUSTATE.....USER.EXE
GETMENUSTRING.....USER.EXE
GETMESSAGE.....USER.EXE
GETMESSAGE2.....USER.EXE
GETMESSAGEPOS.....USER.EXE
GETMESSAGE TIME.....USER.EXE
GETMOUSEEVENTPROC.....USER.EXE
GETNEXTDLGGROUPITEM.....USER.EXE
GETNEXTDLGTABITEM.....USER.EXE
GETNEXTQUEUEWINDOW.....USER.EXE
GETNEXTWINDOW.....USER.EXE
GETPARENT.....USER.EXE
GETPRIORITYCLIPBOARDFORMAT...USER.EXE
GETPROP.....USER.EXE
GETQUEUESTATUS.....USER.EXE

GETSCROLLPOS.....USER.EXE
GETSCROLLRANGE.....USER.EXE
GETSUBMENU.....USER.EXE
GETSYSCOLOR.....USER.EXE
GETSYSMODALWINDOW.....USER.EXE
GETSYSTEMMENU.....USER.EXE
GETSYSTEMMETRICS.....USER.EXE
GETTABBEDTEXTTEXTENT.....USER.EXE
GETTASKFROMHWND.....USER.EXE
GETTICKCOUNT.....USER.EXE
GETTIMERRESOLUTION.....USER.EXE
GETTOPWINDOW.....USER.EXE
GETUPDATERECT.....USER.EXE
GETUPDATERGN.....USER.EXE
GETWC2.....USER.EXE
GETWINDOW.....USER.EXE
GETWINDOWDC.....USER.EXE
GETWINDOWLONG.....USER.EXE
GETWINDOWRECT.....USER.EXE
GETWINDOWTASK.....USER.EXE
GETWINDOWTEXT.....USER.EXE
GETWINDOWTEXTLENGTH.....USER.EXE
GETWINDOWWORD.....USER.EXE
GLOBALADDATOM.....USER.EXE
GLOBALDELETEATOM.....USER.EXE
GLOBALFINDATOM.....USER.EXE
GLOBALGETATOMNAME.....USER.EXE
GRAYSTRING.....USER.EXE
HIDECARET.....USER.EXE
HILITEMENUITEM.....USER.EXE
ICONSIZE.....USER.EXE
INFLATERECT.....USER.EXE
INITAPP.....USER.EXE
INSENDMESSAGE.....USER.EXE
INSERTMENU.....USER.EXE
INTERSECTRECT.....USER.EXE
INVALIDATERECT.....USER.EXE
INVALIDATERGN.....USER.EXE
INVERTRECT.....USER.EXE
ISCHARALPHA.....USER.EXE
ISCHARALPHANUMERIC.....USER.EXE
ISCHARLOWER.....USER.EXE
ISCHARUPPER.....USER.EXE
ISCHILD.....USER.EXE
ISCLIPBOARDFORMATAVAILABLE....USER.EXE
ISDIALOGMESSAGE.....USER.EXE
ISDLGBUTTONCHECKED.....USER.EXE
ISICONIC.....USER.EXE
ISRECTEMPTY.....USER.EXE
ISTWOBYTECHARPREFIX.....USER.EXE
ISUSERIDLE.....USER.EXE
ISWINDOW.....USER.EXE
ISWINDOWENABLED.....USER.EXE
ISWINDOWVISIBLE.....USER.EXE
ISZOOMED.....USER.EXE
KILLSYSTEMTIMER.....USER.EXE
KILLTIMER.....USER.EXE

KILLTIMER2.....USER.EXE
LBOXCARETBLINKER.....USER.EXE
LBOXCTLWNDPROC.....USER.EXE
LOADACCELERATORS.....USER.EXE
LOADBITMAP.....USER.EXE
LOADCURSOR.....USER.EXE
LOADCURSORICONHANDLER.....USER.EXE
LOADDIBCURSORHANDLER.....USER.EXE
LOADDIBICONHANDLER.....USER.EXE
LOADICON.....USER.EXE
LOADICONHANDLER.....USER.EXE
LOADMENU.....USER.EXE
LOADMENUINDIRECT.....USER.EXE
LOADSTRING.....USER.EXE
LOCKMYTASK.....USER.EXE
LOOKUPMENUHANDLE.....USER.EXE
LSTRCMP.....USER.EXE
LSTRCMPI.....USER.EXE
MAPDIALOGRECT.....USER.EXE
MB_DLGPROC.....USER.EXE
MDICLIENTWNDPROC.....USER.EXE
MENUITEMSTATE.....USER.EXE
MENUWNDPROC.....USER.EXE
MESSAGEBEEP.....USER.EXE
MESSAGEBOX.....USER.EXE
MODIFYMENU.....USER.EXE
MOVEWINDOW.....USER.EXE
OFFSETRECT.....USER.EXE
OLDEXITWINDOWS.....USER.EXE
OPENCLIPBOARD.....USER.EXE
OPENCOMM.....USER.EXE
OPENICON.....USER.EXE
PAINTRECT.....USER.EXE
PEEKMESSAGE.....USER.EXE
POSTAPPMESSAGE.....USER.EXE
POSTMESSAGE.....USER.EXE
POSTMESSAGE2.....USER.EXE
POSTQUITMESSAGE.....USER.EXE
PTINRECT.....USER.EXE
READCOMM.....USER.EXE
REALIZEPALETTE.....USER.EXE
REGISTERCLASS.....USER.EXE
REGISTERCLIPBOARDFORMAT.....USER.EXE
REGISTERWINDOWMESSAGE.....USER.EXE
RELEASECAPTURE.....USER.EXE
RELEASEDC.....USER.EXE
REMOVEMENU.....USER.EXE
REMOVEPROP.....USER.EXE
REPAINTSCREEN.....USER.EXE
REPLYMESSAGE.....USER.EXE
SBWNDPROC.....USER.EXE
SCREENTOCLIENT.....USER.EXE
SCROLLCHILDREN.....USER.EXE
SCROLLDC.....USER.EXE
SCROLLWINDOW.....USER.EXE
SELECTPALETTE.....USER.EXE
SENDDLGITEMMESSAGE.....USER.EXE

SENDMESSAGE.....USER.EXE
SENDMESSAGE2.....USER.EXE
SETACTIVEWINDOW.....USER.EXE
SETCAPTURE.....USER.EXE
SETCARETBLINKTIME.....USER.EXE
SETCARETPOS.....USER.EXE
SETCLASSLONG.....USER.EXE
SETCLASSWORD.....USER.EXE
SETCLIPBOARDATA.....USER.EXE
SETCLIPBOARDVIEWER.....USER.EXE
SETCOMMBREAK.....USER.EXE
SETCOMMEVENTMASK.....USER.EXE
SETCOMMSTATE.....USER.EXE
SETCURSOR.....USER.EXE
SETCURSORPOS.....USER.EXE
SETDESKPATTERN.....USER.EXE
SETDESKWALLPAPER.....USER.EXE
SETDLGITEMINT.....USER.EXE
SETDLGITEMTEXT.....USER.EXE
SETDOUBLECLICKTIME.....USER.EXE
SETEVENTHOOK.....USER.EXE
SETFOCUS.....USER.EXE
SETGETKBDSTATE.....USER.EXE
SETGRIDGRANULARITY.....USER.EXE
SETINTERNALWINDOWPOS.....USER.EXE
SETKEYBOARDSTATE.....USER.EXE
SETMENU.....USER.EXE
SETMENUITEMBITMAPS.....USER.EXE
SETMESSAGEQUEUE.....USER.EXE
SETPARENT.....USER.EXE
SETPROP.....USER.EXE
SETRECT.....USER.EXE
SETRECTEMPTY.....USER.EXE
SETSCROLLPOS.....USER.EXE
SETSCROLLRANGE.....USER.EXE
SETSYSCOLORS.....USER.EXE
SETSYSMODALWINDOW.....USER.EXE
SETSYSTEMMENU.....USER.EXE
SETSYSTEMTIMER.....USER.EXE
SETTIMER.....USER.EXE
SETTIMER2.....USER.EXE
SETWC2.....USER.EXE
SETWINDOWLONG.....USER.EXE
SETWINDOWPOS.....USER.EXE
SETWINDOWSHOOK.....USER.EXE
SETWINDOWTEXT.....USER.EXE
SETWINDOWWORD.....USER.EXE
SHOWCARET.....USER.EXE
SHOWCURSOR.....USER.EXE
SHOWOWNEDPOPUPS.....USER.EXE
SHOWSCROLLBAR.....USER.EXE
SHOWWINDOW.....USER.EXE
SIGNALPROC.....USER.EXE
SNAPWINDOW.....USER.EXE
STATICWNDPROC.....USER.EXE
STRINGFUNC.....USER.EXE
SWAPMOUSEBUTTON.....USER.EXE

SWITCHTOTHISWINDOW.....USER.EXE
SWITCHWNDPROC.....USER.EXE
SYSERRORBOX.....USER.EXE
TABBEDTEXTOUT.....USER.EXE
TILECHILDWINDOWS.....USER.EXE
TITLEWNDPROC.....USER.EXE
TRACKPOPUPMENU.....USER.EXE
TRANSLATEACCELERATOR.....USER.EXE
TRANSLATEMDISYSACCEL.....USER.EXE
TRANSLATEMESSAGE.....USER.EXE
TRANSMITCOMMCHAR.....USER.EXE
UNGETCOMMCHAR.....USER.EXE
UNHOOKWINDOWSHOOK.....USER.EXE
UNIONRECT.....USER.EXE
UNREGISTERCLASS.....USER.EXE
UPDATEWINDOW.....USER.EXE
USERYIELD.....USER.EXE
VALIDATERECT.....USER.EXE
VALIDATERGN.....USER.EXE
WAITMESSAGE.....USER.EXE
WINDOWFROMPOINT.....USER.EXE
WINFARFRAME.....USER.EXE
WINHELP.....USER.EXE
WINOLDAPPHACKOMATIC.....USER.EXE
WNETADDCONNECTION.....USER.EXE
WNETBROWSEDIALOG.....USER.EXE
WNETCANCELCONNECTION.....USER.EXE
WNETCANCELJOB.....USER.EXE
WNETCLOSEJOB.....USER.EXE
WNETDEVICEMODE.....USER.EXE
WNETGETCAPS.....USER.EXE
WNETGETCONNECTION.....USER.EXE
WNETGETERROR.....USER.EXE
WNETGETERRORTEXT.....USER.EXE
WNETGETUSER.....USER.EXE
WNETHOLDJOB.....USER.EXE
WNETLOCKQUEUEDATA.....USER.EXE
WNETOPENJOB.....USER.EXE
WNETRELEASEJOB.....USER.EXE
WNETSETJOBCOPIES.....USER.EXE
WNETUNLOCKQUEUEDATA.....USER.EXE
WNETUNWATCHQUEUE.....USER.EXE
WNETWATCHQUEUE.....USER.EXE
WRITECOMM.....USER.EXE
WVSPRINTF.....USER.EXE
XCSTODS.....USER.EXE

COMM.DRV

Function Name	DLL Name
---------------	----------

CCLRBRK.....	COMM.DRV
CEVT.....	COMM.DRV
CEVTGET.....	COMM.DRV
CEXTFCN.....	COMM.DRV
CFLUSH.....	COMM.DRV
CSETBRK.....	COMM.DRV
CTX.....	COMM.DRV
GETDCB.....	COMM.DRV
INICOM.....	COMM.DRV
REACTIVATEOPENCOMMPORTS.....	COMM.DRV
RECCOM.....	COMM.DRV
SETCOM.....	COMM.DRV
SETQUE.....	COMM.DRV
SNDCOM.....	COMM.DRV
STACOM.....	COMM.DRV
SUSPENDOPENCOMMPORTS.....	COMM.DRV
TRMCOM.....	COMM.DRV

SOUND.DRV

Function Name	DLL Name
---------------	----------

CLOSESOUND.....	SOUND.DRV
COUNTVOICENOTES.....	SOUND.DRV
DOBEEP.....	SOUND.DRV
GETTHRESHOLDEVENT.....	SOUND.DRV
GETTHRESHOLDSTATUS.....	SOUND.DRV
MYOPENSOUND.....	SOUND.DRV
OPENSOUND.....	SOUND.DRV
SETSOUNDNOISE.....	SOUND.DRV
SETVOICEACCENT.....	SOUND.DRV
SETVOICEENVELOPE.....	SOUND.DRV
SETVOICENOTE.....	SOUND.DRV
SETVOICEQUEUE SIZE.....	SOUND.DRV
SETVOICESOUND.....	SOUND.DRV
SETVOICETHRESHOLD.....	SOUND.DRV
STARTSOUND.....	SOUND.DRV
STOPSOUND.....	SOUND.DRV
SYNCALLVOICES.....	SOUND.DRV
WAITSOUNDSTATE.....	SOUND.DRV

MOUSE.DRV

Function Name	DLL Name
DISABLE.....	MOUSE.DRV
ENABLE.....	MOUSE.DRV
INQUIRE.....	MOUSE.DRV
MOUSEGETINTVECT.....	MOUSE.DRV

KEYBOARD.DRV

Function Name	DLL Name
ANSITOOEM.....	KEYBOARD.DRV
ANSITOOEMBUFF.....	KEYBOARD.DRV
DISABLE.....	KEYBOARD.DRV
ENABLE.....	KEYBOARD.DRV
ENABLEKBSYSREQ.....	KEYBOARD.DRV
GETKBCODEPAGE.....	KEYBOARD.DRV
GETKEYBOARDTYPE.....	KEYBOARD.DRV
GETKEYNAMETEXT.....	KEYBOARD.DRV
GETTABLESEG.....	KEYBOARD.DRV
INQUIRE.....	KEYBOARD.DRV
MAPVIRTUALKEY.....	KEYBOARD.DRV
NEWTABLE.....	KEYBOARD.DRV
OEMKEYSCAN.....	KEYBOARD.DRV
OEMTOANSI.....	KEYBOARD.DRV
OEMTOANSIBUFF.....	KEYBOARD.DRV
SCREENSWITCHENABLE.....	KEYBOARD.DRV
SETSPED.....	KEYBOARD.DRV
TOASCII.....	KEYBOARD.DRV
VKKEYSCAN.....	KEYBOARD.DRV

A

Function Name	DLL Name
---------------	----------

ACCESSRESOURCE.....	KERNEL.EXE
ADDATOM.....	KERNEL.EXE
ADDFONTRESOURCE.....	GDI.EXE
ADJUSTWINDOWRECT.....	USER.EXE
ADJUSTWINDOWRECTEX.....	USER.EXE
ALLOCALIAS.....	KERNEL.EXE
ALLOCCSTODSALIAS.....	KERNEL.EXE
ALLOCDSTOCSALIAS.....	KERNEL.EXE
ALLOCRESOURCE.....	KERNEL.EXE
ALLOCSELECTOR.....	KERNEL.EXE
ALLOCSELECTORARRAY.....	KERNEL.EXE
ANIMATEPALETTE.....	GDI.EXE
ANSILOWER.....	USER.EXE
ANSILOWERBUFF.....	USER.EXE
ANSINEXT.....	USER.EXE
ANSIPREV.....	USER.EXE
ANSITOOEM.....	KEYBOARD.DRV
ANSITOOEMBUFF.....	KEYBOARD.DRV
ANSIUPPER.....	USER.EXE
ANSIUPPERBUFF.....	USER.EXE
ANYPOPUP.....	USER.EXE
APPENDMENU.....	USER.EXE
ARC.....	GDI.EXE
ARRANGEICONICWINDOWS.....	USER.EXE

B

Function Name	DLL Name
BEGINDEFERWINDOWPOS.....	USER.EXE
BEGINPAINT.....	USER.EXE
BITBLT.....	GDI.EXE
BITMAPBITS.....	GDI.EXE
BRINGWINDOWTOTOP.....	USER.EXE
BROADCASTMESSAGE.....	USER.EXE
BUILDCOMMDCB.....	USER.EXE
BUTTONWNDPROC.....	USER.EXE

C

Function Name DLL Name

CALCCHILDSCROLL.....	USER.EXE
CALLMSGFILTER.....	USER.EXE
CALLPROCINSTANCE.....	KERNEL.EXE
CALLWINDOWPROC.....	USER.EXE
CARETBLINKPROC.....	USER.EXE
CASCADECHILDWINDOWS.....	USER.EXE
CATCH.....	KERNEL.EXE
CCLRBRK.....	COMM.DRV
CEVT.....	COMM.DRV
CEVTGET.....	COMM.DRV
CEXTFCN.....	COMM.DRV
CFLUSH.....	COMM.DRV
CHANGECLIPBOARDCHAIN.....	USER.EXE
CHANGEMENU.....	USER.EXE
CHECKDLGBUTTON.....	USER.EXE
CHECKMENUITEM.....	USER.EXE
CHECKRADIOBUTTON.....	USER.EXE
CHILDWINDOWFROMPOINT.....	USER.EXE
CHORD.....	GDI.EXE
CLEARCOMMBREAK.....	USER.EXE
CLIENTTOSCREEN.....	USER.EXE
CLIPCURSOR.....	USER.EXE
CLOSECLIPBOARD.....	USER.EXE
CLOSECOMM.....	USER.EXE
CLOSEJOB.....	GDI.EXE
CLOSEMETAFILE.....	GDI.EXE
CLOSESOUND.....	SOUND.DRV
CLOSEWINDOW.....	USER.EXE
COMBINERGN.....	GDI.EXE
COMBOBOXCTLWNDPROC.....	USER.EXE
COMPATIBLEBITMAP.....	GDI.EXE
COMPUPDATERECT.....	USER.EXE
COMPUPDATERGN.....	USER.EXE
CONTROLPANELINFO.....	USER.EXE
CONTSCROLL.....	USER.EXE
COPY.....	GDI.EXE
COPYMETAFILE.....	GDI.EXE
COPYRECT.....	USER.EXE
COUNTCLIPBOARDFORMATS.....	USER.EXE
COUNTVOICENOTES.....	SOUND.DRV
CREATEBITMAP.....	GDI.EXE
CREATEBITMAPINDIRECT.....	GDI.EXE
CREATEBRUSHINDIRECT.....	GDI.EXE
CREATECARET.....	USER.EXE
CREATECOMPATIBLEBITMAP.....	GDI.EXE
CREATECOMPATIBLEDC.....	GDI.EXE
CREATECURSOR.....	USER.EXE
CREATECURSORICONINDIRECT.....	USER.EXE
CREATEDC.....	GDI.EXE
CREATEDIALOG.....	USER.EXE
CREATEDIALOGINDIRECT.....	USER.EXE
CREATEDIALOGINDIRECTPARAM.....	USER.EXE
CREATEDIALOGPARAM.....	USER.EXE

CREATEDIBITMAP.....GDI.EXE
CREATEDIBPATTERNBRUSH.....GDI.EXE
CREATEDISCARDABLEBITMAP.....GDI.EXE
CREATEELLIPTICRGN.....GDI.EXE
CREATEELLIPTICRGNINDIRECT.....GDI.EXE
CREATEFONT.....GDI.EXE
CREATEFONTINDIRECT.....GDI.EXE
CREATEHATCHBRUSH.....GDI.EXE
CREATEIC.....GDI.EXE
CREATEICON.....USER.EXE
CREATEMENU.....USER.EXE
CREATEMETAFILE.....GDI.EXE
CREATEPALETTE.....GDI.EXE
CREATEPATTERNBRUSH.....GDI.EXE
CREATEPEN.....GDI.EXE
CREATEPENINDIRECT.....GDI.EXE
CREATEPOLYGONRGN.....GDI.EXE
CREATEPOLYPOLYGONRGN.....GDI.EXE
CREATEPOPUPMENU.....USER.EXE
CREATEPQ.....GDI.EXE
CREATEREALBITMAP.....GDI.EXE
CREATEREALBITMAPINDIRECT.....GDI.EXE
CREATERECTRGN.....GDI.EXE
CREATERECTRGNINDIRECT.....GDI.EXE
CREATEROUNDRECTRGN.....GDI.EXE
CREATESOLIDBRUSH.....GDI.EXE
CREATESYSTEMTIMER.....SYSTEM.EXE
CREATEUSERBITMAP.....GDI.EXE
CREATEUSERDISCARDABLEBITMAP...GDI.EXE
CREATEWINDOW.....USER.EXE
CREATEWINDOWEX.....USER.EXE
CSETBRK.....COMM.DRV
CTX.....COMM.DRV
CVWBREAK.....KERNEL.EXE

D

Function Name DLL Name

DEBUGBREAK.....	KERNEL.EXE
DEFDLGPROC.....	USER.EXE
DEFERWINDOWPOS.....	USER.EXE
DEFFRAMEPROC.....	USER.EXE
DEFHOOKPROC.....	USER.EXE
DEFINEHANDLETABLE.....	KERNEL.EXE
DEFMDICHILDPROC.....	USER.EXE
DEFWINDOWPROC.....	USER.EXE
DELETEABOVELINEFONTS.....	GDI.EXE
DELETEATOM.....	KERNEL.EXE
DELETEDC.....	GDI.EXE
DELETEJOB.....	GDI.EXE
DELETEMENU.....	USER.EXE
DELETEMETAFILE.....	GDI.EXE
DELETEOBJECT.....	GDI.EXE
DELETEPATHNAME.....	KERNEL.EXE
DELETEPQ.....	GDI.EXE
DESKTOPWNDPROC.....	USER.EXE
DESTROYCARET.....	USER.EXE
DESTROYCURSOR.....	USER.EXE
DESTROYICON.....	USER.EXE
DESTROYMENU.....	USER.EXE
DESTROYWINDOW.....	USER.EXE
DEVICECOLORMATCH.....	GDI.EXE
DIALOGBOX.....	USER.EXE
DIALOGBOXINDIRECT.....	USER.EXE
DIALOGBOXINDIRECTPARAM.....	USER.EXE
DIALOGBOXPARAM.....	USER.EXE
DIRECTEDYIELD.....	KERNEL.EXE
DIRECTRESALLOC.....	KERNEL.EXE
DISABLE.....	MOUSE.DRV
DISABLE.....	KEYBOARD.DRV
DISABLEDOS.....	KERNEL.EXE
DISABLEKERNEL.....	KERNEL.EXE
DISABLEOEMLAYER.....	USER.EXE
DISABLESYSTEMTIMERS.....	SYSTEM.EXE
DISPATCHMESSAGE.....	USER.EXE
DLGDIRLIST.....	USER.EXE
DLGDIRLISTCOMBOBOX.....	USER.EXE
DLGDIRSELECT.....	USER.EXE
DLGDIRSELECTCOMBOBOX.....	USER.EXE
DMBITBLT.....	GDI.EXE
DMCOLORINFO.....	GDI.EXE
DMENUMDFONTS.....	GDI.EXE
DMENUMOBJ.....	GDI.EXE
DMOUTPUT.....	GDI.EXE
DMPIXEL.....	GDI.EXE
DMREALIZEOBJECT.....	GDI.EXE
DMSCANLR.....	GDI.EXE
DMSTRBLT.....	GDI.EXE
DMTRANPOSE.....	GDI.EXE
DOBEEP.....	SOUND.DRV
DOS3CALL.....	KERNEL.EXE

DOSIGNAL.....KERNEL.EXE
DPTOLP.....GDI.EXE
DPXLATE.....GDI.EXE
DRAGDETECT.....USER.EXE
DRAGOBJECT.....USER.EXE
DRAWFOCUSRECT.....USER.EXE
DRAWICON.....USER.EXE
DRAWMENUBAR.....USER.EXE
DRAWTEXT.....USER.EXE
DUMPICON.....USER.EXE

E

Function Name DLL Name

EDITWNDPROC.....	USER.EXE
ELLIPSE.....	GDI.EXE
EMPTYCLIPBOARD.....	USER.EXE
EMSCOPY.....	KERNEL.EXE
ENABLE.....	MOUSE.DRV
ENABLE.....	KEYBOARD.DRV
ENABLEDOS.....	KERNEL.EXE
ENABLEHARDWAREINPUT.....	USER.EXE
ENABLEKBSYSREQ.....	KEYBOARD.DRV
ENABLEKERNEL.....	KERNEL.EXE
ENABLEMENUITEM.....	USER.EXE
ENABLEOEMLAYER.....	USER.EXE
ENABLESYSTEMTIMERS.....	SYSTEM.EXE
ENABLEWINDOW.....	USER.EXE
ENDDEFERWINDOWPOS.....	USER.EXE
ENDDIALOG.....	USER.EXE
ENDMENU.....	USER.EXE
ENDPAINT.....	USER.EXE
ENDSPOOLPAGE.....	GDI.EXE
ENUMCALLBACK.....	GDI.EXE
ENUMCHILDWINDOWS.....	USER.EXE
ENUMCLIPBOARDFORMATS.....	USER.EXE
ENUMFONTS.....	GDI.EXE
ENUMMETAFILE.....	GDI.EXE
ENUMOBJECTS.....	GDI.EXE
ENUMPROPS.....	USER.EXE
ENUMTASKWINDOWS.....	USER.EXE
ENUMWINDOWS.....	USER.EXE
EQUALRECT.....	USER.EXE
EQUALRGN.....	GDI.EXE
ESCAPE.....	GDI.EXE
ESCAPECOMMFUNCTION.....	USER.EXE
EXCLUDECLIPRECT.....	GDI.EXE
EXCLUDEUPDATERGN.....	USER.EXE
EXCLUDEVISRECT.....	GDI.EXE
EXITKERNEL.....	KERNEL.EXE
EXITWINDOWS.....	USER.EXE
EXTFLOODFILL.....	GDI.EXE
EXTRACTPQ.....	GDI.EXE
EXTTEXTOUT.....	GDI.EXE

F

Function Name	DLL Name
---------------	----------

FARCALLNETDRIVER.....	USER.EXE
FASTWINDOWFRAME.....	GDI.EXE
FATALAPPEXIT.....	KERNEL.EXE
FATALEXIT.....	KERNEL.EXE
FILECDR.....	KERNEL.EXE
FILEPORTDLGPROC.....	USER.EXE
FILLRECT.....	USER.EXE
FILLRGN.....	GDI.EXE
FILLWINDOW.....	USER.EXE
FINALGDIINIT.....	GDI.EXE
FINALUSERINIT.....	USER.EXE
FINDATOM.....	KERNEL.EXE
FINDRESOURCE.....	KERNEL.EXE
FINDWINDOW.....	USER.EXE
FLASHWINDOW.....	USER.EXE
FLOODFILL.....	GDI.EXE
FLUSHCOMM.....	USER.EXE
FRAMERECT.....	USER.EXE
FRAMERGN.....	GDI.EXE
FREELIBRARY.....	KERNEL.EXE
FREEMODULE.....	KERNEL.EXE
FREEPROCINSTANCE.....	KERNEL.EXE
FREERESOURCE.....	KERNEL.EXE
FREESELECTOR.....	KERNEL.EXE

G

Function Name DLL Name

GDIINIT2.....	GDI.EXE
GDIMOVEBITMAP.....	GDI.EXE
GDIREALIZEPALETTE.....	GDI.EXE
GDISELECTPALETTE.....	GDI.EXE
GET80X87SAVESIZE.....	SYSTEM.EXE
GETACTIVEWINDOW.....	USER.EXE
GETASPECTRATIOFILTER.....	GDI.EXE
GETASYNCKEYSTATE.....	USER.EXE
GETATOMHANDLE.....	KERNEL.EXE
GETATOMNAME.....	KERNEL.EXE
GETBITMAPBITS.....	GDI.EXE
GETBITMAPDIMENSION.....	GDI.EXE
GETBKCOLOR.....	GDI.EXE
GETBKMODE.....	GDI.EXE
GETBRUSHORG.....	GDI.EXE
GETCAPTURE.....	USER.EXE
GETCARETBLINKTIME.....	USER.EXE
GETCARETPOS.....	USER.EXE
GETCHARWIDTH.....	GDI.EXE
GETCLASSINFO.....	USER.EXE
GETCLASSLONG.....	USER.EXE
GETCLASSNAME.....	USER.EXE
GETCLASSWORD.....	USER.EXE
GETCLIENTRECT.....	USER.EXE
GETCLIPBOARDATA.....	USER.EXE
GETCLIPBOARDFORMATNAME.....	USER.EXE
GETCLIPBOARDOWNER.....	USER.EXE
GETCLIPBOARDVIEWER.....	USER.EXE
GETCLIPBOX.....	GDI.EXE
GETCLIPRGN.....	GDI.EXE
GETCODEHANDLE.....	KERNEL.EXE
GETCODEINFO.....	KERNEL.EXE
GETCOMMERROR.....	USER.EXE
GETCOMMEVENTMASK.....	USER.EXE
GETCOMMSTATE.....	USER.EXE
GETCONTROLBRUSH.....	USER.EXE
GETCURLOGFONT.....	GDI.EXE
GETCURPID.....	KERNEL.EXE
GETCURRENTPDB.....	KERNEL.EXE
GETCURRENTPOSITION.....	GDI.EXE
GETCURRENTTASK.....	KERNEL.EXE
GETCURRENTTIME.....	USER.EXE
GETCURSORPOS.....	USER.EXE
GETDC.....	USER.EXE
GETDCB.....	COMM.DRV
GETDCORG.....	GDI.EXE
GETDCSTATE.....	GDI.EXE
GETDESKTOPHWNDD.....	USER.EXE
GETDESKTOPWINDOW.....	USER.EXE
GETDEVICECAPS.....	GDI.EXE
GETDIALOGBASEUNITS.....	USER.EXE
GETDIBITS.....	GDI.EXE
GETDLGCTRLID.....	USER.EXE

GETDLGITEM.....USER.EXE
GETDLGITEMINT.....USER.EXE
GETDLGITEMTEXT.....USER.EXE
GETDOSENVIRONMENT.....KERNEL.EXE
GETDOUBLECLICKTIME.....USER.EXE
GETDRIVETYPE.....KERNEL.EXE
GETENVIRONMENT.....GDI.EXE
GETEXEPTR.....KERNEL.EXE
GETEXEVERSION.....KERNEL.EXE
GETEXPWINVER.....KERNEL.EXE
GETFILEPORTNAME.....USER.EXE
GETFOCUS.....USER.EXE
GETFREESPACE.....KERNEL.EXE
GETHEAPSPACES.....KERNEL.EXE
GETICONID.....USER.EXE
GETINPUTSTATE.....USER.EXE
GETINSTANCEDATA.....KERNEL.EXE
GETINTERNALWINDOWPOS.....USER.EXE
GETKBCODEPAGE.....KEYBOARD.DRV
GETKEYBOARDSTATE.....USER.EXE
GETKEYBOARDTYPE.....KEYBOARD.DRV
GETKEYNAMETEXT.....KEYBOARD.DRV
GETKEYSTATE.....USER.EXE
GETLASTACTIVEPOPUP.....USER.EXE
GETLASTDISKCHANGE.....KERNEL.EXE
GETLPERRMODE.....KERNEL.EXE
GETMAPMODE.....GDI.EXE
GETMENU.....USER.EXE
GETMENUMCHECKMARKDIMENSIONS....USER.EXE
GETMENUITEMCOUNT.....USER.EXE
GETMENUITEMID.....USER.EXE
GETMENUSTATE.....USER.EXE
GETMENUSTRING.....USER.EXE
GETMESSAGE.....USER.EXE
GETMESSAGE2.....USER.EXE
GETMESSAGEPOS.....USER.EXE
GETMESSAGETIME.....USER.EXE
GETMETAFILE.....GDI.EXE
GETMETAFILEBITS.....GDI.EXE
GETMODULEFILENAME.....KERNEL.EXE
GETMODULEHANDLE.....KERNEL.EXE
GETMODULEUSAGE.....KERNEL.EXE
GETMOUSEEVENTPROC.....USER.EXE
GETNEARESTCOLOR.....GDI.EXE
GETNEARESTPALETTEINDEX.....GDI.EXE
GETNEXTDLGGROUPITEM.....USER.EXE
GETNEXTDLGTABITEM.....USER.EXE
GETNEXTQUEUEWINDOW.....USER.EXE
GETNEXTWINDOW.....USER.EXE
GETNUMTASKS.....KERNEL.EXE
GETOBJECT.....GDI.EXE
GETPALETTEENTRIES.....GDI.EXE
GETPARENT.....USER.EXE
GETPHYSICALFONTHANDLE.....GDI.EXE
GETPIXEL.....GDI.EXE
GETPOLYFILLMODE.....GDI.EXE
GETPRIORITYCLIPBOARDFORMAT....USER.EXE

GETPRIVATEPROFILEINT.....KERNEL.EXE
GETPRIVATEPROFILESTRING.....KERNEL.EXE
GETPROCADDRESS.....KERNEL.EXE
GETPROFILEINT.....KERNEL.EXE
GETPROFILESTRING.....KERNEL.EXE
GETPROP.....USER.EXE
GETQUEUESTATUS.....USER.EXE
GETRELABS.....GDI.EXE
GETTRGNBOX.....GDI.EXE
GETROP2.....GDI.EXE
GETSCROLLPOS.....USER.EXE
GETSCROLLRANGE.....USER.EXE
GETSELECTORBASE.....KERNEL.EXE
GETSELECTORLIMIT.....KERNEL.EXE
GETSPOOLJOB.....GDI.EXE
GETSTOCKOBJECT.....GDI.EXE
GETSTRETCHBLTMODE.....GDI.EXE
GETSUBMENU.....USER.EXE
GETSYSCOLOR.....USER.EXE
GETSYSMODALWINDOW.....USER.EXE
GETSYSTEMDIRECTORY.....KERNEL.EXE
GETSYSTEMMENU.....USER.EXE
GETSYSTEMMETRICS.....USER.EXE
GETSYSTEMMSECCOUNT.....SYSTEM.EXE
GETSYSTEMPALETTEENTRIES.....GDI.EXE
GETSYSTEMPALETTEUSE.....GDI.EXE
GETTABBEDTEXTTEXTENT.....USER.EXE
GETTABLESEG.....KEYBOARD.DRV
GETTASKDS.....KERNEL.EXE
GETTASKFROMHWND.....USER.EXE
GETTASKQUEUE.....KERNEL.EXE
GETTASKQUEUEEDS.....KERNEL.EXE
GETTASKQUEUEEES.....KERNEL.EXE
GETTEMPDRIVE.....KERNEL.EXE
GETTEMPFILENAME.....KERNEL.EXE
GETTEXTALIGN.....GDI.EXE
GETTEXTCHARACTEREXTRA.....GDI.EXE
GETTEXTCOLOR.....GDI.EXE
GETTEXTTEXTENT.....GDI.EXE
GETTEXTFACE.....GDI.EXE
GETTEXTMETRICS.....GDI.EXE
GETTHRESHOLDEVENT.....SOUND.DRV
GETTHRESHOLDSTATUS.....SOUND.DRV
GETTICKCOUNT.....USER.EXE
GETTIMERRESOLUTION.....USER.EXE
GETTOPWINDOW.....USER.EXE
GETUPDATERECT.....USER.EXE
GETUPDATERGN.....USER.EXE
GETVERSION.....KERNEL.EXE
GETVIEWPORTEXT.....GDI.EXE
GETVIEWPORTORG.....GDI.EXE
GETWC2.....USER.EXE
GETWINDOW.....USER.EXE
GETWINDOWDC.....USER.EXE
GETWINDOWEXT.....GDI.EXE
GETWINDOWLONG.....USER.EXE
GETWINDOWORG.....GDI.EXE

GETWINDOWRECT.....USER.EXE
GETWINDOWS DIRECTORY.....KERNEL.EXE
GETWINDOWTASK.....USER.EXE
GETWINDOWTEXT.....USER.EXE
GETWINDOWTEXTLENGTH.....USER.EXE
GETWINDOWWORD.....USER.EXE
GETWINFLAGS.....KERNEL.EXE
GLOBALADDATOM.....USER.EXE
GLOBALALLOC.....KERNEL.EXE
GLOBALCOMPACT.....KERNEL.EXE
GLOBALDELETEDATOM.....USER.EXE
GLOBALDOSALLOC.....KERNEL.EXE
GLOBALDOSFREE.....KERNEL.EXE
GLOBALFINDATOM.....USER.EXE
GLOBALFIX.....KERNEL.EXE
GLOBALFLAGS.....KERNEL.EXE
GLOBALFREE.....KERNEL.EXE
GLOBALFREEALL.....KERNEL.EXE
GLOBALGETATOMNAME.....USER.EXE
GLOBALHANDLE.....KERNEL.EXE
GLOBALHANDLENORIP.....KERNEL.EXE
GLOBALLOCK.....KERNEL.EXE
GLOBALLRUNEWEST.....KERNEL.EXE
GLOBALLRUOLDEST.....KERNEL.EXE
GLOBALMASTERHANDLE.....KERNEL.EXE
GLOBALNOTIFY.....KERNEL.EXE
GLOBALPAGELOCK.....KERNEL.EXE
GLOBALPAGEUNLOCK.....KERNEL.EXE
GLOBALREALLOC.....KERNEL.EXE
GLOBALSIZE.....KERNEL.EXE
GLOBALUNFIX.....KERNEL.EXE
GLOBALUNLOCK.....KERNEL.EXE
GLOBALUNWIRE.....KERNEL.EXE
GLOBALWIRE.....KERNEL.EXE
GRAYSTRING.....USER.EXE
GSV.....GDI.EXE

H

Function Name

DLL Name

HIDECARET.....	USER.EXE
HILITEMENUITEM.....	USER.EXE

Function Name **DLL Name**

ICONSIZE.....	USER.EXE
INFLATERECT.....	USER.EXE
INICOM.....	COMM.DRV
INITAPP.....	USER.EXE
INITATOMTABLE.....	KERNEL.EXE
INITLIB.....	KERNEL.EXE
INITTASK.....	KERNEL.EXE
INITTASK1.....	KERNEL.EXE
INQUIRE.....	MOUSE.DRV
INQUIRE.....	KEYBOARD.DRV
INQUIRESYSTEM.....	SYSTEM.EXE
INQUIREVISRGN.....	GDI.EXE
INSENDMESSAGE.....	USER.EXE
INSERTMENU.....	USER.EXE
INSERTPQ.....	GDI.EXE
INTERNALCREATEDC.....	GDI.EXE
INTERSECTCLIPRECT.....	GDI.EXE
INTERSECTRECT.....	USER.EXE
INTERSECTVISRECT.....	GDI.EXE
INVALIDATERECT.....	USER.EXE
INVALIDATERGN.....	USER.EXE
INVERTRECT.....	USER.EXE
INVERTRGN.....	GDI.EXE
ISCHARALPHA.....	USER.EXE
ISCHARALPHANUMERIC.....	USER.EXE
ISCHARLOWER.....	USER.EXE
ISCHARUPPER.....	USER.EXE
ISCHILD.....	USER.EXE
ISCLIPBOARDFORMATAVAILABLE....	USER.EXE
ISDCCURRENTPALETTE.....	GDI.EXE
ISDCDIRTY.....	GDI.EXE
ISDIALOGMESSAGE.....	USER.EXE
ISDLGBUTTONCHECKED.....	USER.EXE
ISICONIC.....	USER.EXE
ISRECTEMPTY.....	USER.EXE
ISTASKLOCKED.....	KERNEL.EXE
ISTWOBYTECHARPREFIX.....	USER.EXE
ISUSERIDLE.....	USER.EXE
ISVALIDMETAFILE.....	GDI.EXE
ISWINDOW.....	USER.EXE
ISWINDOWENABLED.....	USER.EXE
ISWINDOWVISIBLE.....	USER.EXE
ISWINOLDAPTASK.....	KERNEL.EXE
ISZOOMED.....	USER.EXE

K

Function Name	DLL Name
KILLSYSTEMTIMER.....	USER.EXE
KILLSYSTEMTIMER.....	SYSTEM.EXE
KILLTIMER.....	USER.EXE
KILLTIMER2.....	USER.EXE

L

Function Name DLL Name

LBOXCARETBLINKER.....	USER.EXE
LBOXCTLWNDPROC.....	USER.EXE
LIMITEMSPAGES.....	KERNEL.EXE
LINEDDA.....	GDI.EXE
LINETO.....	GDI.EXE
LOADACCELERATORS.....	USER.EXE
LOADBITMAP.....	USER.EXE
LOADCursors.....	USER.EXE
LOADCursorsIconHandler.....	USER.EXE
LOADDIBCursorsHandler.....	USER.EXE
LOADDIBIconHandler.....	USER.EXE
LOADICON.....	USER.EXE
LOADIconHandler.....	USER.EXE
LOADLIBRARY.....	KERNEL.EXE
LOADMENU.....	USER.EXE
LOADMENUINDIRECT.....	USER.EXE
LOADMODULE.....	KERNEL.EXE
LOADRESOURCE.....	KERNEL.EXE
LOADSTRING.....	USER.EXE
LOCALALLOC.....	KERNEL.EXE
LOCALCOMPACT.....	KERNEL.EXE
LOCALCOUNTFREE.....	KERNEL.EXE
LOCALFLAGS.....	KERNEL.EXE
LOCALFREE.....	KERNEL.EXE
LOCALHANDLE.....	KERNEL.EXE
LOCALHEAPSIZE.....	KERNEL.EXE
LOCALINIT.....	KERNEL.EXE
LOCALLOCK.....	KERNEL.EXE
LOCALNOTIFY.....	KERNEL.EXE
LOCALREALLOC.....	KERNEL.EXE
LOCALSHRINK.....	KERNEL.EXE
LOCALSIZE.....	KERNEL.EXE
LOCALUNLOCK.....	KERNEL.EXE
LOCKCURRENTTASK.....	KERNEL.EXE
LOCKMYTASK.....	USER.EXE
LOCKRESOURCE.....	KERNEL.EXE
LOCKSEGMENT.....	KERNEL.EXE
LONGPTRADD.....	KERNEL.EXE
LOOKUPMENUHANDLE.....	USER.EXE
LPTODP.....	GDI.EXE
LSTRCAT.....	KERNEL.EXE
LSTRCMP.....	USER.EXE
LSTRCMPi.....	USER.EXE
LSTRCPY.....	KERNEL.EXE
LSTRLEN.....	KERNEL.EXE
LVBUNION.....	GDI.EXE

M

Function Name	DLL Name
---------------	----------

MAKEPROCINSTANCE.....	KERNEL.EXE
MAPDIALOGRECT.....	USER.EXE
MAPVIRTUALKEY.....	KEYBOARD.DRV
MB_DLGPROC.....	USER.EXE
MDICLIENTWNDPROC.....	USER.EXE
MEMORYFREED.....	KERNEL.EXE
MENUITEMSTATE.....	USER.EXE
MENUWNDPROC.....	USER.EXE
MESSAGEBEEP.....	USER.EXE
MESSAGEBOX.....	USER.EXE
MFDRAWTEXT.....	GDI.EXE
MINPQ.....	GDI.EXE
MODIFYMENU.....	USER.EXE
MOUSEGETINTVECT.....	MOUSE.DRV
MOVETO.....	GDI.EXE
MOVEWINDOW.....	USER.EXE
MULDIV.....	GDI.EXE
MYOPENSOUND.....	SOUND.DRV

N

Function Name	DLL Name
NETBIOSCALL.....	KERNEL.EXE
NEWTABLE.....	KEYBOARD.DRV
NOHOOKDOSCALL.....	KERNEL.EXE

O

Function Name	DLL Name
---------------	----------

OEMKEYSCAN.....	KEYBOARD.DRV
OEMTOANSI.....	KEYBOARD.DRV
OEMTOANSIBUFF.....	KEYBOARD.DRV
OFFSETCLIPRGN.....	GDI.EXE
OFFSETORG.....	GDI.EXE
OFFSETRECT.....	USER.EXE
OFFSETTRGN.....	GDI.EXE
OFFSETVIEWPORTORG.....	GDI.EXE
OFFSETVISRGN.....	GDI.EXE
OFFSETWINDOWORG.....	GDI.EXE
OLDEXITWINDOWS.....	USER.EXE
OLDYIELD.....	KERNEL.EXE
OPENCLIPBOARD.....	USER.EXE
OPENCOMM.....	USER.EXE
OPENFILE.....	KERNEL.EXE
OPENICON.....	USER.EXE
OPENJOB.....	GDI.EXE
OPENPATHNAME.....	KERNEL.EXE
OPENSOUND.....	SOUND.DRV
OUTPUTDEBUGSTRING.....	KERNEL.EXE

P

Function Name	DLL Name
---------------	----------

PAINTRECT.....	USER.EXE
PAINTRGN.....	GDI.EXE
PATBLT.....	GDI.EXE
PATCHCODEHANDLE.....	KERNEL.EXE
PEEKMESSAGE.....	USER.EXE
PIE.....	GDI.EXE
PIXTOLINE.....	GDI.EXE
PLAYMETAFILE.....	GDI.EXE
PLAYMETAFILERECORD.....	GDI.EXE
POLYGON.....	GDI.EXE
POLYLINE.....	GDI.EXE
POLYPOLYGON.....	GDI.EXE
POSTAPPMESSAGE.....	USER.EXE
POSTEVENT.....	KERNEL.EXE
POSTMESSAGE.....	USER.EXE
POSTMESSAGE2.....	USER.EXE
POSTQUITMESSAGE.....	USER.EXE
PTINRECT.....	USER.EXE
PTINREGION.....	GDI.EXE
PTVISIBLE.....	GDI.EXE

Q

Function Name

DLL Name

QUERYABORT.....	GDI.EXE
QUERYJOB.....	GDI.EXE

R

Function Name	DLL Name
---------------	----------

RCOS.....	GDI.EXE
REACTIVATEOPENCOMMPORTS.....	COMM.DRV
READCOMM.....	USER.EXE
REALIZEDEFAULTPALETTE.....	GDI.EXE
REALIZEPALETTE.....	USER.EXE
RECCOM.....	COMM.DRV
RECTANGLE.....	GDI.EXE
RECTINREGION.....	GDI.EXE
RECTSTUFF.....	GDI.EXE
RECTVISIBLE.....	GDI.EXE
REGISTERCLASS.....	USER.EXE
REGISTERCLIPBOARDFORMAT.....	USER.EXE
REGISTERPTRACE.....	KERNEL.EXE
REGISTERWINDOWMESSAGE.....	USER.EXE
RELEASECAPTURE.....	USER.EXE
RELEASEDC.....	USER.EXE
REMOVEFONTRESOURCE.....	GDI.EXE
REMOVEMENU.....	USER.EXE
REMOVEPROP.....	USER.EXE
REPAINTSCREEN.....	USER.EXE
REPLACEINST.....	KERNEL.EXE
REPLYMESSAGE.....	USER.EXE
RESIZEPALETTE.....	GDI.EXE
RESTORE80X87STATE.....	SYSTEM.EXE
RESTOREDC.....	GDI.EXE
RESTOREVISRGN.....	GDI.EXE
RESURRECTION.....	GDI.EXE
ROUNDRECT.....	GDI.EXE
RSIN.....	GDI.EXE

S

Function Name DLL Name

SAVE80X87STATE.....	SYSTEM.EXE
SAVEDC.....	GDI.EXE
SAVEVISRGN.....	GDI.EXE
SBWNDPROC.....	USER.EXE
SCALEEXT.....	GDI.EXE
SCALEVIEWPORTEXT.....	GDI.EXE
SCALEWINDOWEXT.....	GDI.EXE
SCANLR.....	GDI.EXE
SCREENSWITCHENABLE.....	KEYBOARD.DRV
SCREENTOCLIENT.....	USER.EXE
SCROLLCHILDREN.....	USER.EXE
SCROLLDC.....	USER.EXE
SCROLLWINDOW.....	USER.EXE
SELECTCLIPRGN.....	GDI.EXE
SELECTOBJECT.....	GDI.EXE
SELECTORACCESSRIGHTS.....	KERNEL.EXE
SELECTPALETTE.....	USER.EXE
SELECTVISRGN.....	GDI.EXE
SENDDLGITEMMESSAGE.....	USER.EXE
SENDMESSAGE.....	USER.EXE
SENDMESSAGE2.....	USER.EXE
SETACTIVEWINDOW.....	USER.EXE
SETBITMAPBITS.....	GDI.EXE
SETBITMAPDIMENSION.....	GDI.EXE
SETBKCOLOR.....	GDI.EXE
SETBKMODE.....	GDI.EXE
SETBRUSHORG.....	GDI.EXE
SETCAPTURE.....	USER.EXE
SETCARETBLINKTIME.....	USER.EXE
SETCARETPOS.....	USER.EXE
SETCLASSLONG.....	USER.EXE
SETCLASSWORD.....	USER.EXE
SETCLIPBOARDATA.....	USER.EXE
SETCLIPBOARDVIEWER.....	USER.EXE
SETCOM.....	COMM.DRV
SETCOMMBREAK.....	USER.EXE
SETCOMMEVENTMASK.....	USER.EXE
SETCOMMSTATE.....	USER.EXE
SETCURSOR.....	USER.EXE
SETCURSORPOS.....	USER.EXE
SETDCORG.....	GDI.EXE
SETDCSTATE.....	GDI.EXE
SETDCSTATUS.....	GDI.EXE
SETDESKPATTERN.....	USER.EXE
SETDESKWALLPAPER.....	USER.EXE
SETDIBITS.....	GDI.EXE
SETDIBITSTODEVICE.....	GDI.EXE
SETDLGITEMINT.....	USER.EXE
SETDLGITEMTEXT.....	USER.EXE
SETDOUBLECLICKTIME.....	USER.EXE
SETENVIRONMENT.....	GDI.EXE
SETERRORMODE.....	KERNEL.EXE
SETEVENTHOOK.....	USER.EXE

SETFOCUS.....USER.EXE
SETGETKBDSTATE.....USER.EXE
SETGRIDGRANULARITY.....USER.EXE
SETHANDLECOUNT.....KERNEL.EXE
SETINTERNALWINDOWPOS.....USER.EXE
SETKEYBOARDSTATE.....USER.EXE
SETMAPMODE.....GDI.EXE
SETMAPPERFLAGS.....GDI.EXE
SETMENU.....USER.EXE
SETMENUITEMBITMAPS.....USER.EXE
SETMESSAGEQUEUE.....USER.EXE
SETMETAFILEBITS.....GDI.EXE
SETPALETTEENTRIES.....GDI.EXE
SETPARENT.....USER.EXE
SETPIXEL.....GDI.EXE
SETPOLYFILLMODE.....GDI.EXE
SETPRIORITY.....KERNEL.EXE
SETPROP.....USER.EXE
SETQUE.....COMM.DRV
SETRECT.....USER.EXE
SETRECTEMPTY.....USER.EXE
SETRECTRGN.....GDI.EXE
SETRELABS.....GDI.EXE
SETRESOURCEHANDLER.....KERNEL.EXE
SETROP2.....GDI.EXE
SETSCROLLPOS.....USER.EXE
SETSCROLLRANGE.....USER.EXE
SETSELECTORBASE.....KERNEL.EXE
SETSELECTORLIMIT.....KERNEL.EXE
SETSIGHANDLER.....KERNEL.EXE
SETSOUNDNOISE.....SOUND.DRV
SETSPEED.....KEYBOARD.DRV
SETSTRETCHBLTMODE.....GDI.EXE
SETSWAPAREASIZE.....KERNEL.EXE
SETSYSCOLORS.....USER.EXE
SETSYSMODALWINDOW.....USER.EXE
SETSYSTEMMENU.....USER.EXE
SETSYSTEMPALETTEUSE.....GDI.EXE
SETSYSTEMTIMER.....USER.EXE
SETTASKQUEUE.....KERNEL.EXE
SETTASKSIGNALPROC.....KERNEL.EXE
SETTEXTALIGN.....GDI.EXE
SETTEXTCHARACTEREXTRA.....GDI.EXE
SETTEXTCOLOR.....GDI.EXE
SETTEXTJUSTIFICATION.....GDI.EXE
SETTIMER.....USER.EXE
SETTIMER2.....USER.EXE
SETVIEWPORTEXT.....GDI.EXE
SETVIEWPORTORG.....GDI.EXE
SETVOICEACCENT.....SOUND.DRV
SETVOICEENVELOPE.....SOUND.DRV
SETVOICENOTE.....SOUND.DRV
SETVOICEQUEUE SIZE.....SOUND.DRV
SETVOICESOUND.....SOUND.DRV
SETVOICETHRESHOLD.....SOUND.DRV
SETWC2.....USER.EXE
SETWINDOWEXT.....GDI.EXE

SETWINDOWLONG.....USER.EXE
SETWINDOWORG.....GDI.EXE
SETWINDOWPOS.....USER.EXE
SETWINDOWSHOOK.....USER.EXE
SETWINDOWTEXT.....USER.EXE
SETWINDOWWORD.....USER.EXE
SETWINVIEWEXT.....GDI.EXE
SHOWCARET.....USER.EXE
SHOWCURSOR.....USER.EXE
SHOWOWNEDPOPUPS.....USER.EXE
SHOWSCROLLBAR.....USER.EXE
SHOWWINDOW.....USER.EXE
SHRINKGDIHEAP.....GDI.EXE
SIGNALPROC.....USER.EXE
SIZEOFRESOURCE.....KERNEL.EXE
SIZEPQ.....GDI.EXE
SNAPWINDOW.....USER.EXE
SNDCOM.....COMM.DRV
STACOM.....COMM.DRV
STARTSOUND.....SOUND.DRV
STARTSPOOLPAGE.....GDI.EXE
STATICWNDPROC.....USER.EXE
STOPSOUND.....SOUND.DRV
STRETCHBLT.....GDI.EXE
STRETCHDIBITS.....GDI.EXE
STRINGFUNC.....USER.EXE
STUFFINREGION.....GDI.EXE
STUFFVISIBLE.....GDI.EXE
SUSPENDOPENCOMMPORTS.....COMM.DRV
SWAPMOUSEBUTTON.....USER.EXE
SWAPRECORDING.....KERNEL.EXE
SWITCHSTACKBACK.....KERNEL.EXE
SWITCHSTACKTO.....KERNEL.EXE
SWITCHTOTHISWINDOW.....USER.EXE
SWITCHWNDPROC.....USER.EXE
SYNCALLVOICES.....SOUND.DRV
SYSERRORBOX.....USER.EXE

T

Function Name	DLL Name
---------------	----------

TABBEDTEXTOUT.....	USER.EXE
TEXTOUT.....	GDI.EXE
THROW.....	KERNEL.EXE
TILECHILDWINDOWS.....	USER.EXE
TITLEWNDPROC.....	USER.EXE
TOASCII.....	KEYBOARD.DRV
TRACKPOPUPMENU.....	USER.EXE
TRANSLATEACCELERATOR.....	USER.EXE
TRANSLATEMDISYSACCEL.....	USER.EXE
TRANSLATEMESSAGE.....	USER.EXE
TRANSMITCOMMCHAR.....	USER.EXE
TRMCOM.....	COMM.DRV

U

Function Name	DLL Name
---------------	----------

UNDEFDYNLINK.....	KERNEL.EXE
UNGETCOMMCHAR.....	USER.EXE
UNHOOKWINDOWSHOOK.....	USER.EXE
UNIONRECT.....	USER.EXE
UNLOCKSEGMENT.....	KERNEL.EXE
UNREALIZEOBJECT.....	GDI.EXE
UNREGISTERCLASS.....	USER.EXE
UPDATECOLORS.....	GDI.EXE
UPDATEWINDOW.....	USER.EXE
USERYIELD.....	USER.EXE

V

Function Name	DLL Name
---------------	----------

VALIDATECODESEGMENTS.....	KERNEL.EXE
VALIDATEFREESPACES.....	KERNEL.EXE
VALIDATERECT.....	USER.EXE
VALIDATERGN.....	USER.EXE
VKKEYSCAN.....	KEYBOARD.DRV

W

Function Name	DLL Name
---------------	----------

WAITEVENT.....	KERNEL.EXE
WAITMESSAGE.....	USER.EXE
WAITSOUNDSTATE.....	SOUND.DRV
WINDOWFROMPOINT.....	USER.EXE
WINEXEC.....	KERNEL.EXE
WINFARFRAME.....	USER.EXE
WINHELP.....	USER.EXE
WINOLDAPCALL.....	KERNEL.EXE
WINOLDAPPHACKOMATIC.....	USER.EXE
WNETADDCONNECTION.....	USER.EXE
WNETBROWSEDIALOG.....	USER.EXE
WNETCANCELCONNECTION.....	USER.EXE
WNETCANCELJOB.....	USER.EXE
WNETCLOSEJOB.....	USER.EXE
WNETDEVICEMODE.....	USER.EXE
WNETGETCAPS.....	USER.EXE
WNETGETCONNECTION.....	USER.EXE
WNETGETERROR.....	USER.EXE
WNETGETERRORTEXT.....	USER.EXE
WNETGETUSER.....	USER.EXE
WNETHOLDJOB.....	USER.EXE
WNETLOCKQUEUEDATA.....	USER.EXE
WNETOPENJOB.....	USER.EXE
WNETRELEASEJOB.....	USER.EXE
WNETSETJOBCOPIES.....	USER.EXE
WNETUNLOCKQUEUEDATA.....	USER.EXE
WNETUNWATCHQUEUE.....	USER.EXE
WNETWATCHQUEUE.....	USER.EXE
WORDSET.....	GDI.EXE
WRITECOMM.....	USER.EXE
WRITEDIALOG.....	GDI.EXE
WRITEPRIVATEPROFILESTRING.....	KERNEL.EXE
WRITEPROFILESTRING.....	KERNEL.EXE
WRITESPOOL.....	GDI.EXE
WVSPRINTF.....	USER.EXE

X

Function Name

DLL Name

XCSTODS.....USER.EXE

Y

Function Name

DLL Name

YIELD.....KERNEL.EXE

A

Constant Name	Value
ABORTDOC.....	2
ABSOLUTE.....	1
ALTERNATE.....	1
ANSI_CHARSET.....	0
ANSI_FIXED_FONT.....	11
ANSI_VAR_FONT.....	12
ASPECTX.....	40
ASPECTXY.....	44
ASPECTY.....	42
ASPECT_FILTERING.....	0x0001

B

Constant Name	Value
BANDINFO.....	24
BEGIN_PATH.....	4096
BITSPIXEL.....	12
BI_RGB.....	0L
BI_RLE4.....	2L
BI_RLE8.....	1L
BLACKNESS.....	(DWORD) 0x00000042
BLACKONWHITE.....	1
BLACK_BRUSH.....	4
BLACK_PEN.....	7
BM_GETCHECK.....	(WM_USER+0)
BM_GETSTATE.....	(WM_USER+2)
BM_SETCHECK.....	(WM_USER+1)
BM_SETSTATE.....	(WM_USER+3)
BM_SETSTYLE.....	(WM_USER+4)
BN_CLICKED.....	0
BN_DISABLE.....	4
BN_DOUBLECLICKED.....	5
BN_HILITE.....	2
BN_PAINT.....	1
BN_UNHILITE.....	3
BS_3STATE.....	0x05L
BS_AUTO3STATE.....	0x06L
BS_AUTOCHECKBOX.....	0x03L
BS_AUTORADIOBUTTON.....	0x09L
BS_CHECKBOX.....	0x02L
BS_DEFPUSHBUTTON.....	0x01L
BS_GROUPBOX.....	0x07L
BS_HATCHED.....	2
BS_HOLLOW.....	BS_NULL
BS_INDEXED.....	4
BS_LEFTTEXT.....	0x20L
BS_NULL.....	1
BS_OWNERDRAW.....	0x0BL
BS_PATTERN.....	3
BS_PUSHBOX.....	0x0AL
BS_PUSHBUTTON.....	0x00L
BS_RADIOBUTTON.....	0x04L
BS_SOLID.....	0
BS_USERBUTTON.....	0x08L

C

Constant Name Value

CBN_DBLCLK.....2
 CBN_DROPDOWN.....7
 CBN_EDITCHANGE.....5
 CBN_EDITUPDATE.....6
 CBN_ERRSPACE.....(-1)
 CBN_KILLFOCUS.....4
 CBN_SELCHANGE.....1
 CBN_SETFOCUS.....3

CBS_AUTOHSCROLL.....0x0040L
 CBS_DROPDOWN.....0x0002L
 CBS_DROPDOWNLIST.....0x0003L
 CBS_HASSTRINGS.....0x0200L
 CBS_NOINTEGRALHEIGHT.....0x0400L
 CBS_OEMCONVERT.....0x0080L
 CBS_OWNERDRAWFIXED.....0x0010L
 CBS_OWNERDRAWVARIABLE.....0x0020L
 CBS_SIMPLE.....0x0001L
 CBS_SORT.....0x0100L

CB_ADDSTRING.....(WM_USER+3)
 CB_DELETESTRING.....(WM_USER+4)
 CB_DIR.....(WM_USER+5)
 CB_ERR.....(-1)
 CB_ERRSPACE.....(-2)
 CB_FINDSTRING.....(WM_USER+12)
 CB_GETCOUNT.....(WM_USER+6)
 CB_GETCURSEL.....(WM_USER+7)
 CB_GETDROPPEDCONTROLRECT.....(WM_USER+18)
 CB_GETEDITSEL.....(WM_USER+0)
 CB_GETITEMDATA.....(WM_USER+16)
 CB_GETLBTEXT.....(WM_USER+8)
 CB_GETLBTEXTLEN.....(WM_USER+9)
 CB_INSERTSTRING.....(WM_USER+10)
 CB_LIMITTEXT.....(WM_USER+1)
 CB_MSGMAX.....(WM_USER+19)
 CB_OKAY.....0
 CB_RESETCONTENT.....(WM_USER+11)
 CB_SELECTSTRING.....(WM_USER+13)
 CB_SETCURSEL.....(WM_USER+14)
 CB_SETEDITSEL.....(WM_USER+2)
 CB_SETITEMDATA.....(WM_USER+17)
 CB_SHOWDROPDOWN.....(WM_USER+15)

CC_CHORD.....4
 CC_CIRCLES.....1
 CC_ELLIPSES.....8
 CC_INTERIORS.....128
 CC_NONE.....0
 CC_PIE.....2
 CC_STYLED.....32
 CC_WIDE.....16
 CC_WIDESTYLED.....64

CE_BREAK.....	0x0010
CE_CTSTO.....	0x0020
CE_DNS.....	0x0800
CE_DSRT0.....	0x0040
CE_FRAME.....	0x0008
CE_IOE.....	0x0400
CE_MODE.....	0x8000
CE_OOP.....	0x1000
CE_OVERRUN.....	0x0002
CE_PTO.....	0x0200
CE_RLSDTO.....	0x0080
CE_RXOVER.....	0x0001
CE_RXPARITY.....	0x0004
CE_TXFULL.....	0x0100
CF_BITMAP.....	2
CF_DIB.....	8
CF_DIF.....	5
CF_DSPBITMAP.....	0x0082
CF_DSPMETAFILEPICT.....	0x0083
CF_DSPTEXT.....	0x0081
CF_GDI OBJFIRST.....	0x0300
CF_GDI OBJLAST.....	0x03FF
CF_METAFILEPICT.....	3
CF_OEMTEXT.....	7
CF_OWNERDISPLAY.....	0x0080
CF_PALETTE.....	9
CF_PRIVATEFIRST.....	0x0200
CF_PRIVATELAST.....	0x02FF
CF_SYLK.....	4
CF_TEXT.....	1
CF_TIFF.....	6
CLIPCAPS.....	36
CLIP_CHARACTER_PRECIS.....	1
CLIP_DEFAULT_PRECIS.....	0
CLIP_STROKE_PRECIS.....	2
CLIP_TO_PATH.....	4097
CLRDTR.....	6
CLRRTS.....	4
COLORONCOLOR.....	3
COLORRES.....	108
COLOR_ACTIVEBORDER.....	10
COLOR_ACTIVECAPTION.....	2
COLOR_APPWORKSPACE.....	12
COLOR_BACKGROUND.....	1
COLOR_BTNFACE.....	15
COLOR_BTNshadow.....	16
COLOR_BTNTEXT.....	18
COLOR_CAPTIONTEXT.....	9
COLOR_ENDCOLORS.....	COLOR_BTNTEXT
COLOR_GRAYTEXT.....	17
COLOR_HIGHLIGHT.....	13
COLOR_HIGHLIGHTTEXT.....	14

COLOR_INACTIVEBORDER.....11
COLOR_INACTIVECAPTION.....3
COLOR_MENU.....4
COLOR_MENUTEXT.....7
COLOR_SCROLLBAR.....0
COLOR_WINDOW.....5
COLOR_WINDOWFRAME.....6
COLOR_WINDOWTEXT.....8

COMPLEXREGION.....3

CP_DIRECT.....2
CP_HWND.....0
CP_NONE.....0
CP_OPEN.....1
CP_RECTANGLE.....1

CS_BYTEALIGNCLIENT.....0x1000
CS_BYTEALIGNWINDOW.....0x2000
CS_CLASSDC.....0x0040
CS_DBLCLKS.....0x0008
CS_GLOBALCLASS.....0x4000
CS_HREDRAW.....0x0002
CS_KEYCVTWINDOW.....0x0004
CS_NOCLOSE.....0x0200
CS_NOKEYCVT.....0x0100
CS_OWNDC.....0x0020
CS_PARENTDC.....0x0080
CS_SAVEBITS.....0x0800
CS_VREDRAW.....0x0001

CTLCOLOR_BTN.....3
CTLCOLOR_DLG.....4
CTLCOLOR_EDIT.....1
CTLCOLOR_LISTBOX.....2
CTLCOLOR_MAX.....8
CTLCOLOR_MSGBOX.....0
CTLCOLOR_SCROLLBAR.....5
CTLCOLOR_STATIC.....6

CURVECAPS.....28
CW_USEDEFAULT.....((int) 0x8000)

D

Constant Name Value

DC_HASDEFID.....	0x534B
DEFAULT_PALETTE.....	15
DEFAULT_PITCH.....	0
DEFAULT_QUALITY.....	0
DEVICEDATA.....	19
DEVICE_DEFAULT_FONT.....	14
DEVICE_FONTTYPE.....	0X0002
DKGRAY_BRUSH.....	3
DLGC_BUTTON.....	0x2000
DLGC_DEFPUSHBUTTON.....	0x0010
DLGC_HASSETSEL.....	0x0008
DLGC_RADIOBUTTON.....	0x0040
DLGC_STATIC.....	0x0100
DLGC_UNDEFPUSHBUTTON.....	0x0020
DLGC_WANTALLKEYS.....	0x0004
DLGC_WANTARROWS.....	0x0001
DLGC_WANTCHARS.....	0x0080
DLGC_WANTMESSAGE.....	0x0004
DLGC_WANTTAB.....	0x0002
DLGWINDOWEXTRA.....	30
DM_GETDEFID.....	(WM_USER+0)
DM_SETDEFID.....	(WM_USER+1)
DRAFTMODE.....	7
DRAFT_QUALITY.....	1
DRAWPATTERNRECT.....	25
DRIVERVERSION.....	0
DRIVE_FIXED.....	3
DRIVE_REMOTE.....	4
DRIVE_REMOVABLE.....	2
DSTINVERT.....	(DWORD) 0x00550009
DS_ABSALIGN.....	0x01L
DS_LOCALEDIT.....	0x20L
DS_MODALFRAME.....	0x80L
DS_NOIDLEMSG.....	0x100L
DS_SETFONT.....	0x40L
DS_SYSMODAL.....	0x02L
DT_BOTTOM.....	0x0008
DT_CALCRECT.....	0x0400
DT_CENTER.....	0x0001
DT_CHARSTREAM.....	4
DT_DISPFILE.....	6

DT_EXPANDTABS.....0x0040
DT_EXTERNALLEADING.....0x0200
DT_INTERNAL.....0x1000
DT_LEFT.....0x0000
DT_METAFILE.....5
DT_NOCLIP.....0x0100
DT_NOPREFIX.....0x0800
DT_PLOTTER.....0
DT_RASCAMERA.....3
DT_RASDISPLAY.....1
DT_RASPRINTER.....2
DT_RIGHT.....0x0002
DT_SINGLELINE.....0x0020
DT_TABSTOP.....0x0080
DT_TOP.....0x0000
DT_VCENTER.....0x0004
DT_WORDBREAK.....0x0010

E

Constant Name	Value
---------------	-------

EM_CANUNDO.....	(WM_USER+22)
EM_EMPTYUNDOBUFFER.....	(WM_USER+29)
EM_FMTLINES.....	(WM_USER+24)
EM_GETHANDLE.....	(WM_USER+13)
EM_GETLINE.....	(WM_USER+20)
EM_GETLINECOUNT.....	(WM_USER+10)
EM_GETMODIFY.....	(WM_USER+8)
EM_GETRECT.....	(WM_USER+2)
EM_GETSEL.....	(WM_USER+0)
EM_GETTHUMB.....	(WM_USER+14)
EM_LIMITTEXT.....	(WM_USER+21)
EM_LINEFROMCHAR.....	(WM_USER+25)
EM_LINEINDEX.....	(WM_USER+11)
EM_LINELENGTH.....	(WM_USER+17)
EM_LINESCROLL.....	(WM_USER+6)
EM_MSGMAX.....	(WM_USER+30)
EM_REPLACESEL.....	(WM_USER+18)
EM_SCROLL.....	(WM_USER+5)
EM_SETFONT.....	(WM_USER+19)
EM_SETHANDLE.....	(WM_USER+12)
EM_SETMODIFY.....	(WM_USER+9)
EM_SETPASSWORDCHAR.....	(WM_USER+28)
EM_SETRECT.....	(WM_USER+3)
EM_SETRECTNP.....	(WM_USER+4)
EM_SETSEL.....	(WM_USER+1)
EM_SETTABSTOPS.....	(WM_USER+27)
EM_SETWORDBREAK.....	(WM_USER+26)
EM_UNDO.....	(WM_USER+23)

ENABLEDUPLEX.....	28
ENABLEPAIRKERNING.....	769
ENABLERELATIVEWIDTHS.....	768
ENDDOC.....	11
END_PATH.....	4098
ENUMPAPERBINS.....	31
ENUMPAPERMETRICS.....	34

EN_CHANGE.....	0x0300
EN_ERRSPACE.....	0x0500
EN_HSCROLL.....	0x0601
EN_KILLFOCUS.....	0x0200
EN_MAXTEXT.....	0x0501
EN_SETFOCUS.....	0x0100
EN_UPDATE.....	0x0400
EN_VSCROLL.....	0x0602

EPSPRINTING.....	33
ERROR.....	0

ES_AUTOHSCROLL.....	0x0080L
ES_AUTOVSCROLL.....	0x0040L
ES_CENTER.....	0x0001L
ES_LEFT.....	0x0000L

ES_LOWERCASE.....0x0010L
ES_MULTILINE.....0x0004L
ES_NOHIDESEL.....0x0100L
ES_OEMCONVERT.....0x0400L
ES_PASSWORD.....0x0020L
ES_RIGHT.....0x0002L
ES_UPPERCASE.....0x0008L

ETO_CLIPPED.....4
ETO_GRAYED.....1
ETO_OPAQUE.....2

EVENPARITY.....2

EV_BREAK.....0x0040
EV_CTS.....0x0008
EV_DSR.....0x0010
EV_ERR.....0x0080
EV_PERR.....0x0200
EV_RING.....0x0100
EV_RLSD.....0x0020
EV_RXCHAR.....0x0001
EV_RXFLAG.....0x0002
EV_TXEMPTY.....0x0004

EXTTEXTOUT.....512
EXT_DEVICE_CAPS.....4099

F

Constant Name	Value
FF_DECORATIVE.....	(5<<4)
FF_DONTCARE.....	(0<<4)
FF_MODERN.....	(3<<4)
FF_ROMAN.....	(1<<4)
FF_SCRIPT.....	(4<<4)
FF_SWISS.....	(2<<4)
FIXED_PITCH.....	1
FLOODFILLBORDER.....	0
FLOODFILLSURFACE.....	1
FLUSHOUTPUT.....	6
FW_BLACK.....	FW_HEAVY
FW_BOLD.....	700
FW_DEMIBOLD.....	FW_SEMIBOLD
FW_DONTCARE.....	0
FW_EXTRABOLD.....	800
FW_EXTRALIGHT.....	200
FW_HEAVY.....	900
FW_LIGHT.....	300
FW_MEDIUM.....	500
FW_NORMAL.....	400
FW_REGULAR.....	FW_NORMAL
FW_SEMIBOLD.....	600
FW_THIN.....	100
FW_ULTRABOLD.....	FW_EXTRABOLD
FW_ULTRALIGHT.....	FW_EXTRALIGHT

G

Constant Name	Value
GCL_MENUNAME.....	(-8)
GCL_WNDPROC.....	(-24)
GCW_CBCLSEXTRA.....	(-20)
GCW_CBWNDEXTRA.....	(-18)
GCW_HBRBACKGROUND.....	(-10)
GCW_HCURSOR.....	(-12)
GCW_HICON.....	(-14)
GCW_HMODULE.....	(-16)
GCW_STYLE.....	(-26)
GETCOLORTABLE.....	5
GETEXTENDEDTEXTMETRICS.....	256
GETTEXTENTTABLE.....	257
GETPAIRKERNTABLE.....	258
GETPENWIDTH.....	16
GETPHYSPAGE_SIZE.....	12
GETPRINTINGOFFSET.....	13
GETSCALINGFACTOR.....	14
GETSETPAPERBINS.....	29
GETSETPAPERMETRICS.....	35
GETSETPRINTORIENT.....	30
GETTECHNOLGY.....	20
GETTECHNOLOGY.....	20
GETTRACKERNTABLE.....	259
GETVECTORBRUSH_SIZE.....	27
GETVECTORPEN_SIZE.....	26
GHND.....	(GMEM_MOVEABLE GMEM_ZEROINIT)
GMEM_DDESHARE.....	0x2000
GMEM_DISCARDABLE.....	0x0100
GMEM_DISCARDED.....	0x4000
GMEM_FIXED.....	0x0000
GMEM_LOCKCOUNT.....	0x00FF
GMEM_LOWER.....	GMEM_NOT_BANKED
GMEM_MODIFY.....	0x0080
GMEM_MOVEABLE.....	0x0002
GMEM_NOCOMPACT.....	0x0010
GMEM_NODISCARD.....	0x0020
GMEM_NOTIFY.....	0x4000
GMEM_NOT_BANKED.....	0x1000
GMEM_SHARE.....	0x2000
GMEM_ZEROINIT.....	0x0040
GPTR.....	(GMEM_FIXED GMEM_ZEROINIT)
GRAY_BRUSH.....	2
GWL_EXSTYLE.....	(-20)
GWL_STYLE.....	(-16)
GWL_WNDPROC.....	(-4)
GW_HINSTANCE.....	(-6)

GWW_HWNDPARENT..... (-8)
GWW_ID..... (-12)

GW_CHILD.....5
GW_HWNDFIRST.....0
GW_HWNDLAST.....1
GW_HWNDNEXT.....2
GW_HWNDPREV.....3
GW_OWNER.....4

H

Constant Name	Value
HCBT_MINMAX.....	1
HCBT_MOVESIZE.....	0
HCBT_QS.....	2
HC_ACTION.....	0
HC_GETNEXT.....	1
HC_LPFNNEXT.....	(-1)
HC_LPLPFNNEXT.....	(-2)
HC_NOREM.....	3
HC_NOREMOVE.....	3
HC_SKIP.....	2
HC_SYSMODALOFF.....	5
HC_SYSMODALON.....	4
HELP_CONTEXT.....	0x0001
HELP_HELPONHELP.....	0x0004
HELP_INDEX.....	0x0003
HELP_KEY.....	0x0101
HELP_MULTIKEY.....	0x0201
HELP_QUIT.....	0x0002
HELP_SETINDEX.....	0x0005
HIDE_WINDOW.....	0
HOLLOW_BRUSH.....	NULL_BRUSH
HORZRES.....	8
HORZSIZE.....	4
HS_BDIAGONAL.....	3
HS_CROSS.....	4
HS_DIAGCROSS.....	5
HS_FDIAGONAL.....	2
HS_HORIZONTAL.....	0
HS_VERTICAL.....	1
HTBOTTOM.....	15
HTBOTTOMLEFT.....	16
HTBOTTOMRIGHT.....	17
HTCAPTION.....	2
HTCLIENT.....	1
HTERROR.....	(-2)
HTGROWBOX.....	4
HTHSCROLL.....	6
HTLEFT.....	10
HTMENU.....	5
HTNOWHERE.....	0
HTREDUCE.....	8
HTRIGHT.....	11
HTSIZE.....	HTGROWBOX
HTSIZEFIRST.....	HTLEFT
HTSIZELAST.....	HTBOTTOMRIGHT
HTSYSMENU.....	3
HTTOP.....	12

HTTOPLEFT.....	13
HTTOPRIGHT.....	14
HTTRANSPARENT.....	(-1)
HTVSCROLL.....	7
HTZOOM.....	9

|

Constant Name	Value
IDABORT.....	3
IDCANCEL.....	2
IDIGNORE.....	5
IDNO.....	7
IDOK.....	1
IDRETRY.....	4
IDYES.....	6
IE_BADID.....	(-1)
IE_BAUDRATE.....	(-12)
IE_BYTESIZE.....	(-11)
IE_DEFAULT.....	(-5)
IE_HARDWARE.....	(-10)
IE_MEMORY.....	(-4)
IE_NOPEN.....	(-3)
IE_OPEN.....	(-2)
IGNORE.....	0
INFINITE.....	0xFFFF

K

Constant Name	Value
---------------	-------

KNJ_ACCEPT.....	0x24
KNJ_CHANGE_UDIC.....	0x33
KNJ_CODECONVERT.....	0x20
KNJ_CONVERT.....	0x21
KNJ_CVT_DEFAULT.....	0x07
KNJ_CVT_HIRAGANA.....	0x04
KNJ_CVT_JIS1.....	0x05
KNJ_CVT_KATAKANA.....	0x03
KNJ_CVT_NEXT.....	0x01
KNJ_CVT_PREV.....	0x02
KNJ_CVT_SJIS2.....	0x06
KNJ_CVT_TYPED.....	0x08
KNJ_END.....	0x02
KNJ_GETMODE.....	0x11
KNJ_JIS1toDEFAULT.....	0x10
KNJ_JIS1toJIS1KATAKANA.....	0x14
KNJ_JIS1toSJIS2.....	0x13
KNJ_JIS1toSJIS2HIRAGANA.....	0x15
KNJ_JIS1toSJIS2KATAKANA.....	0x16
KNJ_JIS1toSJIS2OEM.....	0x1F
KNJ_JIS2toSJIS2.....	0x23
KNJ_LEARN.....	0x30
KNJ_LEARN_MODE.....	0x10
KNJ_MD_ALPHA.....	0x01
KNJ_MD_HALF.....	0x04
KNJ_MD_HIRAGANA.....	0x02
KNJ_MD_JIS.....	0x08
KNJ_MD_SPECIAL.....	0x10
KNJ_NEXT.....	0x22
KNJ_PREVIOUS.....	0x23
KNJ_QUERY.....	0x03
KNJ_REGISTER.....	0x31
KNJ_REMOVE.....	0x32
KNJ_SETMODE.....	0x12
KNJ_SJIS2toJIS2.....	0x32
KNJ_START.....	0x01

L

Constant Name	Value
LBN_DBLCLK.....	2
LBN_ERRSPACE.....	(-2)
LBN_KILLFOCUS.....	5
LBN_SELCANCEL.....	3
LBN_SELCHANGE.....	1
LBN_SETFOCUS.....	4
LBS_EXTENDEDSEL.....	0x0800L
LBS_HASSTRINGS.....	0x0040L
LBS_MULTICOLUMN.....	0x0200L
LBS_MULTIPLESEL.....	0x0008L
LBS_NOINTEGRALHEIGHT.....	0x0100L
LBS_NOREDRA.....	0x0004L
LBS_NOTIFY.....	0x0001L
LBS_OWNERDRAWFIXED.....	0x0010L
LBS_OWNERDRAWVARIABLE.....	0x0020L
LBS_SORT.....	0x0002L
LBS_STANDARD.....	(LBS_NOTIFY LBS_SORT WS_VSCROLL WS_BORDER)
LBS_USETABSTOPS.....	0x0080L
LBS_WANTKEYBOARDINPUT.....	0x0400L
LB_ADDSTRING.....	(WM_USER+1)
LB_CTLCODE.....	0L
LB_DELETESTRING.....	(WM_USER+3)
LB_DIR.....	(WM_USER+14)
LB_ERR.....	(-1)
LB_ERRSPACE.....	(-2)
LB_FINDSTRING.....	(WM_USER+16)
LB_GETCOUNT.....	(WM_USER+12)
LB_GETCURSEL.....	(WM_USER+9)
LB_GETHORIZONTALEXTENT.....	(WM_USER+20)
LB_GETITEMDATA.....	(WM_USER+26)
LB_GETITEMRECT.....	(WM_USER+25)
LB_GETSEL.....	(WM_USER+8)
LB_GETSELCOUNT.....	(WM_USER+17)
LB_GETSELITEMS.....	(WM_USER+18)
LB_GETTEXT.....	(WM_USER+10)
LB_GETTEXTLEN.....	(WM_USER+11)
LB_GETTOPINDEX.....	(WM_USER+15)
LB_INSERTSTRING.....	(WM_USER+2)
LB_MSGMAX.....	(WM_USER+33)
LB_OKAY.....	0
LB_RESETCONTENT.....	(WM_USER+5)
LB_SELECTSTRING.....	(WM_USER+13)
LB_SELITEMRANGE.....	(WM_USER+28)
LB_SETCOLUMNWIDTH.....	(WM_USER+22)
LB_SETCURSEL.....	(WM_USER+7)
LB_SETHORIZONTALEXTENT.....	(WM_USER+21)
LB_SETITEMDATA.....	(WM_USER+27)
LB_SETSEL.....	(WM_USER+6)
LB_SETTABSTOPS.....	(WM_USER+19)
LB_SETTOPINDEX.....	(WM_USER+24)

```

LC_INTERIORS.....128
LC_MARKER.....4
LC_NONE.....0
LC_POLYLINE.....2
LC_POLYMARKER.....8
LC_STYLED.....32
LC_WIDE.....16
LC_WIDESTYLED.....64

LF_FACESIZE.....32
LHND.....(LMEM_MOVEABLE | LMEM_ZEROINIT)
LINECAPS.....30

LMEM_DISCARDABLE.....0x0F00
LMEM_DISCARDED.....0x4000
LMEM_FIXED.....0x0000
LMEM_LOCKCOUNT.....0x00FF
LMEM_MODIFY.....0x0080
LMEM_MOVEABLE.....0x0002
LMEM_NOCOMPACT.....0x0010
LMEM_NODISCARD.....0x0020
LMEM_ZEROINIT.....0x0040

LNOTIFY_DISCARD.....2
LNOTIFY_MOVE.....1
LNOTIFY_OUTOFMEM.....0

LOGPIXELSX.....88
LOGPIXELSY.....90

LPTR.....(LMEM_FIXED | LMEM_ZEROINIT)
LPTx.....0x80
LTGRAY_BRUSH.....1

```

M

Constant Name	Value
MARKPARITY.....	3
MA_ACTIVATE.....	1
MA_ACTIVATEANDEAT.....	2
MA_NOACTIVATE.....	3
MB_ABORTRETRYIGNORE.....	0x0002
MB_APPLMODAL.....	0x0000
MB_DEFBUTTON1.....	0x0000
MB_DEFBUTTON2.....	0x0100
MB_DEFBUTTON3.....	0x0200
MB_DEFMASK.....	0x0F00
MB_ICONASTERISK.....	0x0040
MB_ICONEXCLAMATION.....	0x0030
MB_ICONHAND.....	0x0010
MB_ICONINFORMATION.....	MB_ICONASTERISK
MB_ICONMASK.....	0x00F0
MB_ICONQUESTION.....	0x0020
MB_ICONSTOP.....	MB_ICONHAND
MB_MISCMASK.....	0xC000
MB_MODEMASK.....	0x3000
MB_NOFOCUS.....	0x8000
MB_OK.....	0x0000
MB_OKCANCEL.....	0x0001
MB_RETRYCANCEL.....	0x0005
MB_SYSTEMMODAL.....	0x1000
MB_TASKMODAL.....	0x2000
MB_TYPEMASK.....	0x000F
MB_YESNO.....	0x0004
MB_YESNOCANCEL.....	0x0003
MERGECOPY.....	(DWORD) 0x00C000CA
MERGEPAINT.....	(DWORD) 0x00BB0226
META_ARC.....	0x0817
META_BITBLT.....	0x0922
META_CREATEBITMAP.....	0x06FE
META_CREATEBITMAPINDIRECT.....	0x02FD
META_CREATEBRUSH.....	0x00F8
META_CREATEBRUSHINDIRECT.....	0x02FC
META_CREATEFONTINDIRECT.....	0x02FB
META_CREATEPATTERNBRUSH.....	0x01F9
META_CREATEPENINDIRECT.....	0x02FA
META_CREATEREGION.....	0x06FF
META_DRAWTEXT.....	0x062F
META_ELLIPSE.....	0x0418
META_ESCAPE.....	0x0626
META_EXCLUDECLIPRECT.....	0x0415
META_FILLREGION.....	0x0228
META_FLOODFILL.....	0x0419
META_FRAMEREGION.....	0x0429
META_INTERSECTCLIPRECT.....	0x0416
META_INVERTREGION.....	0x012A

META_LINETO.....0x0213
META_MOVETO.....0x0214
META_OFFSETCLIPRGN.....0x0220
META_OFFSETVIEWPORTORG.....0x0211
META_OFFSETWINDOWORG.....0x020F
META_PAINTREGION.....0x012B
META_PATBLT.....0x061D
META_PIE.....0x081A
META_POLYGON.....0x0324
META_POLYLINE.....0x0325
META_RECTANGLE.....0x041B
META_RESTOREDC.....0x0127
META_ROUNDRECT.....0x061C
META_SAVEDC.....0x001E
META_SCALEVIEWPORTEXT.....0x0412
META_SCALEWINDOWEXT.....0x0400
META_SELECTCLIPREGION.....0x012C
META_SELECTOBJECT.....0x012D
META_SETBKCOLOR.....0x0201
META_SETBKMODE.....0x0102
META_SETMAPMODE.....0x0103
META_SETPIXEL.....0x041F
META_SETPOLYFILLMODE.....0x0106
META_SETRELABS.....0x0105
META_SETROP2.....0x0104
META_SETSTRETCHBLTMODE.....0x0107
META_SETTEXTALIGN.....0x012E
META_SETTEXTCHAREXTRA.....0x0108
META_SETTEXTCOLOR.....0x0209
META_SETTEXTJUSTIFICATION.....0x020A
META_SETVIEWPORTEXT.....0x020E
META_SETVIEWPORTORG.....0x020D
META_SETWINDOWEXT.....0x020C
META_SETWINDOWORG.....0x020B
META_STRETCHBLT.....0x0B23
META_TEXTOUT.....0x0521

MFCOMMENT.....15

MF_APPEND.....0x0100
MF_BITMAP.....0x0004
MF_BYCOMMAND.....0x0000
MF_BYPOSITION.....0x0400
MF_CHANGE.....0x0080
MF_CHECKED.....0x0008
MF_DELETE.....0x0200
MF_DISABLED.....0x0002
MF_ENABLED.....0x0000
MF_END.....0x0080
MF_GRAYED.....0x0001
MF_HELP.....0x4000
MF_HILITE.....0x0080
MF_INSERT.....0x0000
MF_MENUBARBREAK.....0x0020
MF_MENUBREAK.....0x0040
MF_MOUSESELECT.....0x8000
MF_OWNERDRAW.....0x0100

MF_POPUP.....0x0010
MF_REMOVE.....0x1000
MF_SEPARATOR.....0x0800
MF_STRING.....0x0000
MF_SYSMENU.....0x2000
MF_UNCHECKED.....0x0000
MF_UNHILITE.....0x0000
MF_USECHECKBITMAPS.....0x0200

MK_CONTROL.....0x0008
MK_LBUTTON.....0x0001
MK_MBUTTON.....0x0010
MK_RBUTTON.....0x0002
MK_SHIFT.....0x0004

MM_ANISOTROPIC.....8
MM_HIENGLISH.....5
MM_HIMETRIC.....3
MM_ISOTROPIC.....7
MM_LOENGLISH.....4
MM_LOMETRIC.....2
MM_TEXT.....1
MM_TWIPS.....6

MSGF_DIALOGBOX.....0
MSGF_MENU.....2
MSGF_MESSAGEBOX.....1
MSGF_MOVE.....3
MSGF_NEXTWINDOW.....6
MSGF_SCROLLBAR.....5
MSGF_SIZE.....4

N

Constant Name	Value
NEWFRAME.....	1
NEXTBAND.....	3
NONZEROLHND.....	(LMEM_MOVEABLE)
NONZEROLPTR.....	(LMEM_FIXED)
NOPARITY.....	0
NOTSRCCOPY.....	(DWORD) 0x00330008
NOTSRCERASE.....	(DWORD) 0x001100A6
NULLREGION.....	1
NULL_BRUSH.....	5
NULL_PEN.....	8
NUMBRUSHES.....	16
NUMCOLORS.....	24
NUMFONTS.....	22
NUMMARKERS.....	20
NUMPENS.....	18
NUMRESERVED.....	106

O

Constant Name Value

OBJ_BRUSH.....	2
OBJ_PEN.....	1
OBM_BTNCORNERS.....	32758
OBM_BTSIZE.....	32761
OBM_CHECK.....	32760
OBM_CHECKBOXES.....	32759
OBM_CLOSE.....	32754
OBM_COMBO.....	32738
OBM_DNARROW.....	32752
OBM_DNARROWD.....	32742
OBM_LFARROW.....	32750
OBM_LFARROWD.....	32740
OBM_MNARROW.....	32739
OBM_OLD_CLOSE.....	32767
OBM_OLD_DNARROW.....	32764
OBM_OLD_LFARROW.....	32762
OBM_OLD_REDUCE.....	32757
OBM_OLD_RESTORE.....	32755
OBM_OLD_RGARROW.....	32763
OBM_OLD_UPARROW.....	32765
OBM_OLD_ZOOM.....	32756
OBM_REDUCE.....	32749
OBM_REDUCED.....	32746
OBM_RESTORE.....	32747
OBM_RESTORED.....	32744
OBM_RGARROW.....	32751
OBM_RGARROWD.....	32741
OBM_SIZE.....	32766
OBM_UPARROW.....	32753
OBM_UPARROWD.....	32743
OBM_ZOOM.....	32748
OBM_ZOOMD.....	32745
OCR_CROSS.....	32515
OCR_IBEAM.....	32513
OCR_ICOCUR.....	32647
OCR_ICON.....	32641
OCR_NORMAL.....	32512
OCR_SIZE.....	32640
OCR_SIZEALL.....	32646
OCR_SIZENESW.....	32643
OCR_SIZENS.....	32645
OCR_SIZENWSE.....	32642
OCR_SIZEW.....	32644
OCR_UP.....	32516
OCR_WAIT.....	32514
ODA_DRAWENTIRE.....	0x0001
ODA_FOCUS.....	0x0004
ODA_SELECT.....	0x0002
ODDPARITY.....	1

ODS_CHECKED.....0x0008
ODS_DISABLED.....0x0004
ODS_FOCUS.....0x0010
ODS_GRAYED.....0x0002
ODS_SELECTED.....0x0001

ODT_BUTTON.....4
ODT_COMBOBOX.....3
ODT_LISTBOX.....2
ODT_MENU.....1

OEM_CHARSET.....255
OEM_FIXED_FONT.....10

OF_CANCEL.....0x0800
OF_CREATE.....0x1000
OF_DELETE.....0x0200
OF_EXIST.....0x4000
OF_PARSE.....0x0100
OF_PROMPT.....0x2000
OF_READ.....0x0000
OF_READWRITE.....0x0002
OF_REOPEN.....0x8000
OF_SHARE_COMPAT.....0x0000
OF_SHARE_DENY_NONE.....0x0040
OF_SHARE_DENY_READ.....0x0030
OF_SHARE_DENY_WRITE.....0x0020
OF_SHARE_EXCLUSIVE.....0x0010
OF_VERIFY.....0x0400
OF_WRITE.....0x0001

OIC_BANG.....32515
OIC_HAND.....32513
OIC_NOTE.....32516
OIC_QUES.....32514
OIC_SAMPLE.....32512

ONE5STOPBITS.....1
ONESTOPBIT.....0

OPAQUE.....2
ORD_LANGDRIVER.....1

OUT_CHARACTER_PRECIS.....2
OUT_DEFAULT_PRECIS.....0
OUT_STRING_PRECIS.....1
OUT_STROKE_PRECIS.....3

P

Constant Name	Value
PASSTHROUGH.....	19
PATCOPY.....	(DWORD) 0x00F00021
PATINVERT.....	(DWORD) 0x005A0049
PATPAINT.....	(DWORD) 0x00FB0A09
PC_EXPLICIT.....	0x02
PC_INTERIORS.....	128
PC_NONE.....	0
PC_POLYGON.....	1
PC_RECTANGLE.....	2
PC_RESERVED.....	0x01
PC_SCANLINE.....	8
PC_STYLED.....	32
PC_TRAPEZOID.....	4
PC_WIDE.....	16
PC_WIDESTYLED.....	64
PC_WINDPOLYGON.....	4
PDEVICESIZE.....	26
PLANES.....	14
PM_NOREMOVE.....	0x0000
PM_NOYIELD.....	0x0002
PM_REMOVE.....	0x0001
POLYGONALCAPS.....	32
POSTSCRIPT_DATA.....	37
POSTSCRIPT_IGNORE.....	38
PROOF_QUALITY.....	2
PR_JOBSTATUS.....	0x0000
PS_DASH.....	1
PS_DASHDOT.....	3
PS_DASHDOTDOT.....	4
PS_DOT.....	2
PS_INSIDEFRAME.....	6
PS_NULL.....	5
PS_SOLID.....	0

Q

Constant Name

Value

QUERYESCSUPPORT.....8

R

Constant Name	Value
R2_BLACK.....	1
R2_COPYPEN.....	13
R2_MASKNOTPEN.....	3
R2_MASKPEN.....	9
R2_MASKPENNOT.....	5
R2_MERGENOTPEN.....	12
R2_MERGEPEN.....	15
R2_MERGEPENNOT.....	14
R2_NOP.....	11
R2_NOT.....	6
R2_NOTCOPYPEN.....	4
R2_NOTMASKPEN.....	8
R2_NOTMERGEPEN.....	2
R2_NOTXORPEN.....	10
R2_WHITE.....	16
R2_XORPEN.....	7
RASTERCAPS.....	38
RASTER_FONTTYPE.....	0x0001
RC_BANDING.....	2
RC_BITBLT.....	1
RC_BITMAP64.....	8
RC_SCALING.....	4
READ.....	0
READ_WRITE.....	2
RELATIVE.....	2
RESETDEV.....	7
RESTORE_CTM.....	4100
RGN_AND.....	1
RGN_COPY.....	5
RGN_DIFF.....	4
RGN_OR.....	2
RGN_XOR.....	3

S

Constant Name	Value
SAVE_CTM.....	4101
SBS_BOTTOMALIGN.....	0x0004L
SBS_HORZ.....	0x0000L
SBS_LEFTALIGN.....	0x0002L
SBS_RIGHTALIGN.....	0x0004L
SBS_SIZEBOX.....	0x0008L
SBS_SIZEBOXBOTTOMRIGHTALIGN...	0x0004L
SBS_SIZEBOXTOPLEFTALIGN.....	0x0002L
SBS_TOPALIGN.....	0x0002L
SBS_VERT.....	0x0001L
SB_BOTH.....	3
SB_BOTTOM.....	7
SB_CTL.....	2
SB_ENDSCROLL.....	8
SB_HORZ.....	0
SB_LINEDOWN.....	1
SB_LINEUP.....	0
SB_PAGEDOWN.....	3
SB_PAGEUP.....	2
SB_THUMBPOSITION.....	4
SB_THUMBTRACK.....	5
SB_TOP.....	6
SB_VERT.....	1
SC_ARRANGE.....	0xF110
SC_CLOSE.....	0xF060
SC_HSCROLL.....	0xF080
SC_ICON.....	SC_MINIMIZE
SC_KEYMENU.....	0xF100
SC_MAXIMIZE.....	0xF030
SC_MINIMIZE.....	0xF020
SC_MOUSEMENU.....	0xF090
SC_MOVE.....	0xF010
SC_NEXTWINDOW.....	0xF040
SC_PREVWINDOW.....	0xF050
SC_RESTORE.....	0xF120
SC_SIZE.....	0xF000
SC_TASKLIST.....	0xF130
SC_VSCROLL.....	0xF070
SC_ZOOM.....	SC_MAXIMIZE
SELECTPAPERSOURCE.....	18
SETABORTPROC.....	9
SETALLJUSTVALUES.....	771
SETCHARSET.....	772
SETCOLORTABLE.....	4
SETCOPYCOUNT.....	17
SETDIBSCALING.....	32
SETDTR.....	5
SETENDCAP.....	21

SETKERNTRACK.....	770
SETLINEJOIN.....	22
SETMITERLIMIT.....	23
SETRTS.....	3
SETXOFF.....	1
SETXON.....	2
SET_ARC_DIRECTION.....	4102
SET_BACKGROUND_COLOR.....	4103
SET_BOUNDS.....	4109
SET_CLIP_BOX.....	4108
SET_MIRROR_MODE.....	4110
SET_POLY_MODE.....	4104
SET_SCREEN_ANGLE.....	4105
SET_SPREAD.....	4106
SHIFTJIS_CHARSET.....	128
SHOW_FULLSCREEN.....	3
SHOW_ICONWINDOW.....	2
SHOW_OPENNOACTIVATE.....	4
SHOW_OPENWINDOW.....	1
SIMPLEREGION.....	2
SIZEFULLSCREEN.....	2
SIZEICONIC.....	1
SIZENORMAL.....	0
SIZEPALETTE.....	104
SIZEZOOMHIDE.....	4
SIZEZOOMSHOW.....	3
SM_CMETRICS.....	36
SM_CXBORDER.....	5
SM_CXCURSOR.....	13
SM_CXDLGFRAME.....	7
SM_CXFRAME.....	32
SM_CXFULLSCREEN.....	16
SM_CXHSCROLL.....	21
SM_CXHTHUMB.....	10
SM_CXICON.....	11
SM_CXMIN.....	28
SM_CXMINTRACK.....	34
SM_CXSCREEN.....	0
SM_CXSIZE.....	30
SM_CXVSCROLL.....	2
SM_CYBORDER.....	6
SM_CYCAPTION.....	4
SM_CYCURSOR.....	14
SM_CYDLGFRAME.....	8
SM_CYFRAME.....	33
SM_CYFULLSCREEN.....	17
SM_CYHSCROLL.....	3
SM_CYICON.....	12
SM_CYKANJIWINDOW.....	18
SM_CYMENU.....	15
SM_CYMIN.....	29
SM_CYMINTRACK.....	35

SM_CYScreen.....1
SM_CYSIZE.....31
SM_CyVScroll.....20
SM_CyVThumb.....9
SM_DEBUG.....22
SM_MOUSEPRESENT.....19
SM_RESERVED1.....24
SM_RESERVED2.....25
SM_RESERVED3.....26
SM_RESERVED4.....27
SM_SWAPBUTTON.....23

SPACEPARITY.....4

SP_APPABORT.....(-2)
SP_ERROR.....(-1)
SP_NOTREPORTED.....0x4000
SP_OUTOFDISK.....(-4)
SP_OUTOFMEMORY.....(-5)
SP_USERABORT.....(-3)

SRCAND.....(DWORD) 0x008800C6
SRCCOPY.....(DWORD) 0x00CC0020
SRCERASE.....(DWORD) 0x00440328
SRCINVERT.....(DWORD) 0x00660046
SRCPAINT.....(DWORD) 0x00EE0086

SS_BLACKFRAME.....0x07L
SS_BLACKRECT.....0x04L
SS_CENTER.....0x01L
SS_GRAYFRAME.....0x08L
SS_GRAYRECT.....0x05L
SS_ICON.....0x03L
SS_LEFT.....0x00L
SS_LEFTNOWORDWRAP.....0x0CL
SS_NOPREFIX.....0x80L
SS_RIGHT.....0x02L
SS_SIMPLE.....0x0BL
SS_USERITEM.....0x0AL
SS_WHITEFRAME.....0x09L
SS_WHITERECT.....0x06L

STARTDOC.....10
STRETCHBLT.....2048

ST_BEGINSWP.....0
ST_ENDSWP.....1

SWP_DRAWFRAME.....0x0020
SWP_HIDEWINDOW.....0x0080
SWP_NOACTIVATE.....0x0010
SWP_NOCOPYBITS.....0x0100
SWP_NOMOVE.....0x0002
SWP_NOREDRAw.....0x0008
SWP_NOREPOSITION.....0x0200
SWP_NOSIZE.....0x0001
SWP_NOZORDER.....0x0004

SWP_SHOWWINDOW.....0x0040

SW_HIDE.....0
SW_MAXIMIZE.....3
SW_MINIMIZE.....6
SW_NORMAL.....1
SW_OTHERUNZOOM.....4
SW_OTHERZOOM.....2
SW_PARENTCLOSING.....1
SW_PARENTOPENING.....3
SW_RESTORE.....9
SW_SHOW.....5
SW_SHOWMAXIMIZED.....3
SW_SHOWMINIMIZED.....2
SW_SHOWMINNOACTIVE.....7
SW_SHOWNA.....8
SW_SHOWNOACTIVATE.....4
SW_SHOWNORMAL.....1

SYMBOL_CHARSET.....2

SYSTEM_FIXED_FONT.....16

SYSTEM_FONT.....13

S_ALLTHRESHOLD.....2

S_LEGATO.....1

S_NORMAL.....0

S_PERIOD1024.....1

S_PERIOD2048.....2

S_PERIOD512.....0

S_PERIODVOICE.....3

S_QUEUEEMPTY.....0

S_SERBDNT.....(-5)

S_SERDCC.....(-7)

S_SERDDR.....(-14)

S_SERDFQ.....(-13)

S_SERDLN.....(-6)

S_SERDMD.....(-10)

S_SERDPT.....(-12)

S_SERDSH.....(-11)

S_SERDSR.....(-15)

S_SERDST.....(-16)

S_SERDTP.....(-8)

S_SERDVL.....(-9)

S_SERDVNA.....(-1)

S_SERMACT.....(-3)

S_SEROFM.....(-2)

S_SERQFUL.....(-4)

S_STACCATO.....2

S_THRESHOLD.....1

S_WHITE1024.....5

S_WHITE2048.....6

S_WHITE512.....4

S_WHITEVOICE.....7

T

Constant Name	Value
TA_BASELINE.....	24
TA_BOTTOM.....	8
TA_CENTER.....	6
TA_LEFT.....	0
TA_NOUPDATECP.....	0
TA_RIGHT.....	2
TA_TOP.....	0
TA_UPDATECP.....	1
TC_CP_STROKE.....	0x0004
TC_CR_90.....	0x0008
TC_CR_ANY.....	0x0010
TC_EA_DOUBLE.....	0x0200
TC_IA_ABLE.....	0x0400
TC_OP_CHARACTER.....	0x0001
TC_OP_STROKE.....	0x0002
TC_RA_ABLE.....	0x2000
TC_RESERVED.....	0x8000
TC_SA_CONTIN.....	0x0100
TC_SA_DOUBLE.....	0x0040
TC_SA_INTEGER.....	0x0080
TC_SF_X_YINDEP.....	0x0020
TC_SO_ABLE.....	0x1000
TC_UA_ABLE.....	0x0800
TC_VA_ABLE.....	0x4000
TECHNOLOGY.....	2
TEXTCAPS.....	34
TF_FORCEDRIVE.....	(BYTE) 0x80
TRANSFORM_CTM.....	4107
TRANSPARENT.....	1
TWOSTOPBITS.....	2

V

Constant Name Value

VARIABLE_PITCH.....	2
VERTRES.....	10
VERTSIZE.....	6
VK_ACCEPT.....	0x1E
VK_ADD.....	0x6B
VK_BACK.....	0x08
VK_CANCEL.....	0x03
VK_CAPITAL.....	0x14
VK_CLEAR.....	0x0C
VK_CONTROL.....	0x11
VK_CONVERT.....	0x1C
VK_DECIMAL.....	0x6E
VK_DELETE.....	0x2E
VK_DIVIDE.....	0x6F
VK_DOWN.....	0x28
VK_END.....	0x23
VK_ESCAPE.....	0x1B
VK_EXECUTE.....	0x2B
VK_F1.....	0x70
VK_F10.....	0x79
VK_F11.....	0x7A
VK_F12.....	0x7B
VK_F13.....	0x7C
VK_F14.....	0x7D
VK_F15.....	0x7E
VK_F16.....	0x7F
VK_F2.....	0x71
VK_F3.....	0x72
VK_F4.....	0x73
VK_F5.....	0x74
VK_F6.....	0x75
VK_F7.....	0x76
VK_F8.....	0x77
VK_F9.....	0x78
VK_HELP.....	0x2F
VK_HIRAGANA.....	0x18
VK_HOME.....	0x24
VK_INSERT.....	0x2D
VK_KANA.....	0x15
VK_KANJI.....	0x19
VK_LBUTTON.....	0x01
VK_LEFT.....	0x25
VK_MBUTTON.....	0x04
VK_MENU.....	0x12
VK_MODECHANGE.....	0x1F
VK_MULTIPLY.....	0x6A
VK_NEXT.....	0x22
VK_NONCONVERT.....	0x1D
VK_NUMLOCK.....	0x90
VK_NUMPAD0.....	0x60
VK_NUMPAD1.....	0x61

VK_NUMPAD2.....0x62
VK_NUMPAD3.....0x63
VK_NUMPAD4.....0x64
VK_NUMPAD5.....0x65
VK_NUMPAD6.....0x66
VK_NUMPAD7.....0x67
VK_NUMPAD8.....0x68
VK_NUMPAD9.....0x69
VK_PAUSE.....0x13
VK_PRINT.....0x2A
VK_PRIOR.....0x21
VK_RBUTTON.....0x02
VK_RETURN.....0x0D
VK_RIGHT.....0x27
VK_ROMAJI.....0x16
VK_SELECT.....0x29
VK_SEPARATOR.....0x6C
VK_SHIFT.....0x10
VK_SNAPSHOT.....0x2C
VK_SPACE.....0x20
VK_SUBTRACT.....0x6D
VK_TAB.....0x09
VK_UP.....0x26
VK_ZENKAKU.....0x17

W

Constant Name	Value
WC_DEFWINDOWPROC.....	3
WC_DRAWCAPTION.....	7
WC_INIT.....	1
WC_MINMAX.....	4
WC_MOVE.....	5
WC_SIZE.....	6
WC_SWP.....	2
WF_80x87.....	0x0400
WF_CPU086.....	0x0040
WF_CPU186.....	0x0080
WF_CPU286.....	0x0002
WF_CPU386.....	0x0004
WF_CPU486.....	0x0008
WF_ENHANCED.....	0x0020
WF_LARGEFRAME.....	0x0100
WF_PMODE.....	0x0001
WF_SMALLFRAME.....	0x0200
WF_STANDARD.....	0x0010
WF_WIN286.....	0x0010
WF_WIN386.....	0x0020
WHITENESS.....	(DWORD) 0x00FF0062
WHITEONBLACK.....	2
WHITE_BRUSH.....	0
WHITE_PEN.....	6
WH_CALLWNDPROC.....	4
WH_CBT.....	5
WH_GETMESSAGE.....	3
WH_JOURNALPLAYBACK.....	1
WH_JOURNALRECORD.....	0
WH_KEYBOARD.....	2
WH_MSGFILTER.....	(-1)
WH_SYSMSGFILTER.....	6
WH_WINDOWMGR.....	7
WINDING.....	2
WM_ACTIVATE.....	0x0006
WM_ACTIVATEAPP.....	0x001C
WM_ASKCBFORMATNAME.....	0x030C
WM_CANCELMODE.....	0x001F
WM_CHANGECHAIN.....	0x030D
WM_CHAR.....	0x0102
WM_CHARTOITEM.....	0x002F
WM_CHILDACTIVATE.....	0x0022
WM_CLEAR.....	0x0303
WM_CLOSE.....	0x0010
WM_COMMAND.....	0x0111
WM_COMPACTING.....	0x0041
WM_COMPAREITEM.....	0x0039
WM_COPY.....	0x0301

WM_CREATE.....0x0001
WM_CTLCOLOR.....0x0019
WM_CUT.....0x0300
WM_DEADCHAR.....0x0103
WM_DELETEITEM.....0x002D
WM_DESTROY.....0x0002
WM_DESTROYCLIPBOARD.....0x0307
WM_DEVMODECHANGE.....0x001B
WM_DRAWCLIPBOARD.....0x0308
WM_DRAWITEM.....0x002B
WM_ENABLE.....0x000A
WM_ENDSESSION.....0x0016
WM_ENTERIDLE.....0x0121
WM_ERASEBKGD.....0x0014
WM_FONTCHANGE.....0x001D
WM_GETDLGCODE.....0x0087
WM_GETFONT.....0x0031
WM_GETMINMAXINFO.....0x0024
WM_GETTEXT.....0x000D
WM_GETTEXTLENGTH.....0x000E
WM_HSCROLL.....0x0114
WM_HSCROLLCLIPBOARD.....0x030E
WM_ICONERASEBKGD.....0x0027
WM_INITDIALOG.....0x0110
WM_INITMENU.....0x0116
WM_INITMENUPOPUP.....0x0117
WM_KEYDOWN.....0x0100
WM_KEYFIRST.....0x0100
WM_KEYLAST.....0x0108
WM_KEYUP.....0x0101
WM_KILLFOCUS.....0x0008
WM_LBUTTONDOWNCLK.....0x0203
WM_LBUTTONDOWN.....0x0201
WM_LBUTTONUP.....0x0202
WM_MBUTTONDOWNCLK.....0x0209
WM_MBUTTONDOWN.....0x0207
WM_MBUTTONUP.....0x0208
WM_MDIACTIVATE.....0x0222
WM_MDICASCADE.....0x0227
WM_MDICREATE.....0x0220
WM_MDIDESTROY.....0x0221
WM_MDIGETACTIVE.....0x0229
WM_MDIICONARRANGE.....0x0228
WM_MDIMAXIMIZE.....0x0225
WM_MDINEXT.....0x0224
WM_MDIRESTORE.....0x0223
WM_MDISETMENU.....0x0230
WM_MDIITILE.....0x0226
WM_MEASUREITEM.....0x002C
WM_MENUCHAR.....0x0120
WM_MENUSELECT.....0x011F
WM_MOUSEACTIVATE.....0x0021
WM_MOUSEFIRST.....0x0200
WM_MOUSELAST.....0x0209
WM_MOUSEMOVE.....0x0200
WM_MOVE.....0x0003
WM_NCACTIVATE.....0x0086

WM_NCCALCSIZE.....0x0083
WM_NCCREATE.....0x0081
WM_NCDESTROY.....0x0082
WM_NCHITTEST.....0x0084
WM_NCLBUTTONDBLCLK.....0x00A3
WM_NCLBUTTONDOWN.....0x00A1
WM_NCLBUTTONUP.....0x00A2
WM_NCMBUTTONDBLCLK.....0x00A9
WM_NCMBUTTONDOWN.....0x00A7
WM_NCMBUTTONUP.....0x00A8
WM_NCMOUSEMOVE.....0x00A0
WM_NCPAINT.....0x0085
WM_NCRBUTTONDBLCLK.....0x00A6
WM_NCRBUTTONDOWN.....0x00A4
WM_NCRBUTTONUP.....0x00A5
WM_NEXTDLGCTL.....0x0028
WM_NULL.....0x0000
WM_PAINT.....0x000F
WM_PAINTCLIPBOARD.....0x0309
WM_PAINTICON.....0x0026
WM_PALETTECHANGED.....0x0311
WM_PALETTEISCHANGING.....0x0310
WM_PARENTNOTIFY.....0x0210
WM_PASTE.....0x0302
WM_QUERYDRAGICON.....0x0037
WM_QUERYENDSESSION.....0x0011
WM_QUERYNEWPALETTE.....0x030F
WM_QUERYOPEN.....0x0013
WM_QUEUESYNC.....0x0023
WM_QUIT.....0x0012
WM_RBUTTONDBLCLK.....0x0206
WM_RBUTTONDOWN.....0x0204
WM_RBUTTONUP.....0x0205
WM_RENDERALLFORMATS.....0x0306
WM_RENDERFORMAT.....0x0305
WM_SETCURSOR.....0x0020
WM_SETFOCUS.....0x0007
WM_SETFONT.....0x0030
WM_SETREDRAW.....0x000B
WM_SETTEXT.....0x000C
WM_SHOWWINDOW.....0x0018
WM_SIZE.....0x0005
WM_SIZECLIPBOARD.....0x030B
WM_SPOOLERSTATUS.....0x002A
WM_SYSCHAR.....0x0106
WM_SYSCOLORCHANGE.....0x0015
WM_SYSCOMMAND.....0x0112
WM_SYSDEADCHAR.....0x0107
WM_SYSKEYDOWN.....0x0104
WM_SYSKEYUP.....0x0105
WM_TIMECHANGE.....0x001E
WM_TIMER.....0x0113
WM_UNDO.....0x0304
WM_USER.....0x0400
WM_VKEYTOITEM.....0x002E
WM_VSCROLL.....0x0115
WM_VSCROLLCLIPBOARD.....0x030A

```

WM_WININICHANGE.....0x001A

WRITE.....1

WS_BORDER.....0x00800000L
WS_CAPTION.....0x00C00000L
WS_CHILD.....0x40000000L
WS_CHILDWINDOW.....(WS_CHILD)
WS_CLIPCHILDREN.....0x02000000L
WS_CLIPSIBLINGS.....0x04000000L
WS_DISABLED.....0x08000000L
WS_DLGMFRAME.....0x00400000L
WS_EX_DLGMODALFRAME.....0x00000001L
WS_EX_NOPARENTNOTIFY.....0x00000004L
WS_GROUP.....0x00020000L
WS_HSCROLL.....0x00100000L
WS_ICONIC.....WS_MINIMIZE
WS_MAXIMIZE.....0x01000000L
WS_MAXIMIZEBOX.....0x00010000L
WS_MINIMIZE.....0x20000000L
WS_MINIMIZEBOX.....0x00020000L
WS_OVERLAPPED.....0x00000000L
WS_OVERLAPPEDWINDOW.....(WS_OVERLAPPED | WS_CAPTION | WS_SYSMENU |
                           WS_THICKFRAME | WS_MINIMIZEBOX |
                           WS_MAXIMIZEBOX)
WS_POPUP.....0x80000000L
WS_POPUPWINDOW.....(WS_POPUP | WS_BORDER | WS_SYSMENU)
WS_SIZEBOX.....WS_THICKFRAME
WS_SYSMENU.....0x00080000L
WS_TABSTOP.....0x00010000L
WS_THICKFRAME.....0x00040000L
WS_TILED.....WS_OVERLAPPED
WS_TILEDWINDOW.....(WS_OVERLAPPEDWINDOW)
WS_VISIBLE.....0x10000000L
WS_VSCROLL.....0x00200000L

```