

PageSetup Object

The **PageSetup** Object provides properties for retrieving information and setting options for page setup in a report (i.e., paper size, margins, etc.). A PageSetup Object is obtained from the PageSetup property of the **Report** Object.

Properties

Application - Returns a reference to the Application Object this object is associated with. Read only.

BottomMargin - Returns/Sets value specifying the bottom margin*. Read/Write.

LeftMargin - Returns/Sets value specifying the left margin.* Read/Write.

PaperOrientation - Returns/Sets CRPaperOrientation (see table below) indicating the paper orientation. Read/Write.

crDefaultPaperOrientation	0
crLandscape	2
crPortrait	1

PaperSize - Returns/Sets CRPaperSize (see table below) indicating the paper size. Check your printer documentation for a list of paper sizes available for use with your printer. If you choose an unavailable paper size, the default (letter) size will be used. Read/Write.

crDefaultPaperSize	0
crPaper10x14	16
crPaper11x17	17
crPaperA3	8
crPaperA4	9
crPaperA4Small	10
crPaperA5	11
crPaperB4	12
crPaperB5	13
crPaperCsheet	24
crPaperDsheet	25
crPaperEnvelope10	20
crPaperEnvelope11	21
crPaperEnvelope12	22
crPaperEnvelope14	23
crPaperEnvelope9	19
crPaperEnvelopeB4	33
crPaperEnvelopeB5	34
crPaperEnvelopeB6	35
crPaperEnvelopeC3	28
crPaperEnvelopeC4	29
crPaperEnvelopeC5	30
crPaperEnvelopeC6	31
crPaperEnvelopeC65	32
crPaperEnvelopeDL	27
crPaperEnvelopeItaly	36
crPaperEnvelopeMonarch	37
crPaperEnvelopePersonal	38
crPaperEsheet	26
crPaperExecutive	7
crPaperFanfoldLegalGerman	41
crPaperFanfoldStdGerman	40
crPaperFanfoldUS	39

crPaperFolio	14
crPaperLedger	4
crPaperLegal	5
crPaperLetter	1
crPaperLetterSmall	2
crPaperNote	18
crPaperQuarto	15
crPaperStatement	6
crPaperTabloid	3

Parent - Reference to the Parent object (Report Object). Read only.

Report - Reference to Report Object. Read only.

RightMargin - Returns/Sets value specifying the right margin.* Read/Write.

TopMargin - Returns/Sets value specifying the top margin.* Read/Write.

** Left, right, top, and bottom values are all in twips. A twip is 1/1440 of an inch; there are 20 twips in a point. To set .5" margins, for example, you would enter the value 720.*



Left, right, top, and bottom are set to -1 by default. Unless otherwise specified, the default margins set in the report are used.