

Chapter 1

About UnixWare 7 systems

The UnixWare® 7 product line is a family of runtime software, development kits, and optional licenses, products, and services that enable you to tailor a system to meet your computing needs.

This guide discusses installing the base operating system and optional components from the numbered UnixWare 7 CD-ROMs (for example: disks 1, 2, and 3 of 3). For the latest information on the contents of your media kit, refer to the *Installation Roadmap* provided with your software.

UnixWare 7 licenses

When you install UnixWare 7 runtime software, you enter a license corresponding to a UnixWare 7 “Edition”, a collection of software targeted to a specific purpose.

The installation conveniently selects the appropriate software sets, services, and packages to install based on your license, allowing you to bypass the software selection phase of the installation. If you want to customize software selection, you can use the licensed defaults as a base from which to install additional services and packages or remove those you do not need.

This list of Editions matches currently shipping software. When you receive UnixWare 7, more Editions may be available and the contents of some Editions may have changed. For example, later releases of some products may be included, and obsolete products may be removed.

The UnixWare 7 Editions are:

Base Edition

The Base Edition supports one user and one CPU, and includes networking functionality and SCO ARCserve/Open Lite.

About UnixWare 7 systems

Business Edition

The Business Edition supports up to 5 users and 1 CPU, and includes networking functionality, SCO VisionFS™, and SCO ARCserve/Open Lite.

Departmental Edition

The Departmental Edition supports up to 25 users and 2 CPUs, and includes SCO VisionFS file and print services and full SCO ARCserve/Open backup and restore functionality.

Development Edition

The Development Edition includes software from the Development Kits CD-ROM. For more information on this Edition, see the *Release Notes* for the UnixWare and OpenServer Development Kit.

Enterprise Edition

The Enterprise Edition supports up to 50 users and 4 CPUs, plus full Online Data Manager (ODM) functionality, SCO VisionFS (full version), and SCO ARCserve/Open (full version).

Intranet Edition

The Intranet Edition supports one user and up to 2 CPUs, and includes SCO ARCserve/Open (full version), SCO VisionFS, Netscape Enterprise Server™, and Netscape Directory Server™.

Messaging Edition

The Messaging Edition supports one user and up to 2 CPUs, and includes SCO ARCserve/Open (full version), Netscape Mail Server™, and Netscape Directory Server.

Evaluation licenses

The license you enter during the installation transparently selects the correct services and packages to install on your system. If you choose to defer licensing during the installation, or if you install products not included with your license, you will be issued a free 60-day trial license. If you want to continue to use the software after that time, contact your vendor to purchase a license, then use the SCOadmin **License Manager** to remove the evaluation license(s) and re-license the software.

If you defer licensing during installation, the system will be installed using Departmental Edition service and package selection defaults.

NOTE The Strong Encryption Supplement is not available with an evaluation license. You must purchase a license to install this supplement.

UnixWare 7 system profiles

During the installation procedure, you can choose to install:

License-Based Defaults

This choice installs services and packages based on the license you purchased and entered. Selecting this option ensures that only appropriate, fully-licensed software is installed on your system.

Small Footprint Server

This choice installs a subset of services optimized to work well on systems with limited memory and disk capacity. It contains the base operating system and networking utilities; it does not contain graphics support or SCO ARCserve/Open.

Full (All Packages)

This choice enables all services and packages available on the media, with the exception of supplemental languages and multi-processor support. To add these packages, you must select the **Customize Installation of Packages** profile.

Customize Installation of Packages

You decide which services and packages to load (or not load) onto the system. The defaults enabled are based on the license you enter during the installation.

NOTE If you choose **Customize Installation of Packages** or **Full (All Packages)**, read "Evaluation licenses" (page 6) to determine how to license the additional software you might install.

For a complete description of all available services and packages, see the *Runtime Release Notes*.

Media

The contents of the UnixWare media kit are described in the *Installation Roadmap* provided with your software.

If you are performing a networked installation, you must create two 3.5 inch Network Installation Utilities diskettes from the images found in the */info/images* directory on the UnixWare Installation CD-ROM. See (*/info/images/readme.htm*) for more information.

In addition to the UnixWare media, your vendor may have provided you with one or more additional Host Bus Adapter (HBA) diskettes to support new hardware.

Printed documentation

The following printed documentation is included in the UnixWare 7 media kit:

- This *Installation Guide*.
- The *Runtime Release Notes*, which describe late-breaking features and limitations of your UnixWare 7 system.
- The *UnixWare 7 System Handbook*, which describes common system administration and troubleshooting tasks.

See “Related documentation” (page 2) for detailed information about the UnixWare 7 documentation set.

Free* UnixWare 7

Free* UnixWare 7, a functional, single-user version of UnixWare 7, is available for non-commercial and educational use. Free* UnixWare 7 must be licensed (using the license information obtained from the web site listed below), but does not need to be registered through the callback registration process.

The Free* UnixWare 7 media kit, including UnixWare 7 runtime and development system software and documentation, is available for a small materials and shipping cost.

For more information, including information on ordering and licensing Free* UnixWare 7, point your web browser to <http://www.sco.com/offers/>.

Accessing SCO Services information online

The SCO World Wide Web home page contains detailed information about SCO support services.

To access this information, point your web browser to <http://www.sco.com> and click on “Support and Services”.

Finding SCO training

SCO Authorized Education Centers around the world offer training in the use and administration of SCO products. To learn more about available training:

- From anywhere in the world, access the SCO Training home page (<http://www.sco.com/Training>).
- In the United States or Canada, call 1-800-SCO-UNIX (1-800-726-8649).



About UnixWare 7 systems