

ACEHTML 6 README FILE

(C)1996-2005 Visicom Media Inc. All rights reserved.

SUMMARY

- I. WHAT'S NEW IN ACEHTML 6
- II. HOW TO ORDER ACEHTML 6 PRO
- III. HOW TO GET SUPPORT ON ACEHTML
- IV. SYSTEM REQUIREMENTS
- V. AVAILABLE RESOURCES
- VI. THIRD PARTIES SUPPORT
- VII. SEND YOUR COMMENTS

I. WHAT'S NEW IN ACEHTML 6

New Features of AceHTML 6 Pro

- File Editing Directly from the Server
- Server Mapping
- Improved Interface
- Code Snippets
- ASP and PHP Code Completion
- ASP and PHP Syntax Checker
- Full-Site Link Checking

For a full list of features, please visit:

<http://software.visicommedia.com/en/products/acehtml/features/>

II. HOW TO ORDER ACEHTML 6 PRO

To place your order connect to our online store at the following address:

<http://softwares.visicommedia.com/en/store/>

Payment Methods

- Pay by Visa, MasterCard, American Express, or Paypal.
- North American companies and institutions can place an order by using an official purchase order.
- Wire transfers are not accepted unless the order is for multiple licenses. Please contact customer service.

Volume Licensing

We offer volume discounts to corporations, small businesses, education, and government. Starting at 4 copies or more, you can get up to 50% discount for a full site license. Get more info by writing at this email address:

customer@visicommedia.com

Contact Information

Customer Service
Visicom Media Inc.
6200, Taschereau Blvd, #304
Brossard, QC
Canada
J4W 3J8
phone: (450) 672-0401
Fax: (450) 672-9586

III. HOW TO GET SUPPORT ON ACEHTML

For questions and problems using AceHTML, please refer to the support section of our Web site:

<http://software.visicommedia.com/en/support/>

IV. SYSTEM REQUIREMENTS

Following are the minimum system requirements you need to install and run AceHTML:

- 1 Pentium based processor.
- 2 Operating system: Windows 98, ME, 2000, XP or NT4 (SP5 or better).
- 3 Internet Explorer 5.00 or better.
- 4 64MB (128MB for Windows NT or 2000).

V. AVAILABLE RESOURCES

- 5 AceFTP: Extreme Flexibility for Internet File Transfers

<http://softwares.visicommedia.com/en/products/aceftp/>

- 6 Gograph, Your Ultimate Source of Web Graphics:

<http://www.gograph.com/>

VI. THIRD PARTIES SUPPORT

- 7 Third party help files

Other help files can be associated to AceHTML to replace the existing references. A list of help files needs to be included in a file named "**help.ini**" in the subfolder /help

[HELPPFILES]

```
HTML= [URL | PATH TO .CHM | PATH TO .HLP]
PHP= [URL | PATH TO .CHM | PATH TO .HLP]
ASP= [URL | PATH TO .CHM | PATH TO .HLP]
CSS= [URL | PATH TO .CHM | PATH TO .HLP]
JS= [URL | PATH TO .CHM | PATH TO .HLP]
```

;That section is to use only for html to pass the F1 parameter

```
[KWFILES]
HTML= [URL?kw=%s]
PHP= [URL?kw=%s]
ASP= [URL?kw=%s]
CSS= [URL?kw=%s]
JS= [URL?kw=%s]
```

e.g.

```
[HELPPFILES]
HTML=c:\program files\Visicom Media\AceHTML 6 Pro\help\myhtmlhelp.hlp
PHP=c:\program files\Visicom Media\AceHTML 6 Pro\help\phphelp.chm
JS=http://www.visicommedia.com/javascript.html
```

```
[KWFILES]
JS=http://www.visicommedia.com/javascript.html?kw=%s
```

- 8 The URL in the about can be changed for distribution partners. A file named "**about.ini**" must be located in the AceHTML root folder.

```
[ABOUT]
HOSTURL=[URL]
```

e.g.

```
[ABOUT]
HOSTURL=http://www.visicommedia.com
```

VII. SEND US YOUR COMMENTS

Please do not hesitate to contact us with any suggestions or inquiries you may have:

<http://softwares.visicommedia.com/en/support/feedback.html>