

Sheet1

```
\s    {MENUBRANCH main}

main  HP Laser
      Go to HP Laser Jet Settings
      {MENUBRANCH hp}

hp    1. Land
      Landscape, 176 columns, 45 lines per page.
      /pposBLANK~s{esc}\027E\027&l1o\027&k2S~
      mr176~
      p45~
      qq

epson 1. Condensed
      Condensed 132 columns, Double Struck, 88 Lines per Page.
      /pposBLANK~s{esc}\015\027\071\027\048~
      mr132~
      p88~
      qq

\p    /ppagq
```

This macro will use Lotus style menus to allow you to change the set up string, margins and page lengths for the most commonly used HP Laser and Epson printer settings. I suggest that you combine this macro in and out of the way location (HA4000) on your spreadsheet and set it up ready to use.

It contains two parts; \s and \p. The \s will display the menus so you can select the type of printing you need, while the \p will print your selected print range. Note: the page function does not work properly on the HP Laser printer so you will need to take it off line and eject the last page manually.

To invoke the macro hold down the macro key (Alt on most computers) and press the "s" or the "p" key.

If you combined this with another spreadsheet you will have to name the column to the right of the \s. To do this place the cursor on the \s and press slash (/), Range (R), Name (N), Lables (L), Right (R), Page Down and Enter. THis will name the column to the right of the \s to the names in the column with the \s.

Sheet1

Epson
Go to Epson Settings
{MENUBRANCH epon}

2. Land
Landscape, 176 columns, 66 lines per page.
/pposBLANK~s{esc}\027E\027&l1o2e5.647c66F\027&k2S~
mr176~
p66~
qq

2. Condensed
Condensed 132 columns, 66 Lines per Page.
/pposBLANK~s{esc}\015~
mr132~
p66~
qq

Quit
Return to Ready Mode
{QUIT}

3. Land
Landscape, 106 columns, 45 lines per page.
/pposBLANK~s{esc}\027E\027&l1o~
mr106~
p45~
qq

3. Enhanced
Normal print, Double Struck
/pposBLANK~s{esc}\027\071~
mr80~
p66~
qq

Sheet1

4. Land

Landscape, 106 columns, 66 lines per page.

/pposBLANK~s{esc}\027E\027&l1o2e5.647c66F~

mr106~

p66~

qq

Print

Send your selected print range to the printer.

{\p}

/ppppq

5. Portrait

Portrait, 132 columns, 60 lines per page.

/pposBLANK~s{esc}\027E\027&k2S~

mr132~

p60~

qq

Quit

Return to READY

{QUIT}

Sheet1

6. Portrait

Portrait, 132 columns, 89 lines per page.

/pposBLANK~s{esc}\027E\027&l2e5.647c89F\027&k2S~

mr132~

p89~

qq

7. Portrait

Portrait, 80 columns, 66 lines per page.

/pposBLANK~s{esc}\027E\027&l14c1e7.64c66F~

mr80~

p89~

qq

Quit
Return to READY
{QUIT}