

Sound Notes Macro

for Microsoft Excel for the Macintosh, version 2.2

NOTE: The Sound Notes macro is sample code only and is unsupported by Microsoft Corporation. This macro is copyrighted by Microsoft Corporation. You may make an unlimited number of copies of this macro for your own use and for distribution to others. You may modify the macro and create derivative macros based in whole or in part on this macro for your use and for distribution to others. Microsoft owns any derivative works that you create. All copies of this macro, original or derived, must bear the following inscription: "© 1990 Microsoft Corporation. All rights reserved." No copy, original or derived, may be sold. You accept this macro "as-is" without warranties.

Description

The Sound Notes macro provides the ability to record & play sounds and attach them to Microsoft Excel worksheet and macro sheet cells. The Sound Notes macro adds an extra menu, **Sound**, to the worksheet and macro sheet menu bars. Recording sounds requires: (1) the Sound Manager in Macintosh System 6.0.7; (2) an active input device selected via the System 6.0.7 Sound control panel device (The Macintosh LC and Macintosh IIsi have built-in microphones; to use an add-on input device, the correct sound input drivers must be installed).

Operation

Sound Notes adds the following menu to the worksheet and macro sheet menu bars:

| |
|--|
| Sound |
| Help... |
| Record Sound... |
| Play Sound |
| Copy Sound... |
| Delete Sound |
| Select Sounds |
| Good Quality |
| Better Quality |
| <input checked="" type="checkbox"/> Best Quality |
| <input checked="" type="checkbox"/> Mark Cell |

Help brings up a dialog box containing information about the Sound menu and its operation.

Record Sound records a sound and attaches it to the active cell. If Mark Cell is checked, the font color of the cell to which the sound is attached is changed to blue and the font style to outline. If a sound is already attached to the active cell, an alert is given and no recording takes place; the sound in the cell must first be deleted before a new one may be attached. (Keyboard shortcut for Record Sound is Command+Option+r)

Play Sound will play any sounds attached to cells in the current selection. In a multiple cell selection, the sounds will be played as the cells are activated in standard Tab order; no alert is given if an individual cell in the selection has no sound attached. In a single cell selection, however, an alert is given if the cell has no sound attached to it. (Keyboard shortcut is Command+Option+p)

Copy Sound copies the sound attached to the active cell to the destination cell entered into the Copy Sound dialog box. An alert is brought up if the source cell has no sound attached or the destination cell already contains a sound. (Keyboard shortcut is Command+Option+c)

Delete Sound removes the sound attached to the active cell. An alert is brought up if the cell contains no sound. The cell's font color is changed to black and its font style to plain. (Keyboard shortcut is Command+Option+d)

Select Sounds selects all cells on the active sheet to which sounds are attached. An alert is given if the sheet contains no sounds (to distinguish the case in which the active cell contains the only sound on the sheet). (Keyboard shortcut is Command+Option+s)

The **Good Quality**, **Better Quality**, and **Best Quality** check items are mutually exclusive and determine the quality at which sounds are recorded. Best Quality is the default.

Mark Cell is a check item. When it is checked, Record Sound and Copy Sound turn the font color of the cell to which the sound is attached to blue and the font style to outline. The default is checked.