


Casio DA

Copyright 1986 by
Ralph Muha
25A Kelly Rd
Cambridge MA 02139


The Casio Desk Accessory emulates a popular four function digital wristwatch; it is intended to replace the Alarm Clock DA supplied by Apple. In addition to the basic functions of setting and displaying the date and time of day, Casio gives you ten nameable Elapsed Timers, ten nameable Countdown Timers (with optional auto-repeat), ten nameable Alarm Clocks and nine nameable alternate Time Zone displays.

Casio is shareware! If you like it and/or find it useful, please send \$5 to the address above.


The Time-of-Day Clock




Alternate Time Zone Display




Elapsed Timers




Countdown Timer Alarms



Alarm Clocks



How to Change Things



Theory of Operation

Casio gets its time from the hardware Time-of-Day clock. It keeps all its information in a file (named Casio File) which is created on the system disk (for MFS) or in the system folder (for HFS). Each time you run Casio, it reads the file, figures out how much time has elapsed since it last was active and updates its alarms and timers appropriately. When you close Casio (or the application that it is running under) it writes its current state back to the file. It also remembers where you place it on the screen, so when you run it again, it re-appears in the same place.

Alarms

If an alarm goes off while Casio is running (even if it is not the active window) it notifies you by beeping and flashing the display. The alarm will continue until you click on any part of the window. If a countdown alarm is running in auto-repeat mode, Casio chimes once each time the alarm resets.

When you close Casio, it sets the system (hardware) alarm clock to the time that the next alarm should go off. So even if it is not running, you will be notified (by a single beep and a flashing apple). You should then run Casio to retire the alarm (which will set the alarm appropriately for the next time).

The Clipboard

Cut and **copy** both copy the current display text to the clipboard; **paste** is ignored.

Resources

The display mode icons are contained in a single SICN resource; if you don't like them, use a resource editor or the new public domain SICN editor to change them.

Casio takes a few items from the International Resources (INTL 0 and 1): the date and time separators and the 12-24 hour time cycle flag. You can change the 12-24 hour display by using the right button in the time-of-day clock mode. This doesn't change the international resources, though.