

Adobe® InDesign® 1.0 Tryout

December 16, 1999

Welcome to the Adobe InDesign 1.0 Tryout. This version of Adobe InDesign is intended to give you a preview of the features of Adobe InDesign 1.0. It includes nearly all of the core features found in the full version, except for those specifics listed below. Furthermore, to minimize its size, this tryout version includes only a small sampling of the color libraries and dictionaries available with the full version.

Installing the Tryout version

To install the tryout version of InDesign, double-click the setup.exe (Windows) or the installer icon in the Adobe InDesign 1.0 Tryout folder (Mac OS).

System Requirements and Memory Allocation

To use Adobe InDesign for Mac OS, you need the following hardware and software:

- PowerPC 604 processor or greater.
- Mac OS software version 8.5 or later.
- A hard disk with 130 MB or more of available hard-disk space for installation at the time you install InDesign onto it. Installation also requires free disk space on the startup drive for temporary files and for items added to the System folder, even if you install InDesign on a different drive.
- At least 48 MB of random-access memory (RAM) with virtual memory on, or 96 MB with virtual memory off.
- A CD-ROM drive.
- Monitor resolution of 832x624 pixels.
- Adobe PostScript Level 2 (or higher) printer.

NOTE: When printing from InDesign, be sure to specify "PostScript 2 Only" or "PostScript 3 Only" in the printer driver's PostScript Settings dialog box. The driver's "PostScript 1, 2, and 3 Compatible" option amounts to support for Level 1, which does not meet InDesign's PostScript Level 2 requirement.

For the best performance, Adobe Systems recommends the following hardware and software:

- PowerPC G3 processor.
- 128 MB or more of physical RAM.
- High-resolution 24-bit screen display.
- An Internet connection.

InDesign is initially set to use 20 MB of RAM. To optimize performance, you can reset the amount of memory allocated to InDesign. First, select the InDesign application icon from the Finder (do not start InDesign, however), and choose File > Get Info. In the dialog box that appears, choose Memory from the Show pop-up menu, and, depending on the amount of physical RAM in your system, type the following value in the Preferred field:

- Type 30 if you have 128 MB of RAM
- Type 50 if you have 256 MB of RAM

(On systems with less than 128 MB, there is not necessarily a noticeable improvement in performance when you adjust the Preferred setting.)

To launch InDesign, the amount of RAM specified in the Preferred field must be available, plus an additional one MB of system heap memory (with Virtual Memory turned on), or an additional 20 MB of system heap memory (with Virtual Memory turned off). If InDesign reports that there is insufficient memory to start up, decrease the value in the Preferred field such that enough memory becomes available. (If you have reset the Preferred field correctly and InDesign still reports that there is insufficient memory to start up, try restarting your Macintosh to reset system memory.)

To use Adobe InDesign for Windows , you need the following hardware and software:

- Intel Pentium II Processor
- Windows 98 or Windows NT 4.0 service pack 4 or later
- 48 MB of RAM
- 130 MB or more of available hard disk space for installation
- CD-ROM drive
- Video card that supports 256 colors at 800 x 600 monitor resolution
- For PostScript printers: Adobe PostScript Language Level 2 or later

For the best performance, Adobe Systems recommends the following hardware and software:

- Intel Pentium II Processor (300MHz or faster)
- 64MB or more of RAM
- 24-bit high resolution display
- Internet connection

Limitations of the Tryout version

- The Tryout version is available in Universal English only.
- There is no Custom Install option
- Save, Save As and Save a copy is disabled
- Printing and exporting of PDF, SEP and EPS' will have a banner that reads "Adobe InDesign"
- All dictionaries are removed (except for US English, Intl. English, Canadian French, French and German)
- Adobe Gamma has been removed
- AOL (Adobe Online) has been removed
- Only a sampling of Color Libraries are available. (PANTONE Coated, PANTONE Process, PANTONE Uncoated, System (Macintosh), System (Windows), Web)
- Tutorials have been removed.
- Registration/personalization requirements through application have been removed
- Kodak Color Management Profiles are not included.
- The Preflight and Package features have been removed
- The Automatic File Recovery feature has been removed

To utilize the full printing capabilities of Adobe InDesign, the Adobe PS Driver is required.

AdobePS version 8.6 for Macintosh or later

AdobePS version 4.3 Windows 98 or later

AdobePS version 5.1 for Windows NT 4.0 or later

The Adobe PS printer is available for download from the Adobe web site at the following URL:

<http://www.adobe.com>

Technical Support

This Tryout is for demonstration purposes only, so it does not entitle you to receive complimentary support from Adobe technical support staff. You can, however, post questions and comments regarding tryout software on Adobe's User to User Forums or search our Technical Solutions Database on Adobe's Web site at <http://www.adobe.com/support/main.html>

These complimentary services are available 24 hours a day, seven days a week. For free information about Adobe products and services from anywhere in the world, visit the Adobe Home Page on the World Wide Web at <http://www.adobe.com>.

Copyright © 1999 Adobe Systems Incorporated. All rights reserved.

Adobe, Acrobat, Illustrator, InDesign, Photoshop, and PostScript are trademarks of Adobe Systems Incorporated and may be registered in certain jurisdictions. Apple and MacOS are registered trademarks of Apple Computer, Inc. All other brand or product names are trademarks or registered trademarks of their respective holders.