

Sheet1

| PRINTER,C,30             | COM | NOFCOMPON,C,3C | COMPOFF, SETUP,C,3 | UNSET,C,3 | BIGON,C  | BIGOFF,              |
|--------------------------|-----|----------------|--------------------|-----------|----------|----------------------|
| Epson Action Laser II    | 132 | 80             | \027(s16.67H       | \027(s10H | \027(s1Q | \027(s1Q             |
| Epson LQ/FX              | 132 | 80             | \027M\015          | \027P\018 | \027x1   | \027x0 \027w1 \027w0 |
| HP Deskjet               | 132 | 80             | \027(s16.67H       | \027(s10H | \027(s1Q | \027(s1Q             |
| HP Laserjet              | 132 | 80             | \027(s16.66H       | \027(s10H | \027(s1Q | \027(s1Q             |
| HP Laserjet II           | 132 | 80             | \027(s16.67H       | \027(s10H | \027(s1Q | \027(s1Q             |
| HP Laserjet III          | 132 | 80             | \027(s16.67H       | \027(s10H | \027(s1Q | \027(s1Q             |
| HP Laserjet IIID         | 132 | 80             | \027(s16.66H       | \027(s10H | \027(s1Q | \027(s1Q             |
| HP Laserjet IIP          | 132 | 80             | \027(s16.66H       | \027(s10H | \027(s1Q | \027(s1Q             |
| HP Laserjet IIP+         | 132 | 80             | \027(s16.67H       | \027(s10H | \027(s1Q | \027(s1Q             |
| IBM Laser Printer 4019   | 132 | 80             | \027(s16.67H       | \027(s10H | \027(s1Q | \027(s1Q             |
| NEC (Epson LQ Emulation) | 132 | 80             | \015               | \018      | \027x1   | \027x0 \027w1 \027w0 |
| NEC (Epson LQ Emulation) | 132 | 80             | \015               | \018      | \027x1   | \027x0 \027w1 \027w0 |
| Panasonic KX-P1123       | 132 | 80             | \015               | \018      | \027x1   | \027x0 \027w1 \027w0 |
| Panasonic KX-P1124       | 132 | 80             | \015               | \018      | \027x1   | \027x0 \027w1 \027w0 |
| Canon BubbleJet          | 132 | 80             | \015               | \018      |          |                      |
| Generic Printer (TTY)    | 80  | 80             |                    |           |          |                      |

Sheet1

BOLDON,(BOLDOFF ITON,C,30ITOFF,C,3ULON,C,30ULOFF,C,3BOXCODE,C,10

|          |          |          |          |          |         |         |
|----------|----------|----------|----------|----------|---------|---------|
| \027(s3B | \027(s0B | \027(s3S | \027(s0S | \027&d0D | \027&d@ | +-+ +-+ |
| \027E    | \027F    | \0274    | \0273    | \027-1   | \027-0  |         |
| \027(s3B | \027(s0B | \027(s3S | \027(s0S | \027&d0D | \027&d@ |         |
| \027(s3B | \027(s0B | \027(s3S | \027(s0S | \027&d0D | \027&d@ |         |
| \027(s3B | \027(s0B | \027(s3S | \027(s0S | \027&d0D | \027&d@ |         |
| \027(s3B | \027(s0B | \027(s3S | \027(s0S | \027&d0D | \027&d@ |         |
| \027(s3B | \027(s0B | \027(s3S | \027(s0S | \027&d0D | \027&d@ |         |
| \027(s3B | \027(s0B | \027(s3S | \027(s0S | \027&d0D | \027&d@ |         |
| \027E    | \027F    | \0274    | \0273    | \027-1   | \027-0  |         |
| \027E    | \027F    | \0274    | \0273    | \027-1   | \027-0  |         |
| \027E    | \027F    | \0274    | \0273    | \027-1   | \027-0  |         |
| \027E    | \027F    | \0274    | \0273    | \027-1   | \027-0  |         |
| \027E    | \027F    | \0274    | \0273    | \027-1   | \027-0  |         |

+-+|+-+|