

PADLOCK5.EXE(c)1994 Bob Bowker
NOCAD.VBX (c)1994 Bob Bowker
VRBTD.386 (c)1992 Microsoft Corporation

PADLOCK5.EXE is a secure ScreenSaver. When you run the program, the screen will be blanked, and a clock showing your System Time will be shown.

NOTE: CTRL-ALT-DEL IS DISABLED WHILE PADLOCK5.EXE IS RUNNING!

VBRUN300.DLL

To run **PADLOCK5**, you must have the file VBRUN300.DLL in your \WINDOWS\SYSTEM sub-directory; the file is available on most bulletin boards or from Microsoft.

IMPORTANT NOTES

Print out a copy of this file before installing **PADLOCK5.EXE**

Except as noted below, **PADLOCK5** locks out the keyboard. There are only two ways to exit from **PADLOCK5**:

- 1) enter the correct password, or
- 2) reboot the computer with a POWER-OFF/POWER-ON or RESET.

If your computer has the BIOS password enabled, your system is effectively locked up tight.

This version comes with a default password of PASSWORD and a default LOCKUP time of one minute; see UTILITIES below to change these values.

SECURITY: Three incorrect passwords will be accepted before the computer will lock up completely for LOCKUP minutes (default one minute). Thereafter, the SpaceBar will activate the Password Input box once again, but its background color will be red, not yellow, and another three incorrect passwords will be accepted before once again locking up for LOCKUP minutes (default one minute).

TO INSTALL PADLOCK5

1. From Windows, select **FILE:RUN**
2. Type A:\SETUP.EXE
(substitute the drive and directory where the SETUP.EXE program is located)
3. Select **OK** to run **SETUP.EXE**, and follow the instructions to select the drive and directory where you want the program installed. **SETUP** will do the following:
 1. ask you for the name of the sub-directory where you want the files

- installed (this can be a new or an existing sub-directory);
 2. uncompress and copy **PADLOCK5.EXE** and other files to the sub-directory you specify;
 3. uncompress and copy the file **NOCAD.VBX** to your **\WINDOWS\SYSTEM** sub-directory;
 4. uncompress and copy the file **SPIN.DLL** to your **\WINDOWS\SYSTEM** sub-directory;
 5. uncompress and copy the file **VRBTD.386** to your **\WINDOWS\SYSTEM** sub-directory;
 6. add the line "**device=vrbtd.386**" to your **SYSTEM.INI** file (the added line will be preceded by two comment lines identifying the entry as **PADLOCK5's**, and the installation date); and
 7. create a **PADLOCK** folder with two entries, **PADLOCK5** and **README**.
4. **Exit** WINDOWS to DOS, then **restart** WINDOWS.
 5. Double-click on the **README** icon in the **PADLOCK** folder, and print out this file.

TO RUN PADLOCK5.EXE

1. Move the **PADLOCK5.EXE** icon to the folder of your choice.
2. SUGGESTION: define a **Shortcut** to activate the program (e.g. CTRL-SHIFT-P).
3. Run **PADLOCK5** from **FILE:RUN**, or by double-clicking on the **PADLOCK5** icon, or with the **Shortcut** key(s).

TO EXIT FROM PADLOCK5

1. Press the **SPACEBAR**. The clock will be replaced with a yellow Password Input box; type the password (no quotes, upper- or lower-case). Control will be returned to your applications.

NOTE: If you haven't changed it since installation, the password is **PASSWORD** (no quotes, and either upper- or lower-case).

UTILITIES

1. Run **PADLOCK5** from **FILE:RUN**, or by double-clicking on the **PADLOCK5** icon, or with the **Shortcut** Key(s).
2. Type **CTRL-U** (hold down the **CONTROL** key while you hit the **U** key, either upper- or lower-case).
3. Type the password (no quotes, and either upper- or lower-case) and hit **ENTER**. **NOTE:** If you haven't changed it since installation, the password is **PASSWORD** (no quotes, either upper- or lower-case).
4. **TO CHANGE THE PASSWORD:** type in a **NEW PASSWORD** (16 characters max) and

click on the **OK** button (or just hit **ENTER**). You will be asked to retype the **NEW PASSWORD** for verification: type in the **NEW PASSWORD** and click on the **OK** button (or just hit **ENTER**). If verified, you will be returned to the ScreenSaver clock, with the **NEW PASSWORD** enabled. If you make a mistake when you retype the **NEW PASSWORD**, you will be returned to the ScreenSaver clock with the **OLD PASSWORD** still in effect.

TO CHANGE THE LOCKUP LENGTH: click on the **UP** or **DOWN** arrows next to the Lockup time box. Lockup time can be set to any number of whole minutes between 0 and 15. When the new Lockup time you wish to enable is displayed, click on the **OK** button (or just hit **ENTER**).

Bob Bowker
2811 La Cuesta Drive
Los Angeles, CA 90046
(213)851-5298

CompuServe 70250,306